

Pagero EDIFACT D96A IFTMIN

Mapping Implementation Guide

The following specification shall be used as the basis for creating EDIFACT-message IFTMIN

Version 20200622





CHANGELOG			
Date	What changed?		



INTRODUCTION	2
STANDARD	2
HOW TO USE THESE GUIDELINES	2
SEGMENT IMPLEMENTATION DETAILS	
HEADER GROUP	
UNB INTERCHANGE HEADER - MANDATORY	
HEADER SECTION	
GROUP 0 MANDATORY UNH MESSAGE HEADER- MANDATORY	
BGM BEGINNING OF MESSAGE - MANDATORY	
DTM DATE/TIME/PERIOD - REQUIRED	
FTX FREE TEXT – OPTIONAL	
CNT CONTROL TOTAL – REQUIRED	
DELIVERY INFORMATION GROUP 2 OPTIONAL	
TOD TERMS OF DELIVERY OR TRANSPORT - MANDATORY	
LOC PLACE/LOCATION IDENTIFICATION - OPTIONAL	
GROUP 3 REQUIRED	
RFF REFERENCE - MANDATORY	
GROUP 8 OPTIONAL	
TDT DETAILS OF TRANSPORT- MANDATORY	
PARTY INFORMATION	
GROUP 11 MANDATORY	
NAD NAME AND ADDRESS (Party Details) - MANDATORY	
GROUP 12 OPTIONAL	
CTA PARTY CONTACT DETAILS - MANDATORY	
COM COMMUNICATION CONTACT - OPTIONAL	
GOODS DETAILS	
GROUP 18 REQUIRED	
GID GOODS ITEM DETAILS - MANDATORY	
FTX FREE TEXT – OPTIONAL	
GROUP 20 OPTIONAL	
MEA MEASUREMENTS - OPTIONAL	
GROUP 21 OPTIONAL	
DIM DIMENSIONS - MANDATORY	
GROUP 23 OPTIONAL	
PCI PACKAGE IDENTIFICATION - MANDATORY	
RFF REFERENCE - MANDATORY	
Trailer Group	
UNT MESSAGE TRAILER - MANDATORY	
UNZ MESSAGE TRAILER - MANDATORY	
FXAMPLE DATA:	27



Introduction

The following specification shall be used as the basis for creating EDIFACT-message IFTMIN

Standard

Pagero use D.96A for sending EDIFACT IFTMIN.

Pagero use UNOC syntax and defines separators in the UNA-segment as follows: UNA:+.?'

How to Use these Guidelines

The codes shown under the codes heading are those recommended for use within the particular segment and others will not usually be required unless stated otherwise.

The following terms are used to indicate the particular usage of a segment or element. Where a group is optional then any mandatory segments in it are only mandatory if the group is used. Where a segment is optional then any mandatory elements within it are only mandatory when the segment is used:

MANDATORY (M) Must be used - As defined by UN EDIFACT

REQUIRED (R) Should always be used in transmissions
DEPENDENT (D) Usage is determined by specified conditions
OPTIONAL (O) May be used by trading partners by agreement

NOT USED (NU) Not normally required

Where a group or segment is not referred to, this means it is not required to be sent in a transmission of the message. Where a segment is MANDATORY, REQUIRED, DEPENDENT or OPTIONAL and element details are given with appropriate codes, then these are the only elements required in that segment. The complete UN message layout definition, from which this subset has been derived, is provided at http://live.unece.org/trade/untdid/down index.htm.



Segment Implementation Details

Header Group

UNB INTERCHANGE HEADER - MANDATORY

Function: To identify an interchange.

		1	1
S001	SYNTAX IDENTIFIER	M	
0001	Syntax identifier	M a4	UNOC UN/ECE level C
0002	Syntax version number	M n1	3 Version 3
S002	INTERCHANGE SENDER	M	
0004	Sender identification	M an35	Global Location Number (GLN)
0007	Partner identification code qualifier	C an4	14 = EAN International ZZ = Mutually agreed
S003	INTERCHANGE RECIPIENT	М	
0010	Recipient identification	M an35	Global Location Number (GLN)
0007	Partner identification code qualifier	C an4	14 = EAN International ZZ = Mutually agreed
S004	DATE/TIME OF PREPARATION	М	
0017	Date of preparation	M n8	
0019	Time of preparation	M n4	
0020	Interchange control reference	M an14	
S005	RECIPIENT'S REFERENCE PASSWORD	С	
0022	Recipient's reference/password	M an14	
0026	Application reference	M an14	
0029	Processing priority code	C a1	
0031	Acknowledgement request	C n1	
0032	Communications agreement ID	C an35	
0035	Test indicator	C n1	1 = Test

USAGE NOTES

Element	Status	Codes
S001	MANDATORY	
0001	Mandatory	UNOC
0002	Mandatory	3
S002	MANDATORY	
0004	Mandatory	
0007	Requested	
S003	MANDATORY	
0010	Mandatory	
0007	Requested	
S004	MANDATORY	
0017	Mandatory	
0019	Mandatory	
0020	Not used	
S005	NOT USED	



MIG for Pagero EDIFACT D.96A IFTMIN

0022	Not used		
0026	Not used		
0029	Not used		
0031	Not used		
0032	Not used		
0035	Dependent	1 = Test	

SEGMENT EXAMPLE

 ${\tt UNB+UNOC: 3+7300012550009: 14+7350000001204: 14+061010: 1350+12345++++++1'}$



Header section

GROUP 0 MANDATORY

UNH MESSAGE HEADER- MANDATORY

Function: A service segment starting and uniquely identifying a message. The message type code for the Instruction message is IFTMIN.

0062	Message reference number	M an14	
S009	MESSAGE IDENTIFIER	М	
0065	Message type identifier	M an6	IFTMIN = Instruction message
0052	Message type version number	M an3	D = Draft version/UN/EDIFACT
0054	Message type release number	M an3	96A = Release 1996 - A
0051	Controlling agency	M an2	UN = UN/CEFACT
0057	Association assigned code	C an6	PAGERO

USAGE NOTES

Element	Status	Codes
0062	Mandatory	
S009	MANDATORY	
0065	Mandatory	IFTMIN
0052	Mandatory	D
0054	Mandatory	96A
0051	Mandatory	UN
0057	Required	PAGERO

SEGMENT EXAMPLE

UNH+54321+IFTMIN:D:96A:UN:PAGERO'



BGM BEGINNING OF MESSAGE - MANDATORY

Function: A segment to indicate the beginning of a message and to transmit identifying number and type of the message.

C002	DOCUMENT/MESSAGE NAME	С	
1001	Document/message name, coded	C an3	335 = Booking request 340 = Pre-Book
1004	Document/message number	C an35	Document number
1225	Message function, coded	C an3	5 = Replace 9 = Original

USAGE NOTES

Element	Status	Codes
C002	REQUIRED	
1001	Required	335 = Booking request
1004	Required	
1225	Required	9
	·	

SEGMENT EXAMPLE

BGM+335+B123456+9'



DTM DATE/TIME/PERIOD - REQUIRED

Function: A segment to indicate a date and time applying to the whole message, e.g., date and time of document issue.

C507	DATE/TIME/PERIOD	М	
2005	Date/time/period qualifier	M an3	
2380	Date/time/period	C an35	Date/time - (time will be forwarded if available)
2379	Date/time/period format qualifier	C an3	

USAGE NOTES

Element	Status	Codes
C507	MANDATORY	
2005	Mandatory	137 = Document/message Date/Time
		2 = Delivery date/time, requested
		132 = Arrival date/time, estimated
		234 = Collection date/time, earliest
2380	Required	
2379	Required	102 = CCYYMMDD
		203 = CCYYMMDDHHMM

SEGMENT EXAMPLE

DTM+137:20200423:102' DTM+2:202004241355:203'



FTX FREE TEXT – OPTIONAL

Function: A segment to specify free form or processable supplementary information, such as status of transport, remarks to be printed on the transport documents (where required), consignment remarks, insurance instructions, etc., or any other additional information.

4451	Text subject qualifier	M an3
4453	Text function, coded	C an3
C107	TEXT REFERENCE	С
C108	TEXT LITERAL	С
4440	Free text	M an70
4440	Free text	C an70
4440	Free text	C an70
4440	Free text	C an70
4440	Free text	C an70

USAGE NOTES

Element 4451	Status Mandatory	Codes PRD = Product information SSR = Special service request DEL = Delivery information SIC = Sender's instructions to carrier ZZZ = Mutually defined
4453 C107	Not used NOT USED	
C108 4440 4440 4440 4440 4440	REQUIRED Mandatory Optional Optional Optional Optional	

SEGMENT EXAMPLE

FTX+PDR+++This is a free text'



CNT CONTROL TOTAL – REQUIRED

Function: A segment to specify totals for a consignment.

C270	CONTROL	М	
6069	Control total type code qualifier	M an3	
6066	Control total quantity	M n18	Quantity
6411	Measurement unit code	C an8	

USAGE NOTES

Element C270	Status MANDATORY	Codes
6069	Mandatory	7 = Total gross weight 8 = Total pieces 15 = Total consignment, cube 57 = Total loading metres 63 = Distance
6066 6411	Mandatory Optional	KGM = kilogram PCE = piece MTQ = cubic meter MTR = meter KMT = kilometer

SEGMENT EXAMPLE

CNT+7:10:KGM'



Delivery information

GROUP 2 OPTIONAL

A group of segments to specify terms of delivery and related locations.

TOD TERMS OF DELIVERY OR TRANSPORT - MANDATORY

Function: A segment to specify the applicable terms of delivery.

C100	TERMS OF DELIVERY OR TRANSPORT	С	
1131	Code list qualifier	C an3	
4052	Terms of delivery or transport	C an70	
4052	Terms of delivery or transport	C an70	

USAGE NOTES

Element	Status	Codes
C100		
1131	Required	158 = Terms of delivery
4052	Required	
4052	Optional	

SEGMENT EXAMPLE

TOD+++158:Delivery terms text 1:Delivery terms text 2'



GROUP 2 OPTIONAL

LOC PLACE/LOCATION IDENTIFICATION - OPTIONAL

Function: A segment to specify a location related to the terms of delivery.

3227	Place/location qualifier	M an3	
C517	LOCATION IDENTIFICATION	С	
3225	Place/location identification	C an35	City name

USAGE NOTES

Element	Status	Codes
3227	Mandatory	1 = Place of terms of delivery
C517	REQUIRED	
3225	Required	

SEGMENT EXAMPLE

LOC+1+Stockholm'



GROUP 3 REQUIRED

A group of segments containing a reference and constants which apply to the entire message

RFF REFERENCE - MANDATORY

Function: A segment to express a reference which applies to the entire message such as: the document/message number that is to be updated by this very message (according to data element 1225 Message Function, Coded in segment BGM), booking reference, order number, insurance contract, etc.

(C506	REFERENCE	М	
	1153	Reference qualifier	M an3	
	1154	Reference number	C an35	Reference number

USAGE NOTES

Element	Status	Codes
C506	Mandatory	
1153	Mandatory	BN = Booking reference number CU = Consignor's reference number IT = Customer number
1154	Required	

SEGMENT EXAMPLE

RFF+BN:123456'



GROUP 8 OPTIONAL

A group of segments to indicate details of the movement of goods such as mode and means of transport, locations, departure, and arrival date(s) and time(s).

TDT DETAILS OF TRANSPORT- MANDATORY

Function: A segment to indicate information related to a certain stage of the transport, such as mode, means and carrier.

8051	Transport stage qualifier	M an3	
8028	Conveyance reference number	C an17	
C220	MODE OF TRANSPORT	С	
8067	Mode of transport, coded	C an3	
8066	Mode of transport	C an17	

USAGE NOTES

Element	Status	Codes
8051	Mandatory	20 = Main-carriage transport
8028	Not used	
C220	Required	
8067	Not-used	
8066	Required	

SEGMENT EXAMPLE

TDT+20++:Road transport'



Party information

GROUP 11 MANDATORY

A group of segments to identify a party, related references, locations contacts, required documents, and charges to be paid by the party.

NAD NAME AND ADDRESS (Party Details) - MANDATORY

Function: A segment to identify the party's name, address, and function.

3035	Party qualifier	M an3	
C082	PARTY IDENTIFICATION DETAILS	С	
3039	Party id. identification	M an35	
1131	Code list qualifier	C an3	
3055	Code list responsible agency, coded	C an3	
C058	NAME AND ADDRESS	С	
3124	Name and address line	M an35	
3124	Name and address line	C an35	
3124	Name and address line	C an35	
3124	Name and address line	C an35	
3124	Name and address line	C an35	
C080	PARTY NAME	С	
3036	Party name	M an35	
3036	Party name	C an35	
3036	Party name	C an35	
3036	Party name	C an35	
3036	Party name	C an35	
3045	Party name format, coded	C an3	
C059	STREET	С	
3042	Street and number/P.O. Box	M an35	
3042	Street and number/P.O. Box	C an35	
3042	Street and number/P.O. Box	C an35	
3164	City name	C an35	
3229	Country sub-entity ID	C an9	
3251	Postcode identification	C an9	
3207	Country, coded	C an3	

USAGE NOTES

ElementStatusCodes3035MandatoryCZ = Consignor
CN = Consignee

FP = Freight/charges payer DP = Delivery party PW = Despatch party SE = Seller party

C082 REQUIRED
3039 Mandatory

039 Mandatory Code to identify the party by specifying agreed code



MIG for Pagero EDIFACT D.96A IFTMIN

Not Used	
Required	87 = Assigned by carrier
	9 = EAN International
NOT USED	
OPTIONAL	
Mandatory	
Optional	
OPTIONAL	
Mandatory	
Optional	
Optional	
Optional	
Optional	
Optional	
Optional	
	Required NOT USED Not Used Not Used Not Used Not Used OPTIONAL Mandatory Optional Optional Optional Optional Optional Optional Optional Optional

SEGMENT EXAMPLE

NAD+CZ+1234567890123::9++Pagero AB+Street 10+Gothenburg++12345+SE'



GROUP 12 OPTIONAL

A group of segments identifying a contact and its communications related to the party.

CTA PARTY CONTACT DETAILS - MANDATORY

Function: A segment to identify a person or department within a party.

3139	Contact function, coded	C an3	
C056	DEPARTMENT OR EMPLOYEE DETAILS	С	
3413	Department or employee identification	C an17	
3412	Department or employee	C an35	To specify the full name of the contact

USAGE NOTES

Element	Status	Codes
3139	REQUIRED	IC = Information contact
C056 3413 3412	OPTIONAL Not Used Required	

SEGMENT EXAMPLE

CTA+ IC+:JOHN DOE'



GROUP 12 OPTIONAL

COM COMMUNICATION CONTACT - OPTIONAL

Function: A segment to identify a communication number of a person or department to whom communication should be directed.

C076	COMMUNICATION CONTACT	М	
3148	Communication number	M an512	To specify telephone, telefax or e-mail
3155	Communication channel qualifier	M an3	

USAGE NOTES

Element	Status	Codes
C076	MANDATORY	
3148	Mandatory	
3155	Mandatory	TE = Telephone
		EM = Email

SEGMENT EXAMPLE

COM+01812341122:TE'

This specifies the telephone number for the CTA contact



Goods details

GROUP 18 REQUIRED

A group of segments to describe the goods items for which transport is undertaken.

GID GOODS ITEM DETAILS - MANDATORY

Function: A segment to identify a goods item for which transport is undertaken. A goods item can be identified by up to three levels of packaging.

1496	Goods item number	C an5	Consignment- or customs line number
C213	NUMBER AND TYPE OF PACKAGES	С	
7224	Number of packages	C n8	
7065	Type of packages identification	C an17	

USAGE NOTES

Element 1496	Status Optional	Codes
C213 7224	REQUIRED Required	
7065	Required	BA = Barrel
		BB = Bobbin
		BC = Bottlecrate
		BE = Bundle
		BG = Bag
		BJ = Bucket
		BL = Bale, compressed
		BO = Bottle, non-protected, cylindrical
		BR = Bar
		BS = Bottle, Non Protected Bulbous
		BX = Box
		CA = Can, rectangular
		CG = Cage CH = Chest
		CI = Canister
		CR = Crate
		CS = Case
		CT = Carton
		CX = Can, cylindrical
		CY = Cylinder
		DR = Drum
		EN = Envelope
		OH = Pallet ISO 1 - 1/1 EURO Pallet
		NE = Unpacked or unpackaged
		OS = Oneway pallet
		PE = Pallet, modular, collars 80cms * 120cms
		PC = Parcel
		PK = Package
		RL = Reel
		RO = Roll
		SA = Sack
		SK = Case, skeleton
		TK = Tank TN = Tin
		TR = Trunk
		TU = Tube
		VA = Vat
		V/1 - VUC





OP = Wholesaler pallet

OG = Pallet ISO 0 - 1/2 EURO Pallet

AF = Pallet, modular, collars 80cms * 60cms

OI = Pallet ISO 2 – 2/1 EURO Pallet

OJ = 1/4 EURO Pallet

OL = 1/8 EURO Pallet

OS = Oneway pallet

OV = Returnable pallet

O3 = Oneway pallet ISO 0 - 1/2 EURO Pallet

O4 = Oneway pallet ISO 1 - 1/1 EURO Pallet

4D = Box, plywood

7B = Case, wooden

EH = Case, with pallet base, metal

UN = Unit

ZZ = Mutually defined

SEGMENT EXAMPLE

GID+1+2:OG'



GROUP 18 OPTIONAL

FTX FREE TEXT – OPTIONAL

Function: A segment to specify processable supplementary information relating to the goods item.

4451	Text subject qualifier	M an3
4453	Text function, coded	C an3
C107	TEXT REFERENCE	С
C108	TEXT LITERAL	С
4440	Free text	M an70
4440	Free text	C an70
4440	Free text	C an70
4440	Free text	C an70
4440	Free text	C an70

USAGE NOTES

Status	Codes
Mandatory	AAA = Goods description
Not used	
NOT USED	
REQUIRED	
Mandatory	
Optional	
Optional	
Optional	
Optional	
	Mandatory Not used NOT USED REQUIRED Mandatory Optional Optional Optional

SEGMENT EXAMPLE

FTX+AAA+++This is a goods item description'



GROUP 20 OPTIONAL

A group of segments to specify measurements applicable to a goods item.

MEA MEASUREMENTS - OPTIONAL

Function: A segment to specify measurements, other than dimensions, applicable to a goods item.

6311	Measurement application qualifier	M an3	
C502	MEASUREMENT DETAILS	С	
6313	Measurement dimension, coded	C an3	
6321	Measurement significance, coded	C an3	
C174	VALUE/RANGE	С	
6411	Measure unit qualifier	M an3	
6314	Measurement value	C n18	

USAGE NOTES

Element	Status	Codes
6311	Mandatory	PD = Physical dimensions (product ordered
C502	REQUIRED	
6313	Required	AAW = Gross volume
		ACV = Loading meters
		G = Gross weight
		SQ = Shipped quantity
6321	Required	4 = Equal to
C174	REQUIRED	
6411	Mandatory	MTQ = cubic meter
		MTR = meter
		KGM = kilogram
		PCE = piece
6314	Required	

SEGMENT EXAMPLE

MEA+PD+G:4+KGM:100'



GROUP 21 OPTIONAL

A group of segments to specify dimensions applicable to a goods item.

DIM DIMENSIONS - MANDATORY

Function: To specify dimensions applicable to a goods item.

6145	Dimension qualifier	M an3	
C211	DIMENSIONS	М	
6411	Measurement unit code	M an8	
6168	Length measure	C n15	Length
6140	Width measure	C n15	Width
6008	Height measure	C n15	Height

USAGE NOTES

Element	Status	Codes
6145	Mandatory	2 = Package dimensions (including goods)
C211	MANDATORY	
6411	Mandatory	MTR = meter
6168	Optional	
6168	Optional	
6168	Optional	

SEGMENT EXAMPLE

DIM+2+MTR:2:1:0.5'



GROUP 23 OPTIONAL

A group of segments to specify marks and numbers of a goods item.

PCI PACKAGE IDENTIFICATION - MANDATORY

Function: A segment to specify marks and numbers of a goods item.

4233	Marking instructions code	C an3	
C210	MARKS & LABELS	С	
7102	Shipping marks	M an35	Packing mark number

USAGE NOTES

7102

Element	Status	Codes
4233	Required	30 = Mark serial shipping container code
C210	REQUIRED	

SEGMENT EXAMPLE

Mandatory

PCI+30+1234567890123456'



GROUP 23 OPTIONAL

RFF REFERENCE - MANDATORY

Function: A segment to identify a reference relating to the marks and numbers.

C506 REFERENCE		М	
1153	Reference qualifier	M an3	
1154	Reference number	C an35	Reference number

USAGE NOTES

Element	Status	Codes
C506	Mandatory	
1153	Mandatory	CU = Consignor's reference number
1154	Required	

SEGMENT EXAMPLE

RFF+CU:12345689'



Trailer Group

UNT MESSAGE TRAILER - MANDATORY

Function: A service segment ending a message, giving the total number of segments in the message and the control reference number of the message.

0074	Number of segments in a message	M n6	
0062	Message reference number	M an14	

USAGE NOTES

Element	Status	Codes
0074	Mandatory message	To specify the total number of segments making up the inclusive of the UNH and UNT segments
0062	Mandatory	To specify a unique sequential message reference number. match the corresponding 0062 element in the UNH segment at the beginning of the message.

SEGMENT EXAMPLE

UNT+37+54321'



Trailer Group

UNZ MESSAGE TRAILER - MANDATORY

Function: To end and check the completeness of an interchange.

0036	Interchange control count	M n6	
0020	Interchange control reference	M an14	

USAGE NOTES

Element Status Codes

0036 Mandatory 0020 Mandatory

SEGMENT EXAMPLE

UNZ+1+12345'



Example data:

UNA:+.? '

UNB+UNOC:3+7300012550009:14+7350000001204:14+061010:1350+123456789++++++1'

UNH+123456789+IFTMIN:D:96A:UN:PAGERO'

BGM+335+B123456+9'

DTM+137:20200423:102'

DTM+2:202004241355:203'

DTM+234:20200425:102'

FTX+PDR+++Logistics Service'

FTX+SSR+++Additional logistics Services'

FTX+DEL+++Delivery instructions'

CNT+7:100:KGM'

CNT+11:3:PCE'

CNT+15:0.91:MTQ'

CNT+57:11:MTR'

CNT+63:485.13:KMT'

TOD++158:Delivery terms text 1:Delivery terms text 2'

LOC+1+Stockholm'

RFF+BN:123456'

RFF+CU:073400237070027228'

TDT+20++:Road transport'

NAD+CZ+1234567890123::9++Pagero AB+Street 10+Gothenburg++12345+SE'

CTA+ IC+: JOHN DOE'

NAD+CN+0234567891234::9++Pagero AS+Street 11+Oslo++12345+NO'

NAD+FP+0234567891234::9'

NAD+DP+5554443332221::9++Pagero AS+Street 11+Oslo++12345+NO'

CTA+ IC+: JOHN DOE'

COM+0181211111:TE'

NAD+PW+1234567890123::9++Pagero AB+Street 10+Gothenburg++12345+SE'

CTA+ IC+: JOHN DOE'

COM+test@pagero.com:EM'

GID+1+2:0G'

FTX+AAA+++This is a goods item description'

MEA+PD+AAW:4+MTQ:3'

MEA+PD+G:4+MTR:11'

MEA+PD+G:4+KGM:100'

MEA+PD+G:4+PCE:3'

DIM+2+MTR:1.3:0.7:0.5'

PCI+30+12345678'

RFF+CU:073400237070027228'

UNT+38+123456789'

UNZ+1+12345'