## **BLayout Documentation**

- 1. API
  - 1. Types
  - 2. Constants
  - 3. Macros
  - 4. Functions
- 2. Usage
  - blcalc() with blnext()
  - 2. blprev()
  - 3. blnext() VS. blprev()
- 3. LICENSE

### API

- Types
- 2. Constants
- 3. Macros
- 4. Functions

### **Types**

```
typedef size_t blsize;
struct blayout {
    blsize nmemb; blsize size;
    blsize align;
}:
```

- blsize is the API's size type. It's size\_t by default. You may change this type by modifying BLayout's header. A signed type is also valid. You'd have to change BL\_SIZEMAX accordingly (see below).
- blayout describes a single memory allocation request for an object:
  - nmemb is the number of elements (like calloc()'s first argument),
  - size is the size (in bytes) of each element/type (like calloc()'s second argument),
  - align is the alignment<sup>1</sup> of the object's type

#### Constants

```
#define BL_SIZEMAX SIZE_MAX
#define BL_ALIGNMENT alignof(max_align_t)
```

- BL\_SIZEMAX is the equivalent to size\_t's SIZE\_MAX and is equal to that by default. You may override this, but the header assumes that it's greater than 0.
- BL\_ALIGNMENT is never used internally. It's equal to the maximum alignment among C's scalar types. It's provided as a convenience when calling blcalc() (see below). This, too, can be overridden.

Note: To override these, either modify BLayout's header or #define them before including blayout.h.

### **Macros**

```
#define BL_API
#define BL_ASSERT assert
#define BL_INLINE inline
#define BL_DEBUG 0
```

 You may change BL\_API to extern if you want to put the functions in a seperate translation unit. Keep in mind that you'd have to copy-paste the signatures.

<sup>&</sup>lt;sup>1</sup>alignment is always assumed to be valid: (1) it denotes byte boundaries and (2) is a power of 2.

- BLayout can use assertions through the BL\_ASSERT macro to enforce API contracts and prevent footguns. You can override this macro if you use a custom assert () function. See BL\_DEBUG below if you want to disable assertions.
- Every function is inline (C99 semantics) through the BL\_INLINE macro. This is so that you can workaround C's deficiencies, if you so wish.
- BL\_DEBUG takes three possible values:
  - o, where BLayout will use no assertions (see above) and, in addition, will take advantage of compiler-specific optimization hints (e.g. attribute (nonnull(...))). This is the default.
  - 1, where BLayout will use some assertions and optimization hints.
  - 2, where BLayout will use all assertions and no optimization hints.

### **Functions**

- blcalc() returns the minimum size needed to contiguously allocate multiple objects. The function assumes that all arguments are valid and within bounds. If wrap-around is detected when computing the size, 0 is returned instead, indicating error.
  - align is the default alignment your allocator supports. In case you already have an allocated buffer, pass the buffer's alignment. BL\_ALIGNMENT should work with malloc() and with any buffer allocated by it.
  - offs is used in case you already have a buffer and want to allocate starting from an offset into that buffer. Pass 0 otherwise.
  - n is the number of layouts. Should be **greater** than 0.
  - lays is an array of length n containing layouts,
  - prev\_size is used to chain multiple blcalc() calls. When first invoking, 0 must be passed, otherwise the result of the previous blcalc() call must be passed, assuming the call succeeded and a non-0 value was returned. align and offs must not change across any chained calls.
- blnext () allocates the next object in a **left-to-right** manner, where:
  - ptr is a pointer to the current allocated object. When first invoking, pass a pointer to your buffer. It's assumed to **not** be NULL and thus the function doesn't check for this.
  - curr\_size is the size of the current object (see blsizeof()) and is assumed to be valid. When first invoking, pass 0.
  - next\_align is the alignment of the next object's type and is assumed to be valid. When first invoking, pass the alignment
    of the first object's type.
- blprev() is like blnext(), but allocates and returns the previous object, in a right-to-left manner. That means you should allocate in reverse order, starting with last object.
  - ptr is a pointer to the current allocated object. When first invoking, pass a pointer to the end of your buffer. It's assumed to not be NULL and thus the function doesn't check for this.
  - prev\_size is the size of the previous object (see blsizeof()) and is assumed to be valid. When first invoking, pass the size of the **last** object.
  - prev\_align is the alignment of the previous object's type and is assumed to be valid. When first invoking pass the
    alignment of the last object's type.
- blsizeof() returns the total size (in bytes) of an object described by its layout. Effectively, it multiplies blayout.nmemb with blayout.size. It's provided as a convenience.
  - 1 is the pointer to the aforementioned layout.
  - 1. Caveat: Padding due to alignment is **not** taken into account.
  - 2. Caveat: Potential integer overflow is **not** checked. The layout is assumed to be correct. blcalc() already checks for this.

# Usage

- blcalc() with blnext()
- 2. blprev()
- 3. blnext() VS. blprev()

### blcalc() with blnext()

```
* Request:
       I. One integer, naturally aligned. II. Two floats, naturally aligned.
   The order of the `lays` array is important! `blcalc()` takes the order into account when computing its result. And it does that for the simple reason that the whole point of this header is to allow the programmer to lay out their objects in memory exactly how they want. Hence, we preserve the order, because it might be important, we wouldn't know. If the order is _not_ important to _you_, this detail doesn't impair you.
 * This order also defines how `blnext()` (and `blprev()`; see below) should be
 * called. The functions don't check for this, the burden, unfortunately, falls
 * onto the programmer.
size_t size = blcalc(BL_ALIGNMENT, /* Going to use the default alignment. */ /* Allocating from the `0`th position. */
                                                 /* The number of layouts. */
                             2,
                                                 /\star The array of layouts describing our objects. \star/
                            lays,
                            0);
                                                 /* We aren't chaining `blcalc()` calls. */
if (size == 0) {
     fprintf(stderr, "blcalc() error\n");
     return 1;
void *buf = malloc(size);
if (buf == NULL) {
     fprintf(stderr, "malloc() error\n");
     return 1:
/* The first object. */
int *i = blnext(buf,
                                             /* First allocation: pass the buffer. */
/* Continue with the next object... */
                                                     /* Pass the current allocated object. */
float *f = blnext(i,
                                                     /* Pass the size of the current allocated object. */
                        blsizeof(&lays[0]),
                                                     /* Pass the alignment of the next object's type (`float`). */
                        lays[1].align);
assert(f != NULL); /* Likewise. */
/* Use `i` and `f` normally. */
*i = 42;
f[0] = 2.71;
f[1] = 3.14;
printf("*i=%d f[0]=%f f[1]=%f\n", *i, f[0], f[1]);
free(buf); /* `i` and `f` are guaranteed to be cleaned up with a _single_ `free()`. */
return 0;
 * Alternatively, if the alignment of the _first_ object's type is
* _less-or-equal_ to your buffer's alignment, then the pointer to the first
* allocated object is equivalent to a pointer to the buffer.
    In our case:

    The first object's type has alignment `alignof(int)`.
    `BL_ALIGNMENT` is the default alignment of `malloc()` (which we also

         used when calling `blcalc()`).
     3. Thus, the buffer returned to us by `malloc()` (`buf`) has that alignment.
         `malloc()` must, as mandated by the C standard, be able to return a suitably aligned pointer for _every_ naturally aligned type. That
         includes our case: `int`.
     5. Since 'buf' has alignment `BL_ALIGNMENT' and that alignment _must_ be suitable for `int`, we can conclude that `BL_ALIGNMENT >= alignof(int) or, equivalently, `alignof(int) <= BL_ALIGNMENT`.
 */
```

### blprev()

Usage of blprev() is similar to the usage of blnext() with these notable differences:

- 1. You must allocate in reverse order.
- 2. In order to cleanup safely, you **must** retain a pointer to your buffer.

Let's see with a similar example:

```
* ... Same layouts and boilerplate as the `blnext()` example...
 * Assume `buf` of size `size` has already been allocated as above.
size_t size;
void *buf;
 * Allocate in **reverse** order, starting with the **last** object. `blprev()`
* works in a _right-to-left_ manner; we have to pass the _end_ of our buffer * in the first allocation.
void *end = (char *)buf + size;
float *f = blprev(end,
                                            /* First allocation: pass the end of the buffer. */
                    blsizeof(&lays[1]), /* First allocation: pass the size of the last object. */
lays[1].align); /* First allocation: pass the alignment of the last object's
                        type. */
assert(f != NULL); /* Always true, same as before. */
/* Continue with the previous object... */
                                        /* Pass the current allocated object. */
/* Pass the size of the previous object. */
int *i = blprev(f,
                  blsizeof(&lays[0]),
                  lays[0].align);
                                          /* Pass the alignment of the previous object's type. */
assert(i != NULL); /* Likewise. */
*i = 1337;
f[0] = 1.41;
f[1] = 1.61;
printf("*i=%d f[0]=%f f[1]=%f\n", *i, f[0], f[1]);
* Cleanup!
 * NOTE: You can _not_ pass `i` or `f` in the case of `blprev()`! You must pass
          the pointer returned to you by `malloc()`!
* /
free (buf);
return 0;
//free(i); /* XXX: Don't do this _ever_! */
//free(f); /* XXX: Or this either! */
```

## blnext() vs.blprev()

When should you use the one or the other? Given the limitations of blprev(), shouldn't you always use blnext()? It depends. Firstly, you indeed **can only use one**<sup>2</sup> of the two to allocate from a single memory region. Given that, which to pick?

Let's assume your layouts array is {{1, 1, 1}, {1, 2, 2}}. Meaning:

- 1. One (1) type of size 1 (bytes) at an 1-byte alignment boundary, and
- 2. One (1) type of size 2 (bytes) at an 2-byte alignment boundary.

Assuming your buffer is 16-byte aligned, blcalc() (correctly) returns 4 for the above array.

If your buffer sits at address 16 then, using blnext(), the bytes would be laid out like this:

```
Address | 16 17 18 19
Bytes | X0 Y0 Y1
```

But, if you were to use blprev(), allocating from the end of the buffer, they'd be laid out like this:

```
Address | 16 17 18 19
Bytes | X0 Y0 Y1
```

Where xi is the ith byte of object x, respectively y.

Thus, the two methods give different results. This example also makes clear why you need to retain a pointer to your buffer in the case of blprev(): x0 doesn't sit at the (original) address 16!

**Always use blnext ()**, unless you desire the special properties of blprev () and the limitations don't affect you. Here's two scenarios where that could be true:

- You always carry around a pointer to your buffer, so using blprev() has no extra burden. Note that blprev() is 2-3 machine instructions shorter than blnext(), under x86\_64-sysv and also depending on compiler and optimization options (Related).
- You depend on the layout blprev() gives. This happens when giving a "header" to a "payload", just like malloc() does.

```
struct header {
   int id;
struct payload {
   size_t size;
   unsigned char data[]; /* Flexible array member:
       <https://gustedt.wordpress.com/2011/03/14/flexible-array-member/> */
};
struct payload *new_payload(my_ctx *ctx, size_t payload_size)
   size_t size = blcalc(/* ... */, 0, 2, lays, 0);
if (size == 0)
       abort();
   void *buf_end = /* ... */;
struct payload *p = blprev(buf_end, blsizeof(&lays[1]), lays[1].align);
   p->size = payload_size;
   memset (p->data, 0, payload_size);
   struct header *h = blprev(p, blsizeof(&lays[0]), lays[0].align);
   h->id = /* ... */;
   return p;
}
void recycle_payload(my_ctx *ctx, struct payload *p)
   struct header *h = blprev(p, sizeof(*h), alignof(struct header)); /* Okay. */
   int id = h->id;
   /* Do something with `id`... */
}
```

<sup>&</sup>lt;sup>2</sup>Which also means you can't use one function to retrieve objects in reverse order, if you allocated using the other.

The above example **cannot** work with blnext(), it **only works with** blprev(). Even if you only used blnext() to allocate the objects, once you got to retrieve the header in:

```
struct header *h = blprev(p, sizeof(*h), alignof(struct header)); /* I'm sure this is
    perfectly fine, what could possibly go wr */
int id = h->id; /* Kaboom! */
```

your computer would explode. You can't do this! *Even if it works*, you can't depend on this if you allocate using blnext(). Use blprev() instead. Remember that the two functions *lay out objects differently*.

### **LICENSE**

```
Copyright 2025 pan pan_@disroot.org>
Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.
```