
(*) · Basic forwarding functions

- (a). IP Header validation: Fivery IP packet needs to be validated.

 If shows that only well-formed packets are processed further and next are discarded. Also ensures that version is correct, Header length is valid & and matches chocksom.
 - the 18 packet header to provent clooping. If the TI value is zero or negotive, the packet is discarded.
 - La Checksum Recalculation: Since the value of TTL is changed, the value of Checksum on much also be updated.
 - (d) Route lookup; The destination address is used to search forwarding table for output. The crosult of this search will indicate whether the packet is destined to single part (unicost) or multiple part (nutheast).
- le) fragmondation: If the Maximum transmission limit value of output port is less than the size of packet, then the packet needs to be fragmented.
- (f). Hardling IP option: The presence of IP option field indicate that there are especial proterring needs for the packet. The nowter needs to support these needs.
- on complex formalding Amotions:
- (a) Packet classification. The process of differentiating packets and taking necessary actions according to certain rules.



Algorithms to person forwarding table.	
(40). housing table versus formarding table.	
howing table	forwarding Table.
D- Process of finding path blw two new based on their addless.	O. Perocess of cending network data to lite destination port.
Deled by routers to forward traffic from one new to another. Delores destination address for networks. Delontains path routing Rafo. So All routing tables dee a form of forwarding tables. Delontains all the paths to different destinations.	Desides that process such as switches bridges that process packets faster B Responsible for storing next hop for each network. Or Contains port info. Or forwarding tables are not a form of routing tables. Contains only best path to every destination.
(x) Types of Routers: (core, edge, Enterprise)	
(a) Come Routers: + used for inter connecting a few thousand small notworks. - lost of moving traffic is chared among a large automa base. - lapable of Hourdling large amount of traffic. - High speed 8 reliability are primary requirement. - with an increase is no of systems connected, demand is	
placed on core routers to forward prove packets per second. Special algorithms are used for efficient and fast hookups.	

-) form critical nodes in a New Chould not fail under any Assureding and fociting Protocole continue to function b). Edge Rouders: - Also known as access Routers.

- deployed at the edge of the New for providing connectivity to customes. -> Should be capable of Handling dange amount of traffic. (c). Phyterprise Routers: - interconnect and systems located in companies, universities, etc. -) Provide connectivity at loss cool to a large no. of exitence -> hany ethernot segments that are comme ofed by tubs, bridges & switches -> Enexpensive devices. Can be easily installed. - Tends to degrade in performance as stre of Nho increasel. - They should support large no of ports. (x). Plements of Routers: A generic houter consists of & major functional modules: (a) Notwork Interfaces: - Contains many ports that provide connectivity to physical now links. Port serves as the entry & exit point for incoming & outgoing pack of. - N/w Arterfaces understands various data link protocole so that other the pack et asserves, it can decapsulate the packet. If extract the 11 headers

- Encapsulates the packet blu sending out to on the link

(b) forwarding Engines: - Responsible for deciding which now the incoming facket should be forwarded to.

autine packet or just the packet header to tormanding engine

I forwarding engine consults a table and determines the now to which the packet should be cent. This table is forwarding table

- packets when outgoing link is overbooked.

 I when these buffer queues overflow due to congestion, Queue havager selectively deops packets.
- (d). Traftic Manager: Responsible for prioritizing and regulating outgoing traffic.

 Sometimes due functionality of Queue Manager & Traffic Manager are merged into a single component.
- E) back flane! Provides connectivity for New Interfaces.

 It can either be chared where only a interfaces can communicate at any instance or be emplehed, where multiple interfaces can communicate simultaneously.
- (f) houte control brocesor: Responsible for implementing and executing routing protocols.

 Halutdin a routing table from routing table, forwarding table is computed & updated.


 It also handles errors.

(x) New Router Architectules at Shared CPU Architectus - Similar to the Architecture of Converdicual competers. - Shared back plane connecte multiple line cards - functional Modules such as traffic manager, forwarding engine also implemented in software. -) All the interface cards share cell for the functions. I when packet is received not ingress interface, an interrupt is raised at the CPU. Interrupt handler lopies the packet to main memory of CPU where Of 4 performs route bookup for eagress port - fivally it is workton into kutter of relevant cagress interface. - Advantages: Simplicity & Implementation. - Disadvantage: lack of scalability. shored CPY should bus. Enterfor Extenter Ad coface (k). Shared formeas ding Englise archite ture: - forwarding is faster than I'll architecture. Hack forwarding engine would have a different process dedicated perpressor that doil postorm route boky.

-) for waiting engine how memory that can be used to store forwarding

- line cards are connected to each other win a p back place to front

table.



(x) clustered Architecture Wed for increasing the no. of line conds. -) A packet entering New Interface in a line coul depending on the around of route lookup may be destried to line could in same cluster of or line and in a different dutor. - The packet must be forwarded to the appropriate duster. Advantage - Add a cluster of line and as per meed. are I'm aide Disaduantage: Switch core is style point of failure. (+) Sugart of Addressing on lookup: Addressing Architecture is of fundamental Augortance to Routing training - with classful Addelessing scheme, forwarding of packets is straightforward. - houses only ned to examine no pout to of destination addless to free et to destination. Thus, for wording table need to store single entry. such technique is called adolptes aggregation) using profise to preparent a group of addresses. I for classful addressing, the destination can be found using first few but only To wake a correct moter, routers must do more than just said notching be course prefixes can be some for different addresses. It reads to find nost specific mother that is longest mothering profit (d) · longest frefix hostoning! -) Algo used by routers to select an entry from forwarding takk - lockups the 18 profixes that will be destination for next - Routons book at the destination addresses repretis -> The voluter longlements longest mother as follows:

O. It receives a packet De benite processing header, it compares destination it address bit by the with the entries in routing table @ The entry that has longest in of loss New bits that modeline It destroyen address the best water. Example. I howter receives a packet with distinction if & 192.68.1.33 -). Routing table consular. 0 192.168.1.32 128 192.168.1.0/24 192.168.0.0/16. To determine longest notely convert IP addless to birrowy & Compan. 192.168.1.33 -1 11000000. 10101000. 00000001.00100001 Now moter all the Rowling Table Addresses which this -Littles rase 192. 188. 1.32/20 15the best watch -

(x) Bluary Tries A tre, - Also called digital tree / prefix tree is a type of search tree For locating epecific keye within a set. In order to access key, the trie is travelsed depth-first of A node is position defines the key with which it is associated - Huow finding longest profix that matches dest 19. marked as prefix. Partix doutabase P3 00+ 1014 PS 1114 Complexity & day n is the no- of propies.

to Multipit Has:

- Main principle is to examine several belts at a time (called a stride) in order to Improve performance

- strides can be either fixed or variable size.

Eg: Stride length =3. Prefix Motalare Node ! PI Root Node P2 1 0+ Norde 3 000 00× Py 001 101 * 100_ 010 PS 1112 011 PG 1000 × 100 101 mode 2 110