Statistical Learning based Estimation of the Mutual Information (SLEMI) - R package

User Manual

T. Jetka, K. Nienałtowski, T. Winarski, S. Błoński, M. Komorowski Version: August 9, 2018

Contents

1	Pre	liminaries	2
	1.1	Requirements - Hardware	2
		Requirements - Software	
		Installation	
2	Str	ucture of the package	4
	2.1	Input data	6
	2.2	Calculation of the information capacity	7
	2.3	Calculation of the mutual information	7
		Calculation of the probabilities of correct discrimination	
3	Dia	gnostic procedures	9
4	\mathbf{Add}	ditional functionalities of the function capacity_logreg_main()	9
5	Exa	amples	10
	5.1	Minimal example	10
	5.2	Further step-by-step introductory examples	14
	5.3		
6	List	of all package's functions	14

1 Preliminaries

1.1 Requirements - Hardware

- A 32 or 64 bit processor (recommended: 64bit)
- 1GHz processor (recommended: multicore for a comprehensive analysis)
- 2GB MB RAM (recommended: 4GB+, depends on the size of experimental data)

1.2 Requirements - Software

The main software requirement is the installation of the R environment (version: >= 3.2), which can be downloaded from R project website and is distributed for all common operating systems. We tested the package in R environment installed on Windows 7, 10; Mac OS X 10.11 - 10.13 and Ubuntu 18.04 with no significant differences in the performance. The use of a dedicated Integrated development environment (IDE), e.g. RStudio is recommended.

Apart from a base installation of R, SLEMI requires the following R packages:

- 1. for installation
- devtools
- 2. for estimation
- e1071
- Hmisc
- nnet
- glmnet
- caret
- doParallel (if parallel computation are needed)
- 3. for visualisation
- ggplot2
- ggthemes
- gridExtra
- corrplot
- 4. for data handling
- reshape2
- stringr
- plyr

Each of the above packages can be installed by executing

```
install_packages("name_of_a_package")
```

in the R console.

Importantly, during installation availability of the above packages will be verified and missing packages will be automatically installed.

1.3 Installation

The package can be directly installed from GitHub. For installation, open RStudio (or base R) and run following commands in the R console

```
install_packages("devtools") # run if 'devtools' is not installed
library(devtools)
install_github("sysbiosig/SLEMI")
```

Are required packages not found, they will be installed automatically.

2 Structure of the package

The three functions listed below constitute the key wrapper (interface) functions of the package.


- 1. mi_logreg_main() enables calculation of the mutual information
- 2. capacity_logreg_main() enables calculation of the information capacity
- 3. prob_discr_pairwise() serves to calculate probabilities of correct discrimination between pairs of input values

Below, we outline the architectures of these functions.

The function capacity_logreg_main() triggers

- i) preprocessing of the data
- ii) estimation of channel capacity
- iii) running diagnostic procedures
- iv) visualisation.

Each of the above steps is implemented within auxiliary functions as presented by the graph below.



The algorithm to compute the information capacity is implemented within the function capacity_logreg_algorithm(), which uses logistic regression from the nnet package.

Diagnostic procedures (significance and uncertainties of estimates) are provided in the function capacity_logreg_testing(). These are based on data bootstrapping and overfitting test.

For visualization, a set of graphs is created by the function capacity_output_graphs() and saved in a specified directory. In addition, capacity_logreg_main() returns a list with capacity estimates, optimal input probability distribution, diagnostic measures and other summary information about the analysis.

The function mi_logreg_main() serves to calculate the mutual information. It initiates similar steps as the function capacity_logreg_main() but without performing the optimization of the distribution of the input. Instead, it requires the input distribution to be specified bythe user as a function's argument.

Logistic regression and Monte Carlo methods, following an analogous algorithm as within the capacity_logreg_algorithm() function, are combined to estimate mutual information within a function mi_logreg_algorithm(). Visualisation and diagnostics are carried out by the same set of auxillary functions as for channel capacity (capacity_output_graphs() and capacity_logreg_testing()).

The prob_discr_pairwise() allows to estimate probabilities of correct discrimination between two different values of the input. It implements estimation of probabilities of correct classification by logistic regression (from nnet package) for each pair of input values. The probabilities of correct discrimination are visualized with a graph composed of pie charts.

2.1 Input data

Functions mi_logreg_main(), capacity_logreg_main(), prob_discr_pairwise() require data in the form of the object data.frame with a specific structure of rows and columns. As described in detail in Section 1 of the SI, single cell responses y_j^i are assumed to be measured for a finite set of stimuli levels x_1, x_2, \ldots, x_m . The responses y_j^i can be multidimensional. Usually, experimental dataset is represented as a table with rows and columns organized as below

input	output 1	output 2	output 3	
$n_1 \left\{ \begin{array}{c} x_1 \\ \vdots \\ x_1 \end{array} \right.$	$y_1^1(1) \\ \vdots \\ y_{n_1}^1(1)$	$y_1^1(2)$ \vdots $y_{n_1}^1(2)$	$y_1^1(3)$ \vdots $y_{n_1}^1(3)$	
$n_2 \left\{ \begin{array}{c} x_2 \\ \vdots \\ x_2 \end{array} \right.$	$\begin{array}{c c} y_1^2(1) \\ \vdots \\ y_{n_2}^2(1) \end{array}$	$y_1^2(2)$ \vdots $y_{n_2}^2(2)$	$\begin{array}{c c} y_1^2(3) \\ \vdots \\ y_{n_2}^2(3) \end{array}$	
÷	i :	i :	i i	
$n_m \left\{ \begin{array}{c} x_m \\ \vdots \\ x_m \end{array} \right.$	$ \begin{vmatrix} y_1^m(1) \\ \vdots \\ y_{n_m}^m(1) \end{vmatrix} $	$y_1^m(2) \\ \vdots \\ y_{n_m}^m(2)$	$y_1^m(3) \\ \vdots \\ y_{n_m}^m(3)$	

Therefore, the input data frame is expected to have the form represented by the above table, which can be formally described by the following conditions

- each row represent a response of a single cell
- first column contains values of the input (X).
- second and subsequent columns contain values of the measured output(s); these columns should be of type numeric; order and number of outputs should be the same for all cells.
- the number of unique values of the input should be finite
- a large number of observations, possibly >100, per input value is required.

An example of the input data.frame, which contains the measurements of the NfkB system presented in the MP is available within the package under the variable data_nfkb. It has the following format

	signal	response_0	response_3	response_6
1	0ng	0.3840744	0.4252835	0.4271986
2	0ng	0.4709216	0.5777821	0.5361948
3	0ng	0.4274474	0.6696011	0.8544916
10001	8ng	0.3120216	0.3475484	1.0925967
10002	8ng	0.2544961	0.6611051	2.2894928
10003	8ng	0.1807391	0.4336810	1.9783171
11540	100 ng	1.3534083	3.0158004	5.1592848
11541	100 ng	1.7007936	2.2224497	3.5463418
11542	100 ng	0.1997087	0.2886905	1.9324093

where each row represents measurements of a single-cell, the column named signal specifies the level of stimulation, while response_T is the response of the NfkB system in an individual cell at time point T. The above table can be shown in R by calling

```
library(SLEMI)
rbind(data_nkfb[1:3,1:4],data_nkfb[10001:10003,1:4],tail(data_nkfb[,1:4],3))
```

2.2 Calculation of the information capacity

Calculation of the information capacity withdefault settings is perfomed by the command capacity_logreg_main(dataRaw,signal, response, output_path)

where the required arguments are

- dataRaw data frame with column of type factor containing values of input (X) and columns of type numeric containing values of output (Y), where each row represents a single observation
- signal a character which indicates the name of the column in dataRaw with values of input (X)
- response a character vector which indicates the names of columns in dataRaw with values of output (Y)
- output_path a character with the directory, to which output should be saved

The function returns a list with the following elements

- cc a numeric with channel capacity estimate (in bits)
- p_opt a numeric vector with the optimal input distribution
- model a nnet object describing fitted logistic regression model
- data a data.frame with the raw experimental data (if dataout=TRUE)
- time processing time of the algorithm
- params a vector of parameters used in the algorithm
- regression a confusion matrix of logistic regression predictions
- logGraphs a list of gg or ggtables objects with a standard set of exploratory graphs

By default, all returned elements are saved in output_path directory in a file output.rds. Along with the output data, results of the computations are visualised as the graphs listed below

- MainPlot.pdf a simple summary plot with basic distribution visualization and capacity estimate
- MainPlot full.pdf a comprehensive summary plot with distribution visualization and capacity estimate
- capacity.pdf a diagram presenting the capacity estimates
- io relation.pdf a graph with input-output relation
- kdensities.pdf kernel density estimator of data distribution
- histograms.pdf histograms of data
- boxplots.pdf boxplots of data
- violin.pdf violin plots of data

2.3 Calculation of the mutual information

The function mi_logreg_main() takes a similar list of arguments and generates analogous plots to the function capacity_logreg_main(). The differences are listed below.

Firstly, user must specify the distribution of input that should be used for calculation of the mutual information. It is done by passing a numeric vector via the argument pinput of mi_logreg_main() function. Secondly, the returned list stores the value of the computed mutual information (in bits) under the element mi.

2.4 Calculation of the probabilities of correct discrimination

Calculation of the probabilities of correct discrimination between pairs of input values is performed by running the following command

```
prob_discr_pairwise(dataRaw,signal, response, output_path)
```

where the required arguments are analogous to the arguments of the functions capacity_logreg_main() and mi_logreg_main(). The probabilities of correct discrimination are computed for each pair of unique input values and returned as a list with the following elements

- prob_matr a symmetric numeric matrix with a probability of discriminating between i-th and j-th input values in cell (i,j)
- model a list of nnet objects describing fitted logistic regression models of classification two chosen input values.

In addition, a plot of corresponding pie charts is created in output_path in the pdf format.

3 Diagnostic procedures

In addition to the sole calculation of the information capacity, the function <code>capacity_logreg_main()</code> can also be used to asses accuracy of the channel capacity estimates resulting from potentially insuffecient sample size and potential over-fitting of the regression model. Two test are implemented. Precisely, the function can perfom

- 1. Bootstrap test capacity is re-calculated using $\alpha\%$ of data, sampled from the original dataset without replacement. After repeating the procedure n times, standard deviation of the obtained sample can serve as an error of the capacity estimate.
- 2. Over-fitting test the original data is divided into Training and Testing datasets. Then, logistic regression is estimated using $\alpha\%$ of data (training dataset), and integrals of channel capacity are calculated via Monte Carlo using remaining $(1-\alpha)\%$ of data (testing dataset). It is repeated n times.

In order to perform diagostic tests, that by default are turned off, user must set the value of the input argument

• testing = TRUE (default=FALSE)

In addition, settings of the diagnostic test can be altered by changing the following parameters

- TestingSeed (default= 1234) the seed for the random number generator used to sample original dataset.
- testing_cores (default= 4) a number of cores to use (via doParallel package) in parallel computing,
- boot_num (default= 40) a number of repetitions of the bootstrap,
- boot prob (default= 0.8) a fraction of initial observations to use in the bootstrap,
- traintest_num (default= 40) a number of repetitions of the overfitting test,
- partition_trainfrac (default= 0.6) a fraction of initial observations to use as a training dataset in the overfitting test

4 Additional functionalities of the function capacity_logreg_main()

In addition, to the basic functionalities described above, the function <code>capacity_logreg_main()</code> allows to control several other paramters of the alorithm that computes the information capacity. These parameters and their effects are listed below.

- model_out (default=TRUE) logical, specify if nnet model object should be saved into output file
- graphs (default=TRUE) logical, controls creating diagnostic plots in the output directory.
- plot width (default = 6) numeric, the basic width of created plots
- plot_height (default = 4) numeric, the basic height of created plots
- scale (default = TRUE) logical, value indicating if the columns of dataRaw are to be centered and scaled, what is usually recommended for the purpose of stability of numerical computations. From a purely theoretical perspective, such transformation does not influence the value of channel capacity.
- lr_maxit (default = 1000) a maximum number of iterations of fitting step of logistic regression algorithm in nnet function. If a warning regarding lack of convergence of logistic model occurs, should be set to a larger value (possible if data is more complex or of a very high dimension).
- MaxNWts (default = 5000) a maximum number of parameters in logistic regression model. A limit is set to prevent accidental over-loading the memory. It should be set to a larger value in case of exceptionally high dimension of the output data or very high number of input values. In principle, logistic model requires fitting $(m-1) \cdot (d+1)$ parameters, where m is the number of unique input values and d is the dimension of the output.

The latter two parameters, i.e lr_maxit and MaxNWts, allow to change the parameters of the logistic regression model fitting within the dependent nnet package.

5 Examples

5.1 Minimal example

Below, we present a minimal model that may serve as a quick introduction to computations within the package. Precisely, we consider a system

- i) with four different input values X: 0, 0.1, 1 and 10
- ii) with the conditional output, Y|X=x, give by a one-dimensional log-normal distribution $\exp\{\mathcal{N}(10 \cdot \frac{x}{1+x}, 1)\}$
- iii) and the sample consisting of 1000 observations for each input value.

The example is analogous to the Test example 2 of the SI (Section 3.2).

Input data

Firstly, we generate a a synthetic dataset. The data corresponding to the model can be generated, and represented as the data frame tempdata with columns input and output, by running

The generated data frame has the following structure

	input	output
1	0	1.1801782
2	0	-0.4382345
2001	1	3.8476580
2002	1	5.2792912
3999	10	10.4708163
4000	10	8.5643509

Calculation of the information capacity

The Information capacit can be calculated using the capacity_logreg_main() function that takes the data frame "tempdata" as dataRaw argument. Column names "input" and "output" are used as arguments signal and response, respectively. The output_path is set as "minimal_example/". Therefore, the function is run as follows

Results of the computations are returned as a data structure described before. In addition, results are presented in the form of the following graph (by default saved as MainPlot.pdf in minimal_example/directory). It represents the input-output data and gives the corresponding channel capacity.

Calculation of the mutual information

To compare mutual information of experimental data with its channel capacity, we can run (uniform distribution of input values is assumed)




Figure 1: Standard output graph of the minimal working example

[1] "Mutual Information: 1.50434978542695; Channel Capacity: 1.56100716713601"

Calculation of the probabilities of correct discrimination

Probabilities of correct discrimination between input values are calculated as follows

The above command generates the following graph in the output directory

Diagnostics

The diagnostic test can be performed as follows




Figure 2: Standard output graph presenting probabilities of correct discrimination between each pair of input values.

It will run diagnostics with 40 re-sampling of the data, where bootstrap is calculated using 80% of the data, while the over-fitting test uses 60% of the original dataset.

It provides the following result

The top diagram shows the value of the capacity estimate (in black) obtained from the complete dataset and the mean value of bootstrap repetitions with indicated +/- standard deviation (in red). Plots that follow show histograms of calculated capacities for different diagnostic regimes. The black dot represents the estimate of the channel capacity based on the complete dataset. In addition, corresponding empirical p-values of both tests (left- and right-sided) are calculated to assess the randomness of obtained results (PV in the plots).

A reliable estimation of the information capacity should yield the following results of the bootstrap and overfitting tests.

Capacity 0.423 0.403 0.4450.3882185 0.4594617 Capacity (bits) **Bootstrap** PV-left: 0.6 **50** 25 0.43 PV-right: 0.4 0.41 0.45 Capacity (bits) **TrainTest** PV-left: 0.367 density 0 10 0 0 0.39 0.42 0.45 PV-right: 0.633 0.48 Capacity (bits)

Figure 3: Standard output graph of the diagnostic procedures. P-values (PV) are based on empirical test either left- or right- sided. In the top axis, black dot represents the estimate of the channel capacity that involves the compete dataset, red dot is the mean of bootstrap procedures, while the bars are mean +/- sd. The remaining panels are histograms of all repetitions of a specific diagnostic procedure.

- 1. The bootstrap test should yield distribution of the capacity estimates with small variance. In addition, the capacity estimated based on the complete dataset should not be an outlier (p-value>0.05). Otherwise, it would indicate that the sample size is too low for an accurate estimation of the channel capacity.
- 2. The over-fitting test should provide similar results. The capacity estimate obtained based on the complete dataset should lie within the distribution of capacities generated in the test. In the opposite case, it could mean that the logistic regression model does not fully grasp the essential aspects of input-output dependencies in the data.

5.2 Further step-by-step introductory examples

Two step-by-step examples that further illustrate the applicability of the SLEMI package are provided in the Section 6 of the 'testing procedures' pdf file that is part of the package.

5.3 Examples in MP and SI

To reproduce results of the NFkB analysis presented in the MP as well as the results of the comparison with the KNN method presented in the Section 2 of the SI see Section 7 of the 'testing procedures' pdf file that is part of the package.

6 List of all package's functions

The list below contains all functions available to the user:

- capacity_logreg_main() is the main wrapper function that estimates channel capacity based on experimental data
- capacity_logreg_algorithm() implements algorithm to estimate channel capacity using nnet package
- capacity_klogreg_algorithm() implements algorithm to estimate channel capacity using glmnet package
- capacity_logreg_testing() performs diagnostic procedures
- capacity_output_graphs() generates exploratory graphs
- mi_logreg_main() estimates mutual information
- prob_discr_pairwise() estimates probabilities of discrimination between all pairs of input values
- formula_generator() generates a formula object based on input and output specification
- sampling_bootstrap(), sampling_partition(), sampling_shuffle() generates subsets of data to use in diagnostic procedures
- theme_publ() changes the visual elements of ggplot object

The tables below contain full specification of the package's functions

dataRaw signal response output_path scale graphs model_out dataout testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	data frame with input (X) and output (Y) values in separate columns character indicating a name of column of dataRaw with input (X) character vector indicating names of columns of dataRaw with measurements of outputs (Y) directory in which result and graphs will be saved logical indicating if preprocessing (centering and scaling) should be carried out before the analysis logical indicating if standard graphs should be created logical indicating if the model object should be returned logical indicating if the dataRaw should be returned with results logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw with side variables, if NULL no side variables are included in estimation	default (required (required (required TRUE TRUE TRUE TRUE TRUE 1234 1 10 0.8 10 0.6 NULL
signal response output_path scale graphs model_out dataout testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	character indicating a name of column of dataRaw with input (X) character vector indicating names of columns of dataRaw with measurements of outputs (Y) directory in which result and graphs will be saved logical indicating if preprocessing (centering and scaling) should be carried out before the analysis logical indicating if standard graphs should be created logical indicating if the model object should be returned logical indicating if the dataRaw should be returned with results logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	(required (required TRUE) TRUE TRUE TRUE TRUE TRUE FALSE 1234 1 10 0.8 10 0.6
response output_path scale graphs model_out dataout testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	character vector indicating names of columns of dataRaw with measurements of outputs (Y) directory in which result and graphs will be saved logical indicating if preprocessing (centering and scaling) should be carried out before the analysis logical indicating if standard graphs should be created logical indicating if the model object should be returned logical indicating if the dataRaw should be returned with results logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	(required TRUE TRUE TRUE TRUE TRUE FALSE 1234 1 10 0.8 10 0.6
output_path scale graphs model_out dataout testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	with measurements of outputs (Y) directory in which result and graphs will be saved logical indicating if preprocessing (centering and scaling) should be carried out before the analysis logical indicating if standard graphs should be created logical indicating if the model object should be returned logical indicating if the dataRaw should be returned with results logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	(required TRUE TRUE TRUE TRUE FALSE 1234 1 10 0.8 10 0.6
output_path scale graphs model_out dataout testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	directory in which result and graphs will be saved logical indicating if preprocessing (centering and scaling) should be carried out before the analysis logical indicating if standard graphs should be created logical indicating if the model object should be returned logical indicating if the dataRaw should be returned with results logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	TRUE TRUE TRUE TRUE FALSE 1234 1 10 0.8 10 0.6
graphs model_out dataout testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	logical indicating if preprocessing (centering and scaling) should be carried out before the analysis logical indicating if standard graphs should be created logical indicating if the model object should be returned logical indicating if the dataRaw should be returned with results logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	TRUE TRUE TRUE TRUE FALSE 1234 1 10 0.8 10 0.6
graphs model_out dataout testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	should be carried out before the analysis logical indicating if standard graphs should be created logical indicating if the model object should be returned logical indicating if the dataRaw should be returned with results logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	TRUE TRUE TRUE FALSE 1234 1 10 0.8 10 0.6
graphs model_out dataout testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	logical indicating if standard graphs should be created logical indicating if the model object should be returned logical indicating if the dataRaw should be returned with results logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	TRUE TRUE FALSE 1234 1 10 0.8 10 0.6
model_out dataout testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	logical indicating if the model object should be returned logical indicating if the dataRaw should be returned with results logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	TRUE TRUE FALSE 1234 1 10 0.8 10 0.6
dataout testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	logical indicating if the dataRaw should be returned with results logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	TRUE FALSE 1234 1 10 0.8 10 0.6
testing TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	logical indicating if diagnostics should be performed the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	FALSE 1234 1 10 0.8 10 0.6
TestingSeed testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	the seed of random number generator to be used in diagnostics number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	1234 1 10 0.8 10 0.6
testing_cores boot_num boot_prob traintest_num partition_trainfrac side_variables	number of cores to use in parallel computing in diagnostics the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	1 10 0.8 10 0.6
boot_num boot_prob traintest_num partition_trainfrac side_variables	the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	10 0.8 10 0.6
boot_num boot_prob traintest_num partition_trainfrac side_variables	the number of bootstrap tests to be performed (used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	0.8 10 0.6
boot_prob traintest_num partition_trainfrac side_variables	(used if testing=TRUE) the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	10 0.6
traintest_num partition_trainfrac side_variables	the proportion of data to be used in bootstrap (used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	10 0.6
traintest_num partition_trainfrac side_variables	(used if testing=TRUE) the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	10 0.6
partition_trainfrac side_variables	the number of over-fitting tests to be performed (used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	0.6
partition_trainfrac side_variables	(used if testing=TRUE) the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	0.6
side_variables	the proportion of data to be used as a training dataset (used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	
side_variables	(used if testing=TRUE) an optional character vector indicating names of columns in dataRaw	
	an optional character vector indicating names of columns in dataRaw	NITIT T
		1 1/11/11/1
rodomen misse		NOLL
research militry	is the number of resmapling tests to be performed	10
resamp_num	(used if testing=TRUE)	10
plot_height	the basic dimnesion of plots (height)	4
	the basic dimnesions of plots (width)	6
-	the maximum number of iteration to optimise channel capacity	100
	the maximum number of iteration to optimise channel capacity the maximum number of iteration to estimate logisitic model	1000
	9	
	the maximum number of parameters in logistic regression algorithm	5000
formula_string	character object that includes a formula syntax to use in logistic model	NULL
-	logical indicating if the glmnet package should be used	FALSE
	numeric matrix with columns treated as explanatory variables	NULL
	in logistic model (used if glmnet_algorithm=TRUE)	_
glmnet_cores	the number of cores to use in parallel computing of glmnet package	1
	(used if glmnet_algorithm=TRUE)	
glmnet_lambdanum	is the lambda parameter as in glmnet package	10
	(used if glmnet_algorithm=TRUE)	
	Values – a list with elements	
name	description	
cc	a numeric with the estimate of channel capacity (in bits)	
p_opt	a numeric vector with estimated optimal input probability	
time	processing time of the algorithm	
params	a vector of parameters used in the algorithm	
data	a data.frame with the raw experimental data (if dataout=TRUE)	
	confusion matrix of logistic regression predictions	
_	nnet object describing logistic regression model (if model_out=TRUE)	
	a list of gg or ggtables objects with a standard set of exploratory graphs	
U Ir ···	(if graphs=TRUE)	
testing	a list of results of diagnostic procedures, e.g. \$testing\$bootstrap	
<u> </u>	has boot_num elements, each with results of the algorithm of each diagno	ostic run
	a list of left- and right-tailed p-values of diagnostic procedures	ooute rull

Function: mi_logreg_main()
Main wrapper function to mutual information from experimental data

	Arguments	
name	description	default
dataRaw	data frame with input (X) and output (Y) values in separate columns	(required)
signal	character indicating a name of column of dataRaw with input (X)	(required)
response	character vector indicating names of columns of dataRaw	(required)
	with measurements of outputs (Y)	
$\operatorname{output_path}$	directory in which result and graphs will be saved	(required)
scale	logical indicating if preprocessing (centering and scaling)	TRUE
	should be carried out before the analysis	
graphs	logical indicating if standard graphs should be created	TRUE
$model_out$	logical indicating if the model object should be returned	TRUE
dataout	logical indicating if the dataRaw should be returned with results	TRUE
testing	logical indicating if diagnostics should be performed	FALSE
TestingSeed	the seed of random number generator to be used in diagnostics	1234
$testing_cores$	number of cores to use in parallel computing in diagnostics	1
boot_num	the number of bootstrap tests to be performed	10
	(used if testing=TRUE)	
$boot_prob$	the proportion of data to be used in bootstrap	0.8
	(used if testing=TRUE)	
$traintest_num$	the number of over-fitting tests to be performed	10
	(used if testing=TRUE)	
$partition_trainfrac$	the proportion of data to be used as a training dataset	0.6
	(used if testing=TRUE)	
$side_variables$	an optional character vector indicating names of columns in dataRaw	NULL
	with side variables, if NULL no side variables are included in estimation	
$resamp_num$	is the number of resmapling tests to be performed	10
	(used if testing=TRUE)	
plot _height	the basic dimnesion of plots (height)	4
plot _width	the basic dimnesions of plots (width)	6
pinput	an optional numeric vector with arbitrary probabilities of input.	NULL
	If NULL, fractions of observations in full dataset of each class are used.	
lr_maxit	the maximum number of iteration to estimate logisitic model	1000
$\max NWts$	the maximum number of parameters in logistic regression algorithm	5000
$formula_string$	character object that includes a formula syntax to use in logistic model	NULL
$glmnet_algorithm$	logical indicating if the glmnet package should be used	FALSE
dataMatrix	numeric matrix with columns treated as explanatory variables	NULL
	in logistic model (used if glmnet_algorithm=TRUE)	
$glmnet_cores$	the number of cores to use in parallel computing of glmnet package	1
	(used if glmnet_algorithm=TRUE)	
glmnet_lambdanum	is the lambda parameter as in glmnet package	10
	(used if glmnet_algorithm=TRUE)	
	Values – a list with elements	
name	description	
mi	a numeric with the estimate of mutual information (in bits)	
p_opt	a numeric vector with estimated optimal input probability	

name	description
mi	a numeric with the estimate of mutual information (in bits)
p_opt	a numeric vector with estimated optimal input probability
time	processing time of the algorithm
params	a vector of parameters used in the algorithm
data	a data.frame with the raw experimental data (if dataout=TRUE)
regression	confusion matrix of logistic regression predictions
model	nnet object describing logistic regression model (if model_out=TRUE)
logGraphs	a list of gg or ggtables objects with a standard set of exploratory graphs
	(if graphs=TRUE)
testing	a list of results of diagnostic procedures, e.g. \$testing\$bootstrap
	has boot_num elements, each with results of the algorithm of each diagnostic run
$testing_pv$	a list of left- and right-tailed p-values of diagnostic procedures

Function: prob_discr_pairwise() Computation of pairwise probabilities of discrimination

Arguments				
name	description	default		
dataRaw	data frame with input (X) and output (Y) values in separate columns	(required)		
signal	character indicating a name of column of dataRaw with input (X)	(required)		
response	character vector indicating names of columns of dataRaw	(required)		
	with measurements of outputs (Y)			
$output_path$	directory in which result and graphs will be saved	(required)		
scale	logical indicating if preprocessing (centering and scaling)	TRUE		
	should be carried out before the analysis			
$\operatorname{model}\operatorname{_out}$	logical indicating if the model object should be returned	TRUE		
$side_variables$	an optional character vector indicating names of columns in dataRaw	NULL		
	with side variables, if NULL no side variables are included in estimation			
lr_maxit	the maximum number of iteration to estimate logisitic model	1000		
$\max NWts$	the maximum number of parameters in logistic regression algorithm	5000		
$formula_string$	character object that includes a formula syntax to use in logistic model	NULL		
	Values – a graph of pie charts is created in output_path directory.			
	In addition, function returns a list with elements			
name	description			
prob_matr	a symmetric numeric matrix of size			
	$= length(unique(dataRaw[[signal]])) \times length(unique(dataRaw[[signal]])) = length(unique(dataRaw[[signa]])) = length($	nal]]))		
	with probability of discriminating between i-th and j-th input values in [i,j] cell		
model	a list of nnet objects describing logistic regression models (if model_out=	=TRUE)		

Function: capacity_logreg_algorithm()
Implements algorithm to estimate channel capacity using nnet package

Arguments				
name	description	default		
data	data frame with input (X) and output (Y) values in separate columns	(required)		
signal	character indicating a name of column of dataRaw with input (X)	(required)		
response	character vector indicating names of columns of dataRaw	(required)		
	with measurements of outputs (Y)			
$model_out$	logical indicating if the model object should be returned	TRUE		
$side_variables$	an optional character vector indicating names of columns in dataRaw	NULL		
	with side variables, if NULL no side variables are included in estimation			
cc_maxit	the maximum number of iteration to optimise channel capacity	100		
lr_maxit	the maximum number of iteration to estimate logisitic model	1000		
$\max NWts$	the maximum number of parameters in logistic regression algorithm	5000		
$formula_string$	character object that includes a formula syntax to use in logistic model	NULL		
	Values – a list with elements	1		
name	name description			
cc	a numeric with the estimate of channel capacity (in bits)			
p_opt	a numeric vector with estimated optimal input probability			
regression	confusion matrix of logistic regression predictions			
model	model nnet object describing logistic regression model (if model_out=TRUE)			

Function: capacity_klogreg_algorithm()
Implements algorithm to estimate channel capacity using glmnet package

Implements algorithm to estimate channel capacity using gimnet package					
Arguments					
name	description	default			
dataMatrix	numeric matrix with columns treated as explanatory variables	(required)			
	(output, Y, of the channel)				
dataSignal	factor vector with inputs (X) of the channel	(required)			
	length must be equal to the number of rows of dataMatrix				
cv_core_num	the number of cores to use in parallel computing of glmnet package	1			
lambda_num	is the lambda parameter as in glmnet package	10			
$model_out$	logical indicating if the model object should be returned	TRUE			
cc_maxit	the maximum number of iteration to optimise channel capacity	100			
	Values – a list with elements				
name	name description				
cc a numeric with the estimate of channel capacity (in bits)					
p_opt a numeric vector with estimated optimal input probability					
regression	confusion matrix of logistic regression predictions				
model					

Function: capacity_logreg_testing()
Performs diagnostic procedures

	Arguments	
name	description	default
data	data frame with input (X) and output (Y) values in separate columns	(required)
signal	character indicating a name of column of dataRaw with input (X)	(required)
response	character vector indicating names of columns of dataRaw	(required)
	with measurements of outputs (Y)	
$output_path$	directory in which result and graphs will be saved	(required)
TestingSeed	the seed of random number generator to be used in diagnostics	1234
$testing_cores$	number of cores to use in parallel computing in diagnostics	1
$boot_num$	the number of bootstrap tests to be performed	10
	(used if testing=TRUE)	
$boot_prob$	the proportion of data to be used in bootstrap	0.8
	(used if testing=TRUE)	
$traintest_num$	the number of over-fitting tests to be performed	10
	(used if testing=TRUE)	
partition_trainfrac	the proportion of data to be used as a training dataset	0.6
	(used if testing=TRUE)	
$side_variables$	an optional character vector indicating names of columns in dataRaw	NULL
	with side variables, if NULL no side variables are included in estimation	
$resamp_num$	is the number of resmapling tests to be performed	10
	(used if testing=TRUE)	
cc_maxit	the maximum number of iteration to optimise channel capacity	100
lr_maxit	the maximum number of iteration to estimate logisitic model	1000
$\max NWts$	the maximum number of parameters in logistic regression algorithm	5000
$formula_string$	character object that includes a formula syntax to use in logistic model	NULL
$glmnet_algorithm$	logical indicating if the glmnet package should be used	FALSE
dataMatrix	numeric matrix with columns treated as explanatory variables	NULL
	in logistic model (used if glmnet_algorithm=TRUE)	
$glmnet_cores$	the number of cores to use in parallel computing of glmnet package	1
	(used if glmnet_algorithm=TRUE)	
glmnet_lambdanum	is the lambda parameter as in glmnet package	10
	(used if glmnet_algorithm=TRUE)	
	Values – a list with elements	
bootstrap	list of size boot_num, where each element is the returned value of	
	capacity_logreg_algorithm() from a single run of bootstrap	
traintest	list of size traintest_num, where each element is the returned value of	
	capacity_logreg_algorithm() from a single run of over-fitting test	
resamplingMorph	list of size resamp_num, where each element is the returned value of	
	capacity_logreg_algorithm() from a single run of resampling test	
	(used if side_variables is not NULL)	
bootResampMorph	list of size resamp_num, where each element is the returned value of	
	capacity_logreg_algorithm() from a single run of resampling test II	
	(used if side_variables is not NULL)	

Function: capacity_output_graphs() Generates exploratory graphs

Arguments				
name	description	default		
data	data frame with input (X) and output (Y) values in separate columns	(required)		
signal	character indicating a name of column of dataRaw with input (X)	(required)		
response	character vector indicating names of columns of dataRaw	(required)		
	with measurements of outputs (Y)			
$output_path$	directory in which result and graphs will be saved	(required)		
cc_output	logical indicating if preprocessing (centering and scaling)	TRUE		
height	the basic dimnesion of plots (height)	4		
width	the basic dimnesions of plots (width)	6		
	Values – a list with elements			
name	description			
1	A comprehensive summary plot			
2	Input-Output relation			
3	Boxplots of data			
4	Violin plots of data			
5	Histograms of data			
6	Boxplot of side variables in data			
7	Capacity results			
8	Density plots			
9	A simple summary plot			

Function: formula_generator()
Generates a formula object based on input and output specification

Arguments			
name	description	default	
signal	character indicating a name of column of dataRaw with input (X)	(required)	
response	character vector indicating names of columns of dataRaw	(required)	
	with measurements of outputs (Y)		
$side_variables$	an optional character vector indicating names of columns in dataRaw	NULL	
	with side variables, if NULL no side variables are included in estimation		
Values – a list with elements			
name	description		
formula_string	character object that includes a formula syntax to use in logistic model	NULL	

Function: sampling_bootstrap(), sampling_partition(), sampling_shuffle() Used to generate subsets of data to use in diagnostic procedures

Arguments				
name	description	default		
data	data.frame to be resampled	(required)		
dataDiv	character indicating column of data, with respect to which split the data;	(required)		
	only in sampling_bootstrap() and sampling_partition()			
prob	the of data that should be sampled from the whole dataset;	(required)		
	only in sampling_bootstrap()			
partition_trainfrac	the proportion of data to be used as a training dataset;	(required)		
	only in sampling_partition()			
$side_variables$	vector of characters indicating columns of data the will be reshuffled;	(required)		
	only in sampling_shuffle()			
Values – a data.frame with the same structure as initial data object				

Function: theme_publ()
Changes the visual elements of ggplot object

Changes the visual elements of Sapiot object				
Arguments				
name	description	default		
version	possible values: 1,2,3. Selects different coloring and presentation options	1		
$base_size$	the size of font to use in graph	12		
base_family	the type of font to use in graph	sans		
Values – a ggplot theme object				