
CS 33

Machine Programming (1)

Data Types on Intel x86

- "Integer" data of 1, 2, or 4 bytes (plus 8 bytes on x86-64)
 - data values
 - » whether signed or unsigned depends on interpretation
 - addresses (untyped pointers)
- Floating-point data of 4, 8, or 10 bytes
- No aggregate types such as arrays or structures
 - just contiguously allocated bytes in memory


Operand Size



- Rather than mov ...
 - movb
 - movs
 - movl
 - movq (x86-64 only)

General-Purpose Registers (IA32)

Origin (mostly obsolete)



accumulate

counter

data

base

source index

destination
index

stack pointer base

pointer

16-bit virtual registers (backwards compatibility)

Moving Data: IA32

Moving data

mov1 source, dest

- Operand types
 - Immediate: constant integer data
 - » example: \$0x400, \$-533
 - » like C constant, but prefixed with \\$'
 - » encoded with 1, 2, or 4 bytes
 - Register: one of 8 integer registers
 - » example: %eax, %edx
 - » but %esp and %ebp reserved for special use
 - » others have special uses for particular instructions
 - Memory: 4 consecutive bytes of memory at address given by register(s)
 - » simplest example: (%eax)
 - » various other "address modes"

```
%ecx
%edx
%ebx
%esi
%edi
%esp
%ebp
```

movl Operand Combinations

Cannot (normally) do memory-memory transfer with a single instruction

Simple Memory Addressing Modes

- Normal (R) Mem[Reg[R]]
 - -register R specifies memory address

```
movl (%ecx), %eax
```

- Displacement D(R) Mem[Reg[R]+D]
 - -register R specifies start of memory region
 - constant displacement D specifies offset

```
movl 8(%ebp), %edx
```


Using Simple Addressing Modes

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

swap:

```
pushl %ebp
                        Set
movl %esp,%ebp
                        Up
pushl %ebx
mov1 8(%ebp), %edx
movl 12(%ebp), %ecx
movl (%edx), %ebx
                        Body
movl (%ecx), %eax
movl %eax, (%edx)
movl %ebx, (%ecx)
popl %ebx
popl %ebp
                        Finish
ret
```

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```



```
Register Value
%edx xp
%ecx yp
%ebx t0
%eax t1
```

```
movl 8(%ebp), %edx # edx = xp
movl 12(%ebp), %ecx # ecx = yp
movl (%edx), %ebx # ebx = *xp (t0)
movl (%ecx), %eax # eax = *yp (t1)
movl %eax, (%edx) # *xp = t1
movl %ebx, (%ecx) # *yp = t0
```

%eax

%edx

%ecx


%ebx

%esi

%edi

%esp

%ebp 0x104



```
movl 8(%ebp), %edx # edx = xp
movl 12(%ebp), %ecx # ecx = yp
movl (%edx), %ebx # ebx = *xp (t0)
movl (%ecx), %eax # eax = *yp (t1)
movl %eax, (%edx) # *xp = t1
movl %ebx, (%ecx) # *yp = t0
```

%eax

%edx 0x124

%ecx


%ebx

%esi

%edi

%esp

%ebp 0x104



```
movl 8(%ebp), %edx # edx = xp
movl 12(%ebp), %ecx # ecx = yp
movl (%edx), %ebx # ebx = *xp (t0)
movl (%ecx), %eax # eax = *yp (t1)
movl %eax, (%edx) # *xp = t1
movl %ebx, (%ecx) # *yp = t0
```

%eax

%edx 0x124

%ecx 0x120


%ebx

%esi

%edi

%esp

%ebp 0x104



```
movl 8(%ebp), %edx # edx = xp
movl 12(%ebp), %ecx # ecx = yp
movl (%edx), %ebx # ebx = *xp (t0)
movl (%ecx), %eax # eax = *yp (t1)
movl %eax, (%edx) # *xp = t1
movl %ebx, (%ecx) # *yp = t0
```

%eax

%edx 0x124

%ecx 0x120


%ebx 123

%esi

%edi

%esp

%ebp 0x104



```
movl 8(%ebp), %edx # edx = xp
movl 12(%ebp), %ecx # ecx = yp
movl (%edx), %ebx # ebx = *xp (t0)
movl (%ecx), %eax # eax = *yp (t1)
movl %eax, (%edx) # *xp = t1
movl %ebx, (%ecx) # *yp = t0
```

%eax	456
%edx	0x124
%есх	0x120
%ebx	123
%esi	
%edi	
%esp	

		123	0x124
		456	0x120
			0x11c
			0x118
Off	set		0x114
ур	12	0x120	0x110
хр	8	0x124	0x10c
	4	Rtn adr	0x108
%ebp —	→ 0		0x104
	-4		0x100

```
movl 8(%ebp), %edx # edx = xp
movl 12(%ebp), %ecx # ecx = yp
movl (%edx), %ebx # ebx = *xp (t0)
movl (%ecx), %eax # eax = *yp (t1)
movl %eax, (%edx) # *xp = t1
movl %ebx, (%ecx) # *yp = t0
```

 %eax
 456

 %edx
 0x124

 %ecx
 0x120

 %ebx
 123

 %esi
 %esp

%ebp

		456	0x124
		456	0x120
			0x11c
			0x118
0	Offset		0x114
ур	12	0x120	0x110
хр	8	0x124	0x10c
	4	Rtn adr	0x108
%ebp -	→ 0		0x104
	-4		0x100

Address

```
movl 8(%ebp), %edx # edx = xp
movl 12(%ebp), %ecx # ecx = yp
movl (%edx), %ebx # ebx = *xp (t0)
movl (%ecx), %eax # eax = *yp (t1)
movl %eax, (%edx) # *xp = t1
movl %ebx, (%ecx) # *yp = t0
```

0x104


%eax	456
%edx	0x124
%ecx	0x120
%ebx	123
%esi	
%edi	
%esp	
%ebp	0x104

```
456
                          0x124
               123
                          0x120
                          0x11c
                          0x118
      Offset
                          0x114
          12
               0 \times 120
yp
                          0x110
           8
               0x124
хр
                          0x10c
           4
               Rtn adr
                          0x108
%ebp
                          0x104
          -4
                          0 \times 100
```

```
movl 8(%ebp), %edx # edx = xp
movl 12(%ebp), %ecx # ecx = yp
movl (%edx), %ebx # ebx = *xp (t0)
movl (%ecx), %eax # eax = *yp (t1)
movl %eax, (%edx) # *xp = t1
movl %ebx, (%ecx) # *yp = t0
```

Quiz 1

```
movl -4(%ebp), %eax
movl (%eax), %eax
movl (%eax), %eax
movl %eax, -8(%ebp)
```



Which C statements best describe the assembler code?

Complete Memory-Addressing Modes

Most general form

D(Rb,Ri,S) Mem[Reg[Rb]+S*Reg[Ri]+D]

– D: constant "displacement"

Rb: base register: any of 8 integer registers

- Ri: index register: any, except for %esp

» unlikely you'd use %ebp either

- S: scale: 1, 2, 4, or 8

Special cases

(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]]

D(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]+D]

(Rb,Ri,S) Mem[Reg[Rb]+S*Reg[Ri]]

D Mem[D]

Address-Computation Examples

%edx	0xf000
%ecx	0x0100

Expression	Address Computation	Address
0x8(%edx)	0xf000 + 0x8	0xf008
(%edx,%ecx)	0xf000 + 0x0100	0xf100
(%edx,%ecx,4)	0xf000 + 4*0x0100	0xf400
0x80(,%edx,2)	2*0xf000 + 0x80	0x1e080

Address-Computation Instruction

- leal src, dest
 - src is address mode expression
 - set dest to address denoted by expression

Uses

computing addresses without a memory reference

```
» e.g., translation of p = &x[i];
```

computing arithmetic expressions of the form x + k*y

```
  k = 1, 2, 4, or 8
```

Example

```
int mul12(int x)
{
   return x*12;
}
```

Converted to ASM by compiler:

```
movl 8(%ebp), %eax  # get arg
leal (%eax,%eax,2), %eax  # t <- x+x*2
sall $2, %eax  # return t<<2
```

Quiz 2

What value ends up in %ecx?

movl \$1000,%eax
movl \$1,%ebx
movl 2(%eax,%ebx,4),%ecx

a) 0x02030405

b) 0x05040302

c) 0x06070809

d) 0x09080706

1009:

0x09

1008:

80x0

1007:

0x07

1006:

0x06

1005:

0x05

1004:

0x04

1003:

0x03

1002:

0x02

1001:

0x01

%eax \rightarrow 1000:


0x00

Hint:





x86-64 General-Purpose Registers



- Extend existing registers to 64 bits. Add 8 new ones.
- No special purpose for %ebp/%rbp

32-bit Instructions on x86-64

- addl 4(%rdx), %eax
 - memory address must be 64 bits
 - operands (in this case) are 32-bit
 - » result goes into %eax
 - lower half of %rax
 - upper half is filled with zeroes

32-bit code for swap

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

swap:

```
pushl %ebp
                       Set
movl %esp,%ebp
pushl %ebx
movl 8(%ebp), %edx
movl 12(%ebp), %ecx
movl (%edx), %ebx
                       Body
movl (%ecx), %eax
movl %eax, (%edx)
movl %ebx, (%ecx)
popl %ebx
popl %ebp
                       Finish
ret
```

64-bit code for swap

swap:

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

- Arguments passed in registers (why useful?)
 - first (xp) in %rdi, second (yp) in %rsi
 - 64-bit pointers
- No stack operations required
- 32-bit data
 - data held in registers %eax and %edx
 - mov1 operation

64-bit code for long int swap

```
void swap(long *xp, long *yp)
```

```
long t0 = *xp;
long t1 = *yp;
*xp = t1;
*yp = t0;
}
```

```
Set
Up

movq (%rdi), %rdx
movq (%rsi), %rax
movq %rax, (%rdi)
movq %rdx, (%rsi)


Finish
```

64-bit data

- data held in registers %rax and %rdx
- movq operation
 - » "q" stands for quad-word

Turning C into Object Code

- Code in files p1.c p2.c
- Compile with command: gcc -01 p1.c p2.c -o p
 - » use basic optimizations (-01)
 - » put resulting binary in file p



Object Code

Code for sum

0xc3

```
0x401040 < sum > :
    0x55
    0x89
    0xe5
    0x8b
    0x45
    0x0c
    0 \times 0.3
    0 \times 45
    0x08

    Total of 11 bytes

    0x5d
              • Each instruction:
```


1, 2, or 3 bytes

Starts at address

 0×401040

- Assembler
 - translates .s into .o
 - binary encoding of each instruction
 - nearly-complete image of executable code
 - missing linkages between code in different files
- Linker
 - resolves references between files
 - combines with static run-time libraries
 - » e.g., code for printf
 - some libraries are dynamically linked
 - » linking occurs when program begins execution

Instruction Format



Disassembling Object Code

Disassembled

Disassembler

```
objdump -d <file>
```

- useful tool for examining object code
- analyzes bit pattern of series of instructions
- produces approximate rendition of assembly code
- can be run on either executable or object (.o) file

Alternate Disassembly

Object

Disassembled

```
0x401040:

0x55

0x89

0xe5

0x8b

0x45

0x0c

0x03

0x45

0x08

0x5d

0xc3
```

```
Dump of assembler code for function sum:
0x080483c4 < sum + 0 > :
                       push
                               %ebp
0x080483c5 < sum + 1>:
                               %esp,%ebp
                       mov
0x080483c7 < sum + 3>:
                               0xc(%ebp), %eax
                       mov
0x080483ca < sum + 6>: add
                               0x8(%ebp),%eax
0x080483cd < sum + 9>:
                       pop
                               %ebp
0x080483ce < sum + 10>: ret
```

Within gdb debugger

```
gdb <file>
disassemble sum
```

disassemble procedure

```
x/11xb sum
```

examine the 11 bytes starting at sum

How Many Instructions are There?

- We cover ~29
- Implemented by Intel:
 - 80 in original 8086 architecture
 - 7 added with 80186
 - 17 added with 80286
 - 33 added with 386
 - 6 added with 486
 - 6 added with Pentium
 - 1 added with Pentium MMX
 - 4 added with Pentium Pro
 - 8 added with SSE
 - 8 added with SSE2
 - 2 added with SSE3
 - 14 added with x86-64
 - 10 added with VT-x
 - 2 added with SSE4a

- Total: 198
- Doesn't count:
 - floating-point instructions
 - SIMD instructions
 - AMD-added instructions
 - undocumented instructions

Some Arithmetic Operations

Two-operand instructions:

Format	Computat	ion	
addl	Src,Dest	Dest = Dest + Src	
subl	Src,Dest	Dest = Dest - Src	
imull	Src,Dest	Dest = Dest * Src	
sall	Src,Dest	Dest = Dest << Src	Also called shill
sarl	Src,Dest	Dest = Dest >> Src	Arithmetic
shrl	Src,Dest	Dest = Dest >> Src	Logical
xorl	Src,Dest	Dest = Dest ^ Src	
andl	Src,Dest	Dest = Dest & Src	
orl	Src,Dest	Dest = Dest Src	

- watch out for argument order!
- no distinction between signed and unsigned int (why?)

Some Arithmetic Operations

One-operand Instructions

```
incl Dest = Dest + 1
decl Dest = Dest - 1
negl Dest = - Dest
notl Dest = ~Dest
```

See book for more instructions

Arithmetic Expression Example

```
int arith(int x, int y, int z)
{
  int t1 = x+y;
  int t2 = z+t1;
  int t3 = x+4;
  int t4 = y * 48;
  int t5 = t3 + t4;
  int rval = t2 * t5;
  return rval;
}
```

```
arith:
    leal (%rdi,%rsi), %eax
    addl %edx, %eax
    leal (%rsi,%rsi,2), %edx
    sall $4, %edx
    leal 4(%rdi,%rdx), %ecx
    imull %ecx, %eax
    ret
```

Understanding arith

```
int arith(int x, int y, int z)
{
  int t1 = x+y;
  int t2 = z+t1;
  int t3 = x+4;
  int t4 = y * 48;
  int t5 = t3 + t4;
  int rval = t2 * t5;
  return rval;
}
```

```
%rdx z
%rsi y
%rdi x
```

```
leal (%rdi,%rsi), %eax
addl %edx, %eax
leal (%rsi,%rsi,2), %edx
sall $4, %edx
leal 4(%rdi,%rdx), %ecx
imull %ecx, %eax
ret
```

Understanding arith

```
int arith(int x, int y, int z)
{
  int t1 = x+y;
  int t2 = z+t1;
  int t3 = x+4;
  int t4 = y * 48;
  int t5 = t3 + t4;
  int rval = t2 * t5;
  return rval;
}
```

```
%rdx z
%rsi y
%rdi x
```

```
leal (%rdi,%rsi), %eax # eax = x+y (t1)
addl %edx, %eax # eax = t1+z (t2)
leal (%rsi,%rsi,2), %edx # edx = 3*y (t4)
sall $4, %edx # edx = t4*16 (t4)
leal 4(%rdi,%rdx), %ecx # ecx = x+4+t4 (t5)
imull %ecx, %eax # eax *= t5 (rval)
ret
```

Observations about arith

```
int arith(int x, int y, int z)
{
  int t1 = x+y;
  int t2 = z+t1;
  int t3 = x+4;
  int t4 = y * 48;
  int t5 = t3 + t4;
  int rval = t2 * t5;
  return rval;
}
```

- Instructions in different order from C code
- Some expressions might require multiple instructions
- Some instructions might cover multiple expressions

```
leal (%rdi,%rsi), %eax # eax = x+y (t1)
addl %edx, %eax # eax = t1+z (t2)
leal (%rsi,%rsi,2), %edx # edx = 3*y (t4)
sall $4, %edx # edx = t4*16 (t4)
leal 4(%rdi,%rdx), %ecx # ecx = x+4+t4 (t5)
imull %ecx, %eax # eax *= t5 (rval)
ret.
```

Another Example

```
int logical(int x, int y)
{
  int t1 = x^y;
  int t2 = t1 >> 17;
  int mask = (1<<13) - 7;
  int rval = t2 & mask;
  return rval;
}</pre>
```

```
2^{13} = 8192, 2^{13} - 7 = 8185
```

```
xorl %esi, %edi  # edi = x^y (t1)
sarl $17, %edi  # edi = t1>>17 (t2)
movl %edi, %eax  # eax = edi
andl $8185, %eax  # eax = t2 & mask (rval)
```

Quiz 3

What is the final value in %esi?

```
xorl %esi, %esi
incl %esi
sall %esi, %esi
addl %esi, %esi
```

- a) 2
- b) 4
- c) 8
- d) indeterminate