Software Testing, Quality Assurance & Maintenance (ECE453/CS447/CS647/SE465): Midterm

February 10, 2009

This open-book midterm has 5 questions and 90 points. Answer the questions in your answer book. You may consult any printed material (books, notes, etc).

Question 1: Prime Path Coverage (25 points)

Consider the following code (modified from the GPLed library pdfsam by Andrea Vacondio):

```
public static File generateTmpFile(String filePath){
   log.debug("Creating temporary file..");
   File retVal = null;
   boolean alreadyExists = true;
   int enthropy = 0;
   String fileName = "";
   String randomString = "qqqq"; // not so random anymore. -PL
   while(alreadyExists){
        fileName = FileUtility.BUFFER_NAME+randomString+
                     Integer.toString(++enthropy)+".pdf";
       File tmpFile = new File(filePath+File.separator+fileName);
       if (!(alreadyExists = tmpFile.exists())) {
           retVal = tmpFile;
   }
   return retVal;
}
```

(5 points) Draw a control-flow graph for this method. (10 points) Enumerate the test requirements for Prime Path Coverage on your CFG. (10 points) Provide a test suite for this method which will satisfy prime path coverage using Best Effort Touring and explain why your test suite satisfies PPC. If there are infeasible test requirements, state why they are infeasible. (A test case may assume that it starts in an empty directory, but may create new files in that directory before calling generateTmpFile. Just write "create file X".)

Question 2: Comparing ADUPC and PPC (30 points)

Draw a control-flow graph, annotated with the relevant definitions and uses, where ADUPC and PPC impose the same test requirements. (List these test requirements.) **Your CFG must contain a loop.**

Question 3: Comparing EPC and EC (10 points)

Edge-pair coverage ought to impose more test requirements than edge coverage. (6 points) Write a Java method where EPC imposes a test requirement that EC doesn't impose. (You can do this with 3 lines of code.) Draw the CFG and write out the test requirements for both EPC and EC. (2 points) Produce a test set that satisfies EC but not EPC. (2 points) Produce a test set that satisfies EPC.

Question 4: Creating a Finite State Machine (25 points)

Read the attached excerpt from RFC 4254, "The Secure Shell (SSH) Connection protocol". This excerpt descripts the protocol for handling an SSH channel. (a) (10 points) Describe the abstract states in this protocol. (We've seen how to create a single FSM for a specification. If you think you can create interacting server and client FSMs, go for it.) (b) (10 points) Describe the transitions between states. (c) (5 points) Draw the FSM for opening, using, and closing SSH channels.

Note: Avoid creating an FSM that looks like a control-flow graph.

Feb 02, 10 20:33 4254, "The Secure Shell (SSH) Connection protocol", rfc4254-excerpt.txt Page 1/2

Excerpt from RFC 425 by T. Ylonen and C. Lonvick.

Channel Mechanism

Either side may open a channel. All terminal sessions, forwarded connections, etc., are channels. into a single connection. Multiple channels are multiplexed

Channels are identified by numbers at each end. The number referring to a channel may be different on each side. Requests to open a channel contain the sender's channel number. Any other channel-related messages contain the recipient's channel number for the channel.

a message is received to indicate that window space is available Channels are flow-controlled. No data may be sent to a channel until

5.1. Opening a Channel

When either side wishes to open a new channel, it allocates a local number for the channel. It then sends [a] message to the other side, and includes the local channel number and initial window size in the message. [...] the message. [...

The remote side then decides whether it can open the channel, and responds with either SSH_MSG_CHANNEL_OPEN_CONFIRMATION or SSH_MSG_CHANNEL_OPEN_FAILURE

```
uint32
              uint32
                              uint32
                                                               uint32
            initial window size maximum packet size
                                               sender channel
                                                               recipient channel
channel type specific data follows
                                                                             SSH_MSG_CHANNEL_OPEN_CONFIRMATION
```

open request, and 'sender channel' is the channel number allocated by the other side. The 'recipient channel' is the channel number given in the original

```
uint32
string
                                                uint32
string
                                                                 byte
                 description in ISO-10646 UTF-8 encoding [RFC3629]
                                   reason code
                                                recipient channel
 language tag [RFC3066]
                                                              SSH_MSG_CHANNEL_OPEN_FAILURE
```

the precautions discussed in string to the user. the specified 'channel type', it simply responds with 'description' If the recipient of the SSH_MSG_CHANNEL_OPEN message does not support If this is done, the client software should take [SSH-ARCH].

The SSH_MSG_CHANNEL_OPEN_FAILURE 'reason the following table. [...] code' values are defined

SSH_OPEN_UNKNOWN_CHANNEL_TYPE SSH_OPEN_RESOURCE_SHORTAGE	OPEN_	OPEN	Symbolic name
ω 4.	2	1	reason code
	_OPEN_UNKNOWN_CHANNEL_TYPE _OPEN_RESOURCE_SHORTAGE	_OPEN_CONNECT_FAILED _OPEN_UNKNOWN_CHANNEL_TYPE _OPEN_RESOURCE_SHORTAGE	

.2. Data

The window size specifies how many bytes the other party can send

> Feb 02, 10 20:33 rfc4254-excerpt.txt

use

before it must wait for the window to be adjusted. the following message to adjust the window. Both parties

byte uint32 uint32 recipient channel bytes to add SSH_MSG_CHANNEL_WINDOW_ADJUST

is incremented. Implemen of up to 2^32 - 1 bytes. 2^32 - 1 bytes. After receiving this message, the recipient MAY send the given number of bytes more than it was previously allowed to send; the window size bytes more than it was previously allowed to send; the window size incremented. Implementations MUST correctly handle window sizes up to 2^32 - 1 bytes. The window MUST NOT be increased above

Data transfer is done with messages of the following type

uint32 string recipient channel data SSH_MSG_CHANNEL_DATA

window is empty. is smaller. packet size The maximum amount of data allowed is determined by the maximum size for the channel, and the current window size, whichever ller. The window size is decremented by the amount of data Both parties MAY ignore all extra data sent after the allowed

SSH connection layer Implementations are expected to have some limit on the SSH transport layer packet size (any limit for received packets MUST be 32768 byte or larger, as described in [SSH-TRANS]). The implementation of the bytes

- 0 MUST NOT advertise a maximum packet size that would result in transport packets larger than its transport layer is willing (receive. t o
- 0 MUST NOT generate data packets larger than its transport layer is willing to send, even if the remote end would be willing to accept very large packets to accept

5.3. Closing a Channel

When a party will no longer send more data to a channel, it SHOULD send SSH_MSG_CHANNEL_EOF.

uint32 byte recipient channel SSH_MSG_CHANNEL_EOF

may send EOF to whatever is at the other end of the channel. Note that the channel remains open after this message, and more data may still be sent in the other direction. This message does not consume window space and can be sent even if no window space is available. No explicit response is sent to this message. However, the application

message SSH_MSG_CHANNEL_EOF. SSH_MSG_CHANNEL_CLOSE without having message for the channel. The channel is considered closed for a party when it has both sent and received SSH_MSG_CHANNEL_CLOSE, and send back an SSH_MSG_CHANNEL_CLOSE unless it has already sent this When either party wishes to terminate the channel, it sends SSH_MSG_CHANNEL_CLOSE. Upon receiving this message, a party MUST party may then reuse the channel number. sent or received A party MAY send

byte uint32 recipient channel SSH_MSG_CHANNEL_CLOSE

This message window space does not consume window space and is available. can Эd sent even ΞÉ