# The Linux-PAM System Administrators' Guide

Andrew G. Morgan, morgan@kernel.org

 $DRAFT\ v0.77\ 2002/07/10$ 

This manual documents what a system-administrator needs to know about the **Linux-PAM** library. It covers the correct syntax of the PAM configuration file and discusses strategies for maintaining a secure system.

## Contents

1	Inti	roduction	5
2	Son	ne comments on the text	6
3	Ove	erview	6
	3.1	Getting started	8
4	The	e Linux-PAM configuration file	10
	4.1	Configuration file syntax	10
	4.2	Directory based configuration	13
	4.3	Generic optional arguments	14
	4.4	Example configuration file entries	15
		4.4.1 Default policy	15
5	Sec	urity issues of Linux-PAM	17
	5.1	If something goes wrong	17
	5.2	Avoid having a weak 'other' configuration	19
6	A r	reference guide for available modules	19
	6.1	The access module	19
		6.1.1 Synopsis	19
		6.1.2 Overview of module	20
		6.1.3 Account component	20
	6.2	Chroot	21
		6.2.1 Synopsis	21
		6.2.2 Overview of module	21
		6.2.3 Account component:	21
		6.2.4 Authentication component:	21

CONTENTS

	6.2.5	Session component:	. 2	2
6.3	Crackl	lib pluggable password strength-checker	. 2	14
	6.3.1	Synopsis	. 2	2
	6.3.2	Overview of module	. 2	14
	6.3.3	Password component	. 2	٩
6.4	The lo	ocking-out module	. 2	(
	6.4.1	Synopsis	. 2	(
	6.4.2	Overview of module	. 2	(
	6.4.3	Account component	. 2	(
	6.4.4	Authentication component	. 2	17
	6.4.5	Password component	. 2	17
	6.4.6	Session component	. 2	8
6.5	Set/un	nset environment variables	. 2	8
	6.5.1	Synopsis	. 2	8
	6.5.2	Overview of module	. 2	8
	6.5.3	Authentication component	. 2	(
6.6	The fil	lter module	. 2	Ç
	6.6.1	Synopsis	. 2	(
	6.6.2	Overview of module	. 3	(
	6.6.3	$Account + Authentication + Password + Session\ components \\ \dots \\ \dots \\ \dots \\ \dots$	. 3	(
6.7	Anony	rmous access module	. 3	;]
	6.7.1	Synopsis	. 3	;]
	6.7.2	Overview of module	. 3	12
	6.7.3	Authentication component	. 3	12
6.8	The gr	roup access module	. 3	12
	6.8.1	Synopsis	. 3	12
	6.8.2	Overview of module	. 3	او
	6.8.3	Authentication component	. 3	او
6.9	Add is	ssue file to user prompt	. 3	14
	6.9.1	Synopsis	. 3	14
	6.9.2	Overview of module	. 3	14
	6.9.3	Authentication component	. 3	14
6.10	The K	Gerberos 4 module	. 3	16
	6.10.1	Synopsis	. 3	

CONTENTS 3

	6.10.2 Overview of module	36
	6.10.3 Session component	36
	6.10.4 Password component	36
	6.10.5 Authentication component	36
6.11	The last login module	37
	6.11.1 Synopsis	37
	6.11.2 Overview of module	37
	6.11.3 Session component	37
6.12	The resource limits module	38
	6.12.1 Synopsis	38
	6.12.2 Overview of module	39
	6.12.3 Session component	39
6.13	The list-file module	41
	6.13.1 Synopsis	41
	6.13.2 Overview of module	42
	6.13.3 Authentication component	42
6.14	The mail module	43
	6.14.1 Synopsis	43
	6.14.2 Overview of module	43
	6.14.3 Session component	44
	$6.14.4 \ \ Authentication \ component \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	44
6.15	Create home directories on initial login	45
	6.15.1 Synopsis	45
	6.15.2 Overview of module	45
	6.15.3 Session component	45
6.16	Output the motd file	46
	6.16.1 Synopsis	46
	6.16.2 Overview of module	46
	6.16.3 Session component	46
6.17	The no-login module	47
	6.17.1 Synopsis	47
	6.17.2 Overview of module	47
	6.17.3 Authentication component	47
6.18	The promiscuous module	48

CONTENTS 4

	6.18.1 Synopsis	48
	6.18.2 Overview of module	48
	$6.18.3 \ \ Account + Authentication + Password + Session \ components \ \ . \ . \ \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ \ . \ $	48
6.19	The Password-Database module	49
	6.19.1 Synopsis	49
	6.19.2 Overview of module	49
	6.19.3 Account component	49
	6.19.4 Authentication component	50
	6.19.5 Password component	51
	6.19.6 Session component	51
6.20	The RADIUS session module	52
	6.20.1 Synopsis	52
	6.20.2 Overview of module	52
	6.20.3 Session component	52
6.21	The rhosts module	53
	6.21.1 Synopsis	53
	6.21.2 Overview of module	54
	6.21.3 Authentication component	54
6.22	The root access module	55
	6.22.1 Synopsis	55
	6.22.2 Overview of module	56
	6.22.3 Authentication component	56
6.23	The securetty module	56
	6.23.1 Synopsis	56
	6.23.2 Overview of module	57
	6.23.3 Authentication component	57
6.24	The login counter (tallying) module	57
	6.24.1 Synopsis	57
	6.24.2 Overview of module	58
	6.24.3 Authentication component	58
	6.24.4 Account component	59
6.25	Time control	59
	6.25.1 Synopsis	59
	6.25.2 Overview of module	60

1. Introduction 5

		6.25.3 Account component	60
	6.26	The Unix Password module	61
		6.26.1 Synopsis	61
		6.26.2 Overview of module	62
		6.26.3 Account component	62
		6.26.4 Authentication component	62
		6.26.5 Password component	63
		6.26.6 Session component	65
	6.27	The userdb module	65
		6.27.1 Synopsis	65
		6.27.2 Overview of module	66
		6.27.3 Authentication component	66
	6.28	Warning logger module	67
		6.28.1 Synopsis	67
		6.28.2 Overview of module	67
		6.28.3 Authentication+Password component	67
	6.29	The wheel module	68
		6.29.1 Synopsis	68
		6.29.2 Overview of module	68
		6.29.3 Authentication and Account components	68
	D.1		
,	File	S .	69
3	See	also	69
)	Not	es	69
.0	Aut	${f hor/acknowledgments}$	70
1	Bu-	es / omissions	70
. 1	ьug	${ m cs/omissions}$	10
2	Cop	yright information for this document	70

## 1 Introduction

**Linux-PAM** (Pluggable Authentication Modules for Linux) is a suite of shared libraries that enable the local system administrator to choose how applications authenticate users.

In other words, without (rewriting and) recompiling a PAM-aware application, it is possible to switch between the authentication mechanism(s) it uses. Indeed, one may entirely upgrade the local authentication system without touching the applications themselves.

Historically an application that has required a given user to be authenticated, has had to be compiled to use a specific authentication mechanism. For example, in the case of traditional UN\*X systems, the identity of the user is verified by the user entering a correct password. This password, after being prefixed by a two character "salt", is encrypted (with crypt(3)). The user is then authenticated if this encrypted password is identical to the second field of the user's entry in the system password database (the /etc/passwd file). On such systems, most if not all forms of privileges are granted based on this single authentication scheme. Privilege comes in the form of a personal user-identifier (uid) and membership of various groups. Services and applications are available based on the personal and group identity of the user. Traditionally, group membership has been assigned based on entries in the /etc/group file.

Unfortunately, increases in the speed of computers and the widespread introduction of network based computing, have made once secure authentication mechanisms, such as this, vulnerable to attack. In the light of such realities, new methods of authentication are continuously being developed.

It is the purpose of the **Linux-PAM** project to separate the development of privilege granting software from the development of secure and appropriate authentication schemes. This is accomplished by providing a library of functions that an application may use to request that a user be authenticated. This PAM library is configured locally with a system file, /etc/pam.conf (or a series of configuration files located in /etc/pam.d/) to authenticate a user request via the locally available authentication modules. The modules themselves will usually be located in the directory /lib/security and take the form of dynamically loadable object files (see dlopen(3)).

## 2 Some comments on the text

Before proceeding to read the rest of this document, it should be noted that the text assumes that certain files are placed in certain directories. Where they have been specified, the conventions we adopt here for locating these files are those of the relevant RFC (RFC-86.0, see 8 (bibliography)). If you are using a distribution of Linux (or some other operating system) that supports PAM but chooses to distribute these files in a different way you should be careful when copying examples directly from the text.

As an example of the above, where it is explicit, the text assumes that PAM loadable object files (the modules) are to be located in the following directory: /lib/security/. This is generally the location that seems to be compatible with the Linux File System Standard (the FSSTND). On Solaris, which has its own licensed version of PAM, and some other implementations of UN\*X, these files can be found in /usr/lib/security. Please be careful to perform the necessary transcription when using the examples from the text.

## 3 Overview

For the uninitiated, we begin by considering an example. We take an application that grants some service to users; *login* is one such program. *Login* does two things, it first establishes that the requesting user is whom they claim to be and second provides them with the requested service: in the case of *login* the service is a command shell (*bash*, *tcsh*, *zsh*, *etc.*) running with the identity of the user.

3. Overview 7

Traditionally, the former step is achieved by the *login* application prompting the user for a password and then verifying that it agrees with that located on the system; hence verifying that as far as the system is concerned the user is who they claim to be. This is the task that is delegated to **Linux-PAM**.


From the perspective of the application programmer (in this case the person that wrote the *login* application), Linux-PAM takes care of this authentication task – verifying the identity of the user.

The flexibility of **Linux-PAM** is that *you*, the system administrator, have the freedom to stipulate which authentication scheme is to be used. You have the freedom to set the scheme for any/all PAM-aware applications on your Linux system. That is, you can authenticate from anything as naive as *simple trust* (pam\_permit) to something as paranoid as a combination of a retinal scan, a voice print and a one-time password!

To illustrate the flexibility you face, consider the following situation: a system administrator (parent) wishes to improve the mathematical ability of her users (children). She can configure their favorite "Shoot 'em up game" (PAM-aware of course) to authenticate them with a request for the product of a couple of random numbers less than 12. It is clear that if the game is any good they will soon learn their multiplication tables. As they mature, the authentication can be upgraded to include (long) division!

**Linux-PAM** deals with four separate types of (management) task. These are: authentication management; account management; session management; and password management. The association of the preferred management scheme with the behavior of an application is made with entries in the relevant **Linux-PAM** configuration file. The management functions are performed by modules specified in the configuration file. The syntax for this file is discussed in the section 4 (below).

Here is a figure that describes the overall organization of Linux-PAM.



By way of explanation, the left of the figure represents the application; application X. Such an application interfaces with the **Linux-PAM** library and knows none of the specifics of its configured authentication method. The **Linux-PAM** library (in the center) consults the contents of the PAM configuration file and loads the modules that are appropriate for application-X. These modules fall into one of four management

3. Overview 8

groups (lower-center) and are stacked in the order they appear in the configuration file. These modules, when called by **Linux-PAM**, perform the various authentication tasks for the application. Textual information, required from/or offered to the user, can be exchanged through the use of the application-supplied conversation function.

## 3.1 Getting started

The following text was contributed by Seth Chaiklin:

To this point, we have described how PAM should work in an ideal world, in which all applications are coded properly. However, at the present time (October 1998), this is far from the case. Therefore, here are some practical considerations in trying to use PAM in your system.

Why bother, is it really worth all the trouble?

If you running Linux as a single user system, or in an environment where all the users are trusted, then there is no real advantage for using PAM.

**Ed:** there is actually an advantage since you can *dummy down* the authentication to the point where you don't have any... Almost like Win95.

In a networked environment, it is clear that you need to think a little more about how users etc., are authenticated:

If you are running Linux as a server, where several different services are being provided (e.g., WWW with areas restricted by password control, PPP), then there can be some real and interesting value for PAM. In particular, through the use of modules, PAM can enable a program to search through several different password databases, even if that program is not explicitly coded for that particular database. Here are some examples of the possibilities that this enables.

- o Apache has a module that provides PAM services. Now authentication
  - to use particular directories can be conducted by PAM, which means that the range of modules that are available to PAM can be used, including RADIUS, NIS, NCP (which means that Novell password databases can be used).
- o pppd has a PAMified version (available from Red Hat) Now it is possible to use a series of databases to authenticate ppp users. In addition to the normal Linux-based password databases (such as /etc/passwd and /etc/shadow), you can use PAM modules to authenticate against Novell password databases or NT-based password databases.

3. Overview 9

o The preceding two examples can be combined. Imagaine that the persons in your office/department are already registered with a username and password in a Novell or NT LAN. If you wanted to use this database on your Linux server (for PPP access, for web access, or even for normal shell access), you can use PAM to authenticate against this existing database, rather than maintain a separate database on both Linux and the LAN server.

Can I use PAM for any program that requires authentication?

Yes and no. Yes, if you have access to the source code, and can add the appropriate PAM functions. No, if you do not have access to the source code, and the binary does not have the PAM functions included.

In other words, if a program is going to use PAM, then it has to have PAM functions explicitly coded into the program. If they are not, then it is not possible to use PAM.

How can I tell whether a program has PAM coded into it or not?

A quick-and-dirty (but not always reliable) method is to ldd programname>

If libpam and libpam\_misc are not among the libraries that the program uses, then it is not going to work with PAM. However, it is possible that the libraries are included, but there are still problems, because the PAM coding in the program does not work as it should. So a more reliable method is to make the follow tests.

In the /etc/pam.d directory, one needs to make a configuration file for the program that one wants to run. The exact name of the configuration

file is hard-coded into the program. Usually, it is the same name as the

program, but not always. For sake of illustration, let's assume that the program is named "pamprog" and the name of the configuration file is /etc/pam.d/pamprog.

In the /etc/pam.d/pamprog put the following two lines:

auth required pam\_permit.so
auth required pam\_warn.so

Now try to use pamprog. The first line in the configuration file says that all users are permitted. The second line will write a warning to your syslog file (or whether you syslog is writing

messages). If this test succeeds, then you know that you have a program that can understand pam, and you can start the more

interesting work of deciding how to stack modules in your /etc/pam.d/pamprog file.

## 4 The Linux-PAM configuration file

Linux-PAM is designed to provide the system administrator with a great deal of flexibility in configuring the privilege granting applications of their system. The local configuration of those aspects of system security controlled by Linux-PAM is contained in one of two places: either the single system file, /etc/pam.conf; or the /etc/pam.d/ directory. In this section we discuss the correct syntax of and generic options respected by entries to these files.

## 4.1 Configuration file syntax

The reader should note that the **Linux-PAM** specific tokens in this file are case *insensitive*. The module paths, however, are case sensitive since they indicate a file's *name* and reflect the case dependence of typical Linux file-systems. The case-sensitivity of the arguments to any given module is defined for each module in turn.

In addition to the lines described below, there are two *special* characters provided for the convenience of the system administrator: comments are preceded by a '#' and extend to the next end-of-line; also, module specification lines may be extended with a '\' escaped newline.

A general configuration line of the /etc/pam.conf file has the following form:

```
service-name module-type control-flag module-path args
```

Below, we explain the meaning of each of these tokens. The second (and more recently adopted) way of configuring Linux-PAM is via the contents of the /etc/pam.d/ directory. Once we have explained the meaning of the above tokens, we will describe this method.

#### service-name

The name of the service associated with this entry. Frequently the service name is the conventional name of the given application. For example, 'ftpd', 'rlogind' and 'su', etc. .

There is a special service-name, reserved for defining a default authentication mechanism. It has the name 'OTHER' and may be specified in either lower or upper case characters. Note, when there is a module specified for a named service, the 'OTHER' entries are ignored.

#### module-type

One of (currently) four types of module. The four types are as follows:

• auth; this module type provides two aspects of authenticating the user. Firstly, it establishes that the user is who they claim to be, by instructing the application to prompt the user for a password or other means of identification. Secondly, the module can grant group membership (independently of the /etc/groups file discussed above) or other privileges through its credential granting properties.

- account; this module performs non-authentication based account management. It is typically used to restrict/permit access to a service based on the time of day, currently available system resources (maximum number of users) or perhaps the location of the applicant user—'root' login only on the console.
- session; primarily, this module is associated with doing things that need to be done for the user before/after they can be given service. Such things include the logging of information concerning the opening/closing of some data exchange with a user, mounting directories, etc. .
- password; this last module type is required for updating the authentication token associated with the user. Typically, there is one module for each 'challenge/response' based authentication (auth) module-type.

### control-flag

The control-flag is used to indicate how the PAM library will react to the success or failure of the module it is associated with. Since modules can be *stacked* (modules of the same type execute in series, one after another), the control-flags determine the relative importance of each module. The application is not made aware of the individual success or failure of modules listed in the '/etc/pam.conf' file. Instead, it receives a summary *success* or *fail* response from the **Linux-PAM** library. The order of execution of these modules is that of the entries in the /etc/pam.conf file; earlier entries are executed before later ones. As of Linux-PAM v0.60, this *control-flag* can be defined with one of two syntaxes.

The simpler (and historical) syntax for the control-flag is a single keyword defined to indicate the severity of concern associated with the success or failure of a specific module. There are four such keywords: required, requisite, sufficient, optional and include.

The Linux-PAM library interprets these keywords in the following manner:

- required; this indicates that the success of the module is required for the module-type facility to succeed. Failure of this module will not be apparent to the user until all of the remaining modules (of the same module-type) have been executed.
- requisite; like required, however, in the case that such a module returns a failure, control is directly returned to the application. The return value is that associated with the *first* required or requisite module to fail. Note, this flag can be used to protect against the possibility of a user getting the opportunity to enter a password over an unsafe medium. It is conceivable that such behavior might inform an attacker of valid accounts on a system. This possibility should be weighed against the not insignificant concerns of exposing a sensitive password in a hostile environment.
- sufficient; the success of this module is deemed 'sufficient' to satisfy the Linux-PAM library that this module-type has succeeded in its purpose. In the event that no previous required module has failed, no more 'stacked' modules of this type are invoked. (Note, in this case subsequent required modules are not invoked.). A failure of this module is not deemed as fatal to satisfying the application that this module-type has succeeded.
- optional; as its name suggests, this control-flag marks the module as not being critical to the success or failure of the user's application for service. In general, Linux-PAM ignores such a module when determining if the module stack will succeed or fail. However, in the absence of any definite successes or failures of previous or subsequent stacked modules this module will determine the nature of the response to the application. One example of this latter case, is when the other modules return something like PAM\_IGNORE.

• include; this tells PAM to include all lines of given type from the configuration file specified as an argument to this control. The whole idea is to create few "systemwide" pam configs and include parts of them in application pam configs.

The more elaborate (newer) syntax is much more specific and gives the administrator a great deal of control over how the user is authenticated. This form of the control flag is delimeted with square brackets and consists of a series of value=action tokens:

```
[value1=action1 value2=action2 ...]
```

Here, valueI is one of the following return values: success; open\_err; symbol\_err; service\_err; system\_err; buf\_err; perm\_denied; auth\_err; cred\_insufficient; authinfo\_unavail; user\_unknown; maxtries; new\_authtok\_reqd; acct\_expired; session\_err; cred\_unavail; cred\_expired; cred\_err; no\_module\_data; conv\_err; authtok\_err; authtok\_recover\_err; authtok\_lock\_busy; authtok\_disable\_aging; try\_again; ignore; abort; authtok\_expired; module\_unknown; bad\_item; conv\_again; incomplete; and default. The last of these (default) can be used to set the action for those return values that are not explicitly defined.

The actionI can be a positive integer or one of the following tokens: ignore; ok; done; bad; die; and reset. A positive integer, J, when specified as the action, can be used to indicate that the next J modules of the current module-type will be skipped. In this way, the administrator can develop a moderately sophisticated stack of modules with a number of different paths of execution. Which path is taken can be determined by the reactions of individual modules.

- ignore when used with a stack of modules, the module's return status will not contribute to the return code the application obtains.
- bad this action indicates that the return code should be thought of as indicative of the module failing. If this module is the first in the stack to fail, its status value will be used for that of the whole stack.
- die equivalent to bad with the side effect of terminating the module stack and PAM immediately returning to the application.
- ok this tells PAM that the administrator thinks this return code should contribute directly to the return code of the full stack of modules. In other words, if the former state of the stack would lead to a return of PAM\_SUCCESS, the module's return code will override this value. Note, if the former state of the stack holds some value that is indicative of a modules failure, this 'ok' value will not be used to override that value.
- done equivalent to ok with the side effect of terminating the module stack and PAM immediately returning to the application.
- reset clear all memory of the state of the module stack and start again with the next stacked module.

Each of the four keywords: required; requisite; sufficient; and optional, have an equivalent expression in terms of the [...] syntax. They are as follows:

- required is equivalent to [success=ok new\_authtok\_reqd=ok ignore=ignore default=bad]
- requisite is equivalent to [success=ok new\_authtok\_reqd=ok ignore=ignore default=die]
- sufficient is equivalent to [success=done new\_authtok\_reqd=done default=ignore]
- optional is equivalent to [success=ok new\_authtok\_reqd=ok default=ignore]

Just to get a feel for the power of this new syntax, here is a taste of what you can do with it. With Linux-PAM-0.63, the notion of client plug-in agents was introduced. This is something that makes it possible for PAM to support machine-machine authentication using the transport protocol inherent to the client/server application. With the "[ . . . value=action . . . ]" control syntax, it is possible for an application to be configured to support binary prompts with compliant clients, but to gracefully fall over into an alternative authentication mode for older, legacy, applications.

#### module-path

The path-name of the dynamically loadable object file; the pluggable module itself. If the first character of the module path is '/', it is assumed to be a complete path. If this is not the case, the given module path is appended to the default module path: /lib/security (but see the notes 2 (above)).

args

The args are a list of tokens that are passed to the module when it is invoked. Much like arguments to a typical Linux shell command. Generally, valid arguments are optional and are specific to any given module. Invalid arguments are ignored by a module, however, when encountering an invalid argument, the module is required to write an error to syslog(3). For a list of generic options see the next section.

Note, if you wish to include spaces in an argument, you should surround that argument with square brackets. For example:

Note, when using this convention, you can include '[' characters inside the string, and if you wish to include a ']' character inside the string that will survive the argument parsing, you should use '\['. In other words:

```
[..[..\]..] --> ..[..]..
```

Any line in (one of) the configuration file(s), that is not formatted correctly, will generally tend (erring on the side of caution) to make the authentication process fail. A corresponding error is written to the system log files with a call to syslog(3).

#### 4.2 Directory based configuration

More flexible than the single configuration file, as of version 0.56, it is possible to configure libpam via the contents of the /etc/pam.d/ directory. In this case the directory is filled with files each of which has a filename equal to a service-name (in lower-case): it is the personal configuration file for the named service.

Linux-PAM can be compiled in one of two modes. The preferred mode uses either /etc/pam.d/ or /etc/pam.conf configuration but not both. That is to say, if there is a /etc/pam.d/ directory then libpam only uses the files contained in this directory. However, in the absence of the /etc/pam.d/ directory the /etc/pam.conf file is used (this is likely to be the mode your preferred distribution uses). The other mode is to use both /etc/pam.d/ and /etc/pam.conf in sequence. In this mode, entries in /etc/pam.d/ override those of /etc/pam.conf.

The syntax of each file in /etc/pam.d/ is similar to that of the /etc/pam.conf file and is made up of lines of the following form:

#### module-type control-flag module-path arguments

The only difference being that the service-name is not present. The service-name is of course the name of the given configuration file. For example, /etc/pam.d/login contains the configuration for the login service.

This method of configuration has a number of advantages over the single file approach. We list them here to assist the reader in deciding which scheme to adopt:

- A lower chance of misconfiguring an application. There is one less field to mis-type when editing the configuration files by hand.
- Easier to maintain. One application may be reconfigured without risk of interfering with other applications on the system.
- It is possible to symbolically link different services configuration files to a single file. This makes it easier to keep the system policy for access consistent across different applications. (It should be noted, to conserve space, it is equally possible to hard link a number of configuration files. However, care should be taken when administering this arrangement as editing a hard linked file is likely to break the link.)
- A potential for quicker configuration file parsing. Only the relevant entries are parsed when a service gets bound to its modules.
- It is possible to limit read access to individual **Linux-PAM** configuration files using the file protections of the filesystem.
- Package management becomes simpler. Every time a new application is installed, it can be accompanied by an /etc/pam.d/xxxxxx file.

## 4.3 Generic optional arguments

The following are optional arguments which are likely to be understood by any module. Arguments (including these) are in general *optional*.

#### debug

Use the syslog(3) call to log debugging information to the system log files.

#### no\_warn

Instruct module to not give warning messages to the application.

#### use\_first\_pass

The module should not prompt the user for a password. Instead, it should obtain the previously typed password (from the preceding auth module), and use that. If that doesn't work, then the user will not be authenticated. (This option is intended for auth and password modules only).

#### try\_first\_pass

The module should attempt authentication with the previously typed password (from the preceding auth module). If that doesn't work, then the user is prompted for a password. (This option is intended for auth modules only).

#### use\_mapped\_pass

This argument is not currently supported by any of the modules in the Linux-PAM distribution because of possible consequences associated with U.S. encryption exporting restrictions. Within the U.S., module developers are, of course, free to implement it (as are developers in other countries). For compatibility reasons we describe its use as suggested in the DCE-RFC 86.0, see section 8 (bibliography) for a pointer to this document.

The use\_mapped\_pass argument instructs the module to take the clear text authentication token entered by a previous module (that requests such a token) and use it to generate an encryption/decryption key with which to safely store/retrieve the authentication token required for this module. In this way the user can enter a single authentication token and be quietly authenticated by a number of stacked modules. Obviously a convenient feature that necessarily requires some reliably strong encryption to make it secure. This argument is intended for the auth and password module types only.

#### expose\_account

In general the leakage of some information about user accounts is not a secure policy for modules to adopt. Sometimes information such as users names or home directories, or preferred shell, can be used to attack a user's account. In some circumstances, however, this sort of information is not deemed a threat: displaying a user's full name when asking them for a password in a secured environment could also be called being 'friendly'. The expose\_account argument is a standard module argument to encourage a module to be less discrete about account information as it is deemed appropriate by the local administrator.

## 4.4 Example configuration file entries

In this section, we give some examples of entries that can be present in the **Linux-PAM** configuration file. As a first attempt at configuring your system you could do worse than to implement these.

## 4.4.1 Default policy

If a system is to be considered secure, it had better have a reasonably secure 'OTHER' entry. The following is a paranoid setting (which is not a bad place to start!):

```
#
# default; deny access
#

OTHER auth required pam_deny.so
OTHER account required pam_deny.so
OTHER password required pam_deny.so
OTHER session required pam_deny.so
```

Whilst fundamentally a secure default, this is not very sympathetic to a misconfigured system. For example, such a system is vulnerable to locking everyone out should the rest of the file become badly written.

The module pam\_deny (documented in a later section) is not very sophisticated. For example, it logs no information when it is invoked so unless the users of a system contact the administrator when failing to execute a service application, the administrator may go for a long while in ignorance of the fact that his system is misconfigured.

The addition of the following line before those in the above example would provide a suitable warning to the administrator.

```
#
# default; wake up! This application is not configured
#
OTHER auth required pam_warn.so
OTHER password required pam_warn.so
```

Having two "OTHER auth" lines is an example of stacking.

On a system that uses the /etc/pam.d/ configuration, the corresponding default setup would be achieved with the following file:

```
#
# default configuration: /etc/pam.d/other
#
auth required pam_warn.so
auth required pam_deny.so
account required pam_deny.so
password required pam_warn.so
password required pam_deny.so
session required pam_deny.so
```

This is the only explicit example we give for an /etc/pam.d/ file. In general, it should be clear how to transpose the remaining examples to this configuration scheme.

On a less sensitive computer, one on which the system administrator wishes to remain ignorant of much of the power of Linux-PAM, the following selection of lines (in /etc/pam.conf) is likely to mimic the historically familiar Linux setup.

```
#
# default; standard UN*X access
#
OTHER auth required pam_unix.so
OTHER account required pam_unix.so
OTHER password required pam_unix.so
OTHER session required pam_unix.so
```

In general this will provide a starting place for most applications. Unfortunately, most is not all. One application that might require additional lines is ftpd if you wish to enable anonymous-ftp.

To enable anonymous-ftp, the following lines might be used to replace the default (OTHER) ones. (\*WARN-ING\* as of 1996/12/28 this does not work correctly with any ftpd. Consequently, this description may be subject to change or the application will be fixed.)

```
#
# ftpd; add ftp-specifics. These lines enable anonymous ftp over
# standard UN*X access (the listfile entry blocks access to
# users listed in /etc/ftpusers)
#
ftpd auth sufficient pam_ftp.so
```

```
ftpd auth required pam_unix_auth.so use_first_pass
ftpd auth required pam_listfile.so \
    onerr=succeed item=user sense=deny file=/etc/ftpusers
```

Note, the second line is necessary since the default entries are ignored by a service application (here ftpd) if there are any entries in /etc/pam.conf for that specified service. Again, this is an example of authentication module stacking. Note the use of the sufficient control-flag. It says that "if this module authenticates the user, ignore the subsequent auth modules". Also note the use of the "use\_first\_pass" module-argument, this instructs the UN\*X authentication module that it is not to prompt for a password but rely on one already having been obtained by the pam\_ftp module.

## 5 Security issues of Linux-PAM

This section will discuss good practices for using PAM in a secure manner. It is currently sadly lacking...suggestions are welcome!

## 5.1 If something goes wrong

Linux-PAM has the potential to seriously change the security of your system. You can choose to have no security or absolute security (no access permitted). In general, Linux-PAM errs towards the latter. Any number of configuration errors can dissable access to your system partially, or completely.

The most dramatic problem that is likely to be encountered when configuring **Linux-PAM** is that of *deleting* the configuration file(s): /etc/pam.d/\* and/or /etc/pam.conf. This will lock you out of your own system!

To recover, your best bet is to reboot the system in single user mode and set about correcting things from there. The following has been adapted from a life-saving email on the subject from David Wood:

```
> What the hell do I do now?
```

OK, don't panic. The first thing you have to realize is that this happens to 50% of users who ever do anything with PAM. It happened here, not once, not twice, but three times, all different, and in the end, the solution was the same every time.

First, I hope you installed LILO with a delay. If you can, reboot, hit shift or tab or something and type:

```
LILO boot: linux single
```

(Replace 'linux' with 'name-of-your-normal-linux-image'). This will let you in without logging in. Ever wondered how easy it is to break into a linux machine from the console? Now you know.

If you can't do that, then get yourself a bootkernel floppy

and a root disk a-la slackware's rescue.gz. (Red Hat's installation disks can be used in this mode too.)

In either case, the point is to get back your root prompt.

Second, I'm going to assume that you haven't completely nuked your pam installation - just your configuration files. Here's how you make your configs nice again:

```
cd /etc
mv pam.conf pam.conf.orig
mv pam.d pam.d.orig
mkdir pam.d
cd pam.d
```

and then use vi to create a file called "other" in this directory. It should contain the following four lines:

```
auth required pam_unix.so
account required pam_unix.so
password required pam_unix.so
session required pam_unix.so
```

Now you have the simplest possible PAM configuration that will work the way you're used to. Everything should magically start to work again. Try it out by hitting ALT-F2 and logging in on another virtual console. If it doesn't work, you have bigger problems, or you've mistyped something. One of the wonders of this system (seriously, perhaps) is that if you mistype anything in the conf files, you usually get no error reporting of any kind on the console - just some entries in the log file. So look there! (Try 'tail /var/log/messages'.)

From here you can go back and get a real configuration going, hopefully after you've tested it first on a machine you don't care about screwing up. :/

Some pointers (to make everything "right" with Red Hat...):

Install the newest pam, pamconfig, and pwdb from the redhat current directory, and do it all on the same command line with rpm...

```
rpm -Uvh [maybe --force too] pam-* pamconfig-* pwdb-*
```

Then make sure you install (or reinstall) the newest

```
version of libc, util-linux, wuftp, and NetKit. For kicks you might try installing the newest versions of the affected x apps, like xlock, but I haven't gotten those to work at all yet.
```

## 5.2 Avoid having a weak 'other' configuration

It is not a good thing to have a weak default (OTHER) entry. This service is the default configuration for all PAM aware applications and if it is weak, your system is likely to be vulnerable to attack.

Here is a sample "other" configuration file. The pam\_deny module will deny access and the pam\_warn module will send a syslog message to auth.notice:

```
#
# The PAM configuration file for the 'other' service
auth
          required
                     pam_deny.so
auth
          required
                     pam_warn.so
          required
                     pam_deny.so
account
account
          required
                     pam_warn.so
          required
password
                     pam_deny.so
password
          required
                     pam_warn.so
session
          required
                     pam_deny.so
session
          required
                     pam_warn.so
```

## 6 A reference guide for available modules

Here, we collect together some descriptions of the various modules available for **Linux-PAM**. In general these modules should be freely available. Where this is not the case, it will be indicated.

Also please note the comments contained in the section 2 (on text conventions above) when copying the examples listed below.

## 6.1 The access module

#### 6.1.1 Synopsis

## Module Name:

pam\_access

## Author[s]:

Alexei Nogin <alexei@nogin.dnttm.ru>

#### Maintainer:

## Management groups provided:

account

## Cryptographically sensitive:

Security rating:

Clean code base:

## System dependencies:

Requires a configuration file. By default /etc/security/access.conf is used but this can be over-ridden.

#### Network aware:

Through PAM\_TTY if set, otherwise attempts getting tty name of the stdin file descriptor with ttyname(). Standard gethostname(), yp\_get\_default\_domain(), gethostbyname() calls. NIS is used for netgroup support.

#### 6.1.2 Overview of module

Provides logdaemon style login access control.

## 6.1.3 Account component

## Recognized arguments:

```
accessfile=/path/to/file.conf; fieldsep=separators
```

#### Description:

This module provides logdaemon style login access control based on login names and on host (or domain) names, internet addresses (or network numbers), or on terminal line names in case of non-networked logins. Diagnostics are reported through syslog(3). Wietse Venema's login\_access.c from logdaemon-5.6 is used with several changes by A. Nogin.

The behavior of this module can be modified with the following arguments:

- accessfile=/path/to/file.conf indicate an alternative access configuration file to override the default. This can be useful when different services need different access lists.
- fieldsep=separators this option modifies the field separator character that pam\_access will recognize when parsing the access configuration file. For example: fieldsep=| will cause the default ':' character to be treated as part of a field value and '|' becomes the field separator. Doing this is useful in conjuction with a system that wants to use pam\_access with X based applications, since the PAM\_TTY item is likely to be of the form "hostname:0" which includes a ':' character in its value.

## Examples/suggested usage:

Use of module is recommended, for example, on administrative machines such as **NIS** servers and mail servers where you need several accounts active but don't want them all to have login capability.

For /etc/pam.d style configurations where your modules live in /lib/security, start by adding the following line to /etc/pam.d/login, /etc/pam.d/rlogin, /etc/pam.d/rsh and /etc/pam.d/ftp:

account required /lib/security/pam\_access.so

Note that use of this module is not effective unless your system ignores .rhosts files. See the the pam rhosts auth documentation.

A sample access.conf configuration file is included with the distribution.

#### 6.2 Chroot

#### 6.2.1 Synopsis

#### Module Name:

pam\_chroot

#### Author:

Bruce Campbell <br/> <br/>brucec@humbug.org.au>

#### Maintainer:

Author; proposed on 20/11/96 - email for status

#### Management groups provided:

account; session; authentication

#### Cryptographically sensitive:

Security rating:

#### Clean code base:

Unwritten.

#### System dependencies:

#### Network aware:

Expects localhost.

#### 6.2.2 Overview of module

This module is intended to provide a transparent wrapper around the average user, one that puts them in a fake file-system (eg, their '/' is really /some/where/else).

Useful if you have several classes of users, and are slightly paranoid about security. Can be used to limit who else users can see on the system, and to limit the selection of programs they can run.

#### 6.2.3 Account component:

Need more info here.

## 6.2.4 Authentication component:

Need more info here.

#### 6.2.5 Session component:

Need more info here.

#### Recognized arguments:

Arguments and logging levels for the PAM version are being worked on.

#### Description:

#### Examples/suggested usage:

Do provide a reasonable list of programs - just tossing 'cat', 'ls', 'rm', 'cp' and 'ed' in there is a bit...

Don't take it to extremes (eg, you can set up a separate environment for each user, but its a big waste of your disk space.)

## 6.3 Cracklib pluggable password strength-checker

## 6.3.1 Synopsis

#### Module Name:

pam cracklib

#### Author:

Cristian Gafton <gafton@redhat.com>

#### Maintainer:

Author.

## Management groups provided:

password

#### Cryptographically sensitive:

Security rating:

Clean code base:

#### System dependencies:

Requires the system library libcrack and a system dictionary: /var/cache/cracklib/cracklib\_dict.

## Network aware:

## 6.3.2 Overview of module

This module can be plugged into the password stack of a given application to provide some plug-in strength-checking for passwords.

This module works in the following manner: it first calls the *Cracklib* routine to check the strength of the password; if crack likes the password, the module does an additional set of strength checks. These checks are:

#### • Palindrome -

Is the new password a palindrome of the old one?

## • Case Change Only -

Is the new password the the old one with only a change of case?

#### • Similar -

Is the new password too much like the old one? This is primarily controlled by one argument, difok which is a number of characters that if different between the old and new are enough to accept the new password, this defaults to 10 or 1/2 the size of the new password whichever is smaller.

To avoid the lockup associated with trying to change a long and complicated password, difignore is available. This argument can be used to specify the minimum length a new password needs to be before the difok value is ignored. The default value for difignore is 23.

## • Simple -

Is the new password too small? This is controlled by 5 arguments minlen, dcredit, ucredit, lcredit, and ocredit. See the section on the arguments for the details of how these work and there defaults.

#### • Rotated -

Is the new password a rotated version of the old password?

#### • Already used -

Was the password used in the past? Previously used passwords are to be found in /etc/security/opasswd.

This module with no arguments will work well for standard unix password encryption. With md5 encryption, passwords can be longer than 8 characters and the default settings for this module can make it hard for the user to choose a satisfactory new password. Notably, the requirement that the new password contain no more than 1/2 of the characters in the old password becomes a non-trivial constraint. For example, an old password of the form "the quick brown fox jumped over the lazy dogs" would be difficult to change... In addition, the default action is to allow passwords as small as 5 characters in length. For a md5 systems it can be a good idea to increase the required minimum size of a password. One can then allow more credit for different kinds of characters but accept that the new password may share most of these characters with the old password.

#### 6.3.3 Password component

#### Recognized arguments:

debug; type=XXX; retry=N; difok=N; minlen=N; dcredit=N; ucredit=N; lcredit=N; ocredit=N;
use\_authtok;

#### Description:

The action of this module is to prompt the user for a password and check its strength against a system dictionary and a set of rules for identifying poor choices.

The default action is to prompt for a single password, check its strength and then, if it is considered strong, prompt for the password a second time (to verify that it was typed correctly on the first

occasion). All being well, the password is passed on to subsequent modules to be installed as the new authentication token.

The default action may be modified in a number of ways using the arguments recognized by the module:

#### • debug -

this option makes the module write information to syslog(3) indicating the behavior of the module (this option does **not** write password information to the log file).

#### • type=XXX -

the default action is for the module to use the following prompts when requesting passwords: "New UNIX password: " and "Retype UNIX password: ". Using this option you can replace the word UNIX with XXX.

## • retry=N -

the default number of times this module will request a new password (for strength-checking) from the user is 1. Using this argument this can be increased to N.

#### • difok=N-

This argument will change the default of 10 for the number of characters in the new password that must not be present in the old password. In addition, if 1/2 of the characters in the new password are different then the new password will be accepted anyway.

#### • minlen=N -

The minimum acceptable size for the new password (plus one if credits are not disabled which is the default). In addition to the number of characters in the new password, credit (of +1 in length) is given for each different kind of character (other, upper, lower and digit). The default for this parameter is 9 which is good for a old style UNIX password all of the same type of character but may be too low to exploit the added security of a md5 system. Note that there is a pair of length limits in Cracklib itself, a "way too short" limit of 4 which is hard coded in and a defined limit (6) that will be checked without reference to minlen. If you want to allow passwords as short as 5 characters you should either not use this module or recompile the crack library and then recompile this module.

#### • dcredit=N -

(N>=0) This is the maximum credit for having digits in the new password. If you have less than or N digits, each digit will count +1 towards meeting the current minlen value. The default for dcredit is 1 which is the recommended value for minlen less than 10. (N<0) This is the minimum number of digits that must be met for a new password.

#### • ucredit=N -

(N >= 0) This is the maximum credit for having upper case letters in the new password. If you have less than or N upper case letters each letter will count +1 towards meeting the current minlen value. The default for ucredit is 1 which is the recommended value for minlen less than 10. (N < 0) This is the minimum number of upper case letters that must be met for a new password.

#### • lcredit=N -

(N>=0) This is the maximum credit for having lower case letters in the new password. If you have less than or N lower case letters, each letter will count +1 towards meeting the current minlen value. The default for lcredit is 1 which is the recommended value for minlen less than 10. (N < 0) This is the minimum number of lower case letters that must be met for a new password.

## • ocredit=N -

(N>=0) This is the maximum credit for having other characters in the new password. If you have less than or N other characters, each character will count +1 towards meeting the current minlen value. The default for occedit is 1 which is the recommended value for minlen less than 10. (N<0) This is the minimum number of other characters that must be met for a new password.

#### • use\_authtok -

This argument is used to *force* the module to not prompt the user for a new password but use the one provided by the previously stacked password module.

#### Examples/suggested usage:

For an example of the use of this module, we show how it may be stacked with the password component of pam\_unix:

```
#
# These lines stack two password type modules. In this example the
# user is given 3 opportunities to enter a strong password. The
# "use_authtok" argument ensures that the pam_unix module does not
# prompt for a password, but instead uses the one provided by
# pam_cracklib.
#
passwd password required pam_cracklib.so retry=3
passwd password required pam_unix.so use_authtok
```

Another example (in the /etc/pam.d/passwd format) is for the case that you want to use md5 password encryption:

And here is another example in case you don't want to use credits:

In this example we simply say that the password must have a minimum length of 8:

## 6.4 The locking-out module

#### 6.4.1 Synopsis

#### Module Name:

pam\_deny

Author:

Andrew G. Morgan <morgan@kernel.org>

Maintainer:

current Linux-PAM maintainer

Management groups provided:

account; authentication; password; session

Cryptographically sensitive:

Security rating:

Clean code base:

clean.

System dependencies:

Network aware:

## 6.4.2 Overview of module

This module can be used to deny access. It always indicates a failure to the application through the PAM framework. As is commented in the overview section 3 (above), this module might be suitable for using for default (the OTHER) entries.

### 6.4.3 Account component

## Recognized arguments:

#### Description:

This component does nothing other than return a failure. The failure type is PAM\_ACCT\_EXPIRED.

#### Examples/suggested usage:

Stacking this module with type account will prevent the user from gaining access to the system via applications that refer to Linux-PAM's account management function pam\_acct\_mgmt().

The following example would make it impossible to login:

```
#
# add this line to your other login entries to disable all accounts
#
login account required pam_deny.so
```

#### 6.4.4 Authentication component

## Recognized arguments:

## Description:

This component does nothing other than return a failure. The failure type is PAM\_AUTH\_ERR in the case that pam\_authenticate() is called (when the application tries to authenticate the user), and is PAM\_CRED\_UNAVAIL when the application calls pam\_setcred() (to establish and set the credentials of the user — it is unlikely that this function will ever be called in practice).

#### Examples/suggested usage:

To deny access to default applications with this component of the pam\_deny module, you might include the following line in your Linux-PAM configuration file:

```
#
# add this line to your existing OTHER entries to prevent
# authentication succeeding with default applications.
#
OTHER auth required pam_deny.so
```

## 6.4.5 Password component

## Recognized arguments:

#### Description:

This component of the module denies the user the opportunity to change their password. It always responds with PAM\_AUTHTOK\_ERR when invoked.

## Examples/suggested usage:

This module should be used to prevent an application from updating the applicant user's password. For example, to prevent login from automatically prompting for a new password when the old one has expired you should include the following line in your configuration file:

```
#
# add this line to your other login entries to prevent the login
# application from being able to change the user's password.
#
login password required pam_deny.so
```

## 6.4.6 Session component

#### Recognized arguments:

## Description:

This aspect of the module prevents an application from starting a session on the host computer.

## Examples/suggested usage:

Together with another session module, that displays a message of the day perhaps (pam\_motd for example), this module can be used to block a user from starting a shell. We might use the following entries in the configuration file to inform the user it is system time:

## 6.5 Set/unset environment variables

#### 6.5.1 Synopsis

## Module Name:

pam\_env

#### Author:

Dave Kinchlea < kinch@kinch.ark.com>

## Maintainer:

Author

#### Management groups provided:

Authentication (setcred)

#### Cryptographically sensitive:

Security rating:

Clean code base:

## System dependencies:

```
/etc/security/pam_env.conf
```

Network aware:

#### 6.5.2 Overview of module

This module allows the (un)setting of environment variables. Supported is the use of previously set environment variables as well as *PAM\_ITEM*s such as *PAM\_RHOST*.

#### 6.5.3 Authentication component

#### Recognized arguments:

debug; conffile=configuration-file-name; envfile=env-file-name; readenv= $\theta | 1$ 

#### Description:

This module allows you to (un)set arbitrary environment variables using fixed strings, the value of previously set environment variables and/or *PAM ITEMs*.

All is controlled via a configuration file (by default, /etc/security/pam\_env.conf but can be overriden with conffile argument). Each line starts with the variable name, there are then two possible options for each variable **DEFAULT** and **OVERRIDE**. **DEFAULT** allows an administrator to set the value of the variable to some default value, if none is supplied then the empty string is assumed. The **OVERRIDE** option tells pam\_env that it should enter in its value (overriding the default value) if there is one to use. **OVERRIDE** is not used, "" is assumed and no override will be done.

```
VARIABLE [DEFAULT=[value]] [OVERRIDE=[value]]
```

(Possibly non-existent) environment variables may be used in values using the \${string} syntax and (possibly non-existent) PAM\_ITEMs may be used in values using the @{string} syntax. Both the \$ and @ characters can be backslash-escaped to be used as literal values (as in \\$. Double quotes may be used in values (but not environment variable names) when white space is needed the full value must be delimited by the quotes and embedded or escaped quotes are not supported.

This module can also parse a file with simple KEY=VAL pairs on seperate lines (/etc/environment by default). You can change the default file to parse, with the *envfile* flag and turn it on or off by setting the *readenv* flag to 1 or 0 respectively.

The behavior of this module can be modified with one of the following flags:

- debug write more information to syslog(3).
- conffile=filename by default the file /etc/security/pam\_env.conf is used as the configuration file. This option overrides the default. You must supply a complete path + file name.
- envfile=filename by default the file /etc/environment is used to load KEY=VAL pairs directly into the env. This option overrides the default. You must supply a complete path + file name.
- readenv= $\theta|1$  turns on or off the reading of the file specified by envfile (0 is off, 1 is on). By default this option is on.

### Examples/suggested usage:

See sample pam\_env.conf for more information and examples.

#### 6.6 The filter module

## 6.6.1 Synopsis

#### Module Name:

pam filter

#### Author:

Andrew G. Morgan <morgan@kernel.org>

#### Maintainer:

Author.

## Management groups provided:

account; authentication; password; session

## Cryptographically sensitive:

Not yet.

## Security rating:

#### Clean code base:

This module compiles cleanly on Linux based systems.

#### System dependencies:

To function it requires *filters* to be installed on the system.

#### Network aware:

#### 6.6.2 Overview of module

This module was written to offer a plug-in alternative to programs like ttysnoop (XXX - need a reference). Since writing a filter that performs this function has not occurred, it is currently only a toy. The single filter provided with the module simply transposes upper and lower case letters in the input and output streams. (This can be very annoying and is not kind to termcap based editors).

#### 6.6.3 Account+Authentication+Password+Session components

#### Recognized arguments:

debug; new\_term; non\_term; runX

#### Description:

Each component of the module has the potential to invoke the desired filter. The filter is always execv(2)d with the privilege of the calling application and **not** that of the user. For this reason it cannot usually be killed by the user without closing their session.

The behavior of the module can be significantly altered by the arguments passed to it in the **Linux-PAM** configuration file:

• debug -

this option increases the amount of information logged to syslog(3) as the module is executed.

• new\_term -

the default action of the filter is to set the PAM\_TTY item to indicate the terminal that the user is using to connect to the application. This argument indicates that the filter should set PAM\_TTY to the filtered pseudo-terminal.

• non\_term - don't try to set the PAM\_TTY item.

#### • runX -

in order that the module can invoke a filter it should know when to invoke it. This argument is required to tell the filter when to do this. The arguments that follow this one are respectively the full pathname of the filter to be run and any command line arguments that the filter might expect.

Permitted values for X are 1 and 2. These indicate the precise time that the filter is to be run. To understand this concept it will be useful to have read the Linux-PAM Module developer's guide. Basically, for each management group there are up to two ways of calling the module's functions. In the case of the *authentication* and *session* components there are actually two separate functions. For the case of authentication, these functions are \_authenticate and \_setcred - here run1 means run the filter from the \_authenticate function and run2 means run the filter from \_setcred. In the case of the session modules, run1 implies that the filter is invoked at the \_open\_session stage, and run2 for \_close\_session.

For the case of the account component. Either run1 or run2 may be used.

For the case of the password component, run1 is used to indicate that the filter is run on the first occasion \_chauthtok is run (the PAM\_PRELIM\_CHECK phase) and run2 is used to indicate that the filter is run on the second occasion (the PAM\_UPDATE\_AUTHTOK phase).

#### Examples/suggested usage:

At the time of writing there is little real use to be made of this module. For fun you might try adding the following line to your login's configuration entries

## 6.7 Anonymous access module

## 6.7.1 Synopsis

#### Module Name:

```
pam_ftp.so
```

#### Author:

Andrew G. Morgan <morgan@kernel.org>

#### Maintainer:

Author.

#### Management groups provided:

authentication

## Cryptographically sensitive:

Security rating:

#### Clean code base:

## System dependencies:

#### Network aware:

prompts for email address of user; easily spoofed (XXX - needs work)

#### 6.7.2 Overview of module

The purpose of this module is to provide a pluggable anonymous ftp mode of access.

## 6.7.3 Authentication component

## Recognized arguments:

```
debug; users=XXX,YYY,...; ignore
```

## Description:

This module intercepts the user's name and password. If the name is "ftp" or "anonymous", the user's password is broken up at the '@' delimiter into a PAM\_RUSER and a PAM\_RHOST part; these pam-items being set accordingly. The username (PAM\_USER) is set to "ftp". In this case the module succeeds. Alternatively, the module sets the PAM\_AUTHTOK item with the entered password and fails.

The behavior of the module can be modified with the following flags:

- debug log more information to with syslog(3).
- users=XXX,YYY,... instead of "ftp" or "anonymous", provide anonymous login to the comma separated list of users; "XXX,YYY,...". Should the applicant enter one of these usernames the returned username is set to the first in the list; "XXX".
- ignore pay no attention to the email address of the user (if supplied).

#### Examples/suggested usage:

An example of the use of this module is provided in the configuration file section 4 (above). With care, this module could be used to provide new/temporary account anonymous login.

## 6.8 The group access module

#### 6.8.1 Synopsis

#### Module Name:

```
pam_group
```

## Author:

Andrew G. Morgan <morgan@kernel.org>

#### Maintainer:

Author.

#### Management groups provided:

authentication

## Cryptographically sensitive:

#### Security rating:

Sensitive to setgid status of file-systems accessible to users.

#### Clean code base:

## System dependencies:

Requires an /etc/security/group.conf file. Can be compiled with or without libpwdb.

#### Network aware:

Only through correctly set PAM\_TTY item.

#### 6.8.2 Overview of module

This module provides group-settings based on the user's name and the terminal they are requesting a given service from. It takes note of the time of day.

## 6.8.3 Authentication component

## Recognized arguments:

## Description:

This module does not authenticate the user, but instead it grants group memberships (in the credential setting phase of the authentication module) to the user. Such memberships are based on the service they are applying for. The group memberships are listed in text form in the /etc/security/group.conf file.

## Examples/suggested usage:

For this module to function correctly there must be a correctly formatted /etc/security/groups.conf file present. The format of this file is as follows. Group memberships are given based on the service application satisfying any combination of lines in the configuration file. Each line (barring comments which are preceded by '#' marks) has the following syntax:

```
services ; ttys ; users ; times ; groups
```

Here the first four fields share the syntax of the pam\_time configuration file; /etc/security/pam\_time.conf, and the last field, the groups field, is a comma (or space) separated list of the text-names of a selection of groups. If the users application for service satisfies the first four fields, the user is granted membership of the listed groups.

As stated in above this module's usefulness relies on the file-systems accessible to the user. The point being that once granted the membership of a group, the user may attempt to create a *setgid* binary with a restricted group ownership. Later, when the user is not given membership to this group, they can recover group membership with the precompiled binary. The reason that the file-systems that the user has access to are so significant, is the fact that when a system is mounted *nosuid* the user is unable

to create or execute such a binary file. For this module to provide any level of security, all file-systems that the user has write access to should be mounted nosuid.

The pam\_group module fuctions in parallel with the /etc/group file. If the user is granted any groups based on the behavior of this module, they are granted in addition to those entries /etc/group (or equivalent).

## 6.9 Add issue file to user prompt

## 6.9.1 Synopsis

#### Module Name:

pam\_issue

#### Author:

Ben Collins <a href="mailto:collins@debian.org">bcollins@debian.org</a>

#### Maintainer:

Author

#### Management groups provided:

Authentication (pam sm authenticate)

Cryptographically sensitive:

Security rating:

Clean code base:

System dependencies:

Network aware:

## 6.9.2 Overview of module

This module prepends the issue file (/etc/issue by default) when prompting for a username.

## 6.9.3 Authentication component

## Recognized arguments:

issue=issue-file-name; noesc;

#### Description:

This module allows you to prepend an issue file to the username prompt. It also by default parses escape codes in the issue file similar to some common getty's (using x format).

Recognized escapes:

- d current date
- ullet s operating system name

- 1 name of this tty
- m architecture of this system (i686, sparc, powerpc, ...)
- n hostname of this system
- o domainname of this system
- r release number of the operation system (eg. 2.2.12)
- t current time
- u number of users currently logged in
- U same as u, except it is suffixed with "user" or "users" (eg. "1 user" or "10 users"
- $\bullet$  v version/build-date of the operating system (eg. "#3 Mon Aug 23 14:38:16 EDT 1999" on Linux).

The behavior of this module can be modified with one of the following flags:

- $\bullet\,$  issue the file to output if not using the default
- noesc turns off escape code parsing

## Examples/suggested usage:

login auth pam issue.so issue=/etc/issue

#### 6.10 The Kerberos 4 module.

## 6.10.1 Synopsis

#### Module Name:

pam\_krb4

#### Author:

Derrick J. Brashear <shadow@dementia.org>

#### Maintainer:

Author.

## Management groups provided:

authentication; password; session

## Cryptographically sensitive:

uses API

## Security rating:

Clean code base:

#### System dependencies:

libraries - libkrb, libdes, libcom\_err, libkadm; and a set of Kerberos include files.

## Network aware:

Gets Kerberos ticket granting ticket via a Kerberos key distribution center reached via the network.

#### 6.10.2 Overview of module

This module provides an interface for doing Kerberos verification of a user's password, getting the user a Kerberos ticket granting ticket for use with the Kerberos ticket granting service, destroying the user's tickets at logout time, and changing a Kerberos password.

#### 6.10.3 Session component

#### Recognized arguments:

## Description:

This component of the module currently sets the user's KRBTKFILE environment variable (although there is currently no way to export this), as well as deleting the user's ticket file upon logout (until PAM\_CRED\_DELETE is supported by *login*).

## Examples/suggested usage:

This part of the module won't be terribly useful until we can change the environment from within a Linux-PAM module.

#### 6.10.4 Password component

#### Recognized arguments:

```
use_first_pass; try_first_pass
```

#### Description:

This component of the module changes a user's Kerberos password by first getting and using the user's old password to get a session key for the password changing service, then sending a new password to that service.

#### Examples/suggested usage:

This should only be used with a real Kerberos v4 kadmind. It cannot be used with an AFS kaserver unless special provisions are made. Contact the module author for more information.

## 6.10.5 Authentication component

#### Recognized arguments:

```
use_first_pass; try_first_pass
```

#### Description:

This component of the module verifies a user's Kerberos password by requesting a ticket granting ticket from the Kerberos server and optionally using it to attempt to retrieve the local computer's host key and verifying using the key file on the local machine if one exists.

It also writes out a ticket file for the user to use later, and deletes the ticket file upon logout (not until PAM\_CRED\_DELETE is called from login).

# Examples/suggested usage:

This module can be used with a real Kerberos server using MIT v4 Kerberos keys. The module or the system Kerberos libraries may be modified to support AFS style Kerberos keys. Currently this is not supported to avoid cryptography constraints.

# 6.11 The last login module

# 6.11.1 Synopsis

#### Module Name:

pam\_lastlog

#### Author:

Andrew G. Morgan <morgan@kernel.org>

#### Maintainer:

Author

# Management groups provided:

auth

# Cryptographically sensitive:

Security rating:

Clean code base:

### System dependencies:

uses information contained in the /var/log/lastlog file.

#### Network aware:

# 6.11.2 Overview of module

This session module maintains the /var/log/lastlog file. Adding an open entry when called via the pam\_open\_seesion() function and completing it when pam\_close\_session() is called. This module can also display a line of information about the last login of the user. If an application already performs these tasks, it is not necessary to use this module.

# 6.11.3 Session component

#### Recognized arguments:

debug; nodate; noterm; nohost; silent; never

### Description:

This module can be used to provide a "Last login on ..." message. when the user logs into the system from what ever application uses the PAM libraries. In addition, the module maintains the /var/log/lastlog file.

The behavior of this module can be modified with one of the following flags:

- debug write more information to syslog(3).
- nodate neglect to give the date of the last login when displaying information about the last login on the system.
- noterm neglect to diplay the terminal name on which the last login was attempt.
- nohost neglect to indicate from which host the last login was attempted.
- silent neglect to inform the user about any previous login: just update the /var/log/lastlog
- never if the /var/log/lastlog file does not contain any old entries for the user, indicate that the user has never previously logged in with a "welcome..." message.

# Examples/suggested usage:

This module can be used to indicate that the user has new mail when they *login* to the system. Here is a sample entry for your /etc/pam.d/XXX file:

```
#
# When were we last here?
#
session optional pam_lastlog.so
```

Note, some applications may perform this function themselves. In such cases, this module is not necessary.

# 6.12 The resource limits module

# 6.12.1 Synopsis

### Module Name:

pam\_limits

#### Authors:

Cristian Gafton <gafton@redhat.com>

Thanks are also due to Elliot Lee <sopwith@redhat.com> for his comments on improving this module.

### Maintainer:

Cristian Gafton - 1996/11/20

### Management groups provided:

session

# Cryptographically sensitive:

Security rating:

#### Clean code base:

### System dependencies:

requires an /etc/security/limits.conf file and kernel support for resource limits. Also uses the library, libpwdb.

# Network aware:

#### 6.12.2 Overview of module

This module, through the **Linux-PAM** open-session hook, sets limits on the system resources that can be obtained in a user-session. Its actions are dictated more explicitly through the configuration file discussed below.

#### 6.12.3 Session component

### Recognized arguments:

```
debug; conf=/path/to/file.conf; change_uid; utmp_early
```

# Description:

Through the contents of the configuration file, /etc/security/limits.conf, resource limits are placed on users' sessions. Users of uid=0 are not affected by this restriction.

The behavior of this module can be modified with the following arguments:

- debug verbose logging to syslog(3).
- conf=/path/to/file.conf indicate an alternative limits configuration file to the default.
- change\_uid change real uid to the user for who the limits are set up. Use this option if you have problems like login not forking a shell for user who has no processes. Be warned that something else may break when you do this.
- utmp\_early some broken applications actually allocate a utmp entry for the user before the
  user is admitted to the system. If some of the services you are configuring PAM for do this, you
  can selectively use this module argument to compensate for this behavior and at the same time
  maintain system-wide consistency with a single limits.conf file.

# Examples/suggested usage:

In order to use this module the system administrator must first create a *root-only-readable* file (default is /etc/security/limits.conf). This file describes the resource limits the superuser wishes to impose on users and groups. No limits are imposed on uid=0 accounts.

Each line of the configuration file describes a limit for a user in the form:

```
<domain> <type> <item> <value>
```

The fields listed above should be filled as follows...

<domain> can be:

- a username
- $\bullet\,$  a group name, with  ${\tt Qgroup}$  syntax
- the wild-card \*, for default entry
- the wild-card %, for maxlogins limit only, can also be used with %group syntax

<type> can have the three values:

• hard for enforcing *hard* resource limits. These limits are set by the superuser and enforced by the Linux Kernel. The user cannot raise his requirement of system resources above such values.

- soft for enforcing *soft* resource limits. These limits are ones that the user can move up or down within the permitted range by any pre-exisiting *hard* limits. The values specified with this token can be thought of as *default* values, for normal system usage.
- - for enforcing both *soft* and *hard* limits together.

<item> can be one of the following:

- core limits the core file size (KB)
- data max data size (KB)
- fsize maximum filesize (KB)
- memlock max locked-in-memory address space (KB)
- nofile max number of open files
- rss max resident set size (KB)
- stack max stack size (KB)
- cpu max CPU time (MIN)
- nproc max number of processes
- as address space limit
- maxlogins max number of logins for this user
- maxsyslogins max number of logins on system
- priority the priority to run user process with (negative values boost process priority)
- locks max locked files (Linux 2.4 and higher)
- chroot directory to chroot user to

Note, if you specify a type of "-" but neglect to supply the item and value fields then the module will never enforce any limits on the corresponding user/group-members etc. . Note, the first entry of the form which applies to the authenticating user will override all other entries in the limits configuration file. In such cases, the pam\_limits module will always return PAM\_SUCCESS.

In general, individual limits have priority over group limits, so if you impose no limits for admin group, but one of the members in this group have a limits line, the user will have its limits set according to this line.

Also, please note that all limit settings are set *per login*. They are not global, nor are they permanent; existing only for the duration of the session.

In the *limits* configuration file, the "#" character introduces a comment - after which the rest of the line is ignored.

The pam\_limits module does its best to report configuration problems found in its configuration file via syslog(3).

The following is an example configuration file:

#### # EXAMPLE /etc/security/limits.conf file: # <domain> <type> <item> <value> soft Ω core 10000 hard rss @student 20 hard nproc

<pre>@faculty</pre>	soft	nproc	20
<pre>@faculty</pre>	hard	nproc	50
ftp	hard	nproc	0
ftp	-	chroot	/ftp
@student	_	maxlogins	4

Note, the use of soft and hard limits for the same resource (see @faculty) – this establishes the default and permitted extreme level of resources that the user can obtain in a given service-session.

Note, that wild-cards \* and % have the following meaning when used for maxlogins limit

- \* every user
- % all users, or entire group when %group is specified

See the following examples:

Explanation: every user can login 2 times, members of the faculty group can login 4 times, there can be only 30 logins, only 10 from students group.

For the services that need resources limits (login for example) put the following line in /etc/pam.conf as the last line for that service (usually after the pam unix session line:

```
#
# Resource limits imposed on login sessions via pam_limits
#
login session required pam_limits.so
```

### 6.13 The list-file module

#### 6.13.1 Synopsis

# Module Name:

```
pam_listfile
```

### Author:

```
Elliot Lee <sopwith@cuc.edu>
```

# Maintainer:

```
Red Hat Software:
```

```
Michael K. Johnson < johnsonm@redhat.com> 1996/11/18 (if unavailable, contact Elliot Lee < sopwith@cuc.edu>).
```

# Management groups provided:

authentication

Cryptographically sensitive:

Security rating:

Clean code base:

clean

System dependencies:

Network aware:

#### 6.13.2 Overview of module

The list-file module provides a way to deny or allow services based on an arbitrary file.

#### 6.13.3 Authentication component

### Recognized arguments:

```
onerr=succeed|fail; sense=allow|deny; file=filename; item=user|tty|rhost|ruser|group|shell apply=user|@group
```

#### Description:

The module gets the item of the type specified — user specifies the username, PAM\_USER; tty specifies the name of the terminal over which the request has been made, PAM\_TTY; rhost specifies the name of the remote host (if any) from which the request was made, PAM\_RHOST; and ruser specifies the name of the remote user (if available) who made the request, PAM\_RUSER — and looks for an instance of that item in the file filename. filename contains one line per item listed. If the item is found, then if sense=allow, PAM\_SUCCESS is returned, causing the authorization request to succeed; else if sense=deny, PAM\_AUTH\_ERR is returned, causing the authorization request to fail.

If an error is encountered (for instance, if *filename* does not exist, or a poorly-constructed argument is encountered), then if onerr=succeed, PAM\_SUCCESS is returned, otherwise if onerr=fail, PAM\_AUTH\_ERR or PAM\_SERVICE\_ERR (as appropriate) will be returned.

An additional argument, apply=, can be used to restrict the application of the above to a specific user (apply=username) or a given group (apply=@groupname). This added restriction is only meaningful when used with the tty, rhost and shell items.

Besides this last one, all arguments should be specified; do not count on any default behavior, as it is subject to change.

No credentials are awarded by this module.

# Examples/suggested usage:

Classic "ftpusers" authentication can be implemented with this entry in /etc/pam.conf:

```
#
# deny ftp-access to users listed in the /etc/ftpusers file
#
ftp auth required pam_listfile.so \
    onerr=succeed item=user sense=deny file=/etc/ftpusers
```

Note, users listed in /etc/ftpusers file are (counterintuitively) not allowed access to the ftp service. To allow login access only for certain users, you can use a pam. conf entry like this:

```
#
# permit login to users listed in /etc/loginusers
#
login auth required pam_listfile.so \
    onerr=fail item=user sense=allow file=/etc/loginusers
```

For this example to work, all users who are allowed to use the login service should be listed in the file /etc/loginusers. Unless you are explicitly trying to lock out root, make sure that when you do this, you leave a way for root to log in, either by listing root in /etc/loginusers, or by listing a user who is able to su to the root account.

### 6.14 The mail module

### 6.14.1 Synopsis

#### Module Name:

pam\_mail

#### Author:

Andrew G. Morgan <morgan@kernel.org>

# Maintainer:

Author

# Management groups provided:

Authentication (credential) Session (open)

#### Cryptographically sensitive:

Security rating:

Clean code base:

# System dependencies:

Default mail directory /var/spool/mail/

Network aware:

# 6.14.2 Overview of module

This module looks at the user's mail directory and indicates whether the user has any mail in it.

### 6.14.3 Session component

#### Recognized arguments:

debug; dir=directory-name; nopen; close; noenv; empty; hash=hashcount; standard; quiet;

# Description:

This module provides the "you have new mail" service to the user. It can be plugged into any application that has credential hooks. It gives a single message indicating the *newness* of any mail it finds in the user's mail folder. This module also sets the **Linux-PAM** environment variable, MAIL, to the user's mail directory.

The behavior of this module can be modified with one of the following flags:

- debug write more information to syslog(3).
- dir=pathname look for the users' mail in an alternative directory given by pathname. The default location for mail is /var/spool/mail. Note, if the supplied pathname is prefixed by a '~', the directory is interpreted as indicating a file in the user's home directory.
- nopen instruct the module to *not* print any mail information when the user's credentials are acquired. This flag is useful to get the MAIL environment variable set, but to not display any information about it.
- close instruct the module to indicate if the user has any mail at the as the user's credentials are revoked.
- noenv do not set the MAIL environment variable.
- empty indicate that the user's mail directory is empty if this is found to be the case.
- hash=hashcount mail directory hash depth. For example, a hashcount of 2 would make the mailfile be /var/spool/mail/u/s/user.
- standard old style "You have..." format which doesn't show the mail spool being used. this also implies "empty"
- quiet only report when there is new mail.

# Examples/suggested usage:

This module can be used to indicate that the user has new mail when they *login* to the system. Here is a sample entry for your /etc/pam.conf file:

```
#
# do we have any mail?
#
login session optional pam_mail.so
```

Note, if the mail spool file (be it /var/spool/mail/\$USER or a pathname given with the dir= parameter) is a directory then pam\_mail assumes it is in the *Qmail Maildir* format.

Note, some applications may perform this function themselves. In such cases, this module is not necessary.

# 6.14.4 Authentication component

Then authentication companent works the same as the session component, except that everything is done during the pam\_setcred() phase.

# 6.15 Create home directories on initial login

#### 6.15.1 Synopsis

#### Module Name:

pam\_mkhomedir

### Author:

Jason Gunthorpe <jgg@ualberta.ca>

# Maintainer:

Ben Collins <a href="mailto:collins@debian.org">bcollins@debian.org</a>

# Management groups provided:

Session

Cryptographically sensitive:

Security rating:

Clean code base:

System dependencies:

Network aware:

### 6.15.2 Overview of module

Creates home directories on the fly for authenticated users.

# 6.15.3 Session component

### Recognized arguments:

```
skel=skeleton-dir; umask=octal-umask;
```

# Description:

This module is useful for distributed systems where the user account is managed in a central database (such as NIS, NIS+, or LDAP) and accessed through miltiple systems. It frees the administrator from having to create a default home directory on each of the systems by creating it upon the first successfully authenticated login of that user. The skeleton directory (usually /etc/skel/) is used to copy default files and also set's a umask for the creation.

The behavior of this module can be modified with one of the following flags:

- skel The skeleton directory for default files to copy to the new home directory.
- umask An octal for of the same format as you would pass to the shells umask command.

# Examples/suggested usage:

session required pam\_mkhomedir.so skel=/etc/skel/ umask=0022

# 6.16 Output the motd file

### 6.16.1 Synopsis

### Module Name:

pam\_motd

### Author:

Ben Collins <a href="mailto:collins@debian.org">bcollins@debian.org</a>

# Maintainer:

Author

# Management groups provided:

Session (open)

# Cryptographically sensitive:

Security rating:

Clean code base:

System dependencies:

Network aware:

# 6.16.2 Overview of module

This module outputs the motd file (/etc/motd by default) upon successful login.

# 6.16.3 Session component

### Recognized arguments:

```
debug; motd=motd-file-name;
```

# Description:

This module allows you to have arbitrary modd's (message of the day) output after a successful login. By default this file is /etc/motd, but is configurable to any file.

The behavior of this module can be modified with one of the following flags:

• motd - the file to output if not using the default.

### Examples/suggested usage:

login session pam motd.so motd=/etc/motd

# 6.17 The no-login module

#### 6.17.1 Synopsis

#### Module Name:

pam\_nologin

#### Author:

Written by Michael K. Johnson < johnsonm@redhat.com>

#### Maintainer:

# Management groups provided:

account; authentication

Cryptographically sensitive:

Security rating:

Clean code base:

System dependencies:

Network aware:

# 6.17.2 Overview of module

Provides standard Unix nologin authentication.

# 6.17.3 Authentication component

# Recognized arguments:

```
successok, file=<filename>
```

### Description:

Provides standard Unix *nologin* authentication. If the file /etc/nologin exists, only root is allowed to log in; other users are turned away with an error message (and the module returns PAM\_AUTH\_ERR or PAM\_USER\_UNKNOWN). All users (root or otherwise) are shown the contents of /etc/nologin.

If the file /etc/nologin does not exist, this module defaults to returning PAM\_IGNORE, but the successok module argument causes it to return PAM\_SUCCESS in this case.

The administrator can override the default nologin file with the file=pathname module argument.

### Examples/suggested usage:

In order to make this module effective, all login methods should be secured by it. It should be used as a required method listed before any sufficient methods in order to get standard Unix nologin semantics. Note, the use of successok module argument causes the module to return PAM\_SUCCESS and as such would break such a configuration - failing sufficient modules would lead to a successful login because the nologin module succeeded.

# 6.18 The promiscuous module

#### 6.18.1 Synopsis

#### Module Name:

pam permit

### Author:

Andrew G. Morgan, <morgan@kernel.org>

#### Maintainer:

Linux-PAM maintainer.

# Management groups provided:

account; authentication; password; session

### Cryptographically sensitive:

#### Security rating:

VERY LOW. Use with extreme caution.

#### Clean code base:

Clean.

### System dependencies:

Network aware:

#### 6.18.2 Overview of module

This module is very dangerous. It should be used with extreme caution. Its action is always to permit access. It does nothing else.

### 6.18.3 Account+Authentication+Password+Session components

# Recognized arguments:

# Description:

No matter what management group, the action of this module is to simply return PAM\_SUCCESS — operation successful.

In the case of authentication, the user's name will be acquired. Many applications become confused if this name is unknown.

# Examples/suggested usage:

It is seldom a good idea to use this module. However, it does have some legitimate uses. For example, if the system-administrator wishes to turn off the account management on a workstation, and at the same time continue to allow logins, then she might use the following configuration file entry for login:

```
#
# add this line to your other login entries to disable account
# management, but continue to permit users to log in...
#
login account required pam_permit.so
```

#### 6.19 The Password-Database module

# 6.19.1 Synopsis

#### Module Name:

pam pwdb

#### Author:

```
Cristian Gafton <gafton@redhat.com>
and Andrew G. Morgan <morgan@kernel.org>
```

#### Maintainer:

Red Hat.

# Management groups provided:

account; authentication; password; session

### Cryptographically sensitive:

Security rating:

Clean code base:

### System dependencies:

Requires properly configured libpwdb

Network aware:

### 6.19.2 Overview of module

This module is a pluggable replacement for the pam\_unix\_.. modules. It uses the generic interface of the Password Database library libpwdb.

#### 6.19.3 Account component

### Recognized arguments:

debug

# Description:

The debug argument makes the accounting functions of this module syslog(3) more information on its actions. (Remaining arguments supported by the other functions of this module are silently ignored, but others are logged as errors through syslog(3)).

Based on the following pwdb\_elements: expire; last\_change; max\_change; defer\_change; warn\_change, this module performs the task of establishing the status of the user's account and password. In the case of the latter, it may offer advice to the user on changing their password or, through the PAM\_AUTHTOKEN\_REQD return, delay giving service to the user until they have established a new password. The entries listed above are documented in the Password Database Library Guide (see pointer above). Should the user's record not contain one or more of these entries, the corresponding shadow check is not performed.

# Examples/suggested usage:

In its accounting mode, this module can be inserted as follows:

```
#
# Ensure users account and password are still active
#
login account required pam_pwdb.so
```

#### 6.19.4 Authentication component

# Recognized arguments:

```
debug; use_first_pass; try_first_pass; nullok; nodelay; likeauth; noreap
```

# Description:

The debug argument makes the authentication functions of this module syslog(3) more information on its actions.

The default action of this module is to not permit the user access to a service if their *official* password is blank. The nullok argument overrides this default.

When given the argument try\_first\_pass, before prompting the user for their password, the module first tries the previous stacked auth-module's password in case that satisfies this module as well. The argument use\_first\_pass forces the module to use such a recalled password and will never prompt the user - if no password is available or the password is not appropriate, the user will be denied access.

The argument, nodelay, can be used to discourage the authentication component from requesting a delay should the authentication as a whole fail. The default action is for the module to request a delay-on-failure of the order of one second.

Remaining arguments, supported by the other functions of this module, are silently ignored. Other arguments are logged as errors through syslog(3).

A helper binary, pwdb\_chkpwd, is provided to check the user's password when it is stored in a read protected database. This binary is very simple and will only check the password of the user invoking it. It is called transparently on behalf of the user by the authenticating component of this module. In this way it is possible for applications like *xlock* to work without being setuid-root. The module, by default, will temporarily turn off SIGCHLD handling for the duration of execution of the helper binary. This is generally the right thing to do, as many applications are not prepared to handle this signal from a child they didn't know was fork()d. The noreap module argument can be used to suppress this temporary shielding and may be needed for use with certain applications.

The likeauth argument makes the module return the same value when called as a credential setting module and an authentication module. This will help libpam take a sane path through the auth component of your configuration file.

# Examples/suggested usage:

The correct functionality of this module is dictated by having an appropriate /etc/pwdb.conf file, the user databases specified there dictate the source of the authenticated user's record.

# 6.19.5 Password component

# Recognized arguments:

```
debug; nullok; not_set_pass; use_authtok; try_first_pass; use_first_pass; md5; bigcrypt; shadow; radius; unix
```

# Description:

This part of the pam\_pwdb module performs the task of updating the user's password. Thanks to the flexibility of libpwdb this module is able to move the user's password from one database to another, perhaps securing the user's database entry in a dynamic manner (this is very ALPHA code at the moment!) - this is the purpose of the shadow, radius and unix arguments.

In the case of conventional unix databases (which store the password encrypted) the md5 argument is used to do the encryption with the MD5 function as opposed to the *conventional* crypt(3) call. As an alternative to this, the bigcrypt argument can be used to encrypt more than the first 8 characters of a password with DEC's (Digital Equipment Cooperation) 'C2' extension to the standard UNIX crypt() algorithm.

The nullok module is used to permit the changing of a password *from* an empty one. Without this argument, empty passwords are treated as account-locking ones.

The argument use\_first\_pass is used to lock the choice of old and new passwords to that dictated by the previously stacked password module. The try\_first\_pass argument is used to avoid the user having to re-enter an old password when pam\_pwdb follows a module that possibly shared the user's old password - if this old password is not correct the user will be prompted for the correct one. The argument use\_authtok is used to force this module to set the new password to the one provided by the previously stacked password module (this is used in an example of the stacking of the Cracklib module documented above).

The not\_set\_pass argument is used to inform the module that it is not to pay attention to/make available the old or new passwords from/to other (stacked) password modules.

The debug argument makes the password functions of this module syslog(3) more information on its actions. Other arguments may be logged as erroneous to syslog(3).

# Examples/suggested usage:

An example of the stacking of this module with respect to the pluggable password checking module, pam\_cracklib, is given in that modules section above.

# 6.19.6 Session component

#### Recognized arguments:

### Description:

No arguments are recognized by this module component. Its action is simply to log the username and the service-type to syslog(3). Messages are logged at the beginning and end of the user's session.

# Examples/suggested usage:

The use of the session modules is straightforward:

```
#
# pwdb - unix like session opening and closing
#
login session required pam_pwdb.so
```

# 6.20 The RADIUS session module

# 6.20.1 Synopsis

# Module Name:

pam\_radius

### Author:

Cristian Gafton <gafton@redhat.com>

### Maintainer:

Author.

# Management groups provided:

session

# Cryptographically sensitive:

This module does not deal with passwords

# Security rating:

#### Clean code base:

gcc reports 1 warning when compiling /usr/include/rpc/clnt.h. Hey, is not my fault!

# System dependencies:

#### Network aware:

yes; this is a network module (independent of application).

### 6.20.2 Overview of module

This module is intended to provide the session service for users authenticated with a RADIUS server. At the present stage, the only option supported is the use of the RADIUS server as an accounting server.

# 6.20.3 Session component

# Recognized arguments:

```
debug - verbose logging to syslog(3).
```

# Description:

This module is intended to provide the session service for users authenticated with a RADIUS server. At the present stage, the only option supported is the use of the RADIUS server as an *accounting* server.

(There are few things which needs to be cleared out first in the PAM project until one will be able to use this module and expect it to magically start pppd in response to a RADIUS server command to use PPP for this user, or to initiate a telnet connection to another host, or to hang and call back the user using parameters provided in the RADIUS server response. Most of these things are better suited for the radius login application. I hope to make available Real Soon (tm) patches for the login apps to make it work this way.)

When opening a session, this module sends an "Accounting-Start" message to the RADIUS server, which will log/update/whatever a database for this user. On close, an "Accounting-Stop" message is sent to the RADIUS server.

This module has no other prerequisites for making it work. One can install a RADIUS server just for fun and use it as a centralized accounting server and forget about wtmp/last/sac etc. .

# Examples/suggested usage:

For the services that need this module (*login* for example) put the following line in /etc/pam.conf as the last line for that service (usually after the pam unix session line):

```
login session required pam_radius.so
```

Replace login for each service you are using this module.

This module make extensive use of the API provided in libpwdb 0.54preB or later. By default, it will read the radius server configuration (hostname and secret) from /etc/raddb/server. This is a default compiled into libpwdb, and currently there is no way to modify this default without recompiling libpwdb. I am working on extending the radius support from libpwdb to provide a possibility to make this runtime-configurable.

Also please note that libpwdb will require also the RADIUS dictionary to be present (/etc/raddb/dictionary).

# 6.21 The rhosts module

### 6.21.1 Synopsis

# Module Name:

pam\_rhosts\_auth

#### Author:

Al Longvear < longvear@netcom.com>

# Maintainer:

#### Management groups provided:

authentication

# Cryptographically sensitive:

# Security rating:

### Clean code base:

Clean.

# System dependencies:

#### Network aware:

Standard inet\_addr(), gethostbyname() function calls.

#### 6.21.2 Overview of module

This module performs the standard network authentication for services, as used by traditional implementations of rlogin and rsh etc.

# 6.21.3 Authentication component

# Recognized arguments:

no\_hosts\_equiv; no\_rhosts; debug; no\_warn; privategroup; promiscuous; suppress

# Description:

The authentication mechanism of this module is based on the contents of two files; /etc/hosts.equiv (or \_PATH\_HEQUIV in #include <netdb.h>) and ~/.rhosts. Firstly, hosts listed in the former file are treated as equivalent to the localhost. Secondly, entries in the user's own copy of the latter file is used to map "remote-host remote-user" pairs to that user's account on the current host. Access is granted to the user if their host is present in /etc/hosts.equiv and their remote account is identical to their local one, or if their remote account has an entry in their personal configuration file.

Some restrictions are applied to the attributes of the user's personal configuration file: it must be a regular file (as defined by S\_ISREG(x) of POSIX.1); it must be owned by the *superuser* or the user; it must not be writable by any user besides its owner.

The module authenticates a remote user (internally specified by the item PAM\_RUSER) connecting from the remote host (internally specified by the item PAM\_RHOST). Accordingly, for applications to be compatible this authentication module they must set these items prior to calling pam\_authenticate(). The module is not capable of independently probing the network connection for such information.

In the case of root-access, the /etc/host.equiv file is *ignored* unless the hosts\_equiv\_rootok option should be used. Instead, the superuser must have a correctly configured personal configuration file.

The behavior of the module is modified by flags:

- debug log more information to syslog(3). (XXX actually, this module does not do any logging currently, please volunteer to fix this!)
- no\_warn do not give verbal warnings to the user about failures etc. (XXX this module currently does not issue any warnings, please volunteer to fix this!)
- no\_hosts\_equiv ignore the contents of the /etc/hosts.equiv file.
- hosts\_equiv\_rootok allow the use of /etc/hosts.equiv for superuser. Without this option /etc/hosts.equiv is not consulted for the superuser account. This option has no effect if the no\_hosts\_equiv option is used.

- no\_rhosts ignore the contents of all user's personal configuration file ~/.rhosts.
- privategroup normally, the ~/.rhosts file must not be writable by anyone other than its owner. This option overlooks group write access in the case that the group owner of this file has the same name as the user being authenticated. To lessen the security problems associated with this option, the module also checks that the user is the only member of their private group.
- promiscuous A host entry of '+' will lead to all hosts being granted access. Without this option, '+' entries will be ignored. Note, that the debug option will syslog a warning in this latter case.
- suppress This will prevent the module from syslog(3)ing a warning message when this authentication fails. This option is mostly for keeping logs free of meaningless errors, in particular when the module is used with the sufficient control flag.

# Examples/suggested usage:

To allow users to login from trusted remote machines, you should try adding the following line to your /etc/pam.conf file before the line that would otherwise prompt the user for a password:

```
#
# No passwords required for users from hosts listed above.
#
login auth sufficient pam_rhosts_auth.so no_rhosts
```

Note, in this example, the system administrator has turned off all *personal rhosts* configuration files. Also note, that this module can be used to *only* allow remote login from hosts specified in the /etc/host.equiv file, by replacing sufficient in the above example with required.

# 6.22 The root access module

# 6.22.1 Synopsis

#### Module Name:

pam rootok

#### Authora

Andrew G. Morgan <morgan@kernel.org>

#### Maintainer:

Linux-PAM maintainer

### Management groups provided:

authentication

Cryptographically sensitive:

Security rating:

Clean code base:

Clean.

#### System dependencies:

Network aware:

#### 6.22.2 Overview of module

This module is for use in situations where the superuser wishes to gain access to a service without having to enter a password.

# 6.22.3 Authentication component

# Recognized arguments:

debug

### Description:

This module authenticates the user if their uid is 0. Applications that are created *setuid*-root generally retain the uid of the user but run with the authority of an enhanced *effective*-uid. It is the real uid that is checked.

### Examples/suggested usage:

In the case of the su application the historical usage is to permit the superuser to adopt the identity of a lesser user without the use of a password. To obtain this behavior under Linux-PAM the following pair of lines are needed for the corresponding entry in the configuration file:

```
#
# su authentication. Root is granted access by default.
#
su auth sufficient pam_rootok.so
su auth required pam_unix_auth.so
```

Note. For programs that are run by the superuser (or started when the system boots) this module should not be used to authenticate users.

# 6.23 The securetty module

# 6.23.1 Synopsis

#### Module Name:

```
pam_securetty
```

#### Author[s]:

Elliot Lee <sopwith@cuc.edu>

#### Maintainer:

```
Red Hat Software:

currently Michael K. Johnson < johnsonm@redhat.com>

(if unavailable, contact Elliot Lee < sopwith@cuc.edu>).
```

#### Management groups provided:

authentication

# Cryptographically sensitive:

Security rating:

Clean code base:

### System dependencies:

/etc/securetty file

#### Network aware:

Requires the application to fill in the PAM\_TTY item correctly in order to act meaningfully.

#### 6.23.2 Overview of module

Provides standard Unix securetty checking.

### 6.23.3 Authentication component

### Recognized arguments:

# Description:

Provides standard Unix securetty checking, which causes authentication for root to fail unless PAM\_TTY is set to a string listed in the /etc/securetty file. For all other users, it succeeds.

# Examples/suggested usage:

For canonical usage, should be listed as a required authentication method before any sufficient authentication methods.

# 6.24 The login counter (tallying) module

# 6.24.1 Synopsis

# Module Name:

pam tally

# Author[s]:

Tim Baverstock Tomas Mraz

Maintainer:

# Management groups provided:

auth; account

# Cryptographically sensitive:

Security rating:

Clean code base:

# System dependencies:

A faillog file (default location /var/log/faillog)

#### Network aware:

#### 6.24.2 Overview of module

This module maintains a count of attempted accesses, can reset count on success, can deny access if too many attempts fail.

pam\_tally comes in two parts: pam\_tally.so and pam\_tally. The former is the PAM module and the latter, a stand-alone program. pam\_tally is an (optional) application which can be used to interrogate and manipulate the counter file. It can display users' counts, set individual counts, or clear all counts. Setting artificially high counts may be useful for blocking users without changing their passwords. For example, one might find it useful to clear all counts every midnight from a cron job.

The counts file is organized as a binary-word array, indexed by uid. You can probably make sense of it with od, if you don't want to use the supplied appliction.

Note, there are some outstanding issues with this module: pam\_tally is very dependant on getpw\*() - a database of usernames would be much more flexible

# Generic options accepted by both components

- onerr=(succeed|fail): if something weird happens, such as unable to open the file, how should the module react?
- file=/where/to/keep/counts: specify the file location for the counts. The default location is /var/log/faillog.
- audit: display the username typed if the user is not found. It may be useful for scripts, but you should
  know users often type their password instead making your system weaker. Activate it only if you know
  what you are doing.

#### 6.24.3 Authentication component

### Recognized arguments:

```
onerr=(succeed|fail); file=/where/to/keep/counts; deny=n; lock_time=n; unlock_time=n;
magic_root; even_deny_root_account; per_user; no_lock_time no_reset;
```

# Description:

The authentication component first checks if the user should be denied access and if not it increments attempted login counter. Then on call to pam\_setcred it resets the attempts counter if the user is NOT magic root.

# Examples/suggested usage:

The deny=n option is used to deny access if tally for this user exceeds n.

The  $lock\_time=n$  option is used to always deny access for at least n seconds after a failed attempt.

The  $unlock\_time=n$  option is used to allow access after n seconds after the last failed attempt with exceeded tally. If this option is used the user will be locked out only for the specified amount of time after he exceeded his maximum allowed attempts. Otherwise the lock is removed only by a manual intervention of the system administrator.

The magic\_root option is used to indicate that if the module is invoked by a user with uid=0, then the counter is not incremented. The sys-admin should use this for user launched services, like su, otherwise this argument should be omitted.

By way of more explanation, when a process already running as root tries to access some service, the access is *magic*, and bypasses pam\_tally's checks: this is handy for suing from root into an account otherwise blocked. However, for services like telnet or login, which always effectively run from the root account, root (ie everyone) shouldn't be granted this magic status, and the flag 'magic\_root' should not be set in this situation, as noted in the summary above.

Normally, failed attempts to access root will **NOT** cause the root account to become blocked, to prevent denial-of-service: if your users aren't given shell accounts and root may only login via su or at the machine console (not telnet/rsh, etc), this is safe. If you really want root to be blocked for some given service, use even\_deny\_root\_account.

If /var/log/faillog contains a non-zero .fail\_max/.fail\_locktime field for this user then the per\_user module argument will ensure that the module uses this value and not the global deny/lock\_time=n parameter.

The no\_lock\_time option is for ensuring that the module does not use the .fail\_locktime field in /var/log/faillog for this user.

The no\_reset option is used to instruct the module to not reset the count on successful entry.

# 6.24.4 Account component

### Recognized arguments:

```
onerr=(succeed|fail); file=/where/to/keep/counts; magic_root; no_reset;
```

#### Description:

The account component resets attempts counter if the user is NOT magic root. This phase can be used optionally for services which don't call pam\_setcred correctly or if the reset should be done regardless of the failure of the account phase of other modules.

# Examples/suggested usage:

The magic\_root option is used to indicate that if the module is invoked by a user with uid=0, then the counter is not decremented/reset. The sys-admin should use this for user launched services, like su, otherwise this argument should be omitted.

The no\_reset option is used to instruct the module to not reset the count on successful entry.

# 6.25 Time control

#### 6.25.1 Synopsis

### Module Name:

pam\_time

### Author:

Andrew G. Morgan <morgan@kernel.org>

#### Maintainer:

Author

Management groups provided:

account

Cryptographically sensitive:

Security rating:

Clean code base:

System dependencies:

Requires a configuration file /etc/security/time.conf

Network aware:

Through the PAM\_TTY item only

#### 6.25.2 Overview of module

Running a well regulated system occasionally involves restricting access to certain services in a selective manner. This module offers some time control for access to services offered by a system. Its actions are determined with a configuration file. This module can be configured to deny access to (individual) users based on their name, the time of day, the day of week, the service they are applying for and their terminal from which they are making their request.

#### 6.25.3 Account component

### Recognized arguments:

### Description:

This module bases its actions on the rules listed in its configuration file: /etc/security/time.conf. Each rule has the following form,

```
services; ttys; users; times
```

In words, each rule occupies a line, terminated with a newline or the beginning of a comment; a '#'. It contains four fields separated with semicolons, ';'. The fields are as follows:

- services a logic list of service names that are affected by this rule.
- ttys a logic list of terminal names indicating those terminals covered by the rule.
- $\bullet \ user$  a logic list of usernames to which this rule applies

By a logic list we mean a sequence of tokens (associated with the appropriate PAM\_ item), containing no more than one wildcard character; '\*', and optionally prefixed with a negation operator; '!'. Such a sequence is concatenated with one of two logical operators: & (logical AND) and | (logical OR). Two examples are: !morgan&!root, indicating that this rule does not apply to the user morgan nor to root; and tty\*&!ttyp\*, which indicates that the rule applies only to console terminals but not pseudoterminals.

• times - a logic list of times at which this rule applies. The format of each element is a day/time-range. The days are specified by a sequence of two character entries. For example, MoTuSa, indicates Monday Tuesday and Saturday. Note that repeated days are unset; MoTuMo indicates Tuesday, and MoWk means all weekdays bar Monday. The two character combinations accepted are,

```
Mo Tu We Th Fr Sa Su Wk Wd Al
```

The last two of these being weekend days and all 7 days of the week respectively.

The time range part is a pair of 24-hour times, *HHMM*, separated by a hyphen – indicating the start and finish time for the rule. If the finsish time is smaller than the start time, it is assumed to apply on the following day. For an example, Mo1800-0300 indicates that the permitted times are Monday night from 6pm to 3am the following morning.

Note, that the given time restriction is only applied when the first three fields are satisfied by a user's application for service.

For convenience and readability a rule can be extended beyond a single line with a '\newline'.

# Examples/suggested usage:

The use of this module is initiated with an entry in the Linux-PAM configuration file of the following type:

```
#
# apply pam_time accounting to login requests
#
login account required pam_time.so
```

where, here we are applying the module to the *login* application.

Some examples of rules that can be placed in the /etc/security/time.conf configuration file are the following:

```
login ; tty* & !ttyp* ; !root ; !Al0000-2400
    all users except for root are denied access to console-login at all times.
```

```
games ; * ; !waster ; Wd0000-2400 | Wk1800-0800
```

games (configured to use Linux-PAM) are only to be accessed out of working hours. This rule does not apply to the user waster.

Note, currently there is no daemon enforcing the end of a session. This needs to be remedied.

Poorly formatted rules are logged as errors using syslog(3).

#### 6.26 The Unix Password module

# 6.26.1 Synopsis

#### Module Name:

pam unix

# Author:

Maintainer:

# Management groups provided:

account; authentication; password; session

Cryptographically sensitive:

Security rating:

Clean code base:

System dependencies:

Network aware:

#### 6.26.2 Overview of module

This is the standard Unix authentication module. It uses standard calls from the system's libraries to retrieve and set account information as well as authentication. Usually this is obtained from the /etc/passwd and the /etc/shadow file as well if shadow is enabled.

#### 6.26.3 Account component

# Recognized arguments:

debug; audit

# Description:

The debug argument makes the accounting functions of this module syslog(3) more information on its actions. (Remaining arguments supported by the other functions of this module are silently ignored, but others are logged as errors through syslog(3)). The audit argument causes even more logging.

Based on the following shadow elements: expire; last\_change; max\_change; min\_change; warn\_change, this module performs the task of establishing the status of the user's account and password. In the case of the latter, it may offer advice to the user on changing their password or, through the PAM\_AUTHTOKEN\_REQD return, delay giving service to the user until they have established a new password. The entries listed above are documented in the GNU Libc info documents. Should the user's record not contain one or more of these entries, the corresponding shadow check is not performed.

### Examples/suggested usage:

In its accounting mode, this module can be inserted as follows:

```
#
# Ensure users account and password are still active
#
login account required pam_unix.so
```

### 6.26.4 Authentication component

# Recognized arguments:

```
debug; audit; use_first_pass; try_first_pass; nullok; nodelay; noreap
```

# Description:

The debug argument makes the authentication functions of this module syslog(3) more information on its actions. The audit causes even more information to be logged.

The default action of this module is to not permit the user access to a service if their *official* password is blank. The nullok argument overrides this default.

When given the argument try\_first\_pass, before prompting the user for their password, the module first tries the previous stacked auth-module's password in case that satisfies this module as well. The argument use\_first\_pass forces the module to use such a recalled password and will never prompt the user - if no password is available or the password is not appropriate, the user will be denied access.

The argument, nodelay, can be used to discourage the authentication component from requesting a delay should the authentication as a whole fail. The default action is for the module to request a delay-on-failure of the order of one second.

A helper binary, unix\_chkpwd, is provided to check the user's password when it is stored in a read protected database. This binary is very simple and will only check the password of the user invoking it. It is called transparently on behalf of the user by the authenticating component of this module. In this way it is possible for applications like xlock to work without being setuid-root. The module, by default, will temporarily turn off SIGCHLD handling for the duration of execution of the helper binary. This is generally the right thing to do, as many applications are not prepared to handle this signal from a child they didn't know was fork()d. The noreap module argument can be used to suppress this temporary shielding and may be needed for use with certain applications.

Remaining arguments, supported by the other functions of this module, are silently ignored. Other arguments are logged as errors through syslog(3).

# Examples/suggested usage:

The correct functionality of this module is dictated by having an appropriate /etc/nsswitch.conf file, the user databases specified there dictate the source of the authenticated user's record.

In its authentication mode, this module can be inserted as follows:

```
#
# Authenticate the user
#
login auth required pam_unix.so
```

#### 6.26.5 Password component

# Recognized arguments:

```
debug; audit; nullok; not_set_pass; use_authtok; try_first_pass; use_first_pass; md5;
bigcrypt; shadow; nis; min; max; obscure; remember
```

#### Description:

This part of the pam\_unix module performs the task of updating the user's password.

In the case of conventional unix databases (which store the password encrypted) the md5 argument is used to do the encryption with the MD5 function as opposed to the *conventional* crypt(3) call. As an alternative to this, the bigcrypt argument can be used to encrypt more than the first 8 characters of a password with DEC's (Digital Equipment Cooperation) 'C2' extension to the standard UNIX crypt() algorithm.

The nullok argument is used to permit the changing of a password *from* an empty one. Without this argument, empty passwords are treated as account-locking ones.

The argument use\_first\_pass is used to lock the choice of old and new passwords to that dictated by the previously stacked password module. The try\_first\_pass argument is used to avoid the user having to re-enter an old password when pam\_unix follows a module that possibly shared the user's old password - if this old password is not correct the user will be prompted for the correct one. The argument use\_authtok is used to force this module to set the new password to the one provided by the previously stacked password module (this is used in an example of the stacking of the Cracklib module documented above).

The not\_set\_pass argument is used to inform the module that it is not to pay attention to/make available the old or new passwords from/to other (stacked) password modules.

The debug argument makes the password functions of this module syslog(3) more information on its actions. Other arguments may be logged as erroneous to syslog(3). The audit argument causes even more information to be logged.

With the nis argument, pam\_unix will attempt to use NIS RPC for setting new passwords.

The remember argument takes one value. This is the number of most recent passwords to save for each user. These are saved in /etc/security/opasswd in order to force password change history and keep the user from alternating between the same password too frequently.

The min and max options allow control over the length of the password. These have a hard coded default of 1 and 8. The values are inclusive.

The obscure option enables some extra checks on the password. These is taken after the same obscure checks enabled in the original shadow package. This works very similar to the pam\_cracklib module and implements these checks (it does not implement dictionary checks):

#### • Palindrome -

Is the new password a palindrome of the old one? A palindrome is where the words read the same backwards and forwards (eg. madam and radar).

#### • Case Change Only -

Is the new password the the old one with only a change of case?

#### • Similar -

Is the new password too much like the old one?

# • Simple -

Is the new password too small? This is based on the length of the password and the number of different types of characters used (ie.alpha, numeric...).

# • Rotated -

Is the new password a rotated version of the old password (eg. "billy" and "illyb")?

# Examples/suggested usage:

Standard usage:

```
#
# Change the users password
#
passwd password required pam_unix.so
```

An example of the stacking of this module with respect to the pluggable password checking module, pam\_cracklib:

```
#
# Change the users password
#
passwd password required pam_cracklib.so retry=3 minlen=6 difok=3
passwd password required pam_unix.so use_authtok nullok md5
```

# 6.26.6 Session component

# Recognized arguments:

# Description:

No arguments are recognized by this module component. Its action is simply to log the username and the service-type to syslog(3). Messages are logged at the beginning and end of the user's session.

# Examples/suggested usage:

The use of the session modules is straightforward:

```
#
# session opening and closing
#
login session required pam_unix.so
```

# 6.27 The userdb module

### 6.27.1 Synopsis

# Module Name:

pam\_userdb

#### Author:

Cristian Gafton <gafton@redhat.com>

# Maintainer:

Author.

# Management groups provided:

authentication

# Cryptographically sensitive:

Security rating:

Clean code base:

# System dependencies:

Requires Berkeley DB.

# Network aware:

#### 6.27.2 Overview of module

Look up users in a .db database and verify their password against what is contained in that database.

#### 6.27.3 Authentication component

# Recognized arguments:

```
debug; icase; dump; db=XXXX; use_authtok; unknown_ok;
```

# Description:

This module is used to verify a username/password pair against values stored in a Berkeley DB database. The database is indexed by the username, and the data fields corresponding to the username keys are the passwords, in unencrypted form, so caution must be exercised over the access rights to the DB database itself...

The module will read the password from the user using the conversation mechanism. If you are using this module on top of another authentication module (like pam\_unix;) then you should tell that module to read the entered password from the PAM AUTHTOK field, which is set by this module.

The action of the module may be modified from this default by one or more of the following flags in the /etc/pam.d/<service> file.

- debug Supply more debugging information to syslog(3).
- icase Perform the password comparisons case insensitive.
- dump dump all the entries in the database to the log (eek, don't do this by default!)
- db=XXXX use the database found on pathname XXXX. Note that Berkeley DB usually adds the needed filename extension for you, so you should use something like /etc/foodata instead of /etc/foodata.db.
- use\_authtok use the authentication token previously obtained by another module that did the conversation with the application. If this token can not be obtained then the module will try to converse again. This option can be used for stacking different modules that need to deal with the authentication tokens.
- unknown\_ok do not return error when checking for a user that is not in the database. This can be used to stack more than one pam\_userdb module that will check a username/password pair in more than a database.

# Examples/suggested usage:

This is a normal ftp configuration file (usually placed as /etc/pam.d/ftp on most systems) that will accept for login users whose username/password pairs are provided in the /tmp/dbtest.db file:

```
#%PAM-1.0
                        pam_listfile.so item=user sense=deny file=/etc/ftpusers onerr=succeed
           required
auth
                        pam_userdb.so icase db=/tmp/dbtest
auth
           sufficient
auth
           required
                        pam_unix.so shadow nullok try_first_pass
auth
           required
                        pam_shells.so
           required
                        pam_unix.so
account
session
           required
                        pam_unix.so
```

# 6.28 Warning logger module

# 6.28.1 Synopsis

### Module Name:

pam\_warn

### Author:

Andrew G. Morgan <morgan@kernel.org>

### Maintainer:

Author.

# Management groups provided:

authentication; password

# Cryptographically sensitive:

Security rating:

Clean code base:

# System dependencies:

#### Network aware:

logs information about the remote user and host (if pam-items are known)

#### 6.28.2 Overview of module

This module is principally for logging information about a proposed authentication or application to update a password.

# 6.28.3 Authentication+Password component

# Recognized arguments:

### Description:

Log the service, terminal, user, remote user and remote host to syslog(3). The items are not probed for, but instead obtained from the standard pam-items.

# Examples/suggested usage:

an example is provided in the configuration file section 4 (above).

### 6.29 The wheel module

# 6.29.1 Synopsis

#### Module Name:

pam\_wheel

### Author:

Cristian Gafton <gafton@redhat.com>

#### Maintainer:

Author.

# Management groups provided:

authentication; account

Cryptographically sensitive:

Security rating:

Clean code base:

System dependencies:

Network aware:

# 6.29.2 Overview of module

Only permit root access to members of the wheel (gid=0) group.

# 6.29.3 Authentication and Account components

### Recognized arguments:

```
debug; trust; deny; group=XXXX
```

# Description:

This module is used to enforce the so-called *wheel* group. By default, it permits root access to the system if the applicant user is a member of the wheel group (first, the module checks for the existence of a 'wheel' group. Otherwise the module defines the group with group-id 0 to be the *wheel* group).

The module can be used as either an 'auth' or an 'account' module.

The action of the module may be modified from this default by one or more of the following flags in the /etc/pam.conf file.

- debug Supply more debugging information to syslog(3).
- trust This option instructs the module to return PAM\_SUCCESS should it find the user applying for root privilege is a member of the wheel group. The default action is to return PAM\_IGNORE in this situation. By using the trust option it is possible to arrange for wheel-group members to become root without typing a password. USE WITH CARE.

7. Files 69

• deny - This is used to reverse the logic of the module's behavior. If the user is trying to get uid=0 access and is a member of the wheel group, deny access (for the wheel group, this is perhaps nonsense!): it is intended for use in conjunction with the group= argument... Conversely, if the user is not in the group, return PAM\_IGNORE (unless trust was also specified, in which case we return PAM\_SUCCESS).

• group=XXXX - Instead of checking the gid=0 group, use the user's XXXX group membership for the authentication. Here, XXXX is the name of the group and **not** its numeric identifier.

# Examples/suggested usage:

To restrict access to superuser status to the members of the wheel group, use the following entries in your configuration file:

```
#
# root gains access by default (rootok), only wheel members can
# become root (wheel) but Unix authenticate non-root applicants.
#
su auth sufficient pam_rootok.so
su auth required pam_wheel.so
su auth required pam_unix.so
```

# 7 Files

```
/lib/libpam.so.*
```

the shared library providing applications with access to Linux-PAM.

/etc/pam.conf

the Linux-PAM configuration file.

```
/lib/security/pam_*.so
```

the primary location for Linux-PAM dynamically loadable object files; the modules.

# 8 See also

- The Linux-PAM Application Writers' Guide.
- The Linux-PAM Module Writers' Guide.
- The V. Samar and R. Schemers (SunSoft), "UNIFIED LOGIN WITH PLUGGABLE AUTHENTICATION MODULES", Open Software Foundation Request For Comments 86.0, October 1995. See this url: http://www.kernel.org/pub/linux/libs/pam/pre/doc/rfc86.0.txt.gz

# 9 Notes

I intend to put development comments here... like "at the moment this isn't actually supported". At release time what ever is in this section will be placed in the Bugs section below! :)

Are we going to be able to support the use\_mapped\_pass module argument? Anyone know a cheap (free) good lawyer?!

• This issue may go away, as Sun have investigated adding a new management group for mappings. In this way, libpam would have mapping modules that could securely store passwords using strong cryptography and in such a way that they need not be distributed with Linux-PAM.

# 10 Author/acknowledgments

This document was written by Andrew G. Morgan (morgan@kernel.org) with many contributions from Chris Adams, Peter Allgeyer, Tim Baverstock, Tim Berger, Craig S. Bell, Derrick J. Brashear, Ben Buxton, Seth Chaiklin, Oliver Crow, Chris Dent, Marc Ewing, Cristian Gafton, Emmanuel Galanos, Brad M. Garcia, Eric Hester, Michel D'Hooge, Roger Hu, Eric Jacksch, Michael K. Johnson, David Kinchlea, Olaf Kirch, Marcin Korzonek, Stephen Langasek, Nicolai Langfeldt, Elliot Lee, Luke Kenneth Casson Leighton, Al Longyear, Ingo Luetkebohle, Marek Michalkiewicz, Robert Milkowski, Aleph One, Martin Pool, Sean Reifschneider, Jan Rekorajski, Erik Troan, Theodore Ts'o, Jeff Uphoff, Myles Uyema, Savochkin Andrey Vladimirovich, Ronald Wahl, David Wood, John Wilmes, Joseph S. D. Yao and Alex O. Yuriev.

Thanks are also due to Sun Microsystems, especially to Vipin Samar and Charlie Lai for their advice. At an early stage in the development of **Linux-PAM**, Sun graciously made the documentation for their implementation of PAM available. This act greatly accelerated the development of **Linux-PAM**.

# 11 Bugs/omissions

More PAM modules are being developed all the time. It is unlikely that this document will ever be truely up to date!

This manual is unfinished. Only a partial list of people is credited for all the good work they have done.

# 12 Copyright information for this document

Copyright (c) Andrew G. Morgan 1996-2002. All rights reserved.

Email: <morgan@kernel.org>

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, and the entire permission notice in its entirety, including the disclaimer of warranties.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

Alternatively, this product may be distributed under the terms of the GNU General Public License (GPL), in which case the provisions of the GNU GPL are required instead of the above restrictions. (This clause is necessary due to a potential bad interaction between the GNU GPL and the restrictions contained in a BSD-style copyright.)

THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

\$Id: pam\_source.sgml 278 2005-07-13 10:57:05Z vorlon \$