# Inter-VLAN Routing


#### **Inter-VLAN Routing**

- Process of forwarding network traffic from one VLAN to another VLAN.
- 3 options:
  - 🚺 🔎 Legacy Inter-VLAN Routing: Legacy. Does not scale well.
  - 2 \* Router-on-a-Stick (RoaS): Acceptable for small to medium-sized network.
  - **3** ★ Inter-VLAN Routing on a Layer 3 Switch: Most scalable solution for medium to large organizations.



#### Legacy Inter-VLAN Routing

- Using a Router requiring 1 physical interface per VLAN.
- Limitation: Routers have a limited number of interfaces.
- No longer implemented!!! Explanation purposes only!!!




#### 2 Router-on-a-Stick Inter-VLAN Routing (RoaS)

- Only requires 1 physical interface to route traffic between multiple VLANs.
- Router (trunk port)
   Link
   Switch (trunk port)
- Using software-based subinterfaces to identify routable VLANs.
  - Each subinterface configured for each VLAN.
- Limitation: does not scale beyond 50 VLANs.


#### **2** RoaS Configuration (S1/S2)

```
S2(config)# vlan 10
S2(config-vlan)# name LAN10
S2(config-vlan)# vlan 20
S2(config-vlan)# name LAN20
S2(config-vlan)# vlan 99
S2(config-vlan)# name Management
S2(config-vlan)# interface vlan 99
S2(config-if)# ip add 192.168.99.3 255.255.255.0
S2(config-if)# no shutdown
S2(config-if)# exit
S2(config)# ip default-gateway 192.168.99.1
S2(config)# interface f0/18
S2(config-if)# switchport mode access
S2(config-if)# switchport access vlan 20
S2(config-if)# no shutdown
```



## **2** RoaS Configuration (R1)

```
R1(config)# interface g0/0/1.10
R1(config-subif)# description Default gw for VLAN 10
R1(config-subif)# encapsulation dot1q 10
R1(config-subif)# ip add 192.168.10.1 255.255.255.0
R1(config-subif)# interface g0/0/1.20
R1(config-subif)# description Default gw for VLAN 20
R1(config-subif)# encapsulation dot1q 20
R1(config-subif)# ip add 192.168.20.1 255.255.255.0
R1(config-subif)# interface g0/0/1.99
R1(config-subif)# description Default gw for VLAN 99
R1(config-subif)# encapsulation dot1q 99
R1(config-subif)# ip add 192.168.99.1 255.255.255.0
R1(config-subif)# interface g0/0/1
R1(config-if)# description Trunk link to S1
R1(config-if)# no shutdown
```



#### **3** ★ Inter-VLAN Routing on a Layer 3 Switch

- Modern method that uses Layer 3 / Multilayer Switches and SVIs.
- SVI created for each VLAN interface vlan 10
- Convert a Layer 2 switchport to a Layer 3 interface (routed port).
- Advantages:
  - Much faster than RoaS.
  - No need for external links from the switch to the router.
  - Not limited to 1 link
     EtherChannels as trunk links between switches
  - Latency much lower.
  - More commonly deployed in a Campus LAN than router.
- Disavantage: Layer 3 Switches are more expensive.

## **3** L3 Switch Routing Config

```
D1(config)# vlan 10
D1(config-vlan)# name LAN10
D1(config-vlan)# vlan 20
D1(config-vlan)# name LAN20
D1(config-vlan)# interface vlan 10
D1(config-if)# description Default gw for 192.168.10.0/24
D1(config-if)# ip add 192.168.10.1 255.255.255.0
D1(config-if)# no shutdown
D1(config-if)# interface vlan 20
D1(config-if)# description Default gw for 192.168.20.0/24
D1(config-if)# ip add 192.168.20.1 255.255.255.0
D1(config-if)# no shutdown
D1(config-if)# interface GigabitEthernet1/0/6
D1(config-if)# description Access port to PC1
D1(config-if)# switchport mode access
D1(config-if)# switchport access vlan 10
D1(config-if)# interface GigabitEthernet1/0/18
D1(config-if)# description Access port to PC2
D1(config-if)# switchport mode access
D1(config-if)# switchport access vlan 20
D1(config-if)# exit
D1(config)# ip routing
```

