# *Fundamentos de Sistemas Operativos / Sistemas de Operação*

DETI

*Interprocess communication*

Artur Pereira / António Rui Borges

# *Concepts*

- In a multiprogrammed environment, two or more processes can be:
  - *independent* – if they, from their creation to their termination, never explicitly interact
    - actually. there is an implicit interaction, as they compete for system resources
    - ex: jobs in a batch system; processes from different users
  - *cooperative* – if they share information or explicitly communicate
    - the *sharing* requires a common address space
    - *communication* can be done through a common address space or a communication channel connecting them

DETI

# Concepts










- *independent processs* competing for a resource
- it is the responsibility of the OS to ensure the assignment of resources to processes is done in a controlled way, such that no information lost occurs
- in general, this imposes that only one process can use the resource at a time -- mutual exclusive access

- *cooperative processes* sharing information or communicating
- it is the responsibility of the processes to ensure that access to the shared area is done in a controlled way, such that no information lost occurs
- in general, this imposes that only one process can use the resource at a time -- mutual exclusive access
- the communication channel is typically a system resource; so processes compete for it

# *Concepts*

- Having access to a resource or to a shared area actually means executing the code that does the access
- This code, because **race conditions** need to be avoided (can result in loss of information), is called **critical section**



# *Concepts*

- Mutual exclusion in the access to a resource or shared area can result in:
  - ***deadlock*** – when two or more processes are waiting forever for access to their respective critical section, waiting for events that can be demonstrated will never happen
    - operations are blocked
  - ***starvation*** – when one or more processes compete for access to a critical section and, due to a conjunction of circumstances in which new processes that exceed them continually arise, access is successively deferred
    - operations are continuously postponed

DETI

# *Access to a resource or to a shared area*

```
/* processes competing for a resource - p = 0, 1, ..., N-1 */
void main (unsigned int p)
{
  forever
  {
    do_something();
    access_resource(p);    →  { enter_critical_section(p);
    do_something_else();       use_resource();              ← critical section
  }                            leave_critical_section(p);
}
```

```
/* shared data structure */
shared DATA d;
/* processes sharing data - p = 0, 1, ..., N-1 */
void main (unsigned int p)
{
  forever
  {
    do_something();
    access_shared_area(p);  →  { enter_critical_section(p);
    do_something_else();        manipulate_shared_area();   ← critical section
  }                             leave_critical_section(p);
}
```

# *Producer / consumer relationship*

```
/* communicating data structure: FIFO of fixed size */

shared FIFO fifo;

/* producer processes - p = 0, 1, ..., N-1 */
void producer(unsigned int p)
{
    DATA val;
    bool done;

    forever
    {
        produce_data(&val);
        done = false;
        do
        {
            enter_critical_section(p);
            if (fifo.notFull())
            {
                fifo.insert(val);
                done = true;
            }
            leave_critical_section(p);

        } while (!done);
        do_something_else();
    }
}
```

***critical section***



DETI

# Producer / consumer relationship

```
/* communicating data structure: FIFO of fixed size */

shared FIFO fifo;

/* consumer processes - p = 0, 1, ..., M-1 */
void consumer(unsigned int p)
{
    DATA val;
    bool done;

    forever
    {
        done = false;
        do
        {
            enter_critical_section(p);
            if (fifo.notEmpty())
            {
                fifo.retrieve(&val);
                done = true;
            }
            leave_critical_section(p);
        } while (!done);
        consume_data(val);
        do_something_else();
  }
}
```

***critical section***

# *Access to a critical section*

- Requirements that should be observed in accessing a critical section:
  - effective mutual exclusion – access to the critical sections associated with the same resource, or shared area, can only be allowed to one process at a time, among all processes that compete for access
  - independence on the number of intervening processes or on their relative speed of execution
  - a process outside the critical section can not prevent another from entering there
  - a process requiring access to the critical section should not have to wait indefinitely
  - length of stay inside a critical section should be necessarily finite

DETI

# ***Type of solutions***

- In general, a memory location is used to control access to the critical region
- ***software solutions*** – solutions that are based on the typical instructions used to access memory location
  - read and write are done by different instructions
- ***hardware solutions*** – solutions that are based on special instructions to access the memory location
  - these instructions allow to read and then write a memory location in an atomic way

DETI

# *Strict alternation*

```
/* control data structure */
#define  R    ...     /* process id = 0, 1, …, R-1 */

shared unsigned int access_turn = 0;

void enter_critical_section(unsigned int own_pid)
{
  while (own_pid != access_turn);
}

void leave_critical_section(unsigned int own_pid)
{
  if (own_pid == access_turn)
     access_turn = (access_turn + 1) % R;
}
```

DETI

# *Strict alternation*

- Not a valid solution
  - Dependence on the relative speed of execution of the intervening processes
    - The process with less accesses imposes its rhythm to the others
  - A process outside the critical section can prevent another from entering there
    - If it is not its turn, a process has to wait, even if no one else wants to enter

DETI

# *Constructing a solution*

```
/* control data structure */
#define  R    2          /* process id = 0, 1 */

shared bool is_in[R] = {false, false};

void enter_critical_section(unsigned int own_pid)
{
    unsigned int other_pid = 1 - own_pid;

    while (is_in[other_pid]);
    is_in[own_pid] = true;
}

void leave_critical_section(unsigned int own_pid)
{
  is_in[own_pid] = false;
}
```

DETI

# *Constructing a solution*

- Not a valid solution
  - Mutual exclusion is not guaranteed
  - Assume that:
    - $P_0$ enters `enter_critical_section` and tests `is_in[1]`, which is *false*
    - $P_1$ enters `enter_critical_section` and tests `is_in[0]`, which is *false*
    - $P_1$ changes `is_in[0]` to *true* and enters its critical section
    - $P_0$ changes `is_in[1]` to *true* and enters its critical section
    - Thus, both processes enter the critical sections

  - It seems that the failure is a result of testing first the other's control variable and then change its own variable

DETI

# *Constructing a solution*

```
/* control data structure */
#define  R    2          /* process pid = 0, 1 */

shared bool want_enter[R] = {false, false};

void enter_critical_section (unsigned int own_pid)
{
  unsigned int other_pid = 1 - own_pid;

  want_enter[own_pid] = true;
  while (want_enter[other_pid]);
}

void leave_critical_section (unsigned int own_pid)
{
  want_enter[own_pid] = false;
}
```

# *Constructing a solution*

- Not a valid solution
  - Mutual exclusion is guaranteed, but deadlock can occur
  - Assume that:
    - $P_0$ enters `enter_critical_section` and sets `want_enter[0]` to *true*
    - $P_1$ enters `enter_critical_section` and sets `want_enter[1]` to *true*
    - $P_1$ tests `want_enter[0]` and, because it is *true*, keeps waiting to enter its critical section
    - $P_0$ tests `want_enter[1]` and, because it is *true*, keeps waiting to enter its critical section
    - Thus, both processes enter in deadlock

  - To solve the deadlock at least one of the processes have to go back

DETI

# *Constructing a solution*

```
/* control data structure */
#define  R    2          /* process id = 0, 1 */

shared bool want_enter[R] = {false, false};

void enter_critical_section(unsigned int own_pid)
{
  unsigned int other_pid = 1 - own_pid;

  want_enter[own_pid] = true;
  while (want_enter[other_pid])
  {
    want_enter[own_pid] = false;
    random_delay();
    want_enter[own_pid] = true;
  }
}

void leave_critical_section(unsigned int own_pid)
{
  want_enter[own_pid] = false;
}
```


DETI

# *Constructing a solution*

- An almost valid solution
  - The Ethernet protocol uses a similar approach to control access to the communication medium
- But, still not completely valid
  - Even if unlikely, deadlock and starvation can still be present
- The solution needs to be deterministic, not random

DETI

# Dekker algorithm (1965)

```
#define  R    2    /* process id = 0, 1 */

shared bool want_enter[R] = {false, false};
shared uint p_w_priority = 0;

void enter_critical_section(uint own_pid)
{
   uint other_pid = 1 - own_pid;

   want_enter[own_pid] = true;
   while (want_enter[other_pid])
   {
      if (own_pid != p_w_priority)
      {
         want_enter[own_pid] = false;
         while (own_pid != p_w_priority);
         want_enter[own_pid] = true;
      }
   }
}
```

```
void leave_critical_section(uint own_pid)
{
   uint other_pid = 1 - own_pid;
   p_w_priority = other_pid;
   want_enter[own_pid] = false;
}
```

# *Dekker algorithm* (*1965*)

- The algorithm uses an alternation mechanism (on the priority) to solve the conflict
- Mutual exclusion in the access to the critical section is guaranteed
- Deadlock and starvation are not present
- No assumptions are done in the relative speed of the intervening processes

- However, it can **not be generalized** to more than 2 processes, satisfying all the requirements

DETI

# *Dijkstra algorithm (1966)*

```
#define  R    ...   /* process id = 0, 1, ..., R-1 */

shared uint want_enter[R] = {NO, NO, ... , NO};
shared uint p_w_priority = 0;

void enter_critical_section(uint own_pid)
{
   uint n;
   do
   {
      want_enter[own_pid] = WANT;
      while (own_pid != p_w_priority)
         if (want_enter[p_w_priority] == NO)
            p_w_priority = own_pid;
      want_enter[own_pid] = DECIDED;
      for (n = 0; n < R; n++)
         if (n != own_pid && want_enter[n] == DECIDED)
            break;
   } while (n < R);
}
```

```
void leave_critical_section(uint own_pid)

{
  p_w_priority = (own_pid + 1) % R;
  want_enter[own_pid] = NO;
}
```

- Can suffer from starvation

# Peterson algorithm (1981)

```
#define  R    2     /* process id = 0, 1 */

shared bool want_enter[R] = {false, false};
shared uint last;


void enter_critical_section(uint own_pid)
{
    uint other_pid = 1 – own_pid;

    want_enter[own_pid] = true;
    last = other_pid;
    while ((want_enter[other_pid]) && (last == other_pid));
}

void leave_critical_section(uint own_pid)
{
    want_enter[own_pid] = false;
}
```

DETI

# *Peterson algorithm (1981)*

- The Peterson algorithm uses the order of arrival to solve conflicts
  - Each process has to write the other's ID in a shared variable (last)
  - The subsequent reading allows to determine which was the last one
- It is a valid solution
  - Guarantees mutual exclusion
  - Avoids deadlock and startvation
  - Make no assumption about the relative speed of intervening processes
- Can be generalized to more than processes
  - The general solution is similar to a waiting queue

DETI

# *Generalized Peterson algorithm (1981)*

```
#define  R    ...     /* process id = 0, 1, ..., R-1 */

shared int level[R] = {-1, -1, ... , -1};
shared int last[R-1];

void enter_critical_section(uint own_pid)
{
   for (uint i = 0; i < R-1; i++)
   {
      level[own_pid] = i;
      last[i] = own_pid;
      do
      {
         test = false;
         for (uint j = 0; j < R; j++)
            if (j != own_pid)
               test = test || (level[j] >= i);
      } while (test && (last[i] == own_pid));
   }
}
```

```
void leave_critical_section(int own_pid)
{
   level[own_pid] = -1;
}
```

# ***Hardware solutions - disabling interrupts***

*Uniprocessor computational system*

- The switching of processes, in a multiprogrammed environment, is always caused by an external device:
  - *real time clock* (*RTC*) – causing the time-out transition in preemptive systems
  - *device controller* – can cause the preempt transitions in case of wake up of a higher priority process
  - In any case, interruptions of the processor
- Thus, access in mutual exclusion can be implemented disabling interrupts
- Only valid in kernel
  - Malicious or buggy code can completely block the system

*Multiprocessor computational system*

- Disabling interrupts in one processor has no effect

DETI

# *Hardware solutions - special instructions*

```
shared bool flag = false;

bool test_and_set(bool * flag)
{
   bool prev = *flag;
   *flag = true;
   return prev;
}


void lock(bool * flag)
{
   while (test_and_set(flag);
}


void unlock(bool * flag)
{
   *flag = false;
}
```

- The **test_and_set** function, if implemented atomically (without interruptions), can be used to construct the lock (enter critical section) primitive
- In the instruction set of some of the current processors, there is an atomic instruction implementing that behavior
- Surprisingly, it is often called TAS (test and set)

DETI

# *Hardware solutions - special instructions*

```
shared int value = 0;

int compare_and_swap(int * value, int expected, int new_value)
{
   int v = *value;
   if (*value == expected)
      *value = new_value;
   return v;
}

void lock(int * flag)
{
   while (compare_and_swap(&flag, 0, 1) != 0);
}


void unlock(bool * flag)
{
   *flag = 0;
}
```

- The **compare_and_swap** function, if implemented atomically (without interruptions), can be used to construct the lock (enter critical section) primitive
- In the instruction set of some of the current processors, there is an atomic instruction implementing that behavior
- In some instruction sets, there is a compare_and_set variant that returns a bool

DETI

# *Busy waiting*

- The previous solutions suffer from ***busy waiting*** – the lock primitive is in the active state (using the CPU) while waiting
  - They are often referred to as **spinlocks**, as the process spins around the variable while waiting for access

- In uniprocessor systems, busy waiting is unwanted, as there is
  - **loss of efficiency** – the time quantum of a process can be used for nothing
  - **risk of deadlock** – if a higher priority process calls lock while a lower priority process is inside its critical section, none of them can proceed

- In multiprocessor system with shared memory, busy waiting can be less critical
  - switching processes cost time, that can be higher than the time spent by the other process inside its critical section

DETI

# *block and wake_up*

- In general, at least in uniprocessor systems, there is the requirement of blocking a process while it is waiting for entering its critical section

```
#define  R    ...        /* process id = 0, 1, ..., R-1 */

shared unsigned int access = 1;


void enter_critical_section(unsigned int own_pid)
{
  if (access == 0) block(own_pid);
     else access -= 1;
}
```

*atomic operation* (can not be interrupted)

```
void leave_critical_section(unsigned int own_pid)
{
  if (there_are_blocked_processes) wake_up_one();
     else access += 1;
}
```

*atomic operation* (can not be interrupted)

- Atomic operations are still required
- Note that `access` is an integer, not a boolean



DETI

# *Semaphores*

- A *semaphore* is a synchronization mechanism, defined by a data type plus two atomic operations, *down* and *up*
  - The operations are also referred to as *wait* and *signal*/*post*, respectively
- Data type:

```
typedef struct
{
   unsigned int val;      /* can not be negative */
   PROCESS *queue;        /* queue of waiting blocked processes */
} SEMAPHORE;
```

- Operations:
  - ***down*** – block process if `val` is zero; decrement val otherwise
  - ***up*** – if `queue` is not empty, wake up one process (accordingly to a given policy); increment `val` otherwise
- Note that `val` can only be manipulated through these operations

# *Semaphores*

```
/* array of semaphores defined in kernel */
#define  R   ... /* semid = 0, 1, ..., R-1 */

static SEMAPHORE sem[R];

void sem_down(unsigned int semid)
{
    disable_interruptions;
    if (sem[semid].val == 0)
        block_on_sem(getpid(), semid);
    else
        sem[semid].val -= 1;
    enable_interruptions;
}

void sem_up(unsigned int semid)
{
    disable_interruptions;
    if (sem[sem_id].queue != NULL)
        wake_up_one_on_sem(semid);
    else
        sem[semid].val += 1;
    enable_interruptions;
}
```

- This implementation is typical of uniprocessor systems. *Why?*

- Semaphores can be binary or not binary
- How to implement *mutual exclusion* using semaphores?

DETI

# Bounded-buffer problem

```
shared FIFO fifo;    /* fixed-size FIFO memory */
```

```
/* producers - p = 0, 1, ..., N-1 */

void producer(unsigned int p)
{
    DATA data;
    forever
    {
        produce_data(&data);
        bool done = false;
        do
        {
            lock(p);
            if (fifo.notFull())
            {
                fifo.insert(data);
                done = true;
            }
            unlock(p);
        } while (!done);
        do_something_else();
    }
}
```

```
/* consumers - c = 0, 1, ..., M-1 */

void consumer(unsigned int c)
{
    DATA data;
    forever
    {
        bool done = false;
        do
        {
            lock(c);
            if (fifo.notEmpty())
            {
                fifo.retrieve(&data);
                done = true;
            }
            unlock(c);
        } while (!done);
        consume_data(data);
        do_something_else();
    }
}
```

- How to implement using semaphores?
  - Guaranteeing mutual exclusion and absence of busy waiting

DETI

# *Solving the bounded-buffer problem using semaphores*

```
shared FIFO fifo;      /* fixed-size FIFO memory */
shared sem access;     /* semaphore to control mutual exclusion */
shared sem nslots;     /* semaphore to control number of available slots*/
shared sem nitems;     /* semaphore to control number of available items */
```

```
/* producers - p = 0, 1, ..., N-1 */
void producer(unsigned int p)
{
    DATA val;

    forever
    {
        produce_data(&val);
        sem_down(nslots);
        sem_down(access);
        fifo.insert(val);
        sem_up(access);
        sem_up(nitems);
        do_something_else();
    }
}
```

```
/* consumers - c = 0, 1, ..., M-1 */
void consumer(unsigned int c)
{
    DATA val;

    forever
    {
        sem_down(nitems);
        sem_down(access);
        fifo.retrieve(&val);
        sem_up(access);
        sem_up(nslots);
        consume_data(val);
        do_something_else();
    }
}
```

- fifo.empty() and fifo.full() are not necessary. *Why?*
- What are the initial values of the semaphores?

DETI

# Wrong solution of the bounded-buffer problem

```
shared FIFO fifo;      /* fixed-size FIFO memory */
shared sem access;     /* semaphore to control mutual exclusion */
shared sem nslots;     /* semaphore to control number of available slots*/
shared sem nitems;     /* semaphore to control number of available items */
```

```
/* producers - p = 0, 1, ..., N-1 */
void producer(unsigned int p)
{
    DATA data;
    forever
    {
        produce_data(&data);
        sem_down(access);
        sem_down(nslots);
        fifo.insert(data);
        sem_up(access);
        sem_up(nitems);
        do_something_else();
    }
}
```

```
/* consumers - c = 0, 1, ..., M-1 */
void consumer(unsigned int c)
{
    DATA data;
    forever
    {
        sem_down(nitems);
        sem_down(access);
        fifo.retrieve(&data);
        sem_up(access);
        sem_up(nslots);
        consume_data(data);
        do_something_else();
    }
}
```

- What is wrong with this solution?





DETI

# *Analysis of semaphores*

- Concorrent solutions based on semaphores have advantages and disadvantages
- *Advantages:*
  - *support at the operating system level* – operations on semaphores are implemented by the kernel and made available to programmers as *system calls*
  - *general* – they are low level contructions and so they are versatile, being able to be used in any type of solution
- *Disadvantages*
  - *specialized knowledge* – the programmer must be aware of concorrent programming principles, as race conditions or deadlock can be easily introduced
    - See the previous example, as an illustration of this

DETI



DETI

# Monitors

- A problem with semaphores is that they are used both to implement mutual exclusion and to synchronize processes
- Being low level primitives, they are applied in a bottom-up perpective
  - if required conditions are not satisfied, processes are blocked before they enter their critical sections
  - this approach is prone to errors, mainly in complex situations, as synchronization points can be scattered throughout the program
- A higher level approach should followed a top-down perpective
  - processes must first enter their critical regions and then block if pursuance conditions are not satisfied
- A solution is to introduce a (concurrent) construction at the programming language level that separately deals with mutual exclusion and synchronization

- A *monitor* is a synchronization mechanism, independently proposed by Hoare and Brinch Hansen, supported by a (concurrent) programming language
  - It is composed of an internal data structure, inicialization code and a number of accessing primitives



DETI

# *Monitors*

```
monitor example
{
   /* internal shared data structure */
   DATA data;

   condition c; /* condition variable */

   /* access methods */
   method_1 (...)
   {
      ...
   }

   method_2 (...)
   {
      ...
   }

   ...

   /* initialization code */
   ...
}
```

- An application is seen as a set of threads that compete to access the shared data structure
- This shared data can only be accessed through the access methods
- Every method is executed in mutual exclusion
- If a thread calls an access method while another thread is inside another access method, its execution is blocked until the other leaves
- Synchronization between threads is possible through *condition variables*
- Two operation on them are possible:
  - *wait* – the thread is blocked and put outside the monitor
  - *signal* – if there are threads blocked, one is waked up. *Which one*?

DETI

# ***Hoare monitor***

- What to do when *signal* occurs?
- *Hoare monitor* – the thread calling *signal* is put out of the monitor, so the just waked up thread can proceed
  - quite general, but its implementation requires a stack where the blocked thread is put




* operation fired when an access methods ends

# *Brinch Hansen monitor*

- *Brinch Hansen monitor* – the thread calling *signal* immediately leaves the monitor (*signal* is the last instruction of the monitor method)
  - easy to implement, but quite restrictive (only one signal allowed in a method)



# *Lampson / Redell monitors*

- *Lampson / Redell monitor* – the thread calling signal continues its execution and the just waked up thread is kept outside the monitor, competing for access
  - easy to implement, but can cause starvation



# Solving the bounded-buffer problem using monitors

```
shared FIFO fifo;      /* fixed-size FIFO memory */
shared mutex access;   /* mutex to control mutual exclusion */
shared cond nslots;    /* condition variable to control availability of slots*/
shared cond nitems;    /* condition variable to control availability of items */
```

```
/* producers - p = 0, 1, ..., N-1 */
void producer(unsigned int p)
{
   DATA data;
   forever
   {
      produce_data(&data);
      lock(access);
      if/while (fifo.isFull())
      {
         wait(nslots, access);
      }
      fifo.insert(data);
      signal(nitems);
      unlock(access);
      do_something_else();
   }
}
```

```
/* consumers - c = 0, 1, ..., M-1 */
void consumer(unsigned int c)
{
   DATA data;
   forever
   {
      lock(access);
      if/while (fifo.isEmpty())
      {
         wait(nitems, access);
      }
      fifo.retrieve(&data);
      signal(nslots);
      unlock(access);
      consume_data(data);
      do_something_else();
   }
}
```

- fifo.empty() and fifo.full() are now necessary. *Why?*
- What is the initial value of the mutex?



DETI

# *Message-passing*

- Processes can communicate exchanging messages
  - A general communication mechanism, not requiring shared memory
  - Valid for uniprocessor and multiprocessor systems
- Two operation are required:
  - **send** and **receive**
- A communication link is required:
  - There are different logical ways of implementing it
    - Direct or indirect (through mailboxes or ports) addressing
    - Synchronous or asynchronous communication
    - Automatic or explicit buffering

DETI

# *Message-passing - direct vs. indirect*

- Symmetric direct communication
  - A process that wants to communicate must explicitly name the receiver or sender
    - **`send`**`(P, message)` - send message to process P
    - **`receive`**`(P, message)` - receive message from process P
  - A communication link in this scheme has the following properties:
    - it is established automatically between a pair of communicating processes
    - it is associated with exactly two processes
    - between a pair of communicating processes there exist exactly one link
- Asymetric direct communication
  - Only the sender must explicitly name the receiver
    - **`send`**`(P, message)` - send message to process P
    - **`receive`**`(id, message)` - receive message from any process

DETI

# *Message-passing - direct vs. indirect*

- Indirect communication
  - The messages are sent and received from mailboxes, or ports
    - **`send`**`(M, message)` - send message to mailbox M
    - **`receive`**`(M, message)` - receive message from mailbox M
  - A communication link in this scheme has the following properties:
    - it is only established if the pair of communicating processes has a shared mailbox
    - it may be associated with more than two processes
    - between a pair of processes there may exist more than one link (a mailbox per each)
  - The problem of two or more processes trying to receive a message from the same mailbox?
    - Is it allowed?
    - If allowed, which one will succeed?

DETI

# *Message-passing - synchronization*

- There are different design options for implementing `send` and `receive`
  - **Blocking send** - the sending process blocks until the message is received by the receiving process or by the mailbox
  - **Nonblocking send** - the sending process sends the message and resumes operation.
  - **Blocking receive** - the receiver blocks until a message is available
  - **Nonblocking receive** - the receiver retrieves either a valid message or the indication that no one exits
- Different combinations of `send` and `receive` are possible

DETI

# *Message-passing - buffering*

- There are different design options for implementing the link supporting the communication
  - **Zero capacity** - there is no queue
    - the sender must block until the recipient receives the message
  - **Bounded capacity** - the queue has finite length
    - if the queue is full, the sender must block until space is available
  - **Unbounded capacity** - the queue has (potentially) infinite length

DETI

# Solving the bounded-buffer problem using messages

```
shared FIFO fifo;      /* fixed-size FIFO memory */
shared mutex access;   /* mutex to control mutual exclusion */
shared cond nslots;    /* condition variable to control availability of slots*/
shared cond nitems;    /* condition variable to control availability of items */
```

```
/* producers - p = 0, 1, ..., N-1 */
void producer(unsigned int p)
{
   DATA data;
   MESSAGE msg;

   forever
   {
      produce_data(&val);
      make_message(msg, data);
      send(msg);
      do_something_else();
    }
}
```

```
/* consumers - c = 0, 1, ..., M-1 */
void consumer(unsigned int c)
{
   DATA data;
   MESSAGE msg;

   forever
   {
      receive(msg);
      extract_data(data, msg);
      consume_data(data);
      do_something_else();
   }
}
```

# *POSIX support for monitors*

- Standard *POSIX*, *IEEE 1003.1c*, defines a programming interface (API) for the creation and synchronization of *threads*.
  - In unix, this interface is implemented by the *pthread* library
- It allows for the implementation of monitors in C/C++
  - Using mutexes and condition variables
  - Note that they are of the Lampson / Redell type
- Some of the available functions:
  - *`pthread_create`* – creates a new thread; similar to `fork`
  - *`pthread_exit`* – equivalent to `exit`
  - *`pthread_join`* – equivalent a `waitpid`
  - *`pthread_self`* – equivalent a `getpid()`
  - *`pthread_mutex_*`* – manipulation of mutexes
  - *`pthread_cond_*`* – manipulation of condition variables
  - *`pthread_once`* – inicialization

# *Semaphores in Unix/Linux*

- System V semaphores
  - creation: `semget`
  - down and up: `semop`
  - other operations: `semctl`
- POSIX semaphores
  - down and up
    - `sem_wait`, `sem_trywait`, `sem_timedwait`, `sem_post`
  - Two types: named and unnamed semaphores
  - Named semaphores
    - `sem_open`, `sem_close`, `sem_unlink`
    - created in a virtual filesystem (e.g., /dev/sem)
  - unnamed semaphores - memory based
    - `sem_init`, `sem_destroy`
  - execute `man sem_overview` for an overview

DETI

# *Message-passing in Unix/Linux*

- System V implementation
  - Defines a message queue where messages of diferent types (a positive integer) can be stored
  - The send operation blocks if space is not available
  - The receive operation has an argument to specify the type of message to receive: a given type, any type or a range of type
    - The oldest message of given type(s) is retrieved
    - Can be blocking or nonblocking
  - see system calls: `msgget`, `msgsnd`, `msgrcv`, and `msgctl`
- POSIX message queue
  - Defines a priority queue
  - The send operation blocks if space is not available
  - The receive operation removes the oldest message with the highest priority
    - Can be blocking or nonblocking
  - see functions: `mq_open`, `mq_send`, `mq_receive`, ...

DETI

# *Shared memory in Unix/Linux*

- Address spaces are independent
- But address spaces are virtual
- The same physical region can be mapped into two or more virtual regions
- This is managed as a resource by the operating system

- System V shared memory
  - creation - `shmget`
  - mapping - `shmat`, `shmdt`
  - other operations – `shmctl`

- POSIX shared memory
  - creation - `shm_open`, `ftruncate`
  - mapping - `mmap`, `munmap`
  - other operations - `close`, `shm_unlink`, `fchmod`, ...

DETI

# ***Bibliography***


*Operating Systems Concepts*, Silberschatz, Galvin, Gagne, John Wiley & Sons, 9th Ed

- Chapter 3: *Processes* (section 3.4)
- Chapter 5: *Process synchronization* (sections 5.1 to 5.8)

*Modern Operating Systems;* Tanenbaum & Bos; Prentice-Hall International Editions, 4rd Ed

- Chapter 2: *Processes and Threads* (sections 2.3 and 2.5)

*Operating Systems, Stallings,* Prentice-Hall International Editions, 7th Ed

- Chapter 5: *Concurrency: mutual exclusion and synchronization* (sections 5.1 to 5.5)


DETI