

# GAMES103: Intro to Physics-Based Animation

## Linear Finite Element Method

Huamin Wang

Dec 2021


# Topics for the Day

- The linear finite element method (FEM)
- The finite volume method (FVM)
- Hyperelastic models


# Linear Finite Element Method

# The Linear FEM Assumption

In a nutshell, linear FEM assumes that for any point  $\mathbf{X}$  in the reference triangle, its deformed correspondence is:  $\mathbf{x} = \mathbf{F}\mathbf{X} + \mathbf{c}$ .



A large grey arrow pointing right contains the equation  $\mathbf{x} = \mathbf{F}\mathbf{X} + \mathbf{c}$ . Above the arrow, the text "constant translational vector" is written next to a vertical line segment above the arrowhead. Below the arrow, the text "constant matrix" is written next to a vertical line segment below the arrowhead. At the bottom of the arrow, the text " $\mathbf{F} = \partial\mathbf{x}/\partial\mathbf{X}$ , known as deformation gradient" is written.




For any vector between two points, we can use  $\mathbf{F}$  to convert it from reference to deformed:

$$\mathbf{x}_{ba} = \mathbf{x}_b - \mathbf{x}_a = \mathbf{F}\mathbf{X}_b + \mathbf{c} - \mathbf{F}\mathbf{X}_a - \mathbf{c} = \mathbf{F}\mathbf{X}_{ba}.$$

# Deformation Gradient

Therefore, we can calculate the deformation gradient by edge vectors.




$$\mathbf{x} = \mathbf{F}\mathbf{X} + \mathbf{c}$$

$$\begin{cases} \mathbf{F}\mathbf{X}_{10} = \mathbf{x}_{10} \\ \mathbf{F}\mathbf{X}_{20} = \mathbf{x}_{20} \end{cases}$$

$$\mathbf{F}[\mathbf{X}_{10}] \quad \mathbf{X}_{20} = [\mathbf{x}_{10} \quad \mathbf{x}_{20}]$$


$$\mathbf{F} = [\mathbf{x}_{10} \quad \mathbf{x}_{20}][\mathbf{X}_{10} \quad \mathbf{X}_{20}]^{-1}$$



Problem:  $\mathbf{F}$  is related to deformation, but it contains rotation.

# Green Strain

Ideally, we need a tensor to describe shape deformation only. Recall that SVD gives  $\mathbf{F} = \mathbf{U}\mathbf{D}\mathbf{V}^T$ , where only  $\mathbf{V}^T$  and  $\mathbf{D}$  are relevant to deformation.




So we get rid of  $\mathbf{U}$  as:  $\mathbf{G} = \frac{1}{2}(\mathbf{F}^T\mathbf{F} - \mathbf{I}) = \frac{1}{2}(\mathbf{V}\mathbf{D}^2\mathbf{V}^T - \mathbf{I}) = \begin{bmatrix} \varepsilon_{uu} & \varepsilon_{uv} \\ \varepsilon_{uv} & \varepsilon_{vv} \end{bmatrix}$ , Green strain.

- If no deformation,  $\mathbf{G} = \mathbf{0}$ ; if deformation increases,  $\|\mathbf{G}\|$  increases.
- Three deformation modes:  $\varepsilon_{uu}$ ,  $\varepsilon_{vv}$  and  $\varepsilon_{uv}$ .
- $\mathbf{G}$  is rotation invariant: if additional rotation  $\mathbf{R}$ , then deformation gradient is  $\mathbf{RF}$  but green strain is the same:  $\mathbf{G} = \frac{1}{2}(\mathbf{F}^T\mathbf{R}^T\mathbf{RF} - \mathbf{I}) = \frac{1}{2}(\mathbf{V}\mathbf{D}^2\mathbf{V}^T - \mathbf{I})$ .

# Strain Energy Density Function

Let  $\mathbf{G}$  be the green strain describing deformation. We consider the energy density per reference area as:  $W(\mathbf{G})$ .



Total energy:

$$E = \int W(\mathbf{G}) dA = A^{\text{ref}} W(\varepsilon_{uu}, \varepsilon_{vv}, \varepsilon_{uv})$$

Constant within the triangle

The Saint Venant-Kirchhoff Model (StVK)

$$W(\varepsilon_{uu}, \varepsilon_{vv}, \varepsilon_{uv}) = \frac{\lambda}{2}(\varepsilon_{uu} + \varepsilon_{vv})^2 + \mu(\varepsilon_{uu}^2 + \varepsilon_{vv}^2 + 2\varepsilon_{uv}^2)$$

$\lambda$  and  $\mu$  are Lamé parameters.

$$\frac{\partial W}{\partial \mathbf{G}} = \begin{bmatrix} \frac{\partial W}{\partial \varepsilon_{uu}} & \frac{1}{2} \frac{\partial W}{\partial \varepsilon_{uv}} \\ \frac{1}{2} \frac{\partial W}{\partial \varepsilon_{uv}} & \frac{\partial W}{\partial \varepsilon_{vv}} \end{bmatrix} = \begin{bmatrix} 2\mu\varepsilon_{uu} + \lambda\varepsilon_{uu} + \lambda\varepsilon_{vv} & 2\mu\varepsilon_{uv} \\ 2\mu\varepsilon_{uv} & 2\mu\varepsilon_{vv} + \lambda\varepsilon_{uu} + \lambda\varepsilon_{vv} \end{bmatrix} = 2\mu\mathbf{G} + \lambda \text{trace}(\mathbf{G})\mathbf{I} = \mathbf{S}$$

Second Piola-Kirchhoff stress tensor,  
something about force

# Forces

Given everything we have, we can now calculate the forces.

$$\mathbf{f}_i = - \left( \frac{\partial E}{\partial \mathbf{x}_i} \right)^T = -A^{\text{ref}} \left( \frac{\partial W}{\partial \mathbf{x}_i} \right)^T = -A^{\text{ref}} \left( \boxed{\frac{\partial W}{\partial \varepsilon_{uu}}} \frac{\partial \varepsilon_{uu}}{\partial \mathbf{x}_i} + \boxed{\frac{\partial W}{\partial \varepsilon_{vv}}} \frac{\partial \varepsilon_{vv}}{\partial \mathbf{x}_i} + \boxed{\frac{\partial W}{\partial \varepsilon_{uv}}} \frac{\partial \varepsilon_{uv}}{\partial \mathbf{x}_i} \right)^T$$

As in stress

# Forces

Recall that,

$$\mathbf{F} = [\mathbf{x}_{10} \quad \mathbf{x}_{20}] [\mathbf{X}_{10} \quad \mathbf{X}_{20}]^{-1} = [\mathbf{x}_{10} \quad \mathbf{x}_{20}] \begin{bmatrix} a & b \\ c & d \end{bmatrix} = [a\mathbf{x}_{10} + c\mathbf{x}_{20} \quad b\mathbf{x}_{10} + d\mathbf{x}_{20}]$$

By definition,

$$\mathbf{G} = \frac{1}{2}(\mathbf{F}^T \mathbf{F} - \mathbf{I}) = \begin{bmatrix} \frac{1}{2}(a\mathbf{x}_{10} + c\mathbf{x}_{20})^T(a\mathbf{x}_{10} + c\mathbf{x}_{20}) - \frac{1}{2} & \frac{1}{2}(a\mathbf{x}_{10} + c\mathbf{x}_{20})^T(b\mathbf{x}_{10} + d\mathbf{x}_{20}) \\ \frac{1}{2}(a\mathbf{x}_{10} + c\mathbf{x}_{20})^T(b\mathbf{x}_{10} + d\mathbf{x}_{20}) & \frac{1}{2}(b\mathbf{x}_{10} + d\mathbf{x}_{20})^T(b\mathbf{x}_{10} + d\mathbf{x}_{20}) - \frac{1}{2} \end{bmatrix}$$

So:

$$\frac{\partial \varepsilon_{uu}}{\partial \mathbf{x}_1} = a(a\mathbf{x}_{10} + c\mathbf{x}_{20})^T \quad \frac{\partial \varepsilon_{vv}}{\partial \mathbf{x}_1} = b(b\mathbf{x}_{10} + d\mathbf{x}_{20})^T \quad \frac{\partial \varepsilon_{uv}}{\partial \mathbf{x}_1} = \frac{1}{2}a(b\mathbf{x}_{10} + d\mathbf{x}_{20})^T + \frac{1}{2}b(a\mathbf{x}_{10} + c\mathbf{x}_{20})^T$$

$$\frac{\partial \varepsilon_{uu}}{\partial \mathbf{x}_2} = c(a\mathbf{x}_{10} + c\mathbf{x}_{20})^T \quad \frac{\partial \varepsilon_{vv}}{\partial \mathbf{x}_2} = d(b\mathbf{x}_{10} + d\mathbf{x}_{20})^T \quad \frac{\partial \varepsilon_{uv}}{\partial \mathbf{x}_2} = \frac{1}{2}c(b\mathbf{x}_{10} + d\mathbf{x}_{20})^T + \frac{1}{2}d(a\mathbf{x}_{10} + c\mathbf{x}_{20})^T$$

# Forces

Together, we get:

$$\begin{aligned}
 \mathbf{f}_1 &= -A^{\text{ref}} \left( \frac{\partial W}{\partial \varepsilon_{uu}} \frac{\partial \varepsilon_{uu}}{\partial \mathbf{x}_1} + \frac{\partial W}{\partial \varepsilon_{vv}} \frac{\partial \varepsilon_{vv}}{\partial \mathbf{x}_1} + \frac{\partial W}{\partial \varepsilon_{uv}} \frac{\partial \varepsilon_{uv}}{\partial \mathbf{x}_1} \right)^T \\
 &= -A^{\text{ref}} \left( \frac{\partial W}{\partial \varepsilon_{uu}} a(\mathbf{ax}_{10} + c\mathbf{cx}_{20})^T + \frac{\partial W}{\partial \varepsilon_{vv}} b(b\mathbf{x}_{10} + d\mathbf{x}_{20})^T + \frac{\partial W}{\partial \varepsilon_{uv}} \frac{1}{2} a(b\mathbf{x}_{10} + d\mathbf{x}_{20})^T + \frac{\partial W}{\partial \varepsilon_{uv}} \frac{1}{2} b(a\mathbf{ax}_{10} + c\mathbf{cx}_{20})^T \right) \\
 &= -A^{\text{ref}} \left( \begin{bmatrix} a\mathbf{ax}_{10} + c\mathbf{cx}_{20} & b\mathbf{x}_{10} + d\mathbf{x}_{20} \end{bmatrix} \begin{bmatrix} \frac{\partial W}{\partial \varepsilon_{uu}} a + \frac{\partial W}{\partial \varepsilon_{uv}} \frac{1}{2} b \\ \frac{\partial W}{\partial \varepsilon_{uv}} \frac{1}{2} a + \frac{\partial W}{\partial \varepsilon_{vv}} b \end{bmatrix} \right) \\
 &= -A^{\text{ref}} \boxed{\begin{bmatrix} a\mathbf{ax}_{10} + c\mathbf{cx}_{20} & b\mathbf{x}_{10} + d\mathbf{x}_{20} \end{bmatrix}} \boxed{\begin{bmatrix} \frac{\partial W}{\partial \varepsilon_{uu}} & \frac{1}{2} \frac{\partial W}{\partial \varepsilon_{uv}} \\ 1 \frac{\partial W}{\partial \varepsilon_{uv}} & \frac{\partial W}{\partial \varepsilon_{vv}} \end{bmatrix}} \begin{bmatrix} a \\ b \end{bmatrix} = -A^{\text{ref}} \mathbf{FS} \begin{bmatrix} a \\ b \end{bmatrix}
 \end{aligned}$$

deformation gradient      Second Piola-Kirchhoff Stress

# Forces

In conclusion, we have:

$$\mathbf{f}_1 = -A^{\text{ref}} \mathbf{FS} \begin{bmatrix} a \\ b \end{bmatrix}$$

$$\mathbf{f}_2 = -A^{\text{ref}} \mathbf{FS} \begin{bmatrix} c \\ d \end{bmatrix}$$

$$[\mathbf{f}_1 \quad \mathbf{f}_2] = -A^{\text{ref}} \mathbf{FS} [\mathbf{X}_{10} \quad \mathbf{X}_{20}]^{-T}$$


# Implementations

- More details?
  - Volino et al. 2009. *A simple approach to nonlinear tensile stiffness for accurate cloth simulation.* TOG
  - Only talks about cloth (2D reference  $\rightarrow$  3D deformation)
- What about tetrahedron (3D reference  $\rightarrow$  3D deformation)?
  - Same idea, but everything is now in 3D.
  - Deformation gradient  $\mathbf{F} \in \mathbf{R}^{3 \times 3}$
  - Green strain  $\mathbf{G} \in \mathbf{R}^{3 \times 3}$
  - Stress tensor  $\mathbf{S} \in \mathbf{R}^{3 \times 3}$
  - Forces  $\mathbf{f}_i \in \mathbf{R}^3$

# Finite Volume Method

# Traction and Stress

First, let's consider traction  $\mathbf{t}$ : the internal force per unit length (area).



Total interface force:

$$\mathbf{f} = \oint_L \mathbf{t} dl$$

Stress tensor  $\boldsymbol{\sigma}$  (interface normal  $\rightarrow$  traction):


$$\mathbf{t} = \boldsymbol{\sigma}\mathbf{n}$$

So,

$$\mathbf{f} = \oint_L \boldsymbol{\sigma}\mathbf{n} dl$$

# The Finite Volume Method

FVM considers force calculation in an integration perspective, not a differentiation perspective.



Force contributed by an element:

$$\mathbf{f}_0 = \oint_L \boldsymbol{\sigma} \mathbf{n} dl$$

Since  $\boldsymbol{\sigma}$  is constant within the element,

$$\oint_L \boldsymbol{\sigma} \mathbf{n} dl + \oint_{L_{20}} \boldsymbol{\sigma} \mathbf{n} dl + \oint_{L_{10}} \boldsymbol{\sigma} \mathbf{n} dl = 0$$


(Divergence Theorem)

We know the force is:

$$\mathbf{f}_0 = - \oint_{L_{20}} \boldsymbol{\sigma} \mathbf{n}_{20} dl - \oint_{L_{10}} \boldsymbol{\sigma} \mathbf{n}_{10} dl = -\boldsymbol{\sigma} \left( \frac{\|\mathbf{x}_{20}\|}{2} \mathbf{n}_{20} + \frac{\|\mathbf{x}_{10}\|}{2} \mathbf{n}_{10} \right)$$

# The Finite Volume Method

In 3D, FVM works in the same way.




Force:


$$\begin{aligned}\mathbf{f}_0 &= - \oint_{\Omega} \sigma \mathbf{n} dA = -\sigma \left( \frac{A_{012}}{3} \mathbf{n}_{012} + \frac{A_{023}}{3} \mathbf{n}_{023} + \frac{A_{031}}{3} \mathbf{n}_{031} \right) \\ &= -\frac{\sigma}{3} \left( \frac{\|\mathbf{x}_{10} \times \mathbf{x}_{20}\|}{2} \frac{\mathbf{x}_{10} \times \mathbf{x}_{20}}{\|\mathbf{x}_{10} \times \mathbf{x}_{20}\|} + \frac{\|\mathbf{x}_{20} \times \mathbf{x}_{30}\|}{2} \frac{\mathbf{x}_{20} \times \mathbf{x}_{30}}{\|\mathbf{x}_{20} \times \mathbf{x}_{30}\|} \right. \\ &\quad \left. + \frac{\|\mathbf{x}_{30} \times \mathbf{x}_{10}\|}{2} \frac{\mathbf{x}_{30} \times \mathbf{x}_{10}}{\|\mathbf{x}_{30} \times \mathbf{x}_{10}\|} \right) \\ &= -\frac{\sigma}{6} (\mathbf{x}_{10} \times \mathbf{x}_{20} + \mathbf{x}_{20} \times \mathbf{x}_{30} + \mathbf{x}_{30} \times \mathbf{x}_{10})\end{aligned}$$

# This stress is not that stress

Although the use of stress tensor is the same: mapping from the interface normal to the traction, it can be defined by different configurations.



In FEM, we define the energy density  $W$  in the reference state. Therefore, this stress  $\mathbf{S}$  is a mapping from the normal  $\mathbf{N}$  to the traction  $\mathbf{T}$ , both in the reference state.




In FVM, we need  $\boldsymbol{\sigma}$  to convert the normal into  $\mathbf{t}$  for force calculation. Therefore, this stress assumes the normal  $\mathbf{n}$  and the traction  $\mathbf{t}$  are in the deformed state.

# Different Stresses

We can now have different stresses, serving the same purpose but in different forms.

Input Output	Interface normal $\mathbf{N}$ in the <i>reference</i> state (unformed)	Interface normal $\mathbf{n}$ in the <i>current</i> state (deformed)
Traction in the <i>reference</i> state (unformed)	Second Piola–Kirchhoff stress ( $\mathbf{S}$ )	
Traction in the <i>current</i> state (formed)	$\mathbf{P} = \mathbf{F}\mathbf{S}$	Cauchy Stress ( $\boldsymbol{\sigma}$ )

# Area Weighted Normals



Now let's figure out the relationship between  $A^{\text{ref}}\mathbf{N}$  and  $A\mathbf{n}$ , the two area weighted normals.

$$2A^{\text{ref}}\mathbf{N} = \mathbf{X}_{a0} \times \mathbf{X}_{b0}$$

$$2A\mathbf{n} = \mathbf{x}_{a0} \times \mathbf{x}_{b0} = \mathbf{F}\mathbf{X}_{a0} \times \mathbf{F}\mathbf{X}_{b0} = (\mathbf{U}\mathbf{D}\mathbf{V}^T\mathbf{X}_{a0}) \times (\mathbf{U}\mathbf{D}\mathbf{V}^T\mathbf{X}_{b0})$$

$$= \mathbf{U} ((\mathbf{D}\mathbf{V}^T\mathbf{X}_{a0}) \times (\mathbf{D}\mathbf{V}^T\mathbf{X}_{b0}))$$

$$= \mathbf{U} \begin{bmatrix} d_1 d_2 & & \\ & d_0 d_2 & \\ & & d_0 d_1 \end{bmatrix} ((\mathbf{V}^T\mathbf{X}_{a0}) \times (\mathbf{V}^T\mathbf{X}_{b0}))$$

$$= \mathbf{U} \begin{bmatrix} d_1 d_2 & & \\ & d_0 d_2 & \\ & & d_0 d_1 \end{bmatrix} \mathbf{V}^T(\mathbf{X}_{a0} \times \mathbf{X}_{b0}) = d_0 d_1 d_2 \mathbf{U} \begin{bmatrix} 1/d_0 & & \\ & 1/d_1 & \\ & & 1/d_2 \end{bmatrix} \mathbf{V}^T(\mathbf{X}_{a0} \times \mathbf{X}_{b0})$$

$$= \det(\mathbf{F}) \mathbf{F}^{-T} (\mathbf{X}_{a0} \times \mathbf{X}_{b0}) = \det(\mathbf{F}) \mathbf{F}^{-T} (2A^{\text{ref}}\mathbf{N})$$

# Different Stresses

Now we know:  $A\mathbf{n} = \det(\mathbf{F})\mathbf{F}^{-T}(A^{\text{ref}}\mathbf{N})$ .

We also know the force can be calculated using two different stresses:

$$\mathbf{f} = -\frac{1}{3}\sum A^{\text{ref}}\mathbf{P}\mathbf{N} = -\frac{1}{3}\sum A\boldsymbol{\sigma}\mathbf{n}$$



Therefore, we get:

$$\mathbf{P}(A^{\text{ref}}\mathbf{N}) = \boldsymbol{\sigma}\det(\mathbf{F})\mathbf{F}^{-T}(A^{\text{ref}}\mathbf{N})$$

$$\det^{-1}(\mathbf{F})\mathbf{P}\mathbf{F}^T = \boldsymbol{\sigma}$$


# Different Stresses

We can now have different stresses, serving the same purpose but in different forms.

Input Output	Interface normal $\mathbf{N}$ in the <i>reference</i> state (unformed)	Interface normal $\mathbf{n}$ in the <i>current</i> state (deformed)
Traction in the <i>reference</i> state (unformed)	Second Piola–Kirchhoff stress ( $\mathbf{S}$ )  $\mathbf{P} = \mathbf{F}\mathbf{S}$	 $\boldsymbol{\sigma} = \det^{-1}(\mathbf{F})\mathbf{F}\mathbf{S}\mathbf{F}^T$
Traction in the <i>current</i> state (formed)	 $\mathbf{P} = \det^{-1}(\mathbf{F})\mathbf{F}\boldsymbol{\sigma}\mathbf{F}^T$	Cauchy Stress ( $\boldsymbol{\sigma}$ )  $\boldsymbol{\sigma} = \det^{-1}(\mathbf{F})\mathbf{P}\mathbf{F}^T$

# The Finite Volume Method

The previous analysis suggests we can use reference normals instead.




$$\begin{aligned}\mathbf{f}_1 &= -\frac{\sigma}{6}(\mathbf{x}_{01} \times \mathbf{x}_{21} + \mathbf{x}_{21} \times \mathbf{x}_{31} + \mathbf{x}_{31} \times \mathbf{x}_{01}) \\ &= -\frac{P}{6}(\mathbf{X}_{01} \times \mathbf{X}_{21} + \mathbf{X}_{21} \times \mathbf{X}_{31} + \mathbf{X}_{31} \times \mathbf{X}_{01}) \\ &\quad \text{Constant, can be precomputed} \\ &= -\frac{FS}{6}\mathbf{b}_1\end{aligned}$$

Second Piola–Kirchhoff stress:

$$\mathbf{S} = \frac{\partial W}{\partial \mathbf{G}}, \text{ as in previous FEM formulation}$$

# The Finite Volume Method



Think about more about  $\mathbf{b}_1 \dots$

$$\begin{aligned}\mathbf{x}_{10}^T \mathbf{b}_1 &= \mathbf{x}_{10}^T (\mathbf{x}_{01} \times \mathbf{x}_{21} + \mathbf{x}_{21} \times \mathbf{x}_{31} + \mathbf{x}_{31} \times \mathbf{x}_{01}) = \mathbf{x}_{10}^T (\mathbf{x}_{21} \times \mathbf{x}_{31}) \\ &= \mathbf{x}_{01}^T (\mathbf{x}_{31} \times \mathbf{x}_{21}) = 6Vol\end{aligned}$$

Meanwhile,

$$\begin{aligned}\mathbf{x}_{20}^T \mathbf{b}_1 &= \mathbf{x}_{20}^T (\mathbf{x}_{01} \times \mathbf{x}_{21} + \mathbf{x}_{21} \times \mathbf{x}_{31} + \mathbf{x}_{31} \times \mathbf{x}_{01}) \\ &= \mathbf{x}_{20}^T (\mathbf{x}_{20} \times \mathbf{x}_{10} + \mathbf{x}_{20} \times \mathbf{x}_{31}) = 0\end{aligned}$$

$$\begin{aligned}\mathbf{x}_{30}^T \mathbf{b}_1 &= \mathbf{x}_{30}^T (\mathbf{x}_{01} \times \mathbf{x}_{21} + \mathbf{x}_{21} \times \mathbf{x}_{31} + \mathbf{x}_{31} \times \mathbf{x}_{01}) \\ &= \mathbf{x}_{30}^T (\mathbf{x}_{21} \times \mathbf{x}_{30} + \mathbf{x}_{10} \times \mathbf{x}_{30}) = 0\end{aligned}$$


# Therefore,

We get:

$$[\mathbf{X}_{10} \quad \mathbf{X}_{20} \quad \mathbf{X}_{30}]^T \mathbf{b}_1 = [\mathbf{X}_{10} \quad \mathbf{X}_{20} \quad \mathbf{X}_{30}]^T (\mathbf{X}_{01} \times \mathbf{X}_{21} + \mathbf{X}_{21} \times \mathbf{X}_{31} + \mathbf{X}_{31} \times \mathbf{X}_{01}) = \begin{bmatrix} 6Vol \\ 0 \\ 0 \end{bmatrix}$$


$$[\mathbf{X}_{10} \quad \mathbf{X}_{20} \quad \mathbf{X}_{30}]^T \mathbf{b}_2 = \begin{bmatrix} 0 \\ 6Vol \\ 0 \end{bmatrix}$$

$$[\mathbf{X}_{10} \quad \mathbf{X}_{20} \quad \mathbf{X}_{30}]^T \mathbf{b}_3 = \begin{bmatrix} 0 \\ 0 \\ 6Vol \end{bmatrix}$$



$$\begin{aligned} [\mathbf{b}_1 \quad \mathbf{b}_2 \quad \mathbf{b}_3] &= 6Vol [\mathbf{X}_{10} \quad \mathbf{X}_{20} \quad \mathbf{X}_{30}]^{-T} \\ &= \frac{1}{\det([\mathbf{X}_{10} \quad \mathbf{X}_{20} \quad \mathbf{X}_{30}]^{-1})} [\mathbf{X}_{10} \quad \mathbf{X}_{20} \quad \mathbf{X}_{30}]^{-T} \end{aligned}$$

# A Quick Summary



# After-Class Reading

Teran et al. 2003. *Finite Volume Methods for the Simulation of Skeleton Muscles.* SCA.

Eurographics/SIGGRAPH Symposium on Computer Animation (2003)  
D. Breen, M. Lin (Editors)

## Finite Volume Methods for the Simulation of Skeletal Muscle

J. Teran,<sup>1</sup> S. Bleeker,<sup>2</sup> V. Ng Thow Hing,<sup>3</sup> and R. Fedkiw<sup>4</sup>

<sup>1</sup> Stanford University, jteran@stanford.edu  
<sup>2</sup> Stanford University, ssbleeker@stanford.edu  
<sup>3</sup> Honda Research Institute USA, vng@honda-ri.com  
<sup>4</sup> Stanford University, fedkiw@cs.stanford.edu

---

### Abstract

Since it relies on a geometrical rather than a variational framework, many find the finite volume method (FVM) more intuitive than the finite element method (FEM). We show that the FVM allows one to interpret the stress inside a tetrahedron as a simple “multidimensional force” pushing on each face. Moreover, this interpretation leads to a heuristic method for calculating the force on each node, which is as simple to implement and comprehend as masses and springs. In the finite volume spirit, we also present a geometric rather than interpolating function definition of strain. We use the FVM and a quasi-incompressible, transversely isotropic, hyperelastic constitutive model to simulate contracting muscle tissue. B-spline solids are used to model fiber directions, and the muscle activation levels are derived from key frame animations.

Categories and Subject Descriptors (according to ACM CCS): I.3.7 [Computer Graphics]: Animation; I.3.5 [Computer Graphics]: Physically based modeling

---

### 1. Introduction

The pioneering work of Lasseter<sup>18</sup> on applying the principles of traditional animation to computer graphics emphasizes squash and stretch, timing, anticipation, follow through, arcs, and secondary action which all appear to the use of physics based animation techniques. A variety of authors have worked to incorporate ideas such as these into their animations, e.g. Neff and Flume<sup>23</sup> incorporated tension and relaxation into the animation of an articulated skeleton. Moreover, when considering the difficulties, such as collapsing elbows<sup>19</sup>, associated with applying free form deformations<sup>28</sup> or related techniques to shape animation, one draws the conclusion that physics based simulation of muscle and fatty tissue should be the ultimate goal. Unfortunately, progress toward this goal has been rather slow due to the high cost of FEM and the poor quality of volumetric mass-spring models.

Significant effort has been placed into accelerating FEM calculations including recent approaches that precompute and cache various quantities<sup>23</sup>, modal analysis<sup>16</sup>, and approximations to local rotations<sup>22</sup>. In spite of significant effort into alternative (and related) methods for the robust simulation of deformable bodies, FVM has been largely ignored. Two aspects of FVM make it attractive. First, it has a firm basis in geometry as opposed to the FEM variational setting. This not only increases the level of intuition and the simplicity of implementation, but also increases the likelihood of aggressive (but robust) optimization and control. Second, there is a large community of researchers using these methods to model solid materials subject to very high deformations. For example, Caramana and Shashkov<sup>1</sup> used the FVM with subcell pressures to eliminate the artificial hour-glass type motions that can arise in materials with strongly diagonally dominant stress tensors, such as incompressible biological materials.

FEM has many attractive features that make it appealing to the engineering community, e.g. a solid theoretical framework for proving theorems and the ability to extend it to higher order accuracy. However, in graphics, visual realism is more important than the convergence rate, and thus the focus is on simulating a large number of cheap first order accurate elements rather than fewer more expensive higher order accurate elements. In fact, the same can be said for many engineering applications where quasi-static and other

© The Eurographics Association 2003.

# After-Class Reading (Optional)

Volino et al. 2009. *A Simple Approach to Nonlinear Tensile Stiffness for Accurate Cloth Simulation*. TOG.



## A simple approach to nonlinear tensile stiffness for accurate cloth simulation

Pascal Volino, Nadia Magnenat-Thalmann, François Faure

### ► To cite this version:

Pascal Volino, Nadia Magnenat-Thalmann, François Faure. A simple approach to nonlinear tensile stiffness for accurate cloth simulation. ACM Transactions on Graphics, Association for Computing Machinery, 2009, 28 (4), pp.Article No. 105. 10.1145/1559755.1559762 . inria-00394466

HAL Id: inria-00394466

<https://hal.inria.fr/inria-00394466>

Submitted on 2 Dec 2009

HAL is a multi-disciplinary open access archive for the deposit and dissemination of scientific research documents, whether they are published or not. The documents may come from teaching and research institutions in France or abroad, or from public or private research centers.

L'archive ouverte pluridisciplinaire HAL, est destinée au dépôt et à la diffusion de documents scientifiques de niveau recherche, publiés ou non, émanant des établissements d'enseignement et de recherche français ou étrangers, des laboratoires publics ou privés.

# Hyperelastic Models


# First Piola–Kirchhoff stress

We treat the first Piola–Kirchhoff stress tensor  $\mathbf{P}$  as a function of deformation gradient  $\mathbf{F}$ :

$$\mathbf{f}_0 = -\frac{\mathbf{P}(\mathbf{F})}{6} (\mathbf{X}_{10} \times \mathbf{X}_{20} + \mathbf{X}_{20} \times \mathbf{X}_{30} + \mathbf{X}_{30} \times \mathbf{X}_{10})$$


It converts an interface normal  $\mathbf{N}$  in the reference state to a traction  $\mathbf{t}$  in the deformed state.

$$\mathbf{t} = \mathbf{P}(\mathbf{U}\mathbf{D}\mathbf{V}^T)\mathbf{N}$$



# Rotation-Invariance

The stress tensor  $\mathbf{P}$  is rotation-invariant to  $\mathbf{U}$ :




$$\mathbf{t} = \mathbf{P}(\mathbf{U}\mathbf{D}\mathbf{V}^T)\mathbf{N}$$

$$\mathbf{P}(\mathbf{U}\mathbf{D}\mathbf{V}^T) = \mathbf{U}\mathbf{P}(\mathbf{D}\mathbf{V}^T)$$

# Isotropic Materials

The stress tensor  $\mathbf{P}$  is rotation-invariant to  $\mathbf{U}$ :



$$\mathbf{t} = \mathbf{P}(\mathbf{D}\mathbf{V}^T)\mathbf{N}$$

$$\mathbf{t} = \mathbf{P}(\mathbf{D})\mathbf{V}^T\mathbf{N}$$

$$\boxed{\mathbf{P}(\mathbf{D}\mathbf{V}^T) = \mathbf{P}(\mathbf{D})\mathbf{V}^T}$$

# Isotropic Materials

Together, we claim:  $\mathbf{P}(\mathbf{F}) = \mathbf{P}(\mathbf{UDV}^T) = \mathbf{U}\underline{\mathbf{P}(\lambda_0, \lambda_1, \lambda_2)}\mathbf{V}^T$

Principal stretches: the singular values of  $\mathbf{F}$

In many literatures, people parameterize  $\mathbf{P}(I_{\mathbf{C}}, II_{\mathbf{C}}, III_{\mathbf{C}})$  by principal invariants, for:

$$I_{\mathbf{C}} = \text{trace}(\mathbf{C}) = \lambda_0^2 + \lambda_1^2 + \lambda_2^2$$

$$III_{\mathbf{C}} = \det(\mathbf{C}^2) = \lambda_0^4 + \lambda_1^4 + \lambda_2^4$$

$$II_{\mathbf{C}} = \frac{1}{2}(\text{trace}^2(\mathbf{C}) - \text{trace}(\mathbf{C}^2)) = \lambda_0^2\lambda_1^2 + \lambda_0^2\lambda_2^2 + \lambda_1^2\lambda_2^2$$

$\mathbf{C} = \mathbf{U}^T \mathbf{U}$  is the right Cauchy-Green deformation tensor.

# Isotropic Models

The Saint Venant-Kirchhoff model (StVK):

$$W = \frac{s_0}{2}(I_C - 3)^2 + \frac{s_1}{4}(II_C - 2I_C + 3)$$

The neo-Hookean model:

$$W = s_0 \left( III_C^{-1/3} I_C - 3 \right) + s_1 \left( III_C^{-1/2} - 1 \right)$$

Against shearing      Against bulky change (volume change)

The Mooney-Rivlin model:

$$W = s_0 \left( III_C^{-1/3} I_C - 3 \right) + s_1 \left( III_C^{-1/2} - 1 \right) + s_2 \left( \frac{1}{2} III_C^{-2/3} (I_C^2 - II_C) - 3 \right)$$

The Fung model:

$$W = s_0 \left( III_C^{-1/3} I_C - 3 \right) + s_1 \left( III_C^{-1/2} - 1 \right) + s_2 (e^{s_3 (III_C^{-1/3} I_C - 3)} - 1)$$

# Isotropic Materials


Anyway, we still use the principal stretches for computation:

$$\mathbf{P}(\lambda_0, \lambda_1, \lambda_2) = \begin{bmatrix} \frac{\partial W}{\partial \lambda_0} \\ \frac{\partial W}{\partial \lambda_1} \\ \frac{\partial W}{\partial \lambda_2} \end{bmatrix}$$


And we compute the first Piola-Kirchhoff stress as:

$$\mathbf{P} = \mathbf{U}\mathbf{P}(\lambda_0, \lambda_1, \lambda_2)\mathbf{V}^T$$


# A Quick Summary (cont.)




# The Limitation of StVK



Irving et al. 2004. *Invertible Finite Elements For Robust Simulation of Large Deformation. SCA*



# Model Behaviors



**Figure 11:** The force-displacement curves generated by the box example. These curves are consistent with the stress-strain relationships of the underlying hyperelastic models.

# A Summary For the Day

- FEM uses the derivates of the strain energy function to obtain the force.
- FVM uses the integral of the interface traction to obtain the force.
- The two approaches lead to the identical outcome, in different formulations
- Hyperelastic models define the strain energy function by principal stretches, i.e., the singular values of the deformation gradient.
- For isotropic materials, we can calculate the stress through diagonalization.