## Killer Yeast Vs. Sensitive Yeast

Evan Cummings Intizor Aliyorov Malachi J. Cryder

MATH 445 - Statistical, Dynamical, and Computational Modeling

December 4, 2013

### Proposal

The differential equation we may use for modeling the growth of yeast is the same as that used for bacterial growth in a chemostat:

$$\begin{split} \frac{dN}{dt} &= k(C)N - \frac{FN}{V}, \\ \frac{dC}{dt} &= -\alpha k(C)N - \frac{FC}{V} + \frac{FC_0}{V}, \end{split}$$

with initial conditions  $C(0) = C_i$  and  $N(0) = N_i$ , N is the unitless optical density of yeast in the chamber, C is the unitless optical density of nutrient in the chamber,  $C_0$  is the unitless optical density of nutrient in the reservoir, F is the in/out volume flow rate with units volume/time, V is the volume of the chamber,  $\alpha$  is a unitless inverse of the yield constant, and k(C) is the reproduction rate for yeast in units 1/time with possible formula chosen such that  $\lim_{C\to\infty} = k_{max}$ , and  $k_{max}$  represents the maximum possible reproduction rate:

$$k(C) = \frac{k_{max}C}{C_n + C}.$$

where  $C_n$  is chosen such that  $k(C_n) = k_{max}/2$ . Because the concentration in the tank C(t) is related to the concentration in the reservoir by  $C(t) \leq C_0$ ,  $C_0$  may be chosen sufficiently small such that

$$k(C) = \frac{k_{max}C}{C_n + C} \approx \frac{k_{max}C}{C_n} = KC,$$

where K has units 1/time. The equations we need to solve then become

$$\frac{dN}{dt} = KCN - \frac{FN}{V},\tag{1}$$

$$\frac{dC}{dt} = -\alpha KCN - \frac{FC}{V} + \frac{FC_0}{V}.$$
 (2)

The quantitative measurement for fitness is a unitless measurement of optical density at steady state (N) at a given flow rate (F) in volumes/hr. In order to find the steady states, we have to find

the intersections of the null-clines at equilibrium points  $(\bar{N}, \bar{C})$ , i.e.  $d\bar{N}/dt = 0$  and  $d\bar{C}/dt = 0$ :

$$\begin{split} \frac{dN(\bar{N},\bar{C})}{dt} &= K\bar{C}\bar{N} - \frac{F\bar{N}}{V}, \\ &= \bar{N}\left(K\bar{C} - \frac{F}{V}\right) = 0, \end{split}$$

which is zero for  $\bar{N}=0$  or  $K\bar{C}=F/V$ . Solving the other equation gives us the other steady-states:

$$\frac{dC(\bar{N},\bar{C})}{dt} = -\alpha K\bar{C}\bar{N} - \frac{F\bar{C}}{V} + \frac{FC_0}{V} = 0,$$

which is zero for  $\alpha K \bar{C} \bar{N} + \frac{F\bar{C}}{V} = \frac{FC_0}{V}$ .

In order to evaluate these null-clines, we need to evaluate the non-trivial cases, here for  $\dot{N}=0,$ 

$$K\bar{C} = \frac{F}{V}$$

$$\implies \bar{C} = \frac{F}{VK}.$$
(3)

Likewise, for  $\dot{C} = 0$ ,

$$\alpha K \bar{C} \bar{N} + \frac{F \bar{C}}{V} = \frac{F C_0}{V}$$

$$\implies \bar{N} = \frac{F C_0}{V \alpha K \bar{C}} - \frac{F}{V \alpha K} = \frac{F}{V \alpha K} \left(\frac{C_0}{\bar{C}} - 1\right). \tag{4}$$

 $ar{
ho} = rac{F}{Vlpha K} \left(rac{C_0}{C} - 1
ight)$ 

Figure 1: The  $\dot{C}=0$  nullcline (red) intersecting with the  $\dot{N}=0$  nullcline (black). The trivial steady-state (0,0) and non-trivial steady-state  $(\bar{N},\bar{C})$  are shown as red dots.

By placing Eq. (3) inside Eq. (4), we can find the intersection of the null-clines:

$$\bar{N}(\bar{C}) = \frac{FC_0}{V\alpha K\bar{C}} - \frac{F}{V\alpha K} \\
= \frac{FC_0}{V\alpha K\frac{F}{VK}} - \frac{F}{V\alpha K} \\
= \frac{C_0}{\alpha} - \frac{F}{V\alpha K} = \frac{1}{\alpha} \left( C_0 - \frac{F}{VK} \right). \quad (5)$$

The unknown parameters in Eq (5) are  $\alpha$  and K. We can find these parameters by fitting Eq (5) to the data by non-linear least squares fitting  $\bar{N}_i$  at  $F_i$  for  $i = 1, \ldots, n$ , where n is the number of observations.

After we obtain estimates for  $\alpha$  and K (and hence  $\bar{C}$ ), we can model a "what if" scenario whereby we place both species of yeast, sensitive and killer, into one chemostat.

The data we are provided with include two sets of two separate runs, along with the concentration of nutrient in the reservoir,  $C_0 = 0.02$ :

# 1 K1 Run

#### Vessel One:

Volumes/Hr	0.028	0.099	0.142	0.207	0.269	0.287	0.352	0.403
Optical Density at Steady State	0.144	0.151	0.099	0.069	0.045	0.02	0.003	0

### Vessel Two:

Volumes/Hr	0.054	0.11	0.141	0.199	0.257	0.296	0.348	0.397	0.41
Optical Density at Steady State	0.164	0.151	0.11	0.092	0.072	0.023	0.006	0.002	0.004


### 2 Sensitive Run

### Vessel One:

Volumes/Hr	0.041	0.099	0.167	0.223	0.266	0.328	0.356	0.401	0.462
Optical Density at Steady State	0.54	0.494	0.459	0.395	0.229	0.019	0.006	0.003	0

# Vessel Two:

		0.0571					
	Optical Density at Steady State	0.385	0.456	0.363	0.197	0.044	0.004



The data provided does not include the volume of the chamber, V. In order to solve Eq. (5), this quantity is needed. Here we have dimensional analysis of the problem:

$$\begin{split} \frac{dN}{dt} &= KCN - \frac{FN}{V} \\ &\equiv \left[\frac{1}{\text{time}}\right] \equiv \left[\frac{1}{\text{time}} - \frac{\text{volume}}{\text{time}} \cdot \frac{1}{\text{volume}}\right] \equiv \left[\frac{1}{\text{time}}\right], \\ \frac{dC}{dt} &= -\alpha KCN - \frac{FC}{V} + \frac{FC_0}{V} \\ &\equiv \left[\frac{1}{\text{time}}\right] \equiv \left[-\frac{1}{\text{time}} - \frac{\text{volume}}{\text{time}} \cdot \frac{1}{\text{volume}} + \frac{\text{volume}}{\text{time}} \cdot \frac{1}{\text{volume}}\right] \equiv \left[\frac{1}{\text{time}}\right]. \end{split}$$