## **Emacs support for the Erlang Programming Language**

<u>Description</u>	<u>Keystroke</u>	Function	Note Note			
Erlang Support	Emacs supports Erlang via the					
See also: • Erlang Reference	<ul> <li>▶ The <u>erlang.el</u> external package (see <u>erlang.el source</u>), part of <u>OTP</u></li></ul>					
Concise Guide To Erlang			ith pel-use-erlang-is. Uses the erlang is Erlang LSP server. Integrates with:			
about-erlang	• Will Helm by using helm-lsr	·	s with <b>pel-use-helm-lsp</b> .    Vel   Vel			
<ul> <li>Developing Erlang</li> <li>Code with PEL</li> </ul>	• <b>p</b> treemacs by using lsp-	treemacs <a>d</a> PEL activates	s with pel-use-treemacs and pel-use-lsp-treemacs.			
set PEL Erlang environment	• origami by using Isp-or		s with pel-use-lsp-origami.			
			re mainly been replaced by EDTS and needs maintenance. PEL does not support it.			
• <u>∑ Hide/Show</u> • <u>∑ Text Modes</u>	The iedit external package	· · · · · _ —	it with pel-use-iedit.			
• <u>National Highlight</u>			s it with <b>pel-use-smart-dash</b> . erlang-mode is in <b>pel-modes-activating-smart-dash-mode</b> .			
• <u>∑ Inserting Text</u>	-		s it with pel-use-smartparens. Add it to pel-erlang-activates-minor-modes.			
• <u>∑ Customize</u>	Customization:	to activate reatures in Enair	g via <b>pel-activates-global-minor-mode</b> : <u>show-paren-mode</u>			
	_		RET to open the specific customization group or one of the following key sequences.			
	• pel-pkg-for-erlang: to activate pel-use-erlang: use <f11> SPC e <f2>, or <f12> <f2> from an Erlang buffer. This has sub-group: see pel-erlang-ide group to activate EDTS and LSP.</f2></f12></f2></f11>					
		when <b>pel-use-erlang</b> is on, when <b>pel-use-edts</b> is on,	use <f11> SPC e <f3> 1 use <f11> SPC e <f3> 3</f3></f11></f3></f11>			
	• Isp-erlang: v	vhen <b>pel-use-erlang-ls</b> is o	n, use <f11> SPC e L <f3> 1</f3></f11>			
		•	n, use <f11> SPC e L <f3> 2 control Erlang editing. Only some of them are described here. Use Emacs for the complete list.</f3></f11>			
⊌ >>			the Erlang shell from echoing every command. ivation of local minor modes in erlang-mode buffers, eg. smart-dash-mode.			
Identify minor modes to	pel-erlang-environment gr	roup:				
activate automatically in erlang-mode buffers	man6 which contain Erla	ng man files. If this is set PE	It directory of Erlang man directory. The man directory should hold the man1, man3, man4 and EL sets (override) the <u>erlang.el</u> <u>erlang-root-dir</u> user-option value with it which activates the			
		iles. Without PEL or if pel-edentifies the directory where	rlang-man-parent-rootdir is nil, you must set the erlang-root-dir user-option yourself.  Erlang binaries are stored.			
	<ul> <li>pel-erlang-version-dete</li> <li>pel-erlang-code-style grown</li> </ul>		mechanism to detect Erlang/OTP version. By default it uses an Erlang script provided with PEL.			
	pel-erlang-fill-columi	n : column where line-wrapp	oing occurs: maximum line length (defaults to 100). You can change the value or set it nil.			
			rlang-mode buffers use the Emacs fill-column value like other major modes. parators are used in Erlang code templates (see the Insert Erlang Code Template section below),			
			nether secondary separator lines are inserted by some Erlang code templates, automatically updated time stamps are inserted in Erlang source code file header blocks.			
• <u>∑ Speedbar</u>			g files to show the list of functions.			
Open this PDF file.	• <f11> SPC e <f1></f1></f11>	(pel-help-pdf &optional	Open the <u>\$1 - Erlang</u> local PDF. If the prefix argument (like <b>C-u</b> or <b>M</b> ) is used, then it opens			
See also: <u>▼ Help/Info</u>	• <f11> SPC e w <f1> • <f11> SPC e L <f1></f1></f11></f1></f11>	OPEN-WEB-PAGE)	the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.			
	• <f12> <f1></f1></f12>		SPC e are available from any major modes.			
	• <f12> w <f1> • <f12> L <f1></f1></f12></f1></f12>		Key sequences that start with <f12> are only available in erlang-mode buffers.  The <f12> keys sequences are mirrored by the <m-f12> key sequence for convenience.</m-f12></f12></f12>			
T O DEL Educa		(pel-customize-pel				
∑ Customize PEL Erlang support	<f11> SPC e <f2></f2></f11>	&optional OTHER-	Customize PEL Erlang support: access PEL user-options to activate Erlang support packages.  • If OTHER-WINDOW is non-nil (use <b>C</b> - <b>u</b> ), display in another window.			
	<f12> <f2></f2></f12>	WINDOW)				
∑ Customize Emacs Erlang support	<f11> SPC e <f3></f3></f11>	(pel-customize-library &optional OTHER-	Customize Emacs Erlang support: erlang, erldoc, edts, auto-highlight-symbol, lsp-mode, lsp-ui, lsp-treemacs.			
	<f12> <f3></f3></f12>	WINDOW)	If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.			
∑ Customize PEL LSP for Erlang support	<f11> SPC e L <f2></f2></f11>	(pel-customize-pel &optional OTHER-	<ul> <li>Customize PEL LSP Erlang support</li> <li>If OTHER-WINDOW is non-nil (use C-u), display in another window.</li> </ul>			
Tor Enaing Support	<f12> L <f2></f2></f12>	WINDOW)	☑ This is available when <b>pel-use-erlang-is</b> is turned on.			
∑ Customize Emacs	<f11> SPC e L <f3></f3></f11>	(pel-customize-library	Customize Emacs LSP Erlang support: Isp-erlang, Isp-mode, Isp-ui, helm-Isp, Isp-ivy, Isp-			
LSP for Erlang support	<f12> L <f3></f3></f12>	&optional OTHER- WINDOW)	origami, Isp-treemacs.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.			
		,	This is available when <b>pel-use-erlang-is</b> is turned on.			
∑ Customize PEL LSP	<f11> SPC e w <f2></f2></f11>	(pel-customize-pel	Customize PEL LSP Erlang support			
Window for Erlang support	<f12> w <f2></f2></f12>	&optional OTHER- WINDOW)	• If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.			
		,	This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on.			
∑ Customize Emacs LSP Window for Erlang	<f11> SPC e w <f3></f3></f11>	(pel-customize-library &optional OTHER-	<ul> <li>Customize Emacs LSP Erlang support: Isp-treemacs, treemacs</li> <li>If OTHER-WINDOW is non-nil (use C-u), display in another window.</li> </ul>			
support	<f12> w <f3></f3></f12>	WINDOW)	This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on.			
<b>Environment Help</b>	Use the following command to	verify your Erlang environn	nent.			
Erlang Mode version	<f11> SPC e ?</f11>	(pel-show-erlang-	Display the following information in the minibuffer.			
		version)				
	<f12> ?</f12>	1	favailable Erlang system, of <u>erlang.el</u> , of <u>erlang_ls</u> (if available), values of erlang-root-dir and pel			
			potdir. For more information see set PEL Erlang environment.			
Syntax Highlighting	Erlang code syntax highlightin	g has 4 levels and can be tu	urned off via Erlang menu: <f10> to access the menu &amp; select Erlang, then Syntax Highlighting.</f10>			
Edit Erlang Code	The following commands help	edit Erlang code.				
Create additional	C-c C-j	(erlang-generate-new-	Create additional Erlang clause header.			
clause	_	clause)	Parses the source file for the name of the current Erlang function. Create the header containing the name, a pair of parentheses, and an arrow. The space between the function			
			name and the first parenthesis is preserved. The point is placed between the parentheses.			
Clone clause	С-с С-у	(erlang-clone-	Insert, at the point, the argument list of the previous clause.			
arguments		arguments)	<ul> <li>Copy the function arguments of the preceding Erlang clause. This command is useful when defining a new clause with almost the same argument as the preceding.</li> </ul>			
			The mark is set at the beginning of the inserted text, the point at the end.			
Align arrows inside region	C-c C-a	(erlang-align-arrows START END)	Align arrows ("->") in <b>function clauses</b> inside marked region or in the current function.  • <b>With a prefix argument</b> , aligns <b>all arrows</b> in the region (or from beginning of buffer up to			
			point), not just those in function clauses.			
		Before: sum(L) -> sum(L, 0).	After: sum(L) -> sum(L, 0).			
		sum([H T], Sum) -> sum sum([], Sum) -> Sum.				
		, , ,				

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Electric Keys	The following keys have "elect	ric" behaviour and perform	special editing tasks to help edit Erlang source code.	
Electric comma	,	(erlang-electric-comma &optional ARG)	Insert a comma character and possibly a new indented line.	
		I comma when supplied with	iterion, when fulfilled a newline is inserted and the next line is indented.  In a numerical arg, point is inside string or comment, or when there are non-whitespace characters	
Electric semicolon	;	(erlang-electric- semicolon &optional ARG)	Insert a semicolon character and possibly a prototype for the next line.	
	line is inserted. Normally the The variable 'erlang-electric	e prototype consists of " ->' -semicolon-insert-blank-line I semicolon when supplied v	a criterion, when fulfilled a newline is inserted, the next line is indented and a prototype for the next ". Should the semicolon end the clause a new clause header is generated. se' controls the number of blank lines inserted between the current line and new function header. with a numerical arg, point is inside string or comment, or when there are non-whitespace	
Electric > (for the end of arrow)	>	(erlang-electric-gt &optional ARG)	Insert a greater-than sign, and optionally insert a new line and indent.	
Erlang Comments Comments @ Erlang Programming Rules & Conventions See also: Comments	% - Single percent     %% - Two percent c     %%% - Three percent The location of the comment c	t characters for comments lo characters are used for comments characters are used to des	wises the following conventions: ocated toward the end of a line of code ments starting at indentation level. cribe modules and are always placed in the first column by the comment-column variable. Set it with comment-set-column, bound to C-x;	
• PEL extension of	M-;	(comment-dwim ARG)	Comment line or region with % or %% style comments depending on the location in the buffer.	
comment-dwim specialized for Erlang. Automatically uses the		(pel-erlang-comment- dwim &optional ARG)	Does the same but adds ability to insert <b>%%%</b> comments. It does that on the very first line in the buffer and lines that follow a line that starts with <b>%%%</b> .	
%%% comment when appropriate.  ★★  Note: • M-; works much	With marked un-commenter     With marked commented re     To force insert %%% comm	On first em On line wit d region: Comment region gion: Un-comments the ent style: type M-3 M-; T	e region. The M-3 prefix identifies 3 % characters to insert. You can use another number.	
better than C-c C-c and C-c C-u			However PEL uses M-1 for something else. s indent-for-comment if nothing is marked.	
<ul> <li>PEL maps M-; to pel-erlang-comment- dwim which works even better.</li> </ul>	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region.  • With just C-u prefix arg, uncomment each line in region BEG END.  • Numeric prefix ARG means use ARG comment characters.  • If ARG is negative, delete that many comment characters instead.	
See also: <u><b>▼ Comments</b></u>	<ul> <li>The comment start is identified by 'comment-start' and 'comment-padding'; the comment end by 'comment-end' and 'comment-padding'.</li> <li>By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'.</li> </ul>			
Un-comment region	С-с С-и	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region. The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.	
Toggle display of comments in buffer or active region See also: <u>Comments</u>	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer.  • If the region is active, then toggle comments in the region. Otherwise, in the whole buffer.  • Requires the <a href="https://hide-commt.el">hide-commt.el</a> package  • PEL activates it with <a href="pel-use-hide-commt">pel-use-hide-commt</a>	
Filling Text See also: Filling/Justification	<ul> <li>Text wrapping and filling applies to all text in the Erlang buffer: code and comment. The auto-fill command will automatically wraps code and comments</li> <li>Filling Erlang code does not work as it treats code as normal text. But filling comment paragraphs is useful.</li> <li>The fill-column variable controls where text wraps.</li> <li>pel-show-fill-column <f11> t f ? shows its value. Use set-fill-column (C-x f) to set it. Toggle a vertical line that shows it with <f11> 8.</f11></f11></li> </ul>			
Fill current paragraph	• M-q • <f11> t f p</f11>	(fill-paragraph &optional JUSTIFY REGION)	Fill multi-line comment at or after point.  • To justify as well: C-u M-q  • In auto fill mode the text filling is done at the end of the line.	
Indentation			the CC-Mode logic and provided commands listed below. ed at the end of this list. They are also listed in the <u>Indentation</u> table.	
Indent current line or region	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	Indent active region, current line, or block starting on this line.	
See also: <u><b>∑</b> Indentation</u>	Access its custom group     Note that the erlang el log     Behaviour depends on synt     With syntactic-indentation of	buffer using <f12> <f3> gic doubles the indentation lactic-indentation mode (ena</f3></f12>	-level variable from erlang.el. Its default is 4.  1 or <f11> SPC e <f3> 1. Or use <f11> <f2> g erlang RET.  label inside funs. See this S.O. discussion on that.  bled by default but can be toggled on/off with the <f12> M-i key):  indent the region.</f12></f2></f11></f3></f11>	
	Otherwise reindent just the This might seem strang of the current line or every With syntactic-indentation of the current line or every the With syntactic-indentation of the C-u - <a href="tab">- </a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a>			

See also:  ■ Notice the 3 sets of commands:  ■ Navigation  ■ Moving by Defuns  ■ Moving by Defuns  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■ Comparison  ■ Comparison  ■ Comparison  ■ Notice the 3 sets of commands:  ■ Comparison  ■	<u>N</u>	Function	<u>Keystroke</u>	Description
• to start of function  • Go backward to beginning of the previous function of previous function as the property of previous function  • Go forward to beginning of next function of the previous function of function of previous function of fun	The erlang-mode provides commands to navigate across Erlang source code. PEL complements these. And EDTS also.  Several commands are specialization of the normal navigation commands which are described in the table <u>Navigation</u> , but several are specific to Erlang:  Notice the 3 sets of commands:  1. <f12> <up> and <f12> <down> move to the beginning of Erlang functions skipping all compiler directives.  2. The standard navigation commands, (mapped to <f6> prefix) move to beginning/end of Erlang functions but stop at compiler directives.  3. The <f12> <m-cursor> commands (also accessible via <m-f12> <m-cursor>, move across Erlang clauses (as opposed to functions).  The list below describe the specialized commands only. See the others inside <u>Navigation</u>, like the navigation by blocks.  Note that all <f12> prefixes shown below are available in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11></f12></m-cursor></m-f12></m-cursor></f12></f6></down></f12></up></f12>			
Continued to beginning of the previous function supplied functions	npiler directives. Skips clauses.	on beginning/end at/skippir	Move to next/previous funct	• By <u>Function</u> • Mo
Seginaring of previous function		etion	Move to beginning of fun-	to start of function
C-c C-d C-b (feri-goto-previous-function)  • Go forward to beginning of next function  • C+212> <a href="cellpass">document of the previous function." Sixps all compiler directives.  • C+212&gt; fin.  • C+212&gt; <a href="cellpass">cellpass all compiler directives.</a>  • C+212&gt; fin.  • C-2 c</a>	oves point to the first character of the function that the function prefix argument N repeat N times.		• <f12> f p</f12>	beginning of e <f< td=""></f<>
• Go forward to beginning of next function  • <pre> • Go forward to beginning of next function beginning of next function  • <fi> &lt; fi &gt; fi &gt; fi &gt; fi &gt; fi &gt; fi &gt; f</fi></pre>	ift marking is available for the key sequence		• <f11> SPC e f p</f11>	• <f< td=""></f<>
Soptional N	ips all compiler directives.		C-c C-d C-b	С-с
• f11> SPC e f n	oves point to the first character of the function the prefix argument N repeat N times.	u	• <f12> f n</f12>	beginning of next function
* Lo start of function/directive     ** Move to beginning of function or compiler directive     ** C-N-a				
## Go backward to beginning of previous:  * Go backward to beginning of previous:  * C-N-a  * C-N-a  * C-N-chome>  * C-N-chome>  * C-R-chome>	ips all compiler directives.	(ferl-goto-next-function)	C-c C-d C-f	С-с
beginning of previous:		ction or compiler directive	Move to beginning of fundamental	
• C-M-a • tunction • tunction • compiler directive • <pre></pre>	0 0		<f12> f P</f12>	
defun &optional SILENT   Lunction   compiler directive   - (f11) SPC of N   - (f5) < down>   - (f5) < down>   - (f5) < down>   - (f11) SPC of N	ginning of defun. ift marking is available in graphics mode, r ome>). However <f6> p and <f6> &lt;</f6></f6>	(erlang-beginning- of-function	• C-M- <home> • <f6> p • <f6> <up></up></f6></f6></home>	previous:     function     compiler     directive
• function • compiler directive • *f6> a			<f12> f N</f12>	
Backward to end of previous:	he beginning of next function is found, pus DNT-PUSH_MARK is non-nil. Move back to previous position with M-`.		• <f6> <down></down></f6>	• function • compiler
of previous:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function directive  - Forward to end of next:     • function directive  - Forward to end of next:     • function definition.  - Shift marking is available for the <f6> bindings.  - With a numerical argument of to the that many times.  - Forward to line after end of Erlang function.  With a numerical argument repeat that many times.  - Forward to line after end of defun.      • Forward to line after end of defun.      • Flang function.  - Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-index).  - Forward to line after end of Erlang function.  - Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-index).  - Forward to line after end of Erlang duretion.  - Forward to line after end of Erlang duretion.  - Forward to line after end of Erlang function.  - Forward to line after end of Erlang duretion.  - Forward to l</f6>		r compiler directive	Move to end of function of	to end of function
next:     • function     • compiler directive      • By Expression     • functions, etc      • Go to beginning of statement      • Go to end of statement      • Go to end of statement      • Go to end of statement      • Cf12> s e      • Cf6> <right>      • Cf6&gt; <right>      • Cf6&gt; <right>      • ARG)     (erlang-end-of-function &amp; optional ARG)      • With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun.      • Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-i     // End&gt;      • With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun.      • Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-i     // End&gt;      • Note that in Erlang every single expression or expression sequence ends with a period. Expressions in expression sequences are separated by comparison or expressions in a sequence of expressions.      • Go to beginning of statement      • Go to beginning of statement      • Go to end of statement      • Go to end of statement      • With a numerical argument repeat that many times.      • With a numerical argument repeat that many times.      • With a numerical argument repeat that many times.</right></right></right>	eps if does not find end of previous function he end of previous function is found, push ISH_MARK is non-nil. Move back to previous position with M-`.	defun &optional SILENT	<f6> <left></left></f6>	of previous:     • function     • compiler
<ul> <li>functions, etc</li> <li>The following commands move to the beginning/end of single expression or expression sequence.</li> <li>They do not move across expressions in a sequence of expressions.</li> <li>Since Erlang function definition is also an Erlang expression, these commands move across function definitions.</li> <li>Go to beginning of statement</li> <li>M-a</li> <li>(backward-sentence &amp; optional ARG)</li> <li>With a numerical argument repeat that many times.</li> <li>Go forward to the end of an Erlang statement.</li> <li>With a numerical argument repeat that many times.</li> <li>With a numerical argument repeat that many times.</li> </ul>	argument, do it that many times. Negative eding end of defun. nift marking is available in graphics mode,	ARG) (erlang-end-of- function & optional	• C-M- <end></end>	next: • function • compiler
<ul> <li>statement</li> <li><f12> s a</f12></li> <li>Go to end of statement</li> <li>M-e</li> <li>(forward-sentence &amp; optional ARG)</li> <li>With a numerical argument repeat that many times.</li> <li>Go forward to the end of an Erlang statement.</li> <li>With a numerical argument repeat that many times.</li> <li>With a numerical argument repeat that many times.</li> </ul>	xpression or expression sequence.	e to the beginning/end of sin pressions in a sequence of	The following commands move  • They do not move across ex	• functions, etc The f
statement <pre>statement</pre> <pre></pre>				statement
By <u>Function Clause</u> Move by clauses of a function. A function definition (statement) may have multiple clauses, each separated by a semicolon.		,		statement
	may have multiple clauses, each separate	A function definition (stater	Move by clauses of a function.	By Function Clause Move
• Go backward to beginning of clause • <pre></pre>	th argument, do this that many times.		• <f12> c a</f12>	beginning of clause • <f< td=""></f<>
• Go forward to beginning of next clause  • <f12> c n • <m-f12> <m-down> clause  • <f12> c n • <m-f12> <m-down> clause  • Move forward to the beginning of next clause. • Pushes mark; move back to previous position with M-`.  ⇒Shift marking is available.</m-down></m-f12></f12></m-down></m-f12></f12>	shes mark; move back to previous position			beginning of next • <n< td=""></n<>
• Go backward to end of previous clause  • <f12> c p • <m-f12> <m-left>  (pel-end-of-previous-clause)  Move backward to the end of the previous clause. • Pushes mark; move back to previous position with M−`.  Shift marking is available.</m-left></m-f12></f12>	shes mark; move back to previous position		<del>-</del>	
• Go forward to end of current clause • <f12> c e • <m-right>  (erlang-end-of-clause &amp; optional ARG)  Move to the end of the current clause. • With argument, do this that many times.  Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.</m-right></f12>	th argument, do this that many times.	,	• <f12> c e</f12>	current clause • <f< td=""></f<>

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Block Navigation  See also:	<ul> <li>( ) for function p</li> <li>{ } for tuples, re</li> <li>[ ] for lists</li> <li>" " for strings</li> </ul>	erameters, expression grou ecords, maps	wing character pairs, generically called <i>block parens</i> : ping ental support in PEL. Under development.
∑X Smartparens			igate across and into these balanced blocks. Their name is shown in <b>black</b> in the following rows. en smartparens-mode minor-mode is active. Some are PEL specializations of smartparens code.
To start/end of Blocks	The following commands mov	e to the beginning or end of	a block, skipping over Erlang terms inside these blocks.
Go backward to beginning of previous block Skips terms.	• С-м-р	(backward-list &optional ARG)	Move backward to beginning of previous block.  • Supports blocks of (), [] and {}.  • With ARG, do it that many times.  • A negative argument N means forward-list N.  • This command assumes point is not in a string or comment.  -spec ejabberd_started 6 () -> ok.  ejabberd_started 5 () ->  gen_server:call 4 (?MODULE, ejabberd_started, ?CALL_TIMEOUT).  -spec config_reloaded 2 () -> ok.  config_reloaded 2 () ->  gen_server:call 1 (?MODULE, config_reloaded, ?CALL_TIMEOUT).
Go backward to end of previous block     Skips terms.     ∑X Smartparens with smartparens-mode active	<m-f7> p</m-f7>	(pel-sp-previous-sexp &optional ARG)	Move backward to end of previous block.  With ARG, do it that many times. If there is no next expression at current level, jump one level up (effectively doing 'sp-up-sexp').  A negative argument N means move to the end of N-th following balanced expression.  -spec ejabberd_started()
Go forward to end of next block     Skips terms.	• C-M-n	(forward-list &optional ARG)	Move forward to end of next block. Supports blocks of (), [] and {}. With ARG, do it that many times. A negative argument N means forward-list N. This command assumes point is not in a string or comment.
Go forward to beginning of next block     Skips terms.     ∑X Smartparens with smartparensmode active	<m-f7> n</m-f7>	(pel-sp-next-sexp &optional ARG)	Move forward to <b>beginning</b> of next block (and term if 'sp-navigate-consider-symbols' is set).  • With ARG, do it that many times.  • If there is no next expression at current level, jump one level up (effectively doing 'sp-backward-up-sexp').  O-spec ejabberd_started 1() -> ok.  ejabberd_started 2() ->  gen_server:call 3(?MODULE, ejabberd_started, ?CALL_TIMEOUT).  -spec config_reloaded 4() -> ok.  config_reloaded 5() ->  gen_server:call 6(?MODULE, config_reloaded, ?CALL_TIMEOUT).
By Blocks and Terms	Several Linux distros map	<pre><left> and Esc C-<righ c-m-<left=""> and C-M-<r< pre=""></r<></righ></left></pre>	o stops at terms.  Le> bindings below, set pel-windmove-on-esc-cursor user-option is set to nil.  Light> to desktop workspace operation. In that case you can either use another key binding or d->shortcuts to prevent it from using that key sequence.
Go backward to beginning of previous term/block	• C-M- <left> • C-[ C-b • Esc C-b • Esc C-<left> 1 • C-M-b</left></left>	(backward-sexp &optional ARG)	Move backward backward to beginning of previous term or block.  • With ARG, do it that many times.  • A negative arg N means move forward to end of N terms/blocks.  • At beginning of block, jump out of the current one.  • This command assumes point is not in a string or comment.  • C-M-P : Shift marking is available in graphics mode, not in terminal mode.  • C-M-b : Shift marking is available in graphics mode, not in terminal mode.  • C-M- <left> : Shift marking works with this command.  • C-M-<left> does not work on Windows, but H-<left> works.  Same as above with the additional behaviour:</left></left></left>
∑x Smartparens     with smartparens- mode active:         C-M-b and <m- f7=""> b use sp-         backward-sexp,         others are using         backward-sexp</m->	• C-M-b • <m-f7> b</m-f7>	&optional ARG)	<ul> <li>With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default.</li> <li>When it is nil, point only stops at 1, 4, 6 and 9: it jumps over terms.</li> <li>-spec ejabberd_started() -&gt; ok. ejabberd_started() -&gt; gen_server:call 9(?MODULE, ejabberd_started, ?CALL_TIMEOUT).</li> <li>-8 spec 7 config_reloaded 6() -&gt; 5 ok.</li> <li>5 config_reloaded 4() -&gt; 3 gen_server: 2 call 1(?MODULE, config_reloaded, ?CALL_TIMEOUT). 0 Inside a block: gen_server:call(?3 MODULE, 2 ejabberd_started, ?1 CALL_TIMEOUT 0).</li> </ul>

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Go forward to end of next term/block	• C-M- <right> • C-[ C-f • Esc C-f • Esc C-<right> • C-M-f</right></right>	( <b>forward-sexp</b> &optional ARG)	Move forward to end of term or block.  • With ARG, do it that many times.  • A negative argument N means move backward to beginning of previous term or block.  • At end of block, jump out of the current one.  • C-M-n : Shift marking is available in graphics mode, not in terminal mode.  • C-M-f : Shift marking is available in graphics mode, not in terminal mode.  • C-M- <right> : Shift marking works with this command.  • C-M-<right> does not work on Windows, but H-<right> does.</right></right></right>
<ul> <li><u>X</u> Smartparens with smartparens- mode active:</li> <li>C-M-f and <m- f=""></m-> f use sp- forward-sexp,</li> <li>others are using forward-sexp</li> </ul>	• C-M-f • <m-f7> f</m-f7>	(sp-forward-sexp &optional ARG)	Same as above with the additional behaviour:  • With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default.  • When it is nil, point only stops at 3, 6 and 9 it jumps over terms.  O-spec1 ejabberd_started2()3 -> ok4.  ejabberd_started5()6 -> gen_server7:call8(?MODULE, ejabberd_started, ?CALL_TIMEOUT)9.  -spec10 config_reloaded() -> ok. config_reloaded() -> ok. config_reloaded() -> gen_server:call(0?MODULE1, config_reloaded2, ?CALL_TIMEOUT3).
Into block	Navigate inside nested blocks	of elements with the follow	ing commands.
Into block forward	C-M-d	(down-list &optional	Move forward to the beginning of inner element of a block.
<u>∑X Smartparens</u> with smartparens-     mode active	• C-M-d • <m-f7> d</m-f7>	(sp-down-sexp &optional ARG)	<ul> <li>With ARG, do this that many times.</li> <li>A negative argument N means move backward but still go down a level.</li> <li>If ARG is raw prefix argument C-u, descend forward as much as possible.</li> <li>If the point is inside block and there is no down expression to descend to, jump to the beginning of current one. If moving backwards, jump to end of current one.</li> <li>music_info() -&gt;</li> <li>[3] noreply, State},</li> <li>{good, {{year, 1974}, {group, "Contraction"},</li> </ul>
Into block backward	• <m-f7> z</m-f7>	(sp-backward-down-	<pre>O[1{2song, "3sam M'Madown"},</pre>
<u>X</u> Smartparens with smartparens- mode active	• C-M-z	sexp &optional ARG)	<ul> <li>With ARG, do this that many times.</li> <li>A negative argument N means move forward but still go down a level.</li> <li>If ARG is raw prefix argument C-u, descend backward as much as possible.</li> <li>If the point is inside sexp and there is no down expression to descend to, jump to the end of current one. If moving forward, jump to beginning of current one.</li> <li>music_info(1) -&gt;</li></ul>
to edge of block			
To beginning of block  • <u>∑x Smartparens</u> with smartparens- mode active	• <m-f7> a</m-f7>	(sp-beginning-of-sexp &optional ARG)	Jump to beginning of the block the point is in.  The beginning is the point after the opening delimiter.  With no argument, this is the same as C-u C-u 'sp-down-sexp'  With ARG positive N > 1, move forward out of the current expression, move N-2 expressions forward and move down one level into next expression.  With ARG negative N < 1, move backward out of the current expression, move N-1 expressions backward and move down one level into next expression.  With ARG raw prefix argument C-u move out of the current expressions and then to the beginning of enclosing expression.  music_info() -> {{error, {noreply, State}}, {good, {{1year, 19074},
To end of current block • forward • ∑X Smartparens with smartparens- mode active	<m-f7> e</m-f7>	(sp-end-of-sexp &optional ARG)	Jump to end of the current block.  • With no argument, this is the same as calling C-u C-u 'sp-backward-down-sexp'.  • With ARG positive N > 1, move forward out of the current expression, move N-1 expressions forward and move down backward one level into previous expression.  • With ARG negative N < 1, move backward out of the current expression, move N-2 expressions backward and move down backward one level into previous expression.  • With ARG raw prefix argument C-u move out of the current expressions and then to the end of enclosing expression.  music_info() ->  {

```
Description
                                                                    Function
                                     Kevstroke
                                                                                                                                       Note

    Out of block

                                                            (up-list &optional ARG
                                                                                        Move forward out of one level of block parens.
Out block forward
                            C-M-1
                                                            ESCAPE-STRINGS NO-
                                                                                        • With ARG, do this that many times.
                                                            SYNTAX-CROSSING)
                                                                                          A negative argument means move backward but still to a less deep spot.

    If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode,
remove the whitespace between end of the expression and the last "thing" inside the

                            • C-M-1
                                                            (sp-up-sexp &optional
                                                            ARG INTERACTIVE)
                            • <M-f7> ]
                                                                                           This behaviour can be suppressed for syntactic string blocks by setting 'sp-navigate-reindent-
  after-up-in-string' to nil.
     with smartparens-

    If 'sp-navigate-close-if-unbalanced' is non-nil, close the unbalanced expressions

                                                                                          automatically.
                                                                                        music_info() ->
                                                                                             {{erOror, {noreply, State}}1,
                                                                                                                                                             example
                                                                                               {go od, {{year, 1974},
                                                                                                                                                             example
                                                                                                           {group, "Contraction"},
                                                                                                                       "Sam M'Madown"},
"A la claire fontaine"},
"L'alarme à l'oeil"},
"La bourse ou la vie"}]
                                                                                                           [{song,
{song,
                                                                                                            {song,
{song,
                                                                                                           {rating, excellent}}1
                            • <M-f7> u
                                                                                        Move backward out of one level of block parens.
Out block backward
                                                            (sp-backward-up-sexp
                                                           &optional ARG
INTERACTIVE)

    With ARG, do this that many times.

  backward
                            • C-M-u
                                                                                          A negative argument means move forward but still to a less deep spot.
                                                                                          If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between beginning of the expression and the first "thing" inside the
  expression.
     with smartparens-
                                                                                        music info() ->
     mode active
                                                                                           [6]{{error, {noreply, State}},
                                                                                           5{good, 4{{year, 1974},
                                                                                                           {group, "Contraction"},
                                                                                                        3[\{song,
                                                                                                                       "Sam M'Madown"},
                                                                                                                         "A la claire fontaine"},
"L'alarme à l'oeil"},
                                                                                                            {song,
{song,
                                                                                                                         1"La bourse ou la Ovie"}]
                                                                                                          2{song,
                                                                                                           {rating, excellent}}}.
                            The commands all use the XX Smartparens external package and required smartparens-mode minor-mode to be active.
Move over space
                                                                                        Skip whitespace and comments moving forward.

If STOP-AT-STRING is non-nil, stop before entering a string (if not already in a string).

If STOP-AFTER-STRING is non-nil, stop after exiting a string.
To beginning of next symbol/block
                            <M-f7> SPC n
                                                            (sp-skip-forward-to-
                                                            symbol &optional STOP-
                                                            AT-STRING STOP-
                                                            AFTER-STRING

    ∑X Smartparens

                                                                                        start_app(App) ->0
                                                            STOP-INSIDE-STRING)
                                                                                                                                         % first clause
                                                                                                                                                                     example
     with smartparens-
                                                                                             1 start_app(App, temporary).
     mode active
                                                                                        start_app(App, 0 1Type) ->
    StartFlag = not is_loaded(),
    start_app(App, Type, StartFlag).
                                                                                                                                         % second clause
                                                                                                                                                                     example
To end of next symbol
                            <M-f7> SPC m
                                                            (sp-forward-symbol
                                                                                        Move point to the next position that is the end of a symbol.
or block
                                                            &optional ARG)
                                                                                           With ARG being positive number N, repeat that many times.

With ARG being negative number -N, repeat that many times in backward direction.
A symbol is any sequence of characters that are in either the word constituent or symbol

    constituent syntax class. Current symbol only extend to the possible opening or closing delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax
     with smartparens-
     mode active
                                                                                           classes.
                                                                                        This stops inside comments instead of skipping them.
                                                                                                                                                                       example
                                                                                        start_app(App) ->
                                                                                                                                      % first clause
                                                                                             start_app(App() temporary(1).
                                                                                        start_app(App(), Type(1) ->
                                                                                                                                        % second 2 clause 3
                                                                                                                                                                        example 
                                                                                             StartFlag = not 5 is_loaded 6 (),
                                                                                             start_app7(App8, Type9, StartFlag10).
                            <M-f7> SPC p
To beginning of
                                                            (sp-backward-symbol
                                                                                        Move point to the next position that is the beginning of a symbol.
                                                            &optional ARG)
                                                                                           With ARG being positive number N, repeat that many times.
                                                                                          With ARG being negative number -N, repeat that many times in forward direction.

A symbol is any sequence of characters that are in either the word constituent or symbol

    ∑X Smartparens

                                                                                          constituent syntax class. Current symbol only extend to the possible opening or closing
     with smartparens-
                                                                                           delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax
     mode active
                                                                                           classes.
                                                                                        This stops inside comments instead of skipping them.
                                                                                                                                        % 🛮 first 🗸 clause 👈 Error! 🚧
                                                                                        10start_app(9App) ->
                                                                                             6start_app(5App, 4temporary).
                                                                                        3start_app(2App, 1Type) ->
                                                                                             OStartFlag = not is_loaded(),
start_app(App, Type, StartFlag).
                                                                                                                                                                      example
                                                            (sp-forward-whitespace
                                                                                        Skip forward past the whitespace characters.
Skip forward past
                            <M-f7> SPC .
whitespace
                                                            &optional ARG)
                                                                                          With non-nil ARG return number of characters skipped.
    ∑ x Smartparens
                                                                                        start_app(App) ->0
                                                                                                                                        1 first clause
                                                                                             start_app(App, temporary).
     with smartparens-
     mode active
                                                                                                                                      % second clause 0
                                                                                        start_app(App, Type) ->
                                                                                             1StartFlag = not is_loaded(),
                                                                                             start_app(App, Type, StartFlag).
                            <M-f7> SPC ,
Skip backward past
                                                                                        Skip backward past the whitespace characters.
                                                            (sp-backward-
                                                            whitespace &optional
                                                                                          With non-nil ARG return number of characters skipped.
                                                            ARG)
                                                                                        start_app(App) ->1
                                                                                                                                         first clause

∑
x Smartparens

                                                                                             start_app(App, temporary).
     with smartparens-
     mode active
                                                                                                                                      % second clause 1
                                                                                        start_app(App, Type) ->
                                                                                             OStartFlag = not is_loaded(),
                                                                                             start_app(App, Type, StartFlag).
```

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Copy and Clone	The following commands prov	vides specialized copy and c	eloning operations. They are provided by \$\sum_{x} \text{Smartparens}\$
• <u>∑</u> x Smartparens	With PEL the commands th	at are marked with <a> disp</a>	ay the copied string when <b>pel-show-copy-cut-text</b> is <b>t</b> . Toggle this display with <b><f11> M-=</f11></b>
Copy current & forward block(s)	<m-f7> =</m-f7>	(sp-copy-sexp &optional ARG)	Copy the following ARG expressions to the kill-ring.  This is exactly like calling 'sp-kill-sexp' with second argument t. All the special prefix arguments work the same way.
Copy previous block(s)	<m-f7> M-=</m-f7>	(sp-backward-copy- sexp &optional ARG)	Copy the previous ARG expressions to the kill-ring.  This is exactly like calling 'sp-backward-kill-sexp' with second argument t. All the special prefix arguments work the same way.
clone current block	<m-f7> c</m-f7>	(sp-clone-sexp)	Clone sexp after or around point.  If the form immediately after point is a sexp, clone it below the current one and put the point in front of it.
Transform	3003		Otherwise get the enclosing sexp and clone it below the current enclosing sexp.
Transpose block		(an Avananasa asym	
elements	<m-f7> t</m-f7>	(sp-transpose-sexp &optional ARG)	foo  bar baz -> bar foo  baz  foo  bar baz -> bar baz foo  ;; 2  (foo)  (bar baz) -> (bar baz) (foo)
			(foo bar) -> (baz quux) ;; keeps the formatting _  (baz quux)
Transpose block elements	<m-f7> T</m-f7>	(sp-transpose-hybrid- sexp &optional ARG)	foo bar baz (quux  baz (quux -> quack) quack) foo bar\n
			[(foo) (bar) -> [(baz)   (foo) (bar) ]  foo bar baz -> quux flux
Push current block	<m-f7> s</m-f7>	(sp-push-hybrid-sexp)	quux flux   foo bar baz\n
after next		(cp pass system cosp)	<pre> x = big_function_call(a,</pre>
Like lispy s			<pre>(a,</pre>
Transform - slurp	쐤		
Enclose next outside element into current block	<m-f7> &gt;</m-f7>	(sp-forward-slurp-sexp &optional ARG)	<pre>(foo  bar) baz</pre>
			"foo  bar" "baz quux" -> "foo  bar baz quux"
Enclose next outside element into current block	<m-f7> M-&gt;</m-f7>	(sp-slurp-hybrid-sexp)	Add hybrid sexp following the current list in it by moving the closing delimiter.  This is conceptually similar to 'sp-forward-slurp-sexp' but works better in "line-based" languages like C or Java.  Because the structure is much looser in these languages, this command currently does not support all the prefix argument triggers that 'sp-forward-slurp-sexp' does.
Enclose previous outside element(s) into	<m-f7> &lt;</m-f7>	(sp-backward-slurp- sexp &optional ARG)	foo (bar  baz) -> (foo bar  baz)
next block		, ,	foo [(bar  baz)] -> [foo (bar  baz)]
			[foo (bar baz)] -> [(foo bar baz)]
			(foo bar baz ( quux)) -> ((foo bar baz  quux)) ;; with C-u
			"foo bar" "baz  quux" -> "foo bar baz  quux"
Enclose next outside element(s) into previous	<m-f7> ]</m-f7>	(sp-add-to-previous- sexp &optional ARG)	(foo bar)  baz quux -> (foo bar  baz) quux
block			(foo bar)  baz quux -> (foo bar  baz quux) ;; 2
			(blab (foo bar)  baz quux) -> (blab (foo bar  baz quux)) ;; C-u
Enclose previous	<m-f7> [</m-f7>	(sp-add-to-next-sexp	(foo bar) (baz  quux) -> (foo bar (baz  quux)) ;; C-u C-u
outside element(s) into next block		&optional ARG)	foo bar  (baz quux) -> foo (bar  baz quux)
			foo bar  (baz quux) -> (foo bar  baz quux) ;; 2  (foo bar  (bar quux) blab) -> ((foo bar  bar quux) blab) ;; C-u
			(foo  bar) (baz quux) -> ((foo  bar) baz quux) ;; C-u C-u
Transform - barf	ini.		The first fi
Eject next element(s)	<m-f7> /</m-f7>	(sp-forward-barf-sexp	
out of current block		&optional ARG)	(foo bar  baz) -> (foo bar ) baz ;; nil (defaults to 1)
			(foo  [bar baz]) -> (foo ) [bar baz] ;; 1 (1 2 3  4 5 6) -> (1 2 3 ) 4 5 6 ;; C-u (or numeric prefix 3)
			(foo bar  baz) -> foo (bar  baz) ;; -1
Eject previous	<m-f7> M-/</m-f7>	(sp-backward-barf-sexp	
element(s) out of current block		&optional ARG)	(foo bar  baz) -> foo (bar  baz)  ([foo bar]  baz) -> [foo bar] ( baz)
			(1 2 3   4 5 6) -> 1 2 3 ( 4 5 6) ;; C-u (or 3)
Re-wrap block	tut.		

```
Function
      Description
                                   Keystroke
                                                                                                                              Note
                                                        (sp-rewrap-sexp PAIR &optional KEEP-OLD)
Re-wrap current block
                          <M-f7> r
                                                                                  Re-wrap current block using another block character.
                                                                                     (foo |bar baz) -> [foo |bar baz] ;; [
                                                                                     (foo |bar baz) -> [(foo |bar baz)] ;; C-u [
Swap wrapping
                          <M-f7> w
                                                        (sp-swap-enclosing-
                                                                                  Swap the wrapping of blocks
characters between
                                                        sexp &optional ARG)
current block and
                                                                                     (foo [|bar] baz)
                                                                                                                           -> [foo (|bar) baz] ;; 1
parent block
                                                                                     (foo {bar [|baz] quux} quack) -> [foo {bar (|baz) quux} quack] ;; 2
Un-wrap block
                          mi
                                                        (sp-unwrap-sexp & optional ARG)
Extract all elements
                          <M-f7> U
                                                                                  Un-wrap current or next block.
from current/next block
                                                                                     I(foo bar baz)
                                                                                                             -> Ifoo bar baz
                                                                                                             -> foo bar| baz
                                                                                     (foo bar| baz)
                                                                                     |(foo) (bar) (baz) -> |(foo) bar (baz) ;; 2
                                                        (sp-backward-unwrap-
Extract all elements
                          <M-f7> W
                                                                                  Un-wrap previous block.
from previous block
                                                        sexp &optional ARG)
                                                                                     (foo bar baz)
                                                                                                             -> foo bar baz
                                                                                     (foo bar) | (baz) -> foo bar | (baz)
                                                                                     (foo) (bar) (baz) | -> foo (bar) (baz) ;; 3
Transformation
                          mi
                                                        (sp-convolute-sexp
&optional ARG)
Convolute
                          <M-f7> C
                                                                                  Exchange the order of application of the two closest outer forms.
                                                                                  In the following, we want to move the 'while' before the 'let'.
                                                                                      (while (we-are-good)
  (let ((stuff 1)
                                                                                                                             (other 2))
|(do-thing 1)
                                                                                           (do-thing 2)
(do-thing 3)))
                                                                                                                                (do-thing 2)
                                                                                                                               (do-thing 3)))
                                                                                  (forward-char (sp-get env |:op-l)) -> (sp-get env (forward-char |:op-l))
Absorb previous
                          <M-f7> A
                                                        (sp-absorb-sexp
                                                                                  Absorb the outer item into the current block and move point before the absorbed item(s).
                                                        &optional ARG)
  lement into current
                                                                                      (do-stuff 1)
block
                                                                                                                 (save-excursion
                                                                                      (save-excursion | (do-stuff 2))
                                                                                                                  |(do-stuff 1)
(do-stuff 2))
                                                                                     foo bar (concat |baz quux) -> (concat |foo bar baz quux) ;; 2
Expel previous items from block
                          <M-f7> E
                                                        (sp-emit-sexp &optional
                                                                                  Expel previous items from current block out of the block.
                                                                                                                 (do-stuff 1)
                                                                                      (save-excursion
                                                                                       (do-stuff 1)
(do-stuff 2) ->
|(do-stuff 3))
                                                                                                                (do-stuff 2)
                                                                                                               (save-excursion | (do-stuff 3))
                                                                                      (while not-done-yet
                                                                                                                       (execute-only-once)
                                                                                       (execute-only-once) -> (while not-done-yet | (execute-in-loop)) | (execute-in-loop))
                                                                                                                                                     ;; arg = 2
                          <M-f7>
                                                        (sp-extract-before-sexp
                                                                                  Move the expression after point before the enclosing balanced expression.
                                                        &optional ARG
                                                                                    The point moves with the extracted expression.
                                                                                  • With ARG positive N, extract N expressions after point.
                                                                                    With ARG negative -N, extract N expressions before point.
                                                                                  • With ARG being raw prefix argument C-u, extract all the expressions up until the end of
                                                                                     enclosing list.
                                                                                  • If the raw prefix is negative, this behaves as C-u 'sp-backward-barf-sexp'.
                                                                                  Move the expression after point after the enclosing balanced expression.
                          < M-f7 >
                                                        (sp-extract-after-sexp
                                                        &optional ARG)
                                                                                     The point moves with the extracted expression.
                                                                                    With ARG positive N, extract N expressions after point.
                                                                                    With ARG negative -N, extract N expressions before point.
With ARG being raw prefix argument C-u, extract all the expressions up until the end of
                                                                                    enclosing list.

With ARG being negative raw prefix argument - C-u, extract all the expressions up until the
                                                                                    start of enclosing list.
Split block
                                                        (sp-split-sexp ARG)
                          <M-f7> |
                                                                                     (foo bar |baz quux) -> (foo bar) |(baz quux)
                                                                                     "foo bar |baz quux" -> "foo bar" |"baz quux"
                                                                                     ([foo |bar baz] quux) -> ([foo] |[bar baz] quux)
                                                                                     (foo bar | baz quux) \rightarrow (foo) (bar | ) (baz) (quux) ;; C-u
Join blocks
                                                        (sp-join-sexp &optional
                          <M-f7> J
                                                                                     (foo bar) I(baz)
                                                                                                                                   -> (foo bar Ibaz)
                                                        ARG)
                                                                                     (foo) | (bar) (baz)
                                                                                                                                  -> (foo |bar baz) ;; 2
                                                                                     [foo] [bar] |[baz]
                                                                                                                                  -> [foo bar |baz] ;; -2
                                                                                  (foo bar (baz) | (quux) (blob bluq)) \rightarrow (foo bar (baz| quux blob bluq)) ;; \mathsf{C-u}
                          In Erlang mode, the superword mode can be useful since snake case is often used. Using superword-mode helps searching.
Search Support
                          PEL activates the superword mode by default in Erlang mode. To change this use the <f11> t <f2> to access the customize buffer.
                                                                                  Toggle superword-mode: a minor mode that treats snake_case as one word. In Erlang, '_' are
Toggle superword-
                          <f12> M-p
                                                        (superword-mode
mode
                                                        &optional ARG)
                                                                                  treated as part of words.
                          • <f11> t m p
                                                                                  • With a prefix argument ARG, enable superword mode if ARG is positive, and disable it
                          • <f11> SPC e M-p
See also:
                                                                                    otherwise.
• <u>▼ Text Modes</u>
                                                                                  + PEL provides the <f12> \mathtt{M-p} key for the programming language modes where \underline{\mathtt{snake\_case}}
• <u>∑ Search/Replace</u>
                                                                                    is popular (Emacs Lisp, C, C++, Erlang, Python, etc...)
Marking
                          The following Erlang-mode specific marking functions are available. They complement what is already available and described in the N Marking table.
                          For those 2 commands the Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.
```

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Mark Erlang function	• C-M-h	(mark-defun &optional	Put mark at end of this function, point at beginning.	
	• <f12> f m</f12>	ARG) (erlang-mark-function	<ul> <li>The function marked is the one that contains point or follows point.</li> <li>With positive ARG, mark this and that many next functions; with negative ARG, change the</li> </ul>	
		&optional ARG)	direction of marking.  • If the mark is active, it marks the next or previous function(s) after the one(s) already marked.	
Mark Erlang Clause	• C-c M-h	(erlang-mark-clause)	Put mark at end of clause, point at beginning.	
	• <f12> c m</f12>	,	71 0 0	
<u>iEdit mode</u>	iEdit Mode - Edit multiple ins	tances of variable/symbol	s simultaneously. Unis mode is very useful to rename symbols or variable during refactoring.	
See also: <u>Neighlight</u>	Requires the <u>iedit</u> external	package. 2 PEL activates	it with pel-use-iedit.	
Toggle iedit mode See also:	• C-; • <f11> e</f11>	(iedit-mode &optional ARG)	Toggle iEdit mode: edit all symbols in scope or region simultaneously.	
• <u>∑ Cursor</u>	• <f11> h i</f11>	7110)	<ul> <li>⚠ Both iEdit and Flyspell use the C-; key as their default binding.</li> <li>PEL detects and reports that situation: modify the binding of one of them if you see it.</li> </ul>	
• <u>∑ Search/Replace</u>	• <f11> m i</f11>		➤ See <u>Search/Replace</u> where all the iedit-mode commands are described.	
Highlighting blocks	show-paren-mode, which h	ighlights the parens that ma	e useful modes to highlight blocks of (), {}, and [].  tches the one before or after point.  s are highlighted with the same colour.	
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode).  • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.	
See also: <u>∑ Highlight</u>	• <f11> h ( • <f11> SPC e M-9</f11></f11>		Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.	
Enable/Disable coloured highlight of	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters- mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth.	
nested blocks (),{},[] See also: > Highlight	• <f11> h R</f11>		Customize the depth and colours with M-x customize-group rainbow-delimiters	
See also. <u>// Highlight</u>	• <f11> SPC e M-r</f11>		Requires: rainbow-delimiters.el  PEL activates this when the pel-use-rainbow-delimiters user option is set to t.	
Inserting code with	Specialized Tempo Skel	etons		
Insert Parentheses	M-(	(insert-parentheses	For Erlang: insert a parenthesis pair '()', leaving point after open-paren.	
	,	&optional ARG)	<ul> <li>A positive ARG encloses the following ARG sexps in parenthesis if they are balanced.</li> <li>A negative ARG encloses the preceding ARG sexps instead.</li> <li>No argument is equivalent to zero: just insert '()' and leave point between.</li> <li>PEL makes 'parens-require-spaces' buffer local and set it to nil in Erlang mode buffers, allowing the use of this command to insert the argument parentheses following a function (and</li> </ul>	
			without placing a space between the function name and the opening parenthesis.  If region is active, insert enclosing characters at region boundaries.  This command assumes point is not in a string or comment.	
Insert Erlang Code			tons using the standard tempo skeleton package. the Erlang/Skeletons menu (via <f10>).</f10>	
Templates	PEL provides the following a	additional functionality:	ed under the <b>pel:erlang-skel</b> key prefix: <b><f12></f12> <f12></f12></b> .	
See also: •	· ·			
more info and	<ul> <li>Several additional templates. These are marked with a +. These are also added to the menu.</li> <li>Several aspects of the PEL Erlang Source Code Style is controlled by the user options inside the pel-erlang-code-style group. The controlled templates affected are marked with a C. The relevant user options are part of the pel-erlang-code-style group accessible with <f12> <f2> from are erlang mode buffer and include the following options:         <ul> <li>pel-erlang-skel-insert-file-timestamp</li> <li>set whether an automatically updated timestamp is inserted in the file header block.</li> <li>pel-erlang-skel-prompt-for-purpose</li> <li>set whether file and function skeletons blocks prompt for purpose and insert it.</li> </ul> </f2></f12></li> </ul>			
tempo skeleton and				
the completely different <u>yasnippet</u>				
template-based text insertion).		pt-for-function-name	: set whether function skeletons prompt for function name and then inserts that name.  s : set whether function skeletons prompt for function arguments and then insert them.	
,	pel-erlang-use-separators     pel-erlang-use-secondary-separators		: set whether blocks use horizontal separator lines (these are the first of potentially 2 separators). : set whether blocks use a second block horizontal separator line.	
	pel-erlang-skel-with-edoc		: set whether generated code comments use EDoc markup.	
	• pel-erlang-skel-with-		: set whether file header blocks use open source software license text controlled by <u>isce.</u>	
	Substitution of the second of			
	If you want to change the behaviour for only one file, write the user option control block at the end of that file. If you want to control the behaviour of the PEL tempo templates for all files inside a directory tree create a .dir-locals file and store the values of the relevant options variables inside that file.			
	This allows you to control	the user options affecting th	ne format of the tempo templates precisely and does not affect what you actually type.  In the pel-tempo-mode) you can move to the next or previous point of interest (so called tempo-	
	marks) with the standard	tempo-mode keys C-c M-	-f and C-c M-b or some other keys like C-c . and C-c ,.	
			an also type the template name and then hit <b>C-c C-M-i</b> or <b><f12> <f12> <f12></f12></f12></f12></b> . This orary buffer. This is mainly useful for templates which short names such as "if", "case", etc	
+ : additional templates	Some of the template nam	es in the title column are als	so links to the relevant Erlang language construct reference page.	
C : templates with customization control		s shown below are available	e in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11>	
∑ Customize PEL Erlang Skeletons layout	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-pel &optional OTHER- WINDOW)	Customize PEL Erlang skeleton layout.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.	
if	<f12> <f12> i</f12></f12>	(pel-erl-if)	Insert an if statement.	
case	<f12> <f12> c</f12></f12>	(pel-erl-case)	Insert a case expression.	
export +	<f12> <f12> x</f12></f12>	(pel-erl-export	Insert an export module attribute expression.	
import +	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.	
try +	<f12> <f12> t</f12></f12>	(pel-erl-try)	Insert a try expression.	
try-of +	<f12> <f12> T</f12></f12>	(pel-erl-try-of)	Insert a try expression with of clauses.	
<u>receive</u>	<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.	
after	<f12> <f12> a</f12></f12>	(pel-erl-after)	Insert a receive expression with an after (timeout) clause.	
loop	<f12> <f12> 1</f12></f12>	(pel-erl-loop)	Insert a simple receive loop.	
module	<f12> <f12> m</f12></f12>	(pel-erl-module)	Insert the module attribute.	
function C	<f12> <f12> f</f12></f12>	(pel-erl-function)	Insert a function definition. This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.	
author	<f12> <f12> `</f12></f12>	(pel-erl-author)	Insert the author attribute. Uses the <b>user-mail-address</b> user option to insert your mail address.	
spec	<f12> <f12> s</f12></f12>	(pel-erl-spec)	Insert a -spec for the function following point.	
small-header C	<f12> <f12> M-h</f12></f12>	(pel-erl-small-header)	Insert a small file header without any comment.	
normal-header C	<f12> <f12> M-H</f12></f12>	(pel-erl-normal-header)	Insert a normal file header: includes author name, copyright notice, doc section, file created date	

Description	<u>Keystroke</u>	Function	<u>Note</u>
large-header C	<f12> <f12> h</f12></f12>	(pel-erl-large-header)	Insert a large header block that includes all normal header fields plus separators.  • All formatting is controlled by user-options described above.  • Distinguish Erlang .erl module files from the .hrl header files.
small-server C	<f12> <f12> M-s</f12></f12>	(pel-erl-small-server)	Insert a large file header and template logic for a small server.
application C	<f12> <f12> M-a</f12></f12>	(pel-erl-application)	Insert a large file header and template logic for an application behaviour.
supervisor C	<f12> <f12> M-u</f12></f12>	(pel-erl-supervisor)	Insert a large file header and template logic for a supervisor behaviour.
supervisor-bridge C	<f12> <f12> M-b</f12></f12>	(pel-erl-supervisor- bridge)	Insert a large file header and template logic for a supervisor bridge behaviour.
generic-server C	<f12> <f12> M-g</f12></f12>	(pel-erl-generic-server)	Insert a large file header and template logic for a gen-server behaviour.
gen-event C	<f12> <f12> M-e</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a gen-event behaviour.
gen-fsm C	<f12> <f12> M-f</f12></f12>	(pel-erl-gen-fsm)	Insert a large file header and template logic for a gen-fsm behaviour.
gen-statem-StateName C	<f12> <f12> M-S</f12></f12>	(pel-erl-gen-statem- StateName)	Insert a large file header and template logic for a gen-statem behaviour.
gen-statem-handle- event C	<f12> <f12> M-E</f12></f12>	(pel-erl-gen-statem- handle-event)	Insert a large file header and template logic for a gen-statem.
wx-object C	<f12> <f12> M-w</f12></f12>	(pel-erl-wx-object)	Insert a large file header and template logic for a wx-object generic server.
gen-lib C	<f12> <f12> M-1</f12></f12>	(pel-erl-gen-lib)	Insert a large file header and template logic for a library module.
gen-corba-cb C	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a <b>CORBA</b> callback module.
ct-test-suite-s	<f12> <f12> M-1</f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite
ct-test-suite-l	<f12> <f12> M-2</f12></f12>	(pel-erl-ct-test-suite-l)	Insert a large file header and template logic for a test suite
	<f12> <f12> M-3</f12></f12>	(pel-erl-ts-test-suite)	Insert a large file header and template logic for a test suite
Tempo Template Tag Insertion	• C-c C-M-i • <f12> <f12> <f12> • <f11> SPC e <f12> <f12></f12></f12></f11></f12></f12></f12>	(tempo-complete-tag &optional SILENT)	Look for a tag and expand it.  Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit C-c C-M-i. (or <f12> <f12> <f12>) A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template.</f12></f12></f12></f12></f12>
	match for is determined can match at all.  If a single match is found, the If a partial completion or no	be altered with the variable the corresponding template is match at all is found, and S	cludes 'tempo-tags') are searched for a match for the text before the point. The way the string to be 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no sexpanded in place of the matching string.  SILENT is non-nil, the function will give a signal. letion-buffer' is non-nil, a buffer containing possible completions is displayed.
Toggle pel-tempo-mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c and C-c, as well as C-
See also:  • <u>∑ Inserting Text</u>	• <f11> SPC e <f12> SPC • <f6> SPC</f6></f12></f11>	&optional ARG)	c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When peltempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode.  When a skeleton is inserted via the execution of one of the pel-erl commands above, the pel-tempo-mode is automatically activated.
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key key bindings are only available when pel-tempo-mode is active.
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward- mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key binding are only available when pel-tempo-mode is active.
Specialized Kill See also:	Specialized delete and kill commands are provided by the The smartparens external package activated by pel-use-smartparens user-option.  • Activate smartparens mode manually with <f11> ( or automatically by adding smartparens-mode to pel-erlang-activates-minor-mode.  • This table uses the and symbols to represent these 2 keys:    activated by pel-use-smartparens user-option.   activated by pel-use-smartparens u</f11>		
kill block elements	The following commands kill the	ne element(s) of a block.	
Kill content of next	• <m-f7> ⊠</m-f7>	(sp-change-inner)	Change the content of current or next block. Point can be anywhere in block or element before block.
• ∑x Smartparens	• <m-f7> - n</m-f7>		Before: {'EXIT',Reason} ->  After: {'EXIT',Reason} ->
Delete content of	<m-f7></m-f7>	(sp-change-enclosing)	{   error, {asn1, Reason}}; {error, {   }};  Delete content of the enclosing block. Point can be anywhere inside the current block.
current block  • <u>∑</u> x Smartparens		(op onlinge onlinesing)	Before:
Kill block elements	<m-f7> - ]</m-f7>	(sp-kill-sexp &optional	Kill block elements after point.
forward		ARG DONT-KILL)	Before: case Tlv9 of
• ∑x Smartparens			<pre>[] -&gt; true;&gt; exit({error,   {asn1, {unexpected, Tlv9}}})  After: case Tlv9 of   [] -&gt; true;&gt; exit({error,  })</pre>
Kill block elements	<m-f7> - [</m-f7>	(sp-backward-kill-sexp	Kill block elements before point.
backward		&optional ARG DONT- KILL)	Before:
• ∑X Smartparens			<pre>case Tlv9 of   [] -&gt; true;&gt; exit({error,   {asn1, {unexpected, Tlv9}}})  After: case Tlv9 of</pre>
			<pre>case Tlv9 of [[] -&gt; true;&gt; exit({ {asn1, {unexpected, Tlv9}}})</pre>
Kill element after current	<m-f7> - }</m-f7>	(sp-kill-hybrid-sexp ARG)	Kill a line as if with 'kill-line', but respecting delimiters.
• <u>∑x Smartparens</u>		With ARG being raw pre     With ARG numeric prefix	efix <b>C-u C-u</b> , kill the hybrid sexp the point is in (see 'sp-get-hybrid-sexp').  x 0 (zero) just call 'kill-line'.  behaviour of this command by toggling 'sp-hybrid-kill-excessive-whitespace'.

```
Function
       Description
                                      Keystroke
                                                                                                                                          Note
                             < M-f7 > -1
                                                             (sp-kill-whole-line)
Kill whole line
                                                                                          🔔 Currently this deletes the whole line. Requires Erlang specific implementation. 🚧

    Kill/splice

Un-wrap current block, splicing its elements in
                                                             (sp-splice-sexp
                             <M-f7> 1 1
                                                                                          Un-wrap current block, splicing its content in enclosing block (if any).
                                                             &optional ARG)
                                                                                          Before:
{|EncBytes,EncLen} = 'enc'(Cdx, []), |EncBytes,EncLen = 'enc'(Cdx, []),
enclosing block

    ∑x Smartparens

                                                                                          Before:
                                                                                                  info(
                                                                                           [{vsn,'2.0.1'},
   {module,'ELDAPv3'},
   {options,[{i,"src"},{|outdir,"src"},noobj,{i,"."},{i,"asn1"}]}]).
                                                                                          After:
                                                                                                  _info(
                                                                                            [{vsn, '2.0.1'},
  {module, 'ELDAPv3'},
  {options,[{i,"src"}, |outdir,"src",noobj,{i,"."},{i,"asn1"}]}]).
Kill block element(s)
                                                              (sp-splice-sexp-killing-
                                                                                          Kill elements before point in block and splice remaining elements into outer block.
                             <M-f7> 1 [
before point and splice
                                                             backward &optional
remaining into outer
                                                              ARG)
                                                                                           case Tlv9 of
    [] -> true; -> exit({error,{asn1, {unexpected, |Tlv9}}})
block

    ∑x Smartparens

                                                                                          After:
                                                                                                  Tlv9 of
                                                                                           case Tlv9 of
[] -> true; -> exit({error,{asn1, |Tlv9}})
Kill block element(s)
                                                                                          Kill elements after point in block and splice remaining elements into outer block.
                                                             (sp-splice-sexp-killing-
                             <M-f7> 1 1
forward and splice
remaining into outer
                                                             forward &optional ARG)
                                                                                          Before:
                                                                                                  Tlv9 of
                                                                                           case Tlv9 of
[] -> true; -> exit({error,{asn1, {unexpected, |Tlv9}}})
block

    ∑x Smartparens

                                                                                          After:
                                                                                           case Tlv9 of
    [] -> true; -> exit({error,{asn1, unexpected|}})
Kill around element
                             <M-f7> 1 o
                                                             (sp-splice-sexp-killing-
                                                                                          Kill content around current element/block.
                                                              around &optional ARG)
                                                                                           serore:
-asn1_info(
[{vsn,'2.0.1'},
{module,'<mark>ELDAPv</mark>3'},
{options,[{i,"src"},|{outdir,"src"},noobj,{i,"."},{i,"<u>asn</u>1"}]}]).
n1_info(
                                                                                            [{vsn, '2.0.1'},
                                                                                             {module, '<u>ELDAPv</u>3'},
{options, |{outdir, "src"},}]).

    Delete/Kill

                             m
   region
                                                             (sp-delete-region BEG END)
Delete region
                             <M-f7> DEL -
                                                                                          Delete the text between point and mark, like 'delete-region'
                                                                                            BEG and END are the bounds of region to be deleted.
                                                                                            If that text is unbalanced, signal an error instead.
                                                                                            With a prefix argument, skip the balance check.
Kill region
                                                             (sp-kill-region BEG END)
                                                                                          Kill the text between point and mark, like 'kill-region'
                             <M-f7> - -

BEG and END are the bounds of region to be killed.
If that text is unbalanced, signal an error instead.

                                                                                            With a prefix argument, skip the balance check.
                                                                                          Kill or copy region between BEG and END according to DONT-KILL.
                             < M - f7 > - r
                                                             (sp--kill-or-copy-region
                                                              BEG END &optional
                                                                                               'evil-mode' is active, copying a region will also add it to the 0 register.
                                                                                          · Additionally, if command was prefixed with a register, copy the region to that register
                                                             DONT-KILL)
                                                             (sp-delete-char
Delete char forward
                             <M-f7> DEL n
                                                              &optional ARG)
                                                                                            (quu|x "zot") -> (quu| "zot")
                                                                                            (quux |"zot") -> (quux "|zot") -> (quux "|ot")
                                                                                            (foo (|) bar) -> (foo | bar)
                                                                                            [(foo bar) -> ([foo bar)
                             <M-f7> DEL p
Delete char backward
                                                             (sp-backward-delete-
                                                                                            ("zot" q|uux) -> ("zot" |uux)
                                                             char &optional ARG)
                                                                                            ("zot"| quux) -> ("zot|" quux) -> ("zo|" quux)
                                                                                            (foo (|) bar) -> (foo | bar)
                                                                                            (foo bar) | -> (foo bar|)

    Delete/Kill word

Delete word backward
                                                             (sp-backward-delete-
                                                                                          (sp-backward-delete-word &optional ARG)
                             <M-f7> DEL v
                                                                                             Delete a word backward, skipping over intervening delimiters.
                                                              word &optional ARG)

    Deleted word does not go to the clipboard or kill ring.
    With ARG being positive number N, repeat that many times.

    With ARG being Negative number -N, repeat that many times in backward direction.

                                                             (sp-delete-word
Delete word forward
                                                                                          Delete a word forward, skipping over intervening delimiters.
                             <M-f7> DEL w
                                                                                             Deleted word does not go to the clipboard or kill ring.
                                                             &optional ARG)
                                                                                            With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in backward direction.
Kill word backward
                                                                                          Kill a word backward, skipping over intervening delimiters.
                             < M-f7 > - v
                                                             (sp-backward-kill-word
                                                              &optional ARG)
                                                                                          · With ARG being positive number N, repeat that many times.
                                                                                          • With ARG being Negative number -N, repeat that many times in backward direction.
Kill word forward
                             < M-f7 > - w
                                                             (sp-kill-word &optional
                                                                                          Kill a word forward, skipping over intervening delimiters.

With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in backward direction.

                                                              ARG)
                             See 'sp-backward-symbol' and 'sp-forward-symbol' for what constitutes a symbol for the backward and forward commands respectively.

    Delete/Kill

   symbol
                                                             (sp-backward-delete-
                                                                                          Delete a symbol backward, skipping over any intervening delimiters.

• Deleted symbol does not go to the clipboard or kill ring.
Delete symbol
                             <M-f7> DEL a
                                                             symbol &optional ARG
backward

With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in forward direction.

                                                             WORD)
```

<u>Description</u>	<u>Keystroke</u>	Function	Note		
Delete symbol forward	<m-f7> DEL s</m-f7>	(sp-delete-symbol &optional ARG WORD)	Delete a symbol forward, skipping over any intervening delimiters.  • Deleted symbol does not go to the clipboard or kill ring.  • With ARG being positive number N, repeat that many times.  • With ARG being Negative number -N, repeat that many times in backward direction.		
Kill symbol backward	<m-f7> - a</m-f7>	(sp-backward-kill- symbol &optional ARG WORD)	<ul> <li>Kill a symbol backward, skipping over any intervening delimiters.</li> <li>With ARG being positive number N, repeat that many times.</li> <li>With ARG being Negative number -N, repeat that many times in forward direction.</li> </ul>		
Kill symbol forward	<m-f7> - s</m-f7>	( <b>sp-kill-symbol</b> &optional ARG WORD)	<ul> <li>Kill a symbol forward, skipping over any intervening delimiters.</li> <li>With ARG being positive number N, repeat that many times.</li> <li>With ARG being Negative number -N, repeat that many times in backward direction.</li> </ul>		
Erlang syntax checking  Using either: • flycheck or • flymake	Syntax checking for the Erlang programming language can be done with Emacs built-in flymake as well as with the external package flycheck.  To activate either set the pel-use-erlang-syntax-check user option is set to either 'use-flycheck or 'use-flymake.  By default, the syntax checker is not automatically launched. If you want to start your selected syntax checker as soon as any Erlang file is opened, add 'erlang-mode to the pel-modes-activating-syntax-check user-option.  flymake is built-in Emacs. The Emacs erlang package provides erlang-flymake to use with Erlang.  PEL automatically installs and activates flycheck when pel-use-goflymake user option is set to 'use-flycheck.  Flymake has several customizable variables, which some listed here:				
See also: • SyntaxCheck	flymake-no-changes-time     flymake-start-syntax-chec     The following variable control r     flymake-wrap-around: If n     flymake-diagnostic-types-	out: time to wait after last ik-on-newline: t to check a navigation to next or previou on-nil, moving to errors wra alist: Alist ((KEY . PROPS))			
Activate/deactivate selected syntax checker	<f12> ! <f11> SPC e !</f11></f12>	(pel-erlang-toggle- syntax-checker)	Toggle the selected Erlang syntax checker mode on/off.  The syntax checker activated or deactivated is either flycheck or flymake, as selected by the user-option variable `pel-use-erlang-syntax-check'.  See the required settings above to activate this command and select the syntax checker.		
Go to next flymake diagnostic	M-n	(flymake-goto-next- error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.		
Go to previous flymake diagnostic	м-р	(flymake-goto-prev- error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.		
Compiling Erlang Code		ed to compile the files. The	ce code files to .beam files located in the same directory as the source code. Detected errors are e buffer shows the location of error and the error description. The following commands are used		
Compile code	• C-c C-k • <f12> M-c • <m-f12> M-c</m-f12></f12>	(erlang-compile)	Compile Erlang module in current buffer.  If buffer visiting file was modified and not saved, prompts the user to save it first.  Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command.  The buffer lists the errors. Hitting RET on the error file/line move point to that line in the Erlang file buffer. The RET key is bound to (compile-goto-error &optional EVENT)  It's also possible to use the next-error and previous error.		
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output.  • Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.		
Move to next compile error	• C-x ` • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; • negative means move back to previous error messages. • Just C-u as a prefix means reparse the error message buffer and start at the first error.  This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.		
Move to previous compile error	• M-g p • M-g M-p	( <b>previous-error</b> &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative).  This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.		
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.		
Move to previous compilation or Flycheck detected error	С-с С-р	(edts-code-previous- issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.		
Erlang Shell	Commands to explicitly launch comint.el library running in erla		that runs under an Emacs inferior-erlang process controlled by the comint mode from the		
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.		
Start new Erlang Shell	<f11> z r e</f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer.  • The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started.		
	<f12> z</f12>		<ul> <li>C-c C-z starts the Erlang Shell from the Erlang Mode.</li> <li><f11> z r is available globally and will work as long as the erl executable is accessible.</f11></li> <li>Under PEL this command is available only when the pel-use-erlang user option is set to t.</li> </ul>		
Work around to issues in the <u>Erlang Shell</u>	When running the Erlang Shell inside Emacs, you may run into some issues. They are listed here along with work-arounds.  • Redundant command echo:  On some systems the Erlang shell annoyingly echoes each typed command. If this is the case for your system, PEL provides a fix:  Set the pel-erlang-shell-prevent-echo user option to t. After doing that execute pel-init or restart Emacs.  • Typing Ctrl-G does not open the Erlang JCL Command Menu: work-around: type the following instead: C-q C-g RET  Unfortunately the above workaround does not work when the Erlang shell is launched inside an Emacs vterm shell (see ∑ Shells).				
Erlang Shell: Command History	The following commands can be used to retrieve previously issued Erlang shell commands at the shell prompt.  Erlang shell command history file:  The Erlang shell history controlled by Emacs is saved inside a file the is restored when opening a new shell: commands from previously opened Erlang shells are also available.  Within an Emacs inferior-erlang the You can also use the Erlang shell commands to access the local shell history.				
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.		
Previous shell command	м-р	(comint-previous-input ARG)	Cycle backwards through Erlang shell input history, saving input.		
		,			

Description	<u>Keystroke</u>	Function	<u>Note</u>	
Using Man inside	Emacs provide 2 main comma			
Emacs and	<ul> <li>Both of these are much mor They are:</li> </ul>	re powerful than the usual m	nan reader available on the shell allowing navigation across man pages and opening hyperlinks.	
support Erlang Man pages	The man command uses     WoMan: Browse Unix Ma		Man" a complete implementation. It has some formatting limitations compared to man but it's a Windows.	
See also: <u><b>∑ Help/Info</b></u>	To see Erlang man pages using the man command:  On most systems the Man pages for Erlang are not available to the man utility and therefore not available for man inside Emacs. There are several ways this can be remedied:  One is to set the MANPATH environment variable to include the directory where these files are located. Then man can be used outside and insi Emacs to access Erlang's man pages. For example the following lines can be stored inside a shell script to do this:  MANPATH=/usr/local/Cellar/erlang/22.3.4/lib/erlang/man: `manpath` export MANPATH  Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add the ca			
	of Emacs man to fin the Erlang's man pages without modifying the capabilities of the parent shell. For example, if we want to use the same di as the above example we need to set the Man-switches which is normally set to nil to the following value:  "-M'manpath':/usr/local/Cellar/erlang/22.3.4/lib/erlang/man"  The second alternative can be used to add other directories for the man pages of other programming languages while leaving the ability to have shells that have their own value of MANPATH. That might be very useful for someone that uses different versions of Erlang in a system and need.			
	MANPATH and therefore p MANPATH and buses man To only see Erlang topics in I	roviding the man pages fron 's ability to view several page		
	directory only. You must all See my description on hove	so ensure that a whatis file in the solution of the solution o		
	EDTS (see below) support	s the ability to download and cess sections inside the man	f Erlang used by various projects: d access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides it's ne pages, allowing EDTS driven man page access to co-exist with manual man command	
About Erlang	environment variable. To senvironment variable wher	ironment group, the pel-er support the ability to open the you select the version of E	o their man pages rlang-man-parent-rootdir user-option can be set to read the man parent directory name from an the man files related to a specific version of Erlang available to the parent OS shell, set the firlang available to the OS shell and set the name of the environment variable in the pel-erlang- installing Erlang pages of the About Erlang document that describes an setting such an editing	
	<ul> <li>Creating whatis files</li> <li>Using the Erlang Mar</li> <li>Using Specialized OS</li> </ul>	files within Emacs		
See also: <u>▼ Menus</u>	Use the following commands to You can also use the toolba		e inside Emacs. th < <b>£10&gt;</b> ) in the Erlang section.	
Open a man page inside an Emacs buffer See also:	• <f11> ? m • %-M</f11>	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because:  • the links are active and can be followed. When the man page describes a directory or file, emacs will open the file or the directory (in direct mode) when pressing RET over the link.  • You can navigate easily between sections (n/p will move to the next/previous section)	
• <u>S Help/Info</u> • <u>S Customize</u>			<ul> <li>You can use any of the searches.</li> <li>You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer.</li> <li>See all keys available in mode, with <f1> m or <f11>? k m.</f11></f1></li> <li>The man command prompts, using the word at point as the default.</li> <li>PEL key sequence to customize man: <f11> <f2> E m</f2></f11></li> </ul>	
Open a man page without external man process: woman See also:  >	<f11> ? w</f11>	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows).  PEL key sequence to customize man: <f11> <f2> E w  text width, use word at point, etc</f2></f11>	
EDTS	EDTS - Erlang Developr	nent Tool Suite		
	The commands in the follo	wing rows require the EDTS	external package. PEL activates it when the <b>pel-use-edts</b> user option is set to <b>t</b> . If you want set <b>pel-use-edts</b> to <b>start-automatically</b> instead of <b>t</b> .	
Erlang Project settings	EDTS is customizable through it edts customization group. With PEL you can open it, with other Erlang specific groups with <f12> <f3>.  EDTS also uses an external .edts configuration file to store Erlang project specific settings. See EDTS: Configure your projects. This allows setting the following: project name, node-name, erlang-cookie, lib-dirs, start-command, top-path, dialyzer-plt, app-include-dirs, project-include-dirs, xref-error whitelist</f3></f12>			
See also: <u>Sessions</u>	<ul> <li>⚠ Desktop restoration often fails when edts-mode was active on session stored: unfortunately edts does not provide a desktop restore handler.</li> <li>♥ PEL does, however provide a desktop restore handler for EDTS which detects edts-mode failures and protect the desktop restoration.</li> <li>▶ If EDTS has not been activated yet, the only EDTS specific key available is <f12> M-SPC to activate it. Once it's activated the other keys are available.</f12></li> </ul>			
Toggle EDTS mode	<f12> M-SPC</f12>	(edts-mode &optional	Turn EDTS mode on or off.	
	<f11> SPC e M-SPC</f11>	ARG)	<ul> <li>EDTS is an easy to set up Development-environment for Erlang.</li> <li>EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further.</li> </ul>	
EDTS/Navigation	EDTS (see below) provides 2 commands to move point across Erlang functions: ferl-goto-previous-function and ferl-goto-next-function. They are listed above in the navigation section. The EDTS navigation functions do not support repetition prefix argument nor they support shift marking. There are other commands and key bindings to move across Erlang functions, and PEL support functions that perform the same and support repetition and shift marking. See the commands listed in the navigation section above.			
EDTS/Cross References			It supports navigating in Erlang source code running in the current and remote nodes. e in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11>	
Find definition of identifier at point	м	(edts-find-source- under-point)	Goto the source code that: defines the function being called at point or header file included at point. For remote calls, contacts an Erlang node to determine which file to look in, with the following algorithm:  • Find the directory of the module's beam file (loading it if necessary).  • Look for the source file in:  • Directory where source file was originally compiled.  • Todo: Same directory as the beam file  • Todo: Again with /ebin/ replaced with /src/  • Todo: Again with /ebin/ replaced with /erl/ Otherwise, report that the file can't be found.	

<u>Description</u>	<u>Keystroke</u>	Function	Note
Go back to where M	м-,	(edts-find-source-	Unwind back from uses of 'edts-navigate'-commands.
was last issued  Lists caller of function	• C-c C-d w	unwind) (edts-xref-who-calls)	Page-up a manu of all callers of the function at point
at point	• <f12> w</f12>	,	Pops-up a menu of all callers of the function at point.
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who- calls)	Redo previous call to edts-who-calls.
Find a function in the current module	• C-c C-d f • <m-f12> M-f</m-f12>	(edts-find-local- function SET-MARK)	<ul> <li>Find a function in the current module.</li> <li>List local functions in the mini-buffer. Support completion. Move point to selected one.</li> <li>With C-u prefix, push mark before moving point.</li> </ul>
Find a module in the current project	• C-c C-d F • <m-f12> M-g</m-f12>	(edts-find-global-function)	Find a module in the current project.  • List project modules in the mini-buffer. Support completion. Open the file of selected one.
EDTS/AHS Editing	in all of the buffer. The automa	atic symbol highlighting mod tts to 1.0 second.	s), and provides commands to modify the name of the highlighted name in the current function or de starts when the cursors stays on a symbol for a period longer than the value identified by the nove point away from the highlighted area.
Edit all highlighted symbols in current function	• C-c C-d e • <f12> e</f12>	(edts-ahs-edit-current-function)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current function.  • Activates ahs-edit-mode with edts-current-function range-plugin.
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer.  • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	Refactor the expression(s) in the region as a function.  The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original function.  New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring.  This command requires Erlang syntax tools package to be available in the node, version 1.2 (or perhaps later.)
EDTS/Man	pages per project, so it is poss	sible to have several Erlang	etion using the information extracted from Erlang Man pages. EDTS maintains a set of Erlang man projects each one with a different version of Erlang and their corresponding man pages. I man commands described above in this table.
Download, install, select Erlang Man pages	<f12> `</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands.
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip.
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function. Find and show the man-page documentation for the Erlang module:function.
EDTS Code Analysis		/ II. II. II.	
Compile current buffer	<f12> a c</f12>	(edts-code-compile- and-display)	Compiles current buffer on node related to that buffer's project.
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION-RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.
EDTS/Debug			
Toggle breakpoint	• C-c C-d b • <f12> d b</f12>	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.
List breakpoints	C-c C-d M-b • <f12> d B</f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle- interpreted)	Toggle the interpretation state for module in current buffer.
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
EDTS/Erlang Node			
Display EDTS Erlang Node Name	<f12> N</f12>	(edts-buffer-node- name)	Print the node sname of the erlang node connected to current buffer.  The node is either: The module's project node, if current buffer is an erlang module, or The buffer's erlang node if buffer is an edts-shell buffer. The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module such as an otp-module or a module loaded by ~/.erlang).
Start an EDTS controlled Erlang Shell	<f12> x</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell.
Start EDTS server	<f12> X</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).
Rendering markup embedded in comments	using these markup languages	to describe UML diagrams	specific markup code embedded inside Erlang source code comments. This can be useful when or finite-state machines for example.
Preview UML diagram	You can also use Graphviz, see	e M Graphviz Dot (pel-render-	Render the PlantUML markup embedded in current mode comment.
free minutes and the same of	11127 U	(pei-render-	Hender the PlantUML markup embedded in current mode comment.

Description	<u>Keystroke</u>	Function	<u>Note</u>	
in current plantUML region of commented source code	<f11> SCP e u</f11>	PREFIX &optional POS)	<ul> <li>Uses prefix (as PREFIX) to choose where to display it:</li> <li>4 (when prefixing the command with C-u) -&gt; new window</li> <li>16 (when prefixing the command with C-u C-u) -&gt; new frame.</li> </ul>	
See also: M PlantUML			<ul> <li>else -&gt; new buffer</li> <li>This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment.</li> </ul>	
	Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command.  PlantUML block and issuing this command.  Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.			
Development Tool	The following commands are u			
Show syntactic	C-c C-s		Show syntactic information for current line.	
information		information)	Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.	
LSP support:  • Isp-mode  • erlang Is  • erlang Is required	The <u>erlang is</u> Erlang server     The <u>erlang is</u> can be	sp external package PE for LSP. You must install the configured using a YAML fit ost projects to set that up, of	by by ded via:  L activates it when the <b>pel-use-erlang-is</b> user-option is turned on (set to <b>t</b> ). It is manually. You will need Git, Erlang, rebar3 and make. The instructions are on the web-site. It is <b>erlang is.config</b> file that must be placed at the root of the Erlang project. It is only the root of the cross-reference features.	
environment	erl, escript and other Erla	ing executables. See <u>Instal</u> g_ls follow the instruction o	lling Erlang if you need to learn how to install Erlang and its tools. n the <u>erlang Is GitHub page</u> : git clone it, then run make and make install.	
• <u><b>S Customize</b></u> Isp-mode	settings are probably what you  lsp-log-io  lsp-ui-sideline-enable  lsp-ui-doc-enable	u may want to customize: control whether the LSP pi control whether LSP displa control whether LSP displa	p-mode customization group. With PEL you can access it via <f12> L <f3>. The following rocess is logging its I/O. Useful for debugging LSP support. By information about the current code line. By documentation about the current code symbol. It is a command to the current code symbol.</f3></f12>	
Toggle code documentation display	<f11> SCP e L D <f12> L D</f12></f11>	(pel-toggle-lsp-ui-doc &optional LOCALLY)	Toggle the display of code documentation. The initial state is set by the 'lsp-ui-doc-enable' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.	
Toggle LSP I/O logging	<f11> SCP e L I <f12> L I</f12></f11>	(pel-toggle-lsp-log-io &optional LOCALLY)	Toggle the logging of LSP I/O.  • The initial state is set by the ' <b>Isp-log-io</b> ' user-option.  • By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.	
Toggle display of information on current line	<f11> SCP e L L <f12> L L</f12></f11>	(pel-toggle-lsp-ui- sideline &optional LOCALLY)	Toggle the display of information of the current line.  The initial state is set by the 'lsp-ui-sideline-enable' user-option.  By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.	
Erlang LS Features	Overview of the features provide  Code completion  Go to Definition  Go to Implementation of OTP Behaviours  Signature Suggestions  Diagnostics on file open/ save:  Compiler Diagnostics  Dialyzer Diagnostics  Elvis Diagnostics	Edoc support     Navigation to Included Files     Find/Peek References	<ul> <li>LSP Lenses: lsp-avy-lens</li> <li>LSP sideline:         <ul> <li>enable with: (setq lsp-ui-sideline-enable t)</li> <li>Use M-x lsp-execute-copde-action to trigger quick-fix actions</li> </ul> </li> <li>Erlang Project-Specific LS Configuration:</li> <li>Erlang LS is customizable by using a YAML syntax file called erlang ls.config that should be placed in the root directory of the project.</li> </ul>	
Isp-mode features	<ul> <li>Completion at point</li> <li>traditional popup with company-mode</li> <li>Code navigation, with</li> <li>lsp-find-references</li> <li>Symbol highlights</li> <li>Code Lenses . The Erlang LS configuration provides</li> <li>ct-run-test: display some Erlang LS server info on top of each module. For debug only.</li> <li>show-behaviour-usages: show the number of modules implementing a behaviour.</li> </ul>			
Isp-mode integrations   see also:	Isp-mode supports integration with:  •			
LSP key bindings:  • Isp-mode • erlang Is See also:  > Input Method	<ul> <li>Key bindings: The Isp-mode is a minor mode and provides customizable prefix key for its key bindings. The default key prefix is s-1.</li> <li>Since the <u>super modifier key</u> is not always available, it can be modified through customization: change the <u>Isp-keymap-prefix</u> value. This can be dowith <u>M-x customize-option</u> or with PEL via the <f11> <f2> o key sequence.</f2></f11></li> <li>With PEL, the following keys are good replacement candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.</m-f9></f9></f9></li> <li>The key bindings shown below show the standard s-1 key prefix.</li> <li>If you change <u>Isp-keymap-prefix</u> that would be replaced with your selected prefix key.</li> </ul>			
Display LSP workspace log buffer	s-l L	(Isp-workspace-show- log WORKSPACE)	Display the log buffer of WORKSPACE.	
Validate LSP performance settings	s-1 d	(Isp-doctor)	Validate performance settings and write report in a *lsp-performance* buffer.	
Reformat Erlang file	s-1 = =	(Isp-format-buffer)	Ask the server to format this document.	
Add directory to the list of workspace folders	s-1 F a	(Isp-workspace-folders- add PROJECT-ROOT)	Add PROJECT-ROOT to the list of workspace folders.  • Prompts for the directory.	
Remove a directory from the workspace blacklist	s-1 F b	(Isp-workspace- blacklist-remove PROJECT-ROOT)	Remove PROJECT-ROOT from the workspace blacklist.	
Remove directory from the list of workspace folders	s-1 F r	(Isp-workspace-folders- remove PROJECT- ROOT)	Remove PROJECT-ROOT from the list of workspace folders.	
Find Identifier definitions	s-1 G g	(Isp-ui-peek-find- definitions & optional EXTRA)	Find definitions to the IDENTIFIER at point.	

Description	<u>Keystroke</u>	Function	<u>Note</u>
Find symbol implementation locations	s-1 G i	(Isp-ui-peek-find- implementation &optional EXTRA)	Find implementation locations of the symbol at point.
Find references	s-1 G r	(Isp-ui-peek-find- references &optional INCLUDE-DECLARATION EXTRA)	Find references to the IDENTIFIER at point.
Find symbols	s-1 G s	(Isp-ui-peek-find- workspace-symbol PATTERN &optional EXTRA)	Find symbols in the worskpace. The symbols are found matching PATTERN.
Toggle diagnostic modeline	s-1 T D	(Isp-modeline- diagnostics-mode &optional ARG)	Toggle diagnostics modeline.
Toggle LSP protocol logging	s-1 T L	(Isp-toggle-trace-io)	Toggle client-server protocol logging.
Toggle current-line status information	s-1 T S	(Isp-ui-sideline-mode &optional ARG)	Minor mode for showing status information for current line.  • Displays code status such as definition errors, etc
Toggle code action on modelling	s-1 т а	(Isp-modeline-code- actions-mode &optional ARG)	Toggle code actions on modeline.
Toggle headline breadcrumbs	s-1 T b	(Isp-headerline- breadcrumb-mode &optional ARG)	Toggle breadcrumb on headerline.  • When active the list of directories are listed on the header line. In graphics mode these are buttons you can use to change directory.
Toggle hover information	s-1 T d	(Isp-ui-doc-mode &optional ARG)	Minor mode for showing hover information in child frame.  When active, information about symbol at point is shown in a pop-up overlay area. In graphics mode the information has links that can be used to open web-located information.  For small window the information may cover too much code, use this command to toggle in and out of view. Also note that when the point is toward the bottom of a window the information window may not show completely and you may have to scroll your window.
Toggle symbol highlighting	s-1 T h	(lsp-toggle-symbol- highlight)	Toggle symbol highlighting.
Toggle code-lens	s-1 T 1	(Isp-lens-mode &optional ARG)	Toggle code-lens overlays.  • Code-lens show information like # times a specific function is referenced.
Execute code action	s-1 a a	(Isp-execute-code- action INPUT0)	Execute code action ACTION.  If ACTION is not set it will be selected from 'lsp-code-actions-at-point'.  Request codeAction/resolve for more info if server supports.
Highlight all relevant references to symbol at point	s-1 a h	(Isp-document- highlight)	Highlight all relevant references to the symbol under point.
Click LSP lens via avy	s-1 a 1	(Isp-avy-lens)	Click lsp lens using 'avy' package.  • The code lens must be active. Use s-1 T 1 to activate it if it's not active.
Apropos search for symbol/regexp	s-1 g a	(xref-find-apropos PATTERN)	Find all meaningful symbols that match PATTERN.  Can be used to search symbol outside project.  The argument has the same meaning as in 'apropos'.  The result is shown in a *xref* buffer.
Find definitions of symbol at point	s-1 g g	(Isp-find-definition &key DISPLAY-ACTION)	Find definitions of the symbol under point.
Find implementations of symbol at point	s-1 g i	(Isp-find- implementation &key DISPLAY-ACTION)	Find implementations of the symbol under point.
Find references of symbol at point	s-1 g r	(Isp-find-references &optional INCLUDE- DECLARATION &key DISPLAY-ACTION	Find references of the symbol under point.  • The result is shown in a *xref* buffer.
Trigger display hover information	s-1 h g	(Isp-ui-doc-glance)	Trigger display hover information popup and hide it on next typing.
Display documentation of symbol at point in *lsp-help*	s-1 h h	(Isp-describe-thing-at- point)	Display the type signature and documentation of the thing at point.  • Display help about symbol at point inside a *lsp-help* buffer.  • Useful in terminal mode as you can navigate inside the buffer and used other functions to open identified URL references.
Refactor source import	s-1 r o	(Isp-organize-imports)	Perform the source.organizeImports code action, if available.
Rename symbol at point See also:  Search/Replace	s-1 r r	(Isp-rename NEWNAME)	Rename the symbol (and all references to it) under point to NEWNAME.  For renaming the arguments of a function, the <u>iedit mode</u> is more appropriate. It supports restricting the scope to the current function. See <u>Search/Replace</u>
Disconnect LSP	s-1 w D	(Isp-disconnect)	Disconnect the buffer from the language server.
Describe LSP session	s-1 w d	(Isp-describe-session)	Describes current 'Isp-session'.  • Show available tools and the available capabilities  • Shows the information inside a LspBrowser buffer.
Shut LSP workspace down	s-1 w q	(Isp-workspace- shutdown WORKSPACE)	Shut the workspace WORKSPACE and the language server associated with it
Restart LSP workspace	s-1 w r	(Isp-workspace-restart WORKSPACE)	Restart the workspace WORKSPACE and the language server associated with it
Activate LSP	s-1 w s	(Isp &optional ARG)	Entry point for the server startup.     When ARG is t the lsp mode will start new language server even if there is language server which can handle current language.     When ARG is nil current file will be opened in multi folder language server if there is such.     When 'lsp' is called with prefix argument ask the user to select which language server to start.
Treemacs support  • ∑X Treemacs	The <u>treemacs</u> and <u>Isp-treemacs</u> external packages described packages respectively activated by PEL user-options pel-use-treemacs and pel-use-lsp-treemacs, provide extra features that help Erlang development. When these are activated PEL provides bindings for the <u>Isp-treemacs</u> features.  Configure Isp-treemacs by accessing the Isp-treemacs customization group. With PEL use <f12> w <f3> from an Erlang buffer.</f3></f12>		
Open LSP Treemacs error list window.	<f12> w e</f12>	(Isp-treemacs-errors- list)	Display an error list window at the bottom of the frame.  • The buffer uses the treemacs-mode and supports its commands and key bindings.  • See **\sum x** Treemacs** for the list of commands and key bindings.  • To close the window, kill its buffer with C-x k
• Quick fix	x	(Isp-treemacs-quick-fix &rest ARGS)	If possible, proposes a quick code fix for the error at point.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Open LSP Treemacs symbol window	<f12> w s</f12>	(Isp-treemacs-symbols)	Show symbols view.  • To close the window, kill its buffer with <b>C-x k</b>
Open LSP Treemacs references window	<f12> w x</f12>	(Isp-treemacs- references ARG)	Show the references for the symbol at point. Issue from an Erlang buffer.  With a prefix argument, select the new window and expand the tree of references automatically.  To close the window, kill its buffer with C-x k
Open LSP Treemacs implementations window	<f12> w i</f12>	(Isp-treemacs- implementations ARG)	Show the implementations for the symbol at point. Issue this command from an Erlang buffer.  With a prefix argument, select the new window expand the tree of implementations automatically.  To close the window, kill its buffer with C-x k
Open LSP Treemacs <u>call hierarchy</u> <u>window</u>	<f12> w c</f12>	(Isp-treemacs-call- hierarchy OUTGOING)	Show the incoming call hierarchy for the symbol at point.  • With a prefix argument, show the outgoing call hierarchy.  This does not seem to have been implemented for Erlang.
Open LSP Treemacs type hierarchy window	<f12> w t</f12>	(Isp-treemacs-type- hierarchy DIRECTION)	Show the type hierarchy for the symbol at point.  • With prefix 0 show sub-types.  • With prefix 1 show super-types.  • With prefix 2 show both.   This is not implemented for Erlang.

## Emacs & Erlang - References

Document	Notes	
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.	
Erlang versions	Erlang Versions - Version Scheme     Erlang Support, Compatibility, Deprecations, and Removal	
Erlang/OTP @ Github	Erlang source code	
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, Erlang Issue Tracker, events.	
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.	
Erlang/BEAM	Erlang was the first of one of several programming language that runs on the BEAM VM.	
Good introduction presentations on Erlang	<ul> <li>The soul of Erlang and Elixir • Saša Jurić • GOTO 2019         A very good presentation that captures the essence of why Erlang is so important. Fast pace. A must see. A great presentation to show people that may be reluctant to use the technology.     </li> <li>The Do's and Don'ts of Error Handling • Joe Armstrong • GOTO 2018</li> </ul>	
Erlang References		
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.	
A Concise Guide to Erlang	A very nice quick reference. From David Matuszek, University of Pennsylvania	
Erlang Code Guidelines		
Erlang Programming Rules and Conventions	Official Ericsson AB Erlang guidelines.	
Inaka's Erlang Coding Standards & Guidelines	Guideline used at Inaka, published on Github.	
EDoc User's Guide	Describes how to document code.	
Erlang Books	There are several printed and online Erlang books. Erlang's FAQ lists several of them. The following lists some extra ones.	
Adopting Erlang	A great and recent (2019 and later) online books on Erlang Development that provides information not available in the Erlang introduction books. Describes how to install Erlang, and how to setup editing tools.  A must read to setup Erlang development. This is still work in progress as of May 2020.  Each page has a date time stamp.	
Erlang Information Sites		
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.	
about-erlang     trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang.  • about-erlang provides general information about Erlang, including:  • Learning Erlang, a table with links to resources to learn Erlang.  • Installing Erlang, describes various ways to install Erlang on macOS.  • Tools for Erlang, describes tools you can use for Erlang development.	
Emacs and Erlang Man files		
How to create a local whatis file	Show how to create a missing whatis file for a set of man pages.	
The Erlang mode for Emacs (user guide) Erlang mode for Emacs (man page)	On the <u>erlang.org</u> site. Start here. Describes the 2 files (erlang.el and erlang-start.el) provided by the Erlang mode support, how to set them up for various operating systems. Note, however, that PEL provides the setting for you. It also provides an overview of the various features the package provides.  • I found bugs in the <u>erlang man</u> page in the <b>Edit- Moving the marker</b> section. 1) it's the point that is moved, not the marker, 2) C-a is not an Emacs key prefix, so their key binding descriptions like C-a M-a and C-a M-e are invalid. Reported as <u>ERL-1314</u> .  • There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric functions and variables.  • The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -> on a function definition line.  • Another issue: inside the OS-level erlang shell, we can tab-completion a module:function string, but that does not work inside the emacs erlang shell.	

**Emacs tools for Erlang** 

Document	Notes
EDTS	EDTS: stands for: The Erlang Development Tool Suite. See also:  • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube  • EDTS:  • configure your project  • One Primary EDTS node  • 1 node per open project  • To setup an Erlang project: a .edts file in the project:  : name "my-project"  : otp-path "path/to/otp"  : node-name "project-node-name"  : lib-dirs '("lib" "deps")
How to install EDTS	Describes some aspects of EDTS and links that may be useful. Lists the requirements.  After installing EDTS, I got several compile errors, and had to install the following other modules: - auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?
Language Server Protocol	Language Server Protocol @ Wikipedia     Language Server Protocol Specifications web site     Language Server Protocol @ Github
LSP for Erlang	LSP support for Erlang is done using the following:  The lsp-mode Emacs Lisp package  The erlang ls Erlang server
company-mode; Modular in-buffer completion framework for Emacs	
Using Tags with Erlang	
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the pel-erlang-shell-prevent-echo is set to t. To activate after setting it: execute pel-init or restart Emacs.