macs support for the TCL Programming Language

D				
Description	Keystroke	Function	Note	
Tcl Editing	Emacs built-in support for Tcl is provided by the tcl.el file which provides the tcl-mode to edit Tcl source code and the inferior-tcl-mode to run a Tcl REPL in a buffer.			
	PEL provides extra support, described in this table, when the pel-use-tcl user-option is set to t.			
	• As of Emacs 30.2 there is no Tree-Sitter aware mode for TCL implemented yet. See <u>∑ Tree Sitter</u> and <u>♠ Tree-sitter</u>			
Last updated on:	2025-10-15			
Open this PDF file.	<f11> SPC t <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-	Open the No I local PDF. If the prefix argument (like C-u or M) is used, then it opens	
See also: <u>∑ Help/Info</u>	<f12> <f1></f1></f12>	PAGE)	the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.	
<u>∑ Customize</u> PEL Tcl	<f11> SPC t <f2></f2></f11>	(pel-customize-pel &optional OTHER-	Customize PEL Tcl support.	
support	<f12> <f2></f2></f12>	WINDOW)	If OTHER-WINDOW is non-nil (use C-u), display in another window.	
∑ Customize Emacs Tcl support	<f11> SPC t <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs Tcl support (which is currently placed in C group): C • If OTHER-WINDOW is non-nil (use C-u), display in another window.	
	<f12> <f3></f3></f12>			
Select tcl-mode for	<f12></f12>	(pel-as &optional FORCE)	Inside a fundamental-mode buffer, interactively select major mode for the buffer. Re-do it	
extension-less file	(112)	(per-as aoptional i Onoc)	with arg. see Create extension-less executable scripts with PEL.	
The <f12> key is available only until a</f12>			amental-mode', when the <f12> key binding is available for it.</f12>	
PEL controlled major mode is activated.	After being used once in a buffer the major mode is selected and the PEL key binding will not be available when PEL supports the major mode. • For Tcl file, select tcl. It will insert a shebang line specified by pel-tcl-shebang-line user option.			
Then it becomes a	 For Icl file, select tcl. It will insert a shebang line specified by delta pel-tcl-shebang-line user option. For Tcl expect script file, select expect. It will insert a shebang line specified by delta pel-tcl-expect-shebang-line user option. 			
buffer prefix key.	PEL defines the (as &optional FORCE) alias unless defined pel-has-alias-as user-option is set to nil. You can use M-x as to invoke it.			
Show PEL setup for	<f12> ? (pel-tcl-setup-info &optional APPEND) Display Tcl setup information inside a *pel-tcl-info* buffer with buttons providing quick</f12>			
TCL setup for	<f11> ?</f11>	(per-ter-setup-inio αυριιοπαι ΑΓΓΕΝΟ)	access to the customization buffer of each variable shown. The information shown includes the value and interpretation of:	
			the user options controlling indentation and hard tab width rendering.	
			To append information in the buffer instead of clearing the previous content type any prefix argument (such as C - u) before the command keystroke.	
Comments				
Toggle display of	<f11> ; ;</f11>	(hide/show-comments-toggle	Toggle hiding/showing of comments in the active region or whole buffer.	
comments in buffer or active region		&optional START END)	• If the region is active then toggle in the region. Otherwise, in the whole buffer. This requires the hide-comnt.el package (see © Comments). PEL activates it when	
See also: <u>N</u> Comments			the pel-use-hide-comnt user option is t.	
Generic code	Several mechanisms have h	peen developed to allow easy insertion of pro-	edefined text in Emacs. PEL does not yet define skeletons for Tcl. You can use the	
skeletons	generic one.			
• Emacs provides the built-in skeleton mechanism and the tempo skeletons. • PEL supports both. They are used a little bit differently. PEL provides generic tempo skeletons you can use for Tcl until PEL adds Tc			ides generic tempo skeletons you can use for Tcl until PEL adds Tcl-specific skeletons.	
∑ Inserting TextT Templates	 PEL provides key bindings to the tempo skeletons: the generic code templates, accessible via the <f6> prefix key, and the language-specific code templates, accessible via the <f12> key prefix.</f12></f6> 			
∑ Customize PEL	<f6> <f2></f2></f6>	(pel-customize-pel &optional OTHER-	Open the customization groups that control the format of the various skeletons including the	
Text Insertions control for Tcl code skeletons.	4610× 4610× 460	• If OTHER-WINDOW is non-nil (use C-11) display in other window	generic skeleton used by the <f6> h key and the <f12><f12> h key (see below). • If OTHER-WINDOW is non-nil (use C-u), display in other window.</f12></f12></f6>	
	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-generic-skels &optional OTHER-WINDOW)		
Insert generic file module header block — Language agnostic	<f6> h</f6>	(pel-generic-file-header)	Insert a file header block at the top of the file. Works only for buffer visiting a file.	
	4610× 4610× 1		↑ The command key binding <f6> h is available only 1 second after Emacs has started. ↑ As mentioned above PEL does not yet define Tcl-specific skeletons, this uses the generic</f6>	
	<f12> <f12> h</f12></f12>		As mentioned above PEL does not yet define Ici-specific skeletons, this uses the generic one.	
After inserting the template, navigate though areas that must be filled with: • forward: C-c. • backward: C-c,	Specify the format of the header via the user-options in the pel-pkg-generic-code-style customization group accessible via <f6> <f2></f2></f6>			
	• Inside a Tcl buffer, <f12> <f2> provides access to the following customization groups:</f2></f12>			
	Shifter inserting a template, use tempo-forward-mark and tempo-backward-mark to move to the beginning of each section that must be filled.			
Toggle pel-tempo-	<f6> SPC</f6>	(pel-tempo-mode &optional ARG)	Toggle PEL tempo mode on/off.	
mode	<f12> <f12> SPC</f12></f12>	,		
	PEL tempo mode activates C-c . and C-c , as well as to C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-			
	mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set of keys are only available in graphics mode. d The pel-generic-file-header command inserts the text using a tempo skeleton: the PEL tempo mode is automatically activated by typing < £6> h.			
Evnand any ton in			, , , , ,	
Expand any tag in template Note: PEL default skeleton does not use tags.	<f6> <f12></f12></f6>	(tempo-complete-tag &optional SILENT)	Look for a tag and expand it. All the tags in the tag lists in 'tempo-local-tags' (this includes 'tempo-tags') are searched for a match for the text before the point. The way the string to match for is determined can be altered with the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all.	
	<f12> <f12> <f12></f12></f12></f12>			
			If a single match is found, the corresponding template is expanded in place of the matching string.	
			If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal.	
			If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer	
			containing possible completions is displayed.	

Emacs & Tcl — References

Document	Notes
The Tcl Programming Language	Tcl @ Wikipedia Tcl home