Text Modes

<u>Operation</u>	<u>Keystroke</u>	Function	Note	
Text Modes	Emacs support naviga	ation and also search for words	and symbols, and the concept of "words" can be modified to include or exclude underscores and	
See also: • <u>Search/Replace</u> • <u>Swhitespace</u>	hyphens. It supports the following special mode: • superword-mode that treats words separated by hyphen and underscores as a single entity, useful for programming languages using snake case like C, C++, Erlang. • subword-mode that treats sections of camelCase and PascalCase as distinct words. That is useful when editing portions of these longer symbols. • As of Emacs 23.2 the CC Mode c-subword-mode is obsolete and has been replaced by the more general subword-mode. PEL provides the ability to activate these modes automatically for various major modes by identifying the major modes in the following user option lists: • pel-modes-activating-superword-mode			
	 pel-modes-activating-subword-mode Emacs also has: several modes that deal with whitespace, drawing modes that allow you to draw in text and navigate over 'void' space different way of handling the concept of marking text in a buffer. The commands to control all those are listed in this table, starting with the commands to get help in Emacs and customize these features.			
Open this PDF file.	<f11> t m <f1></f1></f11>	(pel-help-pdf &optional	Open the local copy of the <u>Text Modes</u> PDF file unless a command prefix (like C-u) was used.	
See also: <u>Nelp/Info</u>	<f11> t m <f2></f2></f11>	(pel-customize-pel	In that case it opens the Github-hosted file instead. Customize PEL cross-reference support: what modes automatically activate superword-mode and	
<u>Secustomize</u> Text Mode support	CIII> t m <12>	&optional OTHER-WINDOW)	subword-mode. • If OTHER-WINDOW is non-nil (use C - u), display in other window.	
Switch Insert/Overwrite mode	• <insert> • <esc><kp-0> • <f11> t o • <f11> `</f11></f11></kp-0></esc></insert>	(overwrite-mode &optional ARG)	Toggles the overwrite mode on/off • With a prefix argument ARG, enable Overwrite mode if ARG is positive, and disable it otherwise. • ► The <insert> key is not available in macOS keyboards. • For keyboards with numerical keyboards the <esc><kp-0> is quite close since <kp-0> is often used as the insert key.</kp-0></kp-0></esc></insert>	
Binary file overwrite only mode	<f11> t 0</f11>	(nhexl-overwrite-only- mode &optional ARG)	Minor mode where text is only overwritten. Insertion/deletion is avoided where possible and replaced by overwriting existing text, if needed with 'nhexl-overwrite-clear-byte'. The nhexl mode must first be activated to edit the file in binary mode. Requires the nhexl-mode package. PEL activates this when the pel-use-nhexl user option is set to t.	
Make Info control text visible/invisible (toggle visible mode)	<f11> t m v</f11>	(visible-mode &optional ARG)	Toggle making all invisible text temporarily visible (Visible mode). With a prefix argument ARG, enable Visible mode if ARG is positive, and disable it otherwise. Useful for developing info files, where some characters are not visible by default. Same in Orgmode (for example to show everything, or to show the syntax of links without expanding anything).	
Toggle subword-mode	• <f11> t m b • <f12> M-b</f12></f11>	(subword-mode &optional ARG)	Toggle subword-mode: a minor mode that treats sections of <u>camelCase</u> and <u>PascalCase</u> as distinct words.	
See also: Search/Replace	• <m-f12> M-b</m-f12>		 With a prefix argument ARG, enable Subword mode if ARG is positive, and disable it otherwise. PEL provides the <f12> M-b key for the programming language modes where camelCase and PascalCase are popular.</f12> 	
Toggle superword-mode See also: Search/Replace	• <f11> t m p • <f12> M-p • <m-f12> M-p</m-f12></f12></f11>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats <u>snake case</u> as one word. In Lisp, '-' and '_' are treated part of words. • With a prefix argument ARG, enable Superword mode if ARG is positive, and disable it otherwise. • PEL provides the <f12> M-p key for the programming language modes where <u>snake case</u> is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12>	
Toggle sentence separators between 1 or 2 spaces	<f11> t m s</f11>	(pel-toggle-sentence-end)	Toggle definition of end of sentence between 2 and 1 space character (to help text filling). This has an impact on the commands that deal with sentences (navigation such as (backwardsentence) and (forward-sentence), kill such as (kill-sentence) and (backward-kill-sentence).	
Toggle local electric quote mode	<f11> t m '</f11>	(electric-quote-local-mode &optional ARG)	Toggle 'electric-quote-mode' only in this buffer. Useful to insert nicer-looking quote characters.	
Show state of text modes	<f11> t m ?</f11>	(pel-show-text-modes)	Display the state of the various text modes in the mini buffer.	
Text Whitespace Modes	The following Emacs command control how whitespace is shown or hidden. The following commands are also described in the Text Whitespace table.			
Toggle Whitespace Mode See also: Whitespace	• <f11> t m w • <f11> t w m</f11></f11>	(whitespace-mode &optional ARG)	Toggle whitespace visualization (Whitespace mode). With a prefix argument ARG, enable Whitespace mode if ARG is positive, and disable it otherwise. The kind of whitespace visualized is determined by the list variable <i>whitespace-style</i> , <i>whitespace-newline</i> .	
Hide/Show trailing whitespaces See also: ∑ Whitespace	<f11> t w T</f11>	(pel-toggle-show-trailing- whitespace)	Toggle highlight of the trailing whitespaces in current buffer. Toggles the value of the variable show-trailing-whitespace .	
Hide/Show trailing empty lines	<f11> t w e</f11>	(pel-toggle-indicate-empty- lines)	Toggle highlight of empty lines.	
See also: Whitespace Toggle individual elements	<f11> t w o</f11>	(whitespace-toggle-	Toggles the value of the variable <i>indicate-empty-lines</i> . • If local whitespace-mode is off, toggle the option given by ARG and turn on local whitespace-	
of whitespace-style See also: Whitespace		options ARG)	 If local whitespace-mode is on, toggle the option given by ARG and restart local whitespace-mode. 	
	toggle face visualization toggle TAB visualization s toggle SPACE and HARD SPA r toggle trailing blanks visualization toggle "long lines" visualization L toggle "long lines" tail visualization L toggle "long lines" tail visualization toggle NEWLINE visualization e toggle empty line at bob and/oc C-i toggle indentation SPACEs vis I toggle indentation SPACEs vis i toggle indentation TABs visual C-t toggle big indentation visualization C-a toggle SPACEs after TAB visual C-a toggle SPACEs after TAB: TAB toggle SPACEs before TAB visual C-b toggle SPACEs before TAB: SI		alization and HARD SPACE visualization lanks visualization es" visualization es" tail visualization E visualization e at bob and/or eob visualization on SPACEs visualization (via 'indent-tabs-mode') on SPACEs visualization on TABs visualization on TABs visualization fater TAB visualization after TAB visualization after TAB visualization after TAB: SPACEs visualization before TAB: SPACEs visualization	

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>		
Mark and Region See also: <u>> Cut & Paste</u> <u>> Marking</u>	With most editors when you type over a "selected" region, the text in the selection is automatically replaced by the new text. By default Emacs does not behave like this; instead it allows typing text while there is an active a marked region. If you want Emacs behave like other editors and automatically replace the text activate the "delete-selection-mode" with the following command.				
Toggles delete selection mode	<f11> t m d</f11>	(delete-selection-mode)	Toggles delete selection-mode on/off. In delete-selection-mode typing a character while a region is active replaces the entire region with what is typed. By default delete selection-mode is off.		
Drawing ASCII in Emacs	Emacs provides the picture-mode and artist-mode to draw ASCII-based pictures. Both are available when Emacs runs in graphics and terminal mode. However, I have not been able to use artist-mode with the mouse, even with xterm-mouse-mode active: each click just prints an ANSI sequence code. Two modes are available: • Artist Mode • Picture Mode The Picture mode can be very useful to type text in vertical fashion when for example, writing reStructuredText table or writing code in tabular fashion.				
Artist Mode	Although you can get some commands to work in terminal mode, it's best to use artist-mode when running Emacs in graphics mode.				
Toggle artist mode See also: <u>∑ Drawing</u>	<f11> D a</f11>	(artist-mode &optional ARG)	Toggle Artist mode. • With argument ARG, turn Artist mode on if ARG is positive. • Artist lets you draw lines, squares, rectangles and poly-lines, ellipses and circles with your mouse and/or keyboard.		
Picture Mode	Emacs supports the picture mode that allow you to move your cursor freely anywhere inside the window, which greatly simplify creating rectangular shapes for tables or even <i>drawing</i> ASCII-art. This work well in both graphics and terminal mode.				
Enter picture mode See also: Drawing	• <f11> D p • <f11> t p</f11></f11>	(picture-mode)	Switch to Picture mode, in which a quarter-plane screen model is used. Very useful to type text in vertical fashion when for example, writing reStructuredText table. Type C-c C-c to exit picture-mode and return to the mode previously used in the buffer.		

Text Modes — References

Topic & Link	Notes
GNU Emacs Manual: Text - Words	
GNU Emacs Manual: Text - Sentences	
GNU Emacs Manual: Text - Paragraphs	
GNU Emacs Manual: Text - Quotation Marks	
GNU Emacs Manual: Modes - Minor Modes	
GNU Emacs Manual: Programs - Other Features Useful for Editing Programs	
GNU Info Manual: Getting Started - Invisible text in Emacs Info	