## **Emacs support for the Erlang Programming Language**

Description	<u>Keystroke</u>	Function	1	Note	
Erlang Support	Emacs has no built-in support	for Erlang. A PEL support	s Erlang when <b>pel-use-erlang</b> user options is turne	ed on.	
See also: • Erlang Reference			e-tree-sitter is set to t. See <u>I Tree Sitter</u> and _	<del></del>	
PEL Manual			se-erlang to 'with-tree-sitter (as long as pel-use-tr (see <u>erlang.el source</u> ) are part of <u>OTP</u> .	ree-sitter is t and Emacs >= 30).	
<ul><li><u>about-erlang</u></li><li><u>Developing Erlang</u></li></ul>			(see <u>enang.er source</u> ) are part or <u>OTP</u> . ang-complete and <mark>₪ company-erlang ಚ</mark> activa	ted by nel-use-company-erland	
Code with PEL  set PEL Erlang	EDTS activated by pel			ned by per-use-company-chang.	
environment			ne <u>erlang Is</u> Erlang LSP server. Integrates with:		
•	• William by using helm-lsp	activated by	pel-use-helm-lsp.	activated by pel-use-Isp-ivy.	
• <u>I Hide/Show</u>	• w treemacs by using lsp-	treemacs 🛂 activated by p	pel-use-treemacs and pel-use-lsp-treemacs.		
<ul> <li>∑ Text Modes</li> <li>∑ Highlight</li> </ul>	• porigami by using Isp-or		pel-use-Isp-origami.		
<ul> <li>∑ Inserting Text</li> </ul>			neck set to 'use-flycheck, or Emacs built-in flymak e mainly been replaced by EDTS and needs mainte		
	hide-comnt.el activate		,		
	iedit activate	ed by <b>pel-use-iedit</b> .			
		ted by <b>pel-use-smart-dash</b>			
	_	ed by <b>pel-use-smartparen</b> or smartparens-mode, autor		ode to pel-erlang-activates-minor-modes	
• <u>∑ Speedbar</u>	<ul> <li>Activate smart-dash-mode or smartparens-mode automatically in erlang-mode buffers by adding their mode to pel-erlang-activates-minor-modes.</li> <li>Add electric pairing without smartparens with built-in electric-pair-local-mode: add electric-pair-local-mode to pel-erlang-activates-minor-modes.</li> </ul>				
- T Customize			ess the customization group and select pairs. g via <b>pel-activates-global-minor-mode</b> : <u>show-pa</u>	aren-mode	
• <u>∑ Customize</u>			g files to show the list of functions.		
		nented in: <u>pel-erlang.el</u> , <u>pe</u> l	-skels-erlang.el, sections of pelkey-macros.el	and <b>pel keys.el</b> and PEL files they require.	
	<ul><li>Customization:</li><li>Type <f11> <f2> q follo</f2></f11></li></ul>	wed by the group name and	RET to open the specific customization group or	one of the following key sequences.	
	pel-pkg-for-erlang: to	o activate pel-use-erlang: u	use <f11> SPC e <f2>, or <f12> <f2> fro</f2></f12></f2></f11>		
	erlang-ide group to ac erlang: w		use <f11> SPC e <f3> 1</f3></f11>		
		when <b>pel-use-edts</b> is on,			
Identify minor modes to			n, use <f11> SPC e L <f3> 1 n, use <f11> SPC e L <f3> 2</f3></f11></f3></f11>		
activate automatically in			control Erlang editing. Only some of them are deshe Erlang shell from echoing every command.	scribed here. Use Emacs for the complete list.	
erlang-mode buffers	<ul> <li>pel-erlang-activates-mi</li> </ul>	nor-modes: Schedules act	ivation of local minor modes in erlang-mode buffer	s, eg. smart-dash-mode.	
Erlang Style	<ul> <li>pel-erlang-environment gr</li> <li>pel-erlang-man-parent-</li> </ul>		t directory of Erlang man directory. The man direct	tory should hold the man1, man3, man4 and man6	
Control •			(override) the <u>erlang.el</u> erlang-root-dir user-optic cotdir is nil, you must set the erlang-root-dir user-o	on value with it which activates the appropriate Erlang	
Ericsson AB Guideline	pel-erlang-exec-path: lo	dentifies the directory where	Erlang binaries are stored.		
Inaka Guideline	pel-erlang-version-dete	ection-method: identifies a	mechanism to detect Erlang/OTP version. By defar	ult it uses an Erlang script provided with PEL.	
	• pel-erlang-code-style group:				
	When pel-erlang-fill	<ul> <li>n : column where line-wrapping occurs : maximum <i>line length</i> (defaults to 100). You can change the value or set it nil.</li> <li>l-column user option is nil, erlang-mode buffers use the global Emacs fill-column value.</li> </ul>			
			parators are used in Erlang code templates (see the ether secondary separator lines are inserted by so		
	pel-erlang-skel-inser	t-file-timestamp: whether a	automatically updated time stamps are inserted in E	Erlang source code file header blocks.	
Last updated on:	• per-eriang-space-and	er-comma-in-blocks: wher	turned on, a space is automatically inserted after	a comma typed inside a parens block.	
Open this PDF file.	• <f11> SPC e <f1></f1></f11>	(pel-help-pdf &optional	Open the WY Ewland level DDE If the profiv argument	ment (like <b>C-u</b> or <b>M</b> ) is used, then it opens the	
See also: <u>∑ Help/Info</u>	• <f11> SPC e <f1></f1></f11>	OPEN-WEB-PAGE)		el-flip-help-pdf-arg user-option is set it's the other	
	• <f11> SPC e L <f1></f1></f11>		way around.		
	• <f12> <f1> • <f12> w <f1></f1></f12></f1></f12>		Key sequences that start with <f11> SPC e Key sequences that start with <f12> are only a</f12></f11>		
	• <f12> W <f1> • <f12> L <f1></f1></f12></f1></f12>		The <f12> keys sequences are mirrored by the</f12>	•	
∑ Customize PEL Erlang	<f11> SPC e <f2></f2></f11>	(pel-customize-pel	Customize PEL Erlang support: access PEL user-	options to activate Erlang support packages.	
support	<f12> <f2></f2></f12>	&optional OTHER- WINDOW)	• If OTHER-WINDOW is non-nil (use <b>C-u</b> ), displa	ay in another window.	
∑ Customize Emacs	<f11> SPC e <f3></f3></f11>	(pel-customize-library	Customize Emacs Erlang support: erlang, erldoc,	erlstack, edts, ivy-erlang-complete, lsp-erlang, lsp-	
Erlang support	<f12> <f3></f3></f12>	&optional OTHER- WINDOW)	mode, lsp-treemacs, auto-highlight-symbol, elect	ricity, smart-dash, smartparens, treemacs.	
		,	If OTHER-WINDOW is non-nil (use C-u), displa	y in another window.	
<u>S</u> Customize PEL LSP for Erlang support	<f11> SPC e L <f2></f2></f11>	(pel-customize-pel &optional OTHER-	<ul><li>Customize PEL LSP Erlang support</li><li>If OTHER-WINDOW is non-nil (use C-u), displa</li></ul>	ay in another window.	
	<f12> L <f2></f2></f12>	WINDOW)	This is available when pel-use-erlang-ls is tu	rned on.	
∑ Customize Emacs LSP	<f11> SPC e L <f3></f3></f11>	(pel-customize-library	9	ı, Isp-mode, Isp-ui, helm-Isp, Isp-ivy, Isp-origami, Isp-	
for Erlang support	<f12> L <f3></f3></f12>	&optional OTHER- WINDOW)	treemacs.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), displa	ay in another window.	
		,	This is available when pel-use-erlang-is is tur	•	
∑ Customize PEL LSP	<f11> SPC e w <f2></f2></f11>	(pel-customize-pel	Customize PEL LSP Erlang support		
Window for Erlang	<f12> w <f2></f2></f12>	&optional OTHER- WINDOW)	• If OTHER-WINDOW is non-nil (use <b>C-u</b> ), displa		
support	122 W 122	WINDOW)	This is available when pel-use-treemacs and	/or pel-use-lsp-treemacs is turned on.	
© Customize Emacs LSP	<f11> SPC e w <f3></f3></f11>	(pel-customize-library &optional OTHER-	Customize Emacs LSP Erlang support: lsp-treema • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), displa		
Window for Erlang support	<f12> w <f3></f3></f12>	WINDOW)	This is available when <b>pel-use-treemacs</b> and		
Environment Help	Use the following command to	verify your Erlang environm	•		
Show PEL setup for		(pel-erlang-setup-info		ang-info* buffer with buttons providing quick access	
Erlang	<f11> SPC e ? ?</f11>	&optional APPEND)	to the customization buffer of each variable show		
	<f12> ? ?</f12>		<ul><li>interpretation of:</li><li>pel-use-erlang(whether the classic or tree-sitter</li></ul>	r based maior mode is used).	
			the user options controlling indentation and har	rd tab width rendering.	
			To append information in the buffer instead of clear (such as <b>C-u</b> ) before the command keystroke.	aring the previous content type any prefix argument	
Erlang Mode version	<f11> SPC e ? v</f11>	(pel-show-erlang-	,	ng supporting tools in the echo area. This includes	
		version)		ete, the Erlang root path and its detection method,	
	<f12> ? v</f12>	Displays current version of		(if available) values of erlang-root dir and no	
	71127 : V		available Erlang system, of <u>erlang.el</u> , of <u>erlang_ls</u> Check that <u>erlang-root-dir</u> matches the version	on of Erlang you use. If not check the setting of the	
			ir. For more information see set PEL Erlang envi	• •	

<u>Description</u>	Keystroke	Function	Note		
Syntax Highlighting	The <u>erlang.el</u> external package  Off, Level 1: comments only There is not key binding for thi	e provides several levels of Erlang code syntax highlighting: Level 2, Level 3, Level 4: maximum variety. s. You must use the Syntax Highlighting section of the Erlang menu:  7> to access the menu, then select Erlang, Syntax Highlighting and the level you want.			
Electric Keys for Erlang  Customize  electric keys	1. the erlang.el external 2. the smartparens exter  • Use <f11> ( ( to t) PEL provides customization ar  • The pel-erlang-electric-  • The pel-erlang-space-af</f11>	ages have an impact on the "electric" behaviour of some keys in erlang-mode buffers:  .el external package, which controls the behaviour of the RET, ,, ; and > keys as controlled by erlang-electric-commands variable.  arens external package, which modifies the behaviour of the DEL and <deletechar> behaviour when smartparens-mode is active.  ( to toggle smartparens-mode on and off.  mization and dynamic control of erlang.el electric key behaviour and provides electric behaviour of some extra keys.  g-electric-keys user-option set which of the RET, ,, ; and &gt; keys have electric behaviour. By default they are all activated.  g-space-after-comma-in-block user-option activates automatic insertion of space after comma inside a block. Disabled by default.  ng-mode buffer, use the M-<f12> M-` prefix key followed by one of these keys to toggle the electric behaviour of the key.</f12></deletechar>			
Toggle , electricity	M- <f12> M-` ,</f12>	(pel-erlang-comma &optional GLOBALLY)			
Toggle automatic insertion of space after comma in block	M- <f12> M-` M-,</f12>	(pel-erlang-toggle- space-after-comma &optional GLOBALLY)	Toggle automatic insertion of space after comma inside blocks. Show its new state.  • To modify the behaviour in all Erlang buffers type: M M- <f12> M-` M-,</f12>		
Toggle > electricity	M- <f12> M-` &gt;</f12>	(pel-erlang-gt &optional GLOBALLY)	Toggle electric behaviour of the greater-than key. Show message describing its new state.  • To modify the behaviour in all Erlang buffers type: M M- <f12> M-` &gt;</f12>		
Toggle RET electricity	M- <f12> M-` RET</f12>	(pel-erlang-newline &optional GLOBALLY)	Toggle electric behaviour of the newline key. Show message describing its new state.  • To modify the behaviour in all Erlang buffers type: M M- <f12> M-\ RET</f12>		
Toggle; electricity	M- <f12> M-`;</f12>	(pel-erlang-semicolon &optional GLOBALLY)	Toggle electric behaviour of the semicolon key. Show message describing its new state.  • To modify the behaviour in all Erlang buffers type: M M- <f12> M-';</f12>		
Toggle . electricity	M- <f12> M-` .</f12>	(pel-erlang-period &optional GLOBALLY)	Toggle Erlang electric behaviour of the semicolon key. Show message describing its new state.  • To modify the behaviour in all Erlang buffers type: M M- <f12> M-\ .</f12>		
Toggle - electricity	M- <f12> M-` -</f12>	(smart-dash-mode &optional ARG)	Toggle the smart-dash-mode on/off. More info in $\underline{\mathbb{Z}}$ <b>Text Modes</b> and $\underline{\mathbb{Z}}$ <b>Inserting Text</b> .		
Matching Pairs	With smartparens-mode act     This requires smartpa     Add smartparens-mode	intax table defines matching pairs made of ( ), [ ], { }, " " and ' '. PEL adds the << >> pair. tivated typing the opening character(s) automatically inserts the closing character(s) arens external package. activated by pel-use-smartparens. The to pel-erlang-activates-minor-modes to activate smartparens-mode automatically for erlang-mode buffers. It is smartparens with built-in electric-pair-local-mode: add electric-pair-local-mode to pel-activates-minor-modes list.			
Matching pairs	(	When the smartparens ex	cternal package is used and the smartparens-mode is active, the characters on the left are taken to be re: ( ), [ ], { }, " ", ' ', and << >> (added by PEL).		
XX Smartparens	1	<ul> <li>When typing the first ch</li> </ul>	aracter of a pair, the rest of the pair is inserted and point is left inside.  xt inside one of those pairs, mark the text area then type the first character of the pair.		
	{	The smartparens-mode can be activated automatically for Erlang by adding erlang-mode to the pel-erlang-activates-minor-modes user-option.  Use the <fi1> ( (key sequence to toggle the smartparens-mode on and off.  There's also the smartparens-strict-mode that imposes balanced pairs but that does not help much in Erlang.  PEL adds support for &lt;&lt; &gt;&gt; including navigation across balanced pairs, something the default erlang.el does not do, by replacing forward-sexp and backward-sexp by specialized functions.</fi1>			
	,				
	<<				
Insert Parentheses	M- (	(insert-parentheses & For Erlang: insert a parenthesis pair '()', leaving point after open-paren. Use this when smartparens is not used.			
	<ul> <li>No argument is equivalent to</li> <li>PEL makes 'parens-require-</li> </ul>	of following ARG sexps in parenthesis if they are balanced. A negative ARG encloses the preceding ARG sexps instead. To zero: just insert '()' and leave point between. If region is active, insert enclosing characters at region boundaries. Spaces' buffer local and set it to nil in Erlang mode buffers, allowing the use of this command to insert the argument parentheses thout placing a space between the function name and the opening parenthesis.			
New Line	RET	(erlang-electric-newline &optional ARG)	Break line at point. If electric behaviour is activated: indent, continuing comment if within one.  Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted.  Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing.		
Electric behaviour: • indent next line		The electric behaviour of this key is controlled by 2 variables:  • erlang-electric-commands must include the erlang-electric-newline symbol to activate the key electric behaviour.  • erlang-electric-newline-criteria identifies how to check whether newline should behave electric. By default, the value is '(t): makes it behave electric as soon as the erlang-electric-commands list includes erlang-electric-newline.			
Electric <  • ©X Smartparens	<	(erlang-electric-lt &optional ARG)	Insert a less-than sign, and optionally mark it as an open paren.  • When smartparens-mode is active << automatically inserts the closing pair.		
Electric > Electric behaviour: • new line & indent	>	(erlang-electric-gt &optional ARG)	Insert a greater-than sign, and optionally insert a new line and indent.  • Electric behaviour: -> force new line and indent.  substituting the substitution of the su		
	M-1 >		Disable electric behaviour for this character: Just insert > by typing M-1 >		
Insert -> by typing		(pel-erlang-electric- period &optional arg)	Insert -> when typing only if the following conditions are met (otherwise inserts ): • period is included in the pel-erlang-electric-keys user-option value • point is inside code and dash does not follow \$, as in \$-		
Electric comma Electric behaviour: • new line & indent • space after comma in block	, M-1 ,	(erlang-electric-comma &optional ARG)	Insert a comma character and possibly:  • a new indented line when the comma is at the end of an Erlang expression.  • a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on.  Disable electric behaviour for this character: Just insert, by typing M-1,		
Electric semicolon  Electric behaviour:  • insert clause function	;	(erlang-electric- semicolon &optional ARG)	Insert a semicolon character and possibly a function clause head prototype on the next line.  Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.  Inserts a function clause head prototype when the selection criteria identified by erlang-electric-comma-criteria indicates that it should be done.		
header		erlang-electric-semico	olon-insert-blank-lines sets # of lines inserted between the current line & new function header.		
smart-dash See: ∑ Inserting Text	• - • <kp-subtract></kp-subtract>	(smart-dash-insert)	Insert underscore following [A-Za-z0-9_], dash otherwise. See: <u>Inserting Text</u> Requires <u>smart-dash</u> <u>activated</u> by <u>pel-use-smart-dash</u> , or when smart-dash-mode is in <u>pel-erlang-activates-minor-modes</u> .		
Filling Text See also:  Experiments Filling/Justification	<ul> <li>Filling Erlang code does r</li> <li>The pel-erlang-fill-column</li> </ul>	not work as it treats code as sets the fill-column variable f11> t f ? shows its val	olies to all text in the Erlang buffer: code and comment. The auto-fill command will automatically wraps code and comments. Not work as it treats code as normal text. But filling comment paragraphs is useful. Sets the fill-column variable to control where text wraps in Erlang buffers.  11> t f ? shows its value. Use set-fill-column (C-x f) to set it.		
Fill current paragraph	• M-q • <f11> t f p</f11>	(fill-paragraph &optional JUSTIFY REGION)	Fill multi-line comment at or after point.  • To justify as well: C-u M-q  • In auto fill mode the text filling is done at the end of the line.		

Description	<u>Keystroke</u>	Function	<u>Note</u>	
Erlang Comments • Erlang Programming Rules & Conventions See also: ∑ Comments	<ul><li>% - Single percent</li><li>%% - Two percent or</li><li>%%% - Three percent</li></ul>	t characters for comments le characters are used for com- c characters are used to des	uses the following conventions: ocated toward the end of a line of code ments starting at indentation level. cribe modules and are always placed in the first column and by the comment-column variable. Set it with comment-set-column, bound to C-x;	
Comment/un-comment • PEL extension of	м-;	(comment-dwim ARG)	Comment line or region with % or %% style comments depending on the location in the buffer.	
comment-dwim specialized for Erlang.		(pel-erlang-comment- dwim &optional ARG)	Does the same but adds ability to insert <b>%%%</b> comments. It does that on the very first line in the buffer and lines that follow a line that starts with <b>%%%</b> .	
Automatically uses the %%% comment when appropriate.    Note:  M-; works much better	With marked un-commented With marked commented re To force insert %%% commented re	On first em On line wit d region: Comment region gion: Un-comments the ent style: type M-3 M-; .1	e region. The M-3 prefix identifies 3 % characters to insert. You can use another number.	
than C-c C-c and C- c C-u	<ul> <li>With numeric argument: cor</li> <li>The erland el code binds N</li> </ul>		f-; However PEL uses M−1 for something else.	
<ul> <li>PEL maps M-; to pelerlang-comment-dwim which works even better.</li> <li>Comment the current line with M-0 M-;</li> </ul>	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region.  • With just <b>C-u</b> prefix arg, uncomment each line in region BEG END.  • Numeric prefix ARG means use ARG comment characters.  • If ARG is negative, delete that many comment characters instead.	
See also: <u>∑ Comments</u>	By default, the 'comment-s	start' markers are inserted a	d 'comment-padding'; the comment end by 'comment-end' and 'comment-padding'. t the current indentation of the region, and comments are terminated on each line (even for syntaxes in es do not get comments). This can be changed with 'comment-style'.	
Un-comment region	C-c C-u	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region.  The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.	
Toggle display of comments in buffer or active region	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer.  • If the region is active, then toggle comments in the region. Otherwise, in the whole buffer.  • Requires the hide-commtel package PEL activates it with pel-use-hide-commt	
Hard Tabs Rendering See also: ∑ Indentation Hard Tab Display Rendering	Like most programming languages, you can use hard tabs and spaces as horizontal whitespace in the Erlang source code.  • Emacs supports all variations of styles: spaces only and mix of hard-tabs and spaces. Using only hard-tabs in Erlang is possible but rare. Some people use hard-tabs for indentation and extra spaces for alignment. Emacs supports all of these styles.  • Emacs provides commands to convert code to remove all hard-tabs (untabify) and replace as many spaces as possible with hard tabs (tabify).  • The tab-width user-option controls the visual rendering of hard tabs not the indentation level.  • PEL provides an Erlang specific user option for hard-tab: pel-erlang-tab-width user-option.  • PEL also provides the following command to dynamically modify the tab width rendering in the current buffer.			
Set visual rendering of hard tabs for the current buffer See <u>Indentation</u>	<f11> M-t</f11>	(pel-set-tab-width N)	Change the tab width of the current buffer, only affecting the display rendering of hard tabs inserted in the buffer text. Prompts for a new value in the [2, 8] range.  • This modifies a buffer local value of the the <b>tab-width</b> user-option.  • The change is temporary and affects the current buffer only.  • To change the tab width used for all Erlang source code files, change the 'pel-erlang-tab-width' user-option variable instead.	
Hard Tab Insertion	The <b>pel-erlang-use-tabs</b> user-option controls whether hard tab characters are inserted in Erlang source code when Emacs inserts indentation whitespace.  • This sets the Emacs <b>indent-tabs-mode</b> for Erlang buffers.			
Indentation indentation	All syntactic indentation control for Erlang is controlled by the erlang-mode logic and several user-options in the erlang group. See indentation.  • Rigid indentation commands are also available and listed at the end of this list. They are also listed in the Indentation table.			
Indent current line or region	<tab></tab>	(indent-for-tab- command & optional ARG)  Indent active region, current line, or block starting on this line: performs syntactic indentation • The indentation level is controlled by the erlang-indent-level user-option. Its default is 4. • Access its custom group buffer using <f12> <f3> 1</f3></f12>		
See also: <u>Sindentation</u> Erlang Guidelines:  Ericsson AB: try to limit most code to 2 levels of indentation.  Inaka: indentation level = 2 space chars.	<ul> <li>In Transient Mark mode, when the region is active, reindent the region.</li> <li>Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line.</li> <li>Otherwise reindent just the current line.</li> </ul>			
Indent complete buffer	<f12> <tab></tab></f12>	(erlang-indent-current- buffer)	Indent current buffer as Erlang code.  • Works on the entire buffer, even if it is narrowed.	
Indent Erlang function	C-c C-q <f12> f <tab></tab></f12>	(erlang-indent-function)	Indent current Erlang function. Point can be located anywhere inside the function.	
Indent function clause	<f12> c <tab></tab></f12>	(erlang-indent-clause)	Indent current Erlang clause. Point can be located anywhere in the Erlang clause.	
Indent lines of list after point	C-M-q	(prog-indent-sexp &optional DEFUN)	Indent the expression after point. See also:     Indentation	
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region.	
	<ul> <li>With no prefix argument, the command chooses one of these methods and indents all the lines with it: <ol> <li>If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it.</li> <li>If 'indent-region-function' is non-nil, call that function to indent the region.</li> <li>Indent each line via 'indent-according-to-mode'.</li> </ol> </li> <li>When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab></li> </ul>			
Outline Erlang Code See <u>Soutline</u> for all key bindings	Once the minor mode is actived. This is very useful to quick	e you can collapse and expa ly see an outline of the code	the Erlang buffer into an outline of function definitions.  outline-regex & outline-level and code as outlines and navigate using the outline commands. See the key bindings in  Outline in a large file. Using the outline-hide-other is particularly effective.  key prefix when the outline-minor-mode is active. Two useful key bindings are shown below.	
Toggle outline minor mode. When active:	<f11> M-1</f11>	(outline-minor-mode &optional ARG)	Toggle Outline minor mode.  • Enable with a prefix positive argument ARG, disable with negative argument.	
Hide other	• <f2> o</f2>	(outline-hide-other)	Hide everything except current body and parent and top-level headings.	
· Tilde Otilei			This also unhides the top heading-less body, if any.	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>			
Navigation in Erlang code See also: • Navigation • Moving by Defuns	The erlang-mode provides commands to navigate across Erlang source code. PEL complements these. And EDTS also.  Several commands are specialization of the normal navigation commands which are described in the table Navigation, but several are specific to Erlang:  Notice the 3 sets of commands:  1. <f12> <up> and <f12> <down> move to the beginning of Erlang functions skipping all compiler directives.  2. The standard navigation commands, (mapped to <f6> prefix) move to beginning/end of Erlang functions but stop at compiler directives.  3. The <f12> M-<cursor> commands (also accessible via M-<f12> M-<cursor>, move across Erlang clauses (as opposed to functions).  The list below describe the specialized commands only. See the others inside Navigation, like the navigation by blocks.  Note that all <f12> prefixes shown below are available in erlang-mode. Their global equivalent is <f11> SPC e. It is not always shown for brevity.  Some navigation examples use icons to represent point position. The start position is shown as with following positions as to to.</f11></f12></cursor></f12></cursor></f12></f6></down></f12></up></f12>					
EDTS/Navigation	The EDTS navigation function	ons do not support repetition	functions: ferl-goto-previous-function and ferl-goto-next-function.  n prefix argument nor they support shift marking.  to t or start-automatically). Activate EDTS (use <f12> M-E) to use these commands.</f12>			
By <u>Function</u>	Move to next/previous funct	Move to next/previous function beginning/end at/skipping compiler directives. Skips clauses.				
to start of function	Move to beginning of function					
<ul> <li>Go backward to beginning of previous function</li> </ul>	<pre>  <f12> <up>   <f12> f p    <f11> SPC e <up>   <f11> SPC e f p</f11></up></f11></f12></up></f12></pre>	(pel-previous-erl- function &optional N)	Move backward to the beginning of the previous function skipping all compiler directives.  • Moves point to the first character of the function name.  • With prefix argument N repeat N times.  • Pushes mark; move back to previous position with M— or <f6><f6>.  • Shift marking is available for the key sequence using a cursor key.</f6></f6>			
<u>EDTS</u> based <b>F</b>	C-c C-d C-b	(ferl-goto-previous- function)	Move backward to the beginning of the previous function.  • Skips all compiler directives. Does not support shift marking.			
Go forward to beginning of next function	• <f12> <down> • <f12> f n  • <f11> SPC e <down> • <f11> SPC e f n</f11></down></f11></f12></down></f12>	(pel-next-erl-function &optional N)	Move forward to the beginning of the next function skipping all compiler directives.  • Moves point to the first character of the function name.  • With prefix argument N repeat N times.  • Pushes mark; move back to previous position with M-\(^\) or <f6><f6>.  • Shift marking is available for the key sequence using a cursor key.</f6></f6>			
<u>EDTS</u> based <b>F</b>	C-c C-d C-f	(ferl-goto-next-function)	Move forward to the beginning of the next function.  Skips all compiler directives. Does not support shift marking.			
to start of function/ directive	Move to beginning of fun	ction or compiler directive				
Go backward to beginning of previous: function compiler directive  Go forward to	<f12> f P  • C-M-a • C-M-<home> • <f6> <up> • <f11> SPC e f P  <f12> f N</f12></f11></up></f6></home></f12>	(beginning-of-defun &optional ARG) (erlang-beginning- of-function &optional ARG)	Move backward to the beginning of an Erlang function or compiler directive.  • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun.  ■ Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). It's always available for <f6> <up>: hold Shift after typing <f6>.  ■ Erlang.el man page indicates an invalid mapping for this.  Move forward to the beginning of the next function definition or compiler directive.</f6></up></f6></home>			
beginning of next:	• <f6> <down> • <f11> SPC e f N</f11></down></f6>	defun &optional SILENT DONT-PUSH_MARK)	<ul> <li>Beeps if does not find beginning of next function unless SILENT is non-nil.</li> <li>If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.</li> <li>Move back to previous position with M- or <f6><f6>.</f6></f6></li> <li>Shift marking is available for the <f6> bindings: hold Shift after typing <f6>.</f6></f6></li> </ul>			
to end of function	Move to end of function or compiler directive					
Backward to end of previous:     function     compiler directive	<f6> <left></left></f6>	(pel-end-of-previous- defun &optional SILENT DONT-PUSH_MARK)	Move backwards to line after end of the previous function definition.  • Beeps if does not find end of previous function unless SILENT is non-nil.  • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.  • Move back to previous position with M-`.  F Shift marking is available for the <f6> bindings.</f6>			
Forward to end of next:     function     compiler directive	• C-M-e • C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG) (erlang-end-of- function &optional ARG)	Move forward to line after end of Erlang function.  With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun.  Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-M- <end>).  However <f6> <right> handle Shift-marking fine in terminal mode.</right></f6></end>			
By Expression     functions, etc	The following commands move  They do not move across expenses.	e to the beginning/end of six pressions in a sequence of	sequence ends with a period. Expressions in expression sequences are separated by commas. ngle expression or expression sequence.  expressions. sicon, these commands move across function definitions.			
Go to beginning of statement	M-a <f12> s a</f12>	(backward-sentence &optional ARG)	Go backward to the beginning of an Erlang statement.  • With a numerical argument repeat that many times.			
Go to end of statement	M-e <f12> s e</f12>	(forward-sentence &optional ARG)	Go forward to the end of an Erlang statement.  • With a numerical argument repeat that many times.			
By <u>Function Clause</u>	Move by clauses of a function.	A function definition (state	ement) may have multiple clauses, each separated by a semicolon.			
Go backward to beginning of clause	• C-c M-a • <f12> c a • M-<f12> M-<up></up></f12></f12>	(erlang-beginning-of- clause &optional ARG)	Move backward to previous start of clause.  • With argument, do this that many times.  **Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.			
Go forward to beginning of next clause	• <f12> c n • M-<f12> M-<down></down></f12></f12>	(pel-beginning-of-next-clause)	Move forward to the beginning of next clause.  • Pushes mark; move back to previous position with M− or <f6><f6>.  ■ Shift marking is available.</f6></f6>			
Go backward to end of previous clause	• <f12> c p • M-<f12> M-<left></left></f12></f12>	(pel-end-of-previous- clause)	Move backward to the end of the previous clause.  • Pushes mark; move back to previous position with M-\(^\) or <f6><f6>.  • Shift marking is available.</f6></f6>			
Go forward to end of current clause	• C-c M-e • <f12> c e • M-<f12> M-<right></right></f12></f12>	(erlang-end-of-clause &optional ARG)	Move to the end of the current clause.  • With argument, do this that many times.  • Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.			

Description	<u>Keystroke</u>	Function	<u>Note</u>		
Block Navigation  See also:	<ul> <li>( ) for function p</li> <li>{ } for tuples, re</li> <li>[ ] for lists</li> <li>" " for strings</li> <li>&lt;&lt; &gt;&gt; for binaries are</li> </ul>				
• <u>DX Smartparens</u>	<ul> <li>Use the <f11> ( (key sequence to toggle the smartparens-mode on and off.</f11></li> <li>Standard Erlang support provide some commands to navigate across and into these balanced blocks. Their name is shown in black in the following rows.</li> <li>Other commands are provided by XX Smartparens when smartparens-mode minor-mode is active. Some are PEL specializations of smartparens code.</li> </ul>				
To Block start/end	The following commands mov	ve to the beginning or end of	f a block, skipping over Erlang terms inside these blocks.		
Go backward to beginning of previous block     Skips terms.	• C-M-p	(backward-list &optional ARG)	Move backward to beginning of previous block.  • Supports blocks of (), [] and {}.  • With ARG, do it that many times.  • A negative argument N means forward-list N.  • This command assumes point is not in a string or comment.  -spec ejabberd_started(6() -> ok.  ejabberd_started(5() ->  gen_server:call(4(?MODULE, ejabberd_started, ?CALL_TIMEOUT).		
			<pre>-spec config_reloaded(3() -&gt; ok. config_reloaded(2() -&gt;     gen_server:call(?MODULE, config_reloaded, ?CALL_TIMEOUT).0</pre>		
Go backward to end of previous block     Skips terms.     XX Smartparens with smartparens-mode active	M- <f7> p</f7>	(pel-sp-previous-sexp &optional ARG)	Move backward to end of previous block.  • With ARG, do it that many times. If there is no next expression at current level, jump one level up (effectively doing 'sp-up-sexp').  • A negative argument N means move to the end of N-th following balanced expression.  -spec ejabberd_started() 6 -> ok.  ejabberd_started() 5 -> gen_server:call(?MODULE, ejabberd_started, ?CALL_TIMEOUT) 4.  -spec config_reloaded() 3 -> ok.  config_reloaded() 2 -> gen_server:call(?MODULE, config_reloaded, ?CALL_TIMEOUT) 1.0		
Go forward to end of next block     Skips terms.	• C-M-n	( <b>forward-list</b> &optional ARG)	Move forward to end of next block.  • Supports blocks of (), [] and {}.  • With ARG, do it that many times.  • A negative argument N means forward-list N.  • This command assumes point is not in a string or comment.  O-spec ejabberd_started() 1 -> ok.  ejabberd_started() 2 ->  gen_server:call(?MODULE, ejabberd_started, ?CALL_TIMEOUT) 3.  -spec config_reloaded() 4 -> ok.  config_reloaded() 5 ->  gen_server:call(?MODULE, config_reloaded, ?CALL_TIMEOUT) 6.		
Go forward to beginning of next block     Skips terms.     ∑X Smartparens with smartparens-mode active	M- <f7> n</f7>	(pel-sp-next-sexp &optional ARG)	Move forward to <b>beginning</b> of next block (and term if 'sp-navigate-consider-symbols' is set).  • With ARG, do it that many times.  • If there is no next expression at current level, jump one level up (effectively doing 'sp-backward-up-sexp').  O-spec ejabberd_started1() -> ok.  ejabberd_started2() -> gen_server:call3(?MODULE, ejabberd_started, ?CALL_TIMEOUT).  -spec config_reloaded4() -> ok.  config_reloaded5() -> gen_server:call6(?MODULE, config_reloaded, ?CALL_TIMEOUT).		
By Blocks and Terms     See also:     X Smartparens	Several Linux distros map Linux key binding in Systems-	<left> and Esc C-<right C-M-<left> and C-M-<r &gt;settings-&gt;keyboard-&gt;shor</r </left></right </left>	b stops at terms.  b bindings below, set pel-windmove-on-esc-cursor user-option is set to nil.  ight> to desktop workspace operation. In that case you can either use another key binding or change touts to prevent it from using that key sequence.  e ability to move across Erlang's << >> bit syntax statement blocks.		
Go backward to beginning of previous term/block	• C-M- <left> • C-[ C-b • Esc C-b • Esc C-<left> 1 • C-M-b</left></left>	(pel-erlang-backward- sexp &optional ARG)	Move backward backward to beginning of previous term or block.  • With ARG, do it that many times.  • A negative arg N means move forward to end of N terms/blocks.  • At beginning of block, jump out of the current one.  • This command assumes point is not in a string or comment.  • C-M-p : ▼ Shift marking is available in graphics mode, not in terminal mode.  • C-M-b : ▼ Shift marking is available in graphics mode, not in terminal mode.  • C-M- <left> : ▼ Shift marking works with this command.  • C-M-<left> does not work on Windows, but H-<left> works.</left></left></left>		
• Ex Smartparens with smartparens- mode active: • C-M-b and M- <f7> b use sp- backward-sexp, • others are using backward-sexp</f7>	• C-M-b • M- <f7> b</f7>	(sp-backward-sexp &optional ARG)	Same as above with the additional behaviour:  • With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default.  • When it is nil, point only stops at 1, 4, 6 and 9: it jumps over terms.  -spec ejabberd_started() -> ok. ejabberd_started() -> gen_server:call 3(?MODULE, ejabberd_started, ?CALL_TIMEOUT).  -8 spec 7config_reloaded 6() -> 5 ok. 5 config_reloaded 4() -> 3 gen_server: 2 call 1(?MODULE, config_reloaded, ?CALL_TIMEOUT). 0 Inside a block: gen_server:call(?3 MODULE, 2 ejabberd_started, ?1 CALL_TIMEOUT 0).		
Go forward to end of next term/block	• C-M- <right> • C-[ C-f • Esc C-f • Esc C-<right></right></right>	(pel-erlang-forward- sexp &optional ARG)	Move forward to end of term or block.  • With ARG, do it that many times.  • A negative argument N means move backward to beginning of previous term or block.  • At end of block, jump out of the current one.  • C-M-n : ▼ Shift marking is available in graphics mode, not in terminal mode.		

```
Function
                                       Keystroke
                                                                                          • C-M-f
                                                                                          • C-M-f : Shift marking is available in graphics mode, not in terminal mode
• C-M-<right> : ► Shift marking works with this command.
                              • C-M-f
                                                                                           ♦ C-M-<right> does not work on Windows, but H-<right> does.
    ∑X Smartparens
                                                                                           Same as above with the additional behaviour:
                                                              (sp-forward-sexp
                              • C-M-f

    With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced
expressions. It is set by default.

                                                              &optional ARG)
                              • M-<f7> f
     with smartparens-
     mode active:
        C-M-f and M-
                                                                                                 • When it is nil, point only stops at 3, 6 and 9 it jumps over terms.
        <f7> f use sp-
forward-sexp,
                                                                                           0-spec1 ejabberd_started2()3 -> ok4.
       others are using forward-sexp
                                                                                           ejabberd_started5()6 ->
                                                                                                gen_server 7: call 8 (?MODULE, ejabberd_started, ?CALL_TIMEOUT) 9.
                                                                                            -spec 10 config_reloaded() -> ok.
                                                                                           config_reloaded() ->
                                                                                                gen_server:call(0?MODULE1, config_reloaded2, ?CALL_TIMEOUT3).
                             Navigate inside nested blocks of elements with the following commands.

    Into block

Into block forward
                                                              (down-list &optional
                                                                                           Move forward to the beginning of inner element of a block.
                              C-M-d
                                                                                             With ARG, do this that many times.

A negative argument N means move backward but still go down a level.
                                                              (sp-down-sexp & optional ARG)
                              • C-M-d
   • If ARG is raw prefix argument C-u, descend forward as much as possible.
                              • M-<f7> d
                                                                                             If ARG is raw prefix argument C-u C-u, jump to the beginning of current list.
     with smartparens-
                                                                                             If the point is inside block and there is no down expression to descend to, jump to the beginning of
                                                                                             current one. If moving backwards, jump to end of current one.
    00
                                                                                           music info() ->
                                                                                                👈 example
                                                                                                              {group, "contraction"},
[0[1{2song, "3sam M'Madown"},
{song, "A la claire fontaine"},
{song, "L'alarme à l'oeil"},
{song, "La bourse ou la vie"}]
{rating, excellent}}}.
                                                                                                                                                                   example
Into block backward
                              • M-<f7> z
                                                              (sp-backward-down-
                                                                                           Move backward down one level to end of block element.
                              • C-M-z
                                                              sexp &optional ARG)
                                                                                           · With ARG, do this that many times.
                                                                                          · A negative argument N means move forward but still go down a level.
     ∑X Smartparens
     with smartparens-
                                                                                             If ARG is raw prefix argument C-u, descend backward as much as possible.
                                                                                             If ARG is raw prefix argument C-u, jump to the end of current list.
     mode active
                                                                                          • If the point is inside sexp and there is no down expression to descend to, jump to the end of current
                                                                                             one. If moving forward, jump to beginning of current one.
                                                                                           music_info(1) ->
                                                                                               example
                                                                                                              {rating, excellent4}3}2}1}.0
                                                                                                                                                                    example
· to edge of block
                                                              (sp-beginning-of-sexp & optional ARG)
                                                                                          Jump to beginning of the block the point is in.
To beginning of block
                              • M-<f7> a
                                                                                             The beginning is the point after the opening delimiter.
                                                                                             With no argument, this is the same as C-u C-u 'sp-down-sexp'
With ARG positive N > 1, move forward out of the current expression, move N-2 expressions

    ∑X Smartparens

     with smartparens-
                                                                                             forward and move down one level into next expression. With ARG negative \bf N < 1, move backward out of the current expression, move N-1 expressions
     mode active
                                                                                             backward and move down one level into next expression.

With ARG raw prefix argument C-u move out of the current expressions and then to the beginning
                                                                                             of enclosing expression
                                                                                          {good, {{1year, 19074},
                                                                                                                                                                    example
                                                                                                              {group, "1 Contract 0 ion"},
                                                                                                                                                                    example
                                                                                                              [1{song, "Sam M'Madown";,
{song, "A la claire fontaine"},
{song, "L'alarme à l'oeil"},
                                                                                                                            "La bourse ou la vie"}[0]
                                                                                                                {song,
                                                                                                                                                                    example
                                                                                                              {rating, excellent}}}.
                                                              (sp-end-of-sexp
&optional ARG)
                                                                                           Jump to end of the current block.
To end of current block
                             M-<f7> e
                                                                                             With no argument, this is the same as calling C-u C-u 'sp-backward-down-sexp'.
  forward

    With ARG positive N > 1, move forward out of the current expression, move N-1 expressions forward and move down backward one level into previous expression.

    ∑X Smartparens
                                                                                            With ARG negative N < 1, move backward out of the current expression, move N-2 expressions backward and move down backward one level into previous expression.
     with smartparens-
     mode active
                                                                                          • With ARG raw prefix argument {\bf C}-{\bf u} move out of the current expressions and then to the end of
    00
                                                                                             enclosing expression.
                                                                                           music info() ->
                                                                                                example
                                                                                                  { Ogood, {{year, 1974},
                                                                                                                                                                      example
                                                                                                              {group, "Contraction"},
                                                                                                                           Contraction",
"Sam M'Madown"},
"A la claire fontaine"},
"L'alarme à l'oeil"},
"La bourse ou la vie"}]
                                                                                                               [{song,
                                                                                                                {song,
{song,
{song,
                                                                                                              {rating, excellent}} 1 }.
```

Description	<u>Keystroke</u>	Function	<u>Note</u>
Out of block			
Out block forward     forward      Ex Smartparens     with smartparens-     mode active	C-M-] • C-M-] • M- <f7> ]</f7>	(up-list &optional ARG ESCAPE-STRINGS NO- SYNTAX-CROSSING) (sp-up-sexp &optional ARG INTERACTIVE)	Move forward out of one level of block parens.  • With ARG, do this that many times.  • A negative argument means move backward but still to a less deep spot.  • If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between end of the expression and the last "thing" inside the expression.  • This behaviour can be suppressed for syntactic string blocks by setting 'sp-navigate-reindent-after-up-in-string' to nil.  • If 'sp-navigate-close-if-unbalanced' is non-nil, close the unbalanced expressions automatically.  • music_info() ->  {{er Oror, {noreply, State}}}  ,
backward     backward     EX Smartparens     with smartparens- mode active	• M- <f7> u • C-M-u</f7>	(sp-backward-up-sexp &optional ARG INTERACTIVE)	Move backward out of one level of block parens.  • With ARG, do this that many times.  • A negative argument means move forward but still to a less deep spot.  • If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between beginning of the expression and the first "thing" inside the expression.  music_info() ->  [output
Move over space	Current implementation of	sp-forward-symbol and sp- tegrated PEL implement wo	age and required smartparens-mode minor-mode to be active.  -backward-symbol stop inside comments. I consider this a bug is so I reported and submitted a bright submitted a comment of the submitted and submitted and commands that do not stop inside comments: pel-sp-forward-symbol and pel-sp-e until the fix is integrated.
To beginning of next symbol/block  • <u>Ex Smartparens</u> with smartparensmode active	M- <f7> SPC n</f7>	(sp-skip-forward-to- symbol &optional STOP- AT-STRING STOP- AFTER-STRING STOP-INSIDE-STRING)	Skip whitespace and comments moving forward.  • If STOP-AT-STRING is non-nil, stop before entering a string (if not already in a string).  • If STOP-AFTER-STRING is non-nil, stop after exiting a string.  • If STOP-INSIDE-STRING is non-nil, stop before exiting a string.  start_app(App) -> 0
To end of next symbol or block  • EX Smartparens with smartparens mode active  See mode active	M- <f7> SPC m</f7>	(pel-sp-forward-symbol &optional ARG)	Move point to the next position that is the end of a symbol.  • With ARG being positive number N, repeat that many times.  • With ARG being negative number -N, repeat that many times in backward direction.  • A symbol is any sequence of characters that are in either the word constituent or symbol constituent syntax class. Current symbol only extend to the possible opening or closing delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax classes.  **start_app(App) ->
To beginning of previous  • <u>*** Smartparens</u> with smartparens- mode active  *** See **** note above.	M- <f7> SPC p</f7>	(pel-sp-backward- symbol &optional ARG)	Move point to the next position that is the beginning of a symbol.  • With ARG being positive number N, repeat that many times.  • With ARG being negative number -N, repeat that many times in forward direction.  • A symbol is any sequence of characters that are in either the word constituent or symbol constituent syntax class. Current symbol only extend to the possible opening or closing delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax classes.  8 start_app(7 App) -> % first clause  6 start_app(5 App, 4 temporary).  3 start_app(2 App, 1 Type) -> % second clause  0 StartFlag = not is_loaded(), startFlag).
Skip forward past whitespace  • <u>EX Smartparens</u> with smartparensmode active	M- <f7> SPC .</f7>	(sp-forward-whitespace &optional ARG)	Skip forward past the whitespace characters.  With non-nil ARG return number of characters skipped.  Start_app(App) ->
Skip backward past whitespace  • <u>E</u> Smartparens with smartparensmode active	M- <f7> SPC ,</f7>	(sp-backward- whitespace &optional ARG)	Skip backward past the whitespace characters.  • With non-nil ARG return number of characters skipped.  start_app(App) ->1

Description	<u>Keystroke</u>	Function	<u>Note</u>		
Cross Reference navigation See Xref  See PEL Manual Erlang Cross Reference section for comparison of available methods.	Erlang cross reference navigation, that uses the M→ key to move to the definition of the thing at point, is supported by several tools:  • The xref-based cross reference tools with the following backends:  • etags (with etags or CTags generated tags file), use <u>etags-erl</u> shell script to create a TAGS file in the directory root to use with etags.  • ② Global/gtags with <u>ggtags</u> . Source the <u>envfor-gtags</u> shell script to set up your shell before starting Emacs to use gtags.  • You must install ☑ GNU Global for this. See <u>PEL manual installation instructions for GNU Global</u> .  • ② With PEL set <u>pel-use-ggtags</u> user-option to t to install the Emacs-side support <u>ggtags</u> package and activate the gtags commands.  • ③ dumb_jump to navigate without having to create external database or tags files. ② Set <u>pel-use-dumb-jump</u> on to activate it.  • For the above use the <f11> x <f2> key sequence to access PEL customization buffer for cross reference control.  • Other specialized tools for Erlang:  • ③ ivy-erlang-complete external package ② activated by <u>pel-use-ivy-erlang-complete</u> user-option.  • ○ Requires a version of Erlang installed that supports <u>Erlang escript</u>.  △ ③ (ivy-erlang-complete replies on GNU sed, which is not accessible on macOS by default.  • Install gnu-sed with Homebrew. I provided a patch which solves the problem by detecting macOS and using <u>gsed</u> instead of <u>sed</u>.  • ○ The <u>EDTS</u> external package ② activated by <u>pel-use-edts</u> user option.  • ○ The <u>Isp-mode</u> external package ② activated by the <u>pel-use-erlang-Is</u> user-option.</f2></f11>				
PEL Unified Cross Reference Navigation	capabilities than etags, which  Each of the above tools use di  PEL unifies all of these tools session.  Select the default cross ref  Modify the cost reference e	is built in Emacs and does in fferent back-end function. So allowing you to select the ference engine by setting the ingine during an editing session.	AGS (etags) or a database (ggtags) that must be setup prior to use. The ggtags tool provide more not require any other external package.  Some of these are accessible via Emacs unified Xref mechanism but not all. one you prefer to use via customization and also allowing you to change the tool during and editing e pel-erlang-xref-engine user-option.  sion with M- <f12> M M Display which one is used with M-<f12> M M.? over it and type the usual M key. It will use the currently selected cross reference engine.</f12></f12>		
Select Cross Reference back-end for Erlang	M- <f12> M M</f12>	(pel-erlang-select-xref)	Select another Erlang cross reference back-end from the back-ends currently available.  The selection remains active for the current editing session.  The 'pel-erlang-xref-engine' user-option identifies the persistent selection.		
Show selected Erlang Cross Reference back- ends	M- <f12> M M-?</f12>	(pel-erlang-show-xref)	Show Erlang cross reference back-end selected by customization and the one currently active.		
Find definition of identifier at point using currently active engine *** See also: ** Xref	м	(pel-erlang-find- definitions)	Grab symbol at point and move cursor to its definition.  Uses the currently active Erlang cross-reference back-end selected by 'pel-erlang-xref-engine' user-option or modified via M- <f12> M M  If there are more than one match, prompt in the *xref* buffer.  For the Xref-driven back-ends: to search for a symbol entered manually, type C-u M</f12>		
Go back to where M was last issued	М-,	(xref-pop-marker-stack)	<ul> <li>Pop back to where M was last invoked.</li> <li>Marker depth is controlled by the xref-marker-ring-length user option.</li> </ul>		
EDTS/Cross References	EDTS provides the following cross-reference commands. It supports navigating in Erlang source code running in the current and remote nodes.  PEL unbinds EDTS M- • and M- , to allow EDTS to work with PEL unified cross reference mechanism, and creates the bindings under C-c C-d.  Requires the EDTS external package. activated by pel-use-edts user option.  PEL integrates EDTS cross reference navigation in the unified cross reference navigation.  While EDTS is active you can use EDTS cross reference mechanism or anything selectable by pel-erlang-select-xref as described above.  If another cross reference engine is active and EDTS is on, you can force using the EDTS commands using the C-c C-d key bindings shown below.				
EDTS Find definition of identifier at point	M C-c C-d M	(edts-find-source- under-point)	Goto the source code that: defines the function being called at point or header file included at point. For remote calls, contacts an Erlang node to determine which file to look in, with the following algorithm:  • Find the directory of the module's beam file (loading it if necessary).  • Look for the source file in:  • Directory where source file was originally compiled.  • Todo: Same directory as the beam file  • Todo: Again with /ebin/ replaced with /src/  • Todo: Again with /ebin/ replaced with /erl/ Otherwise, report that the file can't be found.		
EDTS: Go back to where M was last issued	M-, C-c C-d M-,	(edts-find-source- unwind)	Unwind back from uses of 'edts-navigate'-commands.		
Lists caller of function at point	• C-c C-d w • <f12> w</f12>	(edts-xref-who-calls)	Pops-up a menu of all callers of the function at point.		
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who- calls)	Redo previous call to edts-who-calls.		
Find a function in the current module	• C-c C-d f • M- <f12> M-f</f12>	(edts-find-local- function SET-MARK)	Find a function in the current module.  List local functions in the mini-buffer. Support completion. Move point to selected one.  With <b>C-u</b> prefix, push mark before moving point.		
Find a module in the current project	• C-c C-d F • M- <f12> M-g</f12>	(edts-find-global- function)	Find a module in the current project.  • List project modules in the mini-buffer. Support completion. Open the file of selected one.		
ivy-erlang-complete Cross References	ivy-erlang-complete provides the following functions to navigate across Erlang code.  Requires ivy-erlang-complete external package activated by pel-use-ivy-erlang-complete user-option.  PEL integrates ivy-erlang-complete cross reference navigation in the unified cross reference navigation.  You can use its cross reference mechanism or anything selectable by pel-erlang-select-xref as described above.  While another cross reference engine is active you use ivy-erlang-complete by using the key bindings under C-c as shown below.				
Find definition of identifier at point	• C-c M • M	(ivy-erlang-complete- find-definition)	Find Erlang definition using ivy-erlang-complete.		
	• C-c M-? • M-?	(ivy-erlang-complete-find-references)	Find erlang references.  • Use M-, to go back to original location.		
	• <f12> C-f • C-c C-f</f12>	(ivy-erlang-complete- find-spec)	Find spec at point, with ivy completion listing all found, then opening source file.  • It also find callback definition.		

Description	<u>Keystroke</u>	Function	Note			
Open file at point	The following commands, allo	w opening files from the file	e name taken at point (the cursor location). They work regardless of the input completion method			
		do completion mode, it is p	oossible to instruct Ido to use a file name at point as the basis for the file name to open. This Ido  tuser-option. With PEL you can control it globally or locally with <f11> f M</f11>			
Open file at point.	• <f12> C-o • C-c C-o</f12>	(ivy-erlang-complete- find-file)	Open file at point. Find file in current project.			
Open file or web-page whose name is at point ** Command is also	• M-* • <f11> f . • <u>6y</u></f11>	(pel-open-at-point &optional N)	Open the file, library or the URL, named at point, with potential line & column #s.  Supports glob characters, partial directory path. When multiple files are found it prompts using the method selected by <b>pel-prompt-read-method</b> user-option.			
specialized for:  • MreStructuredText • \$\mathbb{H}\$ - C			The <u>6y</u> key-chord is available if <b>pel-use-key-chord</b> is non-nil. See <u>x Key-Chords</u> . for Erlang major mode: it is able to find source files in Erlang root directory and project tree, including including the project.			
• <u>%\( - C++</u>	inside the Erlang project dependencies (normally stored inside the deps directory tree created when building the project.  The following user option controls this behaviour:  The pel-erlang-project-root-identifiers user-option identifies the files that are used as markers of Erlang project directory root.  The pel-project-root-identifiers user-option identifies the files used to identify the project root in general.					
Finds files in other Erlang directories	The search for file supports gle	ob characters and partial docommand over the string "s	f nothing in the list works for you. lirectory path. something.?hl" in the source code will find all files named something.erl and something.hrl inside			
Generic Delimiting characters		n works by identifying the I	ne, and possibly line and column numbers, from text at point and tries to open the file or directory. beginning & end of the file/directory/library/URL name string by delimiter characters, one of: tab, newline () «» ‹ · · 〈 › 〈 › 《 ) () · 。			
! The complete file detection heuristic is described in the <u>S</u> File mngt description of the	The default is a very prim	itive function implemented	them and prompts using the method selected by <b>pel-prompt-read-method</b> user-option.  I by PEL. You can select a more powerful <u>ivy</u> prompting instead. <b>Del-use-ivy</b> to <b>t</b> and <u>lvy mode</u> will be installed automatically when you restart Emacs.			
same command.	Note that the command s	shows all files found by the	e specified search method, it does not only use the first one found.  Ider file names in large include paths.			
Select target window		•	the following logic controlled by presence or absence of typed numerical prefix arguments:			
	point.		move point to that window and to the line column coordinates if specified following the file name at dow according to the number of editable windows in frame: if 1, split that window and use the new			
N>20 : open the directory <b>▶</b>	window, if 2: use the o  With prefix numeric argur  N < 0: create a new w	ther window, if 3 or more, when the N: rindow and use that.	use the current window.			
	<ul> <li>(abs N) &gt; 20: then open the <b>directory</b> instead of the file. Interpret the window position from the N value adjusted: N-20 (or N+20 if N is negative)</li> <li>N = 0: use the 'other' (the next) window.</li> <li>N = 1, 3, 7or above (excluding 8, 9 and 10): select the target window based on the number of editable windows in frame:</li> </ul>					
See function docstring	<ul><li>if 1 window:</li><li>if 2 windows:</li><li>if 3 or more window</li></ul>	split that window and use the other window,				
for more info.	<ul> <li>if 3 or more windows: use the current window.</li> <li>N is: 8: up, 2: down, 4:left, 5:current, 6:right.</li> <li>N is 9: force opening the file in the OS associated application (with N=29 or N=-29, open the file's directory with the OS associated application (eg. macOS Finder, Windows Explorer). If this is a URL, open it in the OS default web browser.</li> <li>Selecting Minibuffer, inexistent or dedicated window is not allowed.</li> </ul>					
Completion	<ul> <li>Selecting Minibutier, inexistent or dedicated window is not allowed.</li> <li>Completion is available from various sources.</li> <li>Without help from EDTS or LSP, the ivy-erlang-complete external package parses the Erlang libraries to identify the supported functions.</li> </ul>					
	ivy-erlang-complete     Requires a version	vated by <b>pel-use-ivy-erlang-complete</b> user-option. pports <u>Erlang escript</u> .				
	ivy-erlang-complete replies on GNU sed, which is not accessible on macOS by default.      Install gnu-sed with Homebrew. I provided a patch which solves the problem by detecting macOS and using gsed instead of sed.					
	· ·		<b>-company-erlang</b> , the company backends provides completion popup menus to suggest identifiers. ion of already written identifier, with is helpful to modify existing or incomplete code.			
Hippie Expand Abbreviation	M-/	(hippie-expand ARG)	Try to expand text before point, using multiple methods.  Not an Erlang completion command but it can be useful to pick up names present in the files.  The expansion functions in 'hippie-expand-try-functions-list' are tried in order, until a possible expansion is found. Repeated application of 'hippie-expand' inserts successively possible expansions.			
See also: <u>▼ Hide/Show</u>			<ul> <li>With a positive numeric argument, jumps directly to the ARG next function in this list. With a negative argument or just C-u, undoes the expansion.</li> <li>Zelactivates this when the pel-use-hippie-expand user option is set to t.</li> </ul>			
Completion of Erlang code at point.	<f12> . C-:</f12>	(ivy-erlang-complete)	<ul> <li>Erlang completion at point.</li> <li>Aware of Erlang modules and functions for the currently used Erlang version identified by the ivyerlang-complete-erlang-root user-option which is adjusted to the erlang-root-dir</li> <li>⚠ ivy-erlang-complete replies on GNU sed, which is not accessible on macOS by default.</li> <li>To solve the problem you must install gnu-sed with Homebrew since ivy-erlang-complete shell scripts use gsed instead of sed.</li> </ul>			
Display Auto-completion status	<f11> , ?</f11>	(pel-completion-help)	Display information about available auto-completion.  Shows which one is enabled via customization and their current activation state.			
Explicitly List Completion Candidates See   Auto-Completion	• <f11> , , • M-1</f11>	(pel-complete)	List completion candidates.  • Force auto-completion of text at point, don't wait for timeout.  • There must be at least 1 character preceding point.  • Requires company-erlang 2 activated by pel-use-company-erlang.			
Completion Menu keys		nenu is shown, you can us candidate (or <down> curs</down>	e the following keys for operating on that menu:			
<ul> <li>Auto-completion         Menu Operations     </li> <li>Company-Mode Menu Operations</li> </ul>	• M-p : previ • M-1, M-2, M-3, etc • <tab> : comp • <del> : Delet</del></tab>	ous candidate (or <up> cu .: select candidate by line i plete using 1 candidate (if te 1 char of the current can</up>	rrsor) number 1 choice), using the prefix part among many candidates, or cycle through all candidates. ndidate prefix			
See also:   See also:   Secrolling	• <pbel> : Delete 1 char of the current candidate prefix • <ret> : Select current candidate, execute action for candidate if any (eg. when template selection used) • C-? : Show candidate help in separate buffer • <f1> : Show candidate help in separate buffer.   • This is very handy to quickly review documentation of several symbols! • C-M-v : Scroll help buffer forward (note: see the ∑Scrolling table for more info on scrolling) • Esc <pgdown> : Scroll help buffer forward • C-M-S-v : Scroll help buffer backward • Esc <pg-up> : Scroll help buffer backward • C-g : Stop completion</pg-up></pgdown></f1></ret></pbel>					
Set a different root for Erlang project	• <f12> M-e • C-c C-e</f12>	(ivy-erlang-complete- set-project-root)	Set root for current project for ivy-erlang-complete.  d To see the current value of the ivy-erlang-complete-project-root, type <f12> ?</f12>			
Marking See also: <u>▼ Marking</u>	The first 2 command listed I     For those 2 commands the	below are Erlang-mode spe ne <b>E</b> Erlang.el man page ir	ndicates an invalid mapping for this. Reported as ERL-1314.			
	The useful er/expand-region	on benefits from PEL enhar	neement to erlang syntax table supporting the < > pair therefore it is also mentioned here.			

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Mark Erlang function	• C-M-h	(mark-defun &optional	Put mark at end of this function, point at beginning.	
	• <f12> f m</f12>	(erlang-mark-function	<ul> <li>The function marked is the one that contains point or follows point.</li> <li>With positive ARG, mark this and that many next functions; with negative ARG, change the direction of marking.</li> </ul>	
Mark Erlang Clause	• C-c M-h	&optional ARG) (erlang-mark-clause)	If the mark is active, it marks the next or previous function(s) after the one(s) already marked.  Put mark at end of clause, point at beginning.	
	• <f12> c m</f12>			
Mark region by semantic unit, increase marked region on each	• M-= • <f11> . =</f11>	(er/expand-region ARG)	<ul> <li>Increase selected region by semantic units.</li> <li>Type = to expand the region, - to contract it and 0 to reset the operation.</li> </ul>	
invocation. ★★	• See <u><b>x</b> Marking</u> for more in	formation		
Works best with superword-mode on. • See <u>Text Modes</u>	Requires expand-region package, activated by pel-use-expand-region user option.			
Copy and Clone • XX Smartparens	The following commands provides specialized copy and cloning operations. They are provided by <b>EX Smartparens</b> • With PEL the commands that are marked with <b>Quarter of the special string</b> when <b>pel-show-copy-cut-text</b> is <b>t</b> . Toggle this display with <b><f11></f11></b>			
Copy current & forward block(s)	M- <f7> =</f7>	( <b>sp-copy-sexp</b> &optional ARG)	Copy the following ARG expressions to the kill-ring. This is exactly like calling 'sp-kill-sexp' with second argument t. All the special prefix arguments work the same way.	
Copy previous block(s)	M- <f7> M-=</f7>	(sp-backward-copy- sexp &optional ARG)	Copy the previous ARG expressions to the kill-ring.  This is exactly like calling 'sp-backward-kill-sexp' with second argument t. All the special prefix arguments work the same way.	
clone current block	M- <f7> c</f7>	(sp-clone-sexp)	Clone sexp after or around point.  If the form immediately after point is a sexp, clone it below the current one and put the point in front of it.	
Transform code	The following commands can	be used to help transform o	Otherwise get the enclosing sexp and clone it below the current enclosing sexp.      code. Some need external packages.	
iEdit mode			s simultaneously.	
See also: <u>I Highlight</u>	Requires the <u>iedit</u> external			
Toggle iedit mode See also:  •   © Cursor	• C-; • <f11> e</f11>	(iedit-mode &optional ARG)	Toggle iEdit mode: edit all symbols in scope or region simultaneously.  A Both iEdit and Flyspell use the C-; key as their default binding.	
• ∑ Search/Replace	PEL detects and reports that situation: r		<ul> <li>PEL detects and reports that situation: modify the binding of one of them if you see it.</li> <li>See <u>Search/Replace</u> where all the iedit-mode commands are described.</li> </ul>	
Reformat the entire buffer with selected	<f12> R</f12>	(pel-erlang-format- code)	Reformat the Erlang code in the current buffer.  • Use the Erlang formatter command specified by the 'pel-erlang-code-formatter-command' user-	
Erlang Code Formatter			option. By default this is nil. You can specify a command to use or a specific Erlang code formatter format string with a %s replacement to hold the name of a temporary file.  • PEL has built-in support for <u>erlfmt</u> . It must, however, be installed separately and a erlfmt command available on the PATH. Others will be added.  • All code inside the current Erlang buffer is reformatted with the specified code formatter, even if the buffer is not committed to a file. After the command you can undo the changes.	
			described to the state of the s	
Align arrows inside region	C-c C-a	(erlang-align-arrows START END)	<ul> <li>Align arrows ("-&gt;") in function clauses inside marked region or in the current function.</li> <li>With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to point), not just those in function clauses.</li> </ul>	
		Before: sum(L) -> s	After C-c C-a: sum(L, 0). sum(L) -> sum(L, 0).	
		sum([H T], Sum) -> s sum([], Sum) -> Sum.	$sum(T, Sum + H);$ $sum([H T], Sum) \rightarrow sum(T, Sum + H);$	
		To align something else than clauses, select the	Before: After C-u C-c C-a: check(P, [H T]) -> check(P, [H T]) ->	
		code and type: C-u C-c C-a	<pre>case P(H) of     true -&gt; 1;     true -&gt; 1;</pre>	
			false -> 0 false -> 0 end;	
Transpose block elements	M- <f7> t</f7>	(sp-transpose-sexp &optional ARG)	Transpose the expressions around point.  • The operation will move the point after the transposed block, so the next transpose will "drag" it	
<u>IX Smartparens</u> with smartparens-     mode active			<ul> <li>With arg positive N, apply that many times, dragging the expression forward.</li> <li>With arg negative -N, apply N times backward, pushing the word before cursor backward. This will therefore not transpose the expressions before and after point, but push the expression before point over the one before it.</li> </ul>	
es active			Before (for all following examples): AList = [1, 2, 3, [10,11,12, [22,33,44]], 5, 6, 7, 8, []].	
			After M- <f7> t: AList = [1, 2, [10,11,12,[22,33,44]], 3 , 5, 6, 7, 8,[]]. After M-2 M-<f7> t: AList = [1, 2, [10,11,12,[22,33,44]], 5, 3 , 6, 7, 8,[]].</f7></f7>	
			Before (for all following examples):  AList = [{first,[1, 2, 3]} , [10,11,12,[22,33,44]], 5, 6, 7, 8,[]].	
			After M- <f7> t: AList = [[10,11,12,[22,33,44]], {first,[1, 2, 3]} , 5, 6, 7, 8,[]]. After M-2 M-<f7> t: AList = [[10,11,12,[22,33,44]], 5, {first,[1, 2, 3]} , 6, 7, 8,[]].</f7></f7>	
			Before (for all following examples):  AList = [{first,[1, 2, 3]} , [10,11,12,[22,33,44]], 5, 6, 7, 8,[]].  After M M- <f7> t:</f7>	
Push current block after	M_<57> 0	(en-nuch-hybrid cove)	AList = [{first,[1, 3], 2]}, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]].  Push the hybrid sexp after point over the following one.	
next  • XX Smartparens	M- <f7> s</f7>	(sp-push-hybrid-sexp)	Before: After M- <f7> s:</f7>	
with smartparens- mode active			AList = [1, 2, 3,	
			1	

<u>Description</u>	<u>Keystroke</u>	Function		<u>Note</u>
Transform - barf	The following commands extra			
Eject next element(s) out of current block  • XX Smartparens  with smartparens- mode active	M- <f7> /</f7>	(sp-forward-barf-sexp &optional ARG)	Remove the last sexp in the current list by movir  If ARG is positive number N, barf that many exit of ARG is negative number -N, contract the op  If ARG is raw prefix C-u, barf all expressions for place the point before the closing delimiter of  If the current list is empty, do nothing.	xpressions. ening pair instead. rom the one after point to the end of current list and
	native sp problem 💆	smartparens by itself fails to process these examples properly.	<pre>Before: AList = [[1,  2, 3, 4]]. Before: AList = [[1,  2, 3, 4]].</pre>	After M- <f7> /: AList = [[1,  2, 3], 4].  After M-2 M-<f7> /: AList = [[1,  2], 3, 4].</f7></f7>
		PEL fixes the issues with post processing.	Before: AList = [[1,  2, 3, 4]].	After M M- <f7> /: AList = [1,  [2, 3, 4]].</f7>
Eject previous element(s) out of current block	M- <f7> M-/</f7>	(sp-backward-barf-sexp &optional ARG)		ing pair, the opening pair is contracted. For more
<u>xx Smartparens</u> with smartparens-     mode active		This command works fine in Erlang for the following code examples:	Before: AList = [[1,  2, 3, 4]]. Before:	After M- <f7> M-/: AList = [1,  [2, 3, 4]].  After M-3 M-<f7> /:</f7></f7>
			AList = [[1,  2, 3, 4]].	AList = [1,  2, 3, [4]].
Transform - slurp	The following commands perfo	orm slurping operations, how	wever support for Erlang could be improved as the	e commands do not always work properly.
Enclose next outside element into current block  • <u>EX Smartparens</u>	M-<£7> >	(sp-forward-slurp-sexp &optional ARG)	can extend a list or end of file).  If ARG is N, apply this function that many time  If ARG is negative -N, extend the opening pair  If ARG is raw prefix C-u, extend all the way to	end that list (and possibly apply recursively until we as. instead (that is, backward). the end of the parent list. ion to be slurped are strings, they are joined together. Erlang as shown in the first example.
	. sp problem 🔻	smartparens by itself fails to process these examples properly.	Before: Names = [ ]Joe.	After M- <f7> &gt;: Names = [ Joe].</f7>
		PEL fixes the behaviour by using ability to post-	Before: AList = [[1, 2, 3  ], 4, 5].	After M- <f7> &gt;: AList = [[1, 2,  3, 4], 5].</f7>
		process code to ensure correct syntax.	Before: AList = [1, 2, 3, [ 10,11,12,[22,33,44]], 5, 6, 7, 8,[]].	After M M- <f7> &gt;: AList = [1, 2, [3,</f7>
Enclose previous outside element(s) into next block • <u>EX Smartparens</u> with smartparens- mode active	M- <f7> &lt;</f7>	(sp-backward-slurp- sexp &optional ARG)	<ul> <li>Add the sexp preceding the current list in it by moving the opening delimiter.</li> <li>If the current list is the first in a parent list, extend that list (and possibly apply recursively until we can extend a list or beginning of file).</li> <li>If arg is N, apply this function that many times.</li> <li>If arg is negative -N, extend the closing pair instead (that is, forward).</li> <li>If ARG is raw prefix C-u, extend all the way to the beginning of the parent list.</li> <li>If both the current expression and the expression to be slurped are strings, they are joined together.</li> </ul>	
		The position of point inside the list does not matter. The point does not move.  Before:	Before: AList = [0, 1, [2, 3 , 4], 5].  Before: AList = [0, 1, [2, 3 , 4], 5].  After C-u M-<	After M- <f7> &lt;: AList = [0, [1, 2, 3, 4], 5].  After M-2 M-<f7> &lt;: AList = [[0, 1, 2, 3], 4], 5].</f7></f7>
Enclose next element(s)	M- <f7> }</f7>	AList = [-2, -1, 0, (pel-sp-add-to-	1, $[2, 3, 4]$ , 5]. AList = $[[-2, 4]$ Add the expression around point to the first list $[-2, 4]$	-1, 0, 1, 2, 3, 4 ], 5].
into previous block  • <u>SX Smartparens</u> with smartparens- mode active	,	<b>previous-sexp</b> &optional ARG)	<ul> <li>With ARG positive N add that many expressions to the preceding list.</li> <li>If ARG is raw prefix argument C-u add all expressions until the end of enclosing list to the previous.</li> <li>If ARG is raw prefix argument C-u C-u add the current list into the previous.</li> </ul>	
es se		smartparens by itself fails to process these	Before: AList = [0, 1, [2, 3],  4, 5].	After M- <f7> }: AList = [0, 1, [2,  3, 4], 5].</f7>
		examples properly.  PEL fixes the issues with post processing and wrapping function.	Before: AList = [0, 1, [2, 3],  4, 5].	After M-2 M- <f7> }: AList = [0, 1, [2,  3, 4, 5]].</f7>
Enclose previous outside element(s) into next block • <u>xx Smartparens</u> with smartparens-	M- <f7> {</f7>	(sp-add-to-next-sexp &optional ARG)	Add the expressions around point to the first list following point.  With ARG positive N add that many expressions to the following list.  If ARG is raw prefix argument C-u add all expressions until the beginning of enclosing list to the following list.  If ARG is raw prefix argument C-u C-u add the current list into the following list.	
mode active		This command works fine in Erlang for the following code examples:	Before: AList = [1,  2, [3, 4]].	After M- <f7> {: AList = [1,  [2, 3, 4]].</f7>
			Before: AList = [1,  2, [3, 4]]. Before:	After C-u M- <f7> {: AList = [[1,  2, 3, 4]].</f7>
			AList = [[1,  2], [3, 4]].	After C-u C-u M- <f7> {: AList = [[[1,  2], 3, 4]].</f7>
Re-wrap block	Use the following commands t	o change the wrapping cha	racter pair surrounding a block	
Re-wrap current block  • XX Smartparens  with smartparens- mode active	M- <f7> r</f7>	(sp-rewrap-sexp PAIR &optional KEEP-OLD)  This command works fine in Erlang for the following	Re-wrap current block using another block chars • With C-u, keep old delimiter and wrap with Pa  Before:  AList = [[1,  2, 3, 4]].	
<u> </u>		code examples:	Before: AList = [[1,  2, 3, 4]].	After C-u M- <f7> r {: AList = [{[1,  2, 3, 4]}]</f7>
Swap current block and parent block wrapping	M- <f7> w</f7>	(sp-swap-enclosing- sexp &optional ARG)	Swap the enclosing delimiters of this and the pa • With N > 0 numeric argument, ascend that ma	rent expression.
characters • ∑X Smartparens with smartparens-		This command works fine		After M- <f7> w: AList = ([{1,  2, 3, 4}]).</f7>
mode active		1300 SAUTIPIOS.	Before: AList = ({[1,  2, 3, 4]}).	After M- <f7> w:</f7>

Before:
AList = ({[1, |2, 3, 4]}).

After M-<f7> w: AList = [{(1, |2, 3, 4)}].

```
Function
       Description
                                     Keystroke
                                                                                                                                      Note
Un-wrap block
Extract all elements
                            M-<f7> U
                                                           (sp-unwrap-sexp
                                                                                      Un-wrap current or next block.
from current/next block
                                                           &optional ARG)

    With ARG N. unwrap Nth expression as returned by 'sp-forward-sexp'

    If ARG is negative -N, unwrap Nth expression backwards as returned by 'sp-backward-sexp'

    ∑X Smartparens

                                                                                      Before:
                                                                                                                                       After M-<f7> U:
     with smartparens-
                                                                                      AList = (\{[1, 2, 3, 4]\}).
                                                                                                                                       AList = [\{1, 2, 3, 4\}].
                                                                                     Before:
AList = ({[1, |2, 3, 4]}).
                                                                                                                                       After M-<f7> U:
                                                                                                                                        AList = (\{1, |2, 3, 4\}).
                                                                                                                    After M-<f7> U:
                                                           Before:
                                                           AList = [1, 2, 3, 4], 5, [6, 7], 8].
                                                                                                                      AList = [1, 2, 3, 4, 5, [6, 7], 8].
                                                           Before:
                                                                                                                    After M-2 M-<f7> U:
                                                           AList = [1, 2, [3, 4], 5, [6, 7], 8].
                                                                                                                      AList = [1, 2, 3, 4], 5, 6, 7, 8].
Extract all elements
                            M-<f7> W
                                                           (sp-backward-unwrap-
                                                                                      Unwrap the previous block/expression.
                                                           sexp &optional ARG)
                                                                                       With ARG N, unwrap Nth expression as returned by 'sp-backward-sexp'.

    If ARG is negative -N, unwrap Nth expression forward as returned by 'sp-forward-sexp'.

                                                                                     Before:
AList = ({[1, |2, 3, 4]}).
                                                                                                                                       After M-<f7> W
     with smartparens-
                                                                                                                                        AList = (\{1, | 2, 3, 4\}).
     mode active
    00
                                                                                                                                       Again After M-<f7> W:
                                                                                                                                        AList = (1, |2, 3, 4).
                                                                                                                                       Again After M-<f7> W:
                                                                                                                                        AList = 1, |2, 3, 4.
                                                                                     Before:
AList = [0, 1, [2, |3, 4], 5].
                                                                                                                                       After M-<f7> W:
                                                                                                                                       List = [0, 1, 2, 3, 4, 5].
                                                                                                                     After M-<f7> W:
                                                           Before:
                                                           AList = [1, 2, [3, 4], 5, [6, 7], [8].
                                                                                                                      AList = [1, 2, [3, 4], 5, 6, 7, 8].
                                                                                                                     After M-2 M-<f7> W:
                                                           Before:
                                                           AList = [1, 2, [3, 4], 5, [6, 7], 8].
                                                                                                                      AList = [1, 2, 3, 4, 5, [6, 7], 8].
Split & Join
Split block
                                                           (sp-split-sexp ARG)
                                                                                      Split the list or string the point is on into two.
                            M-<f7> |
     ∑X Smartparens
                                                                                        If ARG is a raw prefix C-u split all the sexps in current expression in separate lists enclosed with
     with smartparens-
                                                                                        delimiters of the current expression.
     mode active
                            smartparens by itself fails
                                                          Before:
                                                                                                                    After M-<f7> |:
    00
                                                           AList = [1, 2, [3, 4, 5, 6, 7], 8].
                                                                                                                     AList = [1, 2, [3, 4], | [5, 6, 7], 8].
                            to process the first of these
                            examples properly.
                                                          Before:
Name = "Joe | Armstrong".
                                                                                                                    After M-<f7> |:
Name = "Joe " | "Armstrong".
                            PEL fixes the issues with
                            post processing.
                                                           Before:
                                                                                                                    After C-u M-<f7> |:
                                                           AList = [1, 2, [3, 4, |5, 6, 7], 8].
                                                                                                                    AList = [1, 2, [3], [4], [5], [6], [7], 8].
                                                                                     Join the blocks before and after point if they are of the same type.
Join blocks
                                                           (sp-join-sexp &optional
      X Smartparens

    If ARG is positive N, join N expressions after the point with the one before the point.

                                                                                      • If ARG is negative -N, join N expressions before the point with the one after the point.
     with smartparens-
                                                                                      • If ARG is a raw prefix C-u join all the terms up until the end of current expression.
                                                                                      • The joining stops at the first expression of different type.
    60
                                                                                                                    After M-<f7> J:
                                                           Before:
                                                           AList = [0, 1, [2, 3, 4]], [5, 6], 7].
                                                                                                                       List = [0, 1, [2, 3, 4], 5, 6], 7].
                                                           AList = [[0, 1]], [2, 3, 4], [5, 6], [7].
                                                                                                                      AList = [[0, 1], 2, 3, 4, 5, 6], 7].
                            In Erlang mode, the superword mode can be useful since snake case is often used. Using superword-mode helps searching.
Search Support
                            • PEL activates the superword mode by default in Erlang mode. To change this use the <f11> t <f2> to access the customize buffer.
Toggle superword-mode

• <u>\tilde{\tilde{\tilde{L}}} Text Modes</u>
                            <f12> M-p
                                                                                      Toggle superword-mode: a minor mode that treats snake case as one word.
                                                           (superword-mode

In Erlang, '_' are then treated as part of words.
With prefix argument ARG, enable superword mode if ARG is positive, disable it otherwise.

                            • <f11> t m p

    ∑ Search/Replace

                            • <f11> SPC e M-p
                            The following commands can be used to activate or toggle useful modes to highlight blocks of (), {}, and [].
Highlighting blocks
                             show-paren-mode, which highlights the parens that matches the one before or after point
                            • rainbow delimiters mode, where matching nested parens are highlighted with the same colour
                                                                                      Toggle visualization of matching parens (Show Paren mode).

• With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.
Toggle show-paren
                              <f12> M-9
                                                           (show-paren-mode
mode on/off
                            • M-<f12> M-9
                                                           &optional ARG)

    Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.

                            • <f11> h (
See also: E Highlight
                            • <f11> SPC e M-9
                              <f12> M-r
                                                           (rainbow-delimiters-
                                                                                      Highlight nested parentheses, brackets, and braces with colours according to their depth.
Toggle colouring of
nested blocks
                            • M-<f12> M-r
                                                           mode &optional ARG)

    Customize the depth and colours with M-x customize-group rainbow-delimiters

See also: E Highlight
                                                                                      Requires: rainbow-delimiters.el 🛂 activated by pel-use-rainbow-delimiters.
                            • <f11> h R
Edit Erlang Code
                            The following commands help edit Erlang code.
Create additional clause
                                                                                      Create additional Erlang clause header.
                                                           (erlang-generate-new-
                            C-c C-i

    Parses the source file for the name of the current Erlang function. Create the header containing the
name, a pair of parentheses, and an arrow. The space between the function name and the first

                                                           clause)
                                                                                        parenthesis is preserved. The point is placed between the parentheses.
                                                           (erlang-clone-
                                                                                      Insert, at the point, the argument list of the previous clause.
Clone clause arguments
                                                                                       Copy the function arguments of the preceding Erlang clause. This command is useful when defining
                                                           arguments)
                                                                                        a new clause with almost the same argument as the preceding.
The mark is set at the beginning of the inserted text, the point at the end.
```

Description	Keystroke	Function	Note		
Insert Erlang Code	-		tons, available on the Erlang/Skeletons menu (via <f10>)</f10>		
with Specialized Tempo Skeletons	PEL provides the following a     Quick access keys to insert	additional functionality: ert the templates, all mappe	ed under the <b>pel:erlang-skel</b> key prefix: < <b>f12&gt;</b> < <b>f12&gt;</b> .  h a +. These are also added to the menu.		
Erlang Style	• Several aspects of the PEL Erlang Source Code Style is controlled by the user options inside the pel-erlang-code-style group. The controlled templates affected are marked with a C. The relevant user options are part of the pel-erlang-code-style group accessible with <f12> <f2> from an erlang mode buffer</f2></f12>				
Control 🖝	and include the following options:  • pel-erlang-skel-insert-file-timestamp  : set whether an automatically updated timestamp is inserted in the file header block.				
See also:	pel-erlang-skel-prom     pel-erlang-skel-prom	pt-for-function-name	: set whether file and function skeletons blocks prompt for purpose and insert it. : set whether function skeletons prompt for function name and then inserts that name.		
Erlang-specific  Templates	<ul><li>pel-erlang-skel-prom</li><li>pel-erlang-use-separ</li></ul>		s: set whether function skeletons prompt for function arguments and then insert them. : set whether blocks use horizontal separator lines (these are the first of potentially 2 separators).		
• <u>S Inserting Text</u> for	<ul><li>pel-erlang-use-secor</li><li>pel-erlang-skel-with-</li></ul>		: set whether blocks use a second block horizontal separator line. : set whether generated code comments use EDoc markup.		
more info and information about	• pel-erlang-skel-with-		: set whether file header blocks use open source software license text controlled by <u>lice</u> .		
tempo skeleton and the			But by using file and directory variables ( see <u>E File/Directory Variables</u> ) they can also be used to take		
completely different yasnippet template- based text insertion	change the behaviour for o	only one file, write the user of a directory tree create a .c.	So by default, the user options that control the PEL tempo template take effect globally. If you want to option control block at the end of that file. If you want to control the behaviour of the PEL tempo dir-locals file and store the values of the relevant options variables inside that file. This allows you to upo templates precisely and does not affect what you actually type.		
+ : additional templates  C : templates with			ng the pel-tempo-mode) you can move to the next or previous point of interest (so called <i>tempo-marks</i> )  C-c M-b or some other keys like C-c . and C-c ,.		
customization control	<ul> <li>Instead of using the <f1 listing all completions into</f1 </li> </ul>	2> <f12> bindings, you co a separate temporary buffer</f12>	an also type the template name and then hit <b>C-c C-M-i</b> or <b><f12> <f12> <f12></f12></f12></f12></b> . This supports er. This is mainly useful for templates which short names such as "if", "case", etc so links to the relevant Erlang language construct reference page.		
© Customize PEL Erlang Skeletons layout	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-pel &optional OTHER- WINDOW)	Customize PEL Erlang skeleton layout.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.		
if	<f12> <f12> i</f12></f12>	(pel-erl-if)	Insert an if statement.		
case	<f12> <f12> c</f12></f12>	(pel-erl-case)	Insert a case expression.		
export +	<f12> <f12> x</f12></f12>	(pel-erl-export	Insert an export module attribute expression.		
import +	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.		
<u>try</u> +	<f12> <f12> t</f12></f12>	(pel-erl-try)	Insert a try expression.		
try-of +	<f12> <f12> T</f12></f12>	(pel-erl-try-of)	Insert a try expression with of clauses.		
receive	<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.		
<u>after</u>	<f12> <f12> a</f12></f12>	(pel-erl-after)	Insert a receive expression with an after (timeout) clause.		
Іоор	<f12> <f12> 1</f12></f12>	(pel-erl-loop)	Insert a simple receive loop.		
module	<f12> <f12> m</f12></f12>	(pel-erl-module)	Insert the module attribute.		
<u>function</u> C	<f12> <f12> f</f12></f12>	(pel-erl-function)	Insert a function definition. This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.		
author	<f12> <f12> `</f12></f12>	(pel-erl-author)	Insert the author attribute. Uses the <b>user-mail-address</b> user option to insert your mail address.		
spec	<f12> <f12> s</f12></f12>	(pel-erl-spec)	Insert a <b>-spec</b> for the function following point.		
small-header C normal-header C	<f12> <f12> M-h <f12> <f12> M-H</f12></f12></f12></f12>	(pel-erl-small-header)	Insert a small file header without any comment.  Insert a normal file header: includes author name, copyright notice, doc section, file created date		
large-header C	<f12> <f12> m-n</f12></f12>	(pel-erl-large-header)	Insert a large header block that includes all normal header fields plus separators.  • User-options control the format. Distinguish Erlang .erl module files from the .hrl header files.		
small-server C	<f12> <f12> M-s</f12></f12>	(pel-erl-small-server)	Insert a large file header and template logic for a small server.		
application C	<f12> <f12> M-a</f12></f12>	(pel-erl-application)	Insert a large file header and template logic for an application behaviour.		
supervisor C	<f12> <f12> M-u</f12></f12>	(pel-erl-supervisor)	Insert a large file header and template logic for a supervisor behaviour.		
supervisor-bridge C	<f12> <f12> M-b</f12></f12>	(pel-erl-supervisor- bridge)	Insert a large file header and template logic for a supervisor bridge behaviour.		
generic-server C	<f12> <f12> M-g</f12></f12>	(pel-erl-generic-server)	Insert a large file header and template logic for a gen-server behaviour.		
gen-event C	<f12> <f12> M-e</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a gen-event behaviour.		
gen-fsm C	<f12> <f12> M-f</f12></f12>	(pel-erl-gen-fsm)	Insert a large file header and template logic for a gen-fsm behaviour.		
gen-statem-StateName C	<f12> <f12> M-S</f12></f12>	(pel-erl-gen-statem- StateName)	Insert a large file header and template logic for a gen-statem behaviour.		
gen-statem-handle- event C	<f12> <f12> M-E</f12></f12>	(pel-erl-gen-statem- handle-event)	Insert a large file header and template logic for a gen-statem.		
wx-object C	<f12> <f12> M-w</f12></f12>	(pel-erl-wx-object)	Insert a large file header and template logic for a wx-object generic server.		
gen-lib C	<f12> <f12> M-1</f12></f12>	(pel-erl-gen-lib)	Insert a large file header and template logic for a library module.		
gen-corba-cb C	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a CORBA callback module.		
ct-test-suite-s	<f12> <f12> M-1 <f12> <f12> M-2</f12></f12></f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite  Insert a large file header and template logic for a test suite		
ts-test-suite	<f12> <f12> M-2</f12></f12>	(pel-erl-ts-test-suite)	Insert a large file header and template logic for a test suite		
Tempo Template Tag	• C-c C-M-i	(tempo-complete-tag	Look for a tag and expand it.   Instead of using the <f12> <f12> key bindings above, type the</f12></f12>		
Insertion	C-C C-M-1  Soptional SILENT)  Look for a tag and expand it. Instead of using the <f12> <f12> key bindings above, type the template name and then hit C-c C-M-i. (or <f12> <f12> <f12>).  A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template.  All the tags in the tag lists in 'tempo-local-tags' (including 'tempo-tags') are searched for a match for the text before the point. The string matching is determined by the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all.  If a single match is found, the corresponding template is expanded in place of the matching string.  If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal.  If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed.</f12></f12></f12></f12></f12>				
Toggle pel-tempo-mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as C-c		
See also:	• <f11> SPC e <f12></f12></f11>	&optional ARG)	C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode		
Inserting Text	SPC • <f6> SPC</f6>		is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode.  When a skeleton is inserted via the execution of one of the pel-erl commands above, the pel-tempo-mode is automatically activated.		
Jump to next tempo	• C-c M-f	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the		
mark	• C-c . • C-c C	, and the state of	These key key bindings are only available when pel-tempo-mode is active.		

<u>Description</u>	<u>Keystroke</u>	Function	Note	
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward- mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key binding are only available when pel-tempo-mode is active.	
Specialized Kill See also: • ∑ Cut & Paste • ∑ Smartparens	Specialized delete and kill commands are provided by the The smartparens external package activated by pel-use-smartparens user-option.  Activate smartparens mode manually with <f11> ( or automatically by adding smartparens-mode to pel-erlang-activates-minor-mode.  This table uses the sand symbols to represent these 2 keys:  : "forward delete" := <deletechar> := Fn a : "backward delete" := <backspace> Often labelled "delete" on keyboards.  With PEL the commands that are marked with sale display the killed string when pel-show-copy-cut-text is t. Toggle this display with <f11> M-=</f11></backspace></deletechar></f11>			
• Delete char  Standard delete forward character	<pre></pre>	&optional KILLFLAG) • If Transient Mark mode is enabled, the mark is active, and N is 1, delete the text in the regi		
			deactivate the mark instead.  Interactively, N is the prefix arg, and KILLFLAG is set if N was explicitly specified.  parting' before it is saved in the kill ring, so the actual saved text might differ from the killed text.	
Delete forward, jump over block pair until block is empty then	• <deletechar></deletechar>	(pel-sp-delete-char &optional <u>ARG</u> )	Same as above with the <u>additional behaviour</u> listed below.  Execute 'sp-delete-char' if no area marked, otherwise delete marked area.	
• <u>SX Smartparens</u> with smartparens mode active	of delete-selection-mode If nothing is marked: If on an opening delimite If on a closing delimiter, r If the delimiter does not f With a numeric prefix arg	e.  r, move forward into balance refuse to delete unless the b form a balanced expression, lument N = 0, simply delete	alanced expression is empty, in which case delete the entire expression.	
Standard delete backward character	• DEL	(backward-delete-char- untabify ARG &optional KILLP)	Delete characters backward, changing tabs into spaces.  Delete ARG chars, and kill (save in kill ring) if KILLP is non-nil.  Interactively, ARG is the prefix arg (default 1) and KILLP is t if a prefix arg was specified.  The exact behavior depends on 'backward-delete-char-untabify-method'.	
<u>Delete character -</u> <u>backward</u> , jump over block pair until block is empty then delete block	• DEL • ©	(pel-sp-backward- delete-char &optional ARG)	Same as above with the <u>additional behaviour</u> :  • If an area is marked deletes the area, regardless of the presence of blocks, even if the resulting text would lead to unbalanced pairs. It also ignores the prefix argument.	
<u>IX Smartparens</u> with smartparens- mode active	<ul> <li>When nothing is marked:</li> <li>Deletes character before cursor (deletes backward), replaces hard tab with spaces as required.</li> <li>Does not delete only one side of a balanced pair block: instead move into the block and delete its content until it is empty. When the block is empty the command deletes both block characters.</li> <li>If on a closing delimiter, move backward into balanced expression.</li> <li>If on an opening delimiter, refuse to delete unless the balanced expression is empty, in which case delete the entire expression.</li> <li>If the delimiter does not form a balanced expression, it will be deleted normally.</li> <li>With a numeric prefix argument N = 0, simply delete a character backward, without regard for delimiter balancing. If ARG is raw prefix argument C-u, decharacters backward until an opening delimiter whose deletion would break the proper pairing is hit.</li> <li>Execute 'sp-delete-char' if no area marked, otherwise delete marked area.</li> </ul>			
Delete char     Does not delete marked areas with balanced pairs.	The forward and backward  Note that these will not	delete keys do the same whaccept to delete or kill a reg	s that delete forward and backward without breaking blocks. een smartparens-mode is active. ion that contains balanced pairs even if the region contains the two sides! I and backwards keys commands that use smart-parens delete as long as the area is not marked.	
Delete char forward	M- <f7> DEL n</f7>	(sp-delete-char &optional ARG)	Delete a character forward or move forward over a delimiter.  If on an opening delimiter, move forward into balanced expression.	
	• If on a closing delimiter, refuse to delete unless the balanced expression is empty, in which case delete the entire expression.  • If the delimiter does not form a balanced expression, it will be deleted normally.  • With a numeric prefix argument N > 0, delete N characters forward.  • With a numeric prefix argument N < 0, delete N characters backward.  • With a numeric prefix argument N = 0, simply delete a character forward, without regard for delimiter balancing.  • If ARG is raw prefix argument C-u, delete characters forward until a closing delimiter whose deletion would break the proper pairing is hit.  (quu   x "zot") -> (quu   "zot")  (quu   "zot") -> (quu x " ot")  (foo   bar)  (foo   bar)			
Delete char backward	M- <f7> DEL p</f7>	(sp-backward-delete- char &optional ARG)	Delete a character backward or move backward over a delimiter.  • It has the same description as the above command but goes backward instead of forward.  ("zot"   quux) -> ("zot"   uux)  ("zot"   quux) -> ("zot   " quux) -> ("zo   " quux)  (foo ( ) bar) -> (foo   bar)  (foo bar) -> (foo bar  )	
Delete/Kill region	These may be useful inside	keyboard macros when dele	is the deletion would not create unbalanced blocks. eting text in area where several balanced and nested blocks are present. ion that contains balanced pairs even if the region contains the two sides!	
Delete region	M- <f7> DEL -</f7>	(sp-delete-region BEG END)	Delete the text between point and mark, like 'delete-region'.  • BEG and END are the bounds of region to be deleted.  • If that text is unbalanced, signal an error instead.  • With a prefix argument, skip the balance check.	
Kill region	M- <f7></f7>	(sp-kill-region BEG END)	Kill the text between point and mark, like 'kill-region'.  • BEG and END are the bounds of region to be killed.  • If that text is unbalanced, signal an error instead.  • With a prefix argument, skip the balance check.	
kill block elements	The following commands kill the	he element(s) of a block.		
Kill content of next block	• M- <f7> © • M-<f7> - n</f7></f7>	(sp-change-inner)	Change the content of current or next block. Point can be anywhere in block or element before block.  Before:  {'EXIT',Reason} -> { error,{asn1,Reason}};  {error,{ }};	
Delete content of current block	M- <f7></f7>	(sp-change-enclosing)	Delete content of the enclosing block. Point can be anywhere inside the current block.  Before: {'EXIT',Reason} -> {error,{ asn1,Reason}}; {error,{ }};	
Kill block elements forward	M- <f7> - ]</f7>	(sp-kill-sexp &optional ARG DONT-KILL)	<pre>Kill block elements after point.  Before:     case Tlv9    of        [] -&gt; true;&gt; exit({error,   {asn1, {unexpected, Tlv9}}})  After:     case Tlv9    of</pre>	
		, , , , , , , , , , , , , , , , , , , ,	[] -> true;> exit({error, })	

(sp-backward-kill-sexp Kill block elements before point.

Kill block elements

M-<f7> - [

```
Keystroke
       Description
                                                                                              Before:
backward
                                                                 &optional ARG DONT
                                                                 KILL)
                     *
                                                                                               case Tlv9 of
[] -> true;_ -> exit({error,|{asn1, {unexpected, Tlv9}}})

    ∑X Smartparens

                                                                                               After:
                                                                                               case Tlv9 of
   [[] -> true;_ -> exit({|{asn1, {unexpected, Tlv9}}})
                                                                                               Kill a line as if with 'kill-line', but respecting delimiters.
Kill element after current
                              M-<f7> - }
                                                                 (sp-kill-hybrid-sexp
                     *
                                                                 \bullet \ \ \text{With ARG being raw prefix } \textbf{C-u} \ \ \textbf{C-u}, \text{ kill the hybrid sexp the point is in (see 'sp-get-hybrid-sexp')}.

    <u>∑X Smartparens</u>

    With ARG numeric prefix 0 (zero) just call 'kill-line'

                                                                    You can customize the behaviour of this command by toggling 'sp-hybrid-kill-excessive-whitespace'.
                                                                 (sp-kill-whole-line)
                               M-<f7> - 1
Kill whole line
                     *
                                                                                               🔔 Currently this deletes the whole line. Requires Erlang specific implementation. 🚧

    Kill/splice

Un-wrap current block,
                               M-<f7> 1 1
                                                                 (sp-splice-sexp
                                                                                               Un-wrap current block, splicing its content in enclosing block (if any).
splicing its elements in enclosing block
                                                                 &optional ARG)
                                                                                               Before:
                                                                                               Before:
{|EncBytes,EncLen} = 'enc'(Cdx, []), |EncBytes,EncLen = 'enc'(Cdx, []),
                                                                                               Before:
                                                                                                lefore:
-asn1_info(
[{vsn, '2.0.1'},
    {module, 'ELDAPv3'},
    {options, [{i, "src"}, {|outdir, "src"}, noobj, {i, "."}, {i, "asn1"}]}]).
                                                                                                  sn1_info(
                                                                                                  [{vsn.
                                                                                               Kill elen...

Before:

Se Tlv9 C
                                                                                               Kill elements before point in block and splice remaining elements into outer block.
Kill block element(s)
                                                                 (sp-splice-sexp-killing-
                               M-<f7> 1 [
before point and splice
                                                                 backward &optional
                                                                 ARG)
remaining into outer
                                                                                                case Tlv9 or
[] -> true; -> exit({error,{asn1, {unexpected, |Tlv9}}})
block
                                                                                               After:
case Tlv9 of
[] -> true; -> exit({error,{asn1, |Tlv9}})

    <u>∑X Smartparens</u>

                                                                 (sp-splice-sexp-killing-
Kill block element(s)
                               M-<f7> 1 ]
                                                                                               Kill elements after point in block and splice remaining elements into outer block.
                                                                                               Before:
case Tlv9 of
  [] -> true; -> exit({error,{asn1, {unexpected, |Tlv9}}})
forward and splic
                                                                 forward &optional ARG)
remaining into outer
                                                                                               After:

case Tlv9 of

[] -> true; -> exit({error,{asn1, unexpected|}})

        \[
        \mathbb{X} \text{Smartparens}
    \]

Kill around element
                               M - < f7 > 1 o
                                                                 (sp-splice-sexp-killing-
                                                                 around &optional ARG)
                                                                                               Before:

    ∑X Smartparens

                                                                                                 asn1 info(
                                                                                                  {vsn, '2.0.1'},
{module,'ELDAPv3'},
{options,|{outdir,"src"},}]).
                                                                                                 [{vsn.
                               These commands complements the standard word kill commands normally available with shorter key bindings. See \mathbb E Cut & Paste

    Delete/Kill word

Delete word backward
                                                                                               (sp-backward-delete-word &optional ARG)
                               M-<f7> DEL v
                                                                 (sp-backward-delete-
                                                                                                 Delete a word backward, skipping over intervening delimiters.
Deleted word does not go to the clipboard or kill ring.
                                                                 word &optional ARG)
                                                                                                 With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in backward direction.
                                                                                               Delete a word forward, skipping over intervening delimiters.
Delete word forward
                                                                 (sp-delete-word
                               M-<f7> DEL w

Deleted word does not go to the clipboard or kill ring.
With ARG being positive number N, repeat that many times.

                                                                 &optional ARG)
                                                                                               • With ARG being Negative number -N, repeat that many times in backward direction.
                                                                                              Kill a word backward, skipping over intervening delimiters.

• With ARG being positive number N, repeat that many times.
Kill word backward
                                                                 (sp-backward-kill-word
                               M-<f7> - v
                                                                 &optional ARG)
                                                                                               • With ARG being Negative number -N, repeat that many times in backward direction.
                                                                                              Kill a word forward, skipping over intervening delimiters.

• With ARG being positive number N, repeat that many times.
                                                                 (sp-kill-word &optional
Kill word forward
                               M-<f7> - w
                                                                 ARG)
                                                                                               • With ARG being Negative number -N, repeat that many times in backward direction.
                               See 'sp-backward-symbol' and 'sp-forward-symbol' for what constitutes a symbol for the backward and forward commands respectively.

    Delete/Kill

                                 These commands complements the standard word delete commands normally available with shorter key bindings. See <u>Set & Paste</u>
   symbol
Delete symbol backward
                                                                 (sp-backward-delete-
                                                                                               Delete a symbol backward, skipping over any intervening delimiters.
                               M-<f7> DEL a
                                                                 symbol &optional ARG
WORD)
                                                                                                 Deleted symbol does not go to the clipboard or kill ring.
With ARG being positive number N, repeat that many times
                                                                                                 With ARG being Negative number -N, repeat that many times in forward direction.
                                                                 (sp-delete-symbol
&optional ARG WORD)
                                                                                              Delete a symbol forward, skipping over any intervening delimiters.

• Deleted symbol does not go to the clipboard or kill ring.
Delete symbol forward
                               M-<f7> DEL s

With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in backward direction.

                                                                 (sp-backward-kill-
                                                                                               Kill a symbol backward, skipping over any intervening delimiters.
Kill symbol backward
                               M-<f7> - a

With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in forward direction.

                                                                 symbol &optional ARG
                                                                 (sp-kill-symbol &optional
Kill symbol forward
                                                                                               Kill a symbol forward, skipping over any intervening delimiters.
                               M-<f7> - s
                                                                                                 With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in backward direction.
                                                                 ARG WORD)
```

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Erlang syntax checking	To activate either set the	pel-use-erlang-syntax-che	e can be done with Emacs built-in <u>flymake</u> as well as with the <b>flycheck</b> external package.  eck user option is set to either 'use-flycheck or 'use-flymake.  unched. If you want to start your selected syntax checker as soon as any Erlang file is opened, add	
Using either: • flycheck or • flymake	<ul> <li>'erlang-mode to the pel-modes-activating-syntax-check user-option.</li> <li>• flymake is built-in Emacs. The Emacs erlang package provides erlang-flymake to use with Erlang.</li> <li>• PEL automatically installs and activates flycheck when pel-use-erlang-syntax-check user option is set to 'use-flycheck.</li> <li>♣ Flymake has several customizable variables, which some listed here:</li> <li>The following customization variables determine the exact circumstances whereupon Flymake decides to initiate a check of the buffer:</li> </ul>			
See also:  See SyntaxCheck	<ul> <li>flymake-start-on-flymake-mode: t to start checking when flymake-mode is started. nil to prevent check.</li> <li>flymake-no-changes-timeout: time to wait after last change to start checking. Default = 0.5 seconds.</li> <li>flymake-start-syntax-check-on-newline: t to check after insertion or removal of newline char from buffer. nil to prevent check.</li> </ul>			
	The following variable control navigation to next or previous error:  • flymake-wrap-around: If non-nil, moving to errors wraps around buffer boundaries.  • flymake-diagnostic-types-alist: Alist ((KEY . PROPS)*) of properties of Flymake diagnostic types. See Emacs documentation for more info.  The M-n and M-p keys are mapped to flymake commands only when flymake-mode is turned on.			
Activate/deactivate selected syntax checker	<f11> ! !</f11>	(pel-erlang-toggle- syntax-checker)	<ul> <li>Toggle the selected Erlang syntax checker mode on/off.</li> <li>The syntax checker activated or deactivated is either <u>flycheck</u> or <u>flymake</u>, as selected by the user-option variable `pel-use-erlang-syntax-check'.</li> <li>See the required settings above to activate this command and select the syntax checker.</li> </ul>	
Go to next flymake diagnostic	M-n	(flymake-goto-next- error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.	
Go to previous flymake diagnostic	М-р	(flymake-goto-prev- error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.	
Compiling Erlang Code		compile the files. The buffe	ce code files to .beam files located in the same directory as the source code. Detected errors are listed er shows the location of error and the error description. The following commands are used to navigate	
Compile code	• C-c C-k • <f12> M-c • M-<f12> M-c</f12></f12>	(erlang-compile)	Compile Erlang module in current buffer.  If buffer visiting file was modified and not saved, prompts the user to save it first.  Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command.  The buffer lists the errors. Hitting RET on the error file/line move point to that line in the Erlang file buffer. The RET key is bound to (compile-goto-error &optional EVENT)  It's also possible to use the next-error and previous error.	
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output.  • Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.	
Move to next compile error	• C-x ` • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; • negative means move back to previous error messages. • Just C-u as a prefix means reparse the error message buffer and start at the first error.  ↑ This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.	
Move to previous compile error	• M-g p • M-g M-p	(previous-error &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative).  1 This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.	
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.	
Move to previous compilation or Flycheck detected error	С-с С-р	(edts-code-previous- issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.	
Development Tool	The following commands are used when adding Emacs Lisp support for Erlang.			
Show syntactic information	C-c C-s	(erlang-show-syntactic-information)	Show syntactic information for current line.  • Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.	
Erlang Shell	Commands to explicitly launch library running in erlang-shell-		that runs under an Emacs inferior-erlang process controlled by the <u>comint mode</u> from the <u>comint.el</u>	
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.	
Start new Erlang Shell	<f11> z r e <f12> z</f12></f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer.  • The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started.  • C-c C-z starts the Erlang Shell from the Erlang Mode.  • <f11> z r is available globally and will work as long as the erl executable is accessible.</f11>	
			Under PEL this command is available only when the pel-use-erlang user option is set to t.	
Start an EDTS controlled Erlang Shell	<f12> M-E z</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell that is EDTS aware.    Requires EDTS   activated by pel-use-edts (set to t or start-automatically).    Use the M-<12> M-E to turn EDTS on if it is not already running to use this command.	
Work around to issues in the Erlang Shell	When running the <a href="Erlang Shell">Erlang Shell</a> inside Emacs, you may run into some issues. They are listed here along with work-arounds.  • Redundant command echo:  On some systems the Erlang shell annoyingly echoes each typed command. If this is the case for your system, PEL provides a fix:  Set the pel-erlang-shell-prevent-echo user option to t. After doing that execute pel-init or restart Emacs.  • Typing Ctrl-G does not open the <a href="Erlang JCL Command Menu">Erlang JCL Command Menu</a> : work-around: type the following instead: <a href="C-q">C-q"&gt;C-q"&gt;C-q"&gt;C-g"&gt;C-G</a> RET <a href="Menu">NET</a> Unfortunately the above workaround does not work when the Erlang shell is launched inside an Emacs vterm shell (see <a href="Shells">Shells</a> ).			
Erlang Shell: Command History	The following commands can be used to retrieve previously issued Erlang shell commands at the shell prompt.  Erlang shell command history file:  The Erlang shell history controlled by Emacs is saved inside a file the is restored when opening a new shell: commands from previously opened Erlang shells are also available.  Within an Emacs inferior-erlang the cursor keys move the point, they do operate on the history: use M-n and M-p keys instead.  You can also use the Erlang shell commands to access the local shell history.			
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.	
Previous shell command	М-р	(comint-previous-input ARG)	Cycle backwards through Erlang shell input history, saving input.	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>		
Using Man inside	Emacs provide 2 main comma  • Both of these are much more		nside buffers. nan reader available on the shell allowing navigation across man pages and opening hyperlinks. They		
Emacs and support Erlang Man pages	<ul> <li>are:</li> <li>The man command uses the system man utility</li> <li><u>WoMan: Browse Unix Manual Pages "W.O. (without) Man"</u> a complete implementation. It has some formatting limitations compared to man but it's very useful in systems where man is not available like Windows.</li> </ul>				
See also: <u>E Help/Info</u>	To see Erlang man pages using the man command:  On most systems the Man pages for Erlang are not available to the man utility and therefore not available for man inside Emacs.  There are several ways this can be remedied:  One is to set the MANPATH environment variable to include the directory where these files are located. Then man can be used outside and inside Emacs to access Erlang's man pages. For example the following lines can be stored inside a shell script to do this:				
	MANPATH=/usr/local/Cellar/erlang/22.3.4/lib/erlang/man:`manpath` export MANPATH  • Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add the capability of Emacs man to fin the Erlang's man pages without modifying the capabilities of the parent shell. For example, if we want to use the same directory as the above example we need to set the Man-switches which is normally set to nil to the following value:  "-M`manpath`:/usr/local/Cellar/erlang/22.3.4/lib/erlang/man"				
	that have their own value of man pages of different ver providing the man pages f	The second alternative can be used to add other directories for the man pages of other programming languages while leaving the ability to have several shells that have their own value of MANPATH. That might be very useful for someone that uses different versions of Erlang in a system and needs access to the man pages of different versions of Erlang. It becomes possible to run different shells inside Emacs with each having its own value of MANPATH and therefore providing the man pages from different locations. It is also possible to place all of these directories inside the Man-switches or MANPATH and buses man's ability to view several pages for the same topic.			
	When learning Erlang it mi directory only. You must al	To only see Erlang topics in Man completion:  When learning Erlang it might help to see only Erlang topics when using the man command completion. To do that, set MANPATH to the Erlang man directory only. You must also ensure that a whatis file is located in the Erlang man page root directory, otherwise Emacs man completion will not work. See my description on how to create whatis file for local man directory.			
	EDTS (see below) support	s the ability to download an sections inside the mane pa	f Erlang used by various projects: d access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides it's own tiges, allowing EDTS driven man page access to co-exist with manual man command execution and the		
About Erlang	PEL supports multiple versions of Erlang and access to their man pages Inside the pel-erlang-environment group, the pel-erlang-man-parent-rootdir user-option can be set to read the man parent directory name from an environment variable. To support the ability to open the man files related to a specific version of Erlang available to the parent OS shell, set the environment variable when you select the version of Erlang available to the OS shell and set the name of the environment variable in the pel-erlang-man-parent-rootdir user-option. See the following Installing Erlang pages of the About Erlang document that describes an setting such an editing environment:  Install Erlang OTP Documentation and Man Files  Creating whatis files for Erlang man pages  Using the Erlang Man files within Emacs  Using Specialized OS Shells for Erlang  Using PEL with Specialized Shells for Erlang to Edit Erlang				
See also: <u>ℤ <b>Menus</b></u>	Use the following commands to open an Erlang man page inside Emacs.  • You can also use the toolbar menu (with PEL open it with <f10>) in the Erlang section.</f10>				
Open a man page inside an Emacs buffer  See also:  • E Help/Info	• <f11> ? m • M-<f8> • %-M</f8></f11>	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because:  • the links are active and can be followed. When the man page describes a directory or file, emacs will open the file or the directory (in direct mode) when pressing <b>RET</b> over the link.  • You can navigate easily between sections (n/p will move to the next/previous section)  • You can use any of the searches.		
• <u>S Customize</u>			<ul> <li>You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer.</li> <li>See all keys available in mode, with <f1> m or <f11>? k m.</f11></f1></li> <li>The man command prompts, using the word at point as the default.</li> <li>PEL key sequence to customize man: <f11> <f2> E m</f2></f11></li> </ul>		
Open a man page without external man process: woman	<f11> ? w</f11>	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows).  PEL key sequence to customize man: <f11> <f2> E w  text width, use word at point, etc</f2></f11>		
Show Erlang Man page documentation of Erlang module:function at point	• C-c C-d • M- <f12> M-d</f12>	(erlang-man-function- no-prompt)	Find manual page for the function under the cursor.  • The Erlang man entry for 'module:function' is displayed. It is aware of imported functions.  • The C-c C-d binding not available when EDTS is active. PEL provides M- <f12> M-dhen.  • Like erlang-man-function below, the current implementation is not able to access documentation of Erlang BIFs unless the function is qualified with the erlang module name:  • it will find the documentation for erlang:abs but not abs.</f12>		
Open Erlang Man page for Erlang module:function specified at prompt	M- <f12> M-D</f12>	(erlang-man-function &optional NAME)	Find manual page for NAME, where NAME is module:function. Prompts for module:function.  • The Erlang man entry for 'module:function' is displayed.  • It is aware of imported functions.		
ivy-erlang-complete based help	The following requires ivy-erlang-complete activated by pel-use-ivy-erlang-complete				
Open web-based Erlang standard library	• <f12> M-h • C-c C-h</f12>	(ivy-erlang-complete- show-doc-at-point)	Show web-based Erlang standard library documentation for function at point.  • Prompt to confirm the selection even if there is only 1 candidate.		
documentation for function at point	0 0 0-11	22.2.2.2.2.2.3	Opens the Erlang documentation inside the OS default browser.  Like erlang-man-function below, the current implementation is not able to access documentation of Erlang BIFs unless the function is qualified with the erlang module name:  it will find the documentation for erlang:abs but not abs.		
EDTS-based help:	The next two commands are a These require DEDTS ac See general information about	ctivated by pel-use-edts (se	÷*		
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip.  • This is able to detect <b>Erlang BIFs</b> ; the functions from the erlang module, when not qualified by the module name.		
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function.  • Find and show the man-page documentation for the Erlang module:function.  • Supports completion: providing you with a list of available Erlang modules, then the list of its functions. This helps when looking for a module or a function.		
			and the state of t		

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
<u>EDTS</u>	EDTS - Erlang Develop	ment Tool Suite		
	The commands in the following rows require the EDTS external package. FEL activates it when the pel-use-edts user option is set to t.  If you want EDTS to start automatically when you open an Erlang file, set pel-use-edts to start-automatically instead of t.  If EDTS reports that it cannot start the main server, check the *\(^/\)-emacs.d/elpa/edts-XXX directory. It should contain a _build sub-directory created by the Makefile. If that does not exists, open a shell that has access to Erlang, cd to *\(^/\)-emacs.d/elpa/edts-XXX and type make to build what is missing.  See EDTS issue 145.  EDTS is customizable through it edts customization group.			
Erlang Project settings	<ul> <li>With PEL, you can access it by typing <f12> <f3> from an Erlang buffer, or <f11> SPC e <f3> from any other buffer) and type character that identified edts.</f3></f11></f3></f12></li> <li>EDTS also uses an external .edts configuration file to store Erlang project specific settings. See EDTS: Configure your projects. This allows setting the following: project name, node-name, erlang-cookie, lib-dirs, start-command, top-path, dialyzer-plt, app-include-dirs, project-include-dirs, xref-error-whitelist, xref-file-whitelist</li> </ul>			
See also: <u>▼ Sessions</u>	<ul> <li>⚠ Desktop restoration often fails when edts-mode was active on session stored: unfortunately edts does not provide a desktop restore handler.</li> <li>☑ PEL does, however provide a desktop restore handler for EDTS which detects edts-mode failures and protect the desktop restoration.</li> <li>☑ Activate EDTS by typing <f12> M-E M-E if it is not active. Use the same key sequence to turn it off. Once active the keys in pink boxes are available.</f12></li> </ul>			
Toggle EDTS mode	<f12> M-E M-E (edts-mode &amp; optional ARG) Turn EDTS mode on or off. • EDTS is an easy to set up Development-environment for Erlang.</f12>			
	<f11> SPC e M-E M-E</f11>	7110)	EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further.	
EDTS/Man	EDTS supports opening documentation for a specific function using the information extracted from Erlang Man pages.  • EDTS maintains a set of Erlang man pages per project, so it is possible to have several Erlang projects each one with a different version of Erlang and their corresponding man pages. See <a href="Man Files used by ETDS">Man Files used by ETDS in About Erlang</a> and the Erlang Man section above.  EDTS supports two commands to retrieve information from the Erlang man pages: edts-show-doc-under-point and edts-find-doc.  • Both are documented above with the other Man help related functions.			
Download, install, select Erlang Man pages	<f12> M-E M-m</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands.  • It prompts before proceeding.	
EDTS/AHS Editing	EDTS supports the automatic highlight symbol mode (AHS) and provides commands to modify the name of the highlighted name in the current function or in all of the buffer. The automatic symbol highlighting mode starts when the cursors stays on a symbol for a period longer than the value identified by the ahs-idle-interval which defaults to 1.0 second.  To turn off the AHS editing mode, move point away from the highlighted area.			
Edit all highlighted symbols in current function	• C-c C-d e • <f12> e</f12>	(edts-ahs-edit-current-function)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current function.  • Activates ahs-edit-mode with edts-current-function range-plugin.	
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer.  • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.	
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.	
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.	
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.	
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	Refactor the expression(s) in the region as a function.  The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original function.  New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring.  This command requires Erlang syntax tools package to be available in the node, version 1.2 (or perhaps later.)	
EDTS Code Analysis				
Compile current buffer	<f12> a c</f12>	(edts-code-compile- and-display)	Compiles current buffer on node related to that buffer's project.	
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION-RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.	
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.	
EDTS/Debug				
Toggle breakpoint	• C-c C-d b • <f12> d b</f12>	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.	
List breakpoints	C-c C-d M-b • <f12> d B</f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle- interpreted)	Toggle the interpretation state for module in current buffer.	
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
EDTS/Erlang Node	EDTS Emacs Lisp code intera • It also provides its own EDT		cess. dts-shell described in the Erlang shell section above.	
Display EDTS Erlang Node Name	<f12> M-E N</f12>	(edts-buffer-node- name)	Print the node sname of the erlang node connected to current buffer.  • The node is either:  • The module's project node, if current buffer is an erlang module, or  • The buffer's erlang node if buffer is an edts-shell buffer.  • The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module such as an otp-module or a module loaded by ~/.erlang).	
Start EDTS server	<f12> M-E x</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).	

<u>Description</u>	Keystroke	Function	Note	
LSP support:  Isp-mode erlang Is	LSP (language Server Protocol) support for Erlang is provided via:  ↑ The lsp-mode Emacs Lisp external package → PEL activates it when the pel-use-erlang-ls user-option is turned on (set to t).  • The erlang Is Erlang server for LSP. You must install this manually. You will need Git, Erlang, rebar3 and make. The instructions are on the web-site.  • ★ The erlang Is can be configured using a YAML file erlang Is.config file that must be placed at the root of the Erlang project.  • It's important for most projects to set that up, otherwise you may not be able to take advantage of several of the cross-reference features  • Both  sp-mode and erlang Is are under heavy development in the end of 2021. You may want to update these projects regularly to take advantage of the new features and fixes.  With PEL you can easily upgrade  sp-mode by moving the its package directory tree into the attic directory and restarting Emacs. If the new version fails just restore the previous one. See the PEL Manual section on manual package update for more information.			
erlang Is required environment	The following executable must be accessible from PATH:  • <u>erl. escript</u> and other Erlang executables. See <u>Installing Erlang</u> if you need to learn how to install Erlang and its tools.  • erlang_ls. To install erlang_ls follow the instruction on the <u>erlang_ls GitHub page</u> : git clone it, then run make and make install.  • and the various <u>Tools for Erlang</u> .			
• <u>E Customize</u>	Several Isp-mode settings are customizable in the Isp-mode customization group. With PEL you can access it via <f12> L <f3>. The following settings</f3></f12>			
lsp-mode	are probably what you may want to customize:  • Isp-log-io : control whether the LSP process is logging its I/O. Useful for debugging LSP support.  • Isp-ui-sideline-enable : control whether LSP display information about the current code line.  • Isp-ui-doc-enable : control whether LSP display documentation about the current code symbol.  You can also use the PEL commands to modify them dynamically using the following commands.			
Toggle code	<f11> SCP e L D</f11>	(pel-toggle-lsp-ui-doc &optional LOCALLY)	Toggle the display of code documentation.  • The initial state is set by the 'Isp-ui-doc-enable' user-option.	
documentation display	<f12> L D</f12>	aoptional LOCALLY)	<ul> <li>By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.</li> </ul>	
† Toggle logging on the LSP client side	<f11> SCP e L I <f12> L I</f12></f11>	(pel-toggle-lsp-log-io &optional LOCALLY)	<ul> <li>Toggle the logging of LSP I/O.</li> <li>The initial state is set by the 'Isp-log-io' user-option.</li> <li>By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.</li> <li>Once client-side logging is active you can then follow it with Isp-workspace-show-log</li> </ul>	
Toggle display of information on current line	<f11> SCP e L L <f12> L L</f12></f11>	(pel-toggle-lsp-ui- sideline &optional LOCALLY)	Toggle the display of information of the current line.  The initial state is set by the 'lsp-ui-sideline-enable' user-option.  By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.	
• Erlang LS Features	Overview of the features provide Breadcrumbs  Code completion  Go to Definition  Go to Implementation of OTP Behaviours  Signature Suggestions  Diagnostics on file open/save:  Compiler Diagnostics	Edoc support     Navigation to Included Files     Find/Peek     References     Outline of Module		
Isp-mode features	Dialyzer Diagnostics     Elvis Diagnostics	Suggest Type Specs     Automatic Code     reloading	line : set len modeline code pation comments user ention	
isp-illoue leatifies	<ul> <li>Completion at point</li> <li>traditional popup with company-mode</li> <li>Code navigation, with</li> <li>lsp-find-definition</li> <li>lsp-find-references</li> <li>Symbol highlights</li> <li>Symbol highlights</li> <li>Code action on mode line: set lsp-modeline-code-action-segments user-option.</li> <li>Breadcrumb on headerline:</li> <li>Use the lsp-headerline-breadcrumb-mode command to toggle their display. The lsp-headerline-breadcrumb-segments</li> <li>Code Lenses: The Erlang LS configuration provides</li> <li>ct-run-test: display a run button next to a Common Test testcase.</li> <li>server-info: display some Erlang LS server info on top of each module. For debug only.</li> <li>show-behaviour-usages: show the number of modules implementing a behaviour.</li> </ul>			
Isp-mode integrations see also:  • ∑ Completion/Input • ∑X Treemacs • ∑ Hide/Show	Isp-mode supports integration with:  •			
LSP key bindings:  Isp-mode  erlang Is See also:  Input Method	Since the super modifier k     M-x customize-optic     With PEL, the following k     The key bindings shown	ey is not always available, in or with PEL via the <f11 are="" eys="" good="" obelow="" replacement="" separates.<="" show="" standard="" td="" the=""><td>candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using M-<f9>.</f9></f9></f9></td></f11>	candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using M-<f9>.</f9></f9></f9>	
LSP Session Control	<ul> <li>The following commands co</li> <li>To start a session use the</li> </ul>	The Language Server supports several programming languages via their back end. Erlang is supported by the <a href="mailto:erlang-ls-server">erlang-ls-server</a> .  • The following commands control the LSP session.  • To start a session use the <a href="mailto:lsp-workspace-shutdown">lsp-workspace-shutdown</a> . Use <a href="mailto:lsp-workspace-shutdown">lsp-workspace-shutdown</a> .		
Activate LSP	s-1 w s	(Isp &optional ARG)	Entry point for the server startup.  Without argument: start server if not already running, otherwise display the name:port of the Language Server connected.  With C-u, prompt the user to select which language server to start.	
Disconnect LSP	s-1 w D	(Isp-disconnect)	Disconnect the buffer from the language server.	
Shut LSP workspace down	s-1 w q	(Isp-workspace- shutdown WORKSPACE)	Shut the workspace WORKSPACE and the language server associated with it.  • It may report some errors. The LSP modelling will show disconnected.	
Restart the language	s-1 w r	(Isp-workspace-restart	Restart the workspace WORKSPACE and the language server associated with it	
Server LSP Diagnostics	WORKSPACE)  Use the following commands to get information about the currently running Language Server session.  • See Erlang LS Troubleshooting for more information.			
Describe LSP session	s-1 w d	(Isp-describe-session)	Describes current 'Isp-session'.  • Show available tools and the available capabilities  • Shows the information inside a LspBrowser buffer.	
Validate LSP performance settings	s-l d	(Isp-doctor)	Validate performance settings and write report in a *lsp-performance* buffer.  • It reports as <i>errors</i> non-optimal settings. These are not really errors, it's just outlining conditions that are not optimum to get the best performance out of the Language Server.	
Toggle LSP protocol logging	s-1 T L	(Isp-toggle-trace-io)	Toggle client-server protocol logging.	
Display LSP workspace log buffer	s-1 L	(Isp-workspace-show- log WORKSPACE)	Display the log buffer of WORKSPACE when IO logging is enabled.  • With PEL toggle IO logging with <f12> L D.  • This shows all LSP JSON transactions occurring.  • To always see the tail of the buffer move point to the end of buffer first, then leave it there. Emacs will automatically scroll the buffer content to keep the point visible.</f12>	

Description	<u>Keystroke</u>	Function	<u>Note</u>
Project Setup			
Add directory to the list of workspace folders	s-1 F a	(Isp-workspace-folders- add PROJECT-ROOT)	Add PROJECT-ROOT to the list of workspace folders.  • Prompts for the directory.
Remove a directory from the workspace blacklist	s-1 F b	(Isp-workspace- blacklist-remove PROJECT-ROOT)	Remove PROJECT-ROOT from the workspace blacklist.
Remove directory from the list of workspace folders	s-1 F r	(Isp-workspace-folders- remove PROJECT- ROOT)	Remove PROJECT-ROOT from the list of workspace folders.
Toggling features			
Toggle diagnostic modeline	s-1 T D	(Isp-modeline- diagnostics-mode &optional ARG)	Toggle diagnostics modeline.
Toggle current-line status information	s-1 T S	(Isp-ui-sideline-mode &optional ARG)	Minor mode for showing status information for current line.  • Displays code status such as definition errors, etc
Toggle code action on modelling	s-l T a	(Isp-modeline-code- actions-mode &optional ARG)	Toggle code actions on modeline.
Toggle headline breadcrumbs	s-l T b	(Isp-headerline- breadcrumb-mode &optional ARG)	Toggle breadcrumb on headerline.  • When active the list of directories are listed on the header line. In graphics mode these are buttons you can use to change directory.
Toggle hover information	s-1 T d	( <b>Isp-ui-doc-mode</b> &optional ARG)	Minor mode for showing hover information in child frame.  When active, information about symbol at point is shown in a pop-up overlay area. In graphics mode the information has links that can be used to open web-located information.  For small window the information may cover too much code, use this command to toggle in and out of view. Also note that when the point is toward the bottom of a window the information window may not show completely and you may have to scroll your window.
Toggle symbol highlighting	s-1 T h	(Isp-toggle-symbol- highlight)	Toggle symbol highlighting.
Toggle code-lens	s-1 T 1	(Isp-lens-mode &optional ARG)	Toggle code-lens overlays.  • Code-lens show information like # times a specific function is referenced.  • This can be used to infer type specs when writing a function.  • For this to work Dialyzer must be setup.  ∴ Code lens are overlays and appear above the corresponding line by default. ★ There seems to be a bug in lsp-mode that prevents scrolling when the overlay hit the top of the window. A work-around is to customize lsp-lens-place-position to 'end-of-line instead.
Code Changes			
Reformat Erlang file	s-1 = =	(Isp-format-buffer)	Reformat the code in the current Erlang buffer.
Refactor source import	s-1 r o	(Isp-organize-imports)	Perform the source.organizeImports code action, if available.
Rename symbol at point See also:  Search/Replace	s-1 r r	(Isp-rename NEWNAME)	Rename the symbol (and all references to it) under point to NEWNAME.  For renaming the arguments of a function, the <u>iedit mode</u> is more appropriate. It supports restricting the scope to the current function. See <u>Search/Replace</u>
Cross Reference			
Find Identifier definitions	s-1 G g	(Isp-ui-peek-find- definitions &optional EXTRA)	Find definitions to the IDENTIFIER at point.
Find symbol implementation locations	s-1 G i	(Isp-ui-peek-find- implementation &optional EXTRA)	Find implementation locations of the symbol at point.
Find references	s-1 G r	(Isp-ui-peek-find- references &optional INCLUDE-DECLARATION EXTRA)	Find references to the IDENTIFIER at point.
Find symbols	s-1 G s	(Isp-ui-peek-find- workspace-symbol PATTERN &optional EXTRA)	Find symbols in the worskpace. The symbols are found matching PATTERN.
Execute code action	s-l a a	(Isp-execute-code- action INPUT0)	Execute code action ACTION.     If ACTION is not set it will be selected from 'Isp-code-actions-at-point'.     Request codeAction/resolve for more info if server supports.
Highlight all relevant references to symbol at point	s-1 a h	(Isp-document- highlight)	Highlight all relevant references to the symbol under point.
Click LSP lens via avy	s-l a l	(Isp-avy-lens)	Click lsp lens using 'avy' package.  • The code lens must be active. Use s-1 T 1 to activate it if it's not active.
Apropos search for symbol/regexp	s-1 g a	(xref-find-apropos PATTERN)	Find all meaningful symbols that match PATTERN.  Can be used to search symbol outside project.  The argument has the same meaning as in 'apropos'.  The result is shown in a *xref* buffer.
Find definitions of symbol at point	s-1 g g	(Isp-find-definition &key DISPLAY-ACTION)	Find definitions of the symbol under point.
Find implementations of symbol at point	s-l g i	(Isp-find- implementation &key DISPLAY-ACTION)	Find implementations of the symbol under point.
Find references of symbol at point	s-l g r	(Isp-find-references &optional INCLUDE- DECLARATION &key DISPLAY-ACTION	Find references of the symbol under point.  • The result is shown in a *xref* buffer.
Trigger display hover information	s-1 h g	(Isp-ui-doc-glance)	Trigger display hover information popup and hide it on next typing.
Display documentation of symbol at point in *Isp-help*	s-1 h h	(Isp-describe-thing-at- point)	Display the type signature and documentation of the thing at point.  • Display help about symbol at point inside a *lsp-help* buffer.  • Useful in terminal mode as you can navigate inside the buffer and used other functions to open identified URL references.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Treemacs support  • Ex Treemacs	The <u>treemacs</u> and <u>lsp-treemacs</u> external packages respectively activated by PEL user-options <u>pel-use-treemacs</u> and <u>pel-use-lsp-treemacs</u> , provide extra features that help Erlang development. When these are activated PEL provides bindings for the <u>lsp-treemacs</u> features.  Configure lsp-treemacs by accessing the lsp-treemacs customization group. With PEL use <f12> w <f3> from an Erlang buffer.</f3></f12>		
Open LSP Treemacs error list window.	<f12> w e</f12>	(Isp-treemacs-errors- list)	Display an error list window at the bottom of the frame.  The buffer uses the treemacs-mode and supports its commands and key bindings.  See ** Treemacs** for the list of commands and key bindings.  To close the window, kill its buffer with *C-x** k
• Quick fix	x	(Isp-treemacs-quick-fix &rest ARGS)	If possible, proposes a quick code fix for the error at point.
Open LSP Treemacs     symbol window	<f12> w s</f12>	(Isp-treemacs-symbols)	Show symbols view.  • To close the window, kill its buffer with C-x k
Open LSP Treemacs references window	<f12> w x</f12>	(Isp-treemacs- references ARG)	Show the references for the symbol at point. Issue from an Erlang buffer.  • With a prefix argument, select the new window and expand the tree of references automatically.  • To close the window, kill its buffer with C-x k
Open LSP Treemacs <u>implementations</u> <u>window</u>	<f12> w i</f12>	(Isp-treemacs- implementations ARG)	Show the implementations for the symbol at point. Issue this command from an Erlang buffer.  • With a prefix argument, select the new window expand the tree of implementations automatically.  • To close the window, kill its buffer with C-x k
Open LSP Treemacs <u>call hierarchy</u> <u>window</u>	<f12> w c</f12>	(Isp-treemacs-call- hierarchy OUTGOING)	Show the incoming call hierarchy for the symbol at point.  • With a prefix argument, show the outgoing call hierarchy.  This does not seem to have been implemented for Erlang.
Open LSP Treemacs type hierarchy window	<f12> w t</f12>	(Isp-treemacs-type- hierarchy DIRECTION)	Show the type hierarchy for the symbol at point.  • With prefix 0 show sub-types.  • With prefix 1 show super-types.  • With prefix 2 show both.  This is not implemented for Erlang.
Rendering markup embedded in comments	The following commands are used to create images from specific markup code embedded inside Erlang source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example.  You can also use Graphviz, see Maraphviz Dot		
Preview UML diagram	<f12> u</f12>	(pel-render-	Render the PlantUML markup embedded in current mode comment.
from plantUML source in current plantUML region of commented source code	<f11> SCP e u</f11>	commented-plantuml PREFIX &optional POS)	<ul> <li>Use region if identified otherwise use PlantUML block at point.</li> <li>Uses prefix (as PREFIX) to choose where to display it:</li> <li>4 (when prefixing the command with C-u) -&gt; new window</li> <li>16 (when prefixing the command with C-u C-u) -&gt; new frame.</li> <li>else -&gt; new buffer</li> </ul>
See also: M PlantUML			<ul> <li>This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment.</li> </ul>
	block and issuing this comr	nand.	cture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML ctivated by <b>pel-use-plantuml</b> user option being non-nil.

## Emacs & Erlang - References

Document	Notes
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.
Erlang versions	Erlang Versions - Version Scheme     Erlang Support, Compatibility, Deprecations, and Removal
Erlang/OTP @ Github	Erlang source code
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, <u>Erlang Issue Tracker</u> , events.
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.
Erlang/BEAM	Erlang was the first of one of several programming language that runs on the BEAM VM.
Good introduction presentations on Erlang	<ul> <li>The soul of Erlang and Elixir • Saša Jurić • GOTO 2019         A very good presentation that captures the essence of why Erlang is so important. Fast pace. A must see. A great presentation to show people that may be reluctant to use the technology.     </li> <li>The Do's and Don'ts of Error Handling • Joe Armstrong • GOTO 2018</li> </ul>
Erlang References	
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.

Document	Notes
Erlang Information Sites	
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.
about-erlang     trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang.  • about-erlang provides general information about Erlang, including:  • Learning Erlang, a table with links to resources to learn Erlang.  • Installing Erlang, describes various ways to install Erlang on macOS.  • Tools for Erlang, describes tools you can use for Erlang development.
Emacs and Erlang Man files	
How to create a local whatis file	Show how to create a missing whatis file for a set of man pages.
The Erlang mode for Emacs (user guide)     Erlang mode for Emacs (man page)	On the <a href="Principles"></a>
	<ul> <li>There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric functions and variables.</li> <li>The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -&gt; on a function definition line.</li> <li>Another issue: inside the OS-level erlang shell, we can tab-completion a module:function string, but that does not work inside the emacs erlang shell.</li> </ul>
<b>Emacs tools for Erlang</b>	
EDTS	EDTS: stands for: The Erlang Development Tool Suite. See also:  • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube  • EDTS:  • configure your project  • One Primary EDTS node  • 1 node per open project: a .edts file in the project:  • rame "my-project"  • otp-path "path/to/otp"  • node-name "project-node-name"  • lib-dirs '("lib" "deps")
How to install EDTS	Describes some aspects of EDTS and links that may be useful. Lists the requirements.  A ****After installing EDTS, I got several compile errors, and had to install the following other modules: - auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?
Language Server Protocol	Language Server Protocol @ Wikipedia Language Server Protocol Specifications web site Language Server Protocol @ Github
LSP for Erlang	LSP support for Erlang is done using the following:  • The <a href="Isp-mode">Isp-mode</a> Erlang server  • The <a href="Isp-mode">Isp-mode</a> Erlang server
Erlang Tools accessible via the erlang_ls	Several Erlang tools are available through the erlang_ls LSP server for Erlang. Building erlang_ls from source is the best way to install it as it will also install the secondary tools it provides.  • The following is not a complete list of all tools available.
Gradualizer: A Gradual Type System for Erlang	Gradualizer is a type checker for Erlang code based on the principles of <u>Gradual Typing</u> that uses the existing Erlang type specs and adds opt-in type checking. It is a work in progress.  • <u>Gradualizer @ Github</u> • Youtube presentation: <u>Dialyzer vs Gradualizer at ElixirConf EU 2019</u>
company-mode ; Modular in-buffer completion framework for Emacs	
Using Tags with Erlang	
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the <b>pel-erlang-shell-prevent-echo</b> is set to <b>t</b> . To activate after setting it: execute pel-init or restart Emacs.