## **Emacs support for Erlang Programming Language**

Description	<u>Keystroke</u>	Function	Note
Erlang Support  • © Customize  See also:  • Developing Erlang Code with PEL  • set PEL Erlang environment	Emacs provides support for Erlang and Erlang Tools via the <u>erlang.el</u> external package (see <u>erlang.el</u> source) and some other packages.  PEL activates Erlang support via the customize user option variable <u>pel-use-erlang</u> . It must be set to t to activate support for Erlang.  PEL customization for Erlang: is in the <u>pel-pkg-for-erlang</u> group. Key bindings: global: <fi>PEL as a relatively large number of user-option variables to control Erlang editing. Only some of them are described here. Use Emacs for the complete list.  • pel-erlang-shell-prevent-echo: set to t to prevent the Erlang shell from echoing every command.  • pel-erlang-activates-minor-modes: list of minor modes that PEL will activate for the Erlang major mode.  This has several sub-groups:  • pel-erlang-environment group:  • pel-erlang-man-parent-rootdir: Identifies the parent directory of Erlang man directory. The man directory should hold the man1, man3, man4 and man6 which contain Erlang man files. If this is set PEL sets (override) the <u>erlang.el</u> erlang-root-dir user-option value with it which activates the appropriate Erlang man files. Without PEL or if pel-erlang-man-parent-rootdir is nil, you must set the erlang-root-dir user-option vourself.  • pel-erlang-exec-path: Identifies the directory where Erlang binaries are stored.  • pel-erlang-eversion-detection-method: identifies a mechanism to detect Erlang/OTP version. By default it uses an Erlang script provided with PEL.  • pel-erlang-slel-column: column where line-wrapping occurs: maximum line length (defaults to 100). You can change the value or set it nil.  • When pel-erlang-skel-use-separators: whether line separators are used in Erlang code templates (see the Insert Erlang Code Template section below),  • pel-erlang-skel-use-secondary-separators: whether secondary separator lines are inserted by some Erlang code templates,  • pel-erlang-skel-insert-file-timestamp: whether automatically updated time stamps are inserted in Erlang source code file header blocks.  • PEL provides the foll</fi>		
4 V Speedbey			
• <u>∑ Speedbar</u> Open this PDF file.	(£11) and (£1)	(not holp not sentional	0 11 00 51 1 1005 (41 5 1 141 5 14 14 14
See also: <u>Nelp/Info</u>	<f11> SPC e <f1> <f12> <f1></f1></f12></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the <u>\$\mathbf{Y}\tilde{\text{I}}\$ - <b>Erlang</b> local PDF. If the prefix argument (like <b>C-u</b> or <b>M</b>) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.</u>
∑ Customize PEL Erlang support	<f11> SPC e <f2> <f12> <f2></f2></f12></f2></f11>	(pel-customize-pel &optional OTHER- WINDOW)	Customize PEL Erlang support: erlang, erldoc, edts, auto-highlight-symbol.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.
∑ Customize Emacs	<f11> SPC e <f3></f3></f11>	(pel-customize-library	Customize Emacs Erlang support: erlang, erldoc, edts, auto-highlight-symbol.
Erlang support	<f12> <f3></f3></f12>	&optional OTHER- WINDOW)	• If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.
Erlang Mode version	<f12> ?</f12>	(pel-show-erlang-version)	Display the current version of available Erlang system and erlang.el in the mini-buffer.
Syntax Highlighting	Erlang code syntax highlighti	ng has 4 levels and can be tu	rned off via Erlang menu: <f10> to access the menu &amp; select Erlang, then Syntax Highlighting.</f10>
Edit Erlang Code	The following commands hel	p edit Erlang code.	
Create additional clause	C-c C-j	(erlang-generate-new-clause)	Create additional Erlang clause header.  Parses the source file for the name of the current Erlang function. Create the header containing the name, a pair of parentheses, and an arrow. The space between the function name and the first parenthesis is preserved. The point is placed between the parentheses.
Clone clause arguments	С-с С-у	(erlang-clone-arguments)	Insert, at the point, the argument list of the previous clause.  Copy the function arguments of the preceding Erlang clause. This command is useful when defining a new clause with almost the same argument as the preceding.  The mark is set at the beginning of the inserted text, the point at the end.
Align arrows inside region	С-с С-а	(erlang-align-arrows START END)	Align arrows ("->") in function clauses inside marked region or in the current function.  • With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to point), not just those in function clauses.  • Example: sum(L) -> sum(L, 0).
Electric Keys	The following keys have "elec	ctric" behaviour and perform s	special editing tasks to help edit Erlang source code.
Electric comma	,	(erlang-electric-comma &optional ARG)	Insert a comma character and possibly a new indented line.  • The variable 'erlang-electric-comma-criteria' states a criterion, when fulfilled a newline is inserted and the next line is indented.  • Behaves just like the normal comma when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.
Electric semicolon	7	(erlang-electric- semicolon &optional ARG)	Insert a semicolon character and possibly a prototype for the next line.  The variable 'erlang-electric-semicolon-criteria' states a criterion, when fulfilled a newline is inserted, the next line is indented and a prototype for the next line is inserted. Normally the prototype consists of "->". Should the semicolon end the clause a new clause  header is generated.  The variable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.  Behaves just like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.
Electric > (for the end of arrow)	>	(erlang-electric-gt &optional ARG)	Insert a greater-than sign, and optionally insert a new line and indent.
Erlang Comments	Erlang uses the % character to identify line comments. It uses the following conventions:  • % - Single percent characters for comments located toward the end of a line of code  • %% - Two percent characters are used for comments starting at indentation level.  • %%% - Three percent characters are used to describe modules and are always placed in the first column		
Comment/un-comment	M-;	(comment-dwim ARG)	Comment line or region with % or %% style comments depending on the location in the buffer.  The erlang.el_code binds M-1 to indent-for-comment. However PEL uses M-1 for something
Note: • M-; works much			else. The <b>M-;</b> binding to comment-dim works just as indent-for-comment if nothing is marked.
better than C-c C-c and C-c C-u  PEL maps key to pel-erlang- comment-dwim which works even		n code: insert <b>%</b> comment starter after the code for an end-of-line comment (each line is commented) ment.	
better.  See also: Comments	<ul> <li>If the region is active an region'). Else, if the curr</li> </ul>		n, call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment- int-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a

Description	<u>Keystroke</u>	Function	<u>Note</u>
	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region.  • With just C-u prefix arg, uncomment each line in region BEG END.  • Numeric prefix ARG means use ARG comment characters.  • If ARG is negative, delete that many comment characters instead.
	'comment-end' and 'com  • By default, the 'comment-	ment-padding'. ·start' markers are inserted at	ment-start' and 'comment-padding'; the strings used as comment ends are built from the current indentation of the region, and comments are terminated on each line (even for a blank lines do not get comments). This can be changed with 'comment-style'.
Un-comment region	C-c C-u	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region. The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.
Comment/un-comment • PEL extension of comment-dwim specialized for Erlang. Automatically uses the %%% comment when appropriate.	M-;	(pel-erlang-comment- dwim &optional ARG)	Insert comment like 'comment-dwim' with ability to extend "%%%" comments.  • The "%%%" comment style is only placed at the beginning of a line, when the line is the first line of a buffer or a line that follows a line that starts with a "%%%" style comment.  • When commenting a region, if the region starts just below a line with "%%%" comment the new comment uses "%%%" comment as well.  • In all other cases the %% style comment is used at the beginning of a line and a single % is used after the beginning of a line.  • If region is already commented, un-comment it.
Fill current paragraph  See also:	• M-q • <f11> t f p</f11>	(fill-paragraph &optional JUSTIFY REGION)	Fill multi-line comment at or after point.  • To justify as well: C-u M-q  • In refill mode this is done automatically. In auto fill mode the filling is done at the end of the line.
➤ Filling/Justification  Toggle display of comments in buffer or active region	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	<ul> <li>See the <u>Filling/Justification</u> for all filling and justification commands.</li> <li>Toggle hiding/showing of comments in the active region or whole buffer.</li> <li>If the region is active then toggle in the region. Otherwise, in the whole buffer.</li> <li>This requires the <u>hide-comnt.el</u> package (see <u>Comments</u>).</li> </ul>
See also: <u>See also</u> : <u>See also: <u>See also</u>: <u>See also: <u>See also: <u>See also: See also: See also: <u>See also</u>: <u>See also: See also: See also: See also: <u>See also: See a</u></u></u></u></u></u>	All syntactic indentation cont	rol for D is controlled by the C	pel-use-hide-comnt user option is t.  CC-Mode logic and provided commands listed below.
Indentation	T	ds are also available and listed	d at the end of this list. They are also listed in the <b><u>Indentation</u></b> table.
Indent current line or region  See also: <u>∑ Indentation</u>	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	<ul> <li>Indent active region, current line, or block starting on this line.</li> <li>Behaviour depends on syntactic-indentation mode (enabled by default but can be toggled on/ off with the <f12> M-i key):</f12></li> <li>With syntactic-indentation on (the default): <ul> <li>In Transient Mark mode, when the region is active, reindent the region.</li> <li>Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line.</li> <li>Otherwise reindent just the current line.</li> <li>This might seem strange for new Emacs users, but it ends up being very useful. You can type <tab> anywhere in the line to adjust the indentation of the current line or everything in the marked area if a block is marked.</tab></li> </ul> </li> <li>With syntactic-indentation off: <ul> <li><a href="calcal-region-line">calcal-region line</a> or M- <a href="calcal-region-line">calcal-region line</a> or M- <a href="calcal-region-line">calcal-region line</a> or M- <a href="calcal-region-line">calcal-region line</a> lindenting marked region is done without syntax knowledge and at the same level as previous line.</li> <li>If you want to indent rigidly you can use:</li> <li>(pel-indent-rigidly &amp;optional N) (bound to C-x <a href="calcal-region-line">calcal-region rigidly</a>.</li> <li>(tab-to-tab-stop), bound to M-i to insert spaces to the next tab stop column.</li> </ul> </li> </ul>
Indent Erlang function	C-c C-q	(erlang-indent-function)	Indent current Erlang function.  Ship This also works with a simple tab (see above).
Indent lines of list after point See also: Indentation	С-М-q	(prog-indent-sexp &optional DEFUN)	Indent the expression after point. When interactively called with prefix, indent the enclosing defun instead.
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region.  • A numeric prefix argument specifies a column: indent each line to that column.  • With no prefix argument, the command chooses one of these methods and indents all the lines with it:  1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it.  2. If 'indent-region-function' is non-nil, call that function to indent the region.  3. Indent each line via 'indent-according-to-mode'.  When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>
Navigation in Erlang code See also: <u>Navigation</u>	Several commands are speci Notice the 3 sets of comm 1. <f12> <up> and    2. The standard navigates 3. The <f12> <u-cut below="" describe="" list="" services<="" td="" the=""></u-cut></f12></up></f12>	alization of the normal navigate ands: <f12> <down> move to the tion commands, (mapped to <rsor> commands (also accespecialized commands only. See the commands only.</rsor></down></f12>	Erlang source code. PEL complements these. And EDTS also tion commands which are described in the table \( \subseteq \textbf{Navigation} \), but several are specific to Erlang:  The beginning of Erlang functions skipping all compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning/end of Erlang functions but stop at compiler directives.  The prefix move to beginning end of Erlang functions but stop at compiler directives.  The prefix move to beginning end of Erlang functions but stop at compiler directives.  The prefix move to beginning end of Erlang functions but stop at compiler directives.  The prefix move to beginning end of Erlang functions but stop at compiler directives.  The prefix move to beginning end of Erlang functions but stop at compiler directives.  The prefix move to beginning end of Erlang functions but stop at compiler directives.  The prefix move to beginning end of Erlang functions but stop at compiler directives.  The prefix move to beginning end of Erlang functions but stop at compiler directives.  The prefix move to be end of Erlang functions but stop at c
Go to beginning of statement	м-а	(backward-sentence &optional ARG)	Go backward to the beginning of an Erlang clause.  • With a numerical argument repeat that many times.
Go to the end of statement	м-е	(forward-sentence &optional ARG)	Go forward to the end of an Erlang clause.  • With a numerical argument repeat that many times.
Go to beginning of current function or top-level function	С-м-а	(c-beginning-of-defun &optional ARG)	Move backward to the beginning of an Erlang function.  Every top level declaration that contains a brace paren block is considered to be a defun.  With a positive argument, move backward that many defuns. A negative argument -N means move forward to the Nth following beginning.
Goto end of current function or top-level function	С-М-е	( <b>c-end-of-defun</b> &optional ARG)	Move forward to the end of an Erlang function.  • With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
Move backward to beginning of previous function	• <f12> <up> • <f12> f p  • <f11> SPC e <up></up></f11></f12></up></f12>	(pel-previous-erl-function &optional N)	Move backward to the beginning of the previous function skipping all compiler directives.  • With prefix argument N repeat N times.  • Pushes mark; move back to previous position with M
	• <f11> SPC e f p</f11>		Shift marking is available for the key sequence using a cursor key.
Move forward to beginning of next function	• <f12> <down> • <f12> f n  • <f11> SPC e</f11></f12></down></f12>	(pel-next-erl-function &optional N)	Move forward to the beginning of the next function skipping all compiler directives.  • With prefix argument N repeat N times.  • Pushes mark; move back to previous position with M−ˆ.   ⇒Shift marking is available for the key sequence using a cursor key.
	<down> • <f11> SPC e f n</f11></down>		1.2 S.M. Harring to available for the Rey Sequence doing a cursor Rey.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Backward to beginning of function or compiler directive	<f12> f P  • C-M-a • C-M-<home> • <f6> p • <f6> <up> • <f11> SPC e f P</f11></up></f6></f6></home></f12>	(beginning-of-defun &optional ARG) (erlang-beginning-of- function &optional ARG)	Move backward to the beginning of an Erlang function or compiler directive.  • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun.  ⇒Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However <f6> p and <f6> <up> handle Shift-marking fine in terminal mode.  ➡Erlang.el man page indicates an invalid mapping for this.</up></f6></f6></home>
Forward to beginning of next function or compiler directive	<f12> f N  • <f6> n  • <f6> <down> • <f11> SPC e f N</f11></down></f6></f6></f12>	(pel-beginning-of-next-defun & optional SILENT DONT-PUSH_MARK)	Move forward to the beginning of the next function definition or compiler directive.  • Beeps if does not find beginning of next function unless SILENT is non-nil.  • If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.  • Move back to previous position with M⁻.  Shift marking is available for the <f6> bindings.  This command complements what end-of-defun does.  • It moves forward but not to the end of the function definition (like end-of-defun) but to the beginning of the function definition, which is often what users of other editors expect.  • It handles nested functions or class methods in languages like Python and others.</f6>
Backward to end of previous function or compiler directive	<f6> <left></left></f6>	(pel-end-of-previous- defun &optional SILENT DONT-PUSH_MARK)	Move backwards to the end of the previous function definition.  • Beeps if does not find end of previous function unless SILENT is non-nil.  • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.  • Move back to previous position with M−ˆ.  ⇒Shift marking is available for the <f6> bindings.  ■This command complements this set of 4 commands.</f6>
Forward to end of function or compiler directive	• C-M-e • C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG) (erlang-end-of- function &optional ARG)	Move forward to end of Erlang function.  With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun.  ➡ Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-M- <nd>end&gt;).  However <f6> <right> handle Shift-marking fine in terminal mode.</right></f6></nd>
Backward to beginning of clause	• C-c M-a • <f12> c a • <m-f12> <m-up></m-up></m-f12></f12>	(erlang-beginning-of- clause &optional ARG)	Move backward to previous start of clause.  • With argument, do this that many times.
Forward to beginning of next clause	• <f12> c n • <m-f12> <m-down></m-down></m-f12></f12>	(pel-beginning-of-next- clause)	Move forward to the beginning of next clause.  • Pushes mark; move back to previous position with M−ˆ.  → Shift marking is available.
Backward to end of previous clause	• <f12> c p • <m-f12> <m-left></m-left></m-f12></f12>	(pel-end-of-previous- clause)	Move backward to the end of the previous clause.  • Pushes mark; move back to previous position with M−ˆ.  ⇒Shift marking is available.
Forward to end of current clause	• C-c M-e • <f12> c e • <m-f12> <m-right></m-right></m-f12></f12>	(erlang-end-of-clause &optional ARG)	Move to the end of the current clause.  • With argument, do this that many times.
EDTS/Navigation	EDTS (see below) provides r	more navigation commands.	
Search Support	In Erlang mode, the superword mode can be useful since <u>snake_case</u> is often used. Using superword-mode helps searching.  PEL activates the superword mode by default in Erlang mode. To change this use the <b><f11> t <f2></f2></f11></b> to access the customize buffer.		
Toggle superword- mode  See also:	<f12> M-p  • <f11> t m p  • <f11> SPC e M-p</f11></f11></f12>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats <u>snake_case</u> as one word. In Erlang, '_' are treated as part of words.  • With a prefix argument ARG, enable superword mode if ARG is positive, and disable it otherwise.  • PEL provides the <f12> M-p key for the programming language modes where <u>snake_case</u> is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12>
Marking	The following Erlang-mode specific marking functions are available. They complement what is already available and described in the <u>Narking</u> table. For those 2 commands the <u>Erlang.el man page</u> indicates an invalid mapping for this. Reported as <u>ERL-1314</u> .		
Mark Erlang function	• C-M-h • <f12> f m</f12>	(mark-defun &optional ARG) (erlang-mark-function &optional ARG)	Put mark at end of this function, point at beginning.  The function marked is the one that contains point or follows point.  With positive ARG, mark this and that many next functions; with negative ARG, change the direction of marking.  If the mark is active, it marks the next or previous function(s) after the one(s) already marked.
Mark Erlang Clause	• C-c M-h • <f12> c m</f12>	(erlang-mark-clause)	Put mark at end of clause, point at beginning.
Highlighting blocks	show-paren-mode, which	highlights the parens that mate	e useful modes to highlight blocks of (), {}, and []. ches the one before or after point. s are highlighted with the same colour.
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode).  • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.
See also: <u>Neighlight</u>	• <f11> h ( • <f11> SPC e M-9</f11></f11>		Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.
Enable/Disable coloured highlight of nested blocks (),{},∏	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters-mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth.  • Customize the depth and colours with M-x customize-group rainbow-delimiters
See also: Mighlight	• <f11> h R • <f11> SPC e M-r</f11></f11>		Requires: rainbow-delimiters.el  PEL activates this when the pel-use-rainbow-delimiters user option is set to t.
Inserting code			
Insert Parentheses	M-(	(insert-parentheses &optional ARG)	For Erlang: insert a parenthesis pair '()', leaving point after open-paren.  • A positive ARG encloses the following ARG sexps in parenthesis if they are balanced.  • A negative ARG encloses the preceding ARG sexps instead.  • No argument is equivalent to zero: just insert '()' and leave point between.  • PEL makes 'parens-require-spaces' buffer local and set it to nil in Erlang mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis.  • If region is active, insert enclosing characters at region boundaries.  • This command assumes point is not in a string or comment.

Description		<u>Keystroke</u>	Function	<u>Note</u>
Insert Erlang Co	de		~	ons using the standard tempo skeleton package.
Templates		PEL provides the following	additional functionality:	he Erlang/Skeletons menu (via <b><f10></f10></b> ).
See also:				d under the pel:erlang-skel key prefix: <f12> <f12>. a +. These are also added to the menu.</f12></f12>
<ul> <li><u>∑ Inserting Text</u> more info and</li> </ul>		Several aspects of the second se	he PEL Erlang Source Code S	tyle is controlled by the user options inside the <b>pel-erlang-code-style</b> group. The controlled
information about tempo skeleton ar		erlang mode buffer and	include the following options:	user options are part of the <b>pel-erlang-code-style</b> group accessible with <f12> <f2> from an</f2></f12>
yasnippet templat based text insertion		<ul> <li>pel-erlang-skel-inse</li> <li>pel-erlang-skel-pro</li> </ul>	•	: set whether an automatically updated timestamp is inserted in the file header block. : set whether file and function skeletons blocks prompt for purpose and insert it.
				set whether function skeletons prompt for function name and then inserts that name. set whether function skeletons prompt for function arguments and then insert them.
		pel-erlang-use-sepa     pel-erlang-use-seco	arators	: set whether blocks use horizontal separator lines (these are the first of potentially 2 separators). : set whether blocks use a second block horizontal separator line.
		pel-erlang-skel-with	n-edoc	: set whether generated code comments use EDoc markup.
		• pel-erlang-skel-with  Emacs user options b		set whether file header blocks use open source software license text controlled by diffee.  But by using file and directory variables (see File/Directory Variables) they can also be used to
		take effect on a single file	e or all files inside a directory t	ree. So by default, the user options that control the PEL tempo template take effect globally. If the the user option control block at the end of that file. If you want to control the behaviour of the
		PEL tempo templates for	all files inside a directory tree	create a .dir-locals file and store the values of the relevant options variables inside that file. This nat of the tempo templates precisely and does not affect what you actually type.
		Once a skeleton was just	st entered (or later by activatin	g the pel-tempo-mode) you can move to the next or previous point of interest (so called tempo-
		Instead of using the <f< th=""><th>12&gt; <f12> bindings, you ca</f12></th><th>f and C-c M-b or some other keys like C-c . and C-c ,.  In also type the template name and then hit C-c C-M-i or <f12> <f12> <f12>. This</f12></f12></f12></th></f<>	12> <f12> bindings, you ca</f12>	f and C-c M-b or some other keys like C-c . and C-c ,.  In also type the template name and then hit C-c C-M-i or <f12> <f12> <f12>. This</f12></f12></f12>
+ : additional templa C : templates with	ates	supports listing all comp	oletions into a separate tempo	rary buffer. This is mainly useful for templates which short names such as "if", "case", etc
customization contro	ol			b links to the relevant Erlang language construct reference page.
<b>∑ Customize</b> PEL E	rlana	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-pel	in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.  Customize PEL Erlang skeleton layout.</f11>
Skeletons layout	inang	1111	&optional OTHER- WINDOW)	• If OTHER-WINDOW is non-nil (use <b>C</b> - <b>u</b> ), display in another window.
<u>if</u>		<f12> <f12> i</f12></f12>	(pel-erl-if)	Insert an if statement.
case		<f12> <f12> c</f12></f12>	(pel-erl-case)	Insert a case expression.
export	+	<f12> <f12> x</f12></f12>	(pel-erl-export	Insert an export module attribute expression.
import	+	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.
try	+	<f12> <f12> t</f12></f12>	(pel-erl-try)	Insert a try expression.
try-of	+	<f12> <f12> T</f12></f12>	(pel-erl-try-of)	Insert a try expression with of clauses.
receive		<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.
<u>after</u>		<f12> <f12> a</f12></f12>	(pel-erl-after)	Insert a receive expression with an after (timeout) clause.
Іоор		<f12> <f12> 1</f12></f12>	(pel-erl-loop)	Insert a simple receive loop.
module		<f12> <f12> m</f12></f12>	(pel-erl-module)	Insert the module attribute.
<u>function</u>	С	<f12> <f12> f</f12></f12>	(pel-erl-function)	Insert a function definition. This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.
author		<f12> <f12> `</f12></f12>	(pel-erl-author)	Insert the author attribute. Uses the <b>user-mail-address</b> user option to insert your mail address.
spec		<f12> <f12> s</f12></f12>	(pel-erl-spec)	Insert a <b>-spec</b> for the function following point.
small-header	С	<f12> <f12> M-h</f12></f12>	(pel-erl-small-header)	Insert a small file header without any comment.
normal-header	С	<f12> <f12> M-H</f12></f12>	(pel-erl-normal-header)	Insert a normal file header: includes author name, copyright notice, doc section, file created date
large-header	С	<f12> <f12> h</f12></f12>	(pel-erl-large-header)	Insert a large header block that includes all normal header fields plus separators.  • All formatting is controlled by user-options described above.
				Distinguish Erlang .erl module files from the .hrl header files.
small-server	С	<f12> <f12> M-s</f12></f12>	(pel-erl-small-server)	Insert a large file header and template logic for a small server.
application supervisor	С	<f12> <f12> M-a <f12> <f12> M-u</f12></f12></f12></f12>	(pel-erl-application) (pel-erl-supervisor)	Insert a large file header and template logic for an application behaviour.  Insert a large file header and template logic for a supervisor behaviour.
supervisor-bridge	С	<f12> <f12> M-u</f12></f12>	(pel-erl-supervisor-bridge)	Insert a large file header and template logic for a supervisor bridge behaviour.
generic-server	С	<f12> <f12> M-q</f12></f12>	(pel-erl-generic-server)	Insert a large file header and template logic for a gen-server behaviour.
gen-event	С	<f12> <f12> M-e</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a gen-event behaviour.
gen-fsm	С	<f12> <f12> M-f</f12></f12>	(pel-erl-gen-fsm)	Insert a large file header and template logic for a gen-fsm behaviour.
gen-statem-StateN	ame C	<f12> <f12> M-S</f12></f12>	(pel-erl-gen-statem- StateName)	Insert a large file header and template logic for a gen-statem behaviour.
gen-statem-handle	-	<f12> <f12> M-E</f12></f12>	(pel-erl-gen-statem-	Insert a large file header and template logic for a gen-statem.
event	С	Z£12\ Z£12\ V	handle-event)	Insert a large file header and tomplate logic for a way chiest generic service
wx-object gen-lib	С	<f12> <f12> M-w <f12> <f12> M-1</f12></f12></f12></f12>	(pel-erl-wx-object) (pel-erl-gen-lib)	Insert a large file header and template logic for a wx-object generic server.  Insert a large file header and template logic for a library module.
gen-corba-cb	С	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a CORBA callback module.
ct-test-suite-s		<f12> <f12> M-1</f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite
ct-test-suite-l		<f12> <f12> M-2</f12></f12>	(pel-erl-ct-test-suite-l)	Insert a large file header and template logic for a test suite
ts-test-suite		<f12> <f12> M-3</f12></f12>	(pel-erl-ts-test-suite)	Insert a large file header and template logic for a test suite
Tempo Template Ta Insertion	g	• C-c C-M-i • <f12> <f12> <f12></f12></f12></f12>	(tempo-complete-tag &optional SILENT)	Look for a tag and expand it.
		• <f12> <f12> <f12> <f12></f12></f12></f12></f12>	Spinorial Order()	Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit C-c C-M-i.</f12></f12>
		<f12></f12>		(or <f12> <f12> <f12>) A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists <b>all</b> available template names). Select the template name</f12></f12></f12>
				and hit RET. Emacs expands the template.
				udes 'tempo-tags') are searched for a match for the text before the point. The way the string to 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no
		match at all.  If a single match is found,	the corresponding template is	expanded in place of the matching string.
				LENT is non-nil, the function will give a signal. etion-buffer' is non-nil, a buffer containing possible completions is displayed.
				÷. 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Toggle pel-tempo-mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as C-c
See also:  • <u>National National Nationa</u>	• <f11> SPC e <f12> SPC • <f6> SPC</f6></f12></f11>	&optional ARG)	C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode.  Swhen a skeleton is inserted via the execution of one of the pel-erl commands above, the pel-tempo-mode is automatically activated.
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key key bindings are only available when pel-tempo-mode is active.
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward-mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key binding are only available when pel-tempo-mode is active.
Erlang syntax checking Using either:	Syntax checking for the Erlang programming language can be done with Emacs built-in flymake as well as with the external package flycheck.  To activate either set the pel-use-erlang-syntax-check user option is set to either 'use-flycheck or 'use-flymake.  By default, the syntax checker is not automatically launched. If you want to start your selected syntax checker as soon as any Erlang file is opened, add 'erlang-mode to the pel-modes-activating-syntax-check user-option.		
<ul> <li>flycheck or</li> <li>flymake</li> </ul>	• PEL automatically inst  Flymake has several cust The following customization • flymake-start-on-flymake • flymake-no-changes-tim • flymake-start-syntax-che The following variable contro • flymake-wrap-around: If	alls and activates flycheck womizable variables, which som variables determine the exact e-mode: to start checking veout: time to wait after last ceck-on-newline: to check and lavingation to next or previous non-nil, moving to errors wrap	circumstances whereupon Flymake decides to initiate a check of the buffer: when flymake-mode is started. <b>nil</b> to prevent check. hange to start checking. Default = 0.5 seconds. fter insertion or removal of newline char from buffer. <b>nil</b> to prevent check. s error:
		"	s only when flymake-mode is turned on.
Activate/deactivate selected syntax checker	<f12> ! <f11> SPC e !</f11></f12>	(pel-erlang-toggle-syntax-checker)	Toggle the selected Erlang syntax checker mode on/off.  The syntax checker activated or deactivated is either flycheck or flymake, as selected by the user-option variable `pel-use-erlang-syntax-check'.  Evaluate the syntax checker.
Go to next flymake diagnostic	M-n	(flymake-goto-next-error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.
Go to previous flymake diagnostic	М-р	(flymake-goto-prev-error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic.  With a prefix arg, skip any diagnostics with a severity less than ':warning'.  Display the error message in the echo line.
Compiling Erlang Code		ened to compile the files. The	e code files to .beam files located in the same directory as the source code. Detected errors are buffer shows the location of error and the error description. The following commands are used to
Compile code	• C-c C-k • <f12> M-c • <m-f12> M-c</m-f12></f12>	(erlang-compile)	Compile Erlang module in current buffer.  If buffer visiting file was modified and not saved, prompts the user to save it first.  Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command.  The buffer lists the errors. Hitting RET on the error file/line move point to that line in the Erlang file buffer. The RET key is bound to (compile-goto-error &optional EVENT)  It's also possible to use the next-error and previous error.
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output.  • Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.
Move to next compile error	• C-x • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; • negative means move back to previous error messages. • Just C-u as a prefix means reparse the error message buffer and start at the first error.  This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to previous compile error	• M-g p • M-g M-p	( <b>previous-error</b> & optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative).  This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Move to previous compilation or Flycheck detected error	C-c C-p	(edts-code-previous-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Erlang Shell	The following commands are	used to explicitly launch an E	rlang shell inside Emacs.
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.
Start Erlang Shell	• <f11> z r • <f11> SPC r z</f11></f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer.  • The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started.
	• <f12> z</f12>		<ul> <li>C-c C-z starts the Erlang Shell from the Erlang Mode.</li> <li><f11> z r starts it anytime, as long as it was installed.</f11></li> <li>Under PEL this command is available only when the pel-use-erlang user option is set to t.</li> </ul>
Inside the Erlang Shell	Redundant command eche     On some systems the Eri     Set the pel-erian     Cannot type the Eriang Ctr     To pass the Ctrl-G to the	ang shell annoyingly echoes e g-shell-prevent-echo user of d-G escape to access Erlang s Erlang shell running inside Erl bove workaround does not wo	ang, type: C-q C-g RET  rk for the Erlang shell invoked via url inside a vterm shell (see <u>S Shells</u> ) launched inside Emacs.
Erlang Shell: Command History	The Erlang shell history co	ontrolled by Emacs is saved in le. You can also use the Erlar	y issued Erlang shell commands at the shell prompt. side a file the is restored when opening a new shell: therefore commands from previously opened ag shell commands to access the local shell history.
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.
Previous shell command	М-р	(comint-previous-input ARG)	Cycle backwards through Erlang shell input history, saving input.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Using Man inside Emacs and support Erlang Man pages	Both of these are much m They are:     The man command use     WoMan: Browse Unix N	es the system man utility Manual Pages "W.O. (without) I	an reader available on the shell allowing navigation across man pages and opening hyperlinks.  Man" a complete implementation. It has some formatting limitations compared to man but it's very
See also: <u>▼ Help/Info</u>	useful in systems where man is not available like Windows.		
oee also. <u>// Trep/illio</u>	To see Erlang man pages using the man command:  On most systems the Man pages for Erlang are not available to the man utility and therefore not available for man inside Emacs.  There are several ways this can be remedied:  One is to set the MANPATH environment variable to include the directory where these files are located. Then man can be used outside and inside Emacs to access Erlang's man pages. For example the following lines can be stored inside a shell script to do this:  MANPATH=/usr/local/Cellar/erlang/22.3.4/lib/erlang/man:`manpath`		
	Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add the capabilities of Emacs man to fin the Erlang's man pages without modifying the capabilities of the parent shell. For example, if we want to use the same directory the above example we need to set the Man-switches which is normally set to nil to the following value:  "-M`manpath':/usr/local/Cellar/erlang/22.3.4/lib/erlang/man"		
	The second alternative can be used to add other directories for the man pages of other programming languages while leaving the ability to have several shells that have their own value of MANPATH. That might be very useful for someone that uses different versions of Erlang in a system and needs access to the man pages of different versions of Erlang. It becomes possible to run different shells inside Emacs with each having its own value of MANPATH and therefore providing the man pages from different locations. It is also possible to place all of these directories inside the Man-switches or MANPATH and buses man's ability to view several pages for the same topic.		
	directory only. You must	might help to see only Erlang t	copics when using the man command completion. To do that , set MANPATH to the Erlang man is located in the Erlang man page root directory, otherwise Emacs man completion will not work.
	EDTS (see below) support	orts the ability to download and ccess sections inside the man	Erlang used by various projects: d access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides it's ne pages, allowing EDTS driven man page access to co-exist with manual man command execution
About Erlang	Inside the pel-erlang-er environment variable. To environment variable wh parent-rootdir user-opti environment:  Install Erlang OTP I Creating whatis file Using the Erlang M Using Specialized O	o support the ability to open the en you select the version of Ei ion. See the following Installi Documentation and Man File is for Erlang man pages an files within Emacs	lang-man-parent-rootdir user-option can be set to read the man parent directory name from an me man files related to a specific version of Erlang available to the parent OS shell, set the rlang available to the OS shell and set the name of the environment variable in the pel-erlang-maning Erlang pages of the About Erlang document that describes an setting such an editing
See also: <u>Menus</u>	_	s to open an Erlang man page oar menu (with PEL open it wit	inside Emacs. th <f10>) in the Erlang section.</f10>
Open a man page inside an Emacs buffer	• <f11> ? m • ₩-M</f11>	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because:  • the links are active and can be followed. When the man page describes a directory or file,
See also: • <u>S Help/Info</u> • <u>S Customize</u>			emacs will open the file or the directory (in direct mode) when pressing RET over the link.  You can navigate easily between sections (n/p will move to the next/previous section)  You can use any of the searches.  You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer.  See all keys available in mode, with <f1> m or <f11>? k m.  PEL key sequence to customize man: <f11> <f2> E m</f2></f11></f11></f1>
Open a man page without external man process: woman See also:  > \( \) \( \) Help/Info  > \( \) Customize	<f11> ? w</f11>	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows).  PEL key sequence to customize man: <f11> <f2> E w  text width, use word at point, etc</f2></f11>
EDTS	EDTS - Erlang Develor	oment Tool Suite	
			external package. PEL activates it when the pel-use-edts user option is set to t. If you want set pel-use-edts to start-automatically instead of t.
Erlang Project settings	EDTS also uses an exter	rnal <b>.edts</b> configuration file to s node-name, erlang-cookie, lib	roup. With PEL you can open it, with other Erlang specific groups with <f12> <f3>.  store Erlang project specific settings. See <a href="EDTS: Configure your projects">EDTS: Configure your projects</a>. This allows setting the podirs, start-command, top-path, dialyzer-plt, app-include-dirs, project-include-dirs, xref-error-</f3></f12>
See also: <u>Sessions</u>	⚠ Desktop restoration often fails when edts-mode was active on session stored: unfortunately edts does not provide a desktop restore handler.  • ⊌ PEL does, however provide a desktop restore handler for EDTS which detects edts-mode failures and protect the desktop restoration.		
			cific key available is <f12> M-SPC to activate it. Once it's activated the other keys are available.</f12>
Toggle EDTS mode	<f12> M-SPC <f11> SPC e M-SPC</f11></f12>	(edts-mode &optional ARG)	Turn EDTS mode on or off.  • EDTS is an easy to set up Development-environment for Erlang.
	SPC & M-SPC		<ul> <li>EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further.</li> </ul>
EDTS/Navigation	support shift marking. Ther	e are other commands and ke	ove point across Erlang functions. These do not support repetition prefix argument nor they by bindings to move across Erlang functions, and PEL support functions that perform the same and listed in the navigation section above.
Move backward to beginning of previous function	C-c C-d C-b	(ferl-goto-previous- function)	Move backward to the beginning of the previous function skipping all compiler directives.  FEL provides a more complete command to move across functions (with or without skipping directives) that push mark and support shift marking. See in the navigation section above.
Move forward to beginning of next function	C-c C-d C-f	(ferl-goto-next-function)	Move forward to the beginning of the next function skipping all compiler directives.  PEL provides a more complete command to move across functions (with or without skipping directives) that push mark and support shift marking. See in the navigation section above.
EDTS/Cross References			It supports navigating in Erlang source code running in the current and remote nodes.  in erlang-mode. Their global equivalent is <b><f11> SPC e</f11></b> . It is not always shown for brevity.

<u>Description</u>	<u>Keystroke</u>	Function	Note
Find definition of	м	(edts-find-source-under-	Goto the source code that: defines the function being called at point or header file included at
identifier at point	n	point)	point. For remote calls, contacts an Erlang node to determine which file to look in, with the
			following algorithm:  • Find the directory of the module's beam file (loading it if necessary).
			<ul> <li>Look for the source file in:</li> <li>Directory where source file was originally compiled.</li> </ul>
			Todo: Same directory as the beam file
			<ul> <li>Todo: Again with /ebin/ replaced with /src/</li> <li>Todo: Again with /ebin/ replaced with /erl/</li> </ul>
			Otherwise, report that the file can't be found.
Go back to where M was last issued	М-,	(edts-find-source-unwind)	Unwind back from uses of 'edts-navigate'-commands.
Lists caller of function at point	• C-c C-d w • <f12> w</f12>	(edts-xref-who-calls)	Pops-up a menu of all callers of the function at point.
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who-calls)	Redo previous call to edts-who-calls.
Find a function in the current module	• C-c C-d f • <m-f12> M-f</m-f12>	(edts-find-local-function SET-MARK)	<ul> <li>Find a function in the current module.</li> <li>List local functions in the mini-buffer. Support completion. Move point to selected one.</li> <li>With C-u prefix, push mark before moving point.</li> </ul>
Find a module in the current project	• C-c C-d F • <m-f12> M-g</m-f12>	(edts-find-global-function)	Find a module in the current project.  • List project modules in the mini-buffer. Support completion. Open the file of selected one.
EDTS/AHS Editing	all of the buffer. The automa idle-interval which defaults	tic symbol highlighting mode s to 1.0 second.	s), and provides commands to modify the name of the highlighted name in the current function or in starts when the cursors stays on a symbol for a period longer than the value identified by the <b>ahs</b> -ove point away from the highlighted area.
Edit all highlighted	• C-c C-d e	(edts-ahs-edit-current-	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the
symbols in current function	• <f12> e</f12>	function)	current function.  • Activates ahs-edit-mode with edts-current-function range-plugin.
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer.  • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	Refactor the expression(s) in the region as a function.  • The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original
			<ul> <li>New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring.</li> <li>This command requires <u>Erlang syntax tools</u> package to be available in the node, version 1.2 (or perhaps later.)</li> </ul>
EDTS/Man	pages per project, so it is po	ssible to have several Erlang p	tion using the information extracted from Erlang Man pages. EDTS maintains a set of Erlang man projects each one with a different version of Erlang and their corresponding man pages. man commands described above in this table.
Download, install, select Erlang Man pages	<f12> `</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands.
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip.
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function. Find and show the man-page documentation for the Erlang module:function.
EDTS Code Analysis			
Compile current buffer	<f12> a c</f12>	(edts-code-compile-and-display)	Compiles current buffer on node related to that buffer's project.
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION-RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.
EDTS/Debug			
Toggle breakpoint	• C-c C-d b • <f12> d b</f12>	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.
List breakpoints	C-c C-d M-b • <f12> d B</f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle- interpreted)	Toggle the interpretation state for module in current buffer.
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
EDTS/Erlang Node			
Display EDTS Erlang	<f12> N</f12>	(edts-buffer-node-name)	Print the node sname of the erlang node connected to current buffer.
Node Name		,	<ul> <li>The node is either:</li> <li>The module's project node, if current buffer is an erlang module, or</li> <li>The buffer's erlang node if buffer is an edts-shell buffer.</li> <li>The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module</li> </ul>
			such as an otp-module or a module loaded by ~/.erlang).

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Start an EDTS controlled Erlang Shell	<f12> x</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell.
Start EDTS server	<f12> X</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).
Rendering markup embedded in comments		es to describe UML diagrams	pecific markup code embedded inside Erlang source code comments. This can be useful when or finite-state machines for example.
Preview UML diagram	<f12> u</f12>	(pel-render-commented-	Render the PlantUML markup embedded in current mode comment.
from plantUML source in current plantUML region of commented source code	<f11> SCP e u</f11>	plantuml PREFIX &optional POS)	<ul> <li>Use region if identified otherwise use PlantUML block at point.</li> <li>Uses prefix (as PREFIX) to choose where to display it:</li> <li>4 (when prefixing the command with C-u) -&gt; new window</li> <li>16 (when prefixing the command with C-u C-u) -&gt; new frame.</li> <li>else -&gt; new buffer</li> </ul>
See also: M PlantUML			This can be used inside buffer using <b>any</b> major mode, when PlantUML markup is embedded inside source code comment.
	block and issuing this comm	and.	ture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML ivated by <b>pel-use-plantuml</b> user option being non-nil.
Development Tool	The following commands are	used when adding Emacs Lis	p support for Erlang.
Show syntactic information	C-c C-s	(erlang-show-syntactic-information)	Show syntactic information for current line.  • Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.
Erlang_ls Language Server support			
	• s-1 = = • <f12></f12>	(Isp-format-buffer)	Ask the server to format this document.
	• s-1 F a • <f12></f12>	(Isp-workspace-folders- add PROJECT-ROOT)	Add PROJECT-ROOT to the list of workspace folders.
	• s-1 F b • <f12></f12>	(Isp-workspace-blacklist- remove PROJECT-ROOT)	Remove PROJECT-ROOT from the workspace blacklist.
	• s-1 F r • <f12></f12>	(Isp-workspace-folders- remove PROJECT-ROOT)	Remove PROJECT-ROOT from the list of workspace folders.
	• s-1 G g • <f12></f12>	(Isp-ui-peek-find- definitions & optional EXTRA)	Find definitions to the IDENTIFIER at point.
	• s-1 G i • <f12></f12>	(Isp-ui-peek-find- implementation &optional EXTRA)	Find implementation locations of the symbol at point.
	• s-1 G r • <f12></f12>	(Isp-ui-peek-find- references & optional INCLUDE-DECLARATION EXTRA)	Find references to the IDENTIFIER at point.
	• s-1 G s • <f12></f12>	(Isp-ui-peek-find- workspace-symbol PATTERN &optional EXTRA)	Find symbols in the worskpace. The symbols are found matching PATTERN.
	• s-1 T D • <f12></f12>	(Isp-modeline- diagnostics-mode &optional ARG)	Toggle diagnostics modeline.
	• s-1 T L • <f12></f12>	(Isp-toggle-trace-io)	Toggle client-server protocol logging.
	• s-1 T S • <f12></f12>	(Isp-ui-sideline-mode &optional ARG)	Minor mode for showing information for current line.
	• s-l T a • <f12></f12>	(Isp-modeline-code- actions-mode &optional ARG)	Toggle code actions on modeline.
	• s-1 T b • <f12></f12>	(Isp-headerline- breadcrumb-mode &optional ARG)	Toggle breadcrumb on headerline.
	• s-1 T d • <f12></f12>	(Isp-ui-doc-mode &optional ARG)	Minor mode for showing hover information in child frame.
	• s-1 T h • <f12></f12>	(Isp-toggle-symbol- highlight)	Toggle symbol highlighting.
	• s-1 T 1 • <f12></f12>	(Isp-lens-mode &optional ARG)	Toggle code-lens overlays.
	• s-l a a • <f12></f12>	(Isp-execute-code-action INPUT0)	Execute code action ACTION.  If ACTION is not set it will be selected from 'lsp-code-actions-at-point'.  Request codeAction/resolve for more info if server supports.
	• s-1 a h • <f12></f12>	(Isp-document-highlight)	Highlight all relevant references to the symbol under point.
	• s-1 a l • <f12></f12>	(Isp-avy-lens)	Click lsp lens using 'avy' package.
	• s-l g a • <f12></f12>	(xref-find-apropos PATTERN)	Find all meaningful symbols that match PATTERN.  • The argument has the same meaning as in 'apropos'.
	• s-l g g • <f12></f12>	(Isp-find-definition &key DISPLAY-ACTION)	Find definitions of the symbol under point.
	• s-l g i • <f12></f12>	(Isp-find-implementation &key DISPLAY-ACTION)	Find implementations of the symbol under point.
	• s-1 g r • <f12></f12>	(Isp-find-references &optional INCLUDE- DECLARATION &key DISPLAY-ACTION	Find references of the symbol under point.
	• s-1 h g • <f12></f12>	(Isp-ui-doc-glance)	Trigger display hover information popup and hide it on next typing.
	• s-1 h h • <f12></f12>	(Isp-describe-thing-at-point)	Display the type signature and documentation of the thing at point.
	1127		8

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
	• s-1 r o • <f12></f12>	(Isp-organize-imports)	Perform the source.organizeImports code action, if available.
	• s-1 r r • <f12></f12>	(Isp-rename NEWNAME)	Rename the symbol (and all references to it) under point to NEWNAME.
	• s-1 w D • <m-f12> M-s M-d</m-f12>	(Isp-disconnect)	Disconnect the buffer from the language server.
	• s-1 w d • <m-f12> M-s ?</m-f12>	(Isp-describe-session)	Describes current 'lsp-session'.  • Shows the information inside a LspBrowser buffer.
	• s-1 w q • <m-f12> M-s M-q</m-f12>	(Isp-workspace-shutdown WORKSPACE)	Shut the workspace WORKSPACE and the language server associated with it
	• s-1 w r • <m-f12> M-s M-r</m-f12>	(Isp-workspace-restart WORKSPACE)	Restart the workspace WORKSPACE and the language server associated with it
	• s-1 w s • <m-f12> M-s M-s</m-f12>	(Isp &optional ARG)	Entry point for the server startup.  When ARG is t the lsp mode will start new language server even if there is language server which can handle current language.  When ARG is nil current file will be opened in multi folder language server if there is such.  When 'lsp' is called with prefix argument ask the user to select which language server to start.

## Emacs & Erlang - References

Document	Notes
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.
Erlang versions	Erlang Versions - Version Scheme     Erlang Support, Compatibility, Deprecations, and Removal
Erlang/OTP @ Github	Erlang source code
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, Erlang Issue Tracker, events.
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.
Erlang References	
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.
Erlang Code Guidelines	
Erlang Programming Rules and Conventions	Official Ericsson AB Erlang guidelines.
Inaka's Erlang Coding Standards & Guidelines	Guideline used at Inaka, published on Github.
EDoc User's Guide	Describes how to document code.
Erlang Books	There are several printed and online Erlang books. Erlang's FAQ lists several of them. The following lists some extra ones.
Adopting Erlang	A great and recent (2019 and later) online books on Erlang Development that provides information not available in the Erlang introduction books. Describes how to install Erlang, and how to setup editing tools.  A must read to setup Erlang development. This is still work in progress as of May 2020.  Each page has a date time stamp.
Erlang Information Sites	
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.
about-erlang     trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang.  • about-erlang provides general information about Erlang, including:  • Learning Erlang, a table with links to resources to learn Erlang.  • Installing Erlang, describes various ways to install Erlang on macOS.
	• Tools for Erlang, describes tools you can use for Erlang development.
Emacs and Erlang Man files	
How to create a local whatis file	Show how to create a missing whatis file for a set of man pages.
The Erlang mode for Emacs (user guide)     Erlang mode for Emacs (man page)	On the <a href="Mailto:erlang.org">erlang.org</a> site. Start here. Describes the 2 files (erlang.el and erlang-start.el) provided by the Erlang mode support, how to set them up for various operating systems. Note, however, that PEL provides the setting for you. It also provides an overview of the various features the package provides.  • If found bugs in the <a href="Mailto:erlang.org">erlang.org</a> in the <a href="Mailto:Erlang.org">Edit: Howing the marker</a> section. 1) it's the point that is moved, not the marker, 2) C-a is not an Emacs key prefix, so their key binding descriptions like C-a M-a and C-a M-e are invalid. Reported as <a href="ERL-1314">ERL-1314</a> .  • There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric functions and variables.  • The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -> on a function definition line.  • Another issue: inside the OS-level erlang shell, we can tab-completion a module:function string, but that does not work inside the emacs erlang shell.
Emacs tools for Erlang	
EDTS	EDTS: stands for: The Erlang Development Tool Suite. See also:  • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube  • EDTS:  • configure your project  • One Primary EDTS node  • 1 node per open project  • To setup an Erlang project: a .edts file in the project:  :name "my-project"  :otp-path "path/to/otp"  :node-name "project-node-name"  :lib-dirs '("lib" "deps")
Harrista in atall EDTO	In

How to install EDTS

Describes some aspects of EDTS and links that may be useful. Lists the requirements.

After installing EDTS, I got several compile errors, and had to install the following other modules:
- auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?

Document	Notes
company-mode; Modular in-buffer completion framework for Emacs	
Using Tags with Erlang	
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the pel-erlang-shell-prevent-echo is set to t. To activate after setting it: execute pel-init or restart Emacs.