Emacs support for the Erlang Programming Language

<u> Topio maex</u>	Emacs su	pport for the	Erlang Programming Language	
<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Erlang Support	Emacs has no built-in support	for Erlang. 2 PEL supports	s Erlang when pel-use-erlang user options is turned on.	
See also: • Erlang Reference	· · · · · · · · · · · · · · · · · · ·	***	e-tree-sitter is set to t. See <u>S Tree Sitter</u> and <u>ft Tree-sitter</u> se-erlang to 'with-tree-sitter (as long as pel-use-tree-sitter is t and Emacs >= 30).	
PEL Manualabout-erlang			(see <u>erlang.el source</u>) are part of <u>OTP</u> .	
Developing Erlang Code with PEL			ang-complete and 🃦 company-erlang 🛂 activated by pel-use-company-erlang.	
set PEL Erlang environment	EDTS activated by pel			
	• W Helm by using helm-lsp		ne <u>erlang_Is</u> Erlang LSP server. Integrates with: pel-use-helm-lsp. Way by using Sp-ivy A activated by pel-use-lsp-ivy.	
 ∑ Auto-Completion ∑ Hide/Show 			pel-use-treemacs and pel-use-lsp-treemacs.	
 ∑ Text Modes ∑ Highlight 	• porigami by using Isp-or		pel-use-lsp-origami.	
• <u>Inserting Text</u>			neck set to 'use-flycheck, or Emacs built-in <u>flymake</u> if set to 'use-flymake. e mainly been replaced by EDTS and needs maintenance. PEL does not support it.	
	hide-comnt.el activate		,,,	
	I I	ed by pel-use-iedit.		
		ted by pel-use-smart-dash. ted by pel-use-smartparen		
• ∑ Speedbar	▼ Activate smart-dash-mode	or smartparens-mode autor	natically in erlang-mode buffers by adding their mode to pel-erlang-activates-minor-modes.	
			ectric-pair-local-mode: add electric-pair-local-mode to pel-erlang-activates-minor-modes. ess the customization group and select pairs.	
• <u>∑ Customize</u>			g via pel-activates-global-minor-mode : <u>show-paren-mode</u> g files to show the list of functions.	
			-skels-erlang.el, sections of pelkey-macros.el and pel keys.el and PEL files they require.	
	Customization:	awad by the group name and	N DETI to open the appelific quetemination group or one of the following key acquences	
	• pel-pkg-for-erlang: t	o activate pel-use-erlang : ι	I RET to open the specific customization group or one of the following key sequences. ISE <f11> SPC e <f2>, or <f12> <f2> from an Erlang buffer. This has sub-group: see pel-</f2></f12></f2></f11>	
	erlang-ide group to ac erlang: w		use <f11> SPC e <f3> 1</f3></f11>	
		when pel-use-edts is on,	use <f11> SPC e <f3> 3 n, use <f11> SPC e L <f3> 1</f3></f11></f3></f11>	
Identify minor modes to	• Isp-mode: v	vhen pel-use-erlang-ls is or	n, use <f11> SPC e L <f3> 2</f3></f11>	
activate automatically in erlang-mode buffers	pel-erlang-shell-preven	t-echo: set to t to prevent t	control Erlang editing. Only some of them are described here. Use Emacs for the complete list. he Erlang shell from echoing every command.	
01 61	pel-erlang-environment gr	roup:	ivation of local minor modes in erlang-mode buffers, eg. smart-dash-mode.	
Erlang Style			t directory of Erlang man directory. The man directory should hold the man1, man3, man4 and man6 (override) the erlang-root-dir user-option value with it which activates the appropriate Erlang	
Gontrol •		or if pel-erlang-man-parent-red dentifies the directory where	potdir is nil, you must set the erlang-root-dir user-option yourself. Erlang binaries are stored.	
 <u>Ericsson AB Guideline</u> <u>Inaka Guideline</u>			mechanism to detect Erlang/OTP version. By default it uses an Erlang script provided with PEL.	
	pel-erlang-code-style group		ing convey manyim we live to make (defaulte to 400). You can change the value as eat it will	
	When pel-erlang-fill	-column user option is nil, e	ing occurs : maximum <i>line length</i> (defaults to 100). You can change the value or set it nil. rlang-mode buffers use the global Emacs fill-column value.	
	 pel-erlang-skel-use-separators: whether line separators are used in Erlang code templates (see the Insert Erlang Code Template section below), pel-erlang-skel-use-secondary-separators: whether secondary separator lines are inserted by some Erlang code templates, 			
		•	automatically updated time stamps are inserted in Erlang source code file header blocks. I turned on, a space is automatically inserted after a comma typed inside a parens block.	
Last updated on:	2025-10-20			
Open this PDF file. See also: Help/Info	• <f11> SPC e <f1></f1></f11>	(pel-help-pdf &optional	Open the NI - Erlang local PDF. If the prefix argument (like C-u or M) is used, then it opens the	
See also. <u>« neip/illio</u>	• <f11> SPC e w <f1> • <f11> SPC e L <f1></f1></f11></f1></f11>	OPEN-WEB-PAGE)	remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.	
	• <f12> <f1></f1></f12>		Key sequences that start with <f11> SPC e are available from any major modes.</f11>	
	• <f12> w <f1> • <f12> L <f1></f1></f12></f1></f12>		Key sequences that start with <f12> are only available in erlang-mode buffers. The <f12> keys sequences are mirrored by the M-<f12> key sequence for convenience.</f12></f12></f12>	
∑ Customize PEL Erlang	<f11> SPC e <f2></f2></f11>	(pel-customize-pel	Customize PEL Erlang support: access PEL user-options to activate Erlang support packages.	
support	<f12> <f2></f2></f12>	&optional OTHER- WINDOW)	 If OTHER-WINDOW is non-nil (use C-u), display in another window. 	
∑ Customize Emacs	<f11> SPC e <f3></f3></f11>	(pel-customize-library	Customize Emacs Erlang support: erlang, erldoc, erlstack, edts, ivy-erlang-complete, lsp-erlang, lsp-	
Erlang support	<f12> <f3></f3></f12>	&optional OTHER- WINDOW)	mode, lsp-treemacs, auto-highlight-symbol, electricity, smart-dash, smartparens, treemacs. • If OTHER-WINDOW is non-nil (use C-u), display in another window.	
∑ Customize PEL LSP for	<f11> SPC e L <f2></f2></f11>	(pel-customize-pel	Customize PEL LSP Erlang support	
Erlang support	<f12> L <f2></f2></f12>	&optional OTHER- WINDOW)	• If OTHER-WINDOW is non-nil (use C-u), display in another window.	
T Customine France I CD		,	This is available when pel-use-erlang-is is turned on.	
∑ Customize Emacs LSP for Erlang support	<f11> SPC e L <f3></f3></f11>	(pel-customize-library &optional OTHER-	Customize Emacs LSP Erlang support: lsp-erlang, lsp-mode, lsp-ui, helm-lsp, lsp-ivy, lsp-origami, lsp-treemacs.	
	<f12> L <f3></f3></f12>	WINDOW)	 If OTHER-WINDOW is non-nil (use C-u), display in another window. ☑ This is available when pel-use-erlang-Is is turned on. 	
∑ Customize PEL LSP	<f11> SPC e w <f2></f2></f11>	(pel-customize-pel	Customize PEL LSP Erlang support	
Window for Erlang	<f12> w <f2></f2></f12>	&optional OTHER- WINDOW)	If OTHER-WINDOW is non-nil (use C-u), display in another window.	
support		,	This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on.	
∑ Customize Emacs LSP Window for Erlang	<f11> SPC e w <f3></f3></f11>	(pel-customize-library &optional OTHER-	Customize Emacs LSP Erlang support: Isp-treemacs, treemacs • If OTHER-WINDOW is non-nil (use C-u), display in another window.	
support	<f12> w <f3></f3></f12>	WINDOW)	This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on.	
Environment Help	Use the following command to	verify your Erlang environm	nent.	
Show PEL setup for	<f11> SPC e ? ?</f11>	(pel-erlang-setup-info	Display Erlang setup information inside a *pel-erlang-info* buffer with buttons providing quick access	
Erlang	<f12> ? ?</f12>	&optional APPEND)	to the customization buffer of each variable shown. The information shown includes the value and interpretation of:	
			 pel-use-erlang(whether the classic or tree-sitter based major mode is used). the user options controlling indentation and hard tab width rendering. 	
			To append information in the buffer instead of clearing the previous content type any prefix argument (such as C-u) before the command keystroke.	
Erlang Mode version	<f11> SPC e ? v</f11>	(pel-show-erlang-	To append information in the buffer instead of clearing the previous content type any prefix argument	
·	<f11> SPC e ? v</f11>	(pel-show-erlang- version)	To append information in the buffer instead of clearing the previous content type any prefix argument (such as C-u) before the command keystroke.	
•	<f11> SPC e ? v <f12> ? v</f12></f11>	version)	To append information in the buffer instead of clearing the previous content type any prefix argument (such as $\mathbf{C} - \mathbf{u}$) before the command keystroke. Display information about Erlang and Emacs Erlang supporting tools in the echo area. This includes the version of Erlang, erlang_ls, ivy-erlang-complete, the Erlang root path and its detection method,	
		version) Displays current version of erlang-man-parent-rootdir.	To append information in the buffer instead of clearing the previous content type any prefix argument (such as $\mathbf{C} - \mathbf{u}$) before the command keystroke. Display information about Erlang and Emacs Erlang supporting tools in the echo area. This includes the version of Erlang, erlang_ls, ivy-erlang-complete, the Erlang root path and its detection method, directory for Man files, lsp-keymap-prefix, etc	

<u>Description</u>	Keystroke	Function	Note			
Syntax Highlighting	The <u>erlang.el</u> external package Off, Level 1: comments only There is not key binding for thi	e provides several levels of Erlang code syntax highlighting: Level 2, Level 3, Level 4: maximum variety. s. You must use the Syntax Highlighting section of the Erlang menu: >> to access the menu, then select Erlang, Syntax Highlighting and the level you want.				
Electric Keys for Erlang Customize electric keys	1. the erlang.el external 2. the smartparens exter • Use <f11> ((to t) PEL provides customization ar • The pel-erlang-electric- • The pel-erlang-space-af</f11>	an impact on the "electric" behaviour of some keys in erlang-mode buffers: al package, which controls the behaviour of the RET, ,,; and > keys as controlled by erlang-electric-commands variable. ternal package, which modifies the behaviour of the DEL and <deletechar> behaviour when smartparens-mode is active. to toggle smartparens-mode on and off. and dynamic control of erlang-el electric key behaviour and provides electric behaviour of some extra keys. behaviour of some extra keys. cheys user-option set which of the RET, ,,; and > keys have electric behaviour. By default they are all activated. after-comma-in-block user-option activates automatic insertion of space after comma inside a block. Disabled by default. buffer, use the M-<f12> M- prefix key followed by one of these keys to toggle the electric behaviour of the key.</f12></deletechar>				
Toggle , electricity	M- <f12> M-` ,</f12>	(pel-erlang-comma &optional GLOBALLY)				
Toggle automatic insertion of space after comma in block	M- <f12> M-` M-,</f12>	(pel-erlang-toggle- space-after-comma &optional GLOBALLY)	Toggle automatic insertion of space after comma inside blocks. Show its new state. • To modify the behaviour in all Erlang buffers type: M M- <f12> M-` M-,</f12>			
Toggle > electricity	M- <f12> M-` ></f12>	(pel-erlang-gt &optional GLOBALLY)	Toggle electric behaviour of the greater-than key. Show message describing its new state. • To modify the behaviour in all Erlang buffers type: M M- <f12> M-` ></f12>			
Toggle RET electricity	M- <f12> M-` RET</f12>	(pel-erlang-newline &optional GLOBALLY)	Toggle electric behaviour of the newline key. Show message describing its new state. • To modify the behaviour in all Erlang buffers type: M M- <f12> M-\ RET</f12>			
Toggle; electricity	M- <f12> M-`;</f12>	(pel-erlang-semicolon &optional GLOBALLY)	Toggle electric behaviour of the semicolon key. Show message describing its new state. • To modify the behaviour in all Erlang buffers type: M M- <f12> M-';</f12>			
Toggle . electricity	M- <f12> M-` .</f12>	(pel-erlang-period &optional GLOBALLY)	Toggle Erlang electric behaviour of the semicolon key. Show message describing its new state. • To modify the behaviour in all Erlang buffers type: M M- <f12> M-\ .</f12>			
Toggle - electricity	M- <f12> M-` -</f12>	(smart-dash-mode &optional ARG)	Toggle the smart-dash-mode on/off. More info in $\underline{\mathbb{Z}}$ Text Modes and $\underline{\mathbb{Z}}$ Inserting Text .			
Matching Pairs	With smartparens-mode act This requires smartpa Add smartparens-mode	ivated typing the opening crens external package. de to pel-erlang-activates-	pairs made of (), [], { }, " " and ' '. PEL adds the << >> pair. character(s) automatically inserts the closing character(s) activated by pel-use-smartparens. minor-modes to activate smartparens-mode automatically for erlang-mode buffers. electric-pair-local-mode: add electric-pair-local-mode to pel-activates-minor-modes list.			
Matching pairs	(When the smartparens ex	cternal package is used and the smartparens-mode is active, the characters on the left are taken to be re: (), [], { }, " ", ' ', and << >> (added by PEL).			
XX Smartparens	1	 When typing the first ch 	aracter of a pair, the rest of the pair is inserted and point is left inside. xt inside one of those pairs, mark the text area then type the first character of the pair.			
	{	 The smartparens-mode can be activated automatically for Erlang by adding erlang-mode to the pel-erlang-activates-minor-modes user-option. 				
	,	• Use the <f11> ((ke</f11>	ey sequence to toggle the smartparens-mode on and off. arens-strict-mode that imposes balanced pairs but that does not help much in Erlang.			
	<<	 PEL adds support for << >> including navigation across balanced pairs, something the default erlang.el does not do, by replacing forward-sexp and backward-sexp by specialized functions. 				
Insert Parentheses	M- (M-((insert-parentheses & optional ARG) For Erlang: insert a parenthesis pair '()', leaving point after open-paren. Use this when smartparens is not used.				
	 No argument is equivalent to PEL makes 'parens-require- 	e following ARG sexps in parenthesis if they are balanced. A negative ARG encloses the preceding ARG sexps instead. o zero: just insert '()' and leave point between. If region is active, insert enclosing characters at region boundaries. spaces' buffer local and set it to nil in Erlang mode buffers, allowing the use of this command to insert the argument parentheses hout placing a space between the function name and the opening parenthesis.				
New Line	RET	(erlang-electric-newline &optional ARG)	Break line at point. If electric behaviour is activated: indent, continuing comment if within one. Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing.			
Electric behaviour: • indent next line		The electric behaviour of this key is controlled by 2 variables: • erlang-electric-commands must include the erlang-electric-newline symbol to activate the key electric behaviour. • erlang-electric-newline-criteria identifies how to check whether newline should behave electric. By default, the value is '(t): makes it behave electric as soon as the erlang-electric-commands list includes erlang-electric-newline.				
Electric < • ©X Smartparens	<	(erlang-electric-lt &optional ARG)	Insert a less-than sign, and optionally mark it as an open paren. • When smartparens-mode is active << automatically inserts the closing pair.			
Electric > Electric behaviour: • new line & indent	>	(erlang-electric-gt &optional ARG)	Insert a greater-than sign, and optionally insert a new line and indent. • Electric behaviour: -> force new line and indent. substituting the substitution of the su			
	M-1 >		Disable electric behaviour for this character: Just insert > by typing M-1 >			
Insert -> by typing		(pel-erlang-electric- period &optional arg)	Insert -> when typing only if the following conditions are met (otherwise inserts): • period is included in the pel-erlang-electric-keys user-option value • point is inside code and dash does not follow \$, as in \$-			
Electric comma Electric behaviour: • new line & indent • space after comma in block	, M-1 ,	(erlang-electric-comma &optional ARG)	Insert a comma character and possibly: • a new indented line when the comma is at the end of an Erlang expression. • a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert, by typing M-1,			
Electric semicolon Electric behaviour: • insert clause function	;	(erlang-electric- semicolon &optional ARG)	Insert a semicolon character and possibly a function clause head prototype on the next line. Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line. Inserts a function clause head prototype when the selection criteria identified by erlang-electric-comma-criteria indicates that it should be done.			
header		erlang-electric-semico	olon-insert-blank-lines sets # of lines inserted between the current line & new function header.			
smart-dash See: ∑ Inserting Text	• - • <kp-subtract></kp-subtract>	(smart-dash-insert)	Insert underscore following [A-Za-z0-9_], dash otherwise. See: <u>Inserting Text</u> Requires <u>smart-dash</u> <u>activated</u> by <u>pel-use-smart-dash</u> , or when smart-dash-mode is in <u>pel-erlang-activates-minor-modes</u> .			
Filling Text See also: Experiments Filling/Justification	 Filling Erlang code does r The pel-erlang-fill-column 	not work as it treats code as sets the fill-column variable f11> t f ? shows its val	buffer: code and comment. The auto-fill command will automatically wraps code and comments. s normal text. But filling comment paragraphs is useful. le to control where text wraps in Erlang buffers. lue. Use set-fill-column (C-x f) to set it. 11> 8.			
Fill current paragraph	• M-q • <f11> t f p</f11>	(fill-paragraph &optional JUSTIFY REGION)	Fill multi-line comment at or after point. • To justify as well: C-u M-q • In auto fill mode the text filling is done at the end of the line.			

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Erlang Comments Erlang Programming			uses the following conventions: ocated toward the end of a line of code	
Rules & Conventions See also: Comments	 %% - Two percent characters are used for comments starting at indentation level. %%% - Three percent characters are used to describe modules and are always placed in the first column The location of the comment inside a code line is controlled by the comment-column variable. Set it with comment-set-column, bound to Comment-column variable. 			
Comment/un-comment • PEL extension of	M-;	(comment-dwim ARG)	Comment line or region with % or %% style comments depending on the location in the buffer.	
comment-dwim specialized for Erlang.		(pel-erlang-comment- dwim &optional ARG)	Does the same but adds ability to insert %% comments. It does that on the very first line in the buffer and lines that follow a line that starts with %%% .	
Automatically uses the %%% comment when appropriate. ** Note:				
 M-; works much better than C-c C-c and C- c C-u 	With numeric argument: cor	mment current line. M-0 M	The M-3 prefix identifies 3 % characters to insert. You can use another number. 1-; However PEL uses M-1 for something else.	
 PEL maps M-; to pel- erlang-comment- dwim which works 	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region. • With just C-u prefix arg, uncomment each line in region BEG END.	
even better. • Comment the current line with M-0 M-;	The comment start is identify	fied by 'comment-start' and	Numeric prefix ARG means use ARG comment characters. If ARG is negative, delete that many comment characters instead. d'comment-padding'; the comment end by 'comment-end' and 'comment-padding'.	
See also: <u></u> Comments	By default, the 'comment-s	start' markers are inserted a	es do not get comments). This can be changed with 'comment-style'.	
Un-comment region	C-c C-u	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region. The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.	
Toggle display of comments in buffer or active region	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active, then toggle comments in the region. Otherwise, in the whole buffer. • PEL activates it with pel-use-hide-commt	
Hard Tabs Rendering See also: <u>Nation</u> Hard Tab Display Rendering	Like most programming languages, you can use hard tabs and spaces as horizontal whitespace in the Erlang source code. • Emacs supports all variations of styles: spaces only and mix of hard-tabs and spaces. Using only hard-tabs in Erlang is possible but rare. Some people use hard-tabs for indentation and extra spaces for alignment. Emacs supports all of these styles. • Emacs provides commands to convert code to remove all hard-tabs (untabify) and replace as many spaces as possible with hard tabs (tabify). • The tab-width user-option controls the visual rendering of hard tabs not the indentation level. • PEL provides an Erlang specific user option for hard-tab: pel-erlang-tab-width user-option. • PEL also provides the following command to dynamically modify the tab width rendering in the current buffer.			
Set visual rendering of hard tabs for the current buffer See Indentation	<f11> <tab> w</tab></f11>	(pel-set-tab-width N)	Change the tab width of the current buffer, only affecting the display rendering of hard tabs inserted the buffer text. Prompts for a new value in the [2, 8] range. • This modifies a buffer local value of the the tab-width user-option. • The change is temporary and affects the current buffer only. • To change the tab width used for all Erlang source code files, change the 'pel-erlang-tab-width' user-option variable instead.	
Hard Tab Insertion	The pel-erlang-use-tabs user-option controls whether hard tab characters are inserted in Erlang source code when Emacs inserts indentation whitespace. • This sets the Emacs indent-tabs-mode for Erlang buffers.			
Indentation indentation	-		the erlang-mode logic and several user-options in the erlang group. See solution independent of this list. They are also listed in the number of the second of the seco	
Indent current line or region	<tab></tab>	(indent-for-tab- command & optional ARG) Indent active region, current line, or block starting on this line: performs syntactic indentation • The indentation level is controlled by the erlang-indent-level user-option. Its default is 4. • Access its custom group buffer using <f12> <f3> 1</f3></f12>		
See also: <u>Nation</u> Erlang Guidelines: Ericsson AB: try to limit most code to 2 levels of indentation. Inaka: indentation level = 2 space chars.	Otherwise reindent just the You can type <tab> anyw Note that the erlang To indent rigidly you can w (pel-indent-rigidly &opti</tab>	ument, rigidly reindent the ecurrent line. */here* in the line to indent th .el logic doubles the indental use: onal N) (bound to C-x	dent the region. Appreciation starting on the current line. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked. The current line or everything in the marked area if a block is marked.	
Indent complete buffer	<f12> <tab></tab></f12>	(erlang-indent-current- buffer)	Indent current buffer as Erlang code. • Works on the entire buffer, even if it is narrowed.	
Indent Erlang function	C-c C-q <f12> f <tab></tab></f12>	(erlang-indent-function)	Indent current Erlang function. Point can be located anywhere inside the function.	
Indent function clause	<f12> c <tab></tab></f12>	(erlang-indent-clause)	Indent current Erlang clause. Point can be located anywhere in the Erlang clause.	
Indent lines of list after point	C-M-q	(prog-indent-sexp &optional DEFUN)	Indent the expression after point. See also: $\underline{\mathbb{Z} \ Indentation}$ When interactively called with prefix, indent the enclosing function instead.	
Indent a region	C-M-\		Indent each nonblank line in the region. • A numeric prefix argument specifies a column: indent each line to that column.	
	 With no prefix argument, the command chooses one of these methods and indents all the lines with it: 1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it. 2. If 'indent-region-function' is non-nil, call that function to indent the region. 3. Indent each line via 'indent-according-to-mode'. When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab> 			
Outline Erlang Code See <u>Soutline</u> for all key bindings	Once the minor mode is active This is very useful to quick	e you can collapse and expa ly see an outline of the code	the Erlang buffer into an outline of function definitions. outline-regex & outline-level and code as outlines and navigate using the outline commands. See the key bindings in Outline in a large file. Using the outline-hide-other is particularly effective. key prefix when the outline-minor-mode is active. Two useful key bindings are shown below.	
Toggle outline minor mode.	<f11> M-1</f11>	(outline-minor-mode &optional ARG)	Toggle Outline minor mode. • Enable with a prefix positive argument ARG, disable with negative argument.	
When active: P				
• Hide other	• <f2> o</f2>	(outline-hide-other)	Hide everything except current body and parent and top-level headings. • This also unhides the top heading-less body, if any.	

Description	<u>Keystroke</u>	Function	Note Note		
Navigation in Erlang	-		Erlang source code. PEL complements these. And EDTS also.		
code See also: • Navigation • Moving by Defuns	Several commands are specialization of the normal navigation commands which are described in the table <u>Navigation</u> , but several are specific to Erlang: Notice the 3 sets of commands: 1. <f12> <up> and <f12> <down> move to the beginning of Erlang functions skipping all compiler directives. 2. The standard navigation commands, (mapped to <f6> prefix) move to beginning/end of Erlang functions but stop at compiler directives. 3. The <f12> M-<cursor> commands (also accessible via M-<f12> M-<cursor>, move across Erlang clauses (as opposed to functions). The list below describe the specialized commands only. See the others inside <u>Navigation</u>, like the navigation by blocks. Note that all <f12> prefixes shown below are available in erlang-mode. Their global equivalent is <f11> SPC e. It is not always shown for brevity. Some navigation examples use icons to represent point position. The start position is shown as 0 with following positions as 1 to 10.</f11></f12></cursor></f12></cursor></f12></f6></down></f12></up></f12>				
EDTS/Navigation	The EDTS navigation function	ons do not support repetition	functions: ferl-goto-previous-function and ferl-goto-next-function. n prefix argument nor they support shift marking. to t or start-automatically). Activate EDTS (use <f12> M-E) to use these commands.</f12>		
By <u>Function</u>	Move to next/previous funct	ion beginning/end at/skippi	ng compiler directives. Skips clauses.		
to start of function	Move to beginning of fund	ction			
 Go backward to beginning of previous function 	<pre> <f12> <up> <f12> f p <f11> SPC e <up></up></f11></f12></up></f12></pre>	(pel-previous-erl- function &optional N)	Move backward to the beginning of the previous function skipping all compiler directives. • Moves point to the first character of the function name. • With prefix argument N repeat N times. • Pushes mark; move back to previous position with M— or <f6><f6>.</f6></f6>		
EDTC boood w	• <f11> SPC e f p C-c C-d C-b</f11>	(ferl-goto-previous-	▼ Shift marking is available for the key sequence using a cursor key. Move backward to the beginning of the previous function.		
EDTS based ►		function)	Skips all compiler directives. Does not support shift marking.		
Go forward to beginning of next function	<pre> <f12> <down> <f12> f n <f11> SPC e <down> <f11> SPC e f n </f11></down></f11></f12></down></f12></pre>	(pel-next-erl-function &optional N)	Move forward to the beginning of the next function skipping all compiler directives. • Moves point to the first character of the function name. • With prefix argument N repeat N times. • Pushes mark; move back to previous position with M⁻ or <f6><f6>. ▼ Shift marking is available for the key sequence using a cursor key.</f6></f6>		
<u>EDTS</u> based ▼	C-c C-d C-f	(ferl-goto-next-function)	Move forward to the beginning of the next function. Skips all compiler directives. Does not support shift marking.		
to start of function/ directive	Move to beginning of fund	ction or compiler directive			
Go backward to beginning of previous:	<f12> f P • C-M-a • C-M-<home> • <f6> <up> • <ff11> SPC e f P</ff11></up></f6></home></f12>	(beginning-of-defun &optional ARG) (erlang-beginning- of-function &optional ARG)	Move backward to the beginning of an Erlang function or compiler directive. • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun. ■ Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). It's always available for <f6> <up>: hold Shift after typing <f6>. ■ Erlang.el man page indicates an invalid mapping for this.</f6></up></f6></home>		
Go forward to beginning of next: function compiler directive	<f12> f N • <f6> <down> • <f11> SPC e f N</f11></down></f6></f12>	(pel-beginning-of-next- defun &optional SILENT DONT-PUSH_MARK)	Move forward to the beginning of the next function definition or compiler directive. • Beeps if does not find beginning of next function unless SILENT is non-nil. • If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−ˆ or <f6><f6>. ▼ Shift marking is available for the <f6> bindings: hold Shift after typing <f6>.</f6></f6></f6></f6>		
to end of function	Move to end of function c	or compiler directive			
Backward to end of previous: function compiler directive	<f6> <left></left></f6>	(pel-end-of-previous- defun &optional SILENT DONT-PUSH_MARK)	Move backwards to line after end of the previous function definition. • Beeps if does not find end of previous function unless SILENT is non-nil. • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−⁻. ■ Shift marking is available for the <f6> bindings.</f6>		
Forward to end of next: function compiler directive	• C-M-e • C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG) (erlang-end-of- function &optional ARG)	Move forward to line after end of Erlang function. With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. ■ Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-M- <end>). However <f6> <right> handle Shift-marking fine in terminal mode.</right></f6></end>		
By Expression functions, etc	Note that in Erlang every single expression or expression sequence ends with a period. Expressions in expression sequences are separated by commas. The following commands move to the beginning/end of single expression or expression sequence. They do not move across expressions in a sequence of expressions. Since Erlang function definition is also an Erlang expression, these commands move across function definitions.				
Go to beginning of statement	м-а	(backward-sentence &optional ARG)	Go backward to the beginning of an Erlang statement. • With a numerical argument repeat that many times.		
	<f12> s a</f12>	,			
Go to end of statement	M-e <f12> s e</f12>	(forward-sentence &optional ARG)	Go forward to the end of an Erlang statement. • With a numerical argument repeat that many times.		
By <u>Function Clause</u>		A function definition (state	ment) may have multiple clauses, each separated by a semicolon.		
Go backward to beginning of clause	• C-c M-a • <f12> c a • M-<f12> M-<up></up></f12></f12>	(erlang-beginning-of- clause &optional ARG)	Move backward to previous start of clause. • With argument, do this that many times. **Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.		
Go forward to beginning of next clause	• <f12> c n • M-<f12> M-<down></down></f12></f12>	(pel-beginning-of-next-clause)	Move forward to the beginning of next clause. • Pushes mark; move back to previous position with M− or <f6><f6>. ■ Shift marking is available.</f6></f6>		
Go backward to end of previous clause	• <f12> c p • M-<f12> M-<left></left></f12></f12>	(pel-end-of-previous- clause)	Move backward to the end of the previous clause. • Pushes mark; move back to previous position with M− or <f6><f6>. ■ Shift marking is available.</f6></f6>		
Go forward to end of current clause	• C-c M-e • <f12> c e • M-<f12> M-<right></right></f12></f12>	(erlang-end-of-clause &optional ARG)	Move to the end of the current clause. • With argument, do this that many times. **Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.		

Description	<u>Keystroke</u>	Function	<u>Note</u>		
Block Navigation See also:	() for function process. () for tuples, process. () for lists. () for strings. () for binaries. The smartparens-mode care.	es and bitstrings can be activated automatically for Erlang by adding erlang-mode to the pel-erlang-activates-minor-modes user-option.			
2x Smartparens	 Use the <f11> ((key sequence to toggle the smartparens-mode on and off.</f11> Standard Erlang support provide some commands to navigate across and into these balanced blocks. Their name is shown in black in the following rows. Other commands are provided by <u>S</u>x Smartparens when smartparens-mode minor-mode is active. Some are PEL specializations of smartparens code. 				
To Block start/end	The following commands mov		a block, skipping over Erlang terms inside these blocks.		
Go backward to beginning of previous block Skips terms.	• C-M-p	(backward-list &optional ARG)	Move backward to beginning of previous block. • Supports blocks of (), [] and {}. • With ARG, do it that many times. • A negative argument N means forward-list N. • This command assumes point is not in a string or comment. —spec ejabberd_started 6 () -> ok.		
			<pre>ejabberd_started 5() -> gen_server:call 4 (?MODULE, ejabberd_started, ?CALL_TIMEOUT). -spec config_reloaded 3() -> ok. config_reloaded 2() -> gen_server:call 1 (?MODULE, config_reloaded, ?CALL_TIMEOUT).0</pre>		
Go backward to end of previous block Skips terms. XX Smartparens with smartparensmode active	M- <f7> p</f7>	(pel-sp-previous-sexp &optional ARG)	Move backward to end of previous block. • With ARG, do it that many times. If there is no next expression at current level, jump one level up (effectively doing 'sp-up-sexp'). • A negative argument N means move to the end of N-th following balanced expression. -spec ejabberd_started() 6 -> ok. ejabberd_started() 5 ->		
			<pre>gen_server:call(?MODULE, ejabberd_started, ?CALL_TIMEOUT) 4. -spec config_reloaded() 3 -> ok. config_reloaded() 2 -> gen_server:call(?MODULE, config_reloaded, ?CALL_TIMEOUT) 1.0</pre>		
Go forward to end of next block Skips terms.	• C-M-n	(forward-list &optional ARG)	Move forward to end of next block. • Supports blocks of (), [] and {}. • With ARG, do it that many times. • A negative argument N means forward-list N. • This command assumes point is not in a string or comment. O-spec ejabberd_started() 1 -> ok.		
			<pre>ejabberd_started()2 -> gen_server:call(?MODULE, ejabberd_started, ?CALL_TIMEOUT)3. -spec config_reloaded()4 -> ok. config_reloaded()5 -> gen_server:call(?MODULE, config_reloaded, ?CALL_TIMEOUT)6.</pre>		
Go forward to beginning of next block Skips terms. ∑X Smartparens with smartparensmode active	M- <f7> n</f7>	(pel-sp-next-sexp &optional ARG)	Move forward to beginning of next block (and term if 'sp-navigate-consider-symbols' is set). • With ARG, do it that many times. • If there is no next expression at current level, jump one level up (effectively doing 'sp-backward-up-sexp'). O-spec ejabberd_started1() -> ok. ejabberd_started2() -> gen_server:call3(?MODULE, ejabberd_started, ?CALL_TIMEOUT).		
			<pre>-spec config_reloaded4() -> ok. config_reloaded5() -> gen_server:call6(?MODULE, config_reloaded, ?CALL_TIMEOUT).</pre>		
By Blocks and Terms See also: X Smartparens	Several Linux distros map Linux key binding in Systems	<left> and Esc C-<right C-M-<left> and C-M-<r ->settings->keyboard->shor</r </left></right </left>	o stops at terms. Le> bindings below, set pel-windmove-on-esc-cursor user-option is set to nil. Light> to desktop workspace operation. In that case you can either use another key binding or change touts to prevent it from using that key sequence. Le ability to move across Erlang's << >> bit syntax statement blocks.		
Go backward to beginning of previous term/block	• C-M- <left> • C-[C-b • Esc C-b • Esc C-<left> • C-M-b</left></left>	(pel-erlang-backward- sexp &optional ARG)	Move backward backward to beginning of previous term or block. • With ARG, do it that many times. • A negative arg N means move forward to end of N terms/blocks. • At beginning of block, jump out of the current one. • This command assumes point is not in a string or comment. • C-M-p : ▼ Shift marking is available in graphics mode, not in terminal mode. • C-M-b : ▼ Shift marking is available in graphics mode, not in terminal mode. • C-M- <left> : ▼ Shift marking works with this command. • C-M-<left> does not work on Windows, but H-<left> works.</left></left></left>		
 Ex Smartparens with smartparens-mode active: C-M-b and M- b use sp-backward-sexp others are using backward-sexp 	• C-M-b • M- <f7> b</f7>	(sp-backward-sexp &optional ARG)	Same as above with the additional behaviour: • With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default. • When it is nil, point only stops at 1, 4, 6 and 9: it jumps over terms. -spec ejabberd_started() -> ok. ejabberd_started() -> gen_server:call 9 (?MODULE, ejabberd_started, ?CALL_TIMEOUT).		
			-8spec 7config_reloaded 6() -> 5 ok. 5config_reloaded 4() -> 3gen_server: 2call 1(?MODULE, config_reloaded, ?CALL_TIMEOUT). 0 Inside a block: gen_server:call(?3MODULE, 2ejabberd_started, ?1CALL_TIMEOUT 0).		
Go forward to end of next term/block	• C-M- <right> • C-[C-f • Esc C-f • Esc C-<right></right></right>	(pel-erlang-forward- sexp &optional ARG)	Move forward to end of term or block. • With ARG, do it that many times. • A negative argument N means move backward to beginning of previous term or block. • At end of block, jump out of the current one. • C-M-n : ■ Shift marking is available in graphics mode, not in terminal mode.		

```
Function
                                       Keystroke
                                                                                          • C-M-f
                                                                                          • C-M-f : Shift marking is available in graphics mode, not in terminal mode
• C-M-<right> : ► Shift marking works with this command.
                              • C-M-f
                                                                                           ♦ C-M-<right> does not work on Windows, but H-<right> does.
    ∑X Smartparens
                                                                                           Same as above with the additional behaviour:
                                                              (sp-forward-sexp
                              • C-M-f

    With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced
expressions. It is set by default.

                                                              &optional ARG)
                              • M-<f7> f
     with smartparens-
     mode active:
        C-M-f and M-
                                                                                                 • When it is nil, point only stops at 3, 6 and 9 it jumps over terms.
        <f7> f use sp-
forward-sexp,
                                                                                           0-spec1 ejabberd_started2()3 -> ok4.
       others are using forward-sexp
                                                                                           ejabberd_started5()6 ->
                                                                                                gen_server 7: call 8 (?MODULE, ejabberd_started, ?CALL_TIMEOUT) 9.
                                                                                            -spec 10 config_reloaded() -> ok.
                                                                                           config_reloaded() ->
                                                                                                gen_server:call(0?MODULE1, config_reloaded2, ?CALL_TIMEOUT3).
                             Navigate inside nested blocks of elements with the following commands.

    Into block

Into block forward
                                                              (down-list &optional
                                                                                           Move forward to the beginning of inner element of a block.
                              C-M-d
                                                                                             With ARG, do this that many times.

A negative argument N means move backward but still go down a level.
                                                              (sp-down-sexp &optional ARG)
                              • C-M-d
   • If ARG is raw prefix argument C-u, descend forward as much as possible.
                              • M-<f7> d
                                                                                             If ARG is raw prefix argument C-u C-u, jump to the beginning of current list.
     with smartparens-
                                                                                             If the point is inside block and there is no down expression to descend to, jump to the beginning of
                                                                                             current one. If moving backwards, jump to end of current one.
    00
                                                                                           music info() ->
                                                                                                👈 example
                                                                                                              {group, "contraction"},
[0[1{2song, "3sam M'Madown"},
{song, "A la claire fontaine"},
{song, "L'alarme à l'oeil"},
{song, "La bourse ou la vie"}]
{rating, excellent}}}.
                                                                                                                                                                   example
Into block backward
                              • M-<f7> z
                                                              (sp-backward-down-
                                                                                           Move backward down one level to end of block element.
                              • C-M-z
                                                              sexp &optional ARG)
                                                                                           · With ARG, do this that many times.
                                                                                          · A negative argument N means move forward but still go down a level.
     ∑X Smartparens
     with smartparens-
                                                                                             If ARG is raw prefix argument C-u, descend backward as much as possible.
                                                                                             If ARG is raw prefix argument C-u, jump to the end of current list.
     mode active
                                                                                          • If the point is inside sexp and there is no down expression to descend to, jump to the end of current
                                                                                             one. If moving forward, jump to beginning of current one.
                                                                                           music_info(1) ->
                                                                                               example
                                                                                                              {rating, excellent4}3}2}1}.0
                                                                                                                                                                   example
· to edge of block
                                                              (sp-beginning-of-sexp & optional ARG)
                                                                                          Jump to beginning of the block the point is in.
To beginning of block
                              • M-<f7> a
                                                                                             The beginning is the point after the opening delimiter.
                                                                                             With no argument, this is the same as C-u C-u 'sp-down-sexp'
With ARG positive N > 1, move forward out of the current expression, move N-2 expressions

    ∑X Smartparens

     with smartparens-
                                                                                             forward and move down one level into next expression. With ARG negative \bf N < 1, move backward out of the current expression, move N-1 expressions
     mode active
                                                                                             backward and move down one level into next expression.

With ARG raw prefix argument C-u move out of the current expressions and then to the beginning
                                                                                             of enclosing expression
                                                                                          {good, {{1year, 19074},
                                                                                                                                                                    example
                                                                                                              {group, "1 Contract 0 ion"},
                                                                                                                                                                    example
                                                                                                              [1{song, "Sam M'Madown";,
{song, "A la claire fontaine"},
{song, "L'alarme à l'oeil"},
                                                                                                                            "La bourse ou la vie"}[0]
                                                                                                                {song,
                                                                                                                                                                    example
                                                                                                              {rating, excellent}}}.
                                                              (sp-end-of-sexp
&optional ARG)
                                                                                           Jump to end of the current block.
To end of current block
                             M-<f7> e
                                                                                             With no argument, this is the same as calling C-u C-u 'sp-backward-down-sexp'.
  forward

    With ARG positive N > 1, move forward out of the current expression, move N-1 expressions forward and move down backward one level into previous expression.

    ∑X Smartparens
                                                                                            With ARG negative N < 1, move backward out of the current expression, move N-2 expressions backward and move down backward one level into previous expression.
     with smartparens-
     mode active
                                                                                          • With ARG raw prefix argument {\bf C}-{\bf u} move out of the current expressions and then to the end of
    00
                                                                                             enclosing expression.
                                                                                           music info() ->
                                                                                                example
                                                                                                  { Ogood, {{year, 1974},
                                                                                                                                                                      example
                                                                                                              {group, "Contraction"},
                                                                                                                           Contraction",
"Sam M'Madown"},
"A la claire fontaine"},
"L'alarme à l'oeil"},
"La bourse ou la vie"}]
                                                                                                               [{song,
                                                                                                                {song,
{song,
{song,
                                                                                                              {rating, excellent}} 1 }.
```

Description	<u>Keystroke</u>	Function	<u>Note</u>
Out of block			
Out block forward forward Ex Smartparens with smartparens- mode active	C-M-] • C-M-] • M- <f7>]</f7>	(up-list &optional ARG ESCAPE-STRINGS NO- SYNTAX-CROSSING) (sp-up-sexp &optional ARG INTERACTIVE)	Move forward out of one level of block parens. • With ARG, do this that many times. • A negative argument means move backward but still to a less deep spot. • If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between end of the expression and the last "thing" inside the expression. • This behaviour can be suppressed for syntactic string blocks by setting 'sp-navigate-reindent-after-up-in-string' to nil. • If 'sp-navigate-close-if-unbalanced' is non-nil, close the unbalanced expressions automatically. • music_info() -> {{er Oror, {noreply, State}}} , example {group, "Contraction"},
backward backward EX Smartparens with smartparens- mode active	• M- <f7> u • C-M-u</f7>	(sp-backward-up-sexp &optional ARG INTERACTIVE)	Move backward out of one level of block parens. • With ARG, do this that many times. • A negative argument means move forward but still to a less deep spot. • If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between beginning of the expression and the first "thing" inside the expression. music_info() -> [output
Move over space	Current implementation of	sp-forward-symbol and sp- tegrated PEL implement wo	age and required smartparens-mode minor-mode to be active. -backward-symbol stop inside comments. I consider this a bug is so I reported and submitted a brighted comments or stop inside comments: pel-sp-forward-symbol and pel-spe until the fix is integrated.
To beginning of next symbol/block • <u>Ex Smartparens</u> with smartparensmode active	M- <f7> SPC n</f7>	(sp-skip-forward-to- symbol &optional STOP- AT-STRING STOP- AFTER-STRING STOP-INSIDE-STRING)	Skip whitespace and comments moving forward. • If STOP-AT-STRING is non-nil, stop before entering a string (if not already in a string). • If STOP-AFTER-STRING is non-nil, stop after exiting a string. • If STOP-INSIDE-STRING is non-nil, stop before exiting a string. start_app(App) -> 0
To end of next symbol or block • EX Smartparens with smartparens mode active See mode active	M- <f7> SPC m</f7>	(pel-sp-forward-symbol &optional ARG)	Move point to the next position that is the end of a symbol. • With ARG being positive number N, repeat that many times. • With ARG being negative number -N, repeat that many times in backward direction. • A symbol is any sequence of characters that are in either the word constituent or symbol constituent syntax class. Current symbol only extend to the possible opening or closing delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax classes. **start_app(App) ->
To beginning of previous • <u>*** Smartparens</u> with smartparens- mode active *** See **** note above.	M- <f7> SPC p</f7>	(pel-sp-backward- symbol &optional ARG)	Move point to the next position that is the beginning of a symbol. • With ARG being positive number N, repeat that many times. • With ARG being negative number -N, repeat that many times in forward direction. • A symbol is any sequence of characters that are in either the word constituent or symbol constituent syntax class. Current symbol only extend to the possible opening or closing delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax classes. 8 start_app(7 App) -> % first clause 6 start_app(5 App, 4 temporary). 3 start_app(2 App, 1 Type) -> % second clause 0 StartFlag = not is_loaded(), startFlag).
Skip forward past whitespace • <u>EX Smartparens</u> with smartparensmode active	M- <f7> SPC .</f7>	(sp-forward-whitespace &optional ARG)	Skip forward past the whitespace characters. With non-nil ARG return number of characters skipped. Start_app(App) ->
Skip backward past whitespace • <u>E</u> Smartparens with smartparens mode active	M- <f7> SPC ,</f7>	(sp-backward- whitespace &optional ARG)	Skip backward past the whitespace characters. • With non-nil ARG return number of characters skipped. start_app(App) ->1

Description	<u>Keystroke</u>	Function	Note			
Cross Reference	Erlang cross reference navigat	ion, that uses the M key	to move to the definition of the thing at point, is supported by several tools:			
navigation See Xref	 The xref-based cross reference tools with the following backends: etags (with etags or CTags generated tags file), use <u>etags-erl</u> shell script to create a TAGS file in the directory root to use with etags. 					
	Global/gtags with	ggtags. Source the envfor-	gtags shell script to set up your shell before starting Emacs to use gtags.			
See PEL Manual Erlang Cross Reference			PEL manual installation instructions for GNU Global.			
section for comparison of available methods.			to to install the Emacs-side support ggtags package and activate the gtags commands.			
c. aranabie memous.	 i dumb-jump to navigate without having to create external database or tags files. i For the above use the <f11> x <f2> key sequence to access PEL customization buffer for cross reference control.</f2></f11> 					
	Other specialized tools for E	•				
	_	ete_external package 🛂 ac ion of Erlang installed that s	supports Erlang escript.			
		The state of the s	d, which is not accessible on macOS by default.			
	Install gnu-sec	with Homebrew. I provide	d a patch which solves the problem by detecting macOS and using gsed instead of sed.			
		I package. 🔁 activated by	pel-use-edts user option. by the pel-use-erlang-is user-option.			
	and Erlang library aware provide Erlang knowledge. The other	ding a good user experience Xref-based tools require a T	server to operate. None of the other tools do. ivy-erlang-complete parse Erlang code and is project e without having to launch an Erlang node or server. dumb-jump uses fast search tools but has limite (AGS (etags) or a database (ggtags) that must be setup prior to use. The ggtags tool provide more not require any other external package.			
PEL Unified Cross Reference	PEL unifies all of these tools		Some of these are accessible via Emacs unified Xref mechanism but not all. one you prefer to use via customization and also allowing you to change the tool during and editing			
Navigation	session. Select the default cross ref	erence engine by setting the	e pel-erlang-xref-engine user-option.			
	Modify the cost reference e	ngine during an editing ses	sion with M- <f12> M M Display which one is used with M-<f12> M M.?</f12></f12>			
	To move point to the definition		over it and type the usual M key. It will use the currently selected cross reference engine.			
† Select Cross Reference back-end for Erlang	M- <f12> M M</f12>	(pel-erlang-select-xref)	Select another Erlang cross reference back-end from the back-ends currently available. The selection remains active for the current editing session. The 'pel-erlang-xref-engine' user-option identifies the persistent selection.			
Show selected Erlang Cross Reference back- ends	M- <f12> M M-?</f12>	(pel-erlang-show-xref)	Show Erlang cross reference back-end selected by customization and the one currently active.			
Find definition of	The state of the s					
identifier at point using currently active engine		definitions)	 Uses the currently active Erlang cross-reference back-end selected by 'pel-erlang-xref-engine' user-option or modified via M-<f12> M M</f12> 			
★★★ See also: ∑ Xref			If there are more than one match, prompt in the *xref* buffer. For the Xref-driven back-ends: to search for a symbol entered manually, type C-u M			
Go back to where M	м-,	(xref-pop-marker-stack)	Pop back to where M was last invoked.			
was last issued	•	,	Marker depth is controlled by the xref-marker-ring-length user option.			
EDTS/Cross References	EDTS provides the following cross-reference commands. It supports navigating in Erlang source code running in the current and remote nodes. PEL unbinds EDTS M and M-, to allow EDTS to work with PEL unified cross reference mechanism, and creates the bindings under C-c C-d.					
	Requires the EDTS external package. 2 activated by pel-use-edts user option.					
			e unified cross reference navigation. e mechanism or anything selectable by pel-erlang-select-xref as described above.			
			s on, you can force using the EDTS commands using the C-c C-d key bindings shown below.			
EDTS	M	(edts-find-source-	Goto the source code that: defines the function being called at point or header file included at point.			
Find definition of identifier at point	C-c C-d M	under-point)	For remote calls, contacts an Erlang node to determine which file to look in, with the following algorithm:			
			 Find the directory of the module's beam file (loading it if necessary). Look for the source file in: 			
			Directory where source file was originally compiled. Todo: Same directory as the beam file			
			Todo: Again with /ebin/ replaced with /src/			
			Todo: Again with /ebin/ replaced with /erl/ Otherwise, report that the file can't be found.			
EDTS: Go back to	M-,	(edts-find-source-	Unwind back from uses of 'edts-navigate'-commands.			
where M was last issued	C-c C-d M-,	unwind)				
Lists caller of function at	• C-c C-d w	(edts-xref-who-calls)	Pops-up a menu of all callers of the function at point.			
point	• <f12> w</f12>					
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who- calls)	Redo previous call to edts-who-calls.			
Find a function in the current module	• C-c C-d f • M- <f12> M-f</f12>	(edts-find-local- function SET-MARK)	 Find a function in the current module. List local functions in the mini-buffer. Support completion. Move point to selected one. With C-u prefix, push mark before moving point. 			
Find a module in the current project	• C-c C-d F • M- <f12> M-g</f12>	(edts-find-global- function)	Find a module in the current project. List project modules in the mini-buffer. Support completion. Open the file of selected one.			
ivy-erlang-complete	ivy-erlang-complete provides	_				
Cross References			ctivated by pel-use-ivy-erlang-complete user-option. navigation in the unified cross reference navigation.			
	You can use its cross refere	nce mechanism or anything	selectable by pel-erlang-select-xref as described above.			
	While another cross reference		ivy-erlang-complete by using the key bindings under C-c as shown below.			
Find definition of identifier at point	• C-c M • M	(ivy-erlang-complete- find-definition)	Find Erlang definition using ivy-erlang-complete.			
	• C-c M-?	(ivy-erlang-complete-	Find erlang references.			
	• M-?	find-references)	Use M-, to go back to original location.			
	• <f12> C-f</f12>	(ivy-erlang-complete-	Find spec at point, with ivy completion listing all found, then opening source file.			
	• C-c C-f	find-spec)	It also find callback definition.			

Description	Kovotroko	Function	Note	
Description Open file at point	Keystroke The following commands, allow		Note name taken at point (the cursor location). They work regardless of the input completion method	
орон но дорони		do completion mode, it is po	mngt ossible to instruct Ido to use a file name at point as the basis for the file name to open. This Ido t user-option. With PEL you can control it globally or locally with <f11> f M</f11>	
Open file at point.	• <f12> C-o</f12>	(ivy-erlang-complete-	Open file at point. Find file in current project.	
	• C-c C-o	find-file)		
Open file or web-page whose name is at point	• M-* • <f11> f .</f11>	(pel-open-at-point &optional N)	Open the file, library or the URL, named at point, with potential line & column #s. Supports glob characters, partial directory path. When multiple files are found it prompts using the	
★★ Command is also	• <u>6y</u>		method selected by pel-prompt-read-method user-option.	
specialized for: • M reStructuredText			The <u>6y</u> key-chord is available if pel-use-key-chord is non-nil. See <u>∑ Key-Chords</u> .	
• <u>\$\pi - C</u>	inside the Erlang project deper	ndencies (normally stored in	or Erlang major mode: it is able to find source files in Erlang root directory and project tree, including nside the deps directory tree created when building the project.	
• <u>क्रा - C++</u>	The following user option of the pel-erlang-project-		identifies the files that are used as markers of Erlang project directory root.	
Finds files in other	 The pel-project-root-identifiers user-option identifies the files used to identify the project root in general. This includes the file .pel-project you can use if nothing in the list works for you. 			
Erlang directories	The search for file supports glo	ob characters and partial discommand over the string "s	,	
Generic Delimiting characters		n works by identifying the b	e, and possibly line and column numbers, from text at point and tries to open the file or directory. eginning & end of the file/directory/library/URL name string by delimiter characters, one of: tab, newline	
! The complete file detection heuristic is			nem and prompts using the method selected by pel-prompt-read-method user-option.	
described in the <u>\(\tilde{\text{File}} \)</u> mngt description of the			by PEL. You can select a more powerful <u>ivy</u> prompting instead. el-use-ivy to t ⊚ and <u>Ivy mode</u> will be installed automatically when you restart Emacs.	
same command.			specified search method, it does not only use the first one found.	
Select target window	The command opens the file in		der file names in large include paths. ne following logic controlled by presence or absence of typed numerical prefix arguments:	
	Select target window: Without argument:			
	point.		nove point to that window and to the line column coordinates if specified following the file name at	
N>20 : open the	window, if 2: use the o	ther window, if 3 or more, u	ow according to the number of editable windows in frame: if 1, split that window and use the new se the current window.	
directory F	With prefix numeric argur N < 0 : create a new w	indow and use that.	the file laborated the critical course this form the Northead Notice and to be all NO (as N 00 (f N is a seeking)	
	• N = 0: use the 'other' (the next) window.	the file. Interpret the window position from the N value adjusted: N-20 (or N+20 if N is negative)	
	• if 1 window:	split that window and us	the target window based on the number of editable windows in frame: se the new window,	
See function docstring for more info.		use the other window, s: use the current window.		
	 N is: 8: up, 2: down, 4:left, 5:current, 6:right. N is 9: force opening the file in the OS associated application (with N=29 or N=-29, open the file's directory with the OS associated application (etc.) 			
	Selecting Minibuffer, inex		L, open it in the OS default web browser. is not allowed.	
Completion	Completion is available from various sources. • Without help from EDTS or LSP, the ivy-erlang-complete external package parses the Erlang libraries to identify the supported functions.			
			ated by pel-use-ivy-erlang-complete user-option.	
		of Erlang installed that sup lete replies on GNU sed, which was the control of th	hich is not accessible on macOS by default.	
	 Install gnu-sed with Homebrew. I provided a patch which solves the problem by detecting macOS and using gsed instead of sed. With company-erlang 2 activated by pel-use-company-erlang, the company backends provides completion popup menus to suggest identifiers. 			
	*		or of already written identifier, with is helpful to modify existing or incomplete code.	
Hippie Expand Abbreviation	M-/	(hippie-expand ARG)	Try to expand text before point, using multiple methods. • Not an Erlang completion command but it can be useful to pick up names present in the files.	
			The expansion functions in 'hippie-expand-try-functions-list' are tried in order, until a possible expansion is found. Repeated application of 'hippie-expand' inserts successively possible.	
			expansions. • With a positive numeric argument, jumps directly to the ARG next function in this list. With a	
See also: <u>National Hide/Show</u>			negative argument or just C-u , undoes the expansion.	
Completion of Erlang	<f12> .</f12>	(ivy-erlang-complete)	PEL activates this when the pel-use-hippie-expand user option is set to t . Erlang completion at point.	
code at point.	C-:	(2) Chang complete)	Aware of Erlang modules and functions for the currently used Erlang version identified by the ivyerlang-complete-erlang-root user-option which is adjusted to the erlang-root-dir	
			▲ ivy-erlang-complete replies on GNU sed, which is not accessible on macOS by default.	
			 To solve the problem you must install gnu-sed with Homebrew since ivy-erlang-complete shell scripts use gsed instead of sed. 	
Display Auto-completion status	<f11> , ?</f11>	(pel-completion-help)	Display information about available auto-completion. Shows which one is enabled via customization and their current activation state.	
Explicitly List	• <f11> , ,</f11>	(pel-complete)	List completion candidates.	
Completion Candidates See Auto-Completion	• M-1		 Force auto-completion of text at point, don't wait for timeout. There must be at least 1 character preceding point. 	
			Requires company-erlang activated by pel-use-company-erlang.	
Completion Menu keys		nenu is shown, you can use candidate (or <down> curse</down>	e the following keys for operating on that menu: or)	
Auto-completion Menu Operations		ous candidate (or <up> curs</up>	sor)	
Company-Mode Menu Operations		olete using 1 candidate (if 1 te 1 char of the current cand	choice), using the prefix part among many candidates, or cycle through all candidates.	
See also: See also:	• <ret> : Selec</ret>		te action for candidate if any (eg. when template selection used)	
	• <f1> : Show</f1>	v candidate help in separate	e buffer. s This is very handy to quickly review documentation of several symbols!	
	• Esc <pgdown> : Scrol</pgdown>	I help buffer forward	e: see the <u>Scrolling</u> table for more info on scrolling)	
	• Esc <pg-up> : Scrol</pg-up>	•		
Set a different root for Erlang project	• C-g : Stop • <f12> M-e • C-c C-e</f12>	(ivy-erlang-complete- set-project-root)	Set root for current project for ivy-erlang-complete. To see the current value of the ivy-erlang-complete-project-root, type \$\forall 12> ?	
Marking			and described in the Marking table.	
See also: <u>Narking</u>	The first 2 command listed be For those 2 commands the second commands the second commands the second command com			
 For those 2 commands the Friang.el man page indicates an invalid mapping for this. Reported as ERL-1314. The useful er/expand-region benefits from PEL enhancement to erlang syntax table supporting the < > pair therefore it is also mentioned he 			······································	
	The useful er/expand-region	on benefits from PEL enhance	cement to erlang syntax table supporting the < > pair therefore it is also mentioned here.	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Mark Erlang function	• C-M-h	(mark-defun &optional	Put mark at end of this function, point at beginning.
	• <f12> f m</f12>	(erlang-mark-function	 The function marked is the one that contains point or follows point. With positive ARG, mark this and that many next functions; with negative ARG, change the direction of marking.
Mark Erlang Clause	• C-c M-h	&optional ARG) (erlang-mark-clause)	If the mark is active, it marks the next or previous function(s) after the one(s) already marked. Put mark at end of clause, point at beginning.
	• <f12> c m</f12>		
Mark region by semantic unit, increase marked region on each	• M-= • <f11> . =</f11>	(er/expand-region ARG)	 Increase selected region by semantic units. Type = to expand the region, - to contract it and 0 to reset the operation.
invocation. ★★	• See <u>x Marking</u> for more in	formation	
Works best with superword-mode on. • See <u>Text Modes</u>	Requires expand-region package, activated by pel-use-expand-region user option.		
Copy and Clone • XX Smartparens			cloning operations. They are provided by Ex Smartparens isplay the copied string when pel-show-copy-cut-text is t. Toggle this display with <f11> M-=</f11>
Copy current & forward block(s)	M- <f7> =</f7>	(sp-copy-sexp &optional ARG)	Copy the following ARG expressions to the kill-ring. This is exactly like calling 'sp-kill-sexp' with second argument t. All the special prefix arguments work the same way.
Copy previous block(s)	M- <f7> M-=</f7>	(sp-backward-copy- sexp &optional ARG)	Copy the previous ARG expressions to the kill-ring. This is exactly like calling 'sp-backward-kill-sexp' with second argument t. All the special prefix arguments work the same way.
clone current block	M- <f7> c</f7>	(sp-clone-sexp)	Clone sexp after or around point. If the form immediately after point is a sexp, clone it below the current one and put the point in front of it.
Transform code	The following commands can	be used to help transform o	Otherwise get the enclosing sexp and clone it below the current enclosing sexp. code. Some need external packages.
iEdit mode			s simultaneously.
See also: <u>I Highlight</u>	Requires the <u>iedit</u> external		
Toggle iedit mode See also: ■ ∑ Cursor	• C-; • <f11> e</f11>	(iedit-mode &optional ARG)	Toggle iEdit mode: edit all symbols in scope or region simultaneously. A Both iEdit and Flyspell use the C-; key as their default binding.
• ∑ Search/Replace	• <f11> h e • <f11> m e</f11></f11>		 PEL detects and reports that situation: modify the binding of one of them if you see it. See <u>Search/Replace</u> where all the iedit-mode commands are described.
Reformat the entire buffer with selected	<f12> R</f12>	(pel-erlang-format- code)	Reformat the Erlang code in the current buffer. • Use the Erlang formatter command specified by the 'pel-erlang-code-formatter-command' user-
Erlang Code Formatter			option. By default this is nil. You can specify a command to use or a specific Erlang code formatter format string with a %s replacement to hold the name of a temporary file. • PEL has built-in support for <u>erlfmt</u> . It must, however, be installed separately and a erlfmt command available on the PATH. Others will be added. • All code inside the current Erlang buffer is reformatted with the specified code formatter, even if the buffer is not committed to a file. After the command you can undo the changes.
			described to the state of the s
Align arrows inside region	C-c C-a	(erlang-align-arrows START END)	 Align arrows ("->") in function clauses inside marked region or in the current function. With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to point), not just those in function clauses.
		Before: sum(L) -> s	After C-c C-a: sum(L, 0). sum(L) -> sum(L, 0).
		sum([H T], Sum) -> s sum([], Sum) -> Sum.	$sum(T, Sum + H);$ $sum([H T], Sum) \rightarrow sum(T, Sum + H);$
		To align something else than clauses, select the	Before: After C-u C-c C-a: check(P, [H T]) -> check(P, [H T]) ->
		code and type: C-u C-c C-a	<pre>case P(H) of true -> 1; true -> 1;</pre>
			false -> 0 false -> 0 end;
Transpose block elements	M- <f7> t</f7>	(sp-transpose-sexp &optional ARG)	Transpose the expressions around point. • The operation will move the point after the transposed block, so the next transpose will "drag" it
<u>IX Smartparens</u> with smartparens- mode active			 With arg positive N, apply that many times, dragging the expression forward. With arg negative -N, apply N times backward, pushing the word before cursor backward. This will therefore not transpose the expressions before and after point, but push the expression before point over the one before it.
es active			Before (for all following examples): AList = [1, 2, 3, [10,11,12, [22,33,44]], 5, 6, 7, 8, []].
			After M- <f7> t: AList = [1, 2, [10,11,12,[22,33,44]], 3 , 5, 6, 7, 8,[]]. After M-2 M-<f7> t: AList = [1, 2, [10,11,12,[22,33,44]], 5, 3 , 6, 7, 8,[]].</f7></f7>
			Before (for all following examples): AList = [{first,[1, 2, 3]} , [10,11,12,[22,33,44]], 5, 6, 7, 8,[]].
			After M- <f7> t: AList = [[10,11,12,[22,33,44]], {first,[1, 2, 3]} , 5, 6, 7, 8,[]]. After M-2 M-<f7> t: AList = [[10,11,12,[22,33,44]], 5, {first,[1, 2, 3]} , 6, 7, 8,[]].</f7></f7>
			Before (for all following examples): AList = [{first,[1, 2, 3]} , [10,11,12,[22,33,44]], 5, 6, 7, 8,[]]. After M M- <f7> t:</f7>
Push current block after	M_<57> 0	(en-nuch-hybrid cove)	AList = [{first,[1, 3], 2]}, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]]. Push the hybrid sexp after point over the following one.
next • XX Smartparens	M- <f7> s</f7>	(sp-push-hybrid-sexp)	Before: After M- <f7> s:</f7>
with smartparens- mode active			AList = [1, 2, 3,
			1

<u>Description</u>	Keystroke	Function		Note
Transform - barf	The following commands extra			114.0
Eject next element(s) out of current block • <u>EX Smartparens</u> with smartparens- mode active		(sp-forward-barf-sexp &optional ARG)	Remove the last sexp in the current list by movin If ARG is positive number N, barf that many ex If ARG is negative number -N, contract the op If ARG is raw prefix C-u, barf all expressions for place the point before the closing delimiter of If the current list is empty, do nothing.	pressions. ening pair instead. om the one after point to the end of current list and
<u>a.c.</u>	♠ native sp problem	smartparens by itself fails to process these examples properly.	Before: AList = [[1, 2, 3, 4]]. Before: AList = [[1, 2, 3, 4]].	After M- <f7> /: AList = [[1, 2, 3], 4]. After M-2 M-<f7> /: AList = [[1, 2], 3, 4].</f7></f7>
		PEL fixes the issues with post processing.	Before: AList = [[1, 2, 3, 4]].	After M M- <f7> /: AList = [1, [2, 3, 4]].</f7>
Eject previous element(s) out of current block	M- <f7> M-/</f7>	(sp-backward-barf-sexp & optional ARG)		ing pair, the opening pair is contracted. For more
<u>xx Smartparens</u> with smartparens- mode active		This command works fine in Erlang for the following code examples:	<pre>Before: AList = [[1, 2, 3, 4]]. Before:</pre>	After M- <f7> M-/: AList = [1, [2, 3, 4]].</f7>
36			AList = [[1, 2, 3, 4]].	After M-3 M- <f7> /: AList = [1, 2, 3, [4]].</f7>
Transform - slurp	The following commands perfo	orm slurping operations, how	wever support for Erlang could be improved as the	e commands do not always work properly.
Enclose next outside element into current block • <u>EX Smartparens</u>	M- <f7> ></f7>	(sp-forward-slurp-sexp &optional ARG)	can extend a list or end of file). If ARG is N, apply this function that many time If ARG is negative -N, extend the opening pair If ARG is raw prefix C-u, extend all the way to	and that list and possibly apply recursively until we s. instead (that is, backward). the end of the parent list. ion to be slurped are strings, they are joined together Erlang as shown in the first example.
	. sp problem 🔽	smartparens by itself fails to process these examples properly.	Before: Names = []Joe. Before:	After M- <f7> >: Names = [Joe]. After M-<f7> >:</f7></f7>
		PEL fixes the behaviour by using ability to post- process code to ensure correct syntax.	AList = [[1, 2, 3], 4, 5]. Before: AList = [1, 2, 3,	AList = [[1, 2, 3, 4], 5]. After M M- <f7> >: AList = [1, 2, [3,</f7>
Enclose previous outside element(s) into next block • £x Smartparens with smartparens-mode active	M- <f7> <</f7>	(sp-backward-slurp- sexp &optional ARG)	Add the sexp preceding the current list in it by moving the opening delimiter. If the current list is the first in a parent list, extend that list (and possibly apply recursively until we can extend a list or beginning of file). If arg is N, apply this function that many times. If arg is negative -N, extend the closing pair instead (that is, forward). If ARG is raw prefix C-u, extend all the way to the beginning of the parent list. If both the current expression and the expression to be slurped are strings, they are joined together.	
		The position of point inside the list does not matter. The point does not move. Before: AList = [-2, -1, 0,	<pre>Before: AList = [0, 1, [2, 3], 4], 5]. Before: AList = [0, 1, [2, 3], 4], 5]. After C-u M-< 1, [2, 3, 4], 5]. AList = [[-2, 4], 5].</pre>	After M- <f7> <: AList = [0, [1, 2, 3, 4], 5]. After M-2 M-<f7> <: AList = [[0, 1, 2, 3], 4], 5]. f7> <: -1, 0, 1, 2, 3, 4], 5].</f7></f7>
Enclose next element(s) into previous block • <u>Ex Smartparens</u> with smartparens- mode active	M-<£7> }	(pel-sp-add-to- previous-sexp &optional ARG)	Add the expression around point to the first list preceding point. With ARG positive N add that many expressions to the preceding list. If ARG is raw prefix argument C-u add all expressions until the end of enclosing list to the prelist. If ARG is raw prefix argument C-u C-u add the current list into the previous	
e a a g		smartparens by itself fails to process these examples properly.	Before: AList = [0, 1, [2, 3], 4, 5]. Before:	After M- <f7> }: AList = [0, 1, [2, 3, 4], 5]. After M-2 M-<f7> }:</f7></f7>
		PEL fixes the issues with post processing and wrapping function.	AList = [0, 1, [2, 3], 4, 5].	AList = [0, 1, [2, 3, 4, 5]].
Enclose previous outside element(s) into next block • <u>EX Smartparens</u> with smartparens-	M-<£7> {	(sp-add-to-next-sexp &optional ARG)	 Add the expressions around point to the first list following point. With ARG positive N add that many expressions to the following list. If ARG is raw prefix argument C-u add all expressions until the beginning of enclosing list to the following list. If ARG is raw prefix argument C-u C-u add the current list into the following list. 	
mode active		This command works fine in Erlang for the following code examples:	AList = [1, 2, [3, 4]].	After M- <f7> {: AList = [1, [2, 3, 4]].</f7>
			Before: AList = [1, 2, [3, 4]]. Before:	After C - u M - < f7 > {: AList = [[1, 2, 3, 4]].
			AList = [[1, 2], [3, 4]].	After C-u C-u M- <f7> {: AList = [[[1, 2], 3, 4]].</f7>
Re-wrap block	Use the following commands t	J 11 0	racter pair surrounding a block	
Re-wrap current block • <u>EX Smartparens</u> with smartparens-	M- <f7> r</f7>	(sp-rewrap-sexp PAIR &optional KEEP-OLD) This command works fine	Re-wrap current block using another block chara • With C-u , keep old delimiter and wrap with Pa Before:	
mode active		in Erlang for the following code examples:	AList = [[1, 2, 3, 4]]. Before:	AList = [{1, 2, 3, 4}] After C-u M- <f7> r {:</f7>
			AList = [[1, 2, 3, 4]].	AList = [{[1, 2, 3, 4]}]
Swap current block and parent block wrapping characters	M- <f7> w</f7>	(sp-swap-enclosing- sexp &optional ARG)	Swap the enclosing delimiters of this and the part With N > 0 numeric argument, ascend that ma	ny levels before swapping.
<u>XX Smartparens</u> with smartparens- mode active		This command works fine in Erlang for the following code examples:	<pre>Before: AList = ({[1, 2, 3, 4]}). Before:</pre>	After M -< £7> w: AList = ([{1, 2, 3, 4}]).

Before:
AList = ({[1, |2, 3, 4]}).

After M-<f7> w: AList = [{(1, |2, 3, 4)}].

```
Function
       Description
                                     Keystroke
                                                                                                                                      Note
Un-wrap block
Extract all elements
                            M-<f7> U
                                                           (sp-unwrap-sexp
                                                                                     Un-wrap current or next block.
from current/next block
                                                           &optional ARG)

    With ARG N. unwrap Nth expression as returned by 'sp-forward-sexp'

    If ARG is negative -N, unwrap Nth expression backwards as returned by 'sp-backward-sexp'

    ∑X Smartparens

                                                                                      Before:
                                                                                                                                       After M-<f7> U:
     with smartparens-
                                                                                      AList = (\{[1, 2, 3, 4]\}).
                                                                                                                                       AList = [\{1, 2, 3, 4\}].
                                                                                     Before:
AList = ({[1, |2, 3, 4]}).
                                                                                                                                       After M-<f7> U:
                                                                                                                                        AList = (\{1, |2, 3, 4\}).
                                                                                                                    After M-<f7> U:
                                                           Before:
                                                           AList = [1, 2, 3, 4], 5, [6, 7], 8].
                                                                                                                      AList = [1, 2, 3, 4, 5, [6, 7], 8].
                                                           Before:
                                                                                                                    After M-2 M-<f7> U:
                                                           AList = [1, 2, [3, 4], 5, [6, 7], 8].
                                                                                                                      AList = [1, 2, 3, 4], 5, 6, 7, 8].
Extract all elements
                            M-<f7> W
                                                           (sp-backward-unwrap-
                                                                                     Unwrap the previous block/expression.
                                                           sexp &optional ARG)
                                                                                       With ARG N, unwrap Nth expression as returned by 'sp-backward-sexp'.

    If ARG is negative -N, unwrap Nth expression forward as returned by 'sp-forward-sexp'.

                                                                                     Before:
AList = ({[1, |2, 3, 4]}).
                                                                                                                                       After M-<f7> W
     with smartparens-
                                                                                                                                        AList = (\{1, | 2, 3, 4\}).
     mode active
    00
                                                                                                                                       Again After M-<f7> W:
                                                                                                                                        AList = (1, |2, 3, 4).
                                                                                                                                       Again After M-<f7> W:
                                                                                                                                        AList = 1, |2, 3, 4.
                                                                                     Before:
AList = [0, 1, [2, |3, 4], 5].
                                                                                                                                       After M-<f7> W:
                                                                                                                                       List = [0, 1, 2, 3, 4, 5].
                                                                                                                     After M-<f7> W:
                                                           Before:
                                                           AList = [1, 2, [3, 4], 5, [6, 7], [8].
                                                                                                                      AList = [1, 2, [3, 4], 5, 6, 7, 8].
                                                                                                                     After M-2 M-<f7> W:
                                                           Before:
                                                           AList = [1, 2, [3, 4], 5, [6, 7], 8].
                                                                                                                      AList = [1, 2, 3, 4, 5, [6, 7], 8].
Split & Join
Split block
                                                           (sp-split-sexp ARG)
                                                                                     Split the list or string the point is on into two.
                            M-<f7> |
     ∑X Smartparens
                                                                                        If ARG is a raw prefix C-u split all the sexps in current expression in separate lists enclosed with
     with smartparens-
                                                                                        delimiters of the current expression.
     mode active
                            smartparens by itself fails
                                                          Before:
                                                                                                                    After M-<f7> |:
    00
                                                           AList = [1, 2, [3, 4, 5, 6, 7], 8].
                                                                                                                     AList = [1, 2, [3, 4], | [5, 6, 7], 8].
                            to process the first of these
                            examples properly.
                                                          Before:
Name = "Joe | Armstrong".
                                                                                                                    After M-<f7> |:
Name = "Joe " | "Armstrong".
                            PEL fixes the issues with
                            post processing.
                                                           Before:
                                                                                                                    After C-u M-<f7> |:
                                                           AList = [1, 2, [3, 4, |5, 6, 7], 8].
                                                                                                                    AList = [1, 2, [3], [4], [5], [6], [7], 8].
                                                                                     Join the blocks before and after point if they are of the same type.
Join blocks
                                                           (sp-join-sexp &optional
      X Smartparens

    If ARG is positive N, join N expressions after the point with the one before the point.

                                                                                      • If ARG is negative -N, join N expressions before the point with the one after the point.
     with smartparens-
                                                                                      • If ARG is a raw prefix C-u join all the terms up until the end of current expression.
                                                                                      • The joining stops at the first expression of different type.
    60
                                                                                                                    After M-<f7> J:
                                                           Before:
                                                           AList = [0, 1, [2, 3, 4]], [5, 6], 7].
                                                                                                                       List = [0, 1, [2, 3, 4], 5, 6], 7].
                                                           AList = [[0, 1]], [2, 3, 4], [5, 6], [7].
                                                                                                                      AList = [[0, 1], 2, 3, 4, 5, 6], 7].
                            In Erlang mode, the superword mode can be useful since snake case is often used. Using superword-mode helps searching.
Search Support
                            • PEL activates the superword mode by default in Erlang mode. To change this use the <f11> t <f2> to access the customize buffer.
Toggle superword-mode

• <u>\tilde{\tilde{\tilde{L}}} Text Modes</u>
                            <f12> M-p
                                                                                      Toggle superword-mode: a minor mode that treats snake case as one word.
                                                           (superword-mode

In Erlang, '_' are then treated as part of words.
With prefix argument ARG, enable superword mode if ARG is positive, disable it otherwise.

                            • <f11> t m p

    ∑ Search/Replace

                            • <f11> SPC e M-p
                            The following commands can be used to activate or toggle useful modes to highlight blocks of (), {}, and [].
Highlighting blocks
                             show-paren-mode, which highlights the parens that matches the one before or after point
                            • rainbow delimiters mode, where matching nested parens are highlighted with the same colour
                                                                                      Toggle visualization of matching parens (Show Paren mode).

• With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.
Toggle show-paren
                              <f12> M-9
                                                           (show-paren-mode
mode on/off
                            • M-<f12> M-9
                                                           &optional ARG)

    Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.

                            • <f11> h (
See also: E Highlight
                            • <f11> SPC e M-9
                              <f12> M-r
                                                           (rainbow-delimiters-
                                                                                      Highlight nested parentheses, brackets, and braces with colours according to their depth.
Toggle colouring of
nested blocks
                            • M-<f12> M-r
                                                           mode &optional ARG)

    Customize the depth and colours with M-x customize-group rainbow-delimiters

See also: E Highlight
                                                                                      Requires: rainbow-delimiters.el 🛂 activated by pel-use-rainbow-delimiters.
                            • <f11> h R
Edit Erlang Code
                            The following commands help edit Erlang code.
Create additional clause
                                                                                     Create additional Erlang clause header.
                                                           (erlang-generate-new-
                            C-c C-i

    Parses the source file for the name of the current Erlang function. Create the header containing the
name, a pair of parentheses, and an arrow. The space between the function name and the first

                                                           clause)
                                                                                        parenthesis is preserved. The point is placed between the parentheses.
                                                           (erlang-clone-
                                                                                      Insert, at the point, the argument list of the previous clause.
Clone clause arguments
                                                                                       Copy the function arguments of the preceding Erlang clause. This command is useful when defining
                                                           arguments)
                                                                                        a new clause with almost the same argument as the preceding.
The mark is set at the beginning of the inserted text, the point at the end.
```

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>		
Insert Erlang Code with Specialized Tempo Skeletons	PEL provides the following aQuick access keys to inse	additional functionality: ert the templates, all mappe	tons, available on the Erlang/Skeletons menu (via <f10>) d under the pel:erlang-skel key prefix: <f12> <f12>.</f12></f12></f10>		
Erlang Style	• Several aspects of the	e PEL Erlang Source Code S	h a +. These are also added to the menu. Style is controlled by the user options inside the pel-erlang-code-style group. The controlled template		
Control •	affected are marked with a C. The relevant user options are part of the pel-erlang-code-style group accessible with <f12> <f2> from an erlang mode buffer and include the following options: • pel-erlang-skel-insert-file-timestamp: set whether an automatically updated timestamp is inserted in the file header block.</f2></f12>				
See also:	pel-erlang-skel-prompel-erlang-skel-prom	pt-for-function-name	: set whether file and function skeletons blocks prompt for purpose and insert it. : set whether function skeletons prompt for function name and then inserts that name.		
Erlang-specific Templates	pel-erlang-skel-prompel-erlang-use-separ		s : set whether function skeletons prompt for function arguments and then insert them. : set whether blocks use horizontal separator lines (these are the first of potentially 2 separators).		
• <u>∑ Inserting Text</u> for	pel-erlang-use-seconpel-erlang-skel-with-		: set whether blocks use a second block horizontal separator line. : set whether generated code comments use EDoc markup.		
more info and information about	• pel-erlang-skel-with-		: set whether file header blocks use open source software license text controlled by dice.		
tempo skeleton and the completely different			But by using file and directory variables (see <u>File/Directory Variables</u>) they can also be used to tak So by default, the user options that control the PEL tempo template take effect globally. If you want t		
yasnippet template- based text insertion			option control block at the end of that file. If you want to control the behaviour of the PEL tempo lir-locals file and store the values of the relevant options variables inside that file. This allows you to		
+ : additional templates	control the user options af	fecting the format of the ten	npo templates precisely and does not affect what you actually type. ng the pel-tempo-mode) you can move to the next or previous point of interest (so called <i>tempo-mark</i> s		
C: templates with customization control	with the standard tempo-	mode keys C-c M-f and C	C-c M-b or some other keys like C-c . and C-c ,. an also type the template name and then hit C-c C-M-i or <f12> <f12> <f12>. This support</f12></f12></f12>		
\$	listing all completions into	a separate temporary buffe	er. This is mainly useful for templates which short names such as "if", "case", etc		
Customize PEL Erlang	Some of the template name <f12> <f12> <f2></f2></f12></f12>	es in the title column are als	co links to the relevant Erlang language construct reference page. Customize PEL Erlang skeleton layout.		
Skeletons layout	<f12> <f12> <f2></f2></f12></f12>	&optional OTHER- WINDOW)	If OTHER-WINDOW is non-nil (use C-u), display in another window.		
if	<f12> <f12> i</f12></f12>	(pel-erl-if)	Insert an if statement.		
case	<f12> <f12> c</f12></f12>	(pel-erl-case)	Insert a case expression.		
export +	<f12> <f12> x</f12></f12>	(pel-erl-export	Insert an export module attribute expression.		
import +	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.		
try +	<f12> <f12> t</f12></f12>	(pel-erl-try)	Insert a try expression.		
try-of +	<f12> <f12> T</f12></f12>	(pel-erl-try-of)	Insert a try expression with of clauses.		
receive	<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.		
after .	<f12> <f12> a</f12></f12>	(pel-erl-after)	Insert a receive expression with an after (timeout) clause.		
loop	<pre><f12> <f12> 1</f12></f12></pre>		·		
module function	<f12> <f12> m (pel-erl-module) Insert the module attribute. (color of the period of the pe</f12></f12>				
function C	<f12> <f12> f</f12></f12>	(pel-erl-function)	Insert a function definition. This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.		
author	<f12> <f12> `</f12></f12>	(pel-erl-author)	Insert the author attribute. Uses the user-mail-address user option to insert your mail address.		
spec	<f12> <f12> s</f12></f12>	(pel-erl-spec)	Insert a -spec for the function following point.		
small-header C normal-header C	<f12> <f12> M-h <f12> <f12> M-H</f12></f12></f12></f12>	(pel-erl-small-header) (pel-erl-normal-header)	Insert a small file header without any comment. Insert a normal file header: includes author name, copyright notice, doc section, file created date		
large-header C	<f12> <f12> h</f12></f12>	(pel-erl-large-header)	Insert a large header block that includes all normal header fields plus separators.		
			User-options control the format. Distinguish Erlang erl module files from the .hrl header files.		
small-server C application C	<f12> <f12> M-s <f12> <f12> M-a</f12></f12></f12></f12>	(pel-erl-small-server) (pel-erl-application)	Insert a large file header and template logic for a small server. Insert a large file header and template logic for an application behaviour.		
	<f12> <f12> M-a <f12> <f12> M-u</f12></f12></f12></f12>	(pel-erl-supervisor)	Insert a large file header and template logic for an application behaviour.		
supervisor-bridge C	<f12> <f12> M-u </f12> M-b</f12>	(pel-erl-supervisor- bridge)	Insert a large file header and template logic for a <u>supervisor bridge behaviour</u> .		
generic-server C	<f12> <f12> M-g</f12></f12>	(pel-erl-generic-server)	Insert a large file header and template logic for a gen-server behaviour.		
gen-event C	<f12> <f12> M-e</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a gen-event behaviour.		
gen-fsm C	<f12> <f12> M-f</f12></f12>	(pel-erl-gen-fsm)	Insert a large file header and template logic for a gen-fsm behaviour.		
gen-statem-StateName C	<f12> <f12> M-S</f12></f12>	(pel-erl-gen-statem- StateName)	Insert a large file header and template logic for a gen-statem behaviour.		
gen-statem-handle- event C	<f12> <f12> M-E</f12></f12>	(pel-erl-gen-statem- handle-event)	Insert a large file header and template logic for a gen-statem.		
wx-object C	<f12> <f12> M-w</f12></f12>	(pel-erl-wx-object)	Insert a large file header and template logic for a wx-object generic server.		
gen-lib C	<f12> <f12> M-1</f12></f12>	(pel-erl-gen-lib)	Insert a large file header and template logic for a library module.		
gen-corba-cb C	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a CORBA callback module.		
ct-test-suite-s	<f12> <f12> M-1</f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite		
ct-test-suite-l	<f12> <f12> M-2</f12></f12>	(pel-erl-ct-test-suite-l)	Insert a large file header and template logic for a test suite		
ts-test-suite Tempo Template Tag	<f12> <f12> M-3 • C-c C-M-i</f12></f12>	(pel-erl-ts-test-suite) (tempo-complete-tag	Insert a large file header and template logic for a test suite		
Insertion	• <f12> <f12> <f12></f12></f12></f12>	&optional SILENT)	Look for a tag and expand it. Instead of using the <f12> <f12> key bindings above, type the template name and then hit C-c C-M-i. (or <f12> <f12> <f12>).</f12></f12></f12></f12></f12>		
	template name and then hit C-c C-M-i. (or <f12> <f12> <f12>). A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template. • All the tags in the tag lists in 'tempo-local-tags' (including 'tempo-tags') are searched for a match for the text before the point. The string matching is determined by the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all. • If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal. • If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed.</f12></f12></f12>				
Toggle pel-tempo-mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as C-c		
See also:	• <f11> SPC e <f12> SPC • <f6> SPC</f6></f12></f11>	&optional ARG)	C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode.		
	CION SPC		When a skeleton is inserted via the execution of one of the pel-erl commands above, the pel-tempo-mode is automatically activated.		

<u>Description</u>	<u>Keystroke</u>	Function	Note		
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward- mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key binding are only available when pel-tempo-mode is active.		
Specialized Kill See also: • ∑ Cut & Paste • ∑ Smartparens	Specialized delete and kill commands are provided by the ↑ The <u>smartparens</u> external package 2 activated by <u>pel-use-smartparens</u> user-option. Activate smartparens mode manually with <f11> (or automatically by adding smartparens-mode to <u>pel-erlang-activates-minor-mode</u>. This table uses the ১ and ১ symbols to represent these 2 keys: : "forward delete" := <deletechar> := Fn</deletechar></f11>				
• Delete char Standard delete forward character	When <u>smartparens</u> is used, the delete keys protect deletion of balanced pairs but allow deletion of marked areas regardless of the block pairs. • <deletechar> • (delete-forward-char N & optional KILLFLAG) Delete the following N characters (previous if N is negative). • If Transient Mark mode is enabled, the mark is active, and N is 1, delete the text in the region</deletechar>				
			deactivate the mark instead. Interactively, N is the prefix arg, and KILLFLAG is set if N was explicitly specified. parting' before it is saved in the kill ring, so the actual saved text might differ from the killed text.		
Delete forward, jump over block pair until block is empty then	• <deletechar></deletechar>	(pel-sp-delete-char &optional <u>ARG</u>)	Same as above with the <u>additional behaviour</u> listed below. Execute 'sp-delete-char' if no area marked, otherwise delete marked area.		
• <u>SX Smartparens</u> with smartparens mode active	of delete-selection-mode If nothing is marked: If on an opening delimite If on a closing delimiter, r If the delimiter does not f With a numeric prefix arg	e. r, move forward into balance refuse to delete unless the b form a balanced expression, lument N = 0, simply delete	alanced expression is empty, in which case delete the entire expression.		
Standard delete backward character	• DEL	(backward-delete-char- untabify ARG &optional KILLP)	Delete characters backward, changing tabs into spaces. Delete ARG chars, and kill (save in kill ring) if KILLP is non-nil. Interactively, ARG is the prefix arg (default 1) and KILLP is t if a prefix arg was specified. The exact behavior depends on 'backward-delete-char-untabify-method'.		
Delete character - backward, jump over block pair until block is empty then delete block	• DEL • ©	(pel-sp-backward- delete-char &optional ARG)	Same as above with the <u>additional behaviour</u> : • If an area is marked deletes the area, regardless of the presence of blocks, even if the resulting text would lead to unbalanced pairs. It also ignores the prefix argument.		
<u>IX Smartparens</u> with smartparens- mode active	 When nothing is marked: Deletes character before cursor (deletes backward), replaces hard tab with spaces as required. Does not delete only one side of a balanced pair block; instead move into the block and delete its content until it is empty. When the block is empty. 				
Delete char Does not delete marked areas with balanced pairs.	The forward and backward Note that these will not	delete keys do the same whaccept to delete or kill a reg	s that delete forward and backward without breaking blocks. een smartparens-mode is active. ion that contains balanced pairs even if the region contains the two sides! I and backwards keys commands that use smart-parens delete as long as the area is not marked.		
Delete char forward	M- <f7> DEL n</f7>	(sp-delete-char &optional ARG)	Delete a character forward or move forward over a delimiter. If on an opening delimiter, move forward into balanced expression.		
	 If on a closing delimiter, refuse to delete unless the balanced expression is empty, in which case delete the entire expression. If the delimiter does not form a balanced expression, it will be deleted normally. With a numeric prefix argument N > 0, delete N characters forward. With a numeric prefix argument N < 0, delete N characters backward. With a numeric prefix argument N = 0, simply delete a character forward, without regard for delimiter balancing. If ARG is raw prefix argument C-u, delete characters forward until a closing delimiter whose deletion would break the proper pairing is hit. \[\begin{align*} (quu \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \				
Delete char backward	M- <f7> DEL p</f7>	(sp-backward-delete- char &optional ARG)	Delete a character backward or move backward over a delimiter. • It has the same description as the above command but goes backward instead of forward. ("zot" q uux) -> ("zot" uux) ("zot" quux) -> ("zot " quux) -> ("zo " quux) (foo () bar) -> (foo bar) (foo bar) -> (foo bar)		
Delete/Kill region	These may be useful inside	keyboard macros when dele	is the deletion would not create unbalanced blocks. eting text in area where several balanced and nested blocks are present. ion that contains balanced pairs even if the region contains the two sides!		
Delete region	M- <f7> DEL -</f7>	(sp-delete-region BEG END)	Delete the text between point and mark, like 'delete-region'. • BEG and END are the bounds of region to be deleted. • If that text is unbalanced, signal an error instead. • With a prefix argument, skip the balance check.		
Kill region	M- <f7></f7>	(sp-kill-region BEG END)	Kill the text between point and mark, like 'kill-region'. • BEG and END are the bounds of region to be killed. • If that text is unbalanced, signal an error instead. • With a prefix argument, skip the balance check.		
kill block elements	The following commands kill the	he element(s) of a block.			
Kill content of next block	• M- <f7> © • M-<f7> - n</f7></f7>	(sp-change-inner)	Change the content of current or next block. Point can be anywhere in block or element before block. Before: {'EXIT',Reason} -> { error,{asn1,Reason}}; {error,{ }};		
Delete content of current block	M- <f7></f7>	(sp-change-enclosing)	Delete content of the enclosing block. Point can be anywhere inside the current block. Before: {'EXIT',Reason} -> {error,{ asn1,Reason}}; {error,{ }};		
Kill block elements forward	M- <f7> -]</f7>	(sp-kill-sexp &optional ARG DONT-KILL)	<pre>Kill block elements after point. Before: case Tlv9 of [] -> true;> exit({error, {asn1, {unexpected, Tlv9}}}) After: case Tlv9 of</pre>		
		, , , , , , , , , , , , , , , , , , , ,	[] -> true;> exit({error, })		

(sp-backward-kill-sexp Kill block elements before point.

Kill block elements

M-<f7> - [

```
Keystroke
       Description
                                                                                               Before:
backward
                                                                  &optional ARG DONT
                                                                  KILL)
                     *
                                                                                                case Tlv9 of
[] -> true;_ -> exit({error,|{asn1, {unexpected, Tlv9}}})

    ∑X Smartparens

                                                                                                After:
                                                                                                case Tlv9 of
   [[] -> true;_ -> exit({|{asn1, {unexpected, Tlv9}}})
                                                                                                Kill a line as if with 'kill-line', but respecting delimiters.
Kill element after current
                               M-<f7> - }
                                                                  (sp-kill-hybrid-sexp
                     *
                                                                 \bullet \ \ \text{With ARG being raw prefix } \textbf{C-u} \ \ \textbf{C-u}, \text{ kill the hybrid sexp the point is in (see 'sp-get-hybrid-sexp')}.

    <u>∑X Smartparens</u>

With ARG numeric prefix 0 (zero) just call 'kill-line'.
You can customize the behaviour of this command by toggling 'sp-hybrid-kill-excessive-whitespace'.

                                                                  (sp-kill-whole-line)
                               M-<f7> - 1
Kill whole line
                     *
                                                                                                🔔 Currently this deletes the whole line. Requires Erlang specific implementation. 🚧

    Kill/splice

Un-wrap current block,
                               M-<f7> 1 1
                                                                  (sp-splice-sexp
                                                                                                Un-wrap current block, splicing its content in enclosing block (if any).
splicing its elements in enclosing block
                                                                  &optional ARG)
                                                                                                Before:
                                                                                                Before:
{|EncBytes,EncLen} = 'enc'(Cdx, []), |EncBytes,EncLen = 'enc'(Cdx, []),
                                                                                                Before:
                                                                                                 lefore:
-asn1_info(
[{vsn, '2.0.1'},
    {module, 'ELDAPv3'},
    {options, [{i, "src"}, {|outdir, "src"}, noobj, {i, "."}, {i, "asn1"}]}]).
                                                                                                   sn1_info(
                                                                                                   [{vsn.
                                                                                               Kill elen...

Before:

Se Tlv9 C
                                                                                                Kill elements before point in block and splice remaining elements into outer block.
Kill block element(s)
                                                                  (sp-splice-sexp-killing-
                               M-<f7> 1 [
before point and splice
                                                                  backward &optional
                                                                  ARG)
remaining into outer
                                                                                                 case Tlv9 or
[] -> true; -> exit({error,{asn1, {unexpected, |Tlv9}}})
block
                                                                                               After:
case Tlv9 of
[] -> true; -> exit({error,{asn1, |Tlv9}})

    <u>∑X Smartparens</u>

                                                                  (sp-splice-sexp-killing-
Kill block element(s)
                               M-<f7> 1 ]
                                                                                                Kill elements after point in block and splice remaining elements into outer block.
                                                                                                Before:
case Tlv9 of
  [] -> true; -> exit({error,{asn1, {unexpected, |Tlv9}}})
forward and splic
                                                                  forward &optional ARG)
remaining into outer
                                                                                               After:

case Tlv9 of

[] -> true; -> exit({error,{asn1, unexpected|}})

        \[
        \mathbb{X} \text{Smartparens}
    \]

Kill around element
                               M - < f7 > 1 o
                                                                  (sp-splice-sexp-killing-
                                                                  around &optional ARG)
                                                                                                Before:

    ∑X Smartparens

                                                                                                  asn1 info(
                                                                                                   {vsn, '2.0.1'},
{module,'ELDAPv3'},
{options,|{outdir,"src"},}]).
                                                                                                  [{vsn.
                                These commands complements the standard word kill commands normally available with shorter key bindings. See \mathbb E Cut & Paste

    Delete/Kill word

Delete word backward
                                                                                                (sp-backward-delete-word &optional ARG)
                               M-<f7> DEL v
                                                                  (sp-backward-delete-
                                                                                                  Delete a word backward, skipping over intervening delimiters.
Deleted word does not go to the clipboard or kill ring.
                                                                  word &optional ARG)
                                                                                                  With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in backward direction.
                                                                                                Delete a word forward, skipping over intervening delimiters.
Delete word forward
                                                                  (sp-delete-word
                               M-<f7> DEL w

Deleted word does not go to the clipboard or kill ring.
With ARG being positive number N, repeat that many times.

                                                                  &optional ARG)
                                                                                                • With ARG being Negative number -N, repeat that many times in backward direction.
                                                                                               Kill a word backward, skipping over intervening delimiters.

• With ARG being positive number N, repeat that many times.
Kill word backward
                                                                  (sp-backward-kill-word
                               M-<f7> - v
                                                                  &optional ARG)
                                                                                                • With ARG being Negative number -N, repeat that many times in backward direction.
                                                                                               Kill a word forward, skipping over intervening delimiters.

• With ARG being positive number N, repeat that many times.
                                                                  (sp-kill-word &optional
Kill word forward
                               M-<f7> - w
                                                                  ARG)
                                                                                                • With ARG being Negative number -N, repeat that many times in backward direction.
                               See 'sp-backward-symbol' and 'sp-forward-symbol' for what constitutes a symbol for the backward and forward commands respectively.

    Delete/Kill

                                 These commands complements the standard word delete commands normally available with shorter key bindings. See <u>Set & Paste</u>
   symbol
Delete symbol backward
                                                                  (sp-backward-delete-
                                                                                                Delete a symbol backward, skipping over any intervening delimiters.
                               M-<f7> DEL a
                                                                  symbol &optional ARG
WORD)
                                                                                                  Deleted symbol does not go to the clipboard or kill ring.
With ARG being positive number N, repeat that many times
                                                                                                  With ARG being Negative number -N, repeat that many times in forward direction.
                                                                  (sp-delete-symbol
&optional ARG WORD)
                                                                                               Delete a symbol forward, skipping over any intervening delimiters.

• Deleted symbol does not go to the clipboard or kill ring.
Delete symbol forward
                               M-<f7> DEL s

With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in backward direction.

                                                                  (sp-backward-kill-
                                                                                                Kill a symbol backward, skipping over any intervening delimiters.
Kill symbol backward
                               M-<f7> - a

With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in forward direction.

                                                                  symbol &optional ARG
                                                                  (sp-kill-symbol &optional
Kill symbol forward
                                                                                               Kill a symbol forward, skipping over any intervening delimiters.
                               M-<f7> - s
                                                                                                  With ARG being positive number N, repeat that many times.
With ARG being Negative number -N, repeat that many times in backward direction.
                                                                  ARG WORD)
```

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Erlang syntax checking	To activate either set the	pel-use-erlang-syntax-che	e can be done with Emacs built-in <u>flymake</u> as well as with the flycheck external package. eck user option is set to either 'use-flycheck or 'use-flymake. unched. If you want to start your selected syntax checker as soon as any Erlang file is opened, add
Using either: • flycheck or • flymake	 'erlang-mode to the pel-modes-activating-syntax-check user-option. • flymake is built-in Emacs. The Emacs erlang package provides erlang-flymake to use with Erlang. • PEL automatically installs and activates flycheck when pel-use-erlang-syntax-check user option is set to 'use-flycheck. ♣ Flymake has several customizable variables, which some listed here: The following customization variables determine the exact circumstances whereupon Flymake decides to initiate a check of the buffer: 		
See also: See SyntaxCheck	 flymake-start-on-flymake-mode: t to start checking when flymake-mode is started. nil to prevent check. flymake-no-changes-timeout: time to wait after last change to start checking. Default = 0.5 seconds. flymake-start-syntax-check-on-newline: t to check after insertion or removal of newline char from buffer. nil to prevent check. 		
	The following variable control navigation to next or previous error: • flymake-wrap-around: If non-nil, moving to errors wraps around buffer boundaries. • flymake-diagnostic-types-alist: Alist ((KEY . PROPS)*) of properties of Flymake diagnostic types. See Emacs documentation for more info. The M-n and M-p keys are mapped to flymake commands only when flymake-mode is turned on.		
Activate/deactivate selected syntax checker	<f11> ! !</f11>	(pel-erlang-toggle- syntax-checker)	 Toggle the selected Erlang syntax checker mode on/off. The syntax checker activated or deactivated is either <u>flycheck</u> or <u>flymake</u>, as selected by the user-option variable `pel-use-erlang-syntax-check'. See the required settings above to activate this command and select the syntax checker.
Go to next flymake diagnostic	M-n	(flymake-goto-next- error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic. • With a prefix arg, skip any diagnostics with a severity less than ':warning'. • Display the error message in the echo line.
Go to previous flymake diagnostic	М-р	(flymake-goto-prev- error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic. • With a prefix arg, skip any diagnostics with a severity less than ':warning'. • Display the error message in the echo line.
Compiling Erlang Code		compile the files. The buffe	ce code files to .beam files located in the same directory as the source code. Detected errors are listed er shows the location of error and the error description. The following commands are used to navigate
Compile code	• C-c C-k • <f12> M-c • M-<f12> M-c</f12></f12>	(erlang-compile)	Compile Erlang module in current buffer. If buffer visiting file was modified and not saved, prompts the user to save it first. Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command. The buffer lists the errors. Hitting RET on the error file/line move point to that line in the Erlang file buffer. The RET key is bound to (compile-goto-error &optional EVENT) It's also possible to use the next-error and previous error.
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output. • Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.
Move to next compile error	• C-x ` • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; • negative means move back to previous error messages. • Just C-u as a prefix means reparse the error message buffer and start at the first error. ↑ This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to previous compile error	• M-g p • M-g M-p	(previous-error &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative). 1 This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error. When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Move to previous compilation or Flycheck detected error	С-с С-р	(edts-code-previous- issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error. When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Development Tool	The following commands are used when adding Emacs Lisp support for Erlang.		
Show syntactic information	C-c C-s	(erlang-show-syntactic-information)	Show syntactic information for current line. • Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.
Erlang Shell	Commands to explicitly launch library running in erlang-shell-		that runs under an Emacs inferior-erlang process controlled by the <u>comint mode</u> from the <u>comint.el</u>
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.
Start new Erlang Shell	<f11> z r e <f12> z</f12></f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer. • The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started. • C-c C-z starts the Erlang Shell from the Erlang Mode. • <f11> z r is available globally and will work as long as the erl executable is accessible.</f11>
			Under PEL this command is available only when the pel-use-erlang user option is set to t.
Start an EDTS controlled Erlang Shell	<f12> M-E z</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell that is EDTS aware. Requires EDTS activated by pel-use-edts (set to t or start-automatically). Use the M-<12> M-E to turn EDTS on if it is not already running to use this command.
Work around to issues in the Erlang Shell	When running the Erlang Shell inside Emacs, you may run into some issues. They are listed here along with work-arounds. * Redundant command echo: On some systems the Erlang shell annoyingly echoes each typed command. If this is the case for your system, PEL provides a fix: Set the pel-erlang-shell-prevent-echo user option to t. After doing that execute pel-init or restart Emacs. * Typing Ctrl-G does not open the Erlang JCL Command Menu: work-around: type the following instead: C-q C-g RET Unfortunately the above workaround does not work when the Erlang shell is launched inside an Emacs vterm shell (see S Shells).		
Erlang Shell: Command History	The following commands can be used to retrieve previously issued Erlang shell commands at the shell prompt. Erlang shell command history file: The Erlang shell history controlled by Emacs is saved inside a file the is restored when opening a new shell: commands from previously opened Erlang shells are also available. Within an Emacs inferior-erlang the cursor keys move the point, they do operate on the history: use M-n and M-p keys instead. You can also use the Erlang shell commands to access the local shell history.		
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.
Previous shell command	М-р	(comint-previous-input ARG)	Cycle backwards through Erlang shell input history, saving input.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Using Man inside	Emacs provide 2 main comma • Both of these are much more		nside buffers. nan reader available on the shell allowing navigation across man pages and opening hyperlinks. They	
Emacs and support Erlang Man pages	 are: The man command uses the system man utility <u>WoMan: Browse Unix Manual Pages "W.O. (without) Man"</u> a complete implementation. It has some formatting limitations compared to man but it's very useful in systems where man is not available like Windows. 			
See also: <u>E Help/Info</u>	To see Erlang man pages using the man command: On most systems the Man pages for Erlang are not available to the man utility and therefore not available for man inside Emacs. There are several ways this can be remedied: One is to set the MANPATH environment variable to include the directory where these files are located. Then man can be used outside and inside Emacs to access Erlang's man pages. For example the following lines can be stored inside a shell script to do this: MANPATH=/usr/local/cellar/erlang/22.3.4/lib/erlang/man: `manpath`			
	export MANPATH • Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add the capability Emacs man to fin the Erlang's man pages without modifying the capabilities of the parent shell. For example, if we want to use the same directory as the above example we need to set the Man-switches which is normally set to nil to the following value: "-M`manpath`:/usr/local/Cellar/erlang/22.3.4/lib/erlang/man" The second alternative can be used to add other directories for the man pages of other programming languages while leaving the ability to have several that have their own value of MANPATH. That might be very useful for someone that uses different versions of Erlang in a system and needs access to the man pages of different versions of Erlang. It becomes possible to run different shells inside Emacs with each having its own value of MANPATH and their providing the man pages from different locations. It is also possible to place all of these directories inside the Man-switches or MANPATH and buses may ability to view several pages for the same topic.			
	directory only. You must al	ght help to see only Erlang	topics when using the man command completion. To do that , set MANPATH to the Erlang man is located in the Erlang man page root directory, otherwise Emacs man completion will not work. See han directory.	
	Using EDTS to access the man pages of the version of Erlang used by various projects: EDTS (see below) supports the ability to download and access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides it's own help command to access sections inside the mane pages, allowing EDTS driven man page access to co-exist with manual man command execution and the techniques described above.			
About Erlang	PEL supports multiple versions of Erlang and access to their man pages Inside the pel-erlang-environment group, the pel-erlang-man-parent-rootdir user-option can be set to read the man parent directory name from an environment variable. To support the ability to open the man files related to a specific version of Erlang available to the parent OS shell, set the environment variable when you select the version of Erlang available to the OS shell and set the name of the environment variable in the pel-erlang-man-parent-rootdir user-option. See the following Installing Erlang pages of the About Erlang document that describes an setting such an editing environment: • Install Erlang OTP Documentation and Man Files • Creating whatis files for Erlang man pages • Using the Erlang Man files within Emacs • Using Specialized OS Shells for Erlang • Using PEL with Specialized Shells for Erlang to Edit Erlang			
See also: <u>ℤ Menus</u>	Use the following commands to You can also use the toolba		e inside Emacs. th <f10>) in the Erlang section.</f10>	
Open a man page inside an Emacs buffer See also:	• <f11> ? m • M-<f8> • %-M</f8></f11>	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because: • the links are active and can be followed. When the man page describes a directory or file, emacs will open the file or the directory (in direct mode) when pressing RET over the link. • You can navigate easily between sections (n/p will move to the next/previous section) • You can use any of the searches.	
• <u>S Customize</u>			 You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer. See all keys available in mode, with <f1> m or <f11>? k m.</f11></f1> The man command prompts, using the word at point as the default. PEL key sequence to customize man: <f11> <f2> E m</f2></f11> 	
Open a man page without external man process: woman	<f11> ? w</f11>	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows). PEL key sequence to customize man: <f11> <f2> E w text width, use word at point, etc</f2></f11>	
Show Erlang Man page documentation of Erlang module:function at point	• C-c C-d • M- <f12> M-d</f12>	(erlang-man-function- no-prompt)	Find manual page for the function under the cursor. • The Erlang man entry for 'module:function' is displayed. It is aware of imported functions. • The C-c C-d binding not available when EDTS is active. PEL provides M- <f12> M-dhen. • Like erlang-man-function below, the current implementation is not able to access documentation of Erlang BIFs unless the function is qualified with the erlang module name: • it will find the documentation for erlang:abs but not abs.</f12>	
Open Erlang Man page for Erlang module:function specified at prompt	M- <f12> M-D</f12>	(erlang-man-function &optional NAME)	Find manual page for NAME, where NAME is module:function. Prompts for module:function. • The Erlang man entry for 'module:function' is displayed. • It is aware of imported functions.	
ivy-erlang-complete based help	The following requires ivy-erlang-complete activated by pel-use-ivy-erlang-complete			
Open web-based Erlang standard library	• <f12> M-h • C-c C-h</f12>	(ivy-erlang-complete- show-doc-at-point)	Show web-based Erlang standard library documentation for function at point. • Prompt to confirm the selection even if there is only 1 candidate.	
documentation for function at point	0 0 0-11	22.2.2.2.2.2.3	Opens the Erlang documentation inside the OS default browser. Like erlang-man-function below, the current implementation is not able to access documentation of Erlang BIFs unless the function is qualified with the erlang module name: it will find the documentation for erlang:abs but not abs.	
EDTS-based help:	These require PEDTS ac	The next two commands are available when EDTS is currently active. It is able to access information about BIFs. These require DETS activated by pel-use-edts (set to t or start-automatically). See general information about EDTS in the section below.		
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip. • This is able to detect Erlang BIFs ; the functions from the erlang module, when not qualified by the module name.	
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function. • Find and show the man-page documentation for the Erlang module:function. • Supports completion: providing you with a list of available Erlang modules, then the list of its functions. This helps when looking for a module or a function.	
			and the state of t	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
<u>EDTS</u>	EDTS - Erlang Develop	ment Tool Suite		
	 The commands in the following rows require the EDTS external package.			
Erlang Project settings	 EDTS is customizable through it edts customization group. With PEL, you can access it by typing <f12> <f3> from an Erlang buffer, or <f11> SPC e <f3> from any other buffer) and type character that identified edts.</f3></f11></f3></f12> EDTS also uses an external .edts configuration file to store Erlang project specific settings. See EDTS: Configure your projects. This allows setting the following: project name, node-name, erlang-cookie, lib-dirs, start-command, top-path, dialyzer-plt, app-include-dirs, project-include-dirs, xref-error-whitelist, xref-file-whitelist 			
See also: <u>▼ Sessions</u>	Desktop restoration often fails when edts-mode was active on session stored: unfortunately edts does not provide a desktop restore handler. PEL does, however provide a desktop restore handler for EDTS which detects edts-mode failures and protect the desktop restoration. Activate EDTS by typing <f12> M-E M-E if it is not active. Use the same key sequence to turn it off. Once active the keys in pink boxes are available.</f12>			
Toggle EDTS mode	<f12> M-E M-E (edts-mode &optional ARG) Turn EDTS mode on or off. • EDTS is an easy to set up Development-environment for Erlang.</f12>			
	<f11> SPC e M-E M-E</f11>	7110)	EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further.	
EDTS/Man	EDTS supports opening documentation for a specific function using the information extracted from Erlang Man pages. • EDTS maintains a set of Erlang man pages per project, so it is possible to have several Erlang projects each one with a different version of Erlang and their corresponding man pages. See Man Files used by ETDS in About Erlang and the Erlang Man section above. EDTS supports two commands to retrieve information from the Erlang man pages: edts-show-doc-under-point and edts-find-doc. • Both are documented above with the other Man help related functions.			
Download, install, select Erlang Man pages	<f12> M-E M-m</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands. • It prompts before proceeding.	
EDTS/AHS Editing	EDTS supports the automatic highlight symbol mode (AHS) and provides commands to modify the name of the highlighted name in the current function or in all of the buffer. The automatic symbol highlighting mode starts when the cursors stays on a symbol for a period longer than the value identified by the ahs-idle-interval which defaults to 1.0 second. To turn off the AHS editing mode, move point away from the highlighted area.			
Edit all highlighted symbols in current function	• C-c C-d e • <f12> e</f12>	(edts-ahs-edit-current-function)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current function. • Activates ahs-edit-mode with edts-current-function range-plugin.	
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer. • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.	
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.	
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.	
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.	
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	Refactor the expression(s) in the region as a function. The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original function. New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring. This command requires Erlang syntax tools package to be available in the node, version 1.2 (or perhaps later.)	
EDTS Code Analysis				
Compile current buffer	<f12> a c</f12>	(edts-code-compile- and-display)	Compiles current buffer on node related to that buffer's project.	
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION-RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.	
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.	
EDTS/Debug				
Toggle breakpoint	• C-c C-d b • <f12> d b</f12>	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.	
List breakpoints	C-c C-d M-b • <f12> d B</f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle- interpreted)	Toggle the interpretation state for module in current buffer.	
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
EDTS/Erlang Node	EDTS Emacs Lisp code intera • It also provides its own EDT		cess. dts-shell described in the Erlang shell section above.	
Display EDTS Erlang Node Name	<f12> M-E N</f12>	(edts-buffer-node- name)	Print the node sname of the erlang node connected to current buffer. The node is either: The module's project node, if current buffer is an erlang module, or The buffer's erlang node if buffer is an edts-shell buffer. The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module such as an otp-module or a module loaded by ~/.erlang).	
Start EDTS server	<f12> M-E x</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).	

<u>Description</u>	Keystroke	Function	Note	
LSP support: Isp-mode erlang Is	LSP (language Server Protocol) support for Erlang is provided via: ↑ The Isp-mode Emacs Lisp external package PEL activates it when the pel-use-erlang-Is user-option is turned on (set to t). • The erlang Is Erlang server for LSP. You must install this manually. You will need Git, Erlang, rebar3 and make. The instructions are on the web-site. • The erlang Is can be configured using a YAML file erlang Is.config file that must be placed at the root of the Erlang project. • It's important for most projects to set that up, otherwise you may not be able to take advantage of several of the cross-reference features ■ Both Isp-mode and erlang Is are under heavy development in the end of 2021. You may want to update these projects regularly to take advantage of the new features and fixes. ■ With PEL you can easily upgrade Isp-mode by moving the its package directory tree into the attic directory and restarting Emacs. If the new version fails just restore the previous one. See the PEL Manual section on manual package update for more information.			
erlang Is required environment	 erl, escript and other Erla erlang_ls. To install erlan 	The following executable must be accessible from PATH: • <u>erl. escript</u> and other Erlang executables. See <u>Installing Erlang</u> if you need to learn how to install Erlang and its tools. • erlang_ls. To install erlang_ls follow the instruction on the <u>erlang_ls GitHub page</u> : git clone it, then run make and make install. • and the various <u>Tools for Erlang</u> .		
• <u>E Customize</u>	Several Isp-mode settings	s are customizable in the Isr	p-mode customization group. With PEL you can access it via <f12> L <f3>. The following settings</f3></f12>	
lsp-mode	are probably what you may want to customize: • Isp-log-io : control whether the LSP process is logging its I/O. Useful for debugging LSP support. • Isp-ui-sideline-enable : control whether LSP display information about the current code line. • Isp-ui-doc-enable : control whether LSP display documentation about the current code symbol. You can also use the PEL commands to modify them dynamically using the following commands.			
Toggle code	<f11> SCP e L D</f11>	(pel-toggle-lsp-ui-doc &optional LOCALLY)	Toggle the display of code documentation. • The initial state is set by the 'Isp-ui-doc-enable' user-option.	
documentation display	<f12> L D</f12>	aoptional LOCALLY)	 By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only. 	
† Toggle logging on the LSP client side	<f11> SCP e L I <f12> L I</f12></f11>	(pel-toggle-lsp-log-io &optional LOCALLY)	 Toggle the logging of LSP I/O. The initial state is set by the 'Isp-log-io' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only. Once client-side logging is active you can then follow it with Isp-workspace-show-log 	
Toggle display of information on current line	<f11> SCP e L L <f12> L L</f12></f11>	(pel-toggle-lsp-ui- sideline &optional LOCALLY)	Toggle the display of information of the current line. The initial state is set by the 'lsp-ui-sideline-enable' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.	
• Erlang LS Features	Overview of the features provide Breadcrumbs Code completion Go to Definition Go to Implementation of OTP Behaviours Signature Suggestions Diagnostics on file open/save: Compiler Diagnostics	Edoc support Navigation to Included Files Find/Peek References Outline of Module		
Isp-mode features	Dialyzer Diagnostics Elvis Diagnostics	Suggest Type Specs Automatic Code reloading	line : set len modeline code pation comments user ention	
isp-illoue leatifies	 Completion at point traditional popup with company-mode Code navigation, with lsp-find-references Symbol highlights Code action on mode line: set lsp-modeline-code-action-segments user-option. Breadcrumb on headerline: Use the lsp-headerline-breadcrumb-mode command to toggle their display. The lsp-headerline-breadcrumb-segments Code Lenses: The Erlang LS configuration provides ct-run-test: display a run button next to a Common Test testcase. server-info: display some Erlang LS server info on top of each module. For debug only. show-behaviour-usages: show the number of modules implementing a behaviour. 			
Isp-mode integrations see also: • ∑ Completion/Input • ∑X Treemacs • ∑ Hide/Show	Isp-mode supports integration with: •			
LSP key bindings: Isp-mode erlang Is See also: Input Method	Key bindings: The lsp-mode is a minor mode and provides customizable prefix key for its key bindings. The default key prefix is s-1. • Since the <u>super modifier key</u> is not always available, it can be modified through customization: change the <u>lsp-keymap-prefix</u> value. This can be done with <u>M-x customize-option</u> or with PEL via the <f11> <f2> o key sequence. • With PEL, the following keys are good replacement candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using M-<f9>. • The key bindings shown below show the standard s-1 key prefix. • If you change <u>lsp-keymap-prefix</u> that would be replaced with your selected prefix key.</f9></f9></f9></f2></f11>			
LSP Session Control	The Language Server supports several programming languages via their back end. Erlang is supported by the erlang-ls-server . The following commands control the LSP session. To start a session use the lsp-workspace-shutdown . Use lsp-workspace-shutdown .			
Activate LSP	s-1 w s	(Isp &optional ARG)	Entry point for the server startup. Without argument: start server if not already running, otherwise display the name:port of the Language Server connected. With C-u, prompt the user to select which language server to start.	
Disconnect LSP	s-1 w D	(Isp-disconnect)	Disconnect the buffer from the language server.	
Shut LSP workspace down	s-1 w q	(Isp-workspace- shutdown WORKSPACE)	Shut the workspace WORKSPACE and the language server associated with it. • It may report some errors. The LSP modelling will show disconnected.	
Restart the language	s-1 w r	(Isp-workspace-restart WORKSPACE)	Restart the workspace WORKSPACE and the language server associated with it	
Server LSP Diagnostics	Use the following commands to See Erlang LS Troubleshood	to get information about the	currently running Language Server session.	
Describe LSP session	s-1 w d	(Isp-describe-session)	Describes current 'Isp-session'. • Show available tools and the available capabilities • Shows the information inside a LspBrowser buffer.	
Validate LSP performance settings	s-l d	(Isp-doctor)	Validate performance settings and write report in a *lsp-performance* buffer. • It reports as <i>errors</i> non-optimal settings. These are not really errors, it's just outlining conditions that are not optimum to get the best performance out of the Language Server.	
Toggle LSP protocol logging	s-1 T L	(Isp-toggle-trace-io)	Toggle client-server protocol logging.	
Display LSP workspace log buffer	s-1 L	(Isp-workspace-show- log WORKSPACE)	Display the log buffer of WORKSPACE when IO logging is enabled. • With PEL toggle IO logging with <f12> L D. • This shows all LSP JSON transactions occurring. • To always see the tail of the buffer move point to the end of buffer first, then leave it there. Emacs will automatically scroll the buffer content to keep the point visible.</f12>	

Description	<u>Keystroke</u>	Function	<u>Note</u>
Project Setup			
Add directory to the list of workspace folders	s-1 F a	(Isp-workspace-folders- add PROJECT-ROOT)	Add PROJECT-ROOT to the list of workspace folders. • Prompts for the directory.
Remove a directory from the workspace blacklist	s-1 F b	(Isp-workspace- blacklist-remove PROJECT-ROOT)	Remove PROJECT-ROOT from the workspace blacklist.
Remove directory from the list of workspace folders	s-1 F r	(Isp-workspace-folders- remove PROJECT- ROOT)	Remove PROJECT-ROOT from the list of workspace folders.
Toggling features			
Toggle diagnostic modeline	s-1 T D	(Isp-modeline- diagnostics-mode &optional ARG)	Toggle diagnostics modeline.
Toggle current-line status information	s-1 T S	(Isp-ui-sideline-mode &optional ARG)	Minor mode for showing status information for current line. • Displays code status such as definition errors, etc
Toggle code action on modelling	s-l T a	(Isp-modeline-code- actions-mode &optional ARG)	Toggle code actions on modeline.
Toggle headline breadcrumbs	s-l T b	(Isp-headerline- breadcrumb-mode &optional ARG)	Toggle breadcrumb on headerline. • When active the list of directories are listed on the header line. In graphics mode these are buttons you can use to change directory.
Toggle hover information	s-1 T d	(Isp-ui-doc-mode &optional ARG)	Minor mode for showing hover information in child frame. When active, information about symbol at point is shown in a pop-up overlay area. In graphics mode the information has links that can be used to open web-located information. For small window the information may cover too much code, use this command to toggle in and out of view. Also note that when the point is toward the bottom of a window the information window may not show completely and you may have to scroll your window.
Toggle symbol highlighting	s-1 T h	(Isp-toggle-symbol- highlight)	Toggle symbol highlighting.
Toggle code-lens	s-1 T 1	(Isp-lens-mode &optional ARG)	Toggle code-lens overlays. • Code-lens show information like # times a specific function is referenced. • This can be used to infer type specs when writing a function. • For this to work Dialyzer must be setup. ∴ Code lens are overlays and appear above the corresponding line by default. ★ There seems to be a bug in lsp-mode that prevents scrolling when the overlay hit the top of the window. A work-around is to customize lsp-lens-place-position to 'end-of-line instead.
Code Changes			
Reformat Erlang file	s-1 = =	(Isp-format-buffer)	Reformat the code in the current Erlang buffer.
Refactor source import	s-1 r o	(Isp-organize-imports)	Perform the source.organizeImports code action, if available.
Rename symbol at point See also: Search/Replace	s-1 r r	(Isp-rename NEWNAME)	Rename the symbol (and all references to it) under point to NEWNAME. For renaming the arguments of a function, the <u>iedit mode</u> is more appropriate. It supports restricting the scope to the current function. See <u>Search/Replace</u>
Cross Reference			
Find Identifier definitions	s-1 G g	(Isp-ui-peek-find- definitions &optional EXTRA)	Find definitions to the IDENTIFIER at point.
Find symbol implementation locations	s-1 G i	(Isp-ui-peek-find- implementation &optional EXTRA)	Find implementation locations of the symbol at point.
Find references	s-1 G r	(Isp-ui-peek-find- references &optional INCLUDE-DECLARATION EXTRA)	Find references to the IDENTIFIER at point.
Find symbols	s-1 G s	(Isp-ui-peek-find- workspace-symbol PATTERN &optional EXTRA)	Find symbols in the worskpace. The symbols are found matching PATTERN.
Execute code action	s-l a a	(Isp-execute-code- action INPUT0)	Execute code action ACTION. If ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Request codeAction/resolve for more info if server supports.
Highlight all relevant references to symbol at point	s-1 a h	(Isp-document- highlight)	Highlight all relevant references to the symbol under point.
Click LSP lens via avy	s-l a l	(Isp-avy-lens)	Click lsp lens using 'avy' package. • The code lens must be active. Use s-1 T 1 to activate it if it's not active.
Apropos search for symbol/regexp	s-1 g a	(xref-find-apropos PATTERN)	Find all meaningful symbols that match PATTERN. Can be used to search symbol outside project. The argument has the same meaning as in 'apropos'. The result is shown in a *xref* buffer.
Find definitions of symbol at point	s-1 g g	(Isp-find-definition &key DISPLAY-ACTION)	Find definitions of the symbol under point.
Find implementations of symbol at point	s-l g i	(Isp-find- implementation &key DISPLAY-ACTION)	Find implementations of the symbol under point.
Find references of symbol at point	s-l g r	(Isp-find-references &optional INCLUDE- DECLARATION &key DISPLAY-ACTION	Find references of the symbol under point. • The result is shown in a *xref* buffer.
Trigger display hover information	s-1 h g	(Isp-ui-doc-glance)	Trigger display hover information popup and hide it on next typing.
Display documentation of symbol at point in *Isp-help*	s-1 h h	(Isp-describe-thing-at- point)	Display the type signature and documentation of the thing at point. • Display help about symbol at point inside a *lsp-help* buffer. • Useful in terminal mode as you can navigate inside the buffer and used other functions to open identified URL references.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Treemacs support • Ex Treemacs	The <u>treemacs</u> and <u>lsp-treemacs</u> external packages respectively activated by PEL user-options <u>pel-use-treemacs</u> and <u>pel-use-lsp-treemacs</u> , provide extra features that help Erlang development. When these are activated PEL provides bindings for the <u>lsp-treemacs</u> features. Configure lsp-treemacs by accessing the lsp-treemacs customization group. With PEL use <f12> w <f3> from an Erlang buffer.</f3></f12>		
Open LSP Treemacs error list window.	<f12> w e</f12>	(Isp-treemacs-errors- list)	Display an error list window at the bottom of the frame. The buffer uses the treemacs-mode and supports its commands and key bindings. See ** Treemacs** for the list of commands and key bindings. To close the window, kill its buffer with *C-x** k
• Quick fix	x	(Isp-treemacs-quick-fix &rest ARGS)	If possible, proposes a quick code fix for the error at point.
Open LSP Treemacs symbol window	<f12> w s</f12>	(Isp-treemacs-symbols)	Show symbols view. • To close the window, kill its buffer with C-x k
Open LSP Treemacs references window	<f12> w x</f12>	(Isp-treemacs- references ARG)	Show the references for the symbol at point. Issue from an Erlang buffer. • With a prefix argument, select the new window and expand the tree of references automatically. • To close the window, kill its buffer with C-x k
Open LSP Treemacs <u>implementations</u> <u>window</u>	<f12> w i</f12>	(Isp-treemacs- implementations ARG)	Show the implementations for the symbol at point. Issue this command from an Erlang buffer. • With a prefix argument, select the new window expand the tree of implementations automatically. • To close the window, kill its buffer with C-x k
Open LSP Treemacs <u>call hierarchy</u> <u>window</u>	<f12> w c</f12>	(Isp-treemacs-call- hierarchy OUTGOING)	Show the incoming call hierarchy for the symbol at point. • With a prefix argument, show the outgoing call hierarchy. This does not seem to have been implemented for Erlang.
Open LSP Treemacs type hierarchy window	<f12> w t</f12>	(Isp-treemacs-type- hierarchy DIRECTION)	Show the type hierarchy for the symbol at point. • With prefix 0 show sub-types. • With prefix 1 show super-types. • With prefix 2 show both. This is not implemented for Erlang.
Rendering markup embedded in comments	The following commands are used to create images from specific markup code embedded inside Erlang source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example. You can also use Graphviz, see Marahviz Dot		
Preview UML diagram	<f12> u</f12>	(pel-render-	Render the PlantUML markup embedded in current mode comment.
from plantUML source in current plantUML region of commented source code	<f11> SCP e u</f11>	commented-plantuml PREFIX &optional POS)	 Use region if identified otherwise use PlantUML block at point. Uses prefix (as PREFIX) to choose where to display it: 4 (when prefixing the command with C-u) -> new window 16 (when prefixing the command with C-u C-u) -> new frame. else -> new buffer
See also: M PlantUML			 This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment.
	block and issuing this comr	nand.	cture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML ctivated by pel-use-plantuml user option being non-nil.

Emacs & Erlang - References

Document	Notes
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.
Erlang versions	Erlang Versions - Version Scheme Erlang Support, Compatibility, Deprecations, and Removal
Erlang/OTP @ Github	Erlang source code
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, <u>Erlang Issue Tracker</u> , events.
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.
Erlang/BEAM	Erlang was the first of one of several programming language that runs on the BEAM VM.
Good introduction presentations on Erlang	 The soul of Erlang and Elixir • Saša Jurić • GOTO 2019 A very good presentation that captures the essence of why Erlang is so important. Fast pace. A must see. A great presentation to show people that may be reluctant to use the technology. The Do's and Don'ts of Error Handling • Joe Armstrong • GOTO 2018
Erlang References	
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.

Document	Notes
Erlang Information Sites	
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.
about-erlang trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang. • about-erlang provides general information about Erlang, including: • Learning Erlang, a table with links to resources to learn Erlang. • Installing Erlang, describes various ways to install Erlang on macOS. • Tools for Erlang, describes tools you can use for Erlang development.
Emacs and Erlang Man files	
How to create a local whatis file	Show how to create a missing whatis file for a set of man pages.
The Erlang mode for Emacs (user guide) Erlang mode for Emacs (man page)	On the <u>erlang.org</u> site. Start here. Describes the 2 files (erlang.el and erlang-start.el) provided by the Erlang mode support, how to set them up for various operating systems. Note, however, that PEL provides the setting for you. It also provides an overview of the various features the package provides. • If found bugs in the <u>erlang man</u> page in the Edit- Moving the marker section. 1) it's the point that is moved, not the marker, 2) C-a is not an Emacs key prefix, so their key binding descriptions like C-a M-a and C-a M-e are invalid. Reported as <u>ERL-1314</u> . • There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric-command variables. • The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -> on a function definition line. • Another issue: inside the OS-level erlang shell, we can tab-completion a module:function string, but that does not work inside the emacs erlang shell.
Emacs tools for Erlang	
EDTS	EDTS: stands for: The Erlang Development Tool Suite. See also: • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube • EDTS: • configure your project • One Primary EDTS node • 1 node per open project • To setup an Erlang project: a .edts file in the project: :name "my-project" :otp-path "path/to/otp" :node-name "project-node-name" :lib-dirs '("lib" "deps")
How to install EDTS	Describes some aspects of EDTS and links that may be useful. Lists the requirements. A ****After installing EDTS, I got several compile errors, and had to install the following other modules: - auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?
Language Server Protocol	Language Server Protocol @ Wikipedia Language Server Protocol Specifications web site Language Server Protocol @ Github
LSP for Erlang	LSP support for Erlang is done using the following: • The Isp-mode Erlang server • The Isp-mode Erlang server
Erlang Tools accessible via the erlang_ls	Several Erlang tools are available through the erlang_ls LSP server for Erlang. Building erlang_ls from source is the best way to install it as it will also install the secondary tools it provides. • The following is not a complete list of all tools available.
Gradualizer: A Gradual Type System for Erlang	Gradualizer is a type checker for Erlang code based on the principles of <u>Gradual Typing</u> that uses the existing Erlang type specs and adds opt-in type checking. It is a work in progress. • <u>Gradualizer @ Github</u> • Youtube presentation: <u>Dialyzer vs Gradualizer at ElixirConf EU 2019</u>
company-mode ; Modular in-buffer completion framework for Emacs	
Using Tags with Erlang	
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the pel-erlang-shell-prevent-echo is set to t. To activate after setting it: execute pel-init or restart Emacs.