Emacs support for the Erlang Programming Language

<u>Description</u>	<u>Keystroke</u>	Function	Note		
Erlang Support	Emacs supports Erlang via the				
See also: • Erlang Reference			, part of OTP APEL activates it when pel-use-erlang is turned on. It can then also activates: -edts (set to t or start-automatically).		
PEL Manual about-erlang	_		use-erlang-ls. Uses the erlang_ls Erlang LSP server. Integrates with:		
 Developing Erlang 	• Will Helm by using helm-lsp		pel-use-helm-lsp.		
Code with PEL set PEL Erlang	• w treemacs by using lsp-t	reemacs activated by	pel-use-treemacs and pel-use-lsp-treemacs.		
environment	origami by using Isp-or		pel-use-lsp-origami.		
T (2)	The flycheck external package a		el-use-erlang-syntax-check set to 'use-flycheck, or Emacs built-in <u>flymake</u> if set to 'use-flymake. ve mainly been replaced by EDTS and needs maintenance. PEL does not support it.		
• <u>∑ Hide/Show</u> • <u>∑ Text Modes</u>	The <u>hide-comnt.el</u> extern				
• <u>∑ Highlight</u>	The iedit external package activated by pel-use-iedit.				
• <u>∑ Inserting Text</u>	The smart-dash external p				
	Add electric pairing without	or smartparens-mode auto smartparens with built-in <u>e</u>	pel-use-smartparens. pmatically in erlang-mode buffers by adding their mode to pel-erlang-activates-minor-modes. plectric-pair-local-mode: add electric-pair-local-mode to pel-erlang-activates-minor-modes. peess the customization group and select pairs.		
			ng via pel-activates-global-minor-mode : show-paren-mode ng files to show the list of functions.		
<u>// Opecubal</u>			el-erlang-skels.el, sections of pelkey-macros.el and pel keys.el and PEL files they require.		
• ∑ Customize	Customization:				
	pel-pkg-for-erlang: to pel-erlang-ide group in the pel-erlang-ide group in the pel-erlang in the	o activate pel-use-erlang : to activate EDTS and LSP.	d RET to open the specific customization group or one of the following key sequences. use <f11> SPC e <f2>, or <f12> <f2> from an Erlang buffer. This has sub-group: see</f2></f12></f2></f11>		
	_	hen pel-use-erlang is on, hen pel-use-edts is on,	use <f11> SPC e <f3> 1 use <f11> SPC e <f3> 3</f3></f11></f3></f11>		
	• Isp-erlang: v	hen pel-use-erlang-ls is o	on, use <f11> SPC e L <f3> 1 on, use <f11> SPC e L <f3> 2</f3></f11></f3></f11>		
	The pel-pkg-for-erlang group	has several user-options t	o control Erlang editing. Only some of them are described here. Use Emacs for the complete list.		
⊌ >>			the Erlang shell from echoing every command. tivation of local minor modes in erlang-mode buffers, eg. smart-dash-mode.		
Identify minor modes to	pel-erlang-environment gr	oup:	nt directory of Erlang man directory. The man directory should hold the man1, man3, man4 and		
activate automatically in erlang-mode buffers	man6 which contain Erlar	ng man files. If this is set Pl	EL sets (override) the erlang.el erlang-root-dir user-option value with it which activates the		
Pulma Gul			erlang-man-parent-rootdir is nil, you must set the erlang-root-dir user-option yourself. e Erlang binaries are stored.		
Erlang Style	pel-erlang-version-dete	ction-method: identifies a	mechanism to detect Erlang/OTP version. By default it uses an Erlang script provided with PEL.		
Control 🖛	pel-erlang-code-style group		the facility of the second state of the second		
Ericsson AB Guideline	When pel-erlang-fill	-column user option is nil,	ping occurs: maximum <i>line length</i> (defaults to 100). You can change the value or set it nil. erlang-mode buffers use the global Emacs fill-column value.		
Inaka Guideline	pel-erlang-skel-use-s pel-erlang-skel-inser	econdary-separators : w t-file-timestamp: whether	eparators are used in Erlang code templates (see the Insert Erlang Code Template section below), hether secondary separator lines are inserted by some Erlang code templates, automatically updated time stamps are inserted in Erlang source code file header blocks. In turned on, a space is automatically inserted after a comma typed inside a parens block.		
Open this PDF file. See also: <u>▼ Help/Info</u>	• <f11> SPC e <f1> • <f11> SPC e w <f1> • <f11> SPC e L <f1></f1></f11></f1></f11></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the <u>\$\mathbb{N}\cdot\ erlang\ local PDF.</u> If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.		
	• <f12> <f1> • <f12> w <f1> • <f12> L <f1></f1></f12></f1></f12></f1></f12>		≪ Key sequences that start with <f11> SPC e are available from any major modes. Key sequences that start with <f12> are only available in erlang-mode buffers. The <f12> keys sequences are mirrored by the <m-f12> key sequence for convenience.</m-f12></f12></f12></f11>		
<u>> Customize</u> PEL Erlang support	<f11> SPC e <f2> <f12> <f2></f2></f12></f2></f11>	(pel-customize-pel &optional OTHER- WINDOW)	Customize PEL Erlang support: access PEL user-options to activate Erlang support packages. • If OTHER-WINDOW is non-nil (use C-u), display in another window.		
∑ Customize Emacs	<f11> SPC e <f3></f3></f11>	(pel-customize-library	Customize Emacs Erlang support: erlang, erldoc, edts, auto-highlight-symbol, electricity,		
Erlang support	<f12> <f3></f3></f12>	&optional OTHER- WINDOW)	smartparens, smart-dash. • If OTHER-WINDOW is non-nil (use C-u), display in another window.		
∑ Customize PEL LSP	<f11> SPC e L <f2></f2></f11>	(pel-customize-pel	Customize PEL LSP Erlang support		
for Erlang support	<f12> L <f2></f2></f12>	&optional OTHER- WINDOW)	If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-erlang-ls is turned on.		
∑ Customize Emacs LSP for Erlang support	<f11> SPC e L <f3> <f12> L <f3></f3></f12></f3></f11>	(pel-customize-library &optional OTHER- WINDOW)	Customize Emacs LSP Erlang support: lsp-erlang, lsp-mode, lsp-ui, helm-lsp, lsp-ivy, lsp-origami, lsp-treemacs. • If OTHER-WINDOW is non-nil (use C-u), display in another window.		
			This is available when pel-use-erlang-is is turned on.		
∑ Customize PEL LSP	<f11> SPC e w <f2></f2></f11>	(pel-customize-pel	Customize PEL LSP Erlang support		
Window for Erlang support	<f12> w <f2></f2></f12>	&optional OTHER- WINDOW)	 If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on. 		
∑ Customize Emacs	<f11> SPC e w <f3></f3></f11>	(pel-customize-library	Customize Emacs LSP Erlang support: Isp-treemacs, treemacs		
LSP Window for Erlang support	<f12> w <f3></f3></f12>	&optional OTHER- WINDOW)	If OTHER-WINDOW is non-nil (use C-u), display in another window. This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on.		
	Lies the following command to	<u> </u>			
Environment Help Erlang Mode version	Use the following command to	(pel-show-erlang-	Display the following information in the minibuffer.		
LIGHT HOUS VEISION	<f11> SPC e ?</f11>	version)	of available Erlang system, of erlang.el, of erlang ls (if available), values of erlang-root-dir and pel-		
	1127 (erlang-man-parent-rootdi	or available Erlang system, or <u>erlang.er</u> , or <u>erlang_is</u> (if available), values of erlang-root-dir and pel- cotdir. For more information see <u>set PEL Erlang environment</u> .		
Syntax Highlighting	The <u>erlang.el</u> external package provides several levels of Erlang code syntax highlighting: • Off, Level 1: comments only, Level 2, Level 4: maximum variety. There is not key binding for this. You must use the Syntax Highlighting section of the Erlang menu: • In terminal mode Type <f10> to access the menu, then select Erlang, Syntax Highlighting and the level you want.</f10>				

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>		
Electric Keys for			behaviour of some keys in erlang-mode buffers:		
Erlang	2. the smartparens exter	rnal package, which controls the behaviour of the RET , ,, ; and > keys as controlled by erlang-electric-commands variable. external package, which modifies the behaviour of the DEL and <deletechar></deletechar> behaviour when smartparens-mode is active.			
∑ Customize	PEL provides customization ar		g.el electric key behaviour and provides electric behaviour of some extra keys.		
• selectric keys	The pel-erlang-space-at	fter-comma-in-block user-	of the RET, ,, ; and > keys have electric behaviour. By default they are all activated. option activates automatic insertion of space after comma inside a block. Disabled by default.		
Togglo olootrioity		iffer, use the <m-f12> M- (pel-erlang-comma</m-f12>	refix key followed by one of these keys to toggle the electric behaviour of the key.		
Toggle , electricity	<m-f12> M-` ,</m-f12>	&optional GLOBALLY)	Toggle electric behaviour of the comma key. Show message describing its new state. • To modify the behaviour in all Erlang buffers type: M <m-f12> M-`,</m-f12>		
Toggle automatic insertion of space after	<m-f12> M-` M-,</m-f12>	(pel-erlang-toggle- space-after-comma	Toggle automatic insertion of space after comma inside blocks. Show its new state. • To modify the behaviour in all Erlang buffers type: M <m-f12> M- M-,</m-f12>		
comma in block		&optional GLOBALLY)			
Toggle > electricity	<m-f12> M-` ></m-f12>	(pel-erlang-gt &optional GLOBALLY)	Toggle electric behaviour of the greater-than key. Show message describing its new state. • To modify the behaviour in all Erlang buffers type: M <m-f12> M-`></m-f12>		
Toggle RET electricity	<m-f12> M-` RET</m-f12>	(pel-erlang-newline &optional GLOBALLY)	Toggle electric behaviour of the newline key. Show message describing its new state. • To modify the behaviour in all Erlang buffers type: M <m-f12> M-` RET</m-f12>		
Toggle ; electricity	<m-f12> M-`;</m-f12>	(pel-erlang-semicolon &optional GLOBALLY)	Toggle electric behaviour of the semicolon key. Show message describing its new state. • To modify the behaviour in all Erlang buffers type: M <m-f12> M-`;</m-f12>		
Toggle . electricity	<m-f12> M-`.</m-f12>	(pel-erlang-period &optional GLOBALLY)	Toggle Erlang electric behaviour of the semicolon key. Show message describing its new state. • To modify the behaviour in all Erlang buffers type: $M < M-f12> M-$.		
Toggle - electricity	<m-f12> M-` -</m-f12>	(smart-dash-mode &optional ARG)	Toggle the smart-dash-mode on/off. More info in $\ \ \ \ \ \ \ \ \ \ \ \ \ $		
Matching Pairs			pairs made of (), [], { }, " " and ' '. PEL adds the << >> pair. haracter(s) automatically inserts the closing character(s)		
	This requires smartpa	rens external package.	activated by pel-use-smartparens.		
		•	minor-modes to activate smartparens-mode automatically for erlang-mode buffers. lectric-pair-local-mode: add electric-pair-local-mode to pel-activates-minor-modes list.		
Matching pairs	(When the smartparens ex	ternal package is used and the smartparens-mode is active, the characters on the left are taken to		
• ∑x Smartparens	[When typing the first ch.	s are: (), [], { }, " ", ' ', and << >> (added by PEL). aracter of a pair, the rest of the pair is inserted and point is left inside.		
	{	The smartparens-mode	xt inside one of those pairs, mark the text area then type the first character of the pair. can be activated automatically for Erlang by adding erlang-mode to the pel-erlang-activates-		
	и		ey sequence to toggle the smartparens-mode on and off.		
	, <<		arens-strict-mode that imposes balanced pairs but that does not help much in Erlang. > including navigation across balanced pairs, something the default erlang.el does not do, by		
Insert Parentheses			and backward-sexp by specialized functions.		
msert Farentieses	M-((insert-parentheses For Erlang: insert a parenthesis pair '()', leaving point after open-paren. Use this when smartparens is not used.			
	No argument is equivalent to	the following ARG sexps in parenthesis if they are balanced. A negative ARG encloses the preceding ARG sexps insteat to zero: just insert '()' and leave point between. If region is active, insert enclosing characters at region boundaries.			
			it to nil in Erlang mode buffers, allowing the use of this command to insert the argument space between the function name and the opening parenthesis.		
New Line	RET	(erlang-electric-newline	Break line at point. If electric behaviour is activated: indent, continuing comment if within one.		
		&optional ARG)			
		&optional ARG)	 Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed 		
Electric behaviour:		The electric behaviour of the	 Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. nis key is controlled by 2 variables: 		
Electric behaviour: • indent next line		The electric behaviour of the electric behaviour of the erlang-electric-commander erlang-electric-newline	 Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. 		
	<	The electric behaviour of the electric behaviour of the erlang-electric-commander erlang-electric-newline	 Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. nis key is controlled by 2 variables: ands must include the erlang-electric-newline symbol to activate the key electric behaviour. a-criteria identifies how to check whether newline should behave electric. By default, the value is 		
indent next line Electric < ∑x Smartparens Electric >	< >	The electric behaviour of the electric behaviour of the erlang-electric-comma erlang-electric-newline (th): makes it behave elected (erlang-electric-lt & eptional ARG) (erlang-electric-gt	Should the current line begin with a comment, and the variable 'comment-multi-line' be non- nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. his key is controlled by 2 variables: ands must include the erlang-electric-newline symbol to activate the key electric behaviourcriteria identifies how to check whether newline should behave electric. By default, the value is ctric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent.		
indent next line Electric < ∑x Smartparens		The electric behaviour of the erlang-electric-comma erlang-electric-newline (th): makes it behave electric-lt &optional ARG)	Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. his key is controlled by 2 variables: unds must include the erlang-electric-newline symbol to activate the key electric behaviour. -criteria identifies how to check whether newline should behave electric. By default, the value is ctric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair.		
• indent next line Electric <		The electric behaviour of the electric behaviour of the erlang-electric-comma erlang-electric-newline (th): makes it behave elected (erlang-electric-lt & eptional ARG) (erlang-electric-gt	Should the current line begin with a comment, and the variable 'comment-multi-line' be non- nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. In skey is controlled by 2 variables: Inds must include the erlang-electric-newline symbol to activate the key electric behaviourcriteria identifies how to check whether newline should behave electric. By default, the value is ctric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: -> force new line and indent.		
• indent next line Electric <	>	The electric behaviour of the electric behaviour of the erlang-electric-comma erlang-electric-newline (th): makes it behave elected (erlang-electric-lt & eptional ARG) (erlang-electric-gt	Should the current line begin with a comment, and the variable 'comment-multi-line' be nonnil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. Siskey is controlled by 2 variables: India must include the erlang-electric-newline symbol to activate the key electric behaviour. Corriteria identifies how to check whether newline should behave electric. By default, the value is ctric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: -> force new line and indent. With PEL, you can also type -> without electric behaviour by typing See below.		
indent next line Electric < ∑X Smartparens Electric > Electric behaviour: new line & indent Insert -> by typing Electric comma	> M-1 >	The electric behaviour of the electric behaviour of the electric-comma electric-newline (t): makes it behave electric-lt & entered electric-lt & entered electric-gt & entered electric-geriod & entered electric-geriod & entered electric-geriod & entered electric-geriod electric-comma	 Should the current line begin with a comment, and the variable 'comment-multi-line' be nonnil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. his key is controlled by 2 variables: ands must include the erlang-electric-newline symbol to activate the key electric behaviour. e-criteria identifies how to check whether newline should behave electric. By default, the value is ctric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: -> force new line and indent. With PEL, you can also type -> without electric behaviour by typing See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert -> when typing only if the following conditions are met (otherwise inserts): period is included in the pel-erlang-electric-keys user-option value point is inside code and dash does not follow \$, as in \$- Insert a comma character and possibly: 		
• indent next line Electric < • ∑ x Smartparens Electric > Electric behaviour: • new line & indent Insert -> by typing Electric comma Electric behaviour: • new line & indent	> M-1 > 	The electric behaviour of the erlang-electric-comma erlang-electric-newline (t): makes it behave electric-lt & electric-lt & electric-gt & electric-gelectric-	Should the current line begin with a comment, and the variable 'comment-multi-line' be nonnil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. In skey is controlled by 2 variables: Inds must include the erlang-electric-newline symbol to activate the key electric behaviour. criteria identifies how to check whether newline should behave electric. By default, the value is ctric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: -> force new line and indent. With PEL, you can also type -> without electric behaviour by typing See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert -> when typing only if the following conditions are met (otherwise inserts): period is included in the pel-erlang-electric-keys user-option value point is inside code and dash does not follow \$, as in \$-		
• indent next line Electric < • ∑ x Smartparens Electric > Electric behaviour: • new line & indent Insert -> by typing Electric comma Electric behaviour:	> M-1 > 	The electric behaviour of the electric behaviour of the electric-comma electric-newline (t): makes it behave electric-lt & entered electric-lt & entered electric-gt & entered electric-geriod & entered electric-geriod & entered electric-geriod & entered electric-geriod electric-comma	 Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. his key is controlled by 2 variables: unds must include the erlang-electric-newline symbol to activate the key electric behaviour. c-criteria identifies how to check whether newline should behave electric. By default, the value is ctric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: -> force new line and indent. With PEL, you can also type -> without electric behaviour by typing See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert -> when typing only if the following conditions are met (otherwise inserts): period is included in the pel-erlang-electric-keys user-option value point is inside code and dash does not follow \$, as in \$- Insert a comma character and possibly: a new indented line when the comma is at the end of an Erlang expression. 		
indent next line Electric < ∑	> M-1 >	The electric behaviour of ti erlang-electric-comma erlang-electric-newline '(t): makes it behave electric-lt &optional ARG) (erlang-electric-gt &optional ARG) (pel-erlang-electric-period &optional arg) (erlang-electric-comma &optional ARG) (erlang-electric-comma &optional ARG)	 Should the current line begin with a comment, and the variable 'comment-multi-line' be nonnil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. his key is controlled by 2 variables: ands must include the erlang-electric-newline symbol to activate the key electric behaviour. c-criteria identifies how to check whether newline should behave electric. By default, the value is otric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: -> force new line and indent. With PEL, you can also type -> without electric behaviour by typing See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert -> when typing only if the following conditions are met (otherwise inserts): period is included in the pel-erlang-electric-keys user-option value point is inside code and dash does not follow \$, as in \$- Insert a comma character and possibly: a new indented line when the comma is at the end of an Erlang expression. a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert , by typing M-1 , Insert a semicolon character and possibly a function clause head prototype on the next line. 		
indent next line Electric < ∑£ Smartparens Electric > Electric behaviour: new line & indent Insert -> by typing Electric comma Electric behaviour: new line & indent space after comma in block Electric semicolon	> M-1 > M-1 ,	The electric behaviour of the electric behaviour of the erlang-electric-comma erlang-electric-newline (the electric-newline) (the electric-lit electric-lit electric-lit electric-git elect	 Should the current line begin with a comment, and the variable 'comment-multi-line' be nonnil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. nis key is controlled by 2 variables: ands must include the erlang-electric-newline symbol to activate the key electric behaviour. a-criteria identifies how to check whether newline should behave electric. By default, the value is ctric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. • When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. • Electric behaviour: → force new line and indent. • With PEL, you can also type → without electric behaviour by typing →. See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert → when typing → only if the following conditions are met (otherwise inserts → .): • period is included in the pel-erlang-electric-keys user-option value • point is inside code and dash does not follow \$, as in \$→ Insert a comma character and possibly: • a new indented line when the comma is at the end of an Erlang expression. • a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert , by typing M-1 , Insert a semicolon character and possibly a function clause head prototype on the next line. • Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line. 		
• indent next line Electric < • ∑ * Smartparens Electric > Electric behaviour: • new line & indent Insert -> by typing Electric comma Electric behaviour: • new line & indent • space after comma in block	> M-1 > M-1 ,	The electric behaviour of ti erlang-electric-comma erlang-electric-newline (t): makes it behave electric-lt &optional ARG) (erlang-electric-gt &optional ARG) (pel-erlang-electric-period &optional arg) (erlang-electric-comma &optional ARG) (erlang-electric-comma &optional ARG)	 Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. nis key is controlled by 2 variables: India must include the erlang-electric-newline symbol to activate the key electric behaviour. p-criteria identifies how to check whether newline should behave electric. By default, the value is stric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: →> force new line and indent. Electric behaviour: →> force new line and indent. With PEL, you can also type →> without electric behaviour by typing →. See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert →> when typing → only if the following conditions are met (otherwise inserts → .): period is included in the pel-erlang-electric-keys user-option value point is inside code and dash does not follow \$, as in \$ − Insert a comma character and possibly: a new indented line when the comma is at the end of an Erlang expression. a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert , by typing M-1 , Insert a semicolon character and possibly a function clause head prototype on the next line. Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line. Inserts a		
• indent next line Electric < • ∑	> M-1 > M-1 , ;	The electric behaviour of the erlang-electric-comma erlang-electric-newline (t): makes it behave electric-lt & eptional ARG) (erlang-electric-gt & eptional ARG) (pel-erlang-electric-geriod & eptional arg) (erlang-electric-comma & eptional ARG) (erlang-electric-comma & eptional ARG) (erlang-electric-semicolon & eptional ARG)	 Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. nis key is controlled by 2 variables: inds must include the erlang-electric-newline symbol to activate the key electric behaviour. p-criteria identifies how to check whether newline should behave electric. By default, the value is ctric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. • When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. • Electric behaviour: →> force new line and indent. • Electric behaviour: →> force new line and indent. • Electric behaviour for this character: Just insert > by typing →. See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert →> when typing →. only if the following conditions are met (otherwise inserts →.): • period is included in the pel-erlang-electric-keys user-option value • point is inside code and dash does not follow \$, as in \$→ Insert a comma character and possibly: • a new indented line when the comma is at the end of an Erlang expression. • a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert , by typing M-1 , Insert a semicolon character and possibly a function clause head prototype on the next line. • Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line. <li< td=""></li<>		
• indent next line Electric < • ∑	> M-1 > M-1 ,	The electric behaviour of ti erlang-electric-comma erlang-electric-newline (t): makes it behave electric-lt &optional ARG) (erlang-electric-gt &optional ARG) (pel-erlang-electric-period &optional arg) (erlang-electric-comma &optional ARG) (erlang-electric-comma &optional ARG)	 Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. nis key is controlled by 2 variables: India must include the erlang-electric-newline symbol to activate the key electric behaviour. p-criteria identifies how to check whether newline should behave electric. By default, the value is stric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: →> force new line and indent. Electric behaviour: →> force new line and indent. With PEL, you can also type →> without electric behaviour by typing →. See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert →> when typing → only if the following conditions are met (otherwise inserts → .): period is included in the pel-erlang-electric-keys user-option value point is inside code and dash does not follow \$, as in \$ − Insert a comma character and possibly: a new indented line when the comma is at the end of an Erlang expression. a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert , by typing M-1 , Insert a semicolon character and possibly a function clause head prototype on the next line. Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line. Inserts a		
• indent next line Electric < • ∑	<pre>M-1 ></pre>	The electric behaviour of the erlang-electric-comma erlang-electric-newline (t): makes it behave electric-lt & eptional ARG) (erlang-electric-gt & eptional ARG) (pel-erlang-electric-geriod & eptional arg) (erlang-electric-comma & eptional ARG) (erlang-electric-comma & eptional ARG) (erlang-electric-semicolon & eptional ARG)	 Should the current line begin with a comment, and the variable 'comment-multi-line' be nonnil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. his key is controlled by 2 variables: inds must include the erlang-electric-newline symbol to activate the key electric behaviour. periteria identifies how to check whether newline should behave electric. By default, the value is circle as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. • When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. • Electric behaviour: →> force new line and indent. • Electric behaviour: →> without electric behaviour by typing →. See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert →> when typing →. only if the following conditions are met (otherwise inserts →.): • period is included in the pel-erlang-electric-keys user-option value • point is inside code and dash does not follow \$, as in \$− Insert a comma character and possibly: • a new indented line when the comma is at the end of an Erlang expression. • a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert , by typing M-1 , Insert a semicolon character and possibly a function clause head prototype on the next line. • Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line. • Insert a function clause head prototype when the selection cri		
• indent next line Electric < • ∑	<pre>M-1 ></pre>	The electric behaviour of the erlang-electric-comma erlang-electric-newline (t): makes it behave electric-lt & eptional ARG) (erlang-electric-gt & eptional ARG) (pel-erlang-electric-geriod & eptional arg) (erlang-electric-comma & eptional ARG) (erlang-electric-comma & eptional ARG) (erlang-electric-semicolon & eptional ARG)	 Should the current line begin with a comment, and the variable 'comment-multi-line' be nonnil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. his key is controlled by 2 variables: unds must include the erlang-electric-newline symbol to activate the key electric behaviour. c-criteria identifies how to check whether newline should behave electric. By default, the value is circle as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: →> force new line and indent. With PEL, you can also type →> without electric behaviour by typing →. See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert →> when typing → only if the following conditions are met (otherwise inserts →): period is included in the pel-erlang-electric-keys user-option value point is inside code and dash does not follow \$, as in \$- Insert a comma character and possibly: a new indented line when the comma is at the end of an Erlang expression. a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert , by typing M-1 , Insert a semicolon character and possibly a function clause head prototype on the next line. Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line. Inserts a function clause head prototype when the selection criteria ide		
• indent next line Electric < • ∑	<pre>M-1 > / M-1 , * * <kp-subtract> * <deletechar> • <\subsetem > * To disable this, set variable</deletechar></kp-subtract></pre>	The electric behaviour of the electric behaviour of the electric-comma erlang-electric-newline (t): makes it behave electric-lit & electric electri	 Should the current line begin with a comment, and the variable 'comment-multi-line' be nonnil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. his key is controlled by 2 variables: inds must include the erlang-electric-newline symbol to activate the key electric behaviour. e-criteria identifies how to check whether newline should behave electric. By default, the value is circi as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: →> force new line and indent. With PEL, you can also type →> without electric behaviour by typing →. See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert →> when typing → only if the following conditions are met (otherwise inserts → .): period is included in the pel-erlang-electric-keys user-option value point is inside code and dash does not follow \$, as in \$- Insert a comma character and possibly: a new indented line when the comma is at the end of an Erlang expression. a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert , by typing M-1 , Insert a semicolon character and possibly a function clause head prototype on the next line. Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line. Insert a function clause head prototype when the selection criteria iden		
indent next line Electric <	M-1 > . M-1 , 	The electric behaviour of the erlang-electric-comma erlang-electric-newline (t): makes it behave electric-lit & erlang-electric-lit & erlang-electric-git & erlang-electric-git & erlang-electric-git & erlang-electric-git & erlang-electric-geriod & erlang-electric-comma & erlang-electric-comma & erlang-electric-semicolon & erlang-electric	 Should the current line begin with a comment, and the variable 'comment-multi-line' be nonnil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. lisk ey is controlled by 2 variables: mds must include the erlang-electric-newline symbol to activate the key electric behaviour. c-criteria identifies how to check whether newline should behave electric. By default, the value is stric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: → force new line and indent. With PEL, you can also type → without electric behaviour by typing → . See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert → when typing → . only if the following conditions are met (otherwise inserts → .): period is included in the pel-erlang-electric-keys user-option value point is inside code and dash does not follow \$, as in \$- Insert a comma character and possibly: a new indented line when the comma is at the end of an Erlang expression. a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert , by typing M-1 , Insert a semicolon character and possibly a function clause head prototype on the next line. Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line. Behaves like t		
indent next line Electric < ∑	M-1 > . M-1 , . * - * <kp-subtract> * <deletechar> * \boxtimes * To disable this, set variable * When killing, the killed text i</deletechar></kp-subtract>	The electric behaviour of ti erlang-electric-comma erlang-electric-newline '(t): makes it behave electric-lt &optional ARG) (erlang-electric-gt &optional ARG) (pel-erlang-electric-period &optional arg) (erlang-electric-comma &optional ARG) (erlang-electric-semicolon &optional ARG) • erlang-electric-semicolon &optional ARG) • erlang-electric-semicolon &optional ARG) (delete-forward-char N &optional KILLFLAG) delete-active-region' to nil. s filltered by 'filter-buffer-sub	 Should the current line begin with a comment, and the variable 'comment-multi-line' be nonnil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. nisk ey is controlled by 2 variables: nids must include the erlang-electric-newline symbol to activate the key electric behaviour. c-criteria identifies how to check whether newline should behave electric. By default, the value is stric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. Electric behaviour: → force new line and indent. With PEL, you can also type → without electric behaviour by typing →. See below. Disable electric behaviour for this character: Just insert > by typing M-1 > Insert → when typing → only if the following conditions are met (otherwise inserts →): period is included in the pel-erlang-electric-keys user-option value point is inside code and dash does not follow \$, as in \$- Insert a comma character and possibly: a new indented line when the comma is at the end of an Erlang expression. a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. Disable electric behaviour for this character: Just insert , by typing M-1 , Insert a semicolon character and possibly a function clause head prototype on the next line. Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.		
Electric <	M-1 > / M-1 , * * <kp-subtract> * <deletechar> * When killing, the killed text if * <deletechar> * If the delimiter does not form</deletechar></deletechar></kp-subtract>	The electric behaviour of the electric behaviour of the electric-comma erlang-electric-newline (t): makes it behave electric-lit & electric electri	 Should the current line begin with a comment, and the variable 'comment-multi-line' be non-nil, a new comment start is inserted. Should the previous command be another electric command we assume that the user pressed newline out of old habit, hence we will do nothing. isk ey is controlled by 2 variables: unds must include the erlang-electric-newline symbol to activate the key electric behaviour. e-criteria identifies how to check whether newline should behave electric. By default, the value is ctric as soon as the erlang-electric-commands list includes erlang-electric-newline. Insert a less-than sign, and optionally mark it as an open paren. When smartparens-mode is active << automatically inserts the closing pair. Insert a greater-than sign, and optionally insert a new line and indent. **Electric behaviour** → Force new line and indent. **Electric behaviour** → Force new line and indent. **Electric behaviour** for this character: Just insert > by typing → See below. **Disable electric behaviour for this character: Just insert > by typing M → 1 Insert → when typing → only if the following conditions are met (otherwise inserts → .): **period is included in the pel-erlang-electric-keys user-option value **point is inside code and dash does not follow \$, as in \$ → Insert a comma character and possibly: ** a new indented line when the comma is at the end of an Erlang expression. ** a space if inside a block and pel-erlang-space-after-comma-in-block user-option is on. **Disable electric behaviour for this character: Just insert , by typing M → 1 Insert a semicolon character and possibly a function clause head prototype on the next line. ** Behaves like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on t		

<u>Description</u>	<u>Keystroke</u>	Function	Note		
Standard delete backward character	• DEL • ☑	(backward-delete-char- untabify ARG &optional KILLP)	Delete characters backward, changing tabs into spaces. Delete ARG chars, and kill (save in kill ring) if KILLP is non-nil. Interactively, ARG is the prefix arg (default 1) and KILLP is t if a prefix arg was specified. The exact behavior depends on 'backward-delete-char-untabify-method'.		
Delete backward, jump over block pair until block is empty then delete block	• DEL • ≪	(sp-backward-delete- char &optional ARG)	Same as above with the <u>additional behaviour</u> : If on a closing delimiter, move backward into balanced expression. If on an opening delimiter, refuse to delete unless the balanced expression is empty, in which case delete the entire expression.		
<u>XX Smartparens</u> with smartparens- mode active	 If the delimiter does not form a balanced expression, it will be deleted normally. With a numeric prefix argument N = 0, simply delete a character backward, without regard for delimiter balancing. If ARG is raw prefix argument C-u, delete characters backward until an opening delimiter whose deletion would break the proper pairing is hit. 				
Erlang Comments • Erlang Programming Rules & Conventions See also: ▼ Comments	Erlang uses the % character to identify line comments. It uses the following conventions: • % - Single percent characters for comments located toward the end of a line of code • %% - Two percent characters are used for comments starting at indentation level. • %%% - Three percent characters are used to describe modules and are always placed in the first column The location of the comment inside a code line is controlled by the comment-column variable. Set it with comment-set-column, bound to C-x;				
Comment/un-comment					
PEL extension of comment-dwim specialized for Erlang. Automatically uses the		(pel-erlang-comment- dwim &optional ARG)	Does the same but adds ability to insert %%% comments. It does that on the very first line in the buffer and lines that follow a line that starts with %%% .		
%%% comment when appropriate. ★★ Note:	With marked un-commente With marked commented re	On first en On line wit d region: Comment region gion: Un-comments the			
• M-; works much better than C-c C-c			However PEL uses M-1 for something else.		
and C-c C-u PEL maps M-; to pel-erlang-comment- dwim which works even better.	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region. • With just C-u prefix arg, uncomment each line in region BEG END. • Numeric prefix ARG means use ARG comment characters. • If ARG is negative, delete that many comment characters instead.		
See also: Comments	By default, the 'comment-s	start' markers are inserted a	d 'comment-padding'; the comment end by 'comment-end' and 'comment-padding'. at the current indentation of the region, and comments are terminated on each line (even for and blank lines do not get comments). This can be changed with 'comment-style'.		
Un-comment region	C-c C-u	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region. The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.		
Toggle display of comments in buffer or active region	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active, then toggle comments in the region. Otherwise, in the whole buffer. • Requires the hide-comnt.el package PEL activates it with pel-use-hide-comnt		
Filling Text See also: Filling/Justification	Filling Erlang code does The pel-erlang-fill-column	not work as it treats code as sets the fill-column variable f11> t f ? shows its val	buffer: code and comment. The auto-fill command will automatically wraps code and comments. s normal text. But filling comment paragraphs is useful. le to control where text wraps in Erlang buffers. lue. Use set-fill-column (C-x f) to set it. 11> 8.		
Fill current paragraph	• M-q • <f11> t f p</f11>				
Hard Tabs Rendering See also: ∑ Indentation Hard Tab Display Rendering	Like most programming languages, you can use hard tabs and spaces as horizontal whitespace in the Erlang source code. • Emacs supports all variations of styles: spaces only and mix of hard-tabs and spaces. Using only hard-tabs in Erlang is possible but rare. Some people use hard-tabs for indentation and extra spaces for alignment. Emacs supports all of these styles. • Emacs provides commands to convert code to remove all hard-tabs (untabify) and replace as many spaces as possible with hard tabs (tabify). • The tab-width user-option controls the visual rendering of hard tabs not the indentation level. • PEL provides an Erlang specific user option for hard-tab: pel-erlang-tab-width user-option. • PEL also provides the following command to dynamically modify the tab width rendering in the current buffer.				
Set visual rendering of hard tabs for the current buffer See <u>National Indentation</u>	<f11> M-t</f11>	(pel-set-tab-width N)	Change the tab width of the current buffer, only affecting the display rendering of hard tabs inserted in the buffer text. Prompts for a new value in the [2, 8] range. • This modifies a buffer local value of the the tab-width user-option. • The change is temporary and affects the current buffer only. • To change the tab width used for all Erlang source code files, change the 'pel-erlang-tab-width' user-option variable instead.		
Hard Tab Insertion	The pel-erlang-use-tabs user This sets the Emacs indent		ard tab characters are inserted in Erlang source code when Emacs inserts indentation whitespace. ers.		
Indentation indentation			the erlang-mode logic and several user-options in the erlang group. See ** indentation . ed at the end of this list. They are also listed in the ** Indentation table.		
Indent current line or region	<tab></tab>	(indent-for-tab- command &optional ARG)	Indent active region, current line, or block starting on this line: performs syntactic indentation. • The indentation level is controlled by the erlang-indent-level user-option. Its default is 4. • Access its custom group buffer using <f12> <f3> 1</f3></f12>		
See also: Indentation Erlang Guidelines: Ericsson AB: try to limit most code to 2 levels of indentation. Inaka: indentation level = 2 space chars.	 In Transient Mark mode, when the region is active, reindent the region. Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line. Otherwise reindent just the current line. You can type <tab> anywhere in the line to indent the current line or everything in the marked area if a block is marked.</tab> Note that the erlang.el logic doubles the indentation label inside funs. See this S.O. discussion on that. To indent rigidly you can use: (pel-indent-rigidly &optional N) (bound to C-x <tab> and to <f11> <tab><tab><tab>) to indent the line or region rigidly.</tab></tab></tab></f11></tab> (tab-to-tab-stop), bound to M-i to insert spaces to the next tab stop column. 				
Indent complete buffer	<f12> <tab></tab></f12>	(erlang-indent-current- buffer)	Indent current buffer as Erlang code. • Works on the entire buffer, even if it is narrowed.		
Indent Erlang function	C-c C-q <f12> f <tab></tab></f12>	(erlang-indent-function)	Indent current Erlang function. Point can be located anywhere inside the function.		
Indent function clause	<f12> c <tab></tab></f12>	(erlang-indent-clause)	Indent current Erlang clause. Point can be located anywhere in the Erlang clause.		
Indent lines of list after point	С-М-q	(prog-indent-sexp &optional DEFUN)	Indent the expression after point. See also: <u>∑ Indentation</u> When interactively called with prefix, indent the enclosing function instead.		
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region. • A numeric prefix argument specifies a column: indent each line to that column.		
	With no prefix argument, the command chooses one of these methods and indents all the lines with it: 1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it. 2. If 'indent-region-function' is non-nil, call that function to indent the region. 3. Indent each line via 'indent-according-to-mode'.				

When a region is marked you can also use the simple **<tab>** to do the same when syntactic-indentation is active.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Outline Erlang			the Erlang buffer into an outline of function definitions.
Code See <u>▶ Outline</u> for all key bindings	Once the minor mode is active you can collapse and expand code as outlines and navigate using the outline commands. See the key bindings in <u>Soutline</u> . This is very useful to quickly see an outline of the code in a large file. Using the outline-hide-other is particularly effective. PEL binds the outline commands under the <f2> key prefix when the outline-minor-mode is active. Two useful key bindings are shown below.</f2>		
Toggle outline minor	<f11> M-1</f11>	(outline-minor-mode	Toggle Outline minor mode.
mode		&optional ARG)	Enable with a prefix positive argument ARG, disable with negative argument. Itide a constitute a great positive and appear and top level headings.
Hide other Show all	• <f2> o</f2>	(outline-hide-other) (outline-show-all)	Hide everything except current body and parent and top-level headings. This also unhides the top heading-less body, if any. Show all of the text in the buffer.
Navigation in	-	,	Erlang source code. PEL complements these. And EDTS also.
Erlang code See also: • <u>Navigation</u> • Moving by Defuns	Several commands are specia Notice the 3 sets of commands 1. <f12> <up> and <: 2. The standard navigating 3. The <f12> <u-curve are="" below="" describe="" list="" of="" specified.<="" specifies="" td="" the="" where=""><td>lization of the normal navigands: f12> <down> move to the commands, (mapped to sor> commands (also acceptailized commands only. So shown below are available.</down></td><td>ition commands which are described in the table Navigation, but several are specific to Erlang: Ne beginning of Erlang functions skipping all compiler directives. From the beginning of Erlang functions skipping all compiler directives. From the beginning of Erlang functions but stop at compiler directives. Seesible via M-f12 M-cursor, move across Erlang clauses (as opposed to functions). See the others inside Navigation, like the navigation by blocks. In erlang-mode. Their global equivalent is f11 SPC e. It is not always shown for brevity. It position. The start position is shown as with following positions as to to to the start position is shown as with following positions as the second commands are second commands.</td></u-curve></f12></up></f12>	lization of the normal navigands: f12> <down> move to the commands, (mapped to sor> commands (also acceptailized commands only. So shown below are available.</down>	ition commands which are described in the table Navigation , but several are specific to Erlang: Ne beginning of Erlang functions skipping all compiler directives. From the beginning of Erlang functions skipping all compiler directives. From the beginning of Erlang functions but stop at compiler directives. Seesible via M-f12 M-cursor , move across Erlang clauses (as opposed to functions). See the others inside Navigation , like the navigation by blocks. In erlang-mode. Their global equivalent is f11 SPC e . It is not always shown for brevity. It position. The start position is shown as with following positions as to to to the start position is shown as with following positions as the second commands are second commands.
By <u>Function</u>	Move to next/previous funct	ion beginning/end at/skippi	ng compiler directives. Skips clauses.
to start of function	Move to beginning of fun	ction	
Go backward to beginning of	• <f12> <up> • <f12> f p</f12></up></f12>	(pel-previous-erl- function &optional N)	Move backward to the beginning of the previous function skipping all compiler directives. Moves point to the first character of the function name.
previous function	• <f11> SPC e <up> • <f11> SPC e f p</f11></up></f11>		 With prefix argument N repeat N times. Pushes mark; move back to previous position with M-\[^\]. Shift marking is available for the key sequence using a cursor key.
	C-c C-d C-b	(ferl-goto-previous- function)	Move backward to the beginning of the previous function. • Skips all compiler directives. • Requires EDTS 2 PEL activates it with pel-use-edts (set to t or start-automatically).
Go forward to beginning of next function	• <f12> <down> • <f12> f n</f12></down></f12>	(pel-next-erl-function &optional N)	Move forward to the beginning of the next function skipping all compiler directives. Moves point to the first character of the function name. With prefix argument N repeat N times.
	• <f11> SPC e <down> • <f11> SPC e f n</f11></down></f11>		 Pushes mark; move back to previous position with M-\. Shift marking is available for the key sequence using a cursor key.
	C-c C-d C-f	(ferl-goto-next-function)	Move forward to the beginning of the next function. • Skips all compiler directives. • Requires EDTS 2 PEL activates it with pel-use-edts (set to t or start-automatically).
 to start of function/ directive 	Move to beginning of function or compiler directive		
 Go backward to beginning of 	<f12> f P</f12>	(beginning-of-defun &optional ARG)	Move backward to the beginning of an Erlang function or compiler directive. • With ARG, do it that many times. Negative ARG means move forward to the ARGth following
previous: function compiler directive	• C-M-a • C-M- <home> • <f6> p • <f6> <up> • <f11> SPC e f P</f11></up></f6></f6></home>	(erlang-beginning- of-function &optional ARG)	beginning of defun. ➡Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However <f6> p and <f6> <up> handle Shift-marking fine in terminal mode. ➡Erlang.el man page indicates an invalid mapping for this.</up></f6></f6></home>
Go forward to	<f12> f N</f12>	(pel-beginning-of-next-	
beginning of next:	• <f6> n • <f6> <down> • <f11> SPC e f N</f11></down></f6></f6>	defun &optional SILENT DONT-PUSH_MARK)	 Beeps if does not find beginning of next function unless SILENT is non-nil. If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. Move back to previous position with M-\[^\circ\]. Shift marking is available for the <f6> bindings.</f6>
to end of function	Move to end of function or compiler directive		
Backward to end of previous: function compiler directive	<f6> <left></left></f6>	(pel-end-of-previous- defun &optional SILENT DONT-PUSH_MARK)	Move backwards to line after end of the previous function definition. • Beeps if does not find end of previous function unless SILENT is non-nil. • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M-^. —Shift marking is available for the <f6> bindings.</f6>
Forward to end of next: function compiler	• C-M-e • C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG) (erlang-end-of- function &optional	Move forward to line after end of Erlang function. With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. ➡ Shift marking is available in graphics mode, not in terminal mode (for C−M−e and C−M−
directive By Expression	Note that in Frland every single	ARG)	<end>). However <f6> <right> handle Shift-marking fine in terminal mode. sequence ends with a period. Expressions in expression sequences are separated by commas.</right></f6></end>
functions, etc	The following commands move • They do not move across ex	e to the beginning/end of sir pressions in a sequence of	ngle expression or expression sequence.
Go to beginning of	м-а	(backward-sentence	Go backward to the beginning of an Erlang statement.
statement	<f12> s a</f12>	&optional ARG)	With a numerical argument repeat that many times.
Go to end of statement	M-e <f12> s e</f12>	(forward-sentence &optional ARG)	Go forward to the end of an Erlang statement. • With a numerical argument repeat that many times.
By <u>Function Clause</u>	Move by clauses of a function.	A function definition (state	ment) may have multiple clauses, each separated by a semicolon.
Go backward to beginning of clause	• C-c M-a • <f12> c a • <m-f12> <m-up></m-up></m-f12></f12>	(erlang-beginning-of- clause &optional ARG)	Move backward to previous start of clause. • With argument, do this that many times. **Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.
Go forward to beginning of next clause	• <f12> c n • <m-f12> <m-down></m-down></m-f12></f12>	(pel-beginning-of-next-clause)	Move forward to the beginning of next clause. • Pushes mark; move back to previous position with M−ˆ. ⇒Shift marking is available.
Go backward to end of previous clause	• <f12> c p • <m-f12> <m-left></m-left></m-f12></f12>	(pel-end-of-previous- clause)	Move backward to the end of the previous clause. • Pushes mark; move back to previous position with M−ˆ. ⇒Shift marking is available.
Go forward to end of current clause	• C-c M-e • <f12> c e • <m-f12> <m-right></m-right></m-f12></f12>	(erlang-end-of-clause &optional ARG)	Move to the end of the current clause. • With argument, do this that many times. **Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.

Description	<u>Keystroke</u>	Function	<u>Note</u>		
Block Navigation	 () for function p { } for tuples, re [] for lists " " for strings << >> for binaries a 	s and bitstrings			
See also: •	• Use the <f11> (key so Standard Erlang support provi</f11>	can be activated automatically for Erlang by adding erlang-mode to the pel-erlang-activates-minor-modes user-option. ey sequence to toggle the smartparens-mode on and off. orovide some commands to navigate across and into these balanced blocks. Their name is shown in black in the following rows. ovided by <u>§</u> *** Smartparens when smartparens-mode minor-mode is active. Some are PEL specializations of smartparens code.			
To Block start/end	The following commands mov	e to the beginning or end of	a block, skipping over Erlang terms inside these blocks.		
Go backward to beginning of previous block	• C-M-p	(backward-list &optional ARG)	Move backward to beginning of previous block. • Supports blocks of (), [] and {}. • With ARG, do it that many times.		
Skips terms.			 A negative argument N means forward-list N. This command assumes point is not in a string or comment. -spec ejabberd_started 6() -> ok. ejabberd_started 5() -> gen_server:call 4(?MODULE, ejabberd_started, ?CALL_TIMEOUT). -spec config_reloaded 3() -> ok. config_reloaded 2() -> gen_server:call 1(?MODULE, config_reloaded, ?CALL_TIMEOUT). 		
Go backward to end of previous block Skips terms. ∑x Smartparens with smartparensmode active	<m-f7> p</m-f7>	(pel-sp-previous-sexp &optional ARG)	Move backward to end of previous block. • With ARG, do it that many times. If there is no next expression at current level, jump one level up (effectively doing 'sp-up-sexp'). • A negative argument N means move to the end of N-th following balanced expression. -spec ejabberd_started() 6 -> ok. ejabberd_started() 5 -> gen_server:call(?MODULE, ejabberd_started, ?CALL_TIMEOUT) 4. -spec config_reloaded() 3 -> ok. config_reloaded() 2 -> gen_server:call(?MODULE, config_reloaded, ?CALL_TIMEOUT) 1.0		
Go forward to end of next block Skips terms.	• C-M-n	(forward-list &optional ARG)	Move forward to end of next block. • Supports blocks of (), [] and {}. • With ARG, do it that many times. • A negative argument N means forward-list N. • This command assumes point is not in a string or comment. O-spec ejabberd_started() 1 -> ok. ejabberd_started() 2 -> gen_server:call(?MODULE, ejabberd_started, ?CALL_TIMEOUT) 3. -spec config_reloaded() 4 -> ok. config_reloaded() 5 -> gen_server:call(?MODULE, config_reloaded, ?CALL_TIMEOUT) 6.		
Go forward to beginning of next block Skips terms. ∑X Smartparens with smartparensmode active	<m-f7> n</m-f7>	(pel-sp-next-sexp &optional ARG)	Move forward to beginning of next block (and term if 'sp-navigate-consider-symbols' is set). • With ARG, do it that many times. • If there is no next expression at current level, jump one level up (effectively doing 'sp-backward-up-sexp'). O-spec ejabberd_started 1() -> ok. ejabberd_started 2() -> gen_server:call 3(?MODULE, ejabberd_started, ?CALL_TIMEOUT). -spec config_reloaded 4() -> ok. config_reloaded 5() -> gen_server:call 6(?MODULE, config_reloaded, ?CALL_TIMEOUT).		
By Blocks and Terms See also: X Smartparens	With PEL: to use Esc C- Several Linux distros map change Linux key binding in S	made of pairs of {}, [] and (). Also stops at terms. De Esc C- <left> and Esc C-<right> bindings below, set pel-windmove-on-esc-cursor user-option is set to nil. Stros map C-M-<left> and C-M-<right> to desktop workspace operation. In that case you can either use another key binding or randing in Systems->settings->keyboard->shortcuts to prevent it from using that key sequence. Schaviour of these keys by providing the ability to move across Erlang's << >> bit syntax statement blocks.</right></left></right></left>			
Go backward to beginning of previous term/block	• C-M- <left> • C-[C-b • Esc C-b • Esc C-<left> • C-M-b</left></left>	(pel-erlang-backward- sexp &optional ARG)	Move backward backward to beginning of previous term or block. • With ARG, do it that many times. • A negative arg N means move forward to end of N terms/blocks. • At beginning of block, jump out of the current one. • This command assumes point is not in a string or comment. • C-M-p : ► Shift marking is available in graphics mode, not in terminal mode. • C-M-b : ► Shift marking is available in graphics mode, not in terminal mode. • C-M- <left> : ► Shift marking works with this command. • C-M-<left> does not work on Windows, but H-<left> works.</left></left></left>		
with smartparens with smartparens-mode active:	• C-M-b • <m-f7> b</m-f7>	(sp-backward-sexp &optional ARG)	Same as above with the additional behaviour: • With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default. • When it is nil, point only stops at 1, 4, 6 and 9: it jumps over terms. -spec ejabberd_started() -> ok. ejabberd_started() -> gen_server:call 9(?MODULE, ejabberd_started, ?CALL_TIMEOUT). -8 spec 7config_reloaded 6() -> 5 ok. 5 config_reloaded 4() -> 3 gen_server: 2 call 1(?MODULE, config_reloaded, ?CALL_TIMEOUT).0 Inside a block:		
			gen_server:call(?3MODULE, 2ejabberd_started, ?1CALL_TIMEOUT0).		

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Go forward to end of next term/block	• C-M- <right> • C-[C-f • Esc C-f • Esc C-<right> • C-M-f</right></right>	(pel-erlang-forward- sexp &optional ARG)	Move forward to end of term or block. • With ARG, do it that many times. • A negative argument N means move backward to beginning of previous term or block. • At end of block, jump out of the current one. • C-M-n : ► Shift marking is available in graphics mode, not in terminal mode. • C-M-f : ► Shift marking is available in graphics mode, not in terminal mode. • C-M- <right> : ► Shift marking works with this command. • C-M-<right> does not work on Windows, but H-<right> does.</right></right></right>
 X Smartparens with smartparens- mode active: C-M-f and <m- f7=""> f use sp- forward-sexp,</m-> others are using forward-sexp 	• C-M-f • <m-f7> f</m-f7>	(sp-forward-sexp &optional ARG)	Same as above with the additional behaviour: • With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default. • When it is nil, point only stops at 3, 6 and 9 it jumps over terms. O-spec1 ejabberd_started2()3 -> ok4. ejabberd_started5()6 -> gen_server7:call3(?MODULE, ejabberd_started, ?CALL_TIMEOUT)9. -spec10 config_reloaded() -> ok. config_reloaded() -> gen_server:call(0?MODULE1, config_reloaded2, ?CALL_TIMEOUT3).
Into block	Navigate inside nested blocks	of elements with the follow	
Into block forward	C-M-d	(down-list &optional	Move forward to the beginning of inner element of a block.
into block forward	C-M-u	ARG)	With ARG, do this that many times.
• <u>Sx Smartparens</u> with smartparens- mode active	• C-M-d • <m-f7> d</m-f7>	(sp-down-sexp &optional ARG)	 A negative argument N means move backward but still go down a level. If ARG is raw prefix argument C-u, descend forward as much as possible. If ARG is raw prefix argument C-u C-u, jump to the beginning of current list. If the point is inside block and there is no down expression to descend to, jump to the beginning of current one. If moving backwards, jump to end of current one. music_info() -> [1{2error, {3noreply, State}},
Into block backward • <u>Sx Smartparens</u> with smartparens- mode active	• <m-f7> z • C-M-z</m-f7>	(sp-backward-down- sexp &optional ARG)	Move backward down one level to end of block element. With ARG, do this that many times. A negative argument N means move forward but still go down a level. If ARG is raw prefix argument C-u, descend backward as much as possible. If ARG is raw prefix argument C-u C-u, jump to the end of current list. If the point is inside sexp and there is no down expression to descend to, jump to the end of current one. If moving forward, jump to beginning of current one. music_info(1) -> O{{error, {noreply, State}},
to edge of block			
To beginning of block • <u>SX Smartparens</u> with smartparens- mode active	• <m-f7> a</m-f7>	(sp-beginning-of-sexp &optional ARG)	Jump to beginning of the block the point is in. The beginning is the point after the opening delimiter. With no argument, this is the same as C-u C-u 'sp-down-sexp' With ARG positive N > 1, move forward out of the current expression, move N-2 expressions forward and move down one level into next expression. With ARG negative N < 1, move backward out of the current expression, move N-1 expressions backward and move down one level into next expression. With ARG raw prefix argument C-u move out of the current expressions and then to the beginning of enclosing expression. music_info() -> {{error, {noreply, State}}, {good, {{ vear, 19074}, example {group, "lcontract0ion"}, example {song, "Sam M'Madown"}, {song, "A la claire fontaine"}, {song, "L'alarme à l'oeil"}, {song, "La bourse ou la vie"}0] example {rating, excellent}}}
To end of current block • forward • ∑X Smartparens with smartparens- mode active	<m-f7> e</m-f7>	(sp-end-of-sexp &optional ARG)	Jump to end of the current block. • With no argument, this is the same as calling C-u C-u 'sp-backward-down-sexp'. • With ARG positive N > 1, move forward out of the current expression, move N-1 expressions forward and move down backward one level into previous expression. • With ARG negative N < 1, move backward out of the current expression, move N-2 expressions backward and move down backward one level into previous expression. • With ARG raw prefix argument C-u move out of the current expressions and then to the end of enclosing expression. music_info() -> {

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Out of block			
Out block forward forward	C-M-] • C-M-] • <m-f7>]</m-f7>	(up-list &optional ARG ESCAPE-STRINGS NO- SYNTAX-CROSSING) (sp-up-sexp &optional ARG INTERACTIVE)	Move forward out of one level of block parens. With ARG, do this that many times. A negative argument means move backward but still to a less deep spot. If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between end of the expression and the last "thing" inside the expression.
X Smartparens with smartparens- mode active			This behaviour can be suppressed for syntactic string blocks by setting 'sp-navigate-reindent-after-up-in-string' to nil. If 'sp-navigate-close-if-unbalanced' is non-nil, close the unbalanced expressions automatically. music_info() ->
			{{erOror, {noreply, State}}1, example {goOod, {{year, 1974}, example {group, "Contraction"}, [{song, "Sam M'Madown"}, {song, "A la claire fontaine"}, {song, "L'alarme à l'oeil"}, {song, "La bourse ou la vie"}] {rating, excellent}}}1}.
Out block backward • backward	• <m-f7> u • C-M-u</m-f7>	(sp-backward-up-sexp &optional ARG INTERACTIVE)	Move backward out of one level of block parens. With ARG, do this that many times. A negative argument means move forward but still to a less deep spot. If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between beginning of the expression and the first "thing" inside the
<u>X Smartparens</u> with smartparens- mode active			expression. music_info() ->
Move over space	Current implementation of	sp-forward-symbol and sp- tegrated PEL implement wo	Rage and required smartparens-mode minor-mode to be active. **Deackward-symbol stop inside comments. I consider this a bug so I reported and submitted a price or stop inside comments: pel-sp-forward-symbol and pel-sp-gruntil the fix is integrated.
To beginning of next symbol/block	<m-f7> SPC n</m-f7>	(sp-skip-forward-to- symbol &optional STOP- AT-STRING STOP-	Skip whitespace and comments moving forward. • If STOP-AT-STRING is non-nil, stop before entering a string (if not already in a string). • If STOP-AFTER-STRING is non-nil, stop after exiting a string.
<u>X Smartparens</u> with smartparens- mode active		AFTER-STRING STOP-INSIDE-STRING)	<pre>• If STOP-INSIDE-STRING is non-nil, stop before exiting a string. start_app(App) -> 0</pre>
To end of next symbol or block • <u>∑X Smartparens</u> with smartparensmode active	<m-f7> SPC m</m-f7>	(pel-sp-forward-symbol &optional ARG)	Move point to the next position that is the end of a symbol. With ARG being positive number N, repeat that many times. With ARG being negative number -N, repeat that many times in backward direction. A symbol is any sequence of characters that are in either the word constituent or symbol constituent syntax class. Current symbol only extend to the possible opening or closing delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax classes.
See **** inote above.			<pre>start_app(App) -> % first clause start_app(App0, temporary1). start_app(App0, Type1) -> % second clause StartFlag2 = not3 is_loaded4(),</pre>
			start_app 5 (App 6, Type 7, StartFlag 8).
To beginning of previous •	<m-f7> SPC p</m-f7>	(pel-sp-backward- symbol &optional ARG)	Move point to the next position that is the beginning of a symbol. With ARG being positive number N, repeat that many times. With ARG being negative number -N, repeat that many times in forward direction. A symbol is any sequence of characters that are in either the word constituent or symbol constituent syntax class. Current symbol only extend to the possible opening or closing delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax classes.
See inote above.			<pre>8start_app(7App) -> % first clause 6start_app(5App, 4temporary). 3start_app(2App, 1Type) -> % second clause 0startFlag = not is_loaded(), ctart_app(App, Type StartFlag)</pre> <pre></pre>
Skip forward past whitespace	<m-f7> SPC .</m-f7>	(sp-forward-whitespace &optional ARG)	start_app(App, Type, StartFlag). Skip forward past the whitespace characters. • With non-nil ARG return number of characters skipped.
X Smartparens with smartparens- mode active			<pre>start_app(App) -> 0</pre>
Skip backward past	<m-f7> SPC ,</m-f7>	(sp-backward-	<pre>StartFlag = not is_loaded(), start_app(App, Type, StartFlag).</pre> Skip backward past the whitespace characters.
whitespace • \(\sum x \) Smartparens with smartparens-		whitespace &optional ARG)	 With non-nil ARG return number of characters skipped. start_app(App) -> 1 start_app(App, temporary).
mode active			<pre>start_app(App, Type) -> % second clause1 OStartFlag = not is_loaded(), start_app(App, Type, StartFlag).</pre>
			7

Description	<u>Keystroke</u>	Function	<u>Note</u>	
Completion	Completion is available from various sources. • Without help from EDTS or LSP, the ivy-erlang-complete external package parses the Erlang libraries to identify the supported functions. • ivy-erlang-complete external package activated by pel-use-ivy-erlang-complete user-option. • Requires a version of Erlang installed that supports Erlang escript. • ivy-erlang-complete replies on GNU sed, which is not accessible on macOS by default. • Install gnu-sed with Homebrew. I provided a patch which solves the problem by detecting macOS and using gsed instead of sed.			
Hippie Expand Abbreviation See also: Hide/Show	M-/	(hippie-expand ARG)	 Try to expand text before point, using multiple methods. Not an Erlang completion command but it can be useful to pick up names present in the files. The expansion functions in 'hippie-expand-try-functions-list' are tried in order, until a possible expansion is found. Repeated application of 'hippie-expand' inserts successively possible expansions. With a positive numeric argument, jumps directly to the ARG next function in this list. With a negative argument or just C-u, undoes the expansion. 	
Completion of Erlang code at point.	<f12> . C-:</f12>	(ivy-erlang-complete)	Erlang completion at point. Aware of Erlang modules and functions for the currently used Erlang version identified by the ivy-erlang-complete-erlang-root user-option which is adjusted to the erlang-root-dir ivy-erlang-complete replies on GNU sed, which is not accessible on macOS by default. To solve the problem you must install gnu-sed with Homebrew since ivy-erlang-complete shell scripts use gsed instead of sed.	
Open web-based Erlang standard library documentation for function at point	• <f12> M-h • C-c C-h</f12>	(ivy-erlang-complete- show-doc-at-point)	Show web-based Erlang standard library documentation for function at point.	
Set a different root for Erlang project	• <f12> M-e • C-c C-e</f12>	(ivy-erlang-complete- set-project-root)	Set root for current project for ivy-erlang-complete. To see the current value of the ivy-erlang-complete-project-root, type <f12> ?</f12>	
Cross Reference navigation See <u>▼ Xref</u>	Erlang cross reference navigation, that uses the M- key to move to the definition of the thing at point, is supported by several tools: • The xref-based cross reference tools with the following backends: • etags (with etags or CTags generated tags file), use etags-erl shell script to create a TAGS file in the directory root to use with etags. • image: Global/gtags with ggtags. Source the envfor-gtags shell script to set up your shell before starting Emacs to use gtags. • You must install GNU Global for this. See PEL manual installation instructions for GNU Global. • With PEL set pel-use-ggtags user-option to t to install the Emacs-side support ggtags package and activate the gtags commands. • With PEL set pel-use-ggtags user-option to t to install the Emacs-side support ggtags package and activate the gtags commands. • Image: GNU Global for this. See PEL manual installation instructions for GNU Global. • With PEL set pel-use-ggtags user-option to t to install the Emacs-side support ggtags package and activate the gtags commands. • Image: GNU Global for this. See PEL manual installation instructions for GNU Global. • Other specialized tools for Erlang: • Other specialized tools for Erlang: • Image: GNU Global for this. See PEL manual installation instructions for GNU gellobal. • Other specialized tools for Erlang: • Image: GNU Global for this. See PEL manual installation instructions for GNU gellobal. • Image: GNU Global for this. See PEL gellobal for GNU gellobal. • Image: GNU Global for this. See PEL gellobal for GNU gellobal for this. • Image: GNU Global for GNU gellobal for this. • Image: GNU Global for GNU gellobal for this. • Image: GNU Global for GNU gellobal for this gellobal for			
Find definition of identifier at point	м	(xref-find-definitions IDENTIFIER)	Grab symbol at point and move cursor to its definition. • If there are more than one match, prompt in the "xref" buffer. • To search for a symbol entered manually, type C-u M	
***			See <u>Xref</u> for commands to select the backends	
Go back to where M was last issued	м-,	(xref-pop-marker-stack)	 Pop back to where M was last invoked. Marker depth is controlled by the xref-marker-ring-length user option. 	
Find definition of identifier at point See also: ∑ Xref	• <f12> M • M</f12>	(ivy-erlang-complete- find-definition)	Find erlang definition.	
	• <f12> M-? M-?</f12>	(ivy-erlang-complete- find-references)	Find erlang references. • Use M-, to go back to original location.	
	• <f12> M-f • C-c C-f</f12>	(ivy-erlang-complete- find-spec)	Find spec at point. It also find callback definition.	
	• <f12> M-o • C-c C-o</f12>	(ivy-erlang-complete-find-file)	Open file at point. Find file in current project.	
Marking See also: <u>∑ Marking</u>	The first 2 command listed if For those 2 commands the	pelow are Erlang-mode spen ne Erlang.el man page in	ind described in the Marking table. cific marking functions. dicates an invalid mapping for this. Reported as ERL-1314. cement to erlang syntax table supporting the < > pair therefore it is also mentioned here.	
Mark Erlang function	• C-M-h • <f12> f m</f12>	(mark-defun & optional ARG) (erlang-mark-function & optional ARG)	Put mark at end of this function, point at beginning. The function marked is the one that contains point or follows point. With positive ARG, mark this and that many next functions; with negative ARG, change the direction of marking.	
Mark Erlang Clause	• C-c M-h • <f12> c m</f12>	(erlang-mark-clause)	If the mark is active, it marks the next or previous function(s) after the one(s) already marked. Put mark at end of clause, point at beginning.	
Mark region by semantic unit, increase marked region on each invocation.	• M-= • <f11> . =</f11>	(er/expand-region ARG)	Increase selected region by semantic units. Requires the expand-region package, activated by pel-use-expand-region user option.	
★ Powerful command Works best with superword-mode on. • See <u>Nature</u> Text Modes	 With prefix argument expands the region that many times. If prefix argument is negative calls 'er/contract-region'. If prefix argument is 0 it resets point and mark to their state before calling 'er/expand-region' for the first time. This command is very powerful: the first time it's typed it selects a word, if you type it again it will expand the selection, and again, and again. The expansions follow the semantics of the current major mode: it uses syntactic information from the major mode. Once M-= is typed, you can quickly type the following single keys in sequence: = to expand the region, - to contract the region, 0 to reset the operation. If you wait too long, then you have to use M-= again to continue the expansion, otherwise the region is de-activated. 			
	Note that you can also use the following key chords to control the contraction of the selected text without having to worry about time: • M— M—= to contract the region • M—0 M—= to reset the operation. • You can also use the cursor keys to expand or contract the region and C—x C—x to exchange mark and point to expand the other side of the region cursors.			

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Copy and Clone • ∑x Smartparens			cloning operations. They are provided by Smartparens lay the copied string when pel-show-copy-cut-text is t. Toggle this display with <f11> M-=</f11>
Copy current & forward block(s)	<m-f7> =</m-f7>	(sp-copy-sexp &optional ARG)	Copy the following ARG expressions to the kill-ring. This is exactly like calling 'sp-kill-sexp' with second argument t. All the special prefix arguments work the same way.
Copy previous block(s)	<m-f7> M-=</m-f7>	(sp-backward-copy- sexp &optional ARG)	Copy the previous ARG expressions to the kill-ring. This is exactly like calling 'sp-backward-kill-sexp' with second argument t. All the special prefix arguments work the same way.
clone current block	<m-f7> c</m-f7>	(sp-clone-sexp)	Clone sexp after or around point. If the form immediately after point is a sexp, clone it below the current one and put the point in front of it. Otherwise get the enclosing sexp and clone it below the current enclosing sexp.
Transform code	The following commands can	be used to help transform c	ode. Some need external packages.
iEdit mode \$2 See also: ∑ Highlight	iEdit Mode - Edit multiple ins Programme Requires the iedit external		s simultaneously.
Toggle iedit mode See also: • <u>∑ Cursor</u> • <u>∑ Search/Replace</u>	• C-; • <f11> e • <f11> h i • <f11> m i</f11></f11></f11>	(iedit-mode &optional ARG)	Toggle iEdit mode: edit all symbols in scope or region simultaneously. ⚠ Both iEdit and Flyspell use the C-; key as their default binding. • PEL detects and reports that situation: modify the binding of one of them if you see it. ➤ See ∑ Search/Replace where all the iedit-mode commands are described.
Align arrows inside region	C-c C-a	(erlang-align-arrows START END)	Align arrows ("->") in function clauses inside marked region or in the current function. • With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to point), not just those in function clauses.
		sum([H T], Sum) -> sum([], Sum) -> Sum. To align something else	After C-c C-a: sum(L, 0). sum(L) -> sum(L, 0). sum(T, Sum + H); sum([H T], Sum) -> sum(T, Sum + H);
Transpose block elements	<m-f7> t</m-f7>	(sp-transpose-sexp &optional ARG)	Transpose the expressions around point. • The operation will move the point after the transposed block, so the next transpose will "drag" it forward.
Smartparens with smartparens- mode active			 With arg positive N, apply that many times, dragging the expression forward. With arg negative -N, apply N times backward, pushing the word before cursor backward. This will therefore not transpose the expressions before and after point, but push the expression before point over the one before it. Before (for all following examples): Alist = [1, 2, 3, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]]. After <-f7> t: AList = [1, 2, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]]. After M-2 <-f7> t: AList = [1, 2, [10,11,12,[22,33,44]], 5, 3, 6, 7, 8,[]]. Before (for all following examples): AList = [{first,[1, 2, 3]}, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]]. After <-f7> t: AList = [[10,11,12,[22,33,44]], 5, {first,[1, 2, 3]}, 6, 7, 8,[]]. Before (for all following examples): AList = [{first,[1, 2, 3]}, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]]. Before (for all following examples): AList = [{first,[1, 2, 3]}, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]]. After M <m-f7> t: AList = [{first,[1, 3], 2]}, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]].</m-f7>
Push current block after next • <u>§</u> £ Smartparens with smartparens-	<m-f7> s</m-f7>	(sp-push-hybrid-sexp)	Push the hybrid sexp after point over the following one. Before: Alist = [1, 2, 3, Alist = [1, 2,
mode active			5, 6, 7, 8,[]]. [10,11,12,[22,33,44]]].
Transform - barf Eject next element(s) out of current block • <u>Sx Smartparens</u> with smartparens- mode active	Eject next element(s) out of current block • ∑X Smartparens with smartparens-		Remove the last sexp in the current list by moving the closing delimiter. If ARG is positive number N, barf that many expressions. If ARG is negative number -N, contract the opening pair instead. If ARG is raw prefix C-u, barf all expressions from the one after point to the end of current list and place the point before the closing delimiter of the list. If the current list is empty, do nothing.
<u>ae</u>		smartparens by itself fails to process these examples properly. PEL fixes the issues with post processing.	Before: AList = [[1, 2, 3, 4]]. Before: AList = [[1, 2, 3, 4]]. After M-2 < M-f7> /: AList = [[1, 2, 3, 4]]. After M-2 < M-f7> /: AList = [[1, 2], 3, 4]. After M < M-f7> /: AList = [[1, 2, 3, 4]]. After M < M-f7> /: AList = [[1, 2, 3, 4]].
Eject previous element(s) out of current block	<m-f7> M-/</m-f7>	(sp-backward-barf-sexp &optional ARG)	This is exactly like calling 'sp-forward-barf-sexp' with minus ARG. In other words, instead of contracting the closing pair, the opening pair is contracted. For more information, see the documentation of 'sp-forward-barf-sexp'.
S Smartparens with smartparens- mode active		This command works fine in Erlang for the following code examples:	AList = [[1, 2, 3, 4]]. AList = [1, [2, 3, 4]].
20			Before: After M-3 < M-f7> /: AList = [[1, 2, 3, 4]]. AList = [1, 2, 3, [4]].

<u>Description</u>	<u>Keystroke</u>	Function	No	<u>ote</u>
Transform - slurp	The following commands perfe	orm slurping operations, ho	wever support for Erlang could be improved as the	e commands do not always work properly.
Enclose next outside element into current block •	(sp-forward-slurp-sexp &optional ARG)	Add sexp following the current list in it by movin If the current list is the last in a parent list, extremed an extend a list or end of file). If ARG is N, apply this function that many time If ARG is negative -N, extend the opening pair If ARG is raw prefix C-u, extend all the way to If both the current expression and the express together. This command does not always work well for use the next command for Erlang in those	end that list (and possibly apply recursively until es. r instead (that is, backward). the end of the parent list. sion to be slurped are strings, they are joined r Erlang as shown in the first example.	
		smartparens by itself fails to process these examples properly. PEL fixes the behaviour by using ability to post-process code to ensure correct syntax.	<pre>Before: Names = []Joe. Before: AList = [[1, 2, 3], 4, 5]. Before: AList = [1, 2, 3,</pre>	After <m-f7> >: Names = [Joe]. After <m-f7> >: AList = [[1, 2, 3, 4], 5]. After M <m-f7> >: AList = [1, 2, [3, 10,11,12,[22,33,44]], 5, 6, 7, 8,[]].</m-f7></m-f7></m-f7>
Enclose previous outside element(s) into next block • <u>X Smartparens</u> with smartparensmode active	<m-f7> <</m-f7>	(sp-backward-slurp- sexp &optional ARG)	Add the sexp preceding the current list in it by m If the current list is the first in a parent list, ext we can extend a list or beginning of file). If arg is N, apply this function that many times If arg is negative -N, extend the closing pair in If ARG is raw prefix C-u, extend all the way to If both the current expression and the express together.	end that list (and possibly apply recursively until
		The position of point inside the list does not matter. The point does not move. Before: Alist = [-2, -1, 0,	Before: AList = [0, 1, [2, 3], 4], 5]. Before: AList = [0, 1, [2, 3], 4], 5]. After C-u <m- 1,="" 3,="" 4],="" 5].="" [2,="" alist="[[-2,</th"><th>After <m-f7> <: AList = [0, [1, 2, 3, 4], 5]. After M-2 <m-f7> <: AList = [[0, 1, 2, 3], 4], 5]. ef7> <: -1, 0, 1, 2, 3, 4], 5].</m-f7></m-f7></th></m->	After <m-f7> <: AList = [0, [1, 2, 3, 4], 5]. After M-2 <m-f7> <: AList = [[0, 1, 2, 3], 4], 5]. ef7> <: -1, 0, 1, 2, 3, 4], 5].</m-f7></m-f7>
Enclose next element(s) into previous block •	<m-f7> }</m-f7>	(pel-sp-add-to- previous-sexp &optional ARG)	Add the expression around point to the first list p With ARG positive N add that many expressio If ARG is raw prefix argument C-u add all expression If ARG is raw prefix argument C-u C-u add the	preceding point. In some to the preceding list. It is ressions until the end of enclosing list to the ecurrent list into the previous
64		smartparens by itself fails to process these examples properly. PEL fixes the issues with post processing and wrapping function.	Before: AList = [0, 1, [2, 3], 4, 5]. Before: AList = [0, 1, [2, 3], 4, 5].	After <m-f7> }: AList = [0, 1, [2, 3, 4], 5]. After M-2 <m-f7> }: AList = [0, 1, [2, 3, 4, 5]].</m-f7></m-f7>
Enclose previous outside element(s) into next block •	<m-f7> {</m-f7>	(sp-add-to-next-sexp &optional ARG)	Add the expressions around point to the first list following point. With ARG positive N add that many expressions to the following list. If ARG is raw prefix argument C-u add all expressions until the beginning of enclose the following list. If ARG is raw prefix argument C-u C-u add the current list into the following list.	
mode active	ns-	This command works fine in Erlang for the following code examples:	Before: AList = [1, 2, [3, 4]]. Before: AList = [1, 2, [3, 4]].	After <m-f7> {: AList = [1, [2, 3, 4]]. After C-u <m-f7> {: AList = [[1, 2, 3, 4]].</m-f7></m-f7>
			<pre>Before: AList = [[1, 2], [3, 4]].</pre>	After C-u C-u <m-f7> {: AList = [[[1, 2], 3, 4]].</m-f7>
Re-wrap block	Use the following commands	to change the wrapping cha	racter pair surrounding a block	
Re-wrap current block • <u>\sum \mathcal{X} \mathcal{S} \mathcal{S}</u>	<m-f7> r</m-f7>	(sp-rewrap-sexp PAIR &optional KEEP-OLD)	Re-wrap current block using another block chara • With C-u , keep old delimiter and wrap with P.	
with smartparens- mode active		This command works fine in Erlang for the following code examples:	AList = [[1, 2, 3, 4]]. Before:	After <m-f7> r {: AList = [{1, 2, 3, 4}] After C-u <m-f7> r {:</m-f7></m-f7>
Swap current block and	<m-f7> w</m-f7>	(sp-swap-enclosing-	AList = [[1, 2, 3, 4]]. Swap the enclosing delimiters of this and the pa	AList = [{[1, 2, 3, 4]}] rent expression.
parent block wrapping characters		sexp &optional ARG) This command works fine	With N > 0 numeric argument, ascend that ma Refore:	any levels before swapping. After <m-£7> w:</m-£7>
<u>∑x Smartparens</u> with smartparens- mode active			AList = $(\{[1, 2, 3, 4]\}).$	AList = ([{1, 2, 3, 4}]).
mode active			Before: AList = ({[1, 2, 3, 4]}).	After <m-f7> w: AList = [{(1, 2, 3, 4)}].</m-f7>
Un-wrap block				
Extract all elements from current/next block	<m-f7> U</m-f7>	(sp-unwrap-sexp &optional ARG)	Un-wrap current or next block. • With ARG N, unwrap Nth expression as return • If ARG is negative -N, unwrap Nth expression	, ,
<u>XX Smartparens</u> with smartparens- mode active		This command works fine in Erlang for the following code examples:	Before: AList = ({[1, 2, 3, 4]}).	After <m-f7> U: AList = [{1, 2, 3, 4}].</m-f7>
26		·	<pre>Before: AList = ({[1, 2, 3, 4]}).</pre>	After <m-f7> U: AList = ({1, 2, 3, 4}).</m-f7>
			After <m-f7> 4], 5, [6, 7], 8]. AList = [1,</m-f7>	2, 3, 4, 5, [6, 7], 8].
		Before: AList = [1, 2, 3,	After M-2 <m 4],="" 5,="" 7],="" 8].="" [6,="" alist="[1,</th"><th>I-f7> U: 2, [3, 4], 5, 6, 7, 8].</th></m>	I-f7> U: 2, [3, 4], 5, 6, 7, 8].

<u>Description</u>	<u>Keystroke</u>	Function		<u>No</u>	<u>ote</u>
Extract all elements from previous block	<m-f7> W</m-f7>	(sp-backward-unwrap- sexp &optional ARG)	Unwrap the previous block. Unwrap the previous expression	un.	
X Smartparens with smartparens- mode active		SEAP AUDITIONAL AND	With ARG N, unwrap Nth expre 'sp-backward-sexp'. If ARG is forward as returned by 'sp-forw	ession as returned negative -N, unw	
69			Before: AList = ({[1, 2, 3, 4]	}).	After <m-f7> W: AList = ({1, 2, 3, 4}).</m-f7>
		code examples:			Again After <m-f7> W: AList = (1, 2, 3, 4).</m-f7>
					Again After <m-f7> W: AList = 1, 2, 3, 4.</m-f7>
			<pre>Before: AList = [0, 1, [2, 3,</pre>	4], 5].	After <m-f7> W: List = [0, 1, 2, 3, 4, 5].</m-f7>
		Before: AList = [1, 2, [3, 4		After <m-f7> AList = [1,</m-f7>	W: 2, [3, 4], 5, 6, 7, 8].
		Before: AList = [1, 2, [3, 4		After M-2 <m AList = [1,</m 	(-f7> W: 2, 3, 4, 5, [6, 7], 8].
Split & Join					
Split block • ∑X Smartparens with smartparens-	<m-f7> </m-f7>	(sp-split-sexp ARG)	Split the list or string the point If ARG is a raw prefix C-u sp with delimiters of the current	olit all the sexps in	n current expression in separate lists enclosed
mode active	smartparens by itself fails to process the first of these examples properly.	<pre>Before: AList = [1, 2, [3, 4]</pre>		After <m-f7> AList = [1, 2</m-f7>	: 2, [3, 4], [5, 6, 7], 8].
	PEL fixes the issues with post processing.	<pre>Before: Name = "Joe Armstro</pre>	ong".		" "Armstrong".
		<pre>Before: AList = [1, 2, [3, 4]</pre>		After C-u <m AList = [1, 2</m 	- f7> : 2, [3], [4], <mark> </mark> [5], [6], [7], 8].
Join blocks • <u>§ </u>	<m-f7> J</m-f7>	(sp-join-sexp &optional ARG) Join the blocks before and after point if they are of the same type. If ARG is positive N, join N expressions after the point with the one before the point with the one after the point with the point w		he point with the one before the point. re the point with the one after the point. b until the end of current expression.	
		Before: AList = [0, 1, [2, 3	3, 4] <mark>, [5, 6], 7].</mark>	After <m-f7> AList = [0,</m-f7>	J: 1, [2, 3, 4], 5, 6], 7].
		Before: AList = [[0, 1], [2	2, 3, 4], [5, 6], 7].	After M-2 <m AList = [[0,</m 	I-f7> J: , 1 , 2, 3, 4, 5, 6], 7].
Search Support			snake case is often used. Usin mode. To change this use the	~ '	
Toggle superword- mode	<f12> M-p</f12>	(superword-mode &optional ARG)	Toggle superword-mode: a mir In Erlang, '_' are then treated		
• <u>∑ Text Modes</u> • <u>∑ Search/Replace</u>	• <f11> t m p • <f11> SPC e M-p</f11></f11>	aoptional And)			mode if ARG is positive, disable it otherwise.
Highlighting blocks	show-paren-mode, which h	ighlights the parens that ma	e useful modes to highlight block tches the one before or after points are highlighted with the same	int.	
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching With a prefix argument ARG, otherwise.		Paren mode). Paren mode if ARG is positive, and disable it
See also: <u>Neighlight</u>	• <f11> h (• <f11> SPC e M-9</f11></f11>		 Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time. 		
Toggle colouring of nested blocks See also: <u>Neighlight</u>	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters- mode &optional ARG)	Highlight nested parentheses, brackets, and braces with colours according to their depth. • Customize the depth and colours with M-x customize-group rainbow-delimiters • Requires: rainbow-delimiters.el		stomize-group rainbow-delimiters
	• <f11> h R</f11>			activated	7
Edit Erlang Code	The following commands help		0 1 1		
Create additional clause	C-c C-j	(erlang-generate-new- clause)	containing the name, a pair of	name of the current of parentheses, ar	ent Erlang function. Create the header nd an arrow. The space between the function The point is placed between the parentheses.
Clone clause arguments	С-с С-у	(erlang-clone- arguments)	Insert, at the point, the argume • Copy the function arguments defining a new clause with a • The mark is set at the beginn	s of the preceding Imost the same ar	Erlang clause. This command is useful when rgument as the preceding.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Insert Erlang Code	The erlang.el external packag	e defines a set of text skele	tons, available on the Erlang/Skeletons menu (via <f10>)</f10>	
with Specialized Tempo Skeletons	· ·	ert the templates, all mappe	ed under the pel:erlang-skel key prefix: <f12></f12> <f12></f12> .	
Erlang Style	 Several additional templates. These are marked with a +. These are also added to the menu. Several aspects of the PEL Erlang Source Code Style is controlled by the user options inside the pel-erlang-code-style group. The controlled templates affected are marked with a C. The relevant user options are part of the pel-erlang-code-style group accessible with <f12> <f2> from a</f2></f12> 			
Control -	erlang mode buffer and include the following options:			
	pel-erlang-skel-inserpel-erlang-skel-prom	pt-for-purpose	: set whether an automatically updated timestamp is inserted in the file header block. : set whether file and function skeletons blocks prompt for purpose and insert it.	
See also: •		pt-for-function-arguments	: set whether function skeletons prompt for function name and then inserts that name. s : set whether function skeletons prompt for function arguments and then insert them.	
more info and information about	pel-erlang-use-separpel-erlang-use-secor	dary-separators	: set whether blocks use horizontal separator lines (these are the first of potentially 2 separators). : set whether blocks use a second block horizontal separator line.	
tempo skeleton and the completely	pel-erlang-skel-with-pel-erlang-skel-with-		: set whether generated code comments use EDoc markup. : set whether file header blocks use open source software license text controlled by dice.	
different <u>yasnippet</u> template-based text	Emacs user options by	default take effect globally.	But by using file and directory variables (see File/Directory Variables) they can also be used	
insertion).	If you want to change the the PEL tempo templates This allows you to control	behaviour for only one file, we for all files inside a directory the user options affecting the control of the	ory tree. So by default, the user options that control the PEL tempo template take effect globally. write the user option control block at the end of that file. If you want to control the behaviour of v tree create a .dir-locals file and store the values of the relevant options variables inside that file. The format of the tempo templates precisely and does not affect what you actually type. In the pel-tempo-mode) you can move to the next or previous point of interest (so called tempo-	
+ : additional templates C : templates with	marks) with the standard	tempo-mode keys C-c M-	-f and C-c M-b or some other keys like C-c . and C-c ,.	
customization control			an also type the template name and then hit C-c C-M-i or <f12> <f12> <f12>. This orary buffer. This is mainly useful for templates which short names such as "if", "case", etc</f12></f12></f12>	
	Some of the template nam		so links to the relevant Erlang language construct reference page.	
∑ Customize PEL Erlang Skeletons layout	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-pel &optional OTHER- WINDOW)	 Customize PEL Erlang skeleton layout. If OTHER-WINDOW is non-nil (use C-u), display in another window. 	
if	<f12> <f12> i</f12></f12>	(pel-erl-if)	Insert an if statement.	
case	<f12> <f12> c</f12></f12>	(pel-erl-case)	Insert a case expression.	
export +	<f12> <f12> x</f12></f12>	(pel-erl-export	Insert an export module attribute expression.	
import +	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.	
<u>try</u> +	<f12> <f12> t</f12></f12>	(pel-erl-try)	Insert a try expression.	
try-of +	<f12> <f12> T</f12></f12>	(pel-erl-try-of)	Insert a try expression with of clauses.	
receive	<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.	
after	<f12> <f12> a (pel-erl-after)</f12></f12>		Insert a receive expression with an after (timeout) clause.	
loop	<f12> <f12> 1 (pel-erl-loop)</f12></f12>		Insert a simple receive loop.	
<u>module</u>	<f12> <f12> m (pel-erl-module) Insert the module attribute.</f12></f12>			
<u>function</u> C	<f12> <f12> f (pel-erl-function)</f12></f12>		Insert a function definition. This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.	
author	<f12> <f12> ` (pel-erl-author)</f12></f12>		Insert the author attribute. Uses the user-mail-address user option to insert your mail address.	
spec	<f12> <f12> s (pel-erl-spec) Insert a -spec for the function following point.</f12></f12>		Insert a -spec for the function following point.	
small-header C	<f12> <f12> M-h</f12></f12>	(pel-erl-small-header)	Insert a small file header without any comment.	
normal-header C	<f12> <f12> M-H</f12></f12>	(pel-erl-normal-header)	Insert a normal file header: includes author name, copyright notice, doc section, file created date	
large-header C	<f12> <f12> h</f12></f12>	(pel-erl-large-header)	Insert a large header block that includes all normal header fields plus separators. • User-options control the format. Distinguish Erlang .erl module files from the .hrl header files.	
small-server C	<f12> <f12> M-s</f12></f12>	(pel-erl-small-server)	Insert a large file header and template logic for a small server.	
application C supervisor C	<f12> <f12> M-a</f12></f12>	(pel-erl-application)	Insert a large file header and template logic for an <u>application behaviour</u> .	
supervisor C supervisor-bridge C	<f12> <f12> M-u <f12> <f12> M-b</f12></f12></f12></f12>	(pel-erl-supervisor)	Insert a large file header and template logic for a <u>supervisor behaviour</u> . Insert a large file header and template logic for a <u>supervisor bridge behaviour</u> .	
supervisor-bridge	(112) (112) M-D	bridge)	insert a large me neader and template logic for a <u>supervisor bridge benaviour</u> .	
generic-server C	<f12> <f12> M-g</f12></f12>	(pel-erl-generic-server)	Insert a large file header and template logic for a gen-server behaviour.	
gen-event C	<f12> <f12> M-e</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a gen-event behaviour .	
gen-statem-StateName	<f12> <f12> M-f <f12> <f12> M-S</f12></f12></f12></f12>	(pel-erl-gen-statem-	Insert a large file header and template logic for a gen-fsm behaviour . Insert a large file header and template logic for a gen-statem behaviour .	
C gen-statem-handle-	<f12> <f12> M-E</f12></f12>	StateName) (pel-erl-gen-statem-	Insert a large file header and template logic for a gen-statem.	
event C wx-object C	<f12> <f12> M-w</f12></f12>	handle-event) (pel-erl-wx-object)	Insert a large file header and template logic for a wx-object generic server.	
gen-lib C	<f12> <f12> M-W</f12></f12>	(pel-erl-gen-lib)	Insert a large file header and template logic for a library module.	
gen-corba-cb C	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a CORBA callback module.	
ct-test-suite-s	<f12> <f12> M-1</f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite	
ct-test-suite-l	<f12> <f12> M-2</f12></f12>	(pel-erl-ct-test-suite-l)	Insert a large file header and template logic for a test suite	
ts-test-suite	<f12> <f12> M-3</f12></f12>	(pel-erl-ts-test-suite)	Insert a large file header and template logic for a test suite	
Tempo Template Tag Insertion	• C-c C-M-i • <f12> <f12> <f12></f12></f12></f12>	(tempo-complete-tag &optional SILENT)	Look for a tag and expand it. Instead of using the <f12> <f12> key bindings above, type the template name and then hit C-c C-M-i. (or <f12> <f12> <f12>).</f12></f12></f12></f12></f12>	
	• <f12> <f12> <f12> <f12> <f12> (stidentification of the template name and then hit C-c C-M-i. (or <f12> <f12> (stidentification of the template name). Select the template name and hit RET. Emacs expands the template. • All the tags in the tag lists in 'tempo-local-tags' (including 'tempo-tags') are searched for a match for the text before the point. The string matching is determined by the variable 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no match at all. • If a single match is found, the corresponding template is expanded in place of the matching string. • If a partial completion or no match at all is found, and SILENT is non-nil, the function will give a signal. • If a partial completion is found and 'tempo-show-completion-buffer' is non-nil, a buffer containing possible completions is displayed.</f12></f12></f12></f12></f12></f12></f12>			
Toggle pel-tempo-mode		(pel-tempo-mode &optional ARG)	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-	
See also: •	• <f11> SPC e <f12> SPC</f12></f11>	·	tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode.	
	• <f6> SPC</f6>		When a skeleton is inserted via the execution of one of the pel-erl commands above, the pel-tempo-mode is automatically activated.	
			10	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key key bindings are only available when pel-tempo-mode is active.
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward- mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key binding are only available when pel-tempo-mode is active.
Specialized Kill See also: • ∑ Cut & Paste • ∑ Smartparens	Activate smartparens mode This table uses the ☒ and ⟨☒ := "forward delete" := ⟨☒ := "backward delete":	manually with <f11> (Substitute states symbols to represent the states states states are states and states states are states states are states</f11>	
kill block elements	The following commands kill th	ne element(s) of a block.	
Kill content of next block	• <m-f7> ⊠ • <m-f7> - n</m-f7></m-f7>	(sp-change-inner)	Change the content of current or next block. Point can be anywhere in block or element before block. Before: {'EXIT',Reason} -> {'EXIT',Reason} ->
S Smartparens Delete content of current block	<m-f7></m-f7>	(sp-change-enclosing)	{ error, {asn1, Reason}}; {error, { }}; Delete content of the enclosing block. Point can be anywhere inside the current block. Before: After:
• <u>∑</u> X Smartparens Kill block elements	<m-f7> -]</m-f7>	(sp-kill-sexp &optional	<pre>{'EXIT', Reason} -> {error, { asn1, Reason}}; Kill block elements after point.</pre> <pre>{'EXIT', Reason} -> {error, { }};</pre>
forward • ∑x Smartparens		ARG DONT-KILL)	<pre>Before: case Tlv9 of [] -> true;> exit({error, {asn1, {unexpected, Tlv9}}}) After:</pre>
Kill block elements	<m-f7> - [</m-f7>	(sp-backward-kill-sexp	<pre>case Tlv9 of [] -> true;> exit({error, }) Kill block elements before point.</pre>
backward • ∑x Smartparens	,	&optional ARG DONT- KILL)	<pre>Before: case Tlv9 of [] -> true; -> exit({error, {asn1, {unexpected, Tlv9}}}) After: case Tlv9 of [[] -> true; -> exit({ {asn1, {unexpected, Tlv9}}})</pre>
Kill element after current	<m-f7> - }</m-f7>	(sp-kill-hybrid-sexp ARG)	Kill a line as if with 'kill-line', but respecting delimiters.
• <u>∑x Smartparens</u>		With ARG numeric prefix	efix C-u C-u , kill the hybrid sexp the point is in (see 'sp-get-hybrid-sexp'). x 0 (zero) just call 'kill-line'. pehaviour of this command by toggling 'sp-hybrid-kill-excessive-whitespace'.
Kill whole line	<m-f7> - 1</m-f7>	(sp-kill-whole-line)	⚠ Currently this deletes the whole line. Requires Erlang specific implementation. ##
Kill/splice Un-wrap current block, splicing its elements in enclosing block ∑x Smartparens	<m-f7> 1 1</m-f7>	(sp-splice-sexp &optional ARG)	Un-wrap current block, splicing its content in enclosing block (if any). Before: { EncBytes,EncLen} = 'enc'(Cdx, []), EncBytes,EncLen = 'enc'(Cdx, []), Before: -asn1_info([{vsn, '2.0.1'}, {module, 'ELDAPv3'}, {options, {{i, "src"}, { outdir, "src"}, noobj, {i, "."}, {i, "asn1"}]}}). After: -asn1_info([{vsn, '2.0.1'}, {module, 'ELDAPv3'}, {module, 'ELDAPv3'}, {options, [{i, "src"}, outdir, "src", noobj, {i, "."}, {i, "asn1"}]}}).
Kill block element(s) before point and splice remaining into outer block • \$\sum x\$ Smartparens	<m-f7> 1 [</m-f7>	(sp-splice-sexp-killing- backward &optional ARG)	Kill elements before point in block and splice remaining elements into outer block. Before: case Tlv9 of [] -> true; -> exit({error, {asn1, {unexpected, Tlv9}}}) After: case Tlv9 of
Kill block element(s) forward and splice remaining into outer block • <u>SX Smartparens</u>	<m-f7> 1]</m-f7>	(sp-splice-sexp-killing- forward &optional ARG)	<pre>[] -> true; -> exit({error,{asn1, Tlv9}}) Kill elements after point in block and splice remaining elements into outer block. Before: case Tlv9 of [] -> true; -> exit({error,{asn1, {unexpected, Tlv9}}}) After: case Tlv9 of [] -> true; -> exit({error,{asn1, unexpected }})</pre>
Kill around element • ∑x Smartparens	<m-f7> 1 o</m-f7>	(sp-splice-sexp-killing- around &optional ARG)	<pre>Kill content around current element/block. Before: -asn1_info([{vsn, '2.0.1'},</pre>
Delete/Kill region	and and		
Delete region	<m-f7> DEL -</m-f7>	(sp-delete-region BEG END)	Delete the text between point and mark, like 'delete-region'. • BEG and END are the bounds of region to be deleted. • If that text is unbalanced, signal an error instead. • With a prefix argument, skip the balance check.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Kill region	<m-f7></m-f7>	(sp-kill-region BEG END)	Kill the text between point and mark, like 'kill-region'. • BEG and END are the bounds of region to be killed. • If that text is unbalanced, signal an error instead. • With a prefix argument, skip the balance check.
	<m-f7> - r</m-f7>	(spkill-or-copy-region BEG END &optional DONT-KILL)	Kill or copy region between BEG and END according to DONT-KILL. • If 'evil-mode' is active, copying a region will also add it to the 0 register. • Additionally, if command was prefixed with a register, copy the region to that register
Delete char forward	<m-f7> DEL n</m-f7>	(sp-delete-char &optional ARG)	(quu x "zot") -> (quu "zot") (quux "zot") -> (quux " zot") -> (quux " ot") (foo () bar) -> [foo bar]
Delete char backward	<m-f7> DEL p</m-f7>	(sp-backward-delete- char &optional ARG)	(foo bar) -> (foo bar) ("zot" q uux) -> ("zot" uux) ("zot" quux) -> ("zot " quux) -> ("zo " quux) (foo () bar) -> (foo bar) (foo bar) -> (foo bar)
Delete/Kill word	-		
Delete word backward	<m-f7> DEL v</m-f7>	(sp-backward-delete- word &optional ARG)	(sp-backward-delete-word &optional ARG) • Delete a word backward, skipping over intervening delimiters. • Deleted word does not go to the clipboard or kill ring. • With ARG being positive number N, repeat that many times. • With ARG being Negative number -N, repeat that many times in backward direction.
Delete word forward	<m-f7> DEL w</m-f7>	(sp-delete-word &optional ARG)	Delete a word forward, skipping over intervening delimiters. Deleted word does not go to the clipboard or kill ring. With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in backward direction.
Kill word backward	<m-f7> - v</m-f7>	(sp-backward-kill-word &optional ARG)	 Kill a word backward, skipping over intervening delimiters. With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in backward direction.
Kill word forward	<m-f7> - w</m-f7>	(sp-kill-word &optional ARG)	Kill a word forward, skipping over intervening delimiters. • With ARG being positive number N, repeat that many times. • With ARG being Negative number -N, repeat that many times in backward direction.
Delete/Kill symbol	See 'sp-backward-symbol' a	and 'sp-forward-symbol' fo	or what constitutes a symbol for the backward and forward commands respectively.
Delete symbol backward	<m-f7> DEL a</m-f7>	(sp-backward-delete- symbol &optional ARG WORD)	Delete a symbol backward, skipping over any intervening delimiters. Deleted symbol does not go to the clipboard or kill ring. With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in forward direction.
Delete symbol forward	<m-f7> DEL s</m-f7>	(sp-delete-symbol &optional ARG WORD)	Delete a symbol forward, skipping over any intervening delimiters. Deleted symbol does not go to the clipboard or kill ring. With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in backward direction.
Kill symbol backward	<m-f7> - a</m-f7>	(sp-backward-kill- symbol &optional ARG WORD)	Kill a symbol backward, skipping over any intervening delimiters. With ARG being positive number N, repeat that many times. With ARG being Negative number -N, repeat that many times in forward direction.
Kill symbol forward	<m-f7> - s</m-f7>	(sp-kill-symbol &optional ARG WORD)	Kill a symbol forward, skipping over any intervening delimiters. • With ARG being positive number N, repeat that many times. • With ARG being Negative number -N, repeat that many times in backward direction.
Erlang syntax checking Using either: • flycheck or • flymake	Syntax checking for the Erlang programming language can be done with Emacs built-in flymake as well as with the flycheck external package. To activate either set the pel-use-erlang-syntax-check user option is set to either 'use-flycheck or 'use-flymake. By default, the syntax checker is not automatically launched. If you want to start your selected syntax checker as soon as any Erlang file is opened, add 'erlang-mode to the pel-modes-activating-syntax-check user-option. flymake is built-in Emacs. The Emacs erlang package provides erlang-flymake to use with Erlang. PEL automatically installs and activates flycheck when pel-use-erlang-syntax-check user option is set to 'use-flycheck.		
See also: • <u>SyntaxCheck</u>	Flymake has several customizable variables, which some listed here: The following customization variables determine the exact circumstances whereupon Flymake decides to initiate a check of the buffer: • flymake-start-on-flymake-mode: t to start checking when flymake-mode is started. nil to prevent check. • flymake-no-changes-timeout: time to wait after last change to start checking. Default = 0.5 seconds. • flymake-start-syntax-check-on-newline: t to check after insertion or removal of newline char from buffer. nil to prevent check.		
	The following variable control navigation to next or previous error: • flymake-wrap-around: If non-nil, moving to errors wraps around buffer boundaries. • flymake-diagnostic-types-alist: Alist ((KEY . PROPS)*) of properties of Flymake diagnostic types. See Emacs documentation for more info. The M-n and M-p keys are mapped to flymake commands only when flymake-mode is turned on.		
Activate/deactivate	<f12> !</f12>	(pel-erlang-toggle-	Toggle the selected Erlang syntax checker mode on/off.
selected syntax checker	<f11> SPC e !</f11>	syntax-checker)	 The syntax checker activated or deactivated is either <u>flycheck</u> or <u>flymake</u>, as selected by the user-option variable <u>pel-use-erlang-syntax-check</u>. See the required settings above to activate this command and select the syntax checker.
Go to next flymake diagnostic	м-п	(flymake-goto-next- error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic. • With a prefix arg, skip any diagnostics with a severity less than ':warning'. • Display the error message in the echo line.
Go to previous flymake diagnostic	м-р	(flymake-goto-prev- error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic. • With a prefix arg, skip any diagnostics with a severity less than ':warning'. • Display the error message in the echo line.
Compiling Erlang Code	The following commands are used to compile Erlang source code files to .beam files located in the same directory as the source code. Detected errors are listed in the *erlang* shell opened to compile the files. The buffer shows the location of error and the error description. The following commands are used to navigate to the next or previous detected error.		
Compile code	• C-c C-k • <f12> M-c • <m-f12> M-c</m-f12></f12>	(erlang-compile)	Compile Erlang module in current buffer. If buffer visiting file was modified and not saved, prompts the user to save it first. Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command. The buffer lists the errors. Hitting RET on the error file/line move point to that line in the Erlang file buffer. The RET key is bound to (compile-goto-error &optional EVENT) It's also possible to use the next-error and previous error.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output. • Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.
Move to next compile error	• C-x • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; • negative means move back to previous error messages. • Just C-u as a prefix means reparse the error message buffer and start at the first error. This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to previous compile error	• M-g p • M-g M-p	(previous-error &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative). This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error. When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Move to previous compilation or Flycheck detected error	С-с С-р	(edts-code-previous- issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error. When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Development Tool	The following commands are u	sed when adding Emacs Li	sp support for Erlang.
Show syntactic information	C-c C-s	(erlang-show-syntactic-information)	Show syntactic information for current line. • Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.
Erlang Shell	Commands to explicitly launch comint.el library running in erla		that runs under an Emacs inferior-erlang process controlled by the comint mode from the
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.
Start new Erlang Shell	<f11> z r e <f12> z</f12></f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer. • The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started. • C-c C-z starts the Erlang Shell from the Erlang Mode. • <f11> z r is available globally and will work as long as the erl executable is accessible.</f11>
			Under PEL this command is available only when the pel-use-erlang user option is set to t .
Work around to issues in the Erlang Shell	Redundant command echo: On some systems the Erlar Set the pel-erlang Typing Ctrl-G does not open	ng shell annoyingly echoes -shell-prevent-echo user of the Erlang JCL Comman	each typed command. If this is the case for your system, PEL provides a fix: option to t. After doing that execute pel-init or restart Emacs. d Menu: work-around: type the following instead: C-q C-g RET ork when the Erlang shell is launched inside an Emacs vterm shell (see <u>S Shells</u>).
Erlang Shell: Command History	The following commands can be used to retrieve previously issued Erlang shell commands at the shell prompt. Erlang shell command history file: The Erlang shell history controlled by Emacs is saved inside a file the is restored when opening a new shell: commands from previously opened Erlang shells are also available. Within an Emacs inferior-erlang the You can also use the Erlang shell commands to access the local shell history.		
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.
Previous shell command	М-р	(comint-previous-input ARG)	Cycle backwards through Erlang shell input history, saving input.
Using Man inside Emacs and support Erlang Man pages	Emacs provide 2 main commands to display man pages inside buffers. Both of these are much more powerful than the usual man reader available on the shell allowing navigation across man pages and opening hyperlinks. They are: The man command uses the system man utility MoMan: Browse Unix Manual Pages "W.O. (without) Man" a complete implementation. It has some formatting limitations compared to man but it's very useful in systems where man is not available like Windows.		
See also: <u>∑ Help/Info</u>	To see Erlang man pages using the man command: On most systems the Man pages for Erlang are not available to the man utility and therefore not available for man inside Emacs. There are several ways this can be remedied: One is to set the MANPATH environment variable to include the directory where these files are located. Then man can be used outside and inside Emacs to access Erlang's man pages. For example the following lines can be stored inside a shell script to do this: MANPATH=/usr/local/Cellar/erlang/22.3.4/lib/erlang/man:`manpath` export MANPATH Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add the capability of Emacs man to fin the Erlang's man pages without modifying the capabilities of the parent shell. For example, if we want to use the same directory as the above example we need to set the Man-switches which is normally set to nil to the following value: "-M`manpath`:/usr/local/Cellar/erlang/22.3.4/lib/erlang/man"		
	The second alternative can be used to add other directories for the man pages of other programming languages while leaving the ability to have several shells that have their own value of MANPATH. That might be very useful for someone that uses different versions of Erlang in a system and needs access to the man pages of different versions of Erlang. It becomes possible to run different shells inside Emacs with each having its own value of MANPATH and therefore providing the man pages from different locations. It is also possible to place all of these directories inside the Man-switches or MANPATH and buses man's ability to view several pages for the same topic.		
	To only see Erlang topics in Man completion: When learning Erlang it might help to see only Erlang topics when using the man command completion. To do that, set MANPATH to the Erlang man directory only. You must also ensure that a whatis file is located in the Erlang man page root directory, otherwise Emacs man completion will not work. See my description on how to create whatis file for local man directory.		
	Using EDTS to access the man pages of the version of Erlang used by various projects: EDTS (see below) supports the ability to download and access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides it's own help command to access sections inside the mane pages, allowing EDTS driven man page access to co-exist with manual man command execution and the techniques described above.		
About Erlang	PEL supports multiple versions of Erlang and access to their man pages Inside the pel-erlang-environment group, the pel-erlang-man-parent-rootdir user-option can be set to read the man parent directory name from an environment variable. To support the ability to open the man files related to a specific version of Erlang available to the parent OS shell, set the environment variable when you select the version of Erlang available to the OS shell and set the name of the environment variable in the pel-erlang-man-parent-rootdir user-option. See the following Installing Erlang pages of the About Erlang document that describes an setting such an editing environment: Install Erlang OTP Documentation and Man Files Creating whatis files for Erlang man pages Using the Erlang Man files within Emacs Using Specialized OS Shells for Erlang Using PEL with Specialized Shells for Erlang to Edit Erlang		

Description	<u>Keystroke</u>	Function	Note
Open a man page inside an Emacs buffer	• <f11> ? m • ₩-M</f11>	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because: • the links are active and can be followed. When the man page describes a directory or file, emacs will open the file or the directory (in direct mode) when pressing RET over the link.
See also: •			 You can navigate easily between sections (n/p will move to the next/previous section) You can use any of the searches. You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer. See all keys available in mode, with <f1> m or <f11>? k m.</f11></f1> The man command prompts, using the word at point as the default. PEL key sequence to customize man: <f11> <f2> E m</f2></f11>
Open a man page without external man process: woman •	<f11> ? w</f11>	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows). PEL key sequence to customize man: <f11> <f2> E w text width, use word at point, etc</f2></f11>
Show Manual page for Erlang function at point	• C-c C-d • <m-f12> M-d</m-f12>	(erlang-man-function- no-prompt)	Find manual page for the function under the cursor. The man entry for 'function' is displayed. This function provides the same functionality as erlang-man-function except for that it does not ask the user to confirm the function name before opening the man page for the function.
EDTS	EDTS - Erlang Developr	nent Tool Suite	
	If you want EDTS to start a If EDTS reports that it cann	utomatically when you open not start the main server, che	external package. PEL activates it when the pel-use-edts user option is set to t. an Erlang file, set pel-use-edts to start-automatically instead of t. eck the ~/.emacs.d/elpa/edts-XXX directory. It should contain a _build sub-directory created by access to Erlang, cd to ~/.emacs.d/elpa/edts-XXX and type make to build what is missing.
Erlang Project settings	identified edts. • EDTS also uses an externathe following: project name	s it by typing <f12> <f3> nal .edts configuration file to ne, node-name, erlang-cook</f3></f12>	roup. • from an Erlang buffer, or <f11> SPC e <f3> from any other buffer) and type character that be store Erlang project specific settings. See EDTS: Configure your projects. This allows setting kie, lib-dirs, start-command, top-path, dialyzer-plt, app-include-dirs, project-include-dirs, xref-</f3></f11>
See also: <u>Sessions</u>	• PEL does, however provi	ails when edts-mode was a de a desktop restore handle	ctive on session stored: unfortunately edts does not provide a desktop restore handler. er for EDTS which detects edts-mode failures and protect the desktop restoration. cific key available is <f12> M-E to activate it. Once it's activated the other keys are available.</f12>
Toggle EDTS mode	<f12> M-E</f12>	(edts-mode &optional	Turn EDTS mode on or off.
	<f11> SPC e M-E</f11>	ARG)	 EDTS is an easy to set up Development-environment for Erlang. EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further.
EDTS/Navigation	above in the navigation section	 The EDTS navigation fun o move across Erlang funct 	cross Erlang functions: ferl-goto-previous-function and ferl-goto-next-function. They are listed ctions do not support repetition prefix argument nor they support shift marking. There are other ions, and PEL support functions that perform the same and support repetition and shift marking.
EDTS/Cross References			It supports navigating in Erlang source code running in the current and remote nodes. e in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11>
Find definition of identifier at point	м	(edts-find-source- under-point)	Goto the source code that: defines the function being called at point or header file included at point. For remote calls, contacts an Erlang node to determine which file to look in, with the following algorithm: • Find the directory of the module's beam file (loading it if necessary). • Look for the source file in: • Directory where source file was originally compiled. • Todo: Same directory as the beam file • Todo: Again with /ebin/ replaced with /src/ • Todo: Again with /ebin/ replaced with /erl/ Otherwise, report that the file can't be found.
Go back to where M was last issued	М-,	(edts-find-source- unwind)	Unwind back from uses of 'edts-navigate'-commands.
Lists caller of function at point	• C-c C-d w • <f12> w</f12>	(edts-xref-who-calls)	Pops-up a menu of all callers of the function at point.
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who- calls)	Redo previous call to edts-who-calls.
Find a function in the current module	• C-c C-d f • <m-f12> M-f</m-f12>	(edts-find-local- function SET-MARK)	Find a function in the current module. • List local functions in the mini-buffer. Support completion. Move point to selected one. • With C-u prefix, push mark before moving point.
Find a module in the current project	• C-c C-d F • <m-f12> M-g</m-f12>	(edts-find-global- function)	Find a module in the current project. List project modules in the mini-buffer. Support completion. Open the file of selected one.
EDTS/AHS Editing	in all of the buffer. The automa	atic symbol highlighting mod lts to 1.0 second.	S), and provides commands to modify the name of the highlighted name in the current function or de starts when the cursors stays on a symbol for a period longer than the value identified by the nove point away from the highlighted area.
Edit all highlighted symbols in current function	• C-c C-d e • <f12> e</f12>	(edts-ahs-edit-current-function)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current function. • Activates ahs-edit-mode with edts-current-function range-plugin.
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer. • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	Refactor the expression(s) in the region as a function. The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original function. New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring. This command requires Erlang syntax tools package to be available in the node, version 1.2 (or perhaps later.)
EDTS/Man	pages per project, so it is poss	sible to have several Erlang	ction using the information extracted from Erlang Man pages. EDTS maintains a set of Erlang man projects each one with a different version of Erlang and their corresponding man pages. I man commands described above in this table.
Download, install, select Erlang Man pages	<f12> `</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands.
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip.
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function. Find and show the man-page documentation for the Erlang module:function.
EDTS Code Analysis			
Compile current buffer	<f12> a c</f12>	(edts-code-compile- and-display)	Compiles current buffer on node related to that buffer's project.
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION-RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.
EDTS/Debug			
Toggle breakpoint	• C-c C-d b • <f12> d b</f12>	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.
List breakpoints	C-c C-d M-b • <f12> d B</f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle- interpreted)	Toggle the interpretation state for module in current buffer.
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
EDTS/Erlang Node			
Display EDTS Erlang Node Name	<f12> N</f12>	(edts-buffer-node- name)	Print the node sname of the erlang node connected to current buffer. • The node is either: • The module's project node, if current buffer is an erlang module, or • The buffer's erlang node if buffer is an edts-shell buffer. • The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module such as an otp-module or a module loaded by ~/.erlang).
Start an EDTS controlled Erlang Shell	<f12> x</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell.
Start EDTS server	<f12> X</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).

	<u>Keystroke</u>	Function	<u>Note</u>
LSP support:	LSP (language Server Protoc		
• <u>Isp-mode</u> • <u>erlang Is</u>	 The <u>Isp-mode</u> Emacs Lisp external package PEL activates it when the <u>pel-use-erlang-is</u> user-option is turned on (set to t). The <u>erlang is</u> Erlang server for LSP. You must install this manually. You will need Git, Erlang, rebar3 and make. The instructions are on the web-site. The <u>erlang is</u> can be configured using a YAML file <u>erlang is.config</u> file that must be placed at the root of the Erlang project. 		
erlang Is required environment	"It's important for most projects to set that up, otherwise you may not be able to take advantage of several of the cross-reference features The following executable must be accessible from PATH: • erl. escript and other Erlang executables. See Installing Erlang if you need to learn how to install Erlang and its tools. • erlang Is. To install erlang Is follow the instruction on the erlang Is GitHub page: git clone it, then run make and make install.		
	 erlang_is. To install erlang_is follow the instruction on the erlang_is GitHuo page: git clone it, then run make and make install. and the various Tools for Erlang. 		
• <u>S Customize</u> Isp-mode	Several lsp-mode settings are customizable in the lsp-mode customization group. With PEL you can access it via <f12> L <f3>. The following settings are probably what you may want to customize: Isp-log-io : control whether the LSP process is logging its I/O. Useful for debugging LSP support. Isp-ui-sideline-enable : control whether LSP display information about the current code line. Isp-ui-doc-enable : control whether LSP display documentation about the current code symbol. You can also use the PEL commands to modify them dynamically using the following commands.</f3></f12>		
Toggle code documentation display	<f11> SCP e L D <f12> L D</f12></f11>	(pel-toggle-lsp-ui-doc &optional LOCALLY)	Toggle the display of code documentation. The initial state is set by the 'lsp-ui-doc-enable' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Toggle LSP I/O logging	<f11> SCP e L I <f12> L I</f12></f11>	(pel-toggle-lsp-log-io &optional LOCALLY)	Toggle the logging of LSP I/O. The initial state is set by the 'Isp-log-io' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Toggle display of information on current line	<f11> SCP e L L <f12> L L</f12></f11>	(pel-toggle-Isp-ui- sideline &optional LOCALLY)	Toggle the display of information of the current line. The initial state is set by the 'lsp-ui-sideline-enable' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Erlang LS Features	Overview of the features provide Code completion Go to Definition Go to Implementation of OTP Behaviours Signature Suggestions Diagnostics on file open/save: Compiler Diagnostics Dialyzer Diagnostics Elvis Diagnostics	Edoc support Navigation to Included Files Find/Peek References	 LSP Lenses: Isp-avy-lens LSP sideline: enable with: (setq Isp-ui-sideline-enable t) Use M-x Isp-execute-copde-action to trigger quick-fix actions Erlang Project-Specific LS Configuration: Erlang LS is customizable by using a YAML syntax file called erlang Is.config that should be placed in the root directory of the project.
Isp-mode features	 Completion at point traditional popup with company-mode Code navigation, with lsp-find-definition lsp-find-references Symbol highlights Code action on mode line: set Isp-modeline-code-action-segments user-option. Breadcrumb on headerline: Use the Isp-headerline-breadcrumb-mode command to toggle their display. The Isp-headerline-breadcrumb-segments user-option. Code Lenses . The Erlang LS configuration provides ct-run-test: display a run button next to a Common Test testcase. server-info: display some Erlang LS server info on top of each module. For debug only. 		
		 show-behaviour-usa 	ages: show the number of modules implementing a behaviour.
Isp-mode integrations see also: • ∑ Completion/Input • ∑ Treemacs • ∑ Hide/Show	Isp-mode supports integration • Whelm by using helm-Isp • Whelm by using Isp-ivy • Whelm by using Isp-ivy • Whelm by using Isp-ivy • Worigami by using Isp-origami	with: PEL activate: PEL activate: PEL activate: PEL activates	
see also: • ∑ Completion/Input • ∑ Treemacs	Helm by using helm-lsp lyy by using lsp-ivy Treemacs by using lsp-ori worigami by using lsp-ori Key bindings: The lsp-mode is Since the super modifier k with M-x customize-op With PEL, the following k The key bindings shown	with: PEL activates	swhen pel-use-helm-lsp is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s customizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done set 11 > <f2> o key sequence. sandidates: <f9> and C-1 . If you use <f9> for Greek letters then consider using <m-f9>.</m-f9></f9></f9></f2>
see also: • © Completion/Input • © Treemacs • © Hide/Show LSP key bindings: • Isp-mode • erlang Is See also: © Input Method Display LSP workspace	Helm by using helm-lsp lyy by using lsp-ivy Treemacs by using lsp-ori worigami by using lsp-ori Key bindings: The lsp-mode is Since the super modifier k with M-x customize-op With PEL, the following k The key bindings shown	with: PEL activates	swhen pel-use-helm-lsp is turned on. s when pel-use-helm-lsp is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s customizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done st11> <f2> o key sequence. candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>1 key prefix.</m-f9></f9></f9></f2>
see also: • © Completion/Input • © Treemacs • © Hide/Show LSP key bindings: • Isp-mode • erlang Is See also: © Input Method Display LSP workspace log buffer Validate LSP	• Whelm by using helm-lsp • Vary by using lsp-ivy • Vareemacs by using lsp-origing l	with: PEL activates	swhen pel-use-helm-lsp is turned on. swhen pel-use-lsp-ivy is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-origami is turned on. scustomizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done cf11> <f2> o key sequence. candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>. L key prefix. can be done considered by the lsp-keymap-prefix value.</m-f9></f9></f9></f2>
see also: • © Completion/Input • © Treemacs • Dide/Show LSP key bindings: • Isp-mode • erlang Is See also: © Input Method Display LSP workspace log buffer	Helm by using helm-lsp lyy by using lsp-ivy treemacs by using lsp-ori worigami by using lsp-ori Key bindings: The lsp-mode is Since the super modifier ke with M-x customize-or With PEL, the following ke The key bindings shown le If you change lsp-key	with: PEL activates	s when pel-use-helm-lsp is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s customizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done cf11> <f2> o key sequence. candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>. lkey prefix. splaced with your selected prefix key. Display the log buffer of WORKSPACE.</m-f9></f9></f9></f2>
see also: • © Completion/Input • © Treemacs • Display LSP workspace log buffer Validate LSP performance settings Reformat Erlang file Add directory to the list	• • Helm by using helm-lsp • Very by using lsp-ivy • Treemacs by using lsp-origing by using lsp-weight by using lsp-weight by using lsp-keying lsp-key	with: PEL activates PEL activ	swhen pel-use-helm-lsp is turned on. swhen pel-use-lsp-ivy is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-origami is turned on. scustomizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done serifl > <f2> o key sequence. sandidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>. 1 key prefix. seplaced with your selected prefix key. Display the log buffer of WORKSPACE. Validate performance settings and write report in a *lsp-performance* buffer. Ask the server to format this document. Add PROJECT-ROOT to the list of workspace folders.</m-f9></f9></f9></f2>
see also: • © Completion/Input • © Treemacs • Dide/Show LSP key bindings: • Isp-mode • erlang Is See also: © Input Method Display LSP workspace log buffer Validate LSP performance settings Reformat Erlang file	Helm by using helm-lsp Wy by using lsp-ivy treemacs by using lsp-origing lsp-sey	with: PEL activates PEL activ	swhen pel-use-helm-lsp is turned on. swhen pel-use-lsp-ivy is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-origami is turned on. scustomizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done scandidates: <f9> okey sequence. sandidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>. 1 key prefix. seplaced with your selected prefix key. Display the log buffer of WORKSPACE. Validate performance settings and write report in a *lsp-performance* buffer. Ask the server to format this document.</m-f9></f9></f9></f9>
see also: • © Completion/Input • © Treemacs • Dide/Show LSP key bindings: • Isp-mode • erlang Is See also: © Input Method Display LSP workspace log buffer Validate LSP performance settings Reformat Erlang file Add directory to the list of workspace folders Remove a directory from the workspace	Helm by using helm-lsp lyy by using lsp-ivy treemacs by using lsp-origing lsp-origi	with: PEL activates PEL activ	swhen pel-use-helm-lsp is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s customizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done cf11> <f2> o key sequence. candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>1 key prefix. splaced with your selected prefix key. Display the log buffer of WORKSPACE. Validate performance settings and write report in a *lsp-performance* buffer. Ask the server to format this document. Add PROJECT-ROOT to the list of workspace folders. • Prompts for the directory.</m-f9></f9></f9></f2>
see also:	Helm by using helm-lsp lyy by using lsp-ivy treemacs by using lsp-origing lsp-origi	with: PEL activates PEL activ	swhen pel-use-helm-lsp is turned on. swhen pel-use-lsp-ivy is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-origami is turned on. scustomizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>1 key prefix1 key prefix1 key prefix1 key prefix1 key prefix held buffer of WORKSPACE. Validate performance settings and write report in a *lsp-performance* buffer. Ask the server to format this document. Add PROJECT-ROOT to the list of workspace folders Prompts for the directory. Remove PROJECT-ROOT from the workspace blacklist.</m-f9></f9></f9>
see also: • ∑ Completion/Input • ∑ Treemacs • ∑ Hide/Show LSP key bindings: • Isp-mode • erlang Is See also: ∑ Input Method Display LSP workspace log buffer Validate LSP performance settings Reformat Erlang file Add directory to the list of workspace folders Remove a directory from the workspace blacklist Remove directory from the list of workspace folders Find Identifier	Helm by using helm-lsp lyy by using lsp-ivy treemacs by using lsp-origing lsp-septime lsp-septi	with: PEL activates PEL activ	ages: show the number of modules implementing a behaviour. s when pel-use-helm-lsp is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s use outsomizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done 11 < 12 o key sequence. andidates: 19 and 11 fyou use 19 for Greek letters then consider using 14 key prefix. aplaced with your selected prefix key. Display the log buffer of WORKSPACE. Validate performance settings and write report in a *lsp-performance* buffer. Ask the server to format this document. Add PROJECT-ROOT to the list of workspace folders. Prompts for the directory. Remove PROJECT-ROOT from the workspace blacklist.
see also: • ∑ Completion/Input • ∑ Treemacs • ∑ Hide/Show LSP key bindings: • Isp-mode • erlang Is See also:	Helm by using helm-lsp Wy by using lsp-ivy treemacs by using lsp-origing lsp-origin	with: PEL activates PEL activ	s when pel-use-helm-lsp is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s customizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done t11> <f2> o key sequence. tandidates: <f2> o key sequence. tandidates: <f3> and C-1. If you use <f3> for Greek letters then consider using <m-f3>. I key prefix. placed with your selected prefix key. Display the log buffer of WORKSPACE. Validate performance settings and write report in a *lsp-performance* buffer. Ask the server to format this document. Add PROJECT-ROOT to the list of workspace folders. • Prompts for the directory. Remove PROJECT-ROOT from the workspace blacklist. Find definitions to the IDENTIFIER at point.</m-f3></f3></f3></f2></f2>
see also:	Helm by using helm-lsp Wy by using lsp-ivy treemacs by using lsp-origing lsp-origin	with: PEL activates PEL activ	swhen pel-use-helm-lsp is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s customizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done tf11> <f2> o key sequence. andidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>. 1 key prefix. splaced with your selected prefix key. Display the log buffer of WORKSPACE. Validate performance settings and write report in a *lsp-performance* buffer. Ask the server to format this document. Add PROJECT-ROOT to the list of workspace folders. • Prompts for the directory. Remove PROJECT-ROOT from the workspace blacklist. Find definitions to the IDENTIFIER at point. Find implementation locations of the symbol at point.</m-f9></f9></f9></f2>
see also: • ∑ Completion/Input • ∑ Treemacs • ∑ Hide/Show LSP key bindings: • Isp-mode • erlang Is See also:	Helm by using helm-lsp lyy by using lsp-ivy treemacs by using lsp-original by using lsp-keys with M-x customize-orger with M-x cus	with: PEL activates PEL activ	ages: show the number of modules implementing a behaviour. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s use modified through customization: change the lsp-keymap-prefix value. This can be done ifil> <f2> o key sequence. andidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>. I key prefix palaced with your selected prefix key. Display the log buffer of WORKSPACE. Validate performance settings and write report in a "lsp-performance" buffer. Ask the server to format this document. Add PROJECT-ROOT to the list of workspace folders. Prompts for the directory. Remove PROJECT-ROOT from the workspace blacklist. Find definitions to the IDENTIFIER at point. Find references to the IDENTIFIER at point.</m-f9></f9></f9></f2>

Description	<u>Keystroke</u>	Function	Note
Toggle current-line status information	s-1 T S	(Isp-ui-sideline-mode &optional ARG)	Minor mode for showing status information for current line. • Displays code status such as definition errors, etc
Toggle code action on modelling	s-1 T a	(Isp-modeline-code- actions-mode &optional ARG)	Toggle code actions on modeline.
Toggle headline breadcrumbs	s-1 T b	(Isp-headerline- breadcrumb-mode &optional ARG)	Toggle breadcrumb on headerline. • When active the list of directories are listed on the header line. In graphics mode these are buttons you can use to change directory.
Toggle hover information	s-1 T d	(Isp-ui-doc-mode &optional ARG)	Minor mode for showing hover information in child frame. When active, information about symbol at point is shown in a pop-up overlay area. In graphics mode the information has links that can be used to open web-located information. For small window the information may cover too much code, use this command to toggle in and out of view. Also note that when the point is toward the bottom of a window the information window may not show completely and you may have to scroll your window.
Toggle symbol highlighting	s-1 T h	(Isp-toggle-symbol- highlight)	Toggle symbol highlighting.
Toggle code-lens	s-1 T 1	(Isp-lens-mode &optional ARG)	Toggle code-lens overlays. • Code-lens show information like # times a specific function is referenced.
Execute code action	s-l a a	(Isp-execute-code- action INPUT0)	Execute code action ACTION. If ACTION is not set it will be selected from 'lsp-code-actions-at-point'. Request codeAction/resolve for more info if server supports.
Highlight all relevant references to symbol at point	s-1 a h	(Isp-document- highlight)	Highlight all relevant references to the symbol under point.
Click LSP lens via avy	s-1 a 1	(Isp-avy-lens)	Click lsp lens using 'avy' package. • The code lens must be active. Use s-1 T 1 to activate it if it's not active.
Apropos search for symbol/regexp	s-1 g a	(xref-find-apropos PATTERN)	Find all meaningful symbols that match PATTERN. Can be used to search symbol outside project. The argument has the same meaning as in 'apropos'. The result is shown in a *xref* buffer.
Find definitions of symbol at point	s-1 g g	(Isp-find-definition &key DISPLAY-ACTION)	Find definitions of the symbol under point.
Find implementations of symbol at point	s-l g i	(Isp-find- implementation &key DISPLAY-ACTION)	Find implementations of the symbol under point.
Find references of symbol at point	s-1 g r	(Isp-find-references &optional INCLUDE- DECLARATION &key DISPLAY-ACTION	Find references of the symbol under point. • The result is shown in a *xref* buffer.
Trigger display hover information	s-1 h g	(Isp-ui-doc-glance)	Trigger display hover information popup and hide it on next typing.
Display documentation of symbol at point in *lsp-help*	s-1 h h	(Isp-describe-thing-at- point)	Display the type signature and documentation of the thing at point. • Display help about symbol at point inside a *Isp-help* buffer. • Useful in terminal mode as you can navigate inside the buffer and used other functions to open identified URL references.
Refactor source import	s-1 r o	(Isp-organize-imports)	Perform the source.organizeImports code action, if available.
Rename symbol at point See also: Search/Replace	s-1 r r	(Isp-rename NEWNAME)	Rename the symbol (and all references to it) under point to NEWNAME. For renaming the arguments of a function, the <u>iedit mode</u> is more appropriate. It supports restricting the scope to the current function. See <u>Search/Replace</u>
Disconnect LSP	s-1 w D	(Isp-disconnect)	Disconnect the buffer from the language server.
Describe LSP session	s-1 w d	(Isp-describe-session)	Describes current 'Isp-session'. • Show available tools and the available capabilities • Shows the information inside a LspBrowser buffer.
Shut LSP workspace down	s-1 w q	(Isp-workspace- shutdown WORKSPACE)	Shut the workspace WORKSPACE and the language server associated with it
Restart LSP workspace	s-1 w r	(Isp-workspace-restart WORKSPACE)	Restart the workspace WORKSPACE and the language server associated with it
Activate LSP	s-1 w s	(Isp &optional ARG)	Entry point for the server startup. When ARG is t the lsp mode will start new language server even if there is language server which can handle current language. When ARG is nil current file will be opened in multi folder language server if there is such. When 'lsp' is called with prefix argument ask the user to select which language server to start.
Treemacs support • ∑x Treemacs	provide extra features that help	p Erlang development. Whe	respectively activated by PEL user-options pel-use-treemacs and pel-use-lsp-treemacs , en these are activated PEL provides bindings for the lsp-treemacs features. s customization group. With PEL use sf12> wwsf12> wsf12> w

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Open LSP Treemacs type hierarchy window	<f12> w t</f12>	(Isp-treemacs-type- hierarchy DIRECTION)	Show the type hierarchy for the symbol at point. • With prefix 0 show sub-types. • With prefix 1 show super-types. • With prefix 2 show both. This is not implemented for Erlang.
Rendering markup embedded in comments	The following commands are used to create images from specific markup code embedded inside Erlang source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example. You can also use Graphviz, see M Graphviz Dot		
Preview UML diagram	<f12> u</f12>	(pel-render-	Render the PlantUML markup embedded in current mode comment.
from plantUML source in current plantUML region of commented source code See also: M PlantUML	<f11> SCP e u</f11>	commented-plantuml PREFIX &optional POS)	 Use region if identified otherwise use PlantUML block at point. Uses prefix (as PREFIX) to choose where to display it: 4 (when prefixing the command with C-u) -> new window 16 (when prefixing the command with C-u C-u) -> new frame. else -> new buffer This can be used inside buffer using any major mode, when PlantUML markup is embedded
	PlantUML block and issuing th	is command.	inside source code comment. cture with PlantUML markup, then generate the UML rendering by moving point inside the stivated by pel-use-plantuml user option being non-nil.

Emacs & Erlang - References

Document	Notes			
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.			
Erlang versions	Erlang Versions - Version Scheme Erlang Support, Compatibility, Deprecations, and Removal			
Erlang/OTP @ Github	Erlang source code			
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, <u>Erlang</u> <u>Issue Tracker</u> , events.			
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.			
Erlang/BEAM	Erlang was the first of one of several programming language that runs on the BEAM VM.			
Good introduction presentations on Erlang	The soul of Erlang and Elixir Saša Jurić GOTO 2019 A very good presentation that captures the essence of why Erlang is so important. Fast pace. A must see. A great presentation to show people that may be reluctant to use the technology. The Do's and Don'ts of Error Handling Joe Armstrong GOTO 2018			
Erlang References				
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.			
A Concise Guide to Erlang	A very nice quick reference. From David Matuszek, University of Pennsylvania			
Erlang Code Guidelines				
Erlang Programming Rules and Conventions	Official Ericsson AB Erlang guidelines.			
Inaka's Erlang Coding Standards & Guidelines	Guideline used at Inaka, published on Github.			
EDoc User's Guide	Describes how to document code. Comments should conform to the Edoc comment style and format.			
2600Hz Erlang Documentation Guideline	An example of a corporate Erlang Documentation Guideline.			
Erlang Books	There are several printed and online Erlang books. Erlang's FAQ lists several of them. The following lists some extra ones.			
Adopting Erlang	A great and recent (2019 and later) online books on Erlang Development that provides information not available in the Erlang introduction books. Describes how to install Erlang, and how to setup editing tools. A must read to setup Erlang development. This is still work in progress as of May 2020. Each page has a date time stamp.			
Erlang Information Sites				
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.			
about-erlang trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang. • about-erlang provides general information about Erlang, including: • Learning Erlang, a table with links to resources to learn Erlang. • Installing Erlang, describes various ways to install Erlang on macOS. • Tools for Erlang, describes tools you can use for Erlang development.			
Emacs and Erlang Man files				
How to create a local whatis file	Show how to create a missing whatis file for a set of man pages.			
The Erlang mode for Emacs (user guide) Erlang mode for Emacs (man page) The Erlang mode for Emacs (man page) The Erlang mode for Emacs (man page)	On the erlang.org site. Start here. Describes the 2 files (erlang.el and erlang-start.el) provided by the Erlang mode support, how to set them up for various operating systems. Note, however, that PEL provides the setting for you. It also provides an overview of the various features the package provides. If found bugs in the erlang-man page in the Edit-Moving the marker section. 1) it's the point that is moved, not the marker, 2) C-a is not an Emacs key prefix, so their key binding descriptions like C-a M-a and C-a M-e are invalid. Reported as ERL-1314 . There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric functions and variables. The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -> on a function definition line. Another issue: inside the OS-level erlang shell, we can tab-completion a module:function string, but that does not work inside the emacs erlang shell.			

Document	Notes
Emacs tools for Erlang	
<u>EDTS</u>	EDTS: stands for: The Erlang Development Tool Suite. See also: • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube • EDTS: • configure your project • One Primary EDTS node • 1 node per open project • To setup an Erlang project: a .edts file in the project: : name "my-project" : otp-path "path/to/otp" : node-name "project-node-name" : lib-dirs '("lib" "deps")
How to install EDTS	Describes some aspects of EDTS and links that may be useful. Lists the requirements. After installing EDTS, I got several compile errors, and had to install the following other modules: - auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?
Language Server Protocol	Language Server Protocol @ Wikipedia Language Server Protocol Specifications web site Language Server Protocol @ Github
LSP for Erlang	LSP support for Erlang is done using the following: The Isp-mode Emacs Lisp package The erlang Is Erlang server
company-mode ; Modular in-buffer completion framework for Emacs	
Using Tags with Erlang	
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the pel-erlang-shell-prevent-echo is set to t. To activate after setting it: execute pel-init or restart Emacs.