## **Buffers**

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>		
Emacs Buffers  • List Buffers  • Switch to Buffer		ds you can use to list and manage buffers.  or-buffer customization group to control some aspect of Emacs buffers. The user options are:			
<ul> <li>Navigate through buffers in current window</li> <li>Cycle through</li> </ul>	pel-use-uniquify :	: activates <u>uniquify</u> to that buffer names show the distinguishing directory after the file name, like this: <b>fname dir</b> : activates <b>activates</b> activates a			
<ul><li><u>buffers using same</u></li><li><u>major mode</u></li><li><u>Buffer Selection</u></li></ul>	☑ pel-use-fzf	: activates package which provides fast fuzzy search on buffer name (but also file finders, see File-mngt)			
Manage Buffers     Accumulate Text     Diff buffer with its file     Locking Buffer     Indirect Buffers     Buffer View Mode	pel-use-nhexl-mode pel-use-popup-switche PEL also provides a Hydra th	activates if iflipb external package. Also activates the hydra external package APEL sets pel-use-hydra option to t.  activates inhexi-mode external package used to display and manipulate the content of the current buffer in hexadecimal.  by popup-switcher external package used for popping up a list of buffers.  at manipulates Emacs windows and buffers. See the Windows table for its description.			
Edit Binary File: hexl, nhexl	Also see <u>∑ ibuffer-mode</u>				
Open this PDF file. See also: <u>ℤ Help/Info</u>	<f11> b <f1></f1></f11>	(pel-help-pdf &optional OPEN- WEB-PAGE)	Open the <u>Note Buffers</u> local PDF. If the prefix argument (like <b>C-u</b> or <b>M</b> ) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> useroption is set it's the other way around.		
<u> ▼ Customize</u> PEL Buffer Support	<f11> b <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL Buffer support: open PEL buffer support specific group.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in other window.		
∑ Customize Emacs & external package buffer support	<f11> b <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs and external packages related to buffer. This includes the following customize groups: Buffer-menu, bs, ibuffer, iflipb, minibuffer, hexl, nhexl, popup-switcher. When a prefix argument (like <b>C-u</b> ) opens the buffer inside another window.  • If required file is not already loaded, PEL prompts to load and access its customization.		
List Buffers	<ul> <li>buffer-menu-open is a</li> <li>psw-switch-buffer is a</li> </ul>	drop-down hiererchical menu pop-up menu.	buffers inside a dedicated buffer/window and provides a set of commands.		
Open buffer menu	• C- <f10> • C-<down-mouse-1></down-mouse-1></f10>	(buffer-menu-open)	Start key navigation of the buffer menu.  • List buffers in a drop-down menu: lists the buffers by major-mode when several buffers		
See also: <u>I Menus</u>	C-\down-mouse-12		of the same major-mode are opened.  In graphics mode this can also be invoked using the C- <down-mouse-1></down-mouse-1>		
List open buffers in popup menu	<f11> b b</f11>	( <b>psw-switch-buffer</b> & optional ARG)	Show buffers list menu to switch buffer in a popup window menu.  • If ARG show only buffers with files and without * in the beginning/end of buffer name.  • Requires popup-switcher 2 PEL activates when pel-use-popup-switcher is t.		
<u>List all buffers</u> using <u>Buffer Menu Mode</u>	• C-x C-b • M-x buffer-menu	(list-buffers &optional ARG)	<ul> <li>Switch to the Buffer Menu.</li> <li>By default, the Buffer Menu lists all buffers except those whose names start with a space (which are for internal use). With prefix argument ARG, show only buffers that are visiting files.</li> <li>In the Buffer Menu, the first column (denoted "C") shows "." for the buffer from which you came, "&gt;" for buffers you mark to be displayed, and "D" for those you mark for deletion.</li> <li>The "R" column has a "%" if the buffer is read-only.</li> <li>The "M" column has a "*" if it is modified, or "S" if you have marked it for saving.</li> <li>The remaining columns show the buffer name, the buffer size in characters, its major mode, and the visited file name (if any).</li> </ul>		
Buffer Menu Mode keys	M- <del> : Remove a spe     u : unmark all ma     x : execute mark     - : mark buffer as     it toggle read-or     it display emacs     2 : Display this but     o : replace other     m : mark buffer to</del>	list list list list list or in list or in list or deletion r deletion r deletion r deletion cous line, remove all marks on buffer decific mark from all buffers orks on buffer ed commands (delete buffers marke s un-modifiable only s in full emacs screen uffer & next in horizontal window (next) window with this buffer be displayed in windows s marked with in as many windows a	: immediately : immediately : immediately : immediately : immediately : immediately : when pressing v		
List buffers using iBuffer  Mode  ★★  See ∑ ibuffer-mode	С-х С-ь	(ibuffer & optional OTHER- WINDOW-P NAME QUALIFIERS NOSELECT SHRINK FILTER- GROUPS FORMATS)	<ul> <li>Begin using lbuffer to show, edit and operate on a list of buffers.</li> <li>PEL binds 'ibuffer' to C-x C-b key sequence.</li> <li>ibuffer provides more functionality, working like dired, allowing to sort by name, size mode, filtering by mode (hit return on the mode of a buffer). Type <f1> m to get th list of possible actions that can be done on the listed buffers.</f1></li> <li>See <u>Sibuffer-mode</u> for more information on commands available in ibuffer-mode.</li> </ul>		
Switch to Buffer	The switch-to-buffer comm	and uses a prompt at the bottom of	the frame.		
Switch to buffer See also: <u>▼ Completion/</u> Input	С-х b	(switch-to-buffer BUFFER-OR- NAME &optional NORECORD FORCE-SAME-WINDOW)	Switch window to display the previous, or another buffer (entered at echo area prompt).  The invisible buffers have a name that start with a space. To see them type space and tab and a list of those buffers will appear before the list of visible buffers.  To show what is currently used, type: <f11> M-c?  To change the main completion mode, type: <f11> M-c <f4>  See © Completion/Input for more information.</f4></f11></f11>		
Switch buffer with fzf See also: <u>E File-mngt</u>	<f11> b z</f11>	(fzf-switch-buffer)	Switch buffer in current window by selecting it with fzf.  • Uses the fzf command line utility for fast & flexible search.    Requires the fzf.el external package   activated by pel-use-fzf.		

<u>Operation</u>	<u>Keystroke</u>	Function	Note			
Navigate through Buffers in current window	To gain access to the keys     Then type the keys listed i	er <u>Hydra</u> the gives quick access to commands that changes the buffer shown in the current window.  rs, type <f7> <f9> key sequence to start the pel-∑buffer Hydra.  in the Hydra table below. Stop the Hydra with <f7> rnal package  PEL provides Hydra when pel-use-hydra or the pel-use-iflipb user option is set to t.</f7></f9></f7>				
Activate the pel-∑buffer Hydra	* <f7> <f9></f9></f7>	Buffer   Buffer Se	election	Flip	Same Mode	Other
**		M-n: next   M: next   M-p: prev   M-,: prev   M-,: prev   M-v: view		<f9>: next S-<f9>: prev M-k: kill</f9></f9>	]: next [: previous	?: hint   <f7>: cancel</f7>
0 = Wr		n the pel-∑buffer Hydra is active. The Hydra menu shows at the bottom of the frame. Type ? to toggle displaying it.				
• Next/Previous	§ You may wan to switch to the <u>pel-∑wnd Hydra</u> to change and manage window(s) by typing <f7> <f7> followed by # or any cursor key.  The following commands change current buffer to next or previous buffer, or to what was used last.  The commands are accessible through the pel-∑buffer Hydra when the <u>hydra</u> package is used. They are also always available from global key sequences.</f7></f7>					
Buffer Switch to next buffer	• C-x <right> • C-x C-<right> • <f11> b n</f11></right></right>	(next-buffer)		uffer displayed in the cu		giobal rey sequences.
Switch to previous buffer	* <f7> <f9> M-n  • C-x <left> • C-x C-<left> • <f11> b p  * <f7> <f9> M-p</f9></f7></f11></left></left></f9></f7>	(previous-buffer)	Switch to the previous buffer displayed in the current window.  • This command is also available in the pel-∑buffer Hydra as M−p		,	
Switch to previous buffer in window	<f11> b 1 * <f7> <f9> M-1</f9></f7></f11>	(pel-switch-to-last-used – buffer)	Switch buffer in curr Used twice returns t	rent window to the buffe to the same buffer.	er previously seen in this	s window.
Flip to next/ previous recently visited buffer	The following commands let you flip between recently visited buffers in a way that resembles what Alt-Tab and Alt-Shift-Tab does on Windows.  • A list of buffers is shown in the minibuffer at the bottom of the screen when you use the command. You can see them in the pel-∑buffer Hydra above.  • You can also identify buffer filtering in the iflipb customization group (use <f11> b <f3> and select iflipb to access it).  This requires the iflipb external package PEL activates it when pel-use-iflipb user-option is turned on (set to t). This also forces activation of the hydra package because the iflipb commands are bound to the pel-∑buffer Hydra. allowing quick single keystroke access without the use of a prefix key.</f3></f11>			ouffer Hydra above.		
Flip to next buffer	* <f7> <f9> <f9></f9></f9></f7>	(iflipb-next-buffer ARG)	Flip to the next buffer in the buffer list.  Consecutive invocations switch to less recent buffers in the buffer list.  Buffers matching 'iflipb-always-ignore-buffers' are always ignored.  Without a prefix argument, buffers matching 'iflipb-ignore-buffers' are also ignored.			d.
Flip to previous buffer	* <f7> <f9> S-<f9></f9></f9></f7>	(iflipb-previous-buffer)		Flip to the previous buffer in the buffer list.  Consecutive invocations switch to more recent buffers in the buffer list.		
Kill buffer (but keep the flip buffer state)	* <f7> <f9> M-k</f9></f7>	(iflipb-kill-buffer)	Same as 'kill-buffer' but keep the iflipb buffer list state.			
Cycle Trough buffers using same major-mode	The following 2 PEL commands cycle the buffers using the same major mode inside the current window.  • This works with any mode, including special buffer modes.  d The key bindings that start with <f7> <f9> starts a pel-∑buffer Hydra. After the initial key sequence, single key commands are available.</f9></f7>					
Show next buffer using same major mode	• <f11> b ] * <f7> <f9> ]</f9></f7></f11>	(pel-smb-next &optional REFRESH)  Open next buffer of same major-mode from the registered list.  • Refresh list when wrapping. With optional prefix argument: REFRESH the list		RESH the list of buffers.		
Show previous buffer using same major mode	• <f11> b [ * <f7> <f9> [</f9></f7></f11>	(pel-smb-previous &optional REFRESH)				RESH the list of buffers.
Buffer Selection	The Buffer Selection commands key bindings are also available through the pel-∑buffer Hydra when the <u>hydra</u> package is used.  • These commands are using the built-in <u>bs.el</u> library. PEL provides extra commands that extends it.					
Show next buffer in selection	• <f11> b . * <f7> <f9> M</f9></f7></f11>	(pel-bs-next)	Show next buffer in current window.  Next buffer is selected by the list of buffers selected by the Buffer Selection Mode configuration and sorting order last identified. These can be controlled by opening Buffer Selection Mode with the bs-show command and then using the commands available in this mode, such as: bs-select-next-configuration, bs-toggle-show-a and bs-show-sorted.		trolled by opening the ng the commands	
Show previous buffer in selection	• <f11> b , * <f7> <f9> M-,</f9></f7></f11>	(pel-bs-previous)	Show previous buffer in current window.  Next buffer is selected by the same criteria as for pel-bs-next described above.		escribed above.	
Customize buffer selection	• <f11> b S</f11>	(bs-customize)	Customization of group bs for Buffer Selection Menu.  • Active configuration can be changed in the bs-show buffer. See below.		below.	
Show Buffer Selection	• <f11> b s</f11>	(bs-show ARG)	Open the <b>bs-mode</b> buffer by splitting the current window  Shows menu of buffers to select and manipulate buffers.  With no prefix argument: show buffers selected by the <b>default</b> configuration.  If a <b>C-u</b> prefix argument: show buffers selected by <b>alternative</b> configuration.  With numeric argument ( <b>M-1</b> , <b>M-2</b> ,) show buffers selected by the <b>nth</b> configuration.  The pre-configured configurations are: all, files, file-and-scratch, all-intern-last.		onfiguration. the <b>nth</b> configuration.	
Buffer Selection Menu (bs-mode) commands	There are many key commands similar to 'Buffer-menu-mode' for manipulating the buffer list and the buffers themselves. User can move with [up] or [down], select a buffer by RET or [SPC] Type q to leave Buffer Selection Menu without a selection. Type ? after invocation to get help on commands available. With prefix argument ARG show a different buffer list. Function 'bsconfiguration-name-for-prefix-arg' determine accordingly name of buffer configuration.					
Select current line's buffer : visit buffer	• RET • SPC • f	(bs-select)	Select current line's buffer and other marked buffers.  • If there are no marked buffers the window configuration before starting Buffer Selecti Menu will be restored. If there are marked buffers each marked buffer and the current line's buffer will be selected in a window.  • Leave Buffer Selection Menu.			
View current line's buffer	v	(bs-view)	View current line's buffer in View mode. A minor mode for viewing text but not editing it.  See Buffer View Mode below in this table.  Leave Buffer Selection Menu.			ext but not editing it.
Move point down	• n • <down></down>	(bs-down ARG)	Move point vertically down ARG lines in Buffer Selection Menu.			
Move point up	• p • <up></up>	(bs-up ARG)	Move point vertically up ARG lines in Buffer Selection Menu.			
Refresh Buffer Selection Menu	g	(bs-refresh &rest IGNORED)	Refresh whole Buffer Selection Menu.			
Bury buffer	b	(bs-bury-buffer)	Bury (not kill!) the bu	uffer on this line: move it	t to the end of buffer list	i.

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Cycle through buffer line sorting method	s	(bs-show-sorted)	Show buffer list sorted by next sort aspect.  • The sort methods supported are: by name, by size, by mode, by filename, by nothi (not sorted).	
Toggle show all buffers	a	(bs-toggle-show-all)	Toggle show all buffers / show buffers with current configuration.	
Cycle through buffer selection configuration: types of buffers iterated through	С	(bs-select-next-configuration &optional START-NAME)	Apply next configuration START-NAME and refresh buffer list.  If START-NAME is nil the current configuration 'bs-current-configuration' will be used.  Cycles through the following methods of buffer cycling: all, files, files-and-scratch, all-intern-last	
Prompt for buffer selection configuration	С	(bs-set-configuration-and-refresh)	Ask user for a configuration and apply selected configuration.  • Supports tab-based completion.  • Refresh whole Buffer Selection Menu.	
Add a new configuration to display only buffers of this major mode		(pel-bs-this-mode-only)	Add a Buffer Selection configuration for buffer of this mode only.  Add a Buffer Selection that will be named "only-X" where X is the major mode of the current line buffer.  This configuration will only show buffers that use the same major mode.	
	1. Open the Buffer Sele 2. Move point to a buffe 1. If that mode is cu 3. Hit • to execute pel 4. Hit RET to display the	s of a specific major mode only, do this: ection Mode buffer: execute bs-show: type <f11> b s fer line of the wanted major-mode. currently not displayed, change the configuration to all by typing C all RET first and then move point to the proper line. el-bs-thi-mode-only and select the major mode of interest. he buffer and dismiss the Buffer Selection Mode buffer. r previous buffer of the same major mode activate the pel-\(\subseteq\)buffer Hydra by typing <f7> <f9> M or <f7> <f9> M-, and</f9></f7></f9></f7></f11>		
Open selected buffer in other window	o	(bs-select-other-window)	The window configuration before starting Buffer Selection Menu will be restored unless there is no other window. In this case a new window will be created.  • Leave Buffer Selection Menu.	
Open selected buffer in other window - stay in Buffer Selection buffer	C-0	(bs-tmp-select-other-window)	Make the other window select this line's buffer.  The current window remains selected.	
Save buffer	s	(bs-save)	Save buffer on current line.	
Kill buffer	k	(bs-delete)	Kill buffer on current line.	
Toggle buffer read- only status	ે જે	(bs-toggle-readonly)	Toggle read-only status for buffer on current line.  • Uses function 'read-only-mode'.	
Clear buffer modified-flag	-	(bs-clear-modified)	Set modified flag for buffer on current line to nil.  A Be sure you don't want to save these modifications:  Emacs won't prompt you for that modified buffer when closing.	
Visit tags table file	t	(bs-visit-tags-table)	Visit the tags table in the buffer on this line. See 'visit-tags-table' bound to <f11> x t in PEL. See Xref - Cross References.</f11>	
Mark line's buffer to be displayed	m	(bs-mark-current COUNT)	Mark buffers. Move point vertically down COUNT lines.  • COUNT is the number of buffers to mark.	
Mark line's buffer to show always	+	(bs-set-current-buffer-to-show- always &optional NOT-TO- SHOW-P)	<ul> <li>Toggle status of buffer on line to 'always shown'.</li> <li>NOT-TO-SHOW-P: prefix argument.</li> <li>With no prefix argument the buffer on current line is marked to show always.</li> <li>Otherwise it is marked to show never.</li> </ul>	
Toggle line's buffer show always/never/ normal	М	(bs-toggle-current-to-show)	Toggle status of showing flag for buffer in current line through: never show, always show, show normally	
Unmark previous line buffer to be displayed	DEL	(bs-unmark-previous COUNT)	Unmark previous COUNT buffers.  • Move point vertically up COUNT lines.  • When called interactively a numeric prefix argument sets COUNT.	
Unmark line's buffer to be displayed	u	(bs-unmark-current COUNT)	Unmark buffers. Move point vertically down COUNT lines.  • COUNT is the number of buffers to unmark.	
Unmark all buffer lines	U	(bs-unmark-all)	Unmark all buffers.	
Scroll right	• > • C-x >	(scroll-right &optional ARG SET-MINIMUM)	Scroll selected window display ARG columns right.  • Default for ARG is window width minus 2.	
Scroll left	• < • C-x <	(scroll-left &optional ARG SET-MINIMUM)	Scroll selected window display ARG columns left.  • Default for ARG is window width minus 2.	
Close Buffer- Selection-Menu	• q • C-c C-c	(bs-kill)	Let buffer disappear and reset window configuration.	
Abort	• C-g • C-]	(bs-abort)	Ding and leave Buffer Selection Menu without a selection.	
Display Help	?	(bs-help)	Display help in the Help buffer.  ⚠ This conflicts with PEL pel-∑buffer hint key which takes precedence.	
Manage Buffers	The following commands sup	pport buffer management: display int	formation, change read-only mode, clone buffer, rename buffer, kill buffer, etc	
Show name of previous buffer in window	<f11> b ?</f11>	(pel-show-window-previous- buffer)	Show the name of previous buffer used in the current window.	
Show all buffers, including internal hidden buffers	<f11> b a</f11>	(pel-show-all-buffers &optional FILES-ONLY)	Display all buffers, including hidden internal buffers, listed inside a *Buffer List* buffer.  • If the optional FILES-ONLY argument is set then it displays only buffer associated with files. Interactively, use C-u.  • Do not manipulate internal buffers unless you understand the consequences. This command should not be used by Emacs novices. It is meant as an aid for Emacs Lisp code development.	
Toggle read-only status of buffer	• C-x C-q • <f11> b r</f11>	(read-only-mode &optional ARG)	When the buffer is in read-only mode the mode line shows '%%' on the left side, in the 'ch' area of "cs:ch-fr buf pos line (major minor)".  The manual states: "For a read-only buffer, it shows '%*' if the buffer is modified, and '%%' otherwise."  ■ See also: the View Mode activating commands toward the end of this table.  • A buffer in View Mode cannot be modified.  • The View Mode may be used to ensure that no modifications are made to a buffer (visiting a file or not).	

	<u>Keystroke</u>	Function	<u>Note</u>	
Clone buffer	<f11> b c</f11>	(clone-buffer &optional NEWNAME DISPLAY-FLAG)	Create and return a twin copy of the current buffer.  • Unlike an indirect buffer, the new buffer can be edited independently of the old one (if it is not read-only). NEWNAME is the name of the new buffer. It may be modified by adding or incrementing <n> at the end as necessary to create a unique buffer name.  • For example if buffer *Help* is opened it opens another one named *Help*&lt;2&gt; (or *Help*&lt;3&gt; if *Help*&lt;2&gt; already exists, etc)</n>	
Rename a buffer	<f11> b R</f11>	(rename-buffer NEWNAME &optional UNIQUE)	If UNIQUE argument is non-nil via C-u M-x rename-buffer, the name is auto generated to be unique.	
Rename buffer - use unique name	<f11> b U</f11>	(rename-uniquely)	Rename the current buffer by adding ' <number>' to the end.  • Use this if you want multiple *Buffer* or *Info* buffers for example.  • Example: StackExchange: How can I have multiple help buffer with different content</number>	
Kill current buffer  See also:   Windows	• <f11> b k • %-k • %-&amp;</f11>	(kill-current-buffer)	<ul> <li>Kill (close) the current buffer. Does not prompt if there is no change in the buffer.</li> <li>PEL also provides a window management Hydra with ability to kill the current buffer.</li> <li>See <u>S Windows</u> for more info.</li> </ul>	
Kill buffer See also: <u>∑ Windows</u>	• C-x k * <f7> k</f7>	(kill-buffer &optional BUFFER-OR-NAME)	Kill (close) the current buffer. Prompt to identify a buffer unless inside a Window Hydra which does not prompt.	
Kill current buffer and close window See also:   Windows	• C-x 4 0 * <f7> K</f7>	(kill-buffer-and-window)	Kill the current buffer and delete the selected window.  • PEL also provides a window management Hydra when the <a href="hydra">hydra</a> package is used. with ability to kill the current buffer and close windows in separate operations.	
Kill some buffer		(kill-some-buffers &optional LIST)	Kill some buffers. Asks the user whether to kill each one of them.	
Delete all windows of a specific buffer		( <b>delete-windows-on</b> &optional BUFFER-OR-NAME FRAME)	Deletes all windows showing BUFFER-OR-NAME, by calling 'delete-window' on those windows.	
Accumulating Text	Emacs provides the following	commands to insert text in buffer for	rom various sources.	
Append region to specified buffer	<f11> b M-a</f11>	(append-to-buffer BUFFER START END)	Append to specified BUFFER the text of the region.  The text is inserted into that buffer before its point.  BUFFER can be a buffer or the name of a buffer; this function will create BUFFER if it doesn't already exist.	
Prepend region to specified buffer	<f11> b M-p</f11>	(prepend-to-buffer BUFFER START END)	Prepend to specified BUFFER the text of the region.  The text is inserted into that buffer after its point.  BUFFER can be a buffer or the name of a buffer; this function will create BUFFER if it doesn't already exist.	
Copy region to specified buffer (replacing old content)	<f11> b C-c</f11>	(copy-to-buffer BUFFER START END)	Copy to specified BUFFER the text of the region.  The text is inserted into that buffer, replacing existing text there.  BUFFER can be a buffer or the name of a buffer; this function will create BUFFER if it doesn't already exist.	
Insert content of specified buffer at point	<f11> b i</f11>	(insert-buffer BUFFER)	Insert after point the contents of BUFFER.  • Puts mark after the inserted text.  • BUFFER may be a buffer or a buffer name.	
Append region's text to specified file	<f11> b f</f11>	(append-to-file START END FILENAME)	Append the contents of the region to the end of file FILENAME.  • This does character code conversion and applies annotations like 'write-region' does.	
	Use these commands to see See also: <u>S Diff &amp; Merge</u>	commands to see the difference between the buffer and its file when a buffer is rising a file and the changes were not saved back to the file.  Diff & Merge		
Diff buffer with its file	• <f11> b = • <f11> d b</f11></f11>	(diff-buffer-with-file &optional BUFFER	View the differences between BUFFER and its associated file.  • This requires the external program 'diff' to be in your 'exec-path'.	
edit buffer with its file	• <f11> b M-= • <f11> d e b f</f11></f11>	(ediff-current-file)	Start ediff between current buffer and its file on disk.  This command can be used instead of 'revert-buffer'.  If there is nothing to revert then this command fails.	
Locking Buffer	Lock a buffer against: exit, kil	Il or all (both) to prevent accidental k	illing of the buffer. Controlled by 'emacs-lock-default-locking-mode' normally set to all.	
Toggle emacs lock- mode	<f11> b L</f11>	(emacs-lock-mode &optional ARG)	Toggle Emacs Lock mode in the current buffer. With prefix arg: prompt for locking mode.  • Normally set to all: buffer locked against killing buffer and exiting Emacs.	
Indirect Buffers	As described in <a href="Emacs Indirect Buffer section">Emacs Indirect Buffer section</a> , "an indirect buffer shares the text of some other buffer, called the base buffer of the indirect buffer.  • In some ways it is a buffer analogue of a <b>symbolic link</b> between files.  • The text of the indirect buffer is always identical to the text of its base buffer; changes made by editing either one are visible immediately in the other.  • But in all other respects, the indirect buffer and its base buffer are completely separate.  • They can have different names, different values of point, different narrowing, different markers, different major modes, and different local variables."			
			but want to narrow an area in 1 buffer while seeing the complete text in the other window.	
Create indirect buffer explicitly	<f11> b I m</f11>	(make-indirect-buffer BASE- BUFFER NAME &optional CLONE)	<ul> <li>Create and return an indirect buffer for buffer BASE-BUFFER, named NAME.</li> <li>BASE-BUFFER should be a live buffer, or the name of an existing buffer.</li> <li>NAME should be a string which is not the name of an existing buffer.</li> <li>Optional argument CLONE non-nil means preserve BASE-BUFFER's state, such as major and minor modes, in the indirect buffer.</li> <li>CLONE nil means the indirect buffer's state is reset to default values.</li> </ul>	
Create indirect buffer of current buffer	<f11> b I c</f11>	(clone-indirect-buffer NEWNAME DISPLAY-FLAG &optional NORECORD)	Create an indirect buffer that is a twin copy of the current buffer.	
	<ul> <li>Give the indirect buffer name NEWNAME. Interactively, read NEWNAME from the minibuffer when invoked with a prefix arg. If NEWNAME sourced with a prefix arg, NEWNAME defaults to the current buffer's name. The name is modified by adding a '<n>' suffix to it or by increin an existing suffix. Trying to clone a buffer whose major mode symbol has a non-nil 'no-clone-indirect' property results in an error.</n></li> <li>DISPLAY-FLAG non-nil means show the new buffer with 'pop-to-buffer'. This is always done when called interactively.</li> <li>Optional third arg NORECORD non-nil means do not put this buffer at the front of the list of recently selected ones.</li> </ul>			
Create indirect buffer of current buffer in another window	• C-x 4 c • <f11> b I w</f11>	(clone-indirect-buffer-other- window NEWNAME DISPLAY- FLAG &optional NORECORD)	Like 'clone-indirect-buffer' but display in another window.	

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>		
Buffer View Mode		ffer, etc, see at top of this table) act	tivate the View Mode for a buffer where the buffer is essentially read-only and special		
	commands are available.  • Emacs commands editing the buffer contents are not available; instead, a special set of commands (mostly letters and punctuation) are defined for				
	moving around in the buffer.				
	<ul> <li>Space scrolls forward, Delete scrolls backward.</li> <li>Type H for a list of all View commands. See the View Mode command list below.</li> </ul>				
Prompt for buffer to	<f11> b V</f11>	(view-buffer BUFFER &optional	View BUFFER in View mode, returning to previous buffer when done.		
view in view-mode	-	EXIT-ACTION)	Prompt for buffer to open in view-mode.		
Toggle Buffer view-	<f11> b v</f11>	(view-mode &optional ARG)	Toggle view-mode.		
mode	* <f7> <f9> M-v</f9></f7>		<ul> <li>When View mode is enabled, commands that do not change the buffer contents are available as usual. Kill commands save text but do not delete it from the buffer. Most</li> </ul>		
			other commands beep and tell the user that the buffer is read-only.		
			<ul> <li>The <f7> <f9> M-v Hydra key sequence is available when the hydra package is used.</f9></f7></li> </ul>		
View Mode commands	H, h, ? Show this	s message.			
In view-mode no		refix arguments.			
modifications are	_	prefix argument. the beginning of buffer.			
allowed.	> move to	the end of buffer.			
		that buffer end is at last line of windoward "page size" lines. With prefix			
	DEL, S-SPC scroll bac	kward "page size" lines. With prefix	scroll backward prefix lines.		
		but with prefix sets "page size" to p			
		but with prefix sets "page size" to p ward "half page size" lines. With pre	fix, sets "half page size" to prefix lines and scrolls forward that much.		
			prefix, sets "half page size" to prefix lines and scrolls backward that much.		
	·	ward one line. With prefix scroll forw kward one line. With prefix scroll ba			
	F revert-bu	ffer if necessary and scroll forward.			
	•	e current line number. fix argument (default 100) percent int	o buffer		
		ne given by prefix argument (default			
	set the m				
	•	es point and mark. mark and pops mark ring.  Mark ring	is pushed at start of every successful search and when jump to line occurs.		
	The	mark is set on jump to buffer start or			
		ent position in character register. sition saved in character register.			
		rd incremental search.			
		e incremental search. forward for regular expression, starting after current page. ! and @ have a special meaning at the beginning of the regexp:			
		ns search for a line with no match fo			
		ans start search at beginning (end for			
		backward for regular expression, sta forward for last regular expression.	arting before current page.		
	p searches backward for last regular expression.				
	<ul> <li>q quit View mode, restoring this window and buffer to previous state. q is the normal way to leave view mode.</li> <li>e exit View mode but stay in current buffer. Use this if you started viewing a buffer (file) and find out you want to edit it.</li> </ul>				
	This command restores the previous read-only status of the buffer.				
	exit View mode, and make the current buffer editable even if it was not editable before entry to View mode.  quit View mode, restoring all windows to previous state.  quit View mode and maybe switch buffers, but don't kill this buffer.				
	c quit View				
	The effect of <b>c</b> , <b>q</b> and <b>C</b> dep				
	· ·				
	other-window, or M-x view				
<b>Edit Binary file</b>	Emacs provides the built-in hexl mode to edit files in hexadecimal mode. To use it you must:  • use the hexl-find-file to open the file in binary mode, or				
with <u>hexl</u>			buffer. To <b>exit</b> this mode and go back to the original mode type <b>C-c C-c</b>		
Open a file in hexl-mode	<f11> f M-x</f11>	(hexl-find-file FILENAME)	Edit file FILENAME as a binary file in hex dump format.		
See also: ∑ File-mngt			Switch to a buffer visiting file FILENAME, creating one if none exists, and edit the file in 'hexl-mode'.		
Toggle hext mode	<f11> b M-x</f11>	(hexl-mode &ontional ARG)			
<u>-                                 </u>	<b><f11> b M-x</f11></b> (hexl-mode & optional ARG) Toggle the hexl mode: a mode for editing binary files in hex dump format. • This is not an ordinary major mode; it alters some aspects of the current mode's behavior, but not all; also, you can exit Hexl mode and return to the		, , , , , , , , , , , , , , , , , , ,		
	previous mode using 'hex	-mode-exit'.			
			iat using the function 'hexlify-buffer'. imal) representing the offset into the file that the characters on this line are at and 16		
	characters from the file (d	splayed as hexadecimal values grou	ped every 'hexl-bits' bits, and as their ASCII values).		
			printable (control or meta characters) they will be replaced by periods.		
Insert a byte in decimal	C-M-d	(hexl-insert-decimal-char ARG)	Insert a character given by its decimal code ARG times at point.		
Insert a byte in octal	С-М-о	(hexl-insert-octal-char ARG)	Insert a character given by its octal code ARG times at point.		
Insert a byte in hex	С-М-х	(hexl-insert-hex-char ARG)	Insert a character given by its hexadecimal code ARG times at point.		
Goto 512-byte page	С-М-а	(hexl-beginning-of-512b-page)	Go to beginning of 512 byte boundary.		
Start  Goto to 512-byte page	C V o	(heyl-end-of 512h name)	Go to end of 512 byte boundary.		
Goto to 512-byte page end	С-М-е	(hexl-end-of-512b-page)	ao to tala oi o iz byte boullualy.		
Goto 1K end	C-x ]	(hexl-end-of-1k-page)	Go to end of 1KB boundary.		
Goto 1K end Goto 1K beginning	C-x ] C-x [	(hexl-end-of-1k-page) (hexl-beginning-of-1k-page)	Go to end of 1KB boundary.  Go to beginning of 1KB boundary.		
Goto 1K beginning	C-x [	(hexl-beginning-of-1k-page)	,		
	-		Go to beginning of 1KB boundary.		
Goto 1K beginning  Goto address entered in hexadecimal  Goto to address entered	C-x [	(hexl-beginning-of-1k-page) (hexl-goto-hex-address HEX-	Go to beginning of 1KB boundary.  Go to Hexl mode address (hex string) HEX-ADDRESS.  • Signal error if HEX-ADDRESS is out of range.  Go to hexl-mode (decimal) address ADDRESS.		
Goto 1K beginning Goto address entered in hexadecimal	C-x [ M-g	(hexl-beginning-of-1k-page) (hexl-goto-hex-address HEX-ADDRESS)	Go to beginning of 1KB boundary.  Go to Hexl mode address (hex string) HEX-ADDRESS.  • Signal error if HEX-ADDRESS is out of range.		

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Hexadecimal Editing with nhexl	The <a href="mailto:nhext-mode">nhext-mode</a> external package used to display and manipulate the content of the current buffer in hexadecimal and manipulate hex dump files.  PEL downloads installs and activates this package when the <a href="mailto:pel-use-nhext">pel-use-nhext</a> user option is set to <a href="mailto:to:thexadecimal mode">t.</a> • Use the <a href="mailto:state:thexadecimal mode">state:thexadecimal mode is on, turn it off by executing the nhext-mode command again.  • Good nhext-mode features:  • The nhext-mode keeps the undo history when you toggle the nhext mode. Something that the helx mode does not do.  • You can use all of the normal navigation commands. You don't need to use specialized commands. PEL home and end commands work.</a>			
Toggle buffer between normal and hex display	<f11> b x</f11>	(nhexl-mode &optional ARG)	Toggle minor mode to edit files via hex-dump format.  Requires the <a href="mailto:nhexl-mode">nhexl-mode</a> package <a href="mailto:nhexl-mode">nhexl-mode</a> a package <a href="mailto:nhexl-mode">nhexl-mode</a> a package <a href="mailto:nhexl-mode">nhexl-mode</a> package <a href="mailto:nhexl-mode">nhexl-mode</a> package <a href="mailto:nhexl-mode">nhexl-mode</a> package <a href="mailto:nhexl-mode">nhexl-mode</a> package <a href="mailto:nhexl-mode">nhexl-mod</a>	
Activate Hex nibble editing mode	<f11> b X</f11>	(nhexl-nibble-edit-mode &optional ARG)	Minor mode to edit the hex nibbles in 'nhexl-mode'.  Note: only works after nhexl-mode has been activated once.  Requires the <a href="mailto:nhexl-mode">nhexl-mode</a> package <a href="mailto:activated">activated when pel-use-nhexl</a> user option is t.	