## **Emacs support for the Erlang Programming Language**

<u>Description</u>	Keystroke	Function	lang Programming Language
Erlang Support		Erlang and Erlang Tools via t	he <u>erlang.el</u> external package (see <u>erlang.el source</u> ) and some other packages.
• <u>See also:</u>	PEL activates Erlang support PEL customization for Erland	ort via the customize user opting: is in the pel-pkg-for-erlar	ion variable pel-use-erlang. It must be set to t to activate support for Erlang.  ing group. Key bindings: global: <f11> SPC e <f2>, from an Erlang buffer: <f12> <f2>.  control Erlang editing. Only some of them are described here. Use Emacs for the complete</f2></f12></f2></f11>
Developing Erlang     Code with PEL     set PEL Erlang     servironment	pel-erlang-shell-prevent		e Erlang shell from echoing every command. es that PEL will activate for the Erlang major mode.
<u>environment</u>	pel-erlang-environment gr     pel-erlang-man-parent- man6 which contain Erlar appropriate Erlang man fi     pel-erlang-exec-path: lc     pel-erlang-version-dete     pel-erlang-code-style grou	rootdir: Identifies the parent of grann files. If this is set PEL eles. Without PEL or if pel-erla lentifies the directory where Ection-method: identifies a method: identifies a	g occurs: maximum line length (defaults to 100). You can change the value or set it nil.
• <u>∑ Speedbar</u>	pel-erlang-skel-use-s     pel-erlang-skel-inser     PEL provides the following s     The first one is always ava     next key is a Meta key. For	econdary-separators: whet t-file-timestamp: whether au- set of mode-specific key prefix illable. The other two prefixes r simplification, the <f11></f11>	rators are used in Erlang code templates (see the Insert Erlang Code Template section below), her secondary separator lines are inserted by some Erlang code templates, tomatically updated time stamps are inserted in Erlang source code file header blocks.   kes: <fl1> SPC e, <fl2> and <m-fl2> are only available in erlang-mode buffers. The <m-fl2> prefix helps the typing flow when the SPC e prefix is normally omitted in the table.   files to show the list of functions.</m-fl2></m-fl2></fl2></fl1>
Open this PDF file. See also: <u>N Help/Info</u>	• <f11> SPC e <f1> • <f11> SPC e w <f1> • <f11> SPC e L <f1></f1></f11></f1></f11></f1></f11>	(pel-help-pdf &optional	Open the <u>Mr - Erlang</u> local PDF. If the prefix argument (like <b>c-u</b> or <b>M</b> ) is used, then it opens the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.
	• <f12> <f1> • <f12> w <f1> • <f12> L <f1></f1></f12></f1></f12></f1></f12>		, <b>,</b>
<u><b>∑</b> Customize</u> PEL Erlang support	<f11> SPC e <f2> <f12> <f2></f2></f12></f2></f11>	(pel-customize-pel &optional OTHER- WINDOW)	Customize PEL Erlang support: access PEL user-options to activate Erlang support packages.  • If OTHER-WINDOW is non-nil (use C-u), display in another window.
∑ Customize Emacs Erlang support	<f11> SPC e <f3> <f12> <f3></f3></f12></f3></f11>	(pel-customize-library &optional OTHER- WINDOW)	Customize Emacs Erlang support: erlang, erldoc, edts, auto-highlight-symbol, lsp-mode, lsp-ui, lsp-treemacs.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.
<u><b>∑</b> Customize</u> PEL LSP for Erlang support	<f11> SPC e L <f2> <f12> L <f2></f2></f12></f2></f11>	(pel-customize-pel &optional OTHER- WINDOW)	Customize PEL LSP Erlang support  • If OTHER-WINDOW is non-nil (use C-u), display in another window.  It is available when pel-use-erlang-ls is turned on.
∑ Customize Emacs LSP for Erlang support	<f11> SPC e L <f3></f3></f11>	(pel-customize-library &optional OTHER- WINDOW)	Customize Emacs LSP Erlang support: Isp-mode, Isp-ui, helm-Isp, Isp-ivy, Isp-origami, Isp-treemacs.  • If OTHER-WINDOW is non-nil (use C-u), display in another window.  It is available when pel-use-erlang-is is turned on.
<u><b>∑</b> Customize</u> PEL LSP Window for Erlang support	<f11> SPC e w <f2> <f12> w <f2></f2></f12></f2></f11>	(pel-customize-pel &optional OTHER- WINDOW)	Customize PEL LSP Erlang support  • If OTHER-WINDOW is non-nil (use C-u), display in another window.  If DTHER is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on.
∑ Customize Emacs LSP Window for Erlang support	<f11> SPC e w <f3> <f12> w <f3></f3></f12></f3></f11>	(pel-customize-library &optional OTHER- WINDOW)	Customize Emacs LSP Erlang support: Isp-treemacs, treemacs  • If OTHER-WINDOW is non-nil (use C-u), display in another window.  If DTHER is available when pel-use-treemacs and/or pel-use-Isp-treemacs is turned on.
Erlang Mode version	<f12> ?</f12>	(pel-show-erlang-version)	Display the current version of available Erlang system, of <b>erlang.el</b> and the <b>erlang ls</b> if available, in the mini-buffer.
Syntax Highlighting	Erlang code syntax highlighting	g has 4 levels and can be turn	ned off via Erlang menu: <f10> to access the menu &amp; select Erlang, then Syntax Highlighting.</f10>
Edit Erlang Code	The following commands help	edit Erlang code.	
Create additional clause	C-c C-j	(erlang-generate-new-clause)	Create additional Erlang clause header.  Parses the source file for the name of the current Erlang function. Create the header containing the name, a pair of parentheses, and an arrow. The space between the function name and the first parenthesis is preserved. The point is placed between the parentheses.
Clone clause arguments	С-с С-у	(erlang-clone-arguments)	Insert, at the point, the argument list of the previous clause.  Copy the function arguments of the preceding Erlang clause. This command is useful when defining a new clause with almost the same argument as the preceding.  The mark is set at the beginning of the inserted text, the point at the end.
Align arrows inside region	C-c C-a	(erlang-align-arrows START END)	Align arrows ("->") in function clauses inside marked region or in the current function.  • With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to point), not just those in function clauses.  • Example: sum(L) -> sum(L, 0). sum([H T], Sum) -> sum(T, Sum + H); sum([], Sum) -> Sum.  becomes:
			<pre>sum(L) -&gt; sum(L, 0). sum([H T], Sum) -&gt; sum(T, Sum + H); sum([], Sum) -&gt; Sum.</pre>
Electric Keys	The following keys have "elect	ric" behaviour and perform sp	pecial editing tasks to help edit Erlang source code.
Electric comma	,	(erlang-electric-comma &optional ARG)	Insert a comma character and possibly a new indented line.  The variable 'erlang-electric-comma-criteria' states a criterion, when fulfilled a newline is inserted and the next line is indented.  Behaves just like the normal comma when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.
Electric semicolon	;	(erlang-electric- semicolon &optional ARG)	Insert a semicolon character and possibly a prototype for the next line.  • The variable 'erlang-electric-semicolon-criteria' states a criterion, when fulfilled a newline is inserted, the next line is indented and a prototype for the next line is inserted. Normally the prototype consists of " ->". Should the semicolon end the clause a new clause  • header is generated.  • The variable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header.  • Behaves just like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Electric > (for the end of arrow)	>	(erlang-electric-gt &optional ARG)	Insert a greater-than sign, and optionally insert a new line and indent.
Erlang Comments	• %% - Two percent charac	acters for comments located eters are used for comments s	toward the end of a line of code
Comment/un-comment  Note:  M-; works much better than C-c C-c	М-;	(comment-dwim ARG)	Comment line or region with % or %% style comments depending on the location in the buffer.  The <u>erlang.el</u> code binds M-1 to indent-for-comment. However PEL uses M-1 for something else. The M-; binding to comment-dim works just as indent-for-comment if nothing is marked.
and C-c C-u • PEL maps key to pel-erlang- comment-dwim which works even better.  See also: Comments	With marked un-commented     With marked commented re     To insert %%% comment st     Call the comment command     If the region is active and     region'). Else, if the curre	On line with d region: Comment region (e gion: removes the commyle: type M-3 M-; d you want (Do What I Mean). 'transient-mark-mode' is on,	call 'comment-region' (unless it only consists of comments, in which case it calls 'uncomment-t-insert-comment-function' if it is defined, otherwise insert a comment and indent it. Else if a
	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region.  • With just <b>C-u</b> prefix arg, uncomment each line in region BEG END.  • Numeric prefix ARG means use ARG comment characters.  • If ARG is negative, delete that many comment characters instead.
	'comment-end' and 'comment-s  By default, the 'comment-s	nent-padding'. start' markers are inserted at t	the current indentation of the region, and comments are terminated on each line (even for d blank lines do not get comments). This can be changed with 'comment-style'.
Un-comment region	С-с С-и	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region. The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.
Comment/un-comment • PEL extension of comment-dwim specialized for Erlang. Automatically uses the %%% comment when appropriate.  ★★	M-;	(pel-erlang-comment- dwim &optional ARG)	Insert comment like 'comment-dwim' with ability to extend "%%%" comments.  • The "%%%" comment style is only placed at the beginning of a line, when the line is the first line of a buffer or a line that follows a line that starts with a "%%%" style comment.  • When commenting a region, if the region starts just below a line with "%%%" comment the new comment uses "%%%" comment as well.  • In all other cases the %% style comment is used at the beginning of a line and a single % is used after the beginning of a line.  • If region is already commented, un-comment it.
Fill current paragraph See also: Filling/Justification	• M-q • <f11> t f p</f11>	(fill-paragraph &optional JUSTIFY REGION)	Fill multi-line comment at or after point.  To justify as well: C-u M-q  In refill mode this is done automatically. In auto fill mode the filling is done at the end of the line.  See the Filling/Justification for all filling and justification commands.
Toggle display of comments in buffer or active region See also: <u>Comments</u>	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer.  • If the region is active then toggle in the region. Otherwise, in the whole buffer.  • This requires the <a href="hide-comnt.el">hide-comnt.el</a> package (see <a href="December Comments">December Comments</a> ).  • PEL activates it when the <a href="pel-use-hide-comnt">pel-use-hide-comnt</a> user option is t.
Indentation			C-Mode logic and provided commands listed below. at the end of this list. They are also listed in the <u>∑ Indentation</u> table.
Indent current line or region	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	Indent active region, current line, or block starting on this line.
See also: Indentation	<ul> <li>Behaviour depends on syntactic-indentation mode (enabled by default but can be toggled on/off with the <f12> M-i key):</f12></li> <li>With syntactic-indentation on (the default): <ul> <li>In Transient Mark mode, when the region is active, reindent the region.</li> <li>Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line.</li> <li>Otherwise reindent just the current line.</li> <li>This might seem strange for new Emacs users, but it ends up being very useful. You can type <tab> anywhere in the line to adjust the indentation of the current line or everything in the marked area if a block is marked.</tab></li> </ul> </li> <li>With syntactic-indentation off: <ul> <li><a href="ctab"><a href="ctab"></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></a></li></ul></li></ul>		
Indent Erlang function	C-c C-q	(erlang-indent-function)	Indent current Erlang function.  Indent current Erlang function.  Indent current Erlang function.
Indent lines of list after point See also: Indentation	С-М-q	(prog-indent-sexp &optional DEFUN)	Indent the expression after point. When interactively called with prefix, indent the enclosing defun instead.
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region.  • A numeric prefix argument specifies a column: indent each line to that column.  • With no prefix argument, the command chooses one of these methods and indents all the lines with it:  1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it.  2. If 'indent-region-function' is non-nil, call that function to indent the region.  3. Indent each line via 'indent-according-to-mode'.  When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>
Navigation in Erlang code See also: <u>∑ Navigation</u>	Several commands are specia  Notice the 3 sets of comma  1. <f12> <up> and &lt; 2. The standard navigati 3. The <f12> <m-cur below="" describe="" list="" sp<="" td="" the=""><td>lization of the normal navigationds:  f12&gt; <down> move to the concommands, (mapped to &lt;:sor&gt; commands (also accessor) colalized commands only. See</down></td><td>rilang source code. PEL complements these. And EDTS also on commands which are described in the table Navigation, but several are specific to Erlang:  beginning of Erlang functions skipping all compiler directives.  f6&gt; prefix) move to beginning/end of Erlang functions but stop at compiler directives. saible via <m-f12> <m-cursor>, move across Erlang clauses (as opposed to functions). see the others inside Navigation, like the navigation by blocks.  In erlang-mode. Their global equivalent is <f11> SPC e. It is not always shown for brevity.</f11></m-cursor></m-f12></td></m-cur></f12></up></f12>	lization of the normal navigationds:  f12> <down> move to the concommands, (mapped to &lt;:sor&gt; commands (also accessor) colalized commands only. See</down>	rilang source code. PEL complements these. And EDTS also on commands which are described in the table Navigation, but several are specific to Erlang:  beginning of Erlang functions skipping all compiler directives.  f6> prefix) move to beginning/end of Erlang functions but stop at compiler directives. saible via <m-f12> <m-cursor>, move across Erlang clauses (as opposed to functions). see the others inside Navigation, like the navigation by blocks.  In erlang-mode. Their global equivalent is <f11> SPC e. It is not always shown for brevity.</f11></m-cursor></m-f12>
Go to beginning of statement	м-а	(backward-sentence &optional ARG)	Go backward to the beginning of an Erlang clause.  • With a numerical argument repeat that many times.
Go to the end of	м-е	(forward-sentence	Go forward to the end of an Erlang clause.
statement		&optional ARG)	With a numerical argument repeat that many times.

<u>Description</u>	<u>Keystroke</u>	Function	Note
Go to beginning of current function or top-level function	С-М-а	( <b>c-beginning-of-defun</b> &optional ARG)	Move backward to the beginning of an Erlang function.  Every top level declaration that contains a brace paren block is considered to be a defun.  With a positive argument, move backward that many defuns. A negative argument -N means move forward to the Nth following beginning.
Goto end of current function or top-level function	С-М-е	( <b>c-end-of-defun</b> &optional ARG)	Move forward to the end of an Erlang function.  • With argument, do it that many times. Negative argument -N means move back to Nth preceding end.
Move backward to beginning of previous function	• <f12> <up> • <f12> f p</f12></up></f12>	(pel-previous-erl-function &optional N)	Move backward to the beginning of the previous function skipping all compiler directives.  • With prefix argument N repeat N times.  • Pushes mark; move back to previous position with M-\(^\).
	• <f11> SPC e <up> • <f11> SPC e f p</f11></up></f11>		Shift marking is available for the key sequence using a cursor key.
Move forward to beginning of next function	• <f12> <down> • <f12> f n</f12></down></f12>	(pel-next-erl-function &optional N)	Move forward to the beginning of the next function skipping all compiler directives.  • With prefix argument N repeat N times.  • Pushes mark; move back to previous position with M-\(^\).
	• <f11> SPC e <down> • <f11> SPC e f n</f11></down></f11>		Shift marking is available for the key sequence using a cursor key.
Backward to beginning of function or compiler directive	<f12> f P  • C-M-a • C-M-<home> • <f6> p</f6></home></f12>	(beginning-of-defun &optional ARG) (erlang-beginning-of- function &optional ARG)	Move backward to the beginning of an Erlang function or compiler directive.  • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun.  ➡Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However <f6> p and <f6> <up>handle Shift-marking fine in terminal</up></f6></f6></home>
	• <f6> <up> • <f11> SPC e f P</f11></up></f6>	,	mode. <u>Erlang.el man page</u> indicates an invalid mapping for this.
Forward to beginning of	<f12> f N</f12>	(pel-beginning-of-next-	Move forward to the beginning of the next function definition or compiler directive.
next function or compiler directive	• <f6> n • <f6> <down> • <f11> SPC e f N</f11></down></f6></f6>	defun &optional SILENT DONT-PUSH_MARK)	<ul> <li>Beeps if does not find beginning of next function unless SILENT is non-nil.</li> <li>If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.</li> <li>Move back to previous position with M-\[^\chi\].</li> <li>Shift marking is available for the <f6> bindings.</f6></li> </ul>
	<ul> <li>This command complemen</li> <li>It moves forward but not to other editors expect.</li> <li>It handles nested functions</li> </ul>	the end of the function definit	ion (like end-of-defun) but to the beginning of the function definition, which is often what users of s like Python and others.
Backward to end of previous function or compiler directive	<f6> <left></left></f6>	(pel-end-of-previous-defun &optional SILENT DONT-PUSH_MARK)	Move backwards to the end of the previous function definition.  • Beeps if does not find end of previous function unless SILENT is non-nil.  • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil.  • Move back to previous position with M−ˆ.   ⇒ Shift marking is available for the <f6> bindings.  • This command complements this set of 4 commands.</f6>
Forward to end of function or compiler directive	• C-M-e • C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG) (erlang-end-of- function &optional ARG)	Move forward to end of Erlang function.  With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun.  ➤ Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-M- <nd>end&gt;).  However <f6> <right> handle Shift-marking fine in terminal mode.</right></f6></nd>
Backward to beginning of clause	• C-c M-a • <f12> c a • <m-f12> <m-up></m-up></m-f12></f12>	(erlang-beginning-of- clause &optional ARG)	Move backward to previous start of clause.  • With argument, do this that many times.  Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.
Forward to beginning of next clause	• <f12> c n • <m-f12> <m-down></m-down></m-f12></f12>	(pel-beginning-of-next-clause)	Move forward to the beginning of next clause.  • Pushes mark; move back to previous position with M−ˆ.  ⇒ Shift marking is available.
Backward to end of previous clause	• <f12> c p • <m-f12> <m-left></m-left></m-f12></f12>	(pel-end-of-previous- clause)	Move backward to the end of the previous clause.  • Pushes mark; move back to previous position with M−ˆ.  ⇒Shift marking is available.
Forward to end of current clause	• C-c M-e • <f12> c e • <m-f12> <m-right></m-right></m-f12></f12>	(erlang-end-of-clause &optional ARG)	Move to the end of the current clause.  • With argument, do this that many times.
EDTS/Navigation	EDTS (see below) provides m	ore navigation commands.	
Search Support			<ul> <li>iake case is often used. Using superword-mode helps searching.</li> <li>To change this use the <f11> t <f2> to access the customize buffer.</f2></f11></li> </ul>
Toggle superword- mode	<f12> M-p  • <f11> t m p</f11></f12>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats <u>snake_case</u> as one word. In Erlang, '_' are treated as part of words.  • With a prefix argument ARG, enable superword mode if ARG is positive, and disable it
See also:  • <u>&gt; Text Modes</u> • <u>&gt; Search/Replace</u>	• <f11> SPC e M-p</f11>		<ul> <li>otherwise.</li> <li>PEL provides the <f12> M-p key for the programming language modes where <u>snake case</u> is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12></li> </ul>
Marking	No.		valiable. They complement what is already available and described in the <u><b>Marking</b></u> table. an invalid mapping for this. Reported as <u>ERL-1314</u> .
Mark Erlang function	• C-M-h • <f12> f m</f12>	(mark-defun &optional ARG) (erlang-mark-function &optional ARG)	<ul> <li>Put mark at end of this function, point at beginning.</li> <li>The function marked is the one that contains point or follows point.</li> <li>With positive ARG, mark this and that many next functions; with negative ARG, change the direction of marking.</li> <li>If the mark is active, it marks the next or previous function(s) after the one(s) already marked.</li> </ul>
Mark Erlang Clause	• C-c M-h • <f12> c m</f12>	(erlang-mark-clause)	Put mark at end of clause, point at beginning.
Highlighting blocks	show-paren-mode, which his	ighlights the parens that matc	useful modes to highlight blocks of (), {}, and []. thes the one before or after point. the highlighted with the same colour.
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode).  • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.
See also: <u>National Highlight</u>	• <f11> h ( • <f11> SPC e M-9</f11></f11>		Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.
Enable/Disable coloured highlight of nested blocks (),{},[]	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters-mode &optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth.  • Customize the depth and colours with M-x customize-group rainbow-delimiters
See also: <u>∑ Highlight</u>	• <f11> h R • <f11> SPC e M-r</f11></f11>		PEL activates this when the pel-use-rainbow-delimiters user option is set to t.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Inserting code with	Specialized Tempo Skel	etons	
Insert Parentheses	M-(	(insert-parentheses &optional ARG)	For Erlang: insert a parenthesis pair '()', leaving point after open-paren.  • A positive ARG encloses the following ARG sexps in parenthesis if they are balanced.  • A negative ARG encloses the preceding ARG sexps instead.  • No argument is equivalent to zero: just insert '()' and leave point between.  • PEL makes 'parens-require-spaces' buffer local and set it to nil in Erlang mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis.  • If region is active, insert enclosing characters at region boundaries.  • This command assumes point is not in a string or comment.
Insert Erlang Code Templates  See also:  •	The erlang_el external package defines a set of text skeletons using the standard tempo skeleton package.  The erlang package make these skeletons available on the Erlang/Skeletons menu (via <f10>).  PEL provides the following additional functionality:  Quick access keys to insert the templates, all mapped under the pel:erlang-skel key prefix: <f12> <f12>.  Several additional templates. These are marked with a +. These are also added to the menu.  Several aspects of the PEL Erlang Source Code Style is controlled by the user options inside the pel-erlang-code-style group. The controlled templates affected are marked with a C. The relevant user options are part of the pel-erlang-code-style group accessible with <f12> <f2> from an erlang mode buffer and include the following options:  pel-erlang-skel-insert-file-timestamp : set whether an automatically updated timestamp is inserted in the file header block.  pel-erlang-skel-prompt-for-function-name : set whether file and function skeletons blocks prompt for purpose and insert it.  pel-erlang-use-separators : set whether function skeletons prompt for function name and then inserts that name.  pel-erlang-use-separators : set whether flocks use norizontal separator lines (these are the first of potentially 2 separate pel-erlang-skel-with-license : set whether blocks use open source software license text controlled by set whether file header blocks use open source software license text controlled by ou want to change the behaviour for only one file, write the user option control block at the end of that file. If you want to control the behaviour of PEL tempo templates for all files inside a directory tree. So by default, the user options that control the Deta to control the behaviour of PEL tempo templates for all files inside a directory tree create a .dir-locals file and store the values of the relevant options variables inside that file. If you want to control the user options defecting the format of the tempo templates precisely and does not affect what you actual</f2></f12></f12></f12></f10>		under the pel:erlang-skel key prefix: <f12> <f12>.  a +. These are also added to the menu.  Ale is controlled by the user options inside the pel-erlang-code-style group. The controlled  Ale is controlled by the user options inside the pel-erlang-code-style group. The controlled  Ale is controlled by the user options inside the pel-erlang-code-style group accessible with <f12> <f2> from an  Ale is controlled by the user options inside the pel-erlang-code-style group accessible with <f12> <f2> from an  Ale is controlled by the user options are part of the pel-erlang-code-style group accessible with <f12> <f2> from an  Ale is controlled by the user options are part of the pel-erlang-code-style group accessible with <f12> <f2> from an  Ale is controlled by the user block.  Ale whether file and function skeletons prompt for function name and then inserts that name.  Ale whether function skeletons prompt for function arguments and then insert them.  Ale whether blocks use horizontal separator lines (these are the first of potentially 2 separators).  Ale whether blocks use a second block horizontal separator line.  Ale whether generated code comments use EDoc markup.  Ale whether file header blocks use open source software license text controlled by the lice.  Ale the user option directory variables (see File/Directory Variables) they can also be used  Ale tree. So by default, the user options that control the PEL tempo template take effect globally.  Ale the user option control block at the end of that file. If you want to control the behaviour of the  Ale tree is a dir-locals file and store the values of the relevant options variables inside that file. This  Ale the user option control block at the end of that file and store the values of the relevant options variables inside that file. This  Ale the user option control block at the end of the next or previous point of interest (so called tempo-  Ale the user option control the pel-tempo-mode) you can move to the next or previous point of interest (so called tempo-</f2></f12></f2></f12></f2></f12></f2></f12></f12></f12>
C: templates with customization control  >>> Customize PEL Erlang Skeletons layout		s shown below are available in (pel-customize-pel & optional OTHER-	n erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.  Customize PEL Erlang skeleton layout.  • If OTHER-WINDOW is non-nil (use C-u), display in another window.</f11>
·	45105 45105 /	WINDOW)	leased as if adabases
case	<f12> <f12> i <f12> <f12> c</f12></f12></f12></f12>	(pel-erl-if)	Insert an if statement.  Insert a case expression.
export +	<f12> <f12> c</f12></f12>	(pel-erl-export	Insert an export module attribute expression.
import +	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.
try +	<f12> <f12> t</f12></f12>	(pel-eri-try)	Insert a try expression.
try-of +	<f12> <f12> T</f12></f12>	(pel-eri-try-of)	Insert a try expression with of clauses.
receive	<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.
after	<f12> <f12> a</f12></f12>	(pel-erl-after)	Insert a receive expression with an after (timeout) clause.
loop	<f12> <f12> 1</f12></f12>	(pel-erl-loop)	Insert a simple receive loop.
module	<f12> <f12> m</f12></f12>	(pel-erl-module)	Insert the module attribute.
<u>function</u> C	<f12> <f12> f</f12></f12>	(pel-erl-function)	Insert a function definition. This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.
author	<f12> <f12> `</f12></f12>	(pel-erl-author)	Insert the author attribute. Uses the <b>user-mail-address</b> user option to insert your mail address.
spec	<f12> <f12> s</f12></f12>	(pel-erl-spec)	Insert a <b>-spec</b> for the function following point.
small-header C	<f12> <f12> M-h</f12></f12>	(pel-erl-small-header)	Insert a small file header without any comment.
normal-header C	<f12> <f12> M-H</f12></f12>	(pel-erl-normal-header)	Insert a normal file header: includes author name, copyright notice, doc section, file created date
large-header C	<f12> <f12> h</f12></f12>	(pel-erl-large-header)	Insert a large header block that includes all normal header fields plus separators.  • All formatting is controlled by user-options described above.  • Distinguish Erlang .erl module files from the .hrl header files.
small-server C	<f12> <f12> M-s</f12></f12>	(pel-erl-small-server)	Insert a large file header and template logic for a small server.
application C	<f12> <f12> M-a</f12></f12>	(pel-erl-application)	Insert a large file header and template logic for an application behaviour.
supervisor C	<f12> <f12> M-u</f12></f12>	(pel-erl-supervisor)	Insert a large file header and template logic for a <u>supervisor behaviour</u> .
supervisor-bridge C generic-server C	<f12> <f12> M-b <f12> <f12> M-q</f12></f12></f12></f12>	(pel-erl-supervisor-bridge) (pel-erl-generic-server)	Insert a large file header and template logic for a <u>supervisor bridge behaviour</u> .  Insert a large file header and template logic for a <u>gen-server behaviour</u> .
gen-event C	<f12> <f12> M-e</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a gen-event behaviour.
gen-fsm C	<f12> <f12> M-f</f12></f12>	(pel-erl-gen-fsm)	Insert a large file header and template logic for a gen-fsm behaviour.
gen-statem-StateName	<f12> <f12> M-S</f12></f12>	(pel-erl-gen-statem-	Insert a large file header and template logic for a gen-statem behaviour.
gen-statem-handle- event C	<f12> <f12> M-E</f12></f12>	(pel-erl-gen-statem- handle-event)	Insert a large file header and template logic for a gen-statem.
wx-object C	<f12> <f12> M-W</f12></f12>	(pel-erl-wx-object)	Insert a large file header and template logic for a wx-object generic server.
gen-lib C	<f12> <f12> M-1</f12></f12>	(pel-erl-gen-lib)	Insert a large file header and template logic for a library module.
gen-corba-cb C	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a <b>CORBA</b> callback module.
ct-test-suite-s	<f12> <f12> M-1</f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite
ct-test-suite-l	<f12> <f12> M-2</f12></f12>	(pel-erl-ct-test-suite-l)	Insert a large file header and template logic for a test suite
ts-test-suite	<f12> <f12> M-3</f12></f12>	(pel-erl-ts-test-suite)	Insert a large file header and template logic for a test suite

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Tempo Template Tag Insertion	• C-c C-M-i • <f12> <f12> <f12></f12></f12></f12>	(tempo-complete-tag &optional SILENT)	Look for a tag and expand it.
IIISel doll	• <f12> <f12> <f12> <f12> <f12></f12></f12></f12></f12></f12>	auphonal Silling	
	match for is determined car match at all.	be altered with the variable 't	des 'tempo-tags') are searched for a match for the text before the point. The way the string to tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no
	If a partial completion or no	match at all is found, and SIL	expanded in place of the matching string.  ENT is non-nil, the function will give a signal.  ion-buffer' is non-nil, a buffer containing possible completions is displayed.
Toggle pel-tempo-mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode &optional ARG)	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as
See also:  • <u>National Number Inserting Text</u>	• <f11> SPC e <f12> SPC • <f6> SPC</f6></f12></f11>	aoptona za taj	C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When pel-tempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode.  When a skeleton is inserted via the execution of one of the pel-erl commands above, the pel-tempo-mode is automatically activated.
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  These key key bindings are only available when pel-tempo-mode is active.
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward-mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  These key binding are only available when pel-tempo-mode is active.
Erlang syntax	Syntax checking for the E	rlang programming language o	can be done with Emacs built-in <u>flymake</u> as well as with the <b>P</b> external package <u>flycheck</u> .
checking Using either:	<ul><li>To activate either set the</li><li>By default, the syntax ch</li></ul>	pel-use-erlang-syntax-chec	k user option is set to either 'use-flycheck or 'use-flymake.  nched. If you want to start your selected syntax checker as soon as any Erlang file is opened,
<ul><li>flycheck or</li><li>flymake</li></ul>	PEL automatically insta	lls and activates flycheck wh	ovides erlang-flymake to use with Erlang. en <b>pel-use-goflymake</b> user option is set to 'use-flycheck.
Can also		ariables determine the exact c	ircumstances whereupon Flymake decides to initiate a check of the buffer:
See also:  • <u>∑ SyntaxCheck</u>	flymake-no-changes-time	out : time to wait after last ch	hen flymake-mode is started. <b>nil</b> to prevent check.  lange to start checking. Default = 0.5 seconds.  er insertion or removal of newline char from buffer. <b>nil</b> to prevent check.
	The following variable control • flymake-wrap-around : If r • flymake-diagnostic-types-	on-nil, moving to errors wraps	
	The <b>M-n</b> and <b>M-p</b> keys are ma	apped to flymake commands	only when flymake-mode is turned on.
Activate/deactivate selected syntax	<f12> !</f12>	(pel-erlang-toggle-syntax- checker)	Toggle the selected Erlang syntax checker mode on/off.  • The syntax checker activated or deactivated is either flycheck or flymake, as selected by
checker	<f11> SPC e !</f11>	oncorei	the user-option variable `pel-use-erlang-syntax-check'.  See the required settings above to activate this command and select the syntax checker.
Go to next flymake diagnostic	M-n	(flymake-goto-next-error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.
Go to previous flymake diagnostic	М-р	(flymake-goto-prev-error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.
Compiling Erlang Code		ned to compile the files. The b	code files to .beam files located in the same directory as the source code. Detected errors are buffer shows the location of error and the error description. The following commands are used to
Compile code	• C-c C-k • <f12> M-c • <m-f12> M-c</m-f12></f12>	(erlang-compile)	Compile Erlang module in current buffer.  If buffer visiting file was modified and not saved, prompts the user to save it first.  Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command.  The buffer lists the errors. Hitting RET on the error file/line move point to that line in the Erlang file buffer. The RET key is bound to (compile-goto-error &optional EVENT)  It's also possible to use the next-error and previous error.
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output.  • Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.
Move to next compile error	• C-x ` • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; • negative means move back to previous error messages. • Just C-u as a prefix means reparse the error message buffer and start at the first error.  Î This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to previous compile error	• M-g p • M-g M-p	(previous-error &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative).  This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Move to previous compilation or Flycheck detected error	С-с С-р	(edts-code-previous-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Erlang Shell	Commands to explicitly launch library running in erlang-shell-		at runs under an Emacs inferior-erlang process controlled by the <u>comint mode</u> from the <u>comint.el</u>
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.
Start new Erlang Shell	<f11> z r e</f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer.  • The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started.
	<f12> z</f12>		C-c C-z starts the Erlang Shell from the Erlang Mode. <f11> z r is available globally and will work as long as the erl executable is accessible.  Under PEL this command is available only when the pel-use-erlang user option is set to t.</f11>

<u>Description</u>	<u>Keystroke</u>	Function	Note	
Work around to	When running the Erlang She	II inside Emacs, you may run	into some issues. They are listed here along with work-arounds.	
issues in the	Redundant command echo		ach typed command. If this is the case for your system, PEL provides a fix:	
Erlang Shell			otion to t. After doing that execute pel-init or restart Emacs.	
		· · · · · · · · · · · · · · · · · · ·	Menu: work-around: type the following instead: C-q C-g RET	
	! Unfortunately the abo	ove workaround does not wor	k when the Erlang shell is launched inside an Emacs vterm shell (see <u>Namellas</u> ).	
Erlang Shell:			r issued Erlang shell commands at the shell prompt.	
Command History	Erlang shell command his		inside a file the is restored when opening a new shell: commands from previously opened Erlang	
	shells are also available.	Ť	inside a file the is restored when opening a new shell, commands from previously opened chang	
	<ul> <li>Within an Emacs inferior-</li> <li>You can also use the Erla</li> </ul>	erlang the ang shell commands to acce	ess the local shell history.	
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.	
Previous shell	М-р	(comint-previous-input	Cycle backwards through Erlang shell input history, saving input.	
command	F	ARG)	,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	
<u>Using Man inside</u>	Emacs provide 2 main comma		side buffers. In reader available on the shell allowing navigation across man pages and opening hyperlinks.	
Emacs and support Erlang	They are:		arreader available on the shell allowing havigation across main pages and opening hyperining.	
Man pages	<ul><li>The man command uses</li><li>WoMan: Browse Unix Ma</li></ul>	anual Pages "W.O. (without) N	1an" a complete implementation. It has some formatting limitations compared to man but it's	
	very useful in systems wl	nere man is not available like	Windows.	
See also: <u>▼ Help/Info</u>	To see Erlang man pages us		ilable to the man utility and therefore not available for man inside Emacs.	
	There are several ways thi	s can be remedied:	·	
			clude the directory where these files are located. Then man can be used outside and inside the following lines can be stored inside a shell script to do this:	
	MANPATH=/usr/: export MANPAT		.3.4/lib/erlang/man:`manpath`	
	Another way is to custom	nize the Emacs Man-switche	s user option variable to something that includes the same directory. This will add the capability	
			nodifying the capabilities of the parent shell. For example, if we want to use the same directory as which is normally set to nil to the following value:	
	"-M`manpath`:/usr	r/local/Cellar/erlang/22.3.4/lib	/erlang/man"	
			ories for the man pages of other programming languages while leaving the ability to have several	
			pht be very useful for someone that uses different versions of Erlang in a system and needs . It becomes possible to run different shells inside Emacs with each having its own value of	
		providing the man pages from a's ability to view several page	different locations. It is also possible to place all of these directories inside the Man-switches or es for the same topic.	
	To only see Erlang topics in			
	When learning Erlang it m	ight help to see only Erlang to	pics when using the man command completion. To do that , set MANPATH to the Erlang man	
		lso ensure that a whatis file is <u>w to create whatis file for loca</u>	located in the Erlang man page root directory, otherwise Emacs man completion will not work.	
	Using EDTS to access the m	an pages of the version of I	Erlang used by various projects:	
	EDTS (see below) support	s the ability to download and	access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides it's pages, allowing EDTS driven man page access to co-exist with manual man command	
	execution and the techniq		e pages, allowing EDTS driver main page access to co-exist with manual main command	
	PEL supports multiple version	ons of Erlang and access to	their man pages	
About Erlang			ang-man-parent-rootdir user-option can be set to read the man parent directory name from an eman files related to a specific version of Erlang available to the parent OS shell, set the	
	environment variable when you select the version of Erlang available to the OS shell and set the name of the environment variable in the <b>pel-erlang-man-parent-rootdir</b> user-option. See the following <b>Installing Erlang</b> pages of the <b>About Erlang</b> document that describes an setting such an editing environment:			
		Install Erlang OTP Documentation and Man Files     Creating whatis files for Erlang man pages		
	Using the Erlang Man     Using Specialized OS			
		ialized Shells for Erlang to I	Edit Erlang	
0 1 7 11				
See also: <u><b>∑ Menus</b></u>	<ul> <li>Use the following commands</li> <li>You can also use the toolba</li> </ul>		inside Emacs. <f10>) in the Erlang section.</f10>	
Open a man page	• <f11> ? m</f11>	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because:	
inside an Emacs buffer	• ж-м	,	• the links are active and can be followed. When the man page describes a directory or file, emacs will open the file or the directory (in direct mode) when pressing <b>RET</b> over the link.	
See also:			You can navigate easily between sections (n/p will move to the next/previous section)	
• <u>∑ Help/Info</u> • <u>∑ Customize</u>			<ul><li>You can use any of the searches.</li><li>You can use any of the options to the man command at the prompt, like the -a option to</li></ul>	
<u></u>			access all man pages of the same name. Then use <b>M-n</b> and <b>M-p</b> to move from one to the other page, inside the same buffer.	
			• See all keys available in mode, with <f1> m or <f11> ? k m.</f11></f1>	
			The man command prompts, using the word at point as the default.	
			₽EL key sequence to customize man: <f11> <f2> E m</f2></f11>	
Open a man page without external man	<f11> ? w</f11>	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under	
process: woman See also:		,	environments where man is not available (such as basic Windows).	
• <u>∑ Help/Info</u>			PEL key sequence to customize man: <f11> <f2> E w  text width, use word at point, etc</f2></f11>	
• <u>S Customize</u>				
<u>EDTS</u>	EDTS - Erlang Developr		putavnal package A DEL activates it when the red use alter constitution is at the	
			external package. 2 PEL activates it when the pel-use-edts user option is set to t. If you want et pel-use-edts to start-automatically instead of t.	
Fulance Providence				
Erlang Project settings			pup. With PEL you can open it, with other Erlang specific groups with <b><f12> <f3></f3></f12></b> . tore Erlang project specific settings. See <b>EDTS: Configure your projects.</b> This allows setting	
		e, node-name, erlang-cookie,	lib-dirs, start-command, top-path, dialyzer-plt, app-include-dirs, project-include-dirs, xref-error-	
See also: <u><b>∑ Sessions</b></u>	· ·		tive on session stored: unfortunately edts does not provide a desktop restore handler.	
	> PEL does, however prov	ide a desktop restore handler	for EDTS which detects edts-mode failures and protect the desktop restoration.	
	If EDTS has not been active		ific key available is <f12> M-SPC to activate it. Once it's activated the other keys are available.</f12>	
Toggle EDTS mode	<f12> M-SPC</f12>	(edts-mode &optional	Turn EDTS mode on or off.	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
	<f11> SPC e M-SPC</f11>	Ang)	<ul> <li>EDTS is arreasy to set up bevelopment-environment for Enang.</li> <li>EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further.</li> </ul>
EDTS/Navigation	EDTS (see below) provides the following commands to move point across Erlang functions. These do not support repetition prefix argument nor they support shift marking. There are other commands and key bindings to move across Erlang functions, and PEL support functions that perform the same and support repetition and shift marking. See the commands listed in the navigation section above.		
Move backward to beginning of previous function	C-c C-d C-b	(ferl-goto-previous- function)	Move backward to the beginning of the previous function skipping all compiler directives.  PEL provides a more complete command to move across functions (with or without skipping directives) that push mark and support shift marking. See in the navigation section above.
Move forward to beginning of next function	C-c C-d C-f	(ferl-goto-next-function)	Move forward to the beginning of the next function skipping all compiler directives.  PEL provides a more complete command to move across functions (with or without skipping directives) that push mark and support shift marking. See in the navigation section above.
EDTS/Cross References			supports navigating in Erlang source code running in the current and remote nodes.  n erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11>
Find definition of identifier at point	М	(edts-find-source-under- point)	Goto the source code that: defines the function being called at point or header file included at point. For remote calls, contacts an Erlang node to determine which file to look in, with the following algorithm:  • Find the directory of the module's beam file (loading it if necessary).  • Look for the source file in:  • Directory where source file was originally compiled.  • Todo: Same directory as the beam file  • Todo: Again with /ebin/ replaced with /src/  • Todo: Again with /ebin/ replaced with /erl/ Otherwise, report that the file can't be found.
Go back to where M was last issued	м-,	(edts-find-source-unwind)	Unwind back from uses of 'edts-navigate'-commands.
Lists caller of function at point	• C-c C-d w • <f12> w</f12>	(edts-xref-who-calls)	Pops-up a menu of all callers of the function at point.
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who-calls)	Redo previous call to edts-who-calls.
Find a function in the current module	• C-c C-d f • <m-f12> M-f</m-f12>	(edts-find-local-function SET-MARK)	Find a function in the current module.  List local functions in the mini-buffer. Support completion. Move point to selected one.  With C-u prefix, push mark before moving point.
Find a module in the current project	• C-c C-d F • <m-f12> M-g</m-f12>	(edts-find-global-function)	Find a module in the current project.  • List project modules in the mini-buffer. Support completion. Open the file of selected one.
EDTS/AHS Editing	EDTS supports the automatic highlight symbol mode (AHS). and provides commands to modify the name of the highlighted name in the current function or in all of the buffer. The automatic symbol highlighting mode starts when the cursors stays on a symbol for a period longer than the value identified by the ahs-idle-interval which defaults to 1.0 second.  To turn off the AHS editing mode, use a command to move point away from the highlighted area.		
Edit all highlighted symbols in current function	• C-c C-d e • <f12> e</f12>	(edts-ahs-edit-current-function)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current function.  • Activates ahs-edit-mode with edts-current-function range-plugin.
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer.  • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	Refactor the expression(s) in the region as a function.  The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original function.  New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring.  This command requires Erlang syntax tools package to be available in the node, version 1.2 (or perhaps later.)
EDTS/Man	pages per project, so it is poss	sible to have several Erlang pro	on using the information extracted from Erlang Man pages. EDTS maintains a set of Erlang man ojects each one with a different version of Erlang and their corresponding man pages. nan commands described above in this table.
Download, install, select Erlang Man pages	<f12> `</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands.
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip.
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function. Find and show the man-page documentation for the Erlang module:function.
EDTS Code Analysis			
Compile current buffer	<f12> a c</f12>	(edts-code-compile-and-display)	Compiles current buffer on node related to that buffer's project.
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION-RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.
EDTS/Debug			
Toggle breakpoint	• C-c C-d b • <f12> d b</f12>	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.
List breakpoints	C-c C-d M-b • <f12> d B</f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle-interpreted)	Toggle the interpretation state for module in current buffer.
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.
EDTS/Erlang Node		·	
Display EDTS Erlang Node Name	<f12> N</f12>	(edts-buffer-node-name)	Print the node sname of the erlang node connected to current buffer.  • The node is either:  • The module's project node, if current buffer is an erlang module, or  • The buffer's erlang node if buffer is an edts-shell buffer.  • The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module such as an otp-module or a module loaded by ~/.erlang).
Start an EDTS controlled Erlang Shell	<f12> x</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell.
Start EDTS server	<f12> X</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).
Rendering markup embedded in comments		to describe UML diagrams o	ecific markup code embedded inside Erlang source code comments. This can be useful when r finite-state machines for example.
Preview UML diagram	<f12> u</f12>	(pel-render-commented-	Render the PlantUML markup embedded in current mode comment.
from plantUML source in current plantUML region of commented source code  See also: M PlantUML	<f11> SCP e u</f11>	plantuml PREFIX &optional POS)	Uses prefix (as PREFIX) to choose where to display it:  (when prefixing the command with C-u) -> new window  (lower prefixing the command with C-u) -> new frame.  (lower prefixing the command with C-u) -> new frame.  (lower prefixing the command with C-u) companies from the command with C-u companies from the command with C-u) companies from the command with C-u companies from the comma
	PlantUML block and issuing th	is command.	are with PlantUML markup, then generate the UML rendering by moving point inside the vated by <b>pel-use-plantuml</b> user option being non-nil.
Development Tool	The following commands are u	sed when adding Emacs Lisp	support for Erlang.
Show syntactic information	C-c C-s	(erlang-show-syntactic-information)	Show syntactic information for current line.  • Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.
LSP support:  • Isp-mode  • erlang Is	LSP (language Server Protocol) support for Erlang is provided via:  • The Isp-mode Emacs Lisp external package PEL activates it when the pel-use-erlang-is user-option is turned on (set to t).  • The erlang is Erlang server for LSP. You must install this manually. You will need Git, Erlang, rebar3 and make. The instructions are on the web-site.  • The erlang is can be configured using a YAML file erlang is.config file that must be placed at the root of the Erlang project.  • It's important for most projects to set that up, otherwise you may not be able to take advantage of several of the cross-reference features		
erlang Is required environment		ng executables. See <b>Installir</b> g_ls follow the instruction on	ng Erlang if you need to learn how to install Erlang and its tools. the erlang Is GitHub page: git clone it, then run make and make install.
• <u>S Customize</u> Isp-mode	settings are probably what you  • Isp-log-io  • Isp-ui-sideline-enable :  • Isp-ui-doc-enable	may want to customize: control whether the LSP proc control whether LSP display control whether LSP display	mode customization group. With PEL you can access it via <f12> L <f3>. The following cess is logging its I/O. Useful for debugging LSP support. information about the current code line. documentation about the current code symbol. mically using the following commands.</f3></f12>
Toggle code documentation display	<f11> SCP e L D <f12> L D</f12></f11>	(pel-toggle-lsp-ui-doc &optional LOCALLY)	Toggle the display of code documentation.  The initial state is set by the 'lsp-ui-doc-enable' user-option.  By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Toggle LSP I/O logging	<f11> SCP e L I <f12> L I</f12></f11>	(pel-toggle-lsp-log-io &optional LOCALLY)	<ul> <li>Toggle the logging of LSP I/O.</li> <li>The initial state is set by the 'Isp-log-io' user-option.</li> <li>By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.</li> </ul>
Toggle display of information on current line	<f11> SCP e L L <f12> L L</f12></f11>	(pel-toggle-lsp-ui-sideline &optional LOCALLY)	Toggle the display of information of the current line.  The initial state is set by the 'lsp-ui-sideline-enable' user-option.  By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Erlang LS Features	Overview of the features provide Code completion  Go to Definition  Go to Implementation of OTP Behaviours  Signature Suggestions  Diagnostics on file open/save:  Compiler Diagnostics  Dialyzer Diagnostics  Elvis Diagnostics	Edoc support     Navigation to Included Files     Find/Peek References     Outline of Module	e editors:  • LSP Lenses: lsp-avy-lens  • LSP sideline:  • enable with: (setq lsp-ui-sideline-enable t)  • Use M-x lsp-execute-copde-action to trigger quick-fix actions  Erlang Project-Specific LS Configuration:  • Erlang LS is customizable by using a YAML syntax file called erlang Is.config that should be placed in the root directory of the project.
Isp-mode features	Completion at point     traditional popup with company-mode     Code navigation, with     Isp-find-references     Symbol highlights     Code navigation     Symbol highlights     Symbol highlights     Code Lenses     The Erlang LS configuration provides     Code Lenses     Code Lenses     The Erlang LS configuration provides     Code Lenses     Symbol highlights     Symbol highlights		
Isp-mode integrations see also:	Isp-mode supports integration  • Whelm by using helm-Isp  • Why by using Isp-ivy  • Treemacs by using Isp-iv  • Origami by using Isp-original in the support of the support	with:  A PEL activates v  A PEL activates v  reemacs  PEL activates v	when <b>pel-use-helm-lsp</b> is turned on. when <b>pel-use-lsp-ivy</b> is turned on. when <b>pel-use-lsp-treemacs</b> is turned on. when <b>pel-use-lsp-origami</b> is turned on.

	ey bindings: The Isp-mode is		
• erlang Is	Since the <u>super modifier ke</u> with M-x <u>customize-op</u> With PEL, the following ke The key bindings shown b	ey is not always available, it c tion or with PEL via the <f: eys are good replacement can below show the standard s-1</f: 	
Display LSP workspace Iog buffer	-1 L	(Isp-workspace-show-log WORKSPACE)	Display the log buffer of WORKSPACE.
		(Isp-doctor)	Validate performance settings and write report in a *lsp-performance* buffer.
	-1 = =	(Isp-format-buffer)	Ask the server to format this document.
Add directory to the list of workspace folders		(Isp-workspace-folders- add PROJECT-ROOT)	Add PROJECT-ROOT to the list of workspace folders.  • Prompts for the directory.
Remove a directory from the workspace blacklist		(Isp-workspace-blacklist- remove PROJECT-ROOT)	Remove PROJECT-ROOT from the workspace blacklist.
Remove directory from the list of workspace folders		(Isp-workspace-folders- remove PROJECT-ROOT)	Remove PROJECT-ROOT from the list of workspace folders.
Find Identifier definitions	3	(Isp-ui-peek-find- definitions &optional EXTRA)	Find definitions to the IDENTIFIER at point.
Find symbol implementation locations		(Isp-ui-peek-find- implementation &optional EXTRA)	Find implementation locations of the symbol at point.
Find references s	-	(Isp-ui-peek-find- references &optional INCLUDE-DECLARATION EXTRA)	Find references to the IDENTIFIER at point.
Find symbols s		(Isp-ui-peek-find- workspace-symbol PATTERN &optional EXTRA)	Find symbols in the worskpace. The symbols are found matching PATTERN.
Toggle diagnostic modeline		(Isp-modeline- diagnostics-mode &optional ARG)	Toggle diagnostics modeline.
Toggle LSP protocol logging	-1 T L	(Isp-toggle-trace-io)	Toggle client-server protocol logging.
Toggle current-line status information		(Isp-ui-sideline-mode &optional ARG)	Minor mode for showing status information for current line.  • Displays code status such as definition errors, etc
Toggle code action on modelling		(Isp-modeline-code- actions-mode &optional ARG)	Toggle code actions on modeline.
Toggle headline breadcrumbs		(lsp-headerline- breadcrumb-mode &optional ARG)	Toggle breadcrumb on headerline.  • When active the list of directories are listed on the header line. In graphics mode these are buttons you can use to change directory.
Toggle hover information	-	(Isp-ui-doc-mode &optional ARG)	Minor mode for showing hover information in child frame.  When active, information about symbol at point is shown in a pop-up overlay area. In graphics mode the information has links that can be used to open web-located information.  For small window the information may cover too much code, use this command to toggle in and out of view. Also note that when the point is toward the bottom of a window the information window may not show completely and you may have to scroll your window.
Toggle symbol highlighting		(Isp-toggle-symbol- highlight)	Toggle symbol highlighting.
Toggle code-lens s-		( <b>Isp-lens-mode</b> & optional ARG)	Toggle code-lens overlays.  • Code-lens show information like # times a specific function is referenced.
Execute code action s-		(Isp-execute-code-action INPUT0)	Execute code action ACTION.  If ACTION is not set it will be selected from 'lsp-code-actions-at-point'.  Request codeAction/resolve for more info if server supports.
Highlight all relevant references to symbol at point	-1 a h	(Isp-document-highlight)	Highlight all relevant references to the symbol under point.
Click LSP lens via avy	-1 a 1	(Isp-avy-lens)	Click lsp lens using 'avy' package.  • The code lens must be active. Use s-1 T 1 to activate it if it's not active.
Apropos search for symbol/regexp		(xref-find-apropos PATTERN)	Find all meaningful symbols that match PATTERN.  Can be used to search symbol outside project.  The argument has the same meaning as in 'apropos'.  The result is shown in a *xref* buffer.
Find definitions of symbol at point		(Isp-find-definition &key DISPLAY-ACTION)	Find definitions of the symbol under point.
		(Isp-find-implementation &key DISPLAY-ACTION)	Find implementations of the symbol under point.
Find references of symbol at point	-	(Isp-find-references &optional INCLUDE- DECLARATION &key DISPLAY-ACTION	Find references of the symbol under point.  • The result is shown in a *xref* buffer.
Trigger display hover information		(Isp-ui-doc-glance)	Trigger display hover information popup and hide it on next typing.
		(Isp-describe-thing-at- point)	Display the type signature and documentation of the thing at point.  • Display help about symbol at point inside a *lsp-help* buffer.  substitute of the buffer and used other functions to open identified URL references.
Refactor source import s	-1 r o	(Isp-organize-imports)	Perform the source.organizeImports code action, if available.
Rename symbol at point See also:  Search/Replace	-1 r r	(Isp-rename NEWNAME)	Rename the symbol (and all references to it) under point to NEWNAME.  For renaming the arguments of a function, the <u>iedit mode</u> is more appropriate. It supports restricting the scope to the current function. See <u>Search/Replace</u>
	-1 w D	(Isp-disconnect)	Disconnect the buffer from the language server.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Describe LSP session	s-1 w d	(Isp-describe-session)	Describes current 'Isp-session'.  • Show available tools and the available capabilities  • Shows the information inside a LspBrowser buffer.
Shut LSP workspace down	s-1 w q	(Isp-workspace-shutdown WORKSPACE)	Shut the workspace WORKSPACE and the language server associated with it
Restart LSP workspace	s-1 w r	(Isp-workspace-restart WORKSPACE)	Restart the workspace WORKSPACE and the language server associated with it
Activate LSP	s-1 w s	(Isp &optional ARG)	Entry point for the server startup.     When ARG is t the lsp mode will start new language server even if there is language server which can handle current language.     When ARG is nil current file will be opened in multi folder language server if there is such.     When 'lsp' is called with prefix argument ask the user to select which language server to start.
Treemacs support  • ∑x Treemacs	provide extra features that help	Erlang development. When	respectively activated by PEL user-options <b>pel-use-treemacs</b> and <b>pel-use-lsp-treemacs</b> , these are activated PEL provides bindings for the <a href="https://linear.com/lsp-treemacs">lsp-treemacs</a> features. ustomization group. With PEL use <a href="https://lsp-treemacs">f12&gt; w</a> <a href="https://lsp-treemacs">f3&gt;</a> from an Erlang buffer.
Open LSP Treemacs error list window.	<f12> w e</f12>	(Isp-treemacs-errors-list)	Display an error list window at the bottom of the frame.  The buffer uses the treemacs-mode and supports its commands and key bindings.  See **\sum x** Treemacs** for the list of commands and key bindings.  To close the window, kill its buffer with C-x k
Quick fix	x	(Isp-treemacs-quick-fix &rest ARGS)	If possible, proposes a quick code fix for the error at point.
Open LSP Treemacs symbol window	<f12> w s</f12>	(Isp-treemacs-symbols)	Show symbols view.  • To close the window, kill its buffer with C-x k
Open LSP Treemacs references window	<f12> w x</f12>	(Isp-treemacs-references ARG)	Show the references for the symbol at point. Issue from an Erlang buffer.  With a prefix argument, select the new window and expand the tree of references automatically.  To close the window, kill its buffer with C-x k
Open LSP Treemacs <u>implementations</u> <u>window</u>	<f12> w i</f12>	(Isp-treemacs- implementations ARG)	Show the implementations for the symbol at point. Issue this command from an Erlang buffer.  With a prefix argument, select the new window expand the tree of implementations automatically.  To close the window, kill its buffer with C-x k
Open LSP Treemacs <u>call hierarchy</u> <u>window</u>	<f12> w c</f12>	(Isp-treemacs-call- hierarchy OUTGOING)	Show the incoming call hierarchy for the symbol at point.  • With a prefix argument, show the outgoing call hierarchy.  This does not seem to have been implemented for Erlang.
Open LSP Treemacs     type hierarchy     window	<f12> w t</f12>	(Isp-treemacs-type- hierarchy DIRECTION)	Show the type hierarchy for the symbol at point.  • With prefix 0 show sub-types.  • With prefix 1 show super-types.  • With prefix 2 show both.  This is not implemented for Erlang.

## Emacs & Erlang - References

Document	Notes
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.
Erlang versions	Erlang Versions - Version Scheme     Erlang Support, Compatibility, Deprecations, and Removal
Erlang/OTP @ Github	Erlang source code
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, <u>Erlang</u> <u>Issue Tracker</u> , events.
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.
Erlang/BEAM	Erlang was the first of one of several programming language that runs on the BEAM VM.
Good introduction presentations on Erlang	The soul of Erlang and Elixir Saša Jurić GOTO 2019 A very good presentation that captures the essence of why Erlang is so important. Fast pace. A must see. A great presentation to show people that may be reluctant to use the technology. The Do's and Don'ts of Error Handling Joe Armstrong GOTO 2018
Erlang References	
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.
Erlang Code Guidelines	
Erlang Programming Rules and Conventions	Official Ericsson AB Erlang guidelines.
Inaka's Erlang Coding Standards & Guidelines	Guideline used at Inaka, published on Github.
EDoc User's Guide	Describes how to document code.
Erlang Books	There are several printed and online Erlang books. Erlang's FAQ lists several of them. The following lists some extra ones.
Adopting Erlang	A great and recent (2019 and later) online books on Erlang Development that provides information not available in the Erlang introduction books. Describes how to install Erlang, and how to setup editing tools.  A must read to setup Erlang development. This is still work in progress as of May 2020.  Each page has a date time stamp.
Erlang Information Sites	
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.

Document	Notes
about-erlang     trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang.  • <u>about-erlang</u> provides general information about Erlang, including:  • <u>Learning Erlang</u> , a table with links to resources to learn Erlang.  • <u>Installing Erlang</u> , describes various ways to install Erlang on macOS.  • <u>Tools for Erlang</u> , describes tools you can use for Erlang development.
<b>Emacs and Erlang Man files</b>	
How to create a local whatis file	Show how to create a missing whatis file for a set of man pages.
The Erlang mode for Emacs (user guide)     Erlang mode for Emacs (man page)	On the erlang.org site. Start here. Describes the 2 files (erlang.el and erlang-start.el) provided by the Erlang mode support, how to set them up for various operating systems. Note, however, that PEL provides the setting for you. It also provides an overview of the various features the package provides.  • If found bugs in the erlang man page in the Edit- Moving the marker section. 1) it's the point that is moved, not the marker, 2) C-a is not an Emacs key prefix, so their key binding descriptions like C-a M-a and C-a M-e are invalid. Reported as ERL-1314.  • There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric functions and variables.  • The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -> on a function definition line.  • Another issue: inside the OS-level erlang shell, we can tab-completion a module:function string, but that does not work inside the emacs erlang shell.

Emacs tools for Erlang	
<u>EDTS</u>	EDTS: stands for: The Erlang Development Tool Suite. See also:  • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube  • EDTS:  • configure your project  • One Primary EDTS node  • 1 node per open project  • To setup an Erlang project: a .edts file in the project:  :name "my-project"  :otp-path "path/to/otp"  :node-name "project-node-name"  :lib-dirs '("lib" "deps")
How to install EDTS	Describes some aspects of EDTS and links that may be useful. Lists the requirements.  After installing EDTS, I got several compile errors, and had to install the following other modules: - auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?
Language Server Protocol	Language Server Protocol @ Wikipedia     Language Server Protocol Specifications web site     Language Server Protocol @ Github
LSP for Erlang	LSP support for Erlang is done using the following:  The lsp-mode Emacs Lisp package  The erlang ls Erlang server
company-mode; Modular in-buffer completion framework for Emacs	
Using Tags with Erlang	
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the pel-erlang-shell-prevent-echo is set to t. To activate after setting it: execute pel-init or restart Emacs.