## **Emacs support for the Erlang Programming Language**

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Erlang Support	Emacs supports Erlang via the			
See also: • Erlang Reference			part of OTP PL activates it with pel-use-erlang.	
Concise Guide To			pel-use-edts (set to t or start-automatically).  //th pel-use-erlang-is. Uses the erlang is Erlang LSP server. Integrates with:	
Erlang  about-erlang	<ul> <li>The <u>isp-mode</u> external pace</li> <li>Helm by using <u>helm-lsp</u></li> </ul>	·	with <b>pel-use-erlang-is</b> . Uses the <b>erlang_is</b> Erlang LSP server. Integrates with: s with <b>pel-use-helm-lsp</b> .    Ivy by using   Isp-ivy	
Developing Erlang	_	_	s with pel-use-treemacs and pel-use-lsp-treemacs.	
Code with PEL  set PEL Erlang	• origami by using Isp-or		s with pel-use-Isp-origami.	
<u>environment</u>			ve mainly been replaced by EDTS and needs maintenance. PEL does not support it.	
•	The <u>hide-comnt.el</u> external package.  PEL activates it with <b>pel-use-hide-comnt</b>			
• <u>▼ Text Modes</u>	The <u>iedit</u> external package.    PEL activates it with <b>pel-use-iedit</b> .			
∑ Highlight     ∑ Inserting Text	The <u>smart-dash</u> external package.  PEL activates it with <u>pel-use-smart-dash</u> . erlang-mode is in <u>pel-modes-activating-smart-dash-mode</u> .			
/ // Iliserung Text	The <u>smartparens</u> external	package. 2 PEL activates	s it with <b>pel-use-smartparens</b> . Add it to <b>pel-erlang-activates-minor-modes</b> .	
• <u>∑ Customize</u>		to activate features in Erlan	g via pel-activates-global-minor-mode: show-paren-mode	
	Customization:			
		wed by the group name and	RET to open the specific customization group or one of the following key sequences.	
	pel-pkg-for-erlang: to	o activate <b>pel-use-erlang</b> :	use <f11> SPC e <f2>, or <f12> <f2> from an Erlang buffer. This has sub-group: see</f2></f12></f2></f11>	
		to activate EDTS and LSP.	use <f11> SPC e <f3> 1</f3></f11>	
	• edts: v	when <b>pel-use-edts</b> is on,	use <f11> SPC e <f3> 3</f3></f11>	
		· · ·	un, use <f11> SPC e L <f3> 1 un, use <f11> SPC e L <f3> 2</f3></f11></f3></f11>	
	The <b>pel-pkg-for-erlang</b> group	has several user-options to	control Erlang editing. Only some of them are described here. Use Emacs for the complete list.	
<b>ĕ →</b>			the Erlang shell from echoing every command. tivation of local minor modes in erlang-mode buffers, eg. smart-dash-mode.	
Identify minor modes to	pel-erlang-environment gr	oup:		
activate automatically in erlang-mode buffers			at directory of Erlang man directory. The man directory should hold the man1, man3, man4 and EL sets (override) the <a href="erlang.el">erlang.el</a> erlang-root-dir user-option value with it which activates the	
	appropriate Erlang man f	iles. Without PEL or if pel-e	erlang-man-parent-rootdir is nil, you must set the erlang-root-dir user-option yourself.	
	<ul> <li>pel-erlang-exec-path: log</li> <li>pel-erlang-version-dete</li> </ul>		errang binaries are stored.  mechanism to detect Erlang/OTP version. By default it uses an Erlang script provided with PEL.	
	pel-erlang-code-style group	ıp:		
			ping occurs: maximum line length (defaults to 100). You can change the value or set it nil.  prlang-mode buffers use the Emacs fill-column value like other major modes.	
			parators are used in Erlang code templates (see the Insert Erlang Code Template section below), nether secondary separator lines are inserted by some Erlang code templates,	
			automatically updated time stamps are inserted by some Erlang code templates,	
• <u>∑ Speedbar</u>	<ul> <li>PEL adds ∑ Speedbar for</li> </ul>	erl, .hrl and .escript Erlan	g files to show the list of functions.	
Open this PDF file.	• <f11> SPC e <f1></f1></f11>	(pel-help-pdf &optional	Open the <u>\$\mathbf{N} \tau - Erlang</u> local PDF. If the prefix argument (like <b>C-u</b> or <b>M</b> ) is used, then it opens	
See also: <u>▼ Help/Info</u>	• <f11> SPC e w <f1> • <f11> SPC e L <f1></f1></f11></f1></f11>		the remote GitHub hosted raw PDF instead. If the <b>pel-flip-help-pdf-arg</b> user-option is set it's the other way around.	
	• <f12> <f1></f1></f12>		Key sequences that start with <f11> SPC e are available from any major modes.</f11>	
	• <f12> <f1> • <f12> w <f1></f1></f12></f1></f12>		Key sequences that start with <f12> are only available in erlang-mode buffers.</f12>	
	• <f12> L <f1></f1></f12>		The <f12> keys sequences are mirrored by the <m-f12> key sequence for convenience.</m-f12></f12>	
∑ Customize PEL Erlang	<f11> SPC e <f2></f2></f11>	(pel-customize-pel	Customize PEL Erlang support: access PEL user-options to activate Erlang support packages.	
support	<f12> <f2></f2></f12>	&optional OTHER- WINDOW)	If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.	
∑ Customize Emacs	<f11> SPC e <f3></f3></f11>	(pel-customize-library	Customize Emacs Erlang support: erlang, erldoc, edts, auto-highlight-symbol, lsp-mode, lsp-ui,	
Erlang support	<f12> <f3></f3></f12>	&optional OTHER- WINDOW)	Isp-treemacs.	
		,	If OTHER-WINDOW is non-nil (use C-u), display in another window.	
∑ Customize PEL LSP for Erlang support	<f11> SPC e L <f2></f2></f11>	(pel-customize-pel &optional OTHER-	Customize PEL LSP Erlang support  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.	
Tor Entiry Support	<f12> L <f2></f2></f12>	WINDOW)	This is available when <b>pel-use-erlang-is</b> is turned on.	
<b>∑ Customize</b> Emacs	<f11> SPC e L <f3></f3></f11>	(pel-customize-library	Customize Emacs LSP Erlang support: Isp-erlang, Isp-mode, Isp-ui, helm-Isp, Isp-ivy, Isp-	
LSP for Erlang support	<f12> L <f3></f3></f12>	&optional OTHER-	origami, Isp-treemacs.	
	<112> L <13>	WINDOW)	<ul> <li>If OTHER-WINDOW is non-nil (use C-u), display in another window.</li> <li>This is available when pel-use-erlang-Is is turned on.</li> </ul>	
∑ Customize PEL LSP Window for Erlang	<f11> SPC e w <f2></f2></f11>	(pel-customize-pel &optional OTHER-	<ul> <li>Customize PEL LSP Erlang support</li> <li>If OTHER-WINDOW is non-nil (use C-u), display in another window.</li> </ul>	
support	<f12> w <f2></f2></f12>	WINDOW)	This is available when <b>pel-use-treemacs</b> and/or <b>pel-use-lsp-treemacs</b> is turned on.	
<b>∑ Customize</b> Emacs	<f11> SPC e w <f3></f3></f11>	(pel-customize-library	Customize Emacs LSP Erlang support: Isp-treemacs, treemacs	
LSP Window for Erlang	<f12> w <f3></f3></f12>	&optional OTHER-	If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.	
support	-112~ W \13/	WINDOW)	This is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned on.	
Environment Help	Use the following command to	verify your Erlang environn	nent.	
Erlang Mode version	<f11> SPC e ?</f11>	(pel-show-erlang-	Display the following information in the minibuffer.	
		version)		
	<f12> ?</f12>	' '	f available Erlang system, of <u>erlang.el</u> , of <u>erlang_ls</u> (if available), values of erlang-root-dir and pel-	
		,	<ul> <li>! Check that erlang-root-dir matches the version of Erlang you use. If not check the setting of cotdir. For more information see set PEL Erlang environment.</li> </ul>	
Cumtou Highlightin	The <b>erland of</b> external package		Erlang code syntax highlighting:	
Syntax Highlighting	Off, Level 1: comments only	, Level 2, Level 3, Level 4: n	naximum variety.	
	<ul> <li>Off, Level 1: comments only, Level 2, Level 3, Level 4: maximum variety.</li> <li>There is not key binding for this. You must use the Syntax Highlighting section of the Erlang menu:</li> <li>In terminal mode Type <f10> to access the menu, then select Erlang, Syntax Highlighting and the level you want.</f10></li> </ul>			
Electric 16	71			
Electric Keys	· ,		special editing tasks to help edit Erlang source code.	
Electric > (for the end of arrow)	>	(erlang-electric-gt &optional ARG)	Insert a greater-than sign, and optionally insert a new line and indent.	
Electric comma		(erlang-electric-comma	Insert a comma character and possibly a new indented line.	
Electric Confilla	,	&optional ARG)	moon a comma character and possibly a new indefited line.	
			riterion, when fulfilled a newline is inserted and the next line is indented.	
			h a numerical arg, point is inside string or comment, or when there are non-whitespace characters	
	following the point on the current line.			

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>			
Electric semicolon	;	(erlang-electric- semicolon &optional ARG)	Insert a semicolon character and possibly a prototype for the next line.			
	line is inserted. Normally the The variable 'erlang-electric	ric-semicolon-criteria' states a criterion, when fulfilled a newline is inserted, the next line is indented and a prototype for the next the prototype consists of " ->". Should the semicolon end the clause a new clause header is generated. ric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header. nal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace point on the current line.				
Matching pairs	(	When the <u>smartparens</u> external package is used and the smartparens-mode is active, the characters on the left are taken to be part of a pair. The pairs are: (), [], {}, " ", ' ', and << >>.				
• <u>∑</u> x Smartparens	[ {	The smartparens-mode minor-modes user-option Use the <f11> ( ) ke</f11>	ext inside one of those pairs, mark the text area then type the first character of the pair. can be activated automatically for Erlang by adding erlang-mode to the <b>pel-erlang-activates</b> -on.  Bey sequence to toggle the smartparens-mode on and off. arens-strict-mode but that does not help much in Erlang.			
Erlang Comments Comments @ Erlang Programming Rules & Conventions See also: Comments	Erlang uses the % character to  % - Single percent  %% - Two percent o  %%% - Three percent	t characters for comments le characters are used for comments to characters are used to des	uses the following conventions: ocated toward the end of a line of code ments starting at indentation level. cribe modules and are always placed in the first column by the comment-column variable. Set it with comment-set-column, bound to C-x;			
PEL extension of comment-dwim specialized for Erlang.	M-;	(comment-dwim ARG) (pel-erlang-comment-dwim &optional ARG)	Comment line or region with % or %% style comments depending on the location in the buffer.  Does the same but adds ability to insert %%% comments. It does that on the very first line in the buffer and lines that follow a line that starts with %%%.			
Automatically uses the %%% comment when appropriate.  **  Note:  M-; works much	With marked un-commente     With marked commented re	d no comment: On empty On first em On line wit d region: Comment region gion: Un-comments the	line: insert <b>%%</b> comment starter at the proper indentation level.  pty line in buffer: insert <b>%%%</b> comment. Also following lines or region that starts with <b>%%%</b> h code: insert <b>%</b> comment starter after the code for an end-of-line comment (each line is commented)			
better than C-c C-c and C-c C-u			However PEL uses M-1 for something else. s indent-for-comment if nothing is marked.			
<ul> <li>PEL maps M-; to pel-erlang-comment- dwim which works even better.</li> </ul>	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region.  With just C-u prefix arg, uncomment each line in region BEG END.  Numeric prefix ARG means use ARG comment characters.  If ARG is negative, delete that many comment characters instead.			
See also: Comments	By default, the 'comment-s	start' markers are inserted a	d 'comment-padding'; the comment end by 'comment-end' and 'comment-padding'.  It the current indentation of the region, and comments are terminated on each line (even for and blank lines do not get comments). This can be changed with 'comment-style'.			
Un-comment region	C-c C-u	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region.  The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.			
Toggle display of comments in buffer or active region See also: Comments	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer.  • If the region is active, then toggle comments in the region. Otherwise, in the whole buffer.  • Requires the			

Notice the 3 sets of commands:   Shavigation   Noving by Defuns	<u>N</u>	Function	<u>Keystroke</u>	Description
• to start of function  • Go backward to beginning of the previous function of previous function as the property of previous function  • Go forward to beginning of next function of the previous function of function of previous function of fun	Several commands are specialization of the normal navigation commands which are described in the table Navigation, but several are specific to Erlang:  Notice the 3 sets of commands:  (*f12 > <up> and <f12> <down> move to the beginning of Erlang functions skipping all compiler directives.  The standard navigation commands, (mapped to <f6> prefix) move to beginning/end of Erlang functions but stop at compiler directives.  The <f12> <up> and <up> and</up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></up></f12></up></f12></up></f12></up></f12></up></f12></up></f12></up></f12></f6></down></f12></up>			
Continued to beginning of the previous function supplied functions	npiler directives. Skips clauses.	on beginning/end at/skippir	Move to next/previous funct	• By <u>Function</u> • Mo
Seginaring of previous function		etion	Move to beginning of fun-	to start of function
C-c C-d C-b (feri-goto-previous-function)  • Go forward to beginning of next function  • C+212> <a href="cellpass">document of the previous function of the previous function of the period of the pe</a>	oves point to the first character of the function that the function prefix argument N repeat N times.		• <f12> f p</f12>	beginning of e <f< td=""></f<>
• Go forward to beginning of next function  • <pre> • Go forward to beginning of next function beginning of next function  • <fi> &lt; fi &gt; fi &gt; fi &gt; fi &gt; fi &gt; fi &gt; f</fi></pre>	ift marking is available for the key sequence		• <f11> SPC e f p</f11>	• <f< td=""></f<>
Soptional N	ips all compiler directives.		C-c C-d C-b	С-с
• f11> SPC e f n	oves point to the first character of the function the prefix argument N repeat N times.	u	• <f12> f n</f12>	beginning of next function
* Lo start of function/directive     ** Move to beginning of function or compiler directive     ** C-N-a				
## Go backward to beginning of previous:  * Go backward to beginning of previous:  * C-N-a  * C-N-a  * C-N-chome>  * C-N-chome>  * C-R-chome>	ips all compiler directives.	(ferl-goto-next-function)	C-c C-d C-f	С-с
beginning of previous:		ction or compiler directive	Move to beginning of fundamental	
• C-M-a • tunction • tunction • compiler directive • <pre></pre>	0 0		<f12> f P</f12>	
defun &optional SILENT   Lunction   compiler directive   - (f11) SPC of N   - (f5) < down>   - (f5) < down>   - (f5) < down>   - (f11) SPC of N	beginning of defun.  ►Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However<f6> p and <f6> <up> handle Shift-marking fine in terminal mode</up></f6></f6></home>	(erlang-beginning- of-function	• C-M- <home> • <f6> p • <f6> <up></up></f6></f6></home>	previous:     function     compiler     directive
• function • compiler directive • *f6> a			<f12> f N</f12>	
Backward to end of previous:	he beginning of next function is found, pus DNT-PUSH_MARK is non-nil. Move back to previous position with M-`.		• <f6> <down></down></f6>	• function • <f< td=""></f<>
of previous:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function     • compiler directive  - Forward to end of next:     • function directive  - Forward to end of next:     • function directive  - Forward to end of next:     • function definition.  - Shift marking is available for the <f6> bindings.  - With a numerical argument of to the that many times.  - Forward to line after end of Erlang function.  With a numerical argument repeat that many times.  - Forward to line after end of defun.      • Forward to line after end of defun.      • Flang function.  - Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-index).  - Forward to line after end of Erlang function.  - Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-index).  - Forward to line after end of Erlang duretion.  - Forward to line after end of Erlang duretion.  - Forward to line after end of Erlang function.  - Forward to line after end of Erlang duretion.  - Forward to l</f6>				
next:     • function     • compiler directive      • By Expression     • functions, etc      • Go to beginning of statement      • Go to end of statement      • Go to end of statement      • Go to end of statement      • Cf12> s e      • Cf6> <right>      • Cf6&gt; <right>      • Cf6&gt; <right>      • ARG)     (erlang-end-of-function &amp; optional ARG)      • Cforward-sentence &amp; optional ARG)      • Cf12&gt; s e      • With a numerical argument repeat that many times.      • With a numerical argument repeat that many times.      • With a numerical argument repeat that many times.      • With a numerical argument repeat that many times.</right></right></right>	eps if does not find end of previous function he end of previous function is found, push ISH_MARK is non-nil. Move back to previous position with M-`.	defun &optional SILENT	<f6> <left></left></f6>	of previous:     • function     • compiler
<ul> <li>functions, etc</li> <li>The following commands move to the beginning/end of single expression or expression sequence.</li> <li>They do not move across expressions in a sequence of expressions.</li> <li>Since Erlang function definition is also an Erlang expression, these commands move across function definitions.</li> <li>Go to beginning of statement</li> <li>M-a</li> <li>(backward-sentence &amp; optional ARG)</li> <li>With a numerical argument repeat that many times.</li> <li>Go forward to the end of an Erlang statement.</li> <li>With a numerical argument repeat that many times.</li> <li>With a numerical argument repeat that many times.</li> </ul>	argument, do it that many times. Negative eding end of defun. nift marking is available in graphics mode,	ARG) (erlang-end-of- function & optional	• C-M- <end></end>	next: • function • compiler
<ul> <li>statement</li> <li><f12> s a</f12></li> <li>Go to end of statement</li> <li>M-e</li> <li>(forward-sentence &amp; optional ARG)</li> <li>With a numerical argument repeat that many times.</li> <li>Go forward to the end of an Erlang statement.</li> <li>With a numerical argument repeat that many times.</li> <li>With a numerical argument repeat that many times.</li> </ul>	xpression or expression sequence.	e to the beginning/end of sin pressions in a sequence of	The following commands move  • They do not move across ex	• functions, etc The f
statement <pre>statement</pre> <pre></pre>				statement
By <u>Function Clause</u> Move by clauses of a function. A function definition (statement) may have multiple clauses, each separated by a semicolon.		,		statement
	may have multiple clauses, each separate	A function definition (stater	Move by clauses of a function.	By Function Clause Move
• Go backward to beginning of clause • <pre></pre>	th argument, do this that many times.		• <f12> c a</f12>	beginning of clause • <f< td=""></f<>
• Go forward to beginning of next clause  • <f12> c n • <m-f12> <m-down> clause  • <f12> c n • <m-f12> <m-down> clause  • Move forward to the beginning of next clause. • Pushes mark; move back to previous position with M-`.  ⇒Shift marking is available.</m-down></m-f12></f12></m-down></m-f12></f12>	shes mark; move back to previous position			beginning of next • <n< td=""></n<>
• Go backward to end of previous clause  • <f12> c p • <m-f12> <m-left>  (pel-end-of-previous-clause)  Move backward to the end of the previous clause. • Pushes mark; move back to previous position with M−`.  Shift marking is available.</m-left></m-f12></f12>	shes mark; move back to previous position		<del>-</del>	
• Go forward to end of current clause • <f12> c e • <m-right>  (erlang-end-of-clause &amp; optional ARG)  Move to the end of the current clause. • With argument, do this that many times.  Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.</m-right></f12>	th argument, do this that many times.	,	• <f12> c e</f12>	current clause • <f< td=""></f<>

Description	<u>Keystroke</u>	Function	<u>Note</u>		
Block Navigation	Erlang syntax uses balanced b  ( ) for function p  { } for tuples, re  [ ] for lists  " " strings				
See also:  • <u>∑x Smartparens</u>		be activated automatically	for Erlang by adding erlang-mode to the pel-erlang-activates-minor-modes user-option.		
	Standard Erlang support provide some commands to navigate across and into these balanced blocks. Their name is shown in <b>black</b> in the following row.  Other commands are provided by **\sum **\sum ** Smartparens* when smartparens-mode minor-mode is active. Some are *PEL specializations* of smartparens commands are provided by **\sum **\s				
To Block start/end	The following commands move	e to the beginning or end of	f a block, skipping over Erlang terms inside these blocks.		
Go backward to	• C-M-p	(backward-list &optional	Move backward to beginning of previous block.		
beginning of previous block • Skips terms.	-	ÀRG)	<ul> <li>Supports blocks of (), [] and {}.</li> <li>With ARG, do it that many times.</li> <li>A negative argument N means forward-list N.</li> <li>This command assumes point is not in a string or comment.</li> </ul>		
			<pre>-spec ejabberd_started6() -&gt; ok. ejabberd_started5() -&gt;    gen_server:call4(?MODULE, ejabberd_started, ?CALL_TIMEOUT).</pre>		
			<pre>-spec config_reloaded3() -&gt; ok. config_reloaded2() -&gt;    gen_server:call1(?MODULE, config_reloaded, ?CALL_TIMEOUT).0</pre>		
Go backward to end of previous block Skips terms.  **\sum_{x} \text{Smartparens}  with smartparens	<m-f7> p</m-f7>	(pel-sp-previous-sexp &optional ARG)	Move backward to end of previous block.  • With ARG, do it that many times. If there is no next expression at current level, jump one level up (effectively doing 'sp-up-sexp').  • A negative argument N means move to the end of N-th following balanced expression.		
with smartparens- mode active			<pre>-spec ejabberd_started() 6 -&gt; ok. ejabberd_started() 5 -&gt;    gen_server:call(?MODULE, ejabberd_started, ?CALL_TIMEOUT) 4.</pre>		
			<pre>-spec config_reloaded()3 -&gt; ok. config_reloaded()2 -&gt;    gen_server:call(?MODULE, config_reloaded, ?CALL_TIMEOUT)1.0</pre>		
<ul> <li>Go forward to end of next block</li> <li>Skips terms.</li> </ul>	• C-M-n	(forward-list &optional ARG)	Move forward to end of next block.  Supports blocks of (), [] and {}.  With ARG, do it that many times.  A negative argument N means forward-list N.  This command assumes point is not in a string or comment.		
			<pre>0-spec ejabberd_started() 1 -&gt; ok. ejabberd_started() 2 -&gt; gen_server:call(?MODULE, ejabberd_started, ?CALL_TIMEOUT) 3.</pre>		
			<pre>-spec config_reloaded()4 -&gt; ok. config_reloaded()5 -&gt;    gen_server:call(?MODULE, config_reloaded, ?CALL_TIMEOUT)6.</pre>		
Go forward to beginning of next block     Skips terms.	<m-f7> n</m-f7>	(pel-sp-next-sexp &optional ARG)	Move forward to <b>beginning</b> of next block (and term if 'sp-navigate-consider-symbols' is set).  With ARG, do it that many times.  If there is no next expression at current level, jump one level up (effectively doing 'sp-backward-up-sexp').		
<u>X Smartparens</u> with smartparens-     mode active			<pre>0-spec ejabberd_started1() -&gt; ok. ejabberd_started2() -&gt; gen_server:call3(?MODULE, ejabberd_started, ?CALL_TIMEOUT).</pre>		
			<pre>-spec config_reloaded4() -&gt; ok. config_reloaded5() -&gt;</pre>		
			gen_server:call 6(?MODULE, config_reloaded, ?CALL_TIMEOUT).		
By Blocks and Terms	Move across blocks made of pairs of {}, [] and (). Also stops at terms.  ! With PEL: to use Esc C- <right> bindings below, set pel-windmove-on-esc-cursor user-option is set to nil.  Several Linux distros map C-M-<left> and C-M-<right> to desktop workspace operation. In that case you can either use another key binding or change Linux key binding in Systems-&gt;settings-&gt;keyboard-&gt;shortcuts to prevent it from using that key sequence.</right></left></right>				
Go backward to beginning of previous term/block	• C-M- <left> • C-[ C-b • Esc C-b • Esc C-<left> • C-M-b</left></left>	(backward-sexp &optional ARG)	Move backward backward to beginning of previous term or block.  • With ARG, do it that many times.  • A negative arg N means move forward to end of N terms/blocks.  • At beginning of block, jump out of the current one.  • This command assumes point is not in a string or comment.  • C-M-p : ► Shift marking is available in graphics mode, not in terminal mode.  • C-M-b : ► Shift marking is available in graphics mode, not in terminal mode.  • C-M-Sleft>: ► Shift marking works with this command.		
• <u>∑</u> x Smartparens	• C-M-b	(sp-backward-sexp	♦ C-M- <left> does not work on Windows, but H-<left> works.  Same as above with the additional behaviour:</left></left>		
with smartparens- mode active: • C-M-b and <m- f7&gt; b use sp- backward-sexp,</m- 	• <m-f7> b</m-f7>	&optional ARG)	<ul> <li>With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default.</li> <li>When it is nil, point only stops at 1, 4, 6 and 9: it jumps over terms.</li> <li>-spec ejabberd_started() -&gt; ok.</li> </ul>		
others are using backward-sexp			ejabberd_started() -> gen_server:call 9(?MODULE, ejabberd_started, ?CALL_TIMEOUT).  -8spec 7config_reloaded 6() -> 5ok.		
			<pre>5config_reloaded 4() -&gt;</pre>		
		1	4		

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Go forward to end of next term/block	• C-M- <right> • C-[ C-f • Esc C-f • Esc C-<right> • C-M-f</right></right>	( <b>forward-sexp</b> &optional ARG)	Move forward to end of term or block.  • With ARG, do it that many times.  • A negative argument N means move backward to beginning of previous term or block.  • At end of block, jump out of the current one.  • C-M-n : Shift marking is available in graphics mode, not in terminal mode.  • C-M-f : Shift marking is available in graphics mode, not in terminal mode.  • C-M- <right> : Shift marking works with this command.  • C-M-<right> does not work on Windows, but H-<right> does.</right></right></right>
<ul> <li>         \$\sumes\$ \times \text{Smartparens} \\         \text{with smartparens-mode active:} \\             \text{C-M-f and <m-f7> f use sp-forward-sexp,} \\             \text{others are using forward-sexp}     \] </m-f7></li> </ul>	• C-M-f • <m-f7> f</m-f7>	(sp-forward-sexp &optional ARG)	Same as above with the additional behaviour:  • With 'sp-navigate-consider-symbols' symbols and strings are also considered balanced expressions. It is set by default.  • When it is nil, point only stops at 3, 6 and 9 it jumps over terms.  O-spec 1 ejabberd_started 2() 3 -> ok 4.  ejabberd_started 5() 6 ->  gen_server 7: call 8(?MODULE, ejabberd_started, ?CALL_TIMEOUT) 9.  -spec 10 config_reloaded() -> ok.  config_reloaded() ->  gen_server: call (0?MODULE 1, config_reloaded 2, ?CALL_TIMEOUT 3).
Into block	Navigate inside nested blocks	of elements with the follow	
Into block forward	C-M-d	(down-list &optional	Move forward to the beginning of inner element of a block.
into block forward	C-M-u	ARG)	With ARG, do this that many times.
<u>SX Smartparens</u> with smartparens-     mode active	• C-M-d • <m-f7> d</m-f7>	(sp-down-sexp &optional ARG)	<ul> <li>A negative argument N means move backward but still go down a level.</li> <li>If ARG is raw prefix argument C-u, descend forward as much as possible.</li> <li>If ARG is raw prefix argument C-u C-u, jump to the beginning of current list.</li> <li>If the point is inside block and there is no down expression to descend to, jump to the beginning of current one. If moving backwards, jump to end of current one.</li> <li>music_info() -&gt; <ul> <li>[2error, {3noreply, State}},</li> <li>example</li> <li>good, {{year, 1974},</li> <li>group, "Contraction"},</li> <li>{song, "A la claire fontaine"},</li> <li>{song, "L'alarme à l'oeil"},</li> <li>{song, "La bourse ou la vie"}]</li> <li>{rating, excellent}}}</li> </ul> </li> </ul>
Into block backward  •	• <m-f7> z • C-M-z</m-f7>	(sp-backward-down- sexp &optional ARG)	Move backward down one level to end of block element.  • With ARG, do this that many times.  • A negative argument N means move forward but still go down a level.  • If ARG is raw prefix argument C-u, descend backward as much as possible.  • If ARG is raw prefix argument C-u C-u, jump to the end of current list.  • If the point is inside sexp and there is no down expression to descend to, jump to the end of current one. If moving forward, jump to beginning of current one.  music_info(1) ->  [{error, {noreply, State}},
to edge of block			
To beginning of block  • ∑x Smartparens with smartparens- mode active	• <m-f7> a</m-f7>	(sp-beginning-of-sexp &optional ARG)	Jump to beginning of the block the point is in.  • The beginning is the point after the opening delimiter.  • With no argument, this is the same as C-u C-u 'sp-down-sexp'  • With ARG positive N > 1, move forward out of the current expression, move N-2 expressions forward and move down one level into next expression.  • With ARG negative N < 1, move backward out of the current expression, move N-1 expressions backward and move down one level into next expression.  • With ARG raw prefix argument C-u move out of the current expressions and then to the beginning of enclosing expression.  music_info() -> {{error, {noreply, State}}, {good, {{1year, 19074},
To end of current block • forward • ∑x Smartparens with smartparens- mode active	<m-f7> e</m-f7>	(sp-end-of-sexp &optional ARG)	<pre>Import of the current block. Jump to end of the current block. With no argument, this is the same as calling C-u C-u 'sp-backward-down-sexp'. With ARG positive N &gt; 1, move forward out of the current expression, move N-1 expressions forward and move down backward one level into previous expression, move N-2 expressions backward and move down backward one level into previous expression. With ARG raw prefix argument C-u move out of the current expressions and then to the end of enclosing expression.  music_info() -&gt; {</pre>

```
Description
                                                                   Function
                                     Kevstroke
                                                                                                                                     Note

    Out of block

                                                           (up-list &optional ARG
                                                                                       Move forward out of one level of block parens.
Out block forward
                            C-M-1
                                                           ESCAPE-STRINGS NO-
                                                                                       • With ARG, do this that many times.
                                                           SYNTAX-CROSSING)
                                                                                         A negative argument means move backward but still to a less deep spot.

    If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode,
remove the whitespace between end of the expression and the last "thing" inside the

                            • C-M-1
                                                           (sp-up-sexp &optional
                                                           ARG INTERACTIVE)
                            • <M-f7> ]
                                                                                          This behaviour can be suppressed for syntactic string blocks by setting 'sp-navigate-reindent-
  after-up-in-string' to nil.
     with smartparens-

    If 'sp-navigate-close-if-unbalanced' is non-nil, close the unbalanced expressions

                                                                                         automatically.
                                                                                       music_info() ->
                                                                                            {{erOror, {noreply, State}}1,
                                                                                                                                                            example
                                                                                              {go od, {{year, 1974},
                                                                                                                                                           example
                                                                                                          {group, "Contraction"},
                                                                                                                      "Sam M'Madown"},
"A la claire fontaine"},
"L'alarme à l'oeil"},
"La bourse ou la vie"}]
                                                                                                          [{song,
{song,
                                                                                                           {song,
{song,
                                                                                                          {rating, excellent}}1
                                                                                       Move backward out of one level of block parens.
Out block backward
                            • <M-f7> u
                                                           (sp-backward-up-sexp
                                                           &optional ARG
INTERACTIVE)

    With ARG, do this that many times.

  backward
                            • C-M-u
                                                                                         A negative argument means move forward but still to a less deep spot.
                                                                                         If called interactively and 'sp-navigate-reindent-after-up' is enabled for current major-mode, remove the whitespace between beginning of the expression and the first "thing" inside the
  expression.
     with smartparens-
                                                                                       music info() ->
     mode active
                                                                                          [6]{{error, {noreply, State}},
                                                                                          5{good, 4{{year, 1974},
                                                                                                          {group, "Contraction"},
                                                                                                       3[\{song,
                                                                                                                      "Sam M'Madown"},
                                                                                                                       "A la claire fontaine"},
"L'alarme à l'oeil"},
                                                                                                           {song,
{song,
                                                                                                                       1"La bourse ou la Ovie"}]
                                                                                                         2{song,
                                                                                                          {rating, excellent}}}.
                            The commands all use the XX Smartparens external package and required smartparens-mode minor-mode to be active.
Move over space
                                                                                       Skip whitespace and comments moving forward.

If STOP-AT-STRING is non-nil, stop before entering a string (if not already in a string).

If STOP-AFTER-STRING is non-nil, stop after exiting a string.
To beginning of next symbol/block
                            <M-f7> SPC n
                                                           (sp-skip-forward-to-
                                                           symbol &optional STOP-
                                                           AT-STRING STOP-
                                                           AFTER-STRING
  start_app(App) ->0
                                                           STOP-INSIDE-STRING)
                                                                                                                                        % first clause
                                                                                                                                                                    example
     with smartparens-
                                                                                            1 start_app(App, temporary).
     mode active
                                                                                       start_app(App, 0 1Type) ->
    StartFlag = not is_loaded(),
    start_app(App, Type, StartFlag).
                                                                                                                                        % second clause
                                                                                                                                                                    example
To end of next symbol
                            <M-f7> SPC m
                                                           (sp-forward-symbol
                                                                                       Move point to the next position that is the end of a symbol.
or block
                                                           &optional ARG)
                                                                                          With ARG being positive number N, repeat that many times.

With ARG being negative number -N, repeat that many times in backward direction.
A symbol is any sequence of characters that are in either the word constituent or symbol

   constituent syntax class. Current symbol only extend to the possible opening or closing delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax
     with smartparens-
     mode active
                                                                                          classes.
                                                                                       This stops inside comments instead of skipping them.
                                                                                                                                                                      example
                                                                                       start_app(App) ->
                                                                                                                                     % first clause
                                                                                            start_app(App() temporary(1).
                                                                                       start_app(App(), Type(1) ->
                                                                                                                                      % second 2 clause 3
                                                                                                                                                                      example 
                                                                                            StartFlag4 = not5 is_loaded6(),
                                                                                            start_app7(App8, Type9, StartFlag10).
                            <M-f7> SPC p
To beginning of
                                                           (sp-backward-symbol
                                                                                       Move point to the next position that is the beginning of a symbol.
                                                           &optional ARG)
                                                                                          With ARG being positive number N, repeat that many times.
                                                                                         With ARG being negative number -N, repeat that many times in forward direction.

A symbol is any sequence of characters that are in either the word constituent or symbol
  constituent syntax class. Current symbol only extend to the possible opening or closing
     with smartparens-
                                                                                          delimiter as defined by 'sp-add-pair' even if part of this delimiter would match "symbol" syntax
     mode active
                                                                                          classes.
                                                                                       This stops inside comments instead of skipping them.
                                                                                                                                      % 🛮 first 🗸 clause 👈 Error! 🚧
                                                                                       10start_app(9App) ->
                                                                                            6start_app(5App, 4temporary).
                                                                                       3start_app(2App, 1Type) ->
                                                                                            OStartFlag = not is_loaded(),
start_app(App, Type, StartFlag).
                                                                                                                                                                     example
                                                           (sp-forward-whitespace
                                                                                       Skip forward past the whitespace characters.
Skip forward past
                            <M-f7> SPC .
whitespace
                                                           &optional ARG)
                                                                                         With non-nil ARG return number of characters skipped.
    ∑X Smartparens
                                                                                       start_app(App) ->0
                                                                                                                                      1 first clause
                                                                                             start_app(App, temporary).
     with smartparens-
     mode active
                                                                                                                                     % second clause 0
                                                                                       start_app(App, Type) ->
                                                                                            1StartFlag = not is_loaded(),
                                                                                            start_app(App, Type, StartFlag).
                            <M-f7> SPC ,
Skip backward past
                                                                                       Skip backward past the whitespace characters.
                                                           (sp-backward-
                                                           whitespace &optional
                                                                                         With non-nil ARG return number of characters skipped.
                                                           ARG)
                                                                                       start_app(App) ->1
                                                                                                                                        first clause

    ∑X Smartparens

                                                                                            start_app(App, temporary).
     with smartparens-
     mode active
                                                                                                                                     % second clause 1
                                                                                       start_app(App, Type) ->
                                                                                            OStartFlag = not is_loaded(),
                                                                                            start_app(App, Type, StartFlag).
```

Description	<u>Keystroke</u>	Function	Note
Copy and Clone	· ·		cloning operations. They are provided by <u>SX Smartparens</u>
• <u>S</u> X Smartparens			lay the copied string when <b>pel-show-copy-cut-text</b> is <b>t</b> . Toggle this display with <b><f11> M-=</f11></b>
Copy current & forward block(s)	<m-f7> =</m-f7>	(sp-copy-sexp &optional ARG)	Copy the following ARG expressions to the kill-ring.  This is exactly like calling 'sp-kill-sexp' with second argument t. All the special prefix arguments work the same way.
Copy previous block(s)	<m-f7> M-=</m-f7>	(sp-backward-copy- sexp &optional ARG)	Copy the previous ARG expressions to the kill-ring.  This is exactly like calling 'sp-backward-kill-sexp' with second argument t. All the special prefix arguments work the same way.
clone current block	<m-f7> c</m-f7>	(sp-clone-sexp)	Clone sexp after or around point.  If the form immediately after point is a sexp, clone it below the current one and put the point in front of it.  Otherwise get the enclosing sexp and clone it below the current enclosing sexp.
Edit Erlang Code	The following commands help	edit Erlang code.	
Create additional clause	C-c C-j	(erlang-generate-new-clause)	Create additional Erlang clause header.  Parses the source file for the name of the current Erlang function. Create the header containing the name, a pair of parentheses, and an arrow. The space between the function name and the first parenthesis is preserved. The point is placed between the parentheses.
Clone clause arguments	С-с С-у	(erlang-clone- arguments)	Insert, at the point, the argument list of the previous clause.  Copy the function arguments of the preceding Erlang clause. This command is useful when defining a new clause with almost the same argument as the preceding.  The mark is set at the beginning of the inserted text, the point at the end.
Align arrows inside region	C-c C-a	(erlang-align-arrows START END)	Align arrows ("->") in <b>function clauses</b> inside marked region or in the current function.  • With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to point), not just those in function clauses.
		Before:  Sum(L) -> s  Sum([H T], Sum) -> s  sum([], Sum) -> Sum.  To align something else than clauses, select the code and type:  C-u C-c C-a	
Transform code	The following two commands	from the $\Sigma \mathfrak{X}$ Smartparens $\epsilon$	external package help manipulate Erlang code with blocks.
Transpose block elements  • ∑x Smartparens with smartparensmode active	<m-f7> t</m-f7>	(sp-transpose-sexp &optional ARG)	Transpose the expressions around point.  The operation will move the point after the transposed block, so the next transpose will "drag" it forward.  With arg positive N, apply that many times, dragging the expression forward.  With arg negative -N, apply N times backward, pushing the word before cursor backward. This will therefore not transpose the expressions before and after point, but push the expression before point over the one before it.
			Before (for all following examples):  AList = [1, 2, 3,   [10,11,12,[22,33,44]], 5, 6, 7, 8, []].  After <m-f7> t:  AList = [1, 2, [10,11,12,[22,33,44]], 3 , 5, 6, 7, 8, []].  After M-2 <m-f7> t:  AList = [1, 2, [10,11,12,[22,33,44]], 5, 3 , 6, 7, 8, []].  Before (for all following examples):  AList = [{first,[1, 2, 3]} , [10,11,12,[22,33,44]], 5, 6, 7, 8, []].  After <m-f7> t:  AList = [[10,11,12,[22,33,44]], {first,[1, 2, 3]} , 5, 6, 7, 8, []].  After M-2 <m-f7> t:  AList = [[10,11,12,[22,33,44]], 5, {first,[1, 2, 3]} , 6, 7, 8, []].  Before (for all following examples):  AList = [{first,[1, 2, 3]} , [10,11,12,[22,33,44]], 5, 6, 7, 8, []].  After M <m-f7> t:</m-f7></m-f7></m-f7></m-f7></m-f7>
			AList = [{first,[1, 3 , 2]}, [10,11,12,[22,33,44]], 5, 6, 7, 8,[]].
Push current block after next  • <u>∑x Smartparens</u> with smartparens- mode active	<m-f7> s</m-f7>	(sp-push-hybrid-sexp)	Push the hybrid sexp after point over the following one. <b>Before:</b>
Transform - slurp	The following commands perfo	orm slurping operations, how	wever support for Erlang could be improved as the commands do not always work properly.
Enclose next outside element into current block  • <u>Sx Smartparens</u> with smartparensmode active ###	<m-f7> &gt;</m-f7>	(sp-forward-slurp-sexp &optional ARG)	Add sexp following the current list in it by moving the closing delimiter.  • If the current list is the last in a parent list, extend that list (and possibly apply recursively until we can extend a list or end of file).  • If ARG is N, apply this function that many times.  • If ARG is negative - N, extend the opening pair instead (that is, backward).  • If ARG is raw prefix C-u, extend all the way to the end of the parent list.  • If both the current expression and the expression to be slurped are strings, they are joined together.  • This command does not always work well for Erlang as shown in the first example.  • Use the next command for Erlang in those cases.   Before:  Names = [   Joe. ]  After <m-f7> &gt;:  Names = [   Joe. ]  After <m-f7> &gt;:  AList = [1, 2, 3   1, 4, 5].  After M-f7&gt; &gt;:  AList = [1, 2, 3   4, ], 5].  After M-f7&gt; &gt;:  AList = [1, 2, 3   4, ], 5].  After M-f7&gt; &gt;:  AList = [1, 2, 3   4, ], 5].</m-f7></m-f7>
	<m-f7> M-&gt;</m-f7>	(sp-slurp-hybrid-sexp)	This commands works a little differently and handles some Erlang statement better, but not all.  Before:  Names = [   Joe    Names = [ Joe    After <m-f7> M-&gt;:  Names = [ Joe    After <m-f7> M-&gt;:  AList = [[1, 2, 3   4], 5].</m-f7></m-f7></m-f7></m-f7></m-f7></m-f7></m-f7>

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Enclose previous outside element(s) into next block	<m-f7> &lt;</m-f7>	(sp-backward-slurp- sexp &optional ARG)	Add the sexp preceding the current list in it by moving the opening delimiter.  If the current list is the first in a parent list, extend that list (and possibly apply recursively until we can extend a list or beginning of file).  If arg is N, apply this function that many times.  If arg is negative -N, extend the closing pair instead (that is, forward).  If ARG is raw prefix C-u, extend all the way to the beginning of the parent list.  If both the current expression and the expression to be slurped are strings, they are joined together.
		The position of point inside the list does not matter. The point does not move.	Before: AList = [0, 1, [2, 3], 4], 5].  Before: AList = [0, 1, [2, 3], 4], 5].  After M-2 < M-f7> <: AList = [0, 1, [2, 3], 4], 5].  After M-2 < M-f7> <: AList = [[0, 1, 2, 3], 4], 5].
		<pre>Before: AList = [-2, -1, 0,</pre>	After C-u <m-f7> &lt;: 1, [2, 3, 4], 5].  AList = [[-2, -1, 0, 1, 2, 3, 4], 5].</m-f7>
Enclose next element(s) into previous block  • <u>XX Smartparens</u> with smartparensmode active	<m-f7> ]</m-f7>	(sp-add-to-previous- sexp &optional ARG)	Add the expression around point to the first list preceding point.  With ARG positive N add that many expressions to the preceding list.  If ARG is raw prefix argument C-u add all expressions until the end of enclosing list to the previous list.  If ARG is raw prefix argument C-u C-u add the current list into the previous
• <u>1</u> . ½		This command does not seem to work properly for Erlang as shown by the following examples:	Before: AList = [0, 1, [2, 3],  4, 5].  Before: AList = [0, 1, [2, 3],  4, 5].  After M-2 < M-f7> ]: AList = [0, 1, [2, 3   4, ]5].  After M-2 < M-f7> ]: AList = [0, 1, [2, 3   4, ]5], ].
Enclose previous outside element(s) into next block  • <u>SX Smartparens</u> with smartparens-	<m-£7> [</m-£7>	(sp-add-to-next-sexp &optional ARG)	Add the expressions around point to the first list following point.  With ARG positive N add that many expressions to the following list.  If ARG is raw prefix argument C-u add all expressions until the beginning of enclosing list to the following list.  If ARG is raw prefix argument C-u C-u add the current list into the following list.
mode active		This command works fine in Erlang for the following code examples:	AList = [1,  2, [3, 4]]. AList = [1,  [2, 3, 4]].
			Before:  AList = [1,  2, [3, 4]].  After C-u <m-f7> [:  AList = [[1,  2, 3, 4]].  After C-u C-u <m-f7> [:</m-f7></m-f7>
			AList = [[1,  2], [3, 4]]. AList = [[[1,  2], 3, 4]].
Transform - barf	The following commands extra		Demons the last case in the asymptotics by marine the election delimiter
Eject next element(s) out of current block  • ∑ Smartparens with smartparens- mode active  • 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1	<m-f7> /</m-f7>	(sp-forward-barf-sexp &optional ARG)	Remove the last sexp in the current list by moving the closing delimiter.  If ARG is positive number N, barf that many expressions.  If ARG is negative number -N, contract the opening pair instead.  If ARG is raw prefix C-u, barf all expressions from the one after point to the end of current list and place the point before the closing delimiter of the list.  If the current list is empty, do nothing.
		The forward command does not seem to work properly for Erlang as shown by the	Before:  AList = [[1,  2, 3, 4]].  Before:  Alist = [[1,  2, 3, 4]].  After M <m-f7> /:  After M <m-f7> /:</m-f7></m-f7>
Eject previous element(s) out of	<m-f7> M-/</m-f7>	following examples:  (sp-backward-barf-sexp & optional ARG)	AList = [1,  [2, 3, 4]].  This is exactly like calling 'sp-forward-barf-sexp' with minus ARG.  • In other words, instead of contracting the closing pair, the opening pair is contracted. For
current block  • ∑X Smartparens  with smartparens- mode active			more information, see the documentation of 'sp-forward-barf-sexp'.  Before: AList = [[1,  2, 3, 4]].  AList = [1,  [2, 3, 4]].
		code examples:	Before: After M-3 <m-f7> /: AList = [[1,  2, 3, 4]]. AList = [1,  2, 3, [4]].</m-f7>
Re-wrap block Re-wrap current block	<m-f7> r</m-f7>	(sp-rewrap-sexp PAIR	Re-wrap current block using another block character. Prompt for the pair beginning character.
<u>SX Smartparens</u> with smartparens-		&optional KEEP-OLD)	With C-u, keep old delimiter and wrap with PAIR on the outside of the current expression.
mode active		This command works fine in Erlang for the following code examples:	AList = $[[1,  2, 3, 4]]$ .  AList = $[\{1,  2, 3, 4\}]$ Before:  After C-u <m-f7> r {:</m-f7>
Swap current block and	<m-f7> w</m-f7>	(sp-swap-enclosing-	AList = $[[1,  2, 3, 4]]$ .  AList = $[\{[1,  2, 3, 4]\}]$ Swap the enclosing delimiters of this and the parent expression.
parent block wrapping characters	M-277 W	sexp & optional ARG)  This command works fine	• With N > 0 numeric argument, ascend that many levels before swapping.
<u>XX Smartparens</u> with smartparens-     mode active			AList = ({[1,  2, 3, 4]}). AList = ([{1,  2, 3, 4}]).  Before: After <m-f7> w:</m-f7>
Un-wrap block			AList = $(\{[1,  2, 3, 4]\})$ . AList = $[\{(1,  2, 3, 4)\}]$ .
Extract all elements from current/next block	<m-f7> U</m-f7>	(sp-unwrap-sexp &optional ARG)	Un-wrap current or next block.  • With ARG N, unwrap Nth expression as returned by 'sp-forward-sexp'.  • If ARG is negative -N, unwrap Nth expression backwards as returned by 'sp-backward-sexp'
<u>Standard Standard Standa</u>		This command works fine in Erlang for the following code examples:	
		Before:	<pre>Before: AList = ({[1,  2, 3, 4]}). After <m-f7> U: AList = ({1,  2, 3, 4}). After <m-f7> U:</m-f7></m-f7></pre>
		AList = [1, 2, [3,	
		Before: AList = [1, 2, [3,	After M-2 <m-f7> U: 4], 5, [6, 7], 8]. AList = [1,  2, [3, 4], 5, 6, 7, 8].</m-f7>

Description	<u>Keystroke</u>	Function	<u>Note</u>		
Extract all elements from previous block	<m-f7> W</m-f7>	(sp-backward-unwrap- sexp &optional ARG)	Unwrap the previous block. Unwrap the previous expressio	n.	
• <u>SX Smartparens</u> with smartparens-			With ARG N, unwrap Nth expre 'sp-backward-sexp'. If ARG is forward as returned by 'sp-forw	negative -N, unwrap Nth expression	
mode active		This command works fine in Erlang for the following code examples:	, ,	After <m− £7=""> W:</m−>	
		ood oxampios.		Again <b>After <m-f7> W</m-f7></b> : <b>AList</b> = (1,  2, 3, 4).	
				Again After <m-f7> W: AList = 1,  2, 3, 4.</m-f7>	
			Before: AList = [0, 1, [2, 3,	After <m-f7> W: List = [0, 1, 2,  3, 4, 5].</m-f7>	
		Before: AList = [1, 2, [3, 4	and the second s	After <m-f7> W: AList = [1, 2, [3, 4], 5, 6, 7, 8].</m-f7>	
		Before: AList = [1, 2, [3, 4		After M-2 <m-f7> W: AList = [1, 2, 3, 4, 5, [6, 7],  8].</m-f7>	
Split & Join					
Split block  •  \( \sum \mathcal{X} \) Smartparens  with smartparens- mode active	<m-f7>  </m-f7>	(sp-split-sexp ARG)	with delimiters of the current	blit all the sexps in current expression in separate lists enclosed expression.	
· A im		Before: AList = [1, 2, [3, 4		After <m-f7>  : AList = [1, 2, [3, 4,]   [5, 6, 7], 8]. %</m-f7>	
		Before: Name = "Joe   Armstro		After <m-f7>  : Name = "Joe "   "Armstrong".</m-f7>	
		Before: AList = [1, 2, [3, 4		After C-u <m-f7>  : AList = [1, 2, [3], [4], [5], [6], [7], 8].</m-f7>	
Join blocks  • ∑X Smartparens  with smartparens- mode active	<m-f7> J</m-f7>	(sp-join-sexp &optional ARG)	<ul><li>If ARG is positive N, join N e.</li><li>If ARG is negative -N, join N</li></ul>	r point if they are of the same type.  xpressions after the point with the one before the point.  expressions before the point with the one after the point.  in all the terms up until the end of current expression.  expression of different type.	
		Before: AList = [0, 1, [2, 3		After <m-f7> J: AList = [0, 1, [2, 3, 4 , 5, 6], 7].</m-f7>	
			2, 3, 4], [5, 6], 7].	After M-2 <m-f7> J: AList = [[0, 1 , 2, 3, 4, 5, 6], 7].</m-f7>	
Search Support				g superword-mode helps searching.  11> t <f2> to access the customize buffer.</f2>	
Toggle superword- mode	<f12> M-p  • <f11> t m p</f11></f12>	(superword-mode &optional ARG)	treated as part of words.  • With a prefix argument ARG,	or mode that treats <u>snake_case</u> as one word. In Erlang, '_' are enable superword mode if ARG is positive, and disable it	
See also:  • <u>&gt; Text Modes</u> • <u>&gt; Search/Replace</u>	• <f11> SPC e M-p</f11>		otherwise. • PEL provides the <f12> M- is popular (Emacs Lisp, C, C</f12>	-p key for the programming language modes where snake case ++, Erlang, Python, etc)	
Marking		pecific marking functions are available. They complement what is already available and described in the <b>Marking</b> table.  Erlang.el man page indicates an invalid mapping for this. Reported as ERL-1314.			
Mark Erlang function	• C-M-h • <f12> f m</f12>	(mark-defun &optional ARG) (erlang-mark-function &optional ARG)	With positive ARG, mark this direction of marking.	n, point at beginning. ne that contains point or follows point. and that many next functions; with negative ARG, change the the next or previous function(s) after the one(s) already marked.	
Mark Erlang Clause	• C-c M-h • <f12> c m</f12>	(erlang-mark-clause)	Put mark at end of clause, poin	it at beginning.	
iEdit mode See also: ∑ Highlight	iEdit Mode - Edit multiple ins  Requires the iedit external		· · · · · · · · · · · · · · · · · · ·	e is very useful to rename symbols or variable during refactoring.	
Toggle iedit mode	• C-;	(iedit-mode &optional	-	abols in scope or region simultaneously.	
See also:  • <u>&gt; Cursor</u> • <u>&gt; Search/Replace</u>	• <f11> e • <f11> h i • <f11> m i</f11></f11></f11>	ARG)	PEL detects and reports to	the C-; key as their default binding.  hat situation: modify the binding of one of them if you see it.  ere all the iedit-mode commands are described.	
Highlighting blocks	show-paren-mode, which h	n be used to activate or toggle useful modes to highlight blocks of (), {}, and []. highlights the parens that matches the one before or after point. where matching nested parens are highlighted with the same colour.			
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching  With a prefix argument ARG,		
See also: <u>N Highlight</u>	• <f11> h ( • <f11> SPC e M-9</f11></f11>			al minor mode. When enabled, any matching parenthesis is tyle' after 'show-paren-delay' seconds of Emacs idle time.	
Enable/Disable coloured highlight of nested blocks (),{},[]	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters- mode &optional ARG)	depth.	orackets, and braces with different colours according to their	
See also: N Highlight	• <f11> h R • <f11> SPC e M-r</f11></f11>		Requires: rainbow-delimite		
Inserting code with	Specialized Tempo Skel	etons	!		
Insert Parentheses	M-(	(insert-parentheses &optional ARG)	A positive ARG encloses the     A negative ARG encloses the     No argument is equivalent to     PEL makes 'parens-require-sallowing the use of this commutation without placing a space between	pair '()', leaving point after open-paren. following ARG sexps in parenthesis if they are balanced. e preceding ARG sexps instead. e zero: just insert '()' and leave point between. spaces' buffer local and set it to nil in Erlang mode buffers, mand to insert the argument parentheses following a function (and ween the function name and the opening parenthesis.	
				osing characters at region boundaries. nt is not in a string or comment.	

<u>Description</u>		<u>Keystroke</u>	Function	Note
Insert Erlang Cod	de			tons using the standard tempo skeleton package. the Erlang/Skeletons menu (via <f10>).</f10>
Templates		PEL provides the following a	additional functionality:	
See also:	<b>~</b>			ed under the pel:erlang-skel key prefix: <f12> <f12>.  h a +. These are also added to the menu.</f12></f12>
Inserting Text for more info and  more in	or			Style is controlled by the user options inside the <b>pel-erlang-code-style</b> group. The controlled
information about tempo skeleton and	d		arked with a <b>C</b> . The relevant nclude the following options	t user options are part of the <b>pel-erlang-code-style</b> group accessible with <f12> <f2> from an ::</f2></f12>
the completely different yasnippet		<ul><li>pel-erlang-skel-inser</li><li>pel-erlang-skel-prom</li></ul>		: set whether an automatically updated timestamp is inserted in the file header block. : set whether file and function skeletons blocks prompt for purpose and insert it.
template-based tex insertion).	ct	pel-erlang-skel-prom	pt-for-function-name	: set whether function skeletons prompt for function name and then inserts that name.  s : set whether function skeletons prompt for function arguments and then insert them.
insertion).		pel-erlang-use-separ	rators	: set whether blocks use horizontal separator lines (these are the first of potentially 2 separator
		<ul><li>pel-erlang-use-secor</li><li>pel-erlang-skel-with-</li></ul>		: set whether blocks use a second block horizontal separator line. : set whether generated code comments use EDoc markup.
		• pel-erlang-skel-with-	license	: set whether file header blocks use open source software license text controlled by dice.
				But by using file and directory variables (see <u>File/Directory Variables</u> ) they can also be use bry tree. So by default, the user options that control the PEL tempo template take effect globally
		If you want to change the	behaviour for only one file, v	write the user option control block at the end of that file. If you want to control the behaviour of tree create a .dir-locals file and store the values of the relevant options variables inside that file.
		This allows you to control	the user options affecting th	ne format of the tempo templates precisely and does not affect what you actually type.
		marks) with the standard	tempo-mode keys C-c M-	ng the pel-tempo-mode) you can move to the next or previous point of interest (so called <i>tempo</i> -f and C-c M-b or some other keys like C-c . and C-c ,.
				an also type the template name and then hit <b>C-c C-M-i</b> or <b><f12></f12> <f12></f12> <f12></f12></b> . This orary buffer. This is mainly useful for templates which short names such as "if", "case", etc
I . additional tomorbat				
<ul><li>: additional templat</li><li>: templates with</li></ul>		_ ·		so links to the relevant Erlang language construct reference page. e in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity</f11>
customization control			(	Outtoning DEL Edward skylder knowl
∑ Customize PEL Erl Skeletons layout	ang	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-pel &optional OTHER-	Customize PEL Erlang skeleton layout.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in another window.
£		45105 45105 4	WINDOW)	league on if statement
<u>f</u>		<f12> <f12> i</f12></f12>	(pel-erl-if)	Insert a rif statement.
<u>case</u>		<f12> <f12> c</f12></f12>	(pel-erl-case)	Insert a case expression.
export +	•	<f12> <f12> x</f12></f12>	(pel-erl-export	Insert an export module attribute expression.
mport +	-	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.
ry +	-	<f12> <f12> t</f12></f12>	(pel-erl-try)	Insert a try expression.
<u>ry-of</u> +	-	<f12> <f12> T</f12></f12>	(pel-erl-try-of)	Insert a try expression with of clauses.
receive		<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.
<u>ifter</u>		<f12> <f12> a</f12></f12>	(pel-erl-after)	Insert a receive expression with an after (timeout) clause.
oop		<f12> <f12> 1</f12></f12>	(pel-erl-loop)	Insert a simple receive loop.
<u>nodule</u>		<f12> <f12> m</f12></f12>	(pel-erl-module)	Insert the module attribute.
<u>function</u>	С	<f12> <f12> f</f12></f12>	(pel-erl-function)	Insert a function definition. This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.
author		<f12> <f12> `</f12></f12>	(pel-erl-author)	Insert the author attribute. Uses the <b>user-mail-address</b> user option to insert your mail address
spec		<f12> <f12> s</f12></f12>	(pel-erl-spec)	Insert a <b>-spec</b> for the function following point.
small-header	С	<f12> <f12> M-h</f12></f12>	(pel-erl-small-header)	Insert a small file header without any comment.
normal-header	С	<f12> <f12> M-H</f12></f12>	(pel-erl-normal-header)	Insert a normal file header: includes author name, copyright notice, doc section, file created da
large-header	С	<f12> <f12> h</f12></f12>	(pel-erl-large-header)	Insert a large header block that includes all normal header fields plus separators.  • All formatting is controlled by user-options described above.
				Air formatting is controlled by diser-options described above.     Distinguish Erlang .erl module files from the .hrl header files.
small-server	С	<f12> <f12> M-s</f12></f12>	(pel-erl-small-server)	Insert a large file header and template logic for a small server.
application	С	<f12> <f12> M-a</f12></f12>	(pel-erl-application)	Insert a large file header and template logic for an application behaviour.
supervisor	С	<f12> <f12> M-u</f12></f12>	(pel-erl-supervisor)	Insert a large file header and template logic for a supervisor behaviour.
supervisor-bridge	С	<f12> <f12> M-b</f12></f12>	(pel-erl-supervisor- bridge)	Insert a large file header and template logic for a supervisor bridge behaviour.
generic-server	С	<f12> <f12> M-g</f12></f12>	(pel-erl-generic-server)	Insert a large file header and template logic for a <b>gen-server behaviour</b> .
gen-event	С	<f12> <f12> M-g</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a gen-event behaviour.
gen-fsm	С	<f12> <f12> M-f</f12></f12>	(pel-erl-gen-fsm)	Insert a large file header and template logic for a gen-fsm behaviour.
gen-statem-StateNa		<f12> <f12> M-S</f12></f12>	(pel-erl-gen-statem-	Insert a large file header and template logic for a gen-statem behaviour.
	С		StateName)	
gen-statem-handle- event	С	<f12> <f12> M-E</f12></f12>	(pel-erl-gen-statem- handle-event)	Insert a large file header and template logic for a gen-statem.
wx-object	С	<f12> <f12> M-w</f12></f12>	(pel-erl-wx-object)	Insert a large file header and template logic for a wx-object generic server.
gen-lib	С	<f12> <f12> M-1</f12></f12>	(pel-erl-gen-lib)	Insert a large file header and template logic for a library module.
gen-corba-cb	С	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a <b>CORBA</b> callback module.
ct-test-suite-s		<f12> <f12> M-1</f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite
ct-test-suite-l		<f12> <f12> M-2</f12></f12>	f12> <f12> M-2 (pel-erl-ct-test-suite-l) Insert a large file header and template logic for a test suite</f12>	
s-test-suite		<f12> <f12> M-3</f12></f12>	(pel-erl-ts-test-suite)	Insert a large file header and template logic for a test suite
Tempo Template Tag	ı	• C-c C-M-i	(tempo-complete-tag	Look for a tag and expand it.
Insertion		• <f12> <f12> <f12></f12></f12></f12>	&optional SILENT)	Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit C-c C-M-:</f12></f12>
		• <f11> SPC e <f12> <f12></f12></f12></f11>		(or <f12> <f12> <f12>) A completion buffer opens up if the template name is incomplete</f12></f12></f12>
				(or empty in which case the buffer lists <b>all</b> available template names). Select the template name and hit RET. Emacs expands the template.
				Ludes 'tempo-tags') are searched for a match for the text before the point. The way the string to
		match for is determined car match at all.	n be altered with the variable	e 'tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no
				s expanded in place of the matching string. SILENT is non-nil, the function will give a signal.
				letion-buffer' is non-nil, a buffer containing possible completions is displayed.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Toggle pel-tempo-mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as C-	
See also:  • <u>Namerting Text</u>	• <f11> SPC e <f12> SPC • <f6> SPC</f6></f12></f11>	&optional ARG)	c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When peltempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode.  When a skeleton is inserted via the execution of one of the pel-erl commands above, the pel-tempo-mode is automatically activated.	
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key key bindings are only available when pel-tempo-mode is active.	
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward- mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton.  • These key binding are only available when pel-tempo-mode is active.	
Specialized Kill See also:  • ∑ Cut & Paste  • ∑ X Smartparens	Activate smartparens mode     This table uses the ☒ and ☒ := "forward delete" := ∑ := "backward delete":     □    □    □    □    □    □    □	manually with <f11> ( ( Symbols to represent the <deletechar> := Fn &lt; = <backspace> Often lab</backspace></deletechar></f11>		
kill block elements	The following commands kill the	ne element(s) of a block.		
Kill content of next block	• <m-f7> ⊠ • <m-f7> - n</m-f7></m-f7>	(sp-change-inner)	Change the content of current or next block. Point can be anywhere in block or element before block.	
• <u>∑</u> x Smartparens			<pre>Before:</pre>	
Delete content of current block  ■ ∑X Smartparens	<m-f7></m-f7>	(sp-change-enclosing)	Delete content of the enclosing block. Point can be anywhere inside the current block. <b>Before:</b> {'EXIT', Reason} -> {error, { asn1, Reason}};  {error, { }};	
Kill block elements forward	<m-f7> - ]</m-f7>	(sp-kill-sexp &optional ARG DONT-KILL)	<pre>Kill block elements after point.  Before: case Tlv9 of    [] -&gt; true;&gt; exit({error,   {asn1, {unexpected, Tlv9}}})  After:</pre>	
			<pre>case Tlv9 of [] -&gt; true;&gt; exit({error, })</pre>	
Kill block elements backward	<m-f7> - [</m-f7>	(sp-backward-kill-sexp &optional ARG DONT- KILL)	<pre>Kill block elements before point.  Before:     case Tlv9 of       [] -&gt; true;&gt; exit({error,   {asn1, {unexpected, Tlv9}}})  After:</pre>	
Man I i i			<pre>case Tlv9 of [[] -&gt; true;&gt; exit({ {asn1, {unexpected, Tlv9}}})</pre>	
Kill element after current	<m-f7> - }</m-f7>	( <b>sp-kill-hybrid-sexp</b> ARG)	Kill a line as if with 'kill-line', but respecting delimiters.	
• <u>∑</u> x Smartparens		<ul> <li>With ARG being raw prefix C-u, kill the hybrid sexp the point is in (see 'sp-get-hybrid-sexp').</li> <li>With ARG numeric prefix 0 (zero) just call 'kill-line'.</li> <li>You can customize the behaviour of this command by toggling 'sp-hybrid-kill-excessive-whitespace'.</li> </ul>		
Kill whole line	<m-f7> - 1</m-f7>	(sp-kill-whole-line)	▲ Currently this deletes the whole line. Requires Erlang specific implementation.	
Kill/splice				
Un-wrap current block, splicing its elements in enclosing block	<m-f7> 1 1</m-f7>	(sp-splice-sexp &optional ARG)	Un-wrap current block, splicing its content in enclosing block (if any).  Before: { EncBytes,EncLen} = 'enc'(Cdx, []),  EncBytes,EncLen = 'enc'(Cdx, []),  EncBytes,EncCen = 'enc'(Cdx, []),  E	
• <u>∑</u> X Smartparens			<pre>Before: -asn1_info( [{vsn, '2.0.1'},</pre>	
Kill block element(s) before point and splice remaining into outer block	<m-f7> 1 [</m-f7>	(sp-splice-sexp-killing- backward &optional ARG)	Kill elements before point in block and splice remaining elements into outer block.  Before: case Tlv9 of [] -> true; -> exit({error,{asn1, {unexpected,  Tlv9}}})	
• <u>∑</u> x Smartparens			After: <pre>case Tlv9 of   [] -&gt; true; -&gt; exit({error,{asn1,  Tlv9}})</pre>	
Kill block element(s) forward and splice remaining into outer block	<m-f7> 1 ]</m-f7>	(sp-splice-sexp-killing- forward &optional ARG)	Kill elements after point in block and splice remaining elements into outer block.  Before:  case Tlv9 of [] -> true; -> exit({error, {asn1, {unexpected,  Tlv9}}})	
∑X Smartparens			<pre>After: case Tlv9 of   [] -&gt; true; -&gt; exit({error,{asn1, unexpected }})</pre>	
Kill around element	<m-f7> 1 o</m-f7>	(sp-splice-sexp-killing- around &optional ARG)	Kill content around current element/block.	
• <u>∑</u> x Smartparens			<pre>Before: -asn1_info(   [{vsn, '2.0.1'},</pre>	
			-asn1_info( [{vsn,'2.0.1'},	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Delete/Kill region	<del>åerå</del>			
Delete region	<m-f7> DEL -</m-f7>	(sp-delete-region BEG END)	Delete the text between point and mark, like 'delete-region'.  BEG and END are the bounds of region to be deleted.  If that text is unbalanced, signal an error instead.  With a prefix argument, skip the balance check.	
Kill region	<m-f7></m-f7>	(sp-kill-region BEG END)	Kill the text between point and mark, like 'kill-region'.  • BEG and END are the bounds of region to be killed.  • If that text is unbalanced, signal an error instead.  • With a prefix argument, skip the balance check.	
	<m-f7> - r</m-f7>	(spkill-or-copy-region BEG END &optional DONT-KILL)	Kill or copy region between BEG and END according to DONT-KILL.  If 'evil-mode' is active, copying a region will also add it to the 0 register.  Additionally, if command was prefixed with a register, copy the region to that register	
Delete char forward	<m-f7> DEL n</m-f7>	( <b>sp-delete-char</b> &optional ARG)	(quu x "zot") -> (quu  "zot") (quux  "zot") -> (quux " zot") -> (quux " ot") (foo ( ) bar) -> (foo   bar) (foo bar) -> ( foo bar)	
Delete char backward	<m-f7> DEL p</m-f7>	(sp-backward-delete- char &optional ARG)	("zot" q uux) -> ("zot"  uux)  ("zot"  quux) -> ("zot " quux) -> ("zo " quux)  (foo ( ) bar) -> (foo   bar)  (foo bar) -> (foo bar )	
Delete/Kill word	ini ini			
Delete word backward	<m-f7> DEL V</m-f7>	(sp-backward-delete- word &optional ARG)	<ul> <li>(sp-backward-delete-word &amp;optional ARG)</li> <li>Delete a word backward, skipping over intervening delimiters.</li> <li>Deleted word does not go to the clipboard or kill ring.</li> <li>With ARG being positive number N, repeat that many times.</li> <li>With ARG being Negative number -N, repeat that many times in backward direction.</li> </ul>	
Delete word forward	<m-f7> DEL W</m-f7>	(sp-delete-word &optional ARG)	Delete a word forward, skipping over intervening delimiters.  Deleted word does not go to the clipboard or kill ring.  With ARG being positive number N, repeat that many times.  With ARG being Negative number -N, repeat that many times in backward direction.	
Kill word backward	<m-f7> - v</m-f7>	( <b>sp-backward-kill-word</b> &optional ARG)	<ul> <li>Kill a word backward, skipping over intervening delimiters.</li> <li>With ARG being positive number N, repeat that many times.</li> <li>With ARG being Negative number -N, repeat that many times in backward direction.</li> </ul>	
Kill word forward	<m-f7> - w</m-f7>	( <b>sp-kill-word</b> &optional ARG)	<ul> <li>Kill a word forward, skipping over intervening delimiters.</li> <li>With ARG being positive number N, repeat that many times.</li> <li>With ARG being Negative number -N, repeat that many times in backward direction.</li> </ul>	
Delete/Kill symbol	See 'sp-backward-symbol' a	ckward-symbol' and 'sp-forward-symbol' for what constitutes a symbol for the backward and forward commands respectively.		
Delete symbol backward	<m-f7> DEL a</m-f7>	(sp-backward-delete- symbol &optional ARG WORD)	Delete a symbol backward, skipping over any intervening delimiters.  Deleted symbol does not go to the clipboard or kill ring.  With ARG being positive number N, repeat that many times.  With ARG being Negative number -N, repeat that many times in forward direction.	
Delete symbol forward	<m-f7> DEL S</m-f7>	(sp-delete-symbol &optional ARG WORD)	Delete a symbol forward, skipping over any intervening delimiters.  Deleted symbol does not go to the clipboard or kill ring.  With ARG being positive number N, repeat that many times.  With ARG being Negative number -N, repeat that many times in backward direction.	
Kill symbol backward	<m-f7> - a</m-f7>	(sp-backward-kill- symbol &optional ARG WORD)	<ul> <li>Kill a symbol backward, skipping over any intervening delimiters.</li> <li>With ARG being positive number N, repeat that many times.</li> <li>With ARG being Negative number -N, repeat that many times in forward direction.</li> </ul>	
Kill symbol forward	<m-f7> - s</m-f7>	( <b>sp-kill-symbol</b> &optional ARG WORD)	Kill a symbol forward, skipping over any intervening delimiters.  • With ARG being positive number N, repeat that many times.  • With ARG being Negative number -N, repeat that many times in backward direction.	
Erlang syntax checking	<ul><li>To activate either set the</li><li>By default, the syntax che</li></ul>	pel-use-erlang-syntax-che ecker is not automatically la	e can be done with Emacs built-in <u>flymake</u> as well as with the external package <u>flycheck</u> .  Eck user option is set to either 'use-flycheck or 'use-flymake.  Unched. If you want to start your selected syntax checker as soon as any Erlang file is opened,	
Using either: • flycheck or • flymake	<ul> <li>add 'erlang-mode to the pel-modes-activating-syntax-check user-option.</li> <li>flymake is built-in Emacs. The Emacs erlang package provides erlang-flymake to use with Erlang.</li> <li>in PEL automatically installs and activates flycheck when pel-use-goflymake user option is set to 'use-flycheck.</li> <li>Elymake has several customizable variables, which some listed here:</li> </ul>			
See also:  • <u>▼ SyntaxCheck</u>	The following customization variables determine the exact circumstances whereupon Flymake decides to initiate a check of the buffer:  • flymake-start-on-flymake-mode: t to start checking when flymake-mode is started. nil to prevent check.  • flymake-no-changes-timeout: time to wait after last change to start checking. Default = 0.5 seconds.  • flymake-start-syntax-check-on-newline: t to check after insertion or removal of newline char from buffer. nil to prevent check.  The following variable control navigation to next or previous error:			
	flymake-wrap-around : If n     flymake-diagnostic-types-	rol navigation to next or previous error:  If non-nil, moving to errors wraps around buffer boundaries.  es-alist: Alist ((KEY . PROPS)*) of properties of Flymake diagnostic types. See Emacs documentation for more info.  mapped to flymake commands only when flymake-mode is turned on.		
Activate/deactivate	<f12> !</f12>	(pel-erlang-toggle-	Toggle the selected Erlang syntax checker mode on/off.  The syntax checker activated or deactivated is either flycheck or flymake, as selected by the	
selected syntax checker	<f11> SPC e !</f11>	syntax-checker)	<ul> <li>The syntax checker activated or deactivated is either <u>flycheck</u> or <u>flymake</u>, as selected by the user-option variable <u>pel-use-erlang-syntax-check</u>.</li> <li>See the required settings above to activate this command and select the syntax checker.</li> </ul>	
Go to next flymake diagnostic	M-n	(flymake-goto-next- error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.	
Go to previous flymake diagnostic	м-р	(flymake-goto-prev- error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic.  • With a prefix arg, skip any diagnostics with a severity less than ':warning'.  • Display the error message in the echo line.	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Compiling Erlang Code		ned to compile the files. The	ce code files to .beam files located in the same directory as the source code. Detected errors are e buffer shows the location of error and the error description. The following commands are used	
Compile code	• C-c C-k • <f12> M-c • <m-f12> M-c</m-f12></f12>	(erlang-compile)	Compile Erlang module in current buffer.  If buffer visiting file was modified and not saved, prompts the user to save it first.  Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command.  The buffer lists the errors. Hitting RET on the error file/line move point to that line in the Erlang file buffer. The RET key is bound to (compile-goto-error &optional EVENT)  It's also possible to use the next-error and previous error.	
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output.  • Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.	
Move to next compile error	• C-x ` • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; • negative means move back to previous error messages. • Just C-u as a prefix means reparse the error message buffer and start at the first error.  This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.	
Move to previous compile error	• M-g p • M-g M-p	(previous-error &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative).  This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.	
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.	
Move to previous compilation or Flycheck detected error	С-с С-р	(edts-code-previous- issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error.  When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.	
<b>Development Tool</b>	The following commands are u	used when adding Emacs Li	sp support for Erlang.	
Show syntactic information	C-c C-s	(erlang-show-syntactic-information)	Show syntactic information for current line.  • Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.	
Erlang Shell	Commands to explicitly launch comint.el library running in erla		that runs under an Emacs inferior-erlang process controlled by the comint mode from the	
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.	
Start new Erlang Shell	<f11> z r e <f12> z</f12></f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer.  • The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started.  • C-c C-z starts the Erlang Shell from the Erlang Mode.  • <f11> z r is available globally and will work as long as the erl executable is accessible.  Under PEL this command is available only when the pel-use-erlang user option is set to t.</f11>	
Work around to issues in the Erlang Shell	When running the Erlang Shell inside Emacs, you may run into some issues. They are listed here along with work-arounds.  • Redundant command echo:  On some systems the Erlang shell annoyingly echoes each typed command. If this is the case for your system, PEL provides a fix:  ② Set the pel-erlang-shell-prevent-echo user option to t. After doing that execute pel-init or restart Emacs.  • Typing Ctrl-G does not open the Erlang JCL Command Menu: work-around: type the following instead: C-q C-g RET  ① Unfortunately the above workaround does not work when the Erlang shell is launched inside an Emacs vterm shell (see ∑ Shells).			
Erlang Shell: Command History	The following commands can be used to retrieve previously issued Erlang shell commands at the shell prompt.  Erlang shell command history file:  The Erlang shell history controlled by Emacs is saved inside a file the is restored when opening a new shell: commands from previously opened Erlang shells are also available.  Within an Emacs inferior-erlang the  You can also use the Erlang shell commands to access the local shell history.			
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.	
Previous shell command	м-р	(comint-previous-input ARG)	Cycle backwards through Erlang shell input history, saving input.	

Description	<u>Keystroke</u>	Function	<u>Note</u>
Using Man inside	Emacs provide 2 main comma		
Emacs and	Both of these are much more powerful than the usual man reader available on the shell allowing navigation across man pages and opening hyperlinks.  They are:		
support Erlang Man pages	<ul><li>The man command uses</li><li>WoMan: Browse Unix Ma</li></ul>		Man" a complete implementation. It has some formatting limitations compared to man but it's a Windows.
See also: <u>Nelp/Info</u>	To see Erlang man pages using the man command:  On most systems the Man pages for Erlang are not available to the man utility and therefore not available for man inside Emacs. There are several ways this can be remedied:  One is to set the MANPATH environment variable to include the directory where these files are located. Then man can be used outside and inside Emacs to access Erlang's man pages. For example the following lines can be stored inside a shell script to do this:  MANPATH=/usr/local/Cellar/erlang/22.3.4/lib/erlang/man:`manpath` export MANPATH		
	<ul> <li>Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add of Emacs man to fin the Erlang's man pages without modifying the capabilities of the parent shell. For example, if we want to use the sal as the above example we need to set the Man-switches which is normally set to nil to the following value:         <ul> <li>"-M'manpath':/usr/local/Cellar/erlang/22.3.4/lib/erlang/man"</li> </ul> </li> </ul>		
	shells that have their own access to the man pages of MANPATH and therefore p	value of MANPATH. That mof different versions of Erlan	stories for the man pages of other programming languages while leaving the ability to have several light be very useful for someone that uses different versions of Erlang in a system and needs g. It becomes possible to run different shells inside Emacs with each having its own value of m different locations. It is also possible to place all of these directories inside the Man-switches or ges for the same topic.
	To only see Erlang topics in Man completion: When learning Erlang it might help to see only Erlang topics when using the man command completion. To do that, set MANPATH to the Erlang directory only. You must also ensure that a whatis file is located in the Erlang man page root directory, otherwise Emacs man completion will not See my description on how to create whatis file for local man directory.		
	EDTS (see below) support	s the ability to download and cess sections inside the man	f Erlang used by various projects: d access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides it's ne pages, allowing EDTS driven man page access to co-exist with manual man command
About Erlang	PEL supports multiple versions of Erlang and access to their man pages Inside the pel-erlang-environment group, the pel-erlang-man-parent-rootdir user-option can be set to read the man parent directory name from an environment variable. To support the ability to open the man files related to a specific version of Erlang available to the parent OS shell, set the environment variable when you select the version of Erlang available to the OS shell and set the name of the environment variable in the pel-erlang-man-parent-rootdir user-option. See the following Installing Erlang pages of the About Erlang document that describes an setting such an editing		
	environment:  • Install Erlang OTP Documentation and Man Files  • Creating whatis files for Erlang man pages  • Using the Erlang Man files within Emacs  • Using Specialized OS Shells for Erlang  • Using PEL with Specialized Shells for Erlang to Edit Erlang		
See also: <u>▼ Menus</u>	Use the following commands to You can also use the toolba		e inside Emacs. th <f10>) in the Erlang section.</f10>
Open a man page inside an Emacs buffer See also:	• <f11> ? m • %-M</f11>	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because:  • the links are active and can be followed. When the man page describes a directory or file, emacs will open the file or the directory (in direct mode) when pressing RET over the link.  • You can navigate easily between sections (n/p will move to the next/previous section)
• <u>S Help/Info</u> • <u>S Customize</u>			<ul> <li>You can use any of the searches.</li> <li>You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer.</li> <li>See all keys available in mode, with <f1> m or <f11> ? k m.</f11></f1></li> <li>The man command prompts, using the word at point as the default.</li> <li>PEL key sequence to customize man: <f11> <f2> E m</f2></f11></li> </ul>
Open a man page without external man process: woman See also:  > Nelp/Info  > Customize	<f11> ? w</f11>	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows).  PEL key sequence to customize man: <f11> <f2> E w  text width, use word at point, etc</f2></f11>
EDTS	EDTS - Erlang Developr	nent Tool Suite	
	EDTS - Erlang Development Tool Suite  The commands in the following rows require the EDTS external package. PEL activates it when the pel-use-edts user option is set to t. If you want EDTS to start automatically when you open an Erlang file, set pel-use-edts to start-automatically instead of t.		
Erlang Project settings	EDTS is customizable through it <b>edts</b> customization group. With PEL you can open it, with other Erlang specific groups with <b><f12> <f3></f3></f12></b> .  EDTS also uses an external <b>.edts</b> configuration file to store Erlang project specific settings. See <b>EDTS: Configure your projects.</b> This allows setting the following: project name, node-name, erlang-cookie, lib-dirs, start-command, top-path, dialyzer-plt, app-include-dirs, project-include-dirs, xref-error-whitelist, xref-file-whitelist		
See also: <u>Sessions</u>	<ul> <li>⚠ Desktop restoration often fails when edts-mode was active on session stored: unfortunately edts does not provide a desktop restore handler.</li> <li>☑ PEL does, however provide a desktop restore handler for EDTS which detects edts-mode failures and protect the desktop restoration.</li> <li>If EDTS has not been activated yet, the only EDTS specific key available is <f12> M-SPC to activate it. Once it's activated the other keys are available.</f12></li> </ul>		
Toggle EDTS mode	<f12> M-SPC</f12>	(edts-mode &optional	Turn EDTS mode on or off.
	<f11> SPC e M-SPC</f11>	ARG)	<ul> <li>EDTS is an easy to set up Development-environment for Erlang.</li> <li>EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further.</li> </ul>
EDTS/Navigation	EDTS (see below) provides 2 commands to move point across Erlang functions: ferl-goto-previous-function and ferl-goto-next-function. They are listed above in the navigation section. The EDTS navigation functions do not support repetition prefix argument nor they support shift marking. There are other commands and key bindings to move across Erlang functions, and PEL support functions that perform the same and support repetition and shift marking. See the commands listed in the navigation section above.		
EDTS/Cross References	EDTS provides the following cross-reference commands. It supports navigating in Erlang source code running in the current and remote nodes.  Provides the following cross-reference commands. It supports navigating in Erlang source code running in the current and remote nodes.  Provides the following cross-reference commands. It supports navigating in Erlang source code running in the current and remote nodes.  Provides the following cross-reference commands. It supports navigating in Erlang source code running in the current and remote nodes.		
Find definition of identifier at point	M	(edts-find-source- under-point)	Goto the source code that: defines the function being called at point or header file included at point. For remote calls, contacts an Erlang node to determine which file to look in, with the following algorithm:  • Find the directory of the module's beam file (loading it if necessary).  • Look for the source file in:  • Directory where source file was originally compiled.  • Todo: Same directory as the beam file  • Todo: Again with /ebin/ replaced with /src/  • Todo: Again with /ebin/ replaced with /erl/ Otherwise, report that the file can't be found.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Go back to where M was last issued	М-,	(edts-find-source- unwind)	Unwind back from uses of 'edts-navigate'-commands.	
Lists caller of function at point	• C-c C-d w • <f12> w</f12>	(edts-xref-who-calls)	Pops-up a menu of all callers of the function at point.	
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who-calls)	Redo previous call to edts-who-calls.	
Find a function in the current module	• C-c C-d f • <m-f12> M-f</m-f12>	(edts-find-local- function SET-MARK)	Find a function in the current module.  List local functions in the mini-buffer. Support completion. Move point to selected one.  With C-u prefix, push mark before moving point.	
Find a module in the current project	• C-c C-d F • <m-f12> M-g</m-f12>	(edts-find-global- function)	Find a module in the current project.  • List project modules in the mini-buffer. Support completion. Open the file of selected one.	
EDTS/AHS Editing	in all of the buffer. The automa	atic symbol highlighting mod lts to 1.0 second.	S). and provides commands to modify the name of the highlighted name in the current function or de starts when the cursors stays on a symbol for a period longer than the value identified by the nove point away from the highlighted area.	
Edit all highlighted symbols in current function	• C-c C-d e • <f12> e</f12>	(edts-ahs-edit-current- function)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current function.  • Activates ahs-edit-mode with edts-current-function range-plugin.	
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer.  • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.	
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.	
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.	
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.	
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	Refactor the expression(s) in the region as a function.  The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original function.  New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring.  This command requires Erlang syntax tools package to be available in the node, version 1.2 (or perhaps later.)	
EDTS/Man	pages per project, so it is poss	EDTS supports opening documentation for a specific function using the information extracted from Erlang Man pages. EDTS maintains a set of Erlang man pages per project, so it is possible to have several Erlang projects each one with a different version of Erlang and their corresponding man pages.  These EDTS commands complement the Emacs standard man commands described above in this table.		
Download, install, select Erlang Man pages	<f12> `</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands.	
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip.	
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function. Find and show the man-page documentation for the Erlang module:function.	
EDTS Code Analysis				
Compile current buffer	<f12> a c</f12>	(edts-code-compile- and-display)	Compiles current buffer on node related to that buffer's project.	
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION-RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.	
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.	
EDTS/Debug				
Toggle breakpoint	• C-c C-d b • <f12> d b</f12>	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.	
List breakpoints	C-c C-d M-b • <f12> d B</f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle- interpreted)	Toggle the interpretation state for module in current buffer.	
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
EDTS/Erlang Node				
Display EDTS Erlang Node Name	<f12> N</f12>	(edts-buffer-node- name)	Print the node sname of the erlang node connected to current buffer.  • The node is either:  • The module's project node, if current buffer is an erlang module, or  • The buffer's erlang node if buffer is an edts-shell buffer.  • The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module such as an otp-module or a module loaded by ~/.erlang).	
Start an EDTS controlled Erlang Shell	<f12> x</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell.	
Start EDTS server	<f12> X</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).	

	<u>Keystroke</u>	Function	<u>Note</u>
LSP support:	LSP (language Server Protoc		
• <u>Isp-mode</u> • <u>erlang Is</u>	The <u>erlang Is</u> Erlang server  The <u>erlang Is</u> can be	for LSP. You must install the configured using a YAML fi	L activates it when the <b>pel-use-erlang-Is</b> user-option is turned on (set to t).  is manually. You will need Git, Erlang, rebar3 and make. The instructions are on the web-site.  le <b>erlang Is.config</b> file that must be placed at the root of the Erlang project.
erlang Is required environment	It's important for most projects to set that up, otherwise you may not be able to take advantage of several of the cross-reference features  The following executable must be accessible from PATH:  • erl. escript and other Erlang executables. See Installing Erlang if you need to learn how to install Erlang and its tools.  • erlang_ls. To install erlang_ls follow the instruction on the erlang_ls GitHub page: git clone it, then run make and make install.		
	and the various <u>Tools for</u>		n tne <u>enang is GitHuo page</u> : git clone it, tnen run make and make instali.
• <u><b>© Customize</b></u> Isp-mode	settings are probably what you  Isp-log-io Isp-ui-sideline-enable Isp-ui-doc-enable	u may want to customize: control whether the LSP pi control whether LSP displa control whether LSP displa	p-mode customization group. With PEL you can access it via <f12> L <f3>. The following rocess is logging its I/O. Useful for debugging LSP support. By information about the current code line. By documentation about the current code symbol. By a documentation about the current code symbol. By Information about the current code symbol. By Infor</f3></f12>
Toggle code documentation display	<f11> SCP e L D <f12> L D</f12></f11>	(pel-toggle-lsp-ui-doc &optional LOCALLY)	Toggle the display of code documentation.  The initial state is set by the 'lsp-ui-doc-enable' user-option.  By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Toggle LSP I/O logging	<f11> SCP e L I <f12> L I</f12></f11>	(pel-toggle-lsp-log-io &optional LOCALLY)	Toggle the logging of LSP I/O.  The initial state is set by the 'Isp-log-io' user-option.  By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Toggle display of information on current line	<f11> SCP e L L <f12> L L</f12></f11>	(pel-toggle-Isp-ui- sideline &optional LOCALLY)	Toggle the display of information of the current line. The initial state is set by the 'lsp-ui-sideline-enable' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.
Erlang LS Features	Overview of the features provide  Code completion  Go to Definition  Go to Implementation of OTP Behaviours  Signature Suggestions  Diagnostics on file open/save:  Compiler Diagnostics  Dialyzer Diagnostics  Elvis Diagnostics	Edoc support     Navigation to Included Files     Find/Peek References	<ul> <li>LSP Lenses: Isp-avy-lens</li> <li>LSP sideline: <ul> <li>enable with: (setq Isp-ui-sideline-enable t)</li> <li>Use M-x Isp-execute-copde-action to trigger quick-fix actions</li> </ul> </li> <li>Erlang Project-Specific LS Configuration:</li> <li>Erlang LS is customizable by using a YAML syntax file called erlang Is.config that should be placed in the root directory of the project.</li> </ul>
Isp-mode features	<ul> <li>Completion at point         <ul> <li>traditional popup with company-mode</li> <li>Code navigation, with</li> <li>lsp-find-definition</li> <li>lsp-find-references</li> <li>Symbol highlights</li> </ul> </li> <li>Code navigation is prind-references</li> <li>Symbol highlights</li> <li>Code Lenses . The Erlang LS configuration provides</li> <li>ct-run-test: display a run button next to a Common Test testcase.</li> <li>server-info: display some Erlang LS server info on top of each module. For debug only.</li> <li>show-behaviour-usages: show the number of modules implementing a behaviour.</li> </ul>		
	<u>Cymbol nighiights</u>		
Isp-mode integrations see also:  • ∑ Completion/Input  • ∑ Treemacs  • ∑ Hide/Show	Isp-mode supports integration  Helm by using helm-Isp  Vy by using Isp-ivy  Treemacs by using Isp-ori	• show-behaviour-usa with:	
see also:  • ∑ Completion/Input  • ∑ Treemacs	Isp-mode supports integration  Helm by using helm-Isp  Vy by using Isp-ivy  Treemacs by using Isp-ori  Key bindings: The Isp-mode is  Since the super modifier k with M-x customize-op  With PEL, the following k  The key bindings shown	• show-behaviour-usa with:  PEL activates PE	swhen pel-use-helm-lsp is turned on. swhen pel-use-lsp-ivy is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-origami is turned on.
see also:  • © Completion/Input  • © Treemacs  • © Hide/Show  LSP key bindings:  • Isp-mode  • erlang Is See also:  © Input Method  Display LSP workspace	Isp-mode supports integration  Helm by using helm-Isp  Vy by using Isp-ivy  Treemacs by using Isp-ori  Key bindings: The Isp-mode is  Since the super modifier k with M-x customize-op  With PEL, the following k  The key bindings shown	• show-behaviour-usa with:  PEL activates PE	swhen pel-use-helm-lsp is turned on. s when pel-use-helm-lsp is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s customizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done sf11> <f2> o key sequence. sandidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>1 key prefix.</m-f9></f9></f9></f2>
see also:  • © Completion/Input  • © Treemacs  • Display LSP workspace log buffer  Validate LSP	Isp-mode supports integration  Helm by using helm-Isp  Ivy by using Isp-ivy  Treemacs by using Isp-ori  Key bindings: The Isp-mode is  Since the super modifier key with M-x customize-op  With PEL, the following key the key bindings shown  If you change Isp-keyi	• show-behaviour-usa with:  PEL activates PE	swhen pel-use-helm-lsp is turned on. swhen pel-use-lsp-ivy is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-origami is turned on. scustomizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done cf11> <f2> o key sequence. candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.  L key prefix. can be done candidates: <f9> and c-1 when the lsp-keymap-prefix value.</f9></m-f9></f9></f9></f2>
see also:  • © Completion/Input  • © Treemacs  • Dide/Show  LSP key bindings:  • Isp-mode  • erlang Is See also:  © Input Method  Display LSP workspace log buffer	Isp-mode supports integration  • Whelm by using helm-Isp  • Very by using Isp-ivy  • Veremacs by using Isp-ori  Key bindings: The Isp-mode is  • Since the super modifier key with M-x customize-op  • With PEL, the following key the key bindings shown  • If you change Isp-key	• show-behaviour-usa with:  PEL activates PE	s when pel-use-helm-lsp is turned on.  s when pel-use-lsp-ivy is turned on.  s when pel-use-lsp-treemacs is turned on.  s when pel-use-lsp-treemacs is turned on.  s when pel-use-lsp-origami is turned on.  s customizable prefix key for its key bindings. The default key prefix is s-1.  t can be modified through customization: change the lsp-keymap-prefix value. This can be done  cf11> <f2> o key sequence.  candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.  lkey prefix.  splaced with your selected prefix key.  Display the log buffer of WORKSPACE.</m-f9></f9></f9></f2>
see also:  • © Completion/Input  • © Treemacs  • Dide/Show  LSP key bindings:  • Isp-mode  • erlang Is See also:  © Input Method  Display LSP workspace log buffer  Validate LSP performance settings  Reformat Erlang file  Add directory to the list	Isp-mode supports integration  • Whelm by using helm-Isp  • Why by using Isp-ivy  • Waremacs by using Isp-ori  Key bindings: The Isp-mode is  • Since the super modifier kewith M-x customize-org  • With PEL, the following keyon the first of the super modifier key bindings shown  • If you change Isp-keyon the super modifier key bindings shown  • If you change Isp-keyon the super modifier key bindings shown  • If you change Isp-keyon the super modifier keyon the super modifier key bindings shown  • If you change Isp-keyon the super modifier keyon the super modifier ke	• show-behaviour-usa with:  PEL activates PE	swhen pel-use-helm-lsp is turned on.  swhen pel-use-lsp-ivy is turned on.  swhen pel-use-lsp-ivy is turned on.  swhen pel-use-lsp-treemacs is turned on.  swhen pel-use-lsp-origami is turned on.  scustomizable prefix key for its key bindings. The default key prefix is s-1.  t can be modified through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix value. This can be done  seriol to the standard through customization: change the lsp-keymap-prefix va
see also:  • © Completion/Input  • © Treemacs  • Dide/Show  LSP key bindings:  • Isp-mode  • erlang Is  See also:  © Input Method  Display LSP workspace log buffer  Validate LSP performance settings  Reformat Erlang file	Isp-mode supports integration  Helm by using helm-Isp  Ivy by using Isp-ivy  Treemacs by using Isp-ori  Key bindings: The Isp-mode is  Since the super modifier k with M-x customize-or  With PEL, the following k  The key bindings shown  If you change Isp-keys  - I L  - 1 d  - 1 - 1	• show-behaviour-usa with:  PEL activates PE	swhen pel-use-helm-lsp is turned on. swhen pel-use-lsp-ivy is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-origami is turned on. scustomizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done scandidates: <f9> okey sequence. scandidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.  1 key prefix. seplaced with your selected prefix key.  Display the log buffer of WORKSPACE.  Validate performance settings and write report in a *lsp-performance* buffer.  Ask the server to format this document.</m-f9></f9></f9></f9>
see also:  • © Completion/Input  • © Treemacs  • Dide/Show  LSP key bindings:  • Isp-mode  • erlang Is  See also:  © Input Method  Display LSP workspace log buffer  Validate LSP performance settings  Reformat Erlang file  Add directory to the list of workspace folders  Remove a directory from the workspace	Isp-mode supports integration  Helm by using helm-Isp  Ivy by using Isp-ivy  Treemacs by using Isp-ori  Key bindings: The Isp-mode is  Since the super modifier k with M-x customize-op  With PEL, the following k  The key bindings shown  If you change Isp-keys  L  S-1 d  S-1 =  S-1 F a	• show-behaviour-usa with:  PEL activates PE	swhen pel-use-helm-lsp is turned on. swhen pel-use-lsp-ivy is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-origami is turned on. scustomizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done cf11> <f2> o key sequence. candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>1 key prefix. splaced with your selected prefix key.  Display the log buffer of WORKSPACE.  Validate performance settings and write report in a *lsp-performance* buffer.  Ask the server to format this document.  Add PROJECT-ROOT to the list of workspace folders. • Prompts for the directory.</m-f9></f9></f9></f2>
see also:	Isp-mode supports integration  Helm by using helm-Isp  Ivy by using Isp-ivy  Treemacs by using Isp-ori  Key bindings: The Isp-mode is  Since the super modifier k with M-x customize-op  With PEL, the following k  The key bindings shown  If you change Isp-keys  L  S-1 d  S-1 =  S-1 F a	• show-behaviour-usa with:  PEL activates PE	swhen pel-use-helm-lsp is turned on. swhen pel-use-lsp-ivy is turned on. swhen pel-use-lsp-treemacs is turned on. swhen pel-use-lsp-origami is turned on. scustomizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done candidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>1 key prefix1 key prefix1 key prefix1 key prefix held buffer of WORKSPACE.  Validate performance settings and write report in a *lsp-performance* buffer.  Ask the server to format this document.  Add PROJECT-ROOT to the list of workspace folders. • Prompts for the directory.  Remove PROJECT-ROOT from the workspace blacklist.</m-f9></f9></f9>
see also:  • © Completion/Input  • © Treemacs  • Dide/Show  LSP key bindings:  • Isp-mode  • erlang Is See also:  © Input Method  Display LSP workspace log buffer  Validate LSP performance settings  Reformat Erlang file  Add directory to the list of workspace folders  Remove a directory from the workspace blacklist  Remove directory from the list of workspace folders  Find Identifier	Isp-mode supports integration  Helm by using helm-Isp  Ivy by using Isp-ivy  Treemacs by using Isp-ori  Key bindings: The Isp-mode is  Since the super modifier k with M-x customize-op  With PEL, the following k  The key bindings shown  If you change Isp-keys  L  S-1 d  S-1 =  S-1 F a  S-1 F b	• show-behaviour-usa with:  PEL activates PE	ages: show the number of modules implementing a behaviour.  s when pel-use-helm-lsp is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s use outsomizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done  11 < 12 o key sequence. andidates: 19 and 11 fyou use 19 for Greek letters then consider using 14. I key prefix. aplaced with your selected prefix key.  Display the log buffer of WORKSPACE.  Validate performance settings and write report in a *lsp-performance* buffer.  Ask the server to format this document.  Add PROJECT-ROOT to the list of workspace folders. Prompts for the directory.  Remove PROJECT-ROOT from the workspace blacklist.
see also:  • ∑ Completion/Input • ∑ Treemacs • ∑ Hide/Show  LSP key bindings: • Isp-mode • erlang Is See also:	Isp-mode supports integration  Helm by using helm-Isp  Ivy by using Isp-ivy  treemacs by using Isp-ori  Key bindings: The Isp-mode is  Since the super modifier k with M-x customize-op  With PEL, the following k  The key bindings shown  If you change Isp-keys  L  S-1 d  S-1 = =  S-1 F a  S-1 F b	with:  PEL activates PEL activ	s when pel-use-helm-lsp is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s customizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the lsp-keymap-prefix value. This can be done t11> <f2> o key sequence. tandidates: <f2> o key sequence. tandidates: <f3> and C-1. If you use <f3> for Greek letters then consider using <m-f3>.  I key prefix. placed with your selected prefix key.  Display the log buffer of WORKSPACE.  Validate performance settings and write report in a *lsp-performance* buffer.  Ask the server to format this document.  Add PROJECT-ROOT to the list of workspace folders. • Prompts for the directory.  Remove PROJECT-ROOT from the workspace blacklist.  Find definitions to the IDENTIFIER at point.</m-f3></f3></f3></f2></f2>
see also:	Isp-mode supports integration  Helm by using helm-Isp  Ivy by using Isp-ivy  Treemacs by using Isp-ori  Key bindings: The Isp-mode is  Since the super modifier k with M-x customize-op  With PEL, the following k  The key bindings shown  If you change Isp-keys  I  S-1 d  S-1 = =  S-1 F a  S-1 F b  S-1 G g	• show-behaviour-usa with:  PEL activates PE	swhen pel-use-helm-Isp is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s customizable prefix key for its key bindings. The default key prefix is s-1. t can be modified through customization: change the Isp-keymap-prefix value. This can be done tf11> <f2> o key sequence. anadidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>1 key prefix. eplaced with your selected prefix key.  Display the log buffer of WORKSPACE.  Validate performance settings and write report in a *Isp-performance* buffer.  Ask the server to format this document.  Add PROJECT-ROOT to the list of workspace folders. • Prompts for the directory.  Remove PROJECT-ROOT from the workspace blacklist.  Find definitions to the IDENTIFIER at point.  Find implementation locations of the symbol at point.</m-f9></f9></f9></f2>
see also:  • ∑ Completion/Input • ∑ Treemacs • ∑ Hide/Show  LSP key bindings: • Isp-mode • erlang Is See also:	Isp-mode supports integration  Helm by using helm-Isp  Ivy by using Isp-ivy  Treemacs by using Isp-ori  Key bindings: The Isp-mode is  Since the super modifier k with M-x customize-op  With PEL, the following k  The key bindings shown  If you change Isp-keys  It  S-1 d  S-1 =  S-1 F a  S-1 F f  S-1 G g	• show-behaviour-usa with:  PEL activates PE	ages: show the number of modules implementing a behaviour.  s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-ivy is turned on. s when pel-use-lsp-treemacs is turned on. s when pel-use-lsp-origami is turned on. s use modified through customization: change the lsp-keymap-prefix value. This can be done ifil> <f2> o key sequence. andidates: <f9> and C-1. If you use <f9> for Greek letters then consider using <m-f9>.  I key prefix palaced with your selected prefix key.  Display the log buffer of WORKSPACE.  Validate performance settings and write report in a "lsp-performance" buffer.  Ask the server to format this document.  Add PROJECT-ROOT to the list of workspace folders. Prompts for the directory.  Remove PROJECT-ROOT from the workspace blacklist.  Find definitions to the IDENTIFIER at point.  Find references to the IDENTIFIER at point.</m-f9></f9></f9></f2>

Description   Ricestroke   Function   Description   Status information	a. In graphics n. to toggle in the
Displays code status such as definition errors, etc   Toggle code action on modelling   Sgs-modelline-code actions-mode Soptional ARG    Sgs-modelline-code actions-mode Soptional ARG    Sgs-modelline	a. In graphics n. to toggle in the
Toggle headline breadcrumbs    S-1 T b	a. In graphics n. to toggle in the
breadcrumbs  breadcrumb	a. In graphics n. to toggle in the
Soptional ARG    When active, information about symbol at point is shown in a pop-up overlay year mode the information has interest can be used to open web-located information - For small window the information may cover too much code, use this command in and out of view. Also note that can be used to open web-located information in the provide to sword the bottom of a window information window may not show completely and you may have to scroll your will follow the provide to work of a window information window may not show completely and you may have to scroll your will follow the provided information window may not show completely and you may have to scroll your will follow the provided information window may not show completely and you may have to scroll your will follow the provided information window may not show completely and you may have to scroll your will follow the provided information window may not show completely and you may have to scroll your will follow the provided information window may not show completely and you may have to scroll your will follow the provided information and out of your will have to scroll your will have to scrol	n. to toggle in the
Toggle code-lens   s-1	
Execute code action    Solidaria   Solidar	
Action INPUTO    If ACTION is not set it will be selected from "isp-code-actions-at-point".   Request codeAction/resolve for more info if server supports.	
Click LSP lens via avy   S-1 a 1   (Isp-avy-lens)   Click Isp lens using 'avy' package.   The code lens must be active. Use s-1 T 1 to activate it if it's not active.	
The code lens must be active. Use s-1 T 1 to activate it if it's not active.  Apropos search for symbol/regexp  s-1 g a  (xref-find-apropos PATTERN)  s-1 g a  (xref-find-apropos PATTERN)  Find all meaningful symbols that match PATTERN.  - Can be used to search symbol outside project.  - The argument has the same meaning as in 'apropos'.  - The result is shown in a 'xref' buffer.  Find definitions of symbol at point  s-1 g i  (sp-find-definition &key DISPLAY-ACTION)  Find implementations of the symbol under point.  S-1 g i  (sp-find-implementation &key DISPLAY-ACTION)  Find references of symbol at point  symbol at point  s-1 g r  (sp-find-references & &optional INCLUDE-DECLARATION &key DISPLAY-ACTION)  Trigger display hover information  Display documentation of the symbol under point.  - The result is shown in a 'xref' buffer.  Display documentation of the symbol at point in 'lsp-help'  Display documentation of symbol at point in 'lsp-help' buffer.  Display the type signature and documentation of the thing at point.  - Display help about symbol at point in side a 'lsp-help' buffer.  Display help about symbol at point in side a 'lsp-help' buffer.  Suffer and used other open identified URL references.  Refactor source import  see also:  (sp-rename NEWNAME)  For renaming the active. Use s-1 T 1 to activate it if it's not active. It is a sum and the match part in side a 'lsp-help' buffer.  - Display the type signature and documentation of the thing at point.  - Display help about symbol at point in side a 'lsp-help' buffer.  - Useful in terminal mode as you can navigate inside the buffer and used other open identified URL references.  Rename the symbol (and all references to it) under point to NEWNAME.  For renaming the arguments of a function, the ledit mode is more appropriate. It restriction the scope to the current function See S Search/Replace	
PATTERN)  • Can be used to search symbol outside project. • The result is shown in a "xref" buffer.  Find definitions of symbol at point  Find implementations of symbol at point  Find implementations of symbol at point  Find implementations of symbol at point  Find references of symbol at point  Find references of symbol at point  Find gradisplay hover information  Display documentation of symbol at point in "sp-help"  S-1 h d (Isp-describe-thing-at-point)  Find symbol at point in "sp-help"  Find references of symbol at point in "sp-help"  Find references of some symbol at point in "sp-help"  Find references of some symbol at point in "sp-help"  Find references of some symbol at point in "sp-help"  Find references of the symbol under point.  Find references of the symbol under point.  Trigger display hover information popup and hide it on next typing.  Find references of the symbol under point.  Trigger display hover information popup and hide it on next typing.  Find references of the symbol under point.  Trigger display hover information popup and hide it on next typing.  Find references of the symbol under point.  Trigger display hover information popup and hide it on next typing.  Find references of the symbol at point in side a "isp-help" buffer.  Display help about symbol at point inside a "isp-help" buffer.  Useful in terminal mode as you can navigate inside the buffer and used other open identified URL references.  Refactor source import  Find references of the symbol under point.  Fi	
Symbol at point   DISPLAY-ACTION	
of symbol at point  implementation &key DISPLAY-ACTION)  Find references of symbol at point  S-1 g r  (Isp-find-references &optional INCLUDE-DECLARATION &key DISPLAY-ACTION)  Trigger display hover information  Information  S-1 h g  (Isp-ui-doc-glance)  Irigger display hover information popup and hide it on next typing.  If your display documentation of symbol at point in "Isp-help"  Isp-help*  Isp-help*  Display documentation of symbol at point in "Isp-help"  Isp-help*  Isp-help*  Information  Isp-nelp*  Display the type signature and documentation of the thing at point.  Isp-help*  Display the type signature and documentation of the thing at point.  Isp-help*  Display help about symbol at point in side a "Isp-help" buffer.  Useful in terminal mode as you can navigate inside the buffer and used other open identified URL references.  Refactor source import  S-1 r o  Isp-rename NEWNAME  Rename the symbol (and all references to it) under point to NEWNAME.  For renaming the arguments of a function, the iedit mode is more appropriate. In restricting the scope to the current function. See Search/Replace	
**The result is shown in a *xref* buffer.  **The result is shown in	
Display documentation of symbol at point in *Isp-help*  S-1 h h  (Isp-describe-thing-at-point)  Display the type signature and documentation of the thing at point.  Display help about symbol at point in inside a *Isp-help* buffer.  Useful in terminal mode as you can navigate inside the buffer and used other open identified URL references.  Refactor source import  S-1 r o  (Isp-organize-imports)  Perform the source-organizeImports code action, if available.  Rename symbol at point See also:  See also:  See arch/Replace	
of symbol at point in *Isp-help*  Display help about symbol at point inside a *Isp-help* buffer.  Useful in terminal mode as you can navigate inside the buffer and used other open identified URL references.  Refactor source import  Sename symbol at point See also:  Display help about symbol at point inside a *Isp-help* buffer.  Useful in terminal mode as you can navigate inside the buffer and used other open identified URL references.  Perform the source organize imports code action, if available.  Rename symbol at point in terminal mode as you can navigate inside the buffer and used other open identified URL references.  Perform the source organize imports code action, if available.  Rename the symbol (and all references to it) under point to NEWNAME.  For renaming the arguments of a function, the iedit mode is more appropriate. It restriction the score to the current function. See Search/Replace	
Rename symbol at point See also:  (Isp-rename NEWNAME) Rename the symbol (and all references to it) under point to NEWNAME.  For renaming the arguments of a function, the <u>ledit mode</u> is more appropriate. It restricting the scope to the current function. See Search/Replace	r functions to
point See also:  See also:  For renaming the arguments of a function, the <u>iedit mode</u> is more appropriate. It restricting the scope to the current function. See ∑ Search/Replace	
	t supports
Disconnect LSP s-1 w D (Isp-disconnect) Disconnect the buffer from the language server.	
Describe LSP session  s-1 w d  (Isp-describe-session)  Describes current 'Isp-session'.  Show available tools and the available capabilities Shows the information inside a LspBrowser buffer.	
Shut LSP workspace down (Isp-workspace-shutdown WORKSPACE) Shut the workspace WORKSPACE and the language server associated with it	
Restart LSP workspace s-1 w r (Isp-workspace-restart WORKSPACE) Restart the workspace WORKSPACE and the language server associated with it	
Activate LSP  S-1 w s  (Isp &optional ARG)  Entry point for the server startup.  • When ARG is t the Isp mode will start new language server even if there is langua which can handle current language.  • When ARG is nil current file will be opened in multi folder language server if there  • When 'Isp' is called with prefix argument ask the user to select which language server.	is such.
Treemacs Support  • <u>∑                                  </u>	eemacs,
• Open LSP Treemacs error list window.  (Isp-treemacs-errors- list)  Display an error list window at the bottom of the frame.  • The buffer uses the treemacs-mode and supports its commands and key bindings.  • To close the window, kill its buffer with C-x k	is.
Quick fix	
• Open LSP Treemacs symbols view.  • To close the window, kill its buffer with C-x k	
• Open LSP Treemacs references window  (Isp-treemacs-references ARG)  (Isp-treemacs-references ARG)  Show the references for the symbol at point. Issue from an Erlang buffer.  • With a prefix argument, select the new window and expand the tree of references automatically.  • To close the window, kill its buffer with C-x k	
• Open LSP Treemacs implementations window  (Isp-treemacs-implementations ARG)  (Isp-treemacs-implementations ARG)  (Isp-treemacs-implementations ARG)  • With a prefix argument, select the new window expand the tree of implementation automatically.  • To close the window, kill its buffer with C-x k	
• Open LSP Treemacs call hierarchy window  (Isp-treemacs-call hierarchy OUTGOING)  (Isp-treemacs-call hierarchy outgoing call hierarchy for the symbol at point.  • With a prefix argument, show the outgoing call hierarchy.  This does not seem to have been implemented for Erlang.	s lang buffer.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Open LSP Treemacs type hierarchy window	<f12> w t</f12>	(Isp-treemacs-type- hierarchy DIRECTION)	Show the type hierarchy for the symbol at point.  With prefix 0 show sub-types.  With prefix 1 show super-types.  With prefix 2 show both.  This is not implemented for Erlang.	
Rendering markup embedded in comments		to describe UML diagrams	specific markup code embedded inside Erlang source code comments. This can be useful when or finite-state machines for example.	
Preview UML diagram from plantUML source in current plantUML region of commented source code  See also: M PlantUML	<f12> u</f12>	(pel-render- commented-plantuml PREFIX &optional POS)	Render the PlantUML markup embedded in current mode comment.  Use region if identified otherwise use PlantUML block at point.  Uses prefix (as PREFIX) to choose where to display it:  4 (when prefixing the command with C-u) -> new window  16 (when prefixing the command with C-u C-u) -> new frame.  else -> new buffer  This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment.	
	<f11> SCP e u</f11>			
	Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command.  Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.			

## Emacs & Erlang - References

Document	Notes
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.
Erlang versions	Erlang Versions - Version Scheme     Erlang Support, Compatibility, Deprecations, and Removal
Erlang/OTP @ Github	Erlang source code
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, Erlang Issue Tracker, events.
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.
Erlang/BEAM	Erlang was the first of one of several programming language that runs on the BEAM VM.
Good introduction presentations on Erlang	The soul of Erlang and Elixir Saša Jurić GOTO 2019 A very good presentation that captures the essence of why Erlang is so important. Fast pace. A must see. A great presentation to show people that may be reluctant to use the technology. The Do's and Don'ts of Error Handling Joe Armstrong GOTO 2018
Erlang References	
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.
A Concise Guide to Erlang	A very nice quick reference. From David Matuszek, University of Pennsylvania
Erlang Code Guidelines	
Erlang Programming Rules and Conventions	Official Ericsson AB Erlang guidelines.
Inaka's Erlang Coding Standards & Guidelines	Guideline used at Inaka, published on Github.
EDoc User's Guide	Describes how to document code.
Erlang Books	There are several printed and online Erlang books. Erlang's FAQ lists several of them. The following lists some extra ones.
Adopting Erlang	A great and recent (2019 and later) online books on Erlang Development that provides information not available in the Erlang introduction books. Describes how to install Erlang, and how to setup editing tools.  A must read to setup Erlang development. This is still work in progress as of May 2020.  Each page has a date time stamp.
Erlang Information Sites	
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.
about-erlang     trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang.  • about-erlang provides general information about Erlang, including:  • Learning Erlang, a table with links to resources to learn Erlang.  • Installing Erlang, describes various ways to install Erlang on macOS.  • Tools for Erlang, describes tools you can use for Erlang development.
Emacs and Erlang Man files	
How to create a local whatis file	Show how to create a missing whatis file for a set of man pages.
The Erlang mode for Emacs (user guide) Erlang mode for Emacs (man page)	On the <a href="erlang.org">erlang.org</a> site. Start here. Describes the 2 files (erlang.el and erlang-start.el) provided by the Erlang mode support, how to set them up for various operating systems. Note, however, that PEL provides the setting for you. It also provides an overview of the various features the package provides.  I found bugs in the <a href="erlang.ng">erlang.ng</a> page in the <a href="Edit-Moving the marker">Edit-Moving the marker</a> section. 1) it's the point that is moved, not the marker, 2) C-a is not an Emacs key prefix, so their key binding descriptions like C-a M-a and C-a M-e are invalid. Reported as <a href="ERL-1314">ERL-1314</a> .  There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric functions and variables.  The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -> on a function definition line.  Another issue: inside the OS-level erlang shell, we can tab-completion a module: function string, but that does not work inside the

Document	Notes
Emacs tools for Erlang	
<u>EDTS</u>	EDTS: stands for: The Erlang Development Tool Suite. See also:  • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube  • EDTS:  • configure your project  • One Primary EDTS node  • 1 node per open project  • To setup an Erlang project: a .edts file in the project:  : name "my-project"  : otp-path "path/to/otp"  : node-name "project-node-name"  : lib-dirs '("lib" "deps")
How to install EDTS	Describes some aspects of EDTS and links that may be useful. Lists the requirements.  After installing EDTS, I got several compile errors, and had to install the following other modules: - auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?
Language Server Protocol	Language Server Protocol @ Wikipedia Language Server Protocol Specifications web site Language Server Protocol @ Github
LSP for Erlang	LSP support for Erlang is done using the following:  The Isp-mode Emacs Lisp package  The erlang Is Erlang server
company-mode ; Modular in-buffer completion framework for Emacs	
Using Tags with Erlang	
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the pel-erlang-shell-prevent-echo is set to t. To activate after setting it: execute pel-init or restart Emacs.