Undo/Redo/Repeat/Command Prefix Arguments

Operation	Keystroke	Function	eat/Command Prefix Arguments Note			
Undo	Emacs standard	undo mechanism is powerful bu	ut unusual for users of other editors.			
	It's however exte PEL customizathe standard E The first row be	nsible and a nice extension is thation allows selection of either. I macs undo. elow shows the PEL bindings to				
	Restrict undo to a region: One very interesting aspect of the Emacs undo system is that we can restrict it to an area of the buffer by first selecting a region and then performing the undo operation while the region is active/visible. Nothing outside the region will be affected by the undo commands. The undo actions outside of the marked region are not lost; once the there is no marked region further undo actions will undo changes in the text.					
Undo	• C-/		/ setting the pel-use-undo-tree customize variable to t.			
: pel-use-undo-tree = nil	• C-x u • M-u • C-z • s-z • %-z	(undo &optional ARG)	Undo last changes using standard Emacs undo. If you are not familiar with standard Emacs undo, please first read about it before using it. It might seems strange at first to use the same key to undo and redo.			
Undo : pel-use-undo-tree = t	• C-/ • C-x u • M-u • C-z • s-z • %-z • <f11> u u</f11>	(undo-tree-undo &optional ARG)	Undo changes using the undo-tree Repeat this command to undo more changes. A numeric ARG serves as a repeat count. In Transient Mark mode when the mark is active, only undo changes within the current region. Similarly, when not in Transient Mark mode, just C-u as an argument limits undo to changes within the current region. C-/ only works in graphics mode			
			PEL uses the undo-tree package instead of the default undo. Under PEL activate the undo-tree package by setting the pel-use-undo-tree customize variable to t.			
Redo	• M-U	(undo-tree-redo &optional	Redo changes. A numeric ARG serves as a repeat count.			
	• <f11> u r • s-Z • %-Z</f11>	ARG)	 In Transient Mark mode when the mark is active, only redo changes within the current region. Similarly, when not in Transient Mark mode, just C-u as an argument limits redo to changes within the current region. 			
			PEL uses the <u>undo-tree package</u> instead of the default undo. Under PEL activate the undo-tree package by setting the <u>pel-use-undo-tree</u> customize variable to t.			
Show undo tree	<f11> u v</f11>	(undo-tree-visualize)	Show undo tree of current buffer. The *undo tree* keys are:			
			PEL uses the <u>undo-tree package</u> instead of the default undo. Under PEL activate the undo-tree package by setting the <u>pel-use-undo-tree</u> customize variable to t.			
Switch branch of undo tree	<f11> u x</f11>	(undo-tree-switch-branch BRANCH)	Switch to a different BRANCH of the undo tree. • This will affect which branch to descend when *redoing* changes using 'undo-tree-redo'. • PEL uses the <u>undo-tree package</u> instead of the default undo. • Under PEL activate the undo-tree package by setting the <u>pel-use-undo-tree</u> customize variable to t.			
Goto last change	<f11> u \</f11>	(goto-last-change &optional MARK-POINT MINIMAL- LINE-DISTANCE)	Set point to the position of the last change. Consecutive calls set point to the position of the previous change. With a prefix arg (optional arg MARK-POINT non-nil), set mark so C−x C−x will return point to the current position. This requires the goto-last-change.el package. Under PEL set the pel-use-undo-last-change customize variable to activate this.			
Enable undo in buffer		(buffer-enable-undo &optional BUFFER)	Enable undo recording in the current buffer. No effect if the undo was already recorded as its the case for all buffers except some (like the buffers that have a name that starts with a space). • Interactively it's not possible to pass an argument.			
Disable undo in buffer		(buffer-disable-undo &optional BUFFER)	Disable undo in current buffer. Deletes all previous undo information for that buffer if it previously existed. No effect if undo was previously disabled. Interactively it's not possible to pass an argument.			
Redo/edit last complex command executed	C-x Esc Esc	(repeat-complex-command ARG)	 Edit and re-evaluate last complex command, or ARGth from last. A complex command is one which used the minibuffer. The command is placed in the minibuffer as a Lisp form for editing. The result is executed, repeating the command as changed. If the command has been changed or is not the most recent previous command it is added to the front of the command history. You can use the minibuffer history commands M-n and M-p to get different commands to edit and resubmit. 			
List command history	<f11> ? d H</f11>	(list-command-history)	List history of commands that used the minibuffer. • Show list of commands in the *Command History* buffer as a list of Emacs Lisp forms.			
Undo all changes made since last saving the file	► It's also possible to undo all changes to a buffer associated with a file by reverting the content of the buffer to the content of the file. See the File Management section.					
Repeat last operation	• C-x z • <f5></f5>	(repeat REPEAT-ARG)	Repeat most recently executed command. With a prefix argument, supply a prefix argument to that command. Otherwise, give the command the same prefix argument it was given before, if any. When using C-x z to perform repeat, Once one C-x z has been typed for the first repeat, type z again			
			to again repeat. Typing z continuously continue to repeat last command (any command, even undo).			
Command Arguments	can provide these		command, a function that supports interactive use. A lot of these commands have arguments. The user ing key strokes before typing the needed command using the keys listed below.			
Prefix repeat N time	M- <number> Keystroke</number>		Meta N, where N is a typed number, tells Emacs to repeat the next <i>Keystroke</i> operation N times.			

Operation	Keystroke	Function	Note
Repeat prefix	C-u <number> Keystroke</number>	(universal-argument)	 C-u N, where N is a typed number, tells emacs to repeat the next operation N times. Pressing C-u before executing a command is a way to pass extra information to that command. For example, C-u 5 C-b means move the cursor left 5 characters. Sometimes the extra information is just the fact that C-u was pressed.
Prefix repeat 4 times	C-u	(universal-argument)	C-u alone stands for a flag, or a repeat factor of 4.
Prefix repeat 16 times	C-u C-u	(universal-argument)	C-u C-u means 4 * 4 = 16
Prefix repeat 64 times	C-u C-u C-u	(universal-argument)	C-u C-u means 4*4*4 = 64 repeat.
Negative argument	• C • M • C-M • C • M • C-M	(negative-argument)	Begin a negative numeric argument for the next command. If needed, C-u following digits or minus sign ends the argument. The PEL package also binds the Control and Meta underscore keys to the negative-argument function to help improve typing speed when entering negative arguments.

Undo - Reference

GNU EMacs Lisp Manual — Command Overview	Describes that prior to executing a command Emacs runs undo-boundary to create undo boundary.
GNU Emacs Lisp Manual — Maintaining Undo Lists	Describes the standard Emacs undo mechanism.
Emacs undo-tree package	Author's we site, describes undo-tree.