Emacs support for the Erlang Programming Language

Personal supposet	Pagarintian	-	-	lang Programming Language
So class. De comment of the process of the process of the pollution of th	<u>Description</u>	Keystroke	Function	Note Fallouing pooks and
The Distance and pooling also packing and pooling	See also: • Developing Erlang	The <u>erlang.el</u> external packag The <u>EDTS</u> external packag The <u>Isp-mode</u> external packag	kage (see <u>erlang.el source)</u> , pa le 🕜 PEL activates it when po ckage 🕜 PEL activates it whe	art of OTP 4 PEL downloads & activates it when pel-use-erlang. is turned on. el-use-edts is turned on (set to t or start-automatically). en pel-use-erlang-Is is turned on (set to t). Uses the erlang Is Erlang LSP server.
** Pipe 4:113 * 423 * globoved by the group harms and BET to cover the specific customization group or one of the following bee sequences. ** ** ** ** ** ** ** ** ** ** ** ** **	set PEL Erlang	The <u>Distel</u> external package also exists, but seems to have mainly been replaced by EDTS and needs maintenance. PEL does not support it. Some work is required to identify an optimal working environment for Erlang in Emacs which integrates the best features of the above packages. I am currently trying to provide information on that and select the best possible Emacs/Erlang system to describe it here.		
policytic forwards on control pales and the policy of the complete of the comp	• <u>S Customize</u>	• Type <f11> <f2> g follo</f2></f11>		RET to open the specific customization group or one of the following key sequences.
peletriang-selection-prevent-either acts to 1 to prevent the Etting self-time control group command. peletriang-self-transpervation-control group: peletriang-environment group: peletriang-environment group: peletriang-environment group: peletriang-environment group: peletriang-environment group: peletriang-exe-path iterative the discovery of Esting man directory of Esting and discovery of Esting and Self-time the period of the esting of the environment of the env		• pel-pkg-for-erlang: to pel-erlang-ide group of • erlang: w • edts: v • lsp-erlang: v	o activate pel-use-erlang: us to activate EDTS and LSP. when pel-use-erlang is on, when pel-use-edts is on, when pel-use-erlang-ls is on,	use <f11> SPC e <f3> 1 use <f11> SPC e <f3> 3 use <f11> SPC e L <f3> 1</f3></f11></f3></f11></f3></f11>
rando which contain Februg man files. If this is set FLL sets (overhidd the enting all eriting-rock-dit user-option value with it which activates the appropriate Februg man Februg records in all, you must set the death of component option yourself. • pell-enting-version-detection-method Libertities a michanism to detect transgrifty version. By default it uses as that grant product with product with the pell-enting-version-detection-method Libertities a michanism to detect transgrifty of the pell-enting-version-detection-method Libertities a michanism to detect transgrifty version. By default it uses as that grant product with pell-enting-version-detection-method Libertities a michanism to detect transgrifty version. By default it uses as the state of the product of the pell-enting the version of the pell-enting the pell-entin		 pel-erlang-shell-prevent-echo: set to t to prevent the Erlang shell from echoing every command. pel-erlang-activates-minor-modes: list of minor modes that PEL will activate for the Erlang major mode. This has several sub-groups: 		
* pel-ediang-fille-louisms column where line-wrapping cours: maximum line length (defaults to 100, You can change the value or set it nit. * When pel-ediang-fiel-louism column where line-wrapping cours: maximum line length (defaults to 100, You can change the values or set it nit. * When pel-ediang-fiel-louisms column where line-diange counters are used in Entire Code lengths (see the later Clinic Code line) and pel-ediange-fiel-louisms where automatically updated the stamps are marked in Entire goods code code (line) and the later of the late		man6 which contain Erlar appropriate Erlang man fi • pel-erlang-exec-path: Ic • pel-erlang-version-dete	ng man files. If this is set PEL iles. Without PEL or if pel-erla dentifies the directory where E action-method: identifies a me	sets (override) the erlang.el erlang-root-dir user-option value with it which activates the ang-man-parent-rootdir is nil, you must set the erlang-root-dir user-option yourself. rlang binaries are stored.
Open this PDF file. See also:		pel-erlang-fill-columi When pel-erlang-fill pel-erlang-skel-use-s pel-erlang-skel-use-s pel-erlang-skel-inser PEL provides the following s The first one is always ava	: column where line-wrappin -column user option is nil, erla separators: whether line sepa secondary-separators: whet t-file-timestamp: whether au set of mode-specific key prefiz illable. The other two prefixes	ang-mode buffers use the Emacs fill-column value like other major modes. Irrators are used in Erlang code templates (see the Insert Erlang Code Template section below), Ither secondary separator lines are inserted by some Erlang code templates, Ither secondary separator lines are inserted in Erlang source code file header blocks. Ither secondary separator lines are inserted in Erlang source code file header blocks. Ither secondary separator lines are inserted in Erlang source code file header blocks. Ither secondary separator lines are inserted in Erlang source code file header blocks. Ither secondary separator lines are inserted in Erlang source code file header blocks. Ither secondary separator lines are inserted in Erlang source code file header blocks. Ither secondary separator lines are inserted in Erlang source code file header blocks. Ither secondary separator lines are inserted in Erlang source code file header blocks. Ither secondary separator lines are inserted by some Erlang code templates, Ither secondary separator lines are inserted by some Erlang code templates, Ither secondary separator lines are inserted by some Erlang code templates, Ither secondary separator lines are inserted by some Erlang code templates, Ither secondary
See also: S_Help/Info				files to show the list of functions.
Customize PEL Efrang Support Constomize PEL Efrang Support	•	• <f11> SPC e w <f1> • <f11> SPC e L <f1></f1></f11></f1></f11>		Open the <u>\mathbb{N}\tilde{\text{L}} - Erlang</u> local PDF. If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.
### Support \$\f12 \rightarrow \fifty \figure{f2} \text{Nindow} \figure{f3} \text{Nindow} \figure{f3} \text{Nindow} \figure{f3} \text{Nindow} \text{Nindow} \text{Nindow} \text{Nindow} \text{Nindow} \qquad \qquad \qquad \qquad \q		• <f12> w <f1></f1></f12>		
Soptional OTHER- Soptional O			&optional OTHER-	Customize PEL Erlang support: access PEL user-options to activate Erlang support packages. • If OTHER-WINDOW is non-nil (use C-u), display in another window.
FOTHER-WINDOW is non-nil (use C-u), display in another window. Standard Emacs Coustomize Coustomize Emacs Coustomize Emacs Coustomize Emacs Coustomize Emacs Coustomize Coustomize Emacs Coustomize Emacs Coustomize C	I —		&optional OTHER-	The state of the s
Softonal OTHER-WINDOW **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **This is available when pel-use-erlang-ls is turned on. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **This is available when pel-use-treemacs is turned on. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in another window. **Softonal OTHER-WINDOW is non-nil (use C-u), display in a			&optional OTHER-	• If OTHER-WINDOW is non-nil (use C-u), display in another window.
Soptional OTHER-WINDOW is non-nil (use C-u), display in another window.			&optional OTHER-	• If OTHER-WINDOW is non-nil (use C-u), display in another window.
Septional OTHER-WINDOW is non-nil (use C-u), display in another window. If OTHER-WINDOW is non-nil (use C-u), display in another window. If it is available when pel-use-treemacs and/or pel-use-lsp-treemacs is turned or the pel-use-treemacs and/or pel-use-lsp-treemacs and	Window for Erlang		&optional OTHER-	
Erlang Mode version	LSP Window for Erlang		&optional OTHER-	
erlang_el and the erlang_ls if available. It also displays the value of erlang-root-dir at erlang-man-parent-rootdir. △ Check that erlang-root-dir matches the version of Erlang you use. If not check the of the erlang-man-parent-rootdir. For more information see set PEL Erlang enviror Syntax Highlighting Erlang code syntax highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via</f10></f10></f10></f10></f10></f10></f10></f10></f10></f10></f10></f10></f10></f10>	Environment Help			
erlang-man-parent-rootdir. ⚠ Check that erlang-root-dir matches the version of Erlang you use. If not check the of the erlang-man-parent-rootdir. For more information see set PEL Erlang enviror. Syntax Highlighting Edit Erlang Code The following commands help edit Erlang code. Create additional clause Clause C-c C-j (erlang-generate-new-clause) Clone clause arguments Clone clause Align arrows inside region C-c C-a (erlang-align-arrows START END) Erlang code syntax highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting has 4 levels and can be turned off via Erlang menu: <f10< &="" a="" access="" be="" can="" erlang,="" f10="" menu="" select="" synta<="" td="" the="" then="" to=""><td>Erlang Mode version</td><td><f11> SPC e ?</f11></td><td>(pel-show-erlang-version)</td><td>Display the following information in the minibuffer: current version of available Erlang system, of</td></f10<></f10></f10></f10></f10></f10></f10></f10></f10></f10></f10></f10></f10>	Erlang Mode version	<f11> SPC e ?</f11>	(pel-show-erlang-version)	Display the following information in the minibuffer: current version of available Erlang system, of
Create additional clause C-c C-j (erlang-generate-new-clause) Create additional clause C-c C-j (erlang-generate-new-clause) Create additional Erlang clause header. Parses the source file for the name of the current Erlang function. Create the header containing the name, a pair of parentheses, and an arrow. The space between the funame and the first parenthesis is preserved. The point is placed between the parent linsert, at the point, the argument list of the previous clause. Copy the function arguments of the preceding Erlang clause. This command is useful defining a new clause with almost the same argument as the preceding. The mark is set at the beginning of the inserted text, the point at the end. Align arrows inside region C-c C-a (erlang-align-arrows START END) START END START END Sum([H T], Sum) -> sum(T, 0). Sum(T, Sum + H); Sum([I], Sum) ->		<f12> ?</f12>		
Create additional clause C-c C-j (erlang-generate-new-clause) Create additional Erlang clause header. Parses the source file for the name of the current Erlang function. Create the header containing the name, a pair of parentheses, and an arrow. The space between the function ame and the first parenthesis is preserved. The point is placed between the parent list of the previous clause. C-c C-y (erlang-clone-arguments) Insert, at the point, the argument list of the previous clause. Copy the function arguments of the preceding Erlang clause. This command is useful defining a new clause with almost the same argument as the preceding. The mark is set at the beginning of the inserted text, the point at the end. Align arrows inside region C-c C-a (erlang-align-arrows START END) Align arrows ("->") in function clauses inside marked region or in the current function. With a prefix argument, aligns all arrows in the region (or from beginning of buffer up point), not just those in function clauses. Example: sum(L) -> sum(L, 0). sum([H T], Sum) -> sum(T, Sum + H); sum([I], Sum) -> Sum.	Syntax Highlighting	Erlang code syntax highlighting	g has 4 levels and can be turn	ned off via Erlang menu: <f10> to access the menu & select Erlang, then Syntax Highlighting.</f10>
clause Clause Parses the source file for the name of the current Erlang function. Create the header containing the name, a pair of parentheses, and an arrow. The space between the funame and the first parenthesis is preserved. The point is placed between the parent list of the previous clause. Clone clause arguments Clone clause arguments C-c C-y (erlang-clone-arguments) Insert, at the point, the argument list of the previous clause. Copy the function arguments of the preceding Erlang clause. This command is useful defining a new clause with almost the same argument as the preceding. The mark is set at the beginning of the inserted text, the point at the end. Align arrows inside region C-c C-a (erlang-align-arrows START END) Align arrows ("->") in function clauses inside marked region or in the current function. With a prefix argument, aligns all arrows in the region (or from beginning of buffer up point), not just those in function clauses. Example: sum(L) -> sum(L, 0). sum([H T], Sum) -> sum(T, Sum + H); sum([], Sum) -> Sum.	Edit Erlang Code	The following commands help	edit Erlang code.	
Copy the function arguments of the preceding Erlang clause. This command is useful defining a new clause with almost the same argument as the preceding. The mark is set at the beginning of the inserted text, the point at the end. Align arrows inside region (erlang-align-arrows START END) Align arrows ("->") in function clauses inside marked region or in the current function. With a prefix argument, aligns all arrows in the region (or from beginning of buffer up point), not just those in function clauses. Example: sum([] -> sum(L) -> sum(T, Sum + H); sum([], Sum) -> Sum.		C-c C-j	,	Create additional Erlang clause header. • Parses the source file for the name of the current Erlang function. Create the header containing the name, a pair of parentheses, and an arrow. The space between the function name and the first parenthesis is preserved. The point is placed between the parentheses.
 With a prefix argument, aligns all arrows in the region (or from beginning of buffer up point), not just those in function clauses. Example: sum(L) -> sum(L, 0). sum([H T], Sum) -> sum(T, Sum + H); sum([], Sum) -> Sum. 		С-с С-у	(erlang-clone-arguments)	Copy the function arguments of the preceding Erlang clause. This command is useful when defining a new clause with almost the same argument as the preceding.
<pre>sum(L) -> sum(L, 0). sum([H T], Sum) -> sum(T, Sum + H); sum([], Sum) -> Sum.</pre>	•	C-c C-a		 With a prefix argument, aligns all arrows in the region (or from beginning of buffer up to point), not just those in function clauses. Example: sum(L) -> sum(L, 0). sum([H T], Sum) -> sum(T, Sum + H); sum([], Sum) -> Sum. becomes: sum(L) -> sum(L, 0). sum([H T], Sum) -> sum(T, Sum + H);

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Electric Keys	The following keys have "elect	ric" behaviour and perform sp	pecial editing tasks to help edit Erlang source code.
Electric comma	,	(erlang-electric-comma &optional ARG)	Insert a comma character and possibly a new indented line. The variable 'erlang-electric-comma-criteria' states a criterion, when fulfilled a newline is inserted and the next line is indented. Behaves just like the normal comma when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.
Electric semicolon	;	(erlang-electric- semicolon &optional ARG)	Insert a semicolon character and possibly a prototype for the next line. • The variable 'erlang-electric-semicolon-criteria' states a criterion, when fulfilled a newline is inserted, the next line is indented and a prototype for the next line is inserted. Normally the prototype consists of " ->". Should the semicolon end the clause a new clause • header is generated. • The variable 'erlang-electric-semicolon-insert-blank-lines' controls the number of blank lines inserted between the current line and new function header. • Behaves just like the normal semicolon when supplied with a numerical arg, point is inside string or comment, or when there are non-whitespace characters following the point on the current line.
Electric > (for the end of arrow)	>	(erlang-electric-gt &optional ARG)	Insert a greater-than sign, and optionally insert a new line and indent.
Erlang Comments	• %% - Two percent charac	acters for comments located of acters are used for comments s	toward the end of a line of code
Comment/un-comment • PEL extension of	M-;	(comment-dwim ARG)	Comment line or region with % or %% style comments depending on the location in the buffer.
comment-dwim specialized for Erlang.		(pel-erlang-comment- dwim &optional ARG)	
Automatically uses the %%% comment when appropriate.	When no marked region and With marked un-commenter	On first emp	e: insert %% comment starter at the proper indentation level. ty line in buffer: insert %%% comment. Also following lines or region that starts with %%% code: insert % comment starter after the code for an end-of-line comment ach line is commented)
Note:	With marked commented re	gion: Un-comments the r	
 M-; works much better than C-c C-c and C-c C-u PEL maps M-; to 	➤ The <u>erlang.el</u> code binds ▶	I-1 to indent-for-comment. H	lowever PEL uses M-1 for something else. dent-for-comment if nothing is marked.
pel-erlang-comment- dwim which works even better.	C-c C-c	(comment-region BEG END &optional ARG)	Comment or uncomment each line in the region. • With just C - u prefix arg, uncomment each line in region BEG END. • Numeric prefix ARG means use ARG comment characters. • If ARG is negative, delete that many comment characters instead.
See also: <u>▼ Comments</u>	 The comment start is identified by 'comment-start' and 'comment-padding'; the comment end by 'comment-end' and 'comment-padding'. By default, the 'comment-start' markers are inserted at the current indentation of the region, and comments are terminated on each line (even for syntaxes in which newline does not end the comment and blank lines do not get comments). This can be changed with 'comment-style'. 		
Un-comment region	C-c C-u	(uncomment-region BEG END &optional ARG)	Uncomment each line in the BEG END region. The numeric prefix ARG can specify a number of chars to remove from the comment delimiters.
Fill current paragraph See also: Filling/Justification	• M-q • <f11> t f p</f11>	(fill-paragraph &optional JUSTIFY REGION)	 Fill multi-line comment at or after point. To justify as well: C-u M-q In refill mode this is done automatically. In auto fill mode the filling is done at the end of the line. See the ∑ Filling/Justification for all filling and justification commands.
Toggle display of comments in buffer or active region See also: <u>Comments</u>	<f11> ; ;</f11>	(hide/show-comments- toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. • This requires the hide-comnt.el package (see ∑ Comments). Del-use-hide-comnt user option is t.
Indentation			he CC-Mode logic and provided commands listed below. at the end of this list. They are also listed in the <u>∑ Indentation</u> table.
Indent current line or region	<tab></tab>	(c-indent-line-or-region &optional ARG REGION)	Indent active region, current line, or block starting on this line.
See also: <u>Indentation</u>	 The indentation level is controlled by the erlang-indent-level variable from erlang.el. Its default is 4. Access its custom group buffer using <f12> <f3> 1 or <f11> SPC e <f3> 1. Or use <f11> <f2> g erlang RET.</f2></f11></f3></f11></f3></f12> Note that the erlang.el logic doubles the indentation label inside funs. See this S.O. discussion on that. Behaviour depends on syntactic-indentation mode (enabled by default but can be toggled on/off with the <f12> M-i key):</f12> With syntactic-indentation on (the default): In Transient Mark mode, when the region is active, reindent the region. Otherwise, with a prefix argument, rigidly reindent the expression starting on the current line. Otherwise reindent just the current line. This might seem strange for new Emacs users, but it ends up being very useful. You can type <tab> anywhere in the line to adjust the indentation of the current line or everything in the marked area if a block is marked.</tab> With syntactic-indentation off: <ab> always indent current line by one level C-u -<ab> always indent current line by one level</ab> Indenting marked region is done without syntax knowledge and at the same level as previous line. </ab> If you want to indent rigidly you can use: (pel-indent-rigidly &optional N) (bound to C-x <tab> and to <f11> <tab> <tab> <tab> <tab> tab> tab tab to indent the line or region rigidly.</tab></tab></tab></f11></tab> 		
Indent Erlang function		nd to M-i to insert spaces to (erlang-indent-function)	the next tab stop column. Indent current Erlang function.
Indent lines of list after	C_M_a	(prog_indent.cova	This also works with a simple tab (see above). Indent the expression after point.
point See also: <u>Named Indentation</u>	C-M-q	(prog-indent-sexp &optional DEFUN)	When interactively called with prefix, indent the enclosing defun instead.
Indent a region	C-M-\	(indent-region START END &optional COLUMN)	Indent each nonblank line in the region. • A numeric prefix argument specifies a column: indent each line to that column. • With no prefix argument, the command chooses one of these methods and indents all the lines with it: 1. If 'fill-prefix' is non-nil, insert 'fill-prefix' at the beginning of each line in the region that does not already begin with it. 2. If 'indent-region-function' is non-nil, call that function to indent the region. 3. Indent each line via 'indent-according-to-mode'. When a region is marked you can also use the simple <tab> to do the same when syntactic-indentation is active.</tab>

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Navigation in Erlang code See also: Navigation	Several commands are specia Notice the 3 sets of commands (**12> <up> and <:</up>	The erlang-mode provides commands to navigate across Erlang source code. PEL complements these. And EDTS also Several commands are specialization of the normal navigation commands which are described in the table Navigation, but several are specific to Erlang: Notice the 3 sets of commands: 1. <f12> <up> and <f12> <down> move to the beginning of Erlang functions skipping all compiler directives. 2. The standard navigation commands, (mapped to <f6> prefix) move to beginning/end of Erlang functions but stop at compiler directives. 3. The <f12> <u-cursor> commands (also accessible via <u-cursor>, move across Erlang clauses (as opposed to functions). The list below describe the specialized commands only. See the others inside Navigation, like the navigation by blocks. Note that all <f12> prefixes shown below are available in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11></f12></u-cursor></u-cursor></f12></f6></down></f12></up></f12>		
Go to beginning of statement	м-а	(backward-sentence &optional ARG)	Go backward to the beginning of an Erlang clause. • With a numerical argument repeat that many times.	
Go to the end of statement	м-е	(forward-sentence &optional ARG)	Go forward to the end of an Erlang clause. • With a numerical argument repeat that many times.	
Go to beginning of current function or top- level function	С-м-а	(c-beginning-of-defun &optional ARG)	Move backward to the beginning of an Erlang function. Every top level declaration that contains a brace paren block is considered to be a defun. With a positive argument, move backward that many defuns. A negative argument -N means move forward to the Nth following beginning.	
Goto end of current function or top-level function	С-М-е	(c-end-of-defun &optional ARG)	Move forward to the end of an Erlang function. • With argument, do it that many times. Negative argument -N means move back to Nth preceding end.	
Move backward to beginning of previous function	• <f12> <up> • <f12> f p • <f11> SPC e <up> • <f11> SPC e f p</f11></up></f11></f12></up></f12>	(pel-previous-erl-function &optional N)	Move backward to the beginning of the previous function skipping all compiler directives. • With prefix argument N repeat N times. • Pushes mark; move back to previous position with M-`. Shift marking is available for the key sequence using a cursor key.	
Move forward to beginning of next function	• <f12> <down> • <f12> f n • <f11> SPC e <down> • <f11> SPC e f n</f11></down></f11></f12></down></f12>	(pel-next-erl-function &optional N)	Move forward to the beginning of the next function skipping all compiler directives. • With prefix argument N repeat N times. • Pushes mark; move back to previous position with M−ˆ.	
Backward to beginning of function or compiler directive	<f11> SPC e T N <f12> f P • C-M-a • C-M-<nome> • <f6> p • <f6> <up> • <f11> SPC e f P</f11></up></f6></f6></nome></f12></f11>	(beginning-of-defun &optional ARG) (erlang-beginning-of- function &optional ARG)	Move backward to the beginning of an Erlang function or compiler directive. • With ARG, do it that many times. Negative ARG means move forward to the ARGth following beginning of defun. ⇒Shift marking is available in graphics mode, not in terminal mode (for C-M-a and C-M- <home>). However <f6> p and <f6> <up> handle Shift-marking fine in terminal mode. Erlang.el man page indicates an invalid mapping for this.</up></f6></f6></home>	
Forward to beginning of next function or compiler directive	<f12> f N • <f6> n • <f6> <down> • <f11> SPC e f N</f11></down></f6></f6></f12>	(pel-beginning-of-next- defun &optional SILENT DONT-PUSH_MARK)	Move forward to the beginning of the next function definition or compiler directive. • Beeps if does not find beginning of next function unless SILENT is non-nil. • If the beginning of next function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−ˆ. ⇒ Shift marking is available for the <f6> bindings.</f6>	
	 This command complemen It moves forward but not to other editors expect. It handles nested functions 	the end of the function definiti	ion (like end-of-defun) but to the beginning of the function definition, which is often what users of s like Python and others.	
Backward to end of previous function or compiler directive	<f6> <left></left></f6>	(pel-end-of-previous- defun &optional SILENT DONT-PUSH_MARK)	Move backwards to the end of the previous function definition. • Beeps if does not find end of previous function unless SILENT is non-nil. • If the end of previous function is found, push the start location to the mark ring unless DONT-PUSH_MARK is non-nil. • Move back to previous position with M−`. ⇒Shift marking is available for the <f6> bindings.</f6>	
Forward to end of function or compiler directive	• C-M-e • C-M- <end> • <f6> <right></right></f6></end>	(end-of-defun &optional ARG) (erlang-end-of- function &optional ARG)	Move forward to end of Erlang function. With argument, do it that many times. Negative argument -N means move back to Nth preceding end of defun. ➡ Shift marking is available in graphics mode, not in terminal mode (for C-M-e and C-M- <nd>. However <f6> <right> handle Shift-marking fine in terminal mode.</right></f6></nd>	
Backward to beginning of clause	• C-c M-a • <f12> c a • <m-f12> <m-up></m-up></m-f12></f12>	(erlang-beginning-of- clause &optional ARG)	Move backward to previous start of clause. • With argument, do this that many times.	
Forward to beginning of next clause	• <f12> c n • <m-f12> <m-down></m-down></m-f12></f12>	(pel-beginning-of-next-clause)	Move forward to the beginning of next clause. • Pushes mark; move back to previous position with M−⁻. ⇒Shift marking is available.	
Backward to end of previous clause	• <f12> c p • <m-f12> <m-left></m-left></m-f12></f12>	(pel-end-of-previous- clause)	Move backward to the end of the previous clause. • Pushes mark; move back to previous position with M−`. →Shift marking is available.	
Forward to end of current clause	• C-c M-e • <f12> c e • <m-f12> <m-right></m-right></m-f12></f12>	(erlang-end-of-clause &optional ARG)	Move to the end of the current clause. • With argument, do this that many times.	
EDTS/Navigation	EDTS (see below) provides m	ore navigation commands.		
Search Support		In Erlang mode, the superword mode can be useful since <u>snake case</u> is often used. Using superword-mode helps searching. PEL activates the superword mode by default in Erlang mode. To change this use the <f11> t <f2> to access the customize buffer.</f2></f11>		
Toggle superword- mode See also:	<f12> M-p • <f11> t m p • <f11> SPC e M-p</f11></f11></f12>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats <u>snake_case</u> as one word. In Erlang, '_' are treated as part of words. • With a prefix argument ARG, enable superword mode if ARG is positive, and disable it otherwise.	
• <u>∑ Text Modes</u> • <u>∑ Search/Replace</u>	•		PEL provides the <f12> M-p key for the programming language modes where snake case is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12>	
Marking		,	vailable. They complement what is already available and described in the <u>∑ Marking</u> table. an invalid mapping for this. Reported as <u>ERL-1314</u> .	
Mark Erlang function	• C-M-h • <f12> f m</f12>	(mark-defun &optional ARG) (erlang-mark-function &optional ARG)	Put mark at end of this function, point at beginning. The function marked is the one that contains point or follows point. With positive ARG, mark this and that many next functions; with negative ARG, change the direction of marking. If the mark is active, it marks the next or previous function(s) after the one(s) already marked.	
Mark Erlang Clause	• C-c M-h • <f12> c m</f12>	(erlang-mark-clause)	Put mark at end of clause, point at beginning.	

Description	Voyotroko	Function	Note	
Description Highlighting blocks	Keystroke The following commands can		useful modes to highlight blocks of (), {}, and [].	
Highlighting blocks	show-paren-mode, which h	ighlights the parens that match	hes the one before or after point. are highlighted with the same colour.	
Toggle show-paren mode on/off	• <f12> M-9 • <m-f12> M-9</m-f12></f12>	(show-paren-mode &optional ARG)	Toggle visualization of matching parens (Show Paren mode). • With a prefix argument ARG, enable Show Paren mode if ARG is positive, and disable it otherwise.	
See also: <u>Neighlight</u>	• <f11> h (• <f11> SPC e M-9</f11></f11>		Show Paren mode is a global minor mode. When enabled, any matching parenthesis is highlighted in 'show-paren-style' after 'show-paren-delay' seconds of Emacs idle time.	
Enable/Disable coloured highlight of	• <f12> M-r • <m-f12> M-r</m-f12></f12>	(rainbow-delimiters-mode & optional ARG)	Highlight nested parentheses, brackets, and braces with different colours according to their depth.	
nested blocks (),{},[]	• <f11> h R</f11>	aoptional / ti to/	Customize the depth and colours with M-x customize-group rainbow-delimiters	
See also: <u>∑ Highlight</u>	• <f11> SPC e M-r</f11>		PEL activates this when the pel-use-rainbow-delimiters user option is set to t.	
Inserting code with	Specialized Tempo Ske	pecialized Tempo Skeletons		
Insert Parentheses	M- ((insert-parentheses	For Erlang: insert a parenthesis pair '()', leaving point after open-paren.	
		&optional ARG)	 A positive ARG encloses the following ARG sexps in parenthesis if they are balanced. A negative ARG encloses the preceding ARG sexps instead. No argument is equivalent to zero: just insert '()' and leave point between. PEL makes 'parens-require-spaces' buffer local and set it to nil in Erlang mode buffers, allowing the use of this command to insert the argument parentheses following a function (and without placing a space between the function name and the opening parenthesis. If region is active, insert enclosing characters at region boundaries. This command assumes point is not in a string or comment. 	
Insert Erlang Code			ns using the standard tempo skeleton package. e Erlang/Skeletons menu (via < £10>).	
Templates	PEL provides the following	additional functionality:		
See also:			under the pel:erlang-skel key prefix: <f12> <f12></f12></f12> . a +. These are also added to the menu.	
 <u>Name Inserting Text</u> for more info and 			ries and the december of the ment. It is controlled by the user options inside the pel-erlang-code-style group. The controlled	
information about tempo skeleton and	templates affected are m		ser options are part of the pel-erlang-code-style group accessible with <f12> <f2> from an</f2></f12>	
the completely	pel-erlang-skel-inser	rt-file-timestamp :	set whether an automatically updated timestamp is inserted in the file header block.	
different <u>vasnippet</u> template-based text	pel-erlang-skel-prom pel-erlang-skel-prom	pt-for-function-name :	set whether file and function skeletons blocks prompt for purpose and insert it. set whether function skeletons prompt for function name and then inserts that name.	
insertion).	pel-erlang-skel-pronpel-erlang-use-sepal		set whether function skeletons prompt for function arguments and then insert them. set whether blocks use horizontal separator lines (these are the first of potentially 2 separators).	
	 pel-erlang-use-second pel-erlang-skel-with 		set whether blocks use a second block horizontal separator line. set whether generated code comments use EDoc markup.	
	• pel-erlang-skel-with-		set whether file header blocks use open source software license text controlled by iice.	
			tut by using file and directory variables (see <u>File/Directory Variables</u>) they can also be used	
	you want to change the be PEL tempo templates for allows you to control the u • Once a skeleton was just	to take effect on a single file or all files inside a directory tree. So by default, the user options that control the PEL tempo template take effect globally. you want to change the behaviour for only one file, write the user option control block at the end of that file. If you want to control the behaviour of the PEL tempo templates for all files inside a directory tree create a .dir-locals file and store the values of the relevant options variables inside that file. This allows you to control the user options affecting the format of the tempo templates precisely and does not affect what you actually type. • Once a skeleton was just entered (or later by activating the pel-tempo-mode) you can move to the next or previous point of interest (so called tempo-		
	marks) with the standard tempo-mode keys C-c M-f and C-c M-b or some other keys like C-c . and C-c ,. • Instead of using the <f12> <f12> bindings, you can also type the template name and then hit C-c C-M-i or <f1 a="" all="" buffer.="" completions="" for="" into="" is="" listing="" mainly="" names<="" separate="" short="" supports="" td="" templates="" temporary="" this="" useful="" which=""><td>also type the template name and then hit C-c C-M-i or <f12> <f12> <f12>. This</f12></f12></f12></td></f1></f12></f12>		also type the template name and then hit C-c C-M-i or <f12> <f12> <f12>. This</f12></f12></f12>	
I and the same of				
+ : additional templates C : templates with customization control	Some of the template names in the title column are also links to the relevant Erlang language construct reference page. Note that all <f12> prefixes shown below are available in erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11></f12>			
<u>> Customize</u> PEL Erlang Skeletons layout	<f12> <f12> <f2></f2></f12></f12>	(pel-customize-pel &optional OTHER- WINDOW)	Customize PEL Erlang skeleton layout. • If OTHER-WINDOW is non-nil (use C-u), display in another window.	
if	<f12> <f12> i</f12></f12>	(pel-erl-if)	Insert an if statement.	
<u>case</u>	<f12> <f12> c</f12></f12>	(pel-erl-case)	Insert a case expression.	
export +	<f12> <f12> x</f12></f12>	(pel-erl-export	Insert an export module attribute expression.	
import +	<f12> <f12> I</f12></f12>	(pel-erl-import)	Insert an import module attribute expression.	
<u>try</u> +	<f12> <f12> t</f12></f12>	(pel-erl-try)	Insert a try expression.	
try-of +	<f12> <f12> T</f12></f12>	(pel-erl-try-of)	Insert a try expression with of clauses.	
<u>receive</u>	<f12> <f12> r</f12></f12>	(pel-erl-receive)	Insert a receive expression.	
<u>after</u>	<f12> <f12> a</f12></f12>	(pel-erl-after)	Insert a receive expression with an after (timeout) clause.	
Іоор	<f12> <f12> 1</f12></f12>	(pel-erl-loop)	Insert a simple receive loop.	
module	<f12> <f12> m</f12></f12>	(pel-erl-module)	Insert the module attribute.	
<u>function</u> C	<f12> <f12> f</f12></f12>	(pel-erl-function)	Insert a function definition. This may prompt for function name, argument and purpose according to the user options described above. All prompts maintain independent histories.	
author	<f12> <f12> `</f12></f12>	(pel-erl-author)	Insert the author attribute. Uses the user-mail-address user option to insert your mail address.	
spec	<f12> <f12> s</f12></f12>	(pel-erl-spec)	Insert a -spec for the function following point.	
small-header C	<f12> <f12> M-h</f12></f12>	(pel-erl-small-header)	Insert a small file header without any comment.	
normal-header C	<f12> <f12> M-H</f12></f12>	(pel-erl-normal-header)	Insert a normal file header: includes author name, copyright notice, doc section, file created date	
large-header C	<f12> <f12> h</f12></f12>	(pel-erl-large-header)	Insert a large header block that includes all normal header fields plus separators. • All formatting is controlled by user-options described above. • Distinguish Erlang .erl module files from the .hrl header files.	
small-server C	<f12> <f12> M-s</f12></f12>	(pel-erl-small-server)	Insert a large file header and template logic for a small server.	
application C	<f12> <f12> M-a</f12></f12>	(pel-erl-application)	Insert a large file header and template logic for an application behaviour.	
supervisor C	<f12> <f12> M-u</f12></f12>	(pel-erl-supervisor)	Insert a large file header and template logic for a supervisor behaviour.	
supervisor-bridge C	<f12> <f12> M-b</f12></f12>	(pel-erl-supervisor-bridge)	Insert a large file header and template logic for a supervisor bridge behaviour.	
generic-server C	<f12> <f12> M-g</f12></f12>	(pel-erl-generic-server)	Insert a large file header and template logic for a gen-server behaviour.	
gan avent C	<f12> <f12> M-e</f12></f12>	(pel-erl-gen-event)	Insert a large file header and template logic for a gen-event behaviour.	
gen-event C		and the second of the second o	, ————————————————————————————————————	
gen-fsm C	<f12> <f12> M-f</f12></f12>	(pel-erl-gen-fsm)	Insert a large file header and template logic for a gen-fsm behaviour.	

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
gen-statem-StateName C	<f12> <f12> M-S</f12></f12>	(pel-erl-gen-statem- StateName)	Insert a large file header and template logic for a gen-statem behaviour.
gen-statem-handle- event C	<f12> <f12> M-E</f12></f12>	(pel-erl-gen-statem- handle-event)	Insert a large file header and template logic for a gen-statem.
wx-object C	<f12> <f12> M-W</f12></f12>	(pel-erl-wx-object)	Insert a large file header and template logic for a wx-object generic server.
gen-lib C	<f12> <f12> M-1</f12></f12>	(pel-erl-gen-lib)	Insert a large file header and template logic for a library module.
gen-corba-cb C	<f12> <f12> M-c</f12></f12>	(pel-erl-gen-corba-cb)	Insert a large file header and template logic for a CORBA callback module.
ct-test-suite-s	<f12> <f12> M-1</f12></f12>	(pel-erl-ct-test-suite-s)	Insert a large file header and template logic for a test suite
ct-test-suite-l	<f12> <f12> M-2</f12></f12>	(pel-erl-ct-test-suite-l)	Insert a large file header and template logic for a test suite
ts-test-suite	<f12> <f12> M-3</f12></f12>	(pel-erl-ts-test-suite)	Insert a large file header and template logic for a test suite
Tempo Template Tag	• C-c C-M-i	(tempo-complete-tag	Look for a tag and expand it.
Insertion	• <f12> <f12> <f12> • <f11> SPC e <f12> <f12></f12></f12></f11></f12></f12></f12>	&optional SILENT)	Instead of using the <f12> <f12> key bindings above, you can type the template name (shown in the title column like "if", "case", etc) completely or partially and then hit C-c C-M-i. (or <f12> <f12> <f12>) A completion buffer opens up if the template name is incomplete (or empty in which case the buffer lists all available template names). Select the template name and hit RET. Emacs expands the template.</f12></f12></f12></f12></f12>
	match for is determined can match at all. If a single match is found, the If a partial completion or no	be altered with the variable 't e corresponding template is a match at all is found, and SILI	des 'tempo-tags') are searched for a match for the text before the point. The way the string to tempo-match-finder'. If 'tempo-match-finder' returns nil, then the results are the same as no expanded in place of the matching string. ENT is non-nil, the function will give a signal. ion-buffer' is non-nil, a buffer containing possible completions is displayed.
Toggle pel-tempo-mode	<f12> <f12> SPC</f12></f12>	(pel-tempo-mode	Toggle PEL tempo mode on/off. PEL tempo mode activates C-c . and C-c , as well as
See also: • Note The second of the second o	• <f11> SPC e <f12> SPC • <f6> SPC</f6></f12></f11>	&optional ARG)	C-c C and C-c C-, key bindings to navigate across tempo mark hot-spots. When peltempo-mode is active the pel-tempo-mode lighter (‡) is shown on the status bar. The second set are only available when Emacs runs in graphics mode. When a skeleton is inserted via the execution of one of the pel-erl commands above, the
Lucia d		4	pel-tempo-mode is automatically activated.
Jump to next tempo mark	• C-c M-f • C-c . • C-c C	(tempo-forward-mark)	Jump to the next mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key key bindings are only available when pel-tempo-mode is active.
Jump to previous tempo mark	• C-c M-b • C-c , • C-c C-,	(tempo-backward-mark)	Jump to the previous mark in 'tempo-back-mark-list': the location where code must be updated inside the inserted skeleton. • These key binding are only available when pel-tempo-mode is active.
Checking Using either: • flycheck or • flymake See also: • ∑ SyntaxCheck	 Syntax checking for the Erlang programming language can be done with Emacs built-in flymake as well as with the external package flycheck. To activate either set the pel-use-erlang-syntax-check user option is set to either 'use-flycheck or 'use-flymake. By default, the syntax checker is not automatically launched. If you want to start your selected syntax checker as soon as any Erlang file is opened, add 'erlang-mode to the pel-modes-activating-syntax-check user-option. flymake is built-in Emacs. The Emacs erlang package provides erlang-flymake to use with Erlang. PEL automatically installs and activates flycheck when pel-use-goflymake user option is set to 'use-flycheck. Flymake has several customizable variables, which some listed here: The following customization variables determine the exact circumstances whereupon Flymake decides to initiate a check of the buffer: flymake-start-on-flymake-mode: t to start checking when flymake-mode is started. nil to prevent check. flymake-start-syntax-check-on-newline: t to check after insertion or removal of newline char from buffer. nil to prevent check. 		
	The following variable control navigation to next or previous error: • flymake-wrap-around: If non-nil, moving to errors wraps around buffer boundaries. • flymake-diagnostic-types-alist: Alist ((KEY . PROPS)*) of properties of Flymake diagnostic types. See Emacs documentation for more info. The M-n and M-p keys are mapped to flymake commands only when flymake-mode is turned on.		
Activate/deactivate selected syntax checker	<f12> ! <f11> SPC e !</f11></f12>	(pel-erlang-toggle-syntax-checker)	 Toggle the selected Erlang syntax checker mode on/off. The syntax checker activated or deactivated is either <u>flycheck</u> or <u>flymake</u>, as selected by the user-option variable 'pel-use-erlang-syntax-check'. See the required settings above to activate this command and select the syntax checker.
Go to next flymake diagnostic	M-n	(flymake-goto-next-error &optional N FILTER INTERACTIVE)	Move point to the next Flymake diagnostic. • With a prefix arg, skip any diagnostics with a severity less than ':warning'. • Display the error message in the echo line.
Go to previous flymake diagnostic	М-р	(flymake-goto-prev-error &optional N FILTER INTERACTIVE)	Move point to the previous Flymake diagnostic. With a prefix arg, skip any diagnostics with a severity less than ':warning'. Display the error message in the echo line.
Compiling Erlang Code		ned to compile the files. The b	code files to .beam files located in the same directory as the source code. Detected errors are buffer shows the location of error and the error description. The following commands are used to
Compile code	• C-c C-k • <f12> M-c • <m-f12> M-c</m-f12></f12>	(erlang-compile)	Compile Erlang module in current buffer. If buffer visiting file was modified and not saved, prompts the user to save it first. Opens and *erlang* shell, in which the Erlang compile is done with a eshell c() command. The buffer lists the errors. Hitting RET on the error file/line move point to that line in the Erlang file buffer. The RET key is bound to (compile-goto-error &optional EVENT) It's also possible to use the next-error and previous error.
Display compilation output	C-c C-1	(erlang-compile-display)	Display compilation output. • Essentially opens the shell buffer where the last compilation occurred. If that shell was closed nothing can be displayed.
Move to next compile error	• C-x ` • M-g n • M-g M-n	(next-error &optional ARG RESET)	A prefix ARG specifies how many error messages to move; • negative means move back to previous error messages. • Just C-u as a prefix means reparse the error message buffer and start at the first error. This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to previous compile error	• M-g p • M-g M-p	(previous-error &optional N)	Prefix arg N says how many error messages to move backwards (or forwards, if negative). This only shows the result of compilations; it does not report Flycheck reported errors. To use it you must compile the file first.
Move to next compilation or Flycheck detected error	C-c C-n	(edts-code-next-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error. When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.
Move to previous compilation or Flycheck detected error	С-с С-р	(edts-code-previous-issue &optional WRAPPED)	Moves point to the next error in current buffer and prints the error. When Flymake is active, this command can be used as soon as an error is reported, even if the file was not compiled.

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Erlang Shell	Commands to explicitly launce library running in erlang-shell-		nat runs under an Emacs inferior-erlang process controlled by the <u>comint mode</u> from the <u>comint.el</u>	
Open Erlang Shell	C-c C-z	(erlang-shell-display)	Display the existing Erlang shell, or start a new. Available from Erlang mode buffers only.	
Start new Erlang Shell	<f11> z r e</f11>	(erlang-shell)	Start a new Erlang shell. Can be used from any buffer. • The variable 'erlang-shell-function' decides which method to use, default is to start a new Erlang host. It is possible that, in the future, a new shell on an already running host will be started.	
	<f12> z</f12>		 C-c C-z starts the Erlang Shell from the Erlang Mode. <f11> z r is available globally and will work as long as the erl executable is accessible.</f11> Under PEL this command is available only when the pel-use-erlang user option is set to t. 	
Work around to issues in the Erlang Shell	Redundant command echo On some systems the Erla Set the pel-erlang Typing Ctrl-G does not open	When running the Erlang Shell inside Emacs, you may run into some issues. They are listed here along with work-arounds. • Redundant command echo: On some systems the Erlang shell annoyingly echoes each typed command. If this is the case for your system, PEL provides a fix: □ Set the pel-erlang-shell-prevent-echo user option to t. After doing that execute pel-init or restart Emacs. • Typing Ctrl-G does not open the Erlang JCL Command Menu: work-around: type the following instead: C-q C-g RET □ Unfortunately the above workaround does not work when the Erlang shell is launched inside an Emacs vterm shell (see Shells).		
Erlang Shell: Command History	 Erlang shell command his The Erlang shell history of shells are also available. Within an Emacs inferior- 	story file: controlled by Emacs is saved i	issued Erlang shell commands at the shell prompt. nside a file the is restored when opening a new shell: commands from previously opened Erlang set the local shell history.	
Next shell command	M-n	(comint-next-input ARG)	Cycle forwards through Erlang shell input history.	
Previous shell command	м-р	(comint-previous-input ARG)	Cycle backwards through Erlang shell input history, saving input.	
Using Man inside	Emacs provide 2 main comma			
Emacs and support Erlang Man pages	They are: The man command uses WoMan: Browse Unix Ma	the system man utility	n reader available on the shell allowing navigation across man pages and opening hyperlinks. lan" a complete implementation. It has some formatting limitations compared to man but it's Windows.	
See also: <u>▼ Help/Info</u>	To see Erlang man pages using the man command: On most systems the Man pages for Erlang are not available to the man utility and therefore not available for man inside Emacs. There are several ways this can be remedied: One is to set the MANPATH environment variable to include the directory where these files are located. Then man can be used outside and inside Emacs to access Erlang's man pages. For example the following lines can be stored inside a shell script to do this: MANPATH=/usr/local/Cellar/erlang/22.3.4/lib/erlang/man: manpath export MANPATH Another way is to customize the Emacs Man-switches user option variable to something that includes the same directory. This will add the capability of Emacs man to fin the Erlang's man pages without modifying the capabilities of the parent shell. For example, if we want to use the same directory at the above example we need to set the Man-switches which is normally set to nil to the following value: "-M'manpath':/usr/local/Cellar/erlang/22.3.4/lib/erlang/man" The second alternative can be used to add other directories for the man pages of other programming languages while leaving the ability to have several shells that have their own value of MANPATH. That might be very useful for someone that uses different versions of Erlang in a system and needs access to the man pages of different versions of Erlang. It becomes possible to run different shells inside Emacs with each having its own value of MANPATH and therefore providing the man pages from different locations. It is also possible to place all of these directories inside the Man-switches of MANPATH and buses man's ability to view several pages for the same topic. To only see Erlang topics in Man completion:			
About Erlang	directory only. You must also ensure that a whatis file is located in the Erlang man page root directory, otherwise Emacs man completion will not work. See my description on how to create whatis file for local man directory. Using EDTS to access the man pages of the version of Erlang used by various projects: EDTS (see below) supports the ability to download and access man pages of several Erlang versions, tied to your Erlang projects. EDTS provides it's own help command to access sections inside the mane pages, allowing EDTS driven man page access to co-exist with manual man command execution and the techniques described above. PEL supports multiple versions of Erlang and access to their man pages Inside the pel-erlang-environment group, the pel-erlang-man-parent-rootdir user-option can be set to read the man parent directory name from an environment variable. To support the ability to open the man files related to a specific version of Erlang available to the parent OS shell, set the environment variable when you select the version of Erlang available to the OS shell and set the name of the environment variable in the pel-erlang-man-parent-rootdir user-option. See the following Installing Erlang pages of the About Erlang document that describes an setting such an editing environment: Install Erlang OTP Documentation and Man Files Creating whatis files for Erlang man pages Using Specialized OS Shells for Erlang Using PEL with Specialized Shells for Erlang to Edit Erlang			
See also: <u>∑ Menus</u>	Use the following commands • You can also use the toolba		nside Emacs. <f10>) in the Erlang section.</f10>	
Open a man page inside an Emacs buffer See also: Melp/Info Customize	• <f11> ? m • ₩-M</f11>	(man MAN-ARGS)	Using man pages inside emacs is even better than using it from the shell because: • the links are active and can be followed. When the man page describes a directory or file, emacs will open the file or the directory (in direct mode) when pressing RET over the link. • You can navigate easily between sections (n/p will move to the next/previous section) • You can use any of the searches. • You can use any of the options to the man command at the prompt, like the -a option to access all man pages of the same name. Then use M-n and M-p to move from one to the other page, inside the same buffer. • See all keys available in mode, with <f1> m or <f11>? k m. • The man command prompts, using the word at point as the default. • PEL key sequence to customize man: <f11> <f2> E m</f2></f11></f11></f1>	
Open a man page without external man process: woman See also: • <u>Nelp/Info</u> • Customize	<f11> ? w</f11>	(woman &optional TOPIC RE-CACHE)	Open a man page file in Emacs using the woman mode, completely implemented in Emacs Lisp (and therefore without using the external 'man' process). That can be very useful under environments where man is not available (such as basic Windows). PEL key sequence to customize man: <f11> <f2> E w text width, use word at point, etc</f2></f11>	

<u>Description</u>	<u>Keystroke</u>	Function	Note	
EDTS	EDTS - Erlang Developr	nent Tool Suite		
	The commands in the follo	The commands in the following rows require the EDTS external package. PEL activates it when the pel-use-edts user option is set to t. If you want EDTS to start automatically when you open an Erlang file, set pel-use-edts to start-automatically instead of t.		
Erlang Project settings	EDTS is customizable through it edts customization group. With PEL you can open it, with other Erlang specific groups with <f12> <f3>. EDTS also uses an external .edts configuration file to store Erlang project specific settings. See EDTS: Configure your projects. This allows setting the following: project name, node-name, erlang-cookie, lib-dirs, start-command, top-path, dialyzer-plt, app-include-dirs, project-include-dirs, xref-error-whitelist, xref-file-whitelist</f3></f12>			
See also: <u>∑ Sessions</u>			ive on session stored: unfortunately edts does not provide a desktop restore handler. for EDTS which detects edts-mode failures and protect the desktop restoration.	
	If EDTS has not been activated	ated yet, the only EDTS specif	fic key available is <f12> M-SPC to activate it. Once it's activated the other keys are available.</f12>	
Toggle EDTS mode	<f11> M-SPC <f11> SPC e M-SPC</f11></f11>	(edts-mode &optional ARG)	 Turn EDTS mode on or off. EDTS is an easy to set up Development-environment for Erlang. EDTS also incorporates a couple of other minor-modes, currently auto-highlight-mode and auto-complete-mode. They are configured to work together with EDTS but see their respective documentation for information on how to configure their behaviour further. 	
EDTS/Navigation	support shift marking. There	are other commands and key	ve point across Erlang functions. These do not support repetition prefix argument nor they bindings to move across Erlang functions, and PEL support functions that perform the same and sted in the navigation section above.	
Move backward to beginning of previous function	C-c C-d C-b	(ferl-goto-previous- function)	Move backward to the beginning of the previous function skipping all compiler directives. PEL provides a more complete command to move across functions (with or without skipping directives) that push mark and support shift marking. See in the navigation section above.	
Move forward to beginning of next function	C-c C-d C-f	(ferl-goto-next-function)	Move forward to the beginning of the next function skipping all compiler directives. PEL provides a more complete command to move across functions (with or without skipping directives) that push mark and support shift marking. See in the navigation section above.	
EDTS/Cross References			supports navigating in Erlang source code running in the current and remote nodes. n erlang-mode. Their global equivalent is <f11> SPC e . It is not always shown for brevity.</f11>	
Find definition of identifier at point	м	(edts-find-source-under- point)	Goto the source code that: defines the function being called at point or header file included at point. For remote calls, contacts an Erlang node to determine which file to look in, with the following algorithm: • Find the directory of the module's beam file (loading it if necessary). • Look for the source file in: • Directory where source file was originally compiled. • Todo: Same directory as the beam file • Todo: Again with /ebin/ replaced with /src/ • Todo: Again with /ebin/ replaced with /erl/ Otherwise, report that the file can't be found.	
Go back to where M was last issued	М-,	(edts-find-source-unwind)	Unwind back from uses of 'edts-navigate'-commands.	
Lists caller of function at point	• C-c C-d w • <f12> w</f12>	(edts-xref-who-calls)	Pops-up a menu of all callers of the function at point.	
List the callers again	• C-c C-d W • <f12> W</f12>	(edts-xref-last-who-calls)	Redo previous call to edts-who-calls.	
Find a function in the current module	• C-c C-d f • <m-f12> M-f</m-f12>	(edts-find-local-function SET-MARK)	 Find a function in the current module. List local functions in the mini-buffer. Support completion. Move point to selected one. With C-u prefix, push mark before moving point. 	
Find a module in the current project	• C-c C-d F • <m-f12> M-g</m-f12>	(edts-find-global-function)	Find a module in the current project. • List project modules in the mini-buffer. Support completion. Open the file of selected one.	
EDTS/AHS Editing	EDTS supports the automatic highlight symbol mode (AHS). and provides commands to modify the name of the highlighted name in the current function or in all of the buffer. The automatic symbol highlighting mode starts when the cursors stays on a symbol for a period longer than the value identified by the ahs-idle-interval which defaults to 1.0 second. To turn off the AHS editing mode, use a command to move point away from the highlighted area.			
Edit all highlighted symbols in current function	• C-c C-d e • <f12> e</f12>	(edts-ahs-edit-current- function)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current function. • Activates ahs-edit-mode with edts-current-function range-plugin.	
Edit all highlighted symbols in buffer	• C-c C-d E • <f12> E</f12>	(edts-ahs-edit-buffer)	Once a symbol is highlighted, use this command to start editing all instances of this symbol in the current buffer. • Activates ahs-edit-mode with ahs-range-whole-buffer range-plugin.	
Move to the next highlighted symbol	<f12> n</f12>	(ahs-forward)	Once a symbol is highlighted, move forward to the next highlighted symbol.	
Move to the previous highlighted symbol	<f12> p</f12>	(ahs-backward)	Once a symbol is highlighted, move forward to the previous highlighted symbol.	
Move to the originally highlighted symbol	<f12> .</f12>	(ahs-back-to-start)	Once a symbol is highlighted, move back to the symbol that was highlighted at the start of that highlight session.	
Refactor: replace region by call to function and add a new function	• C-c C-d r • <f12> r</f12>	(edts-refactor-extract- function NAME START END)	 Refactor the expression(s) in the region as a function. The expressions are replaced with a call to the new function, and the function itself is placed on the kill ring for manual placement. The new function's argument list includes all variables that become free during refactoring - that is, the local variables needed from the original function. New bindings created by the refactored expressions are *not* exported back to the original function. Thus this is not a "pure" refactoring. This command requires <u>Erlang syntax tools</u> package to be available in the node, version 1.2 (or perhaps later.) 	
EDTS/Man	pages per project, so it is poss	EDTS supports opening documentation for a specific function using the information extracted from Erlang Man pages. EDTS maintains a set of Erlang man pages per project, so it is possible to have several Erlang projects each one with a different version of Erlang and their corresponding man pages. These EDTS commands complement the Emacs standard man commands described above in this table.		
Download, install, select Erlang Man pages	<f12> `</f12>	(edts-man-setup)	Download and install OTP man-pages that will be used by the following 2 EDTS commands.	
Display help for function at point	• C-c C-d h • <f12> h</f12>	(edts-show-doc-under- point)	Find and display the man-page documentation for function under point in a tooltip.	
Find and show man- page info for an Erlang module:function	• C-c C-d H • <f12> H</f12>	(edts-find-doc)	Prompts for a module, then a function. Find and show the man-page documentation for the Erlang module:function.	
EDTS Code Analysis				

<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>	
Compile current buffer	<f12> a c</f12>	(edts-code-compile-and-display)	Compiles current buffer on node related to that buffer's project.	
Run eunit tests	• C-c C-d t • <f12> a t</f12>	(edts-code-eunit &optional COMPILATION-RESULT)	Runs eunit tests for current buffer on node related to that buffer's project.	
Run dialyzer	<f12> a a</f12>	(edts-dialyzer-analyze)	Runs dialyzer for all live buffers related to current buffer either by belonging to the same project or, if current buffer does not belong to any project, being in the same directory as the current buffer's file.	
EDTS/Debug				
Toggle breakpoint	• C-c C-d b • <f12> d b</f12>	(edts-debug-toggle- breakpoint)	Toggle breakpoint on current line.	
List breakpoints	C-c C-d M-b • <f12> d B</f12>	(edts-debug-list- breakpoints &optional SHOW)	Show a listing of all breakpoint on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
List Erlang processes	• C-c C-d M-p • <f12> d p</f12>	(edts-debug-list- processes &optional SHOW)	Show a listing of all processes on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display process list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
Toggle interpretation state of module	• C-c C-d i • <f12> d i</f12>	(edts-debug-toggle- interpreted)	Toggle the interpretation state for module in current buffer.	
List interpreted modules	• C-c C-d M-i • <f12> d I</f12>	(edts-debug-list- interpreted &optional SHOW)	Show a listing of all interpreted modules on all nodes registered with EDTS. If optional argument SHOW is nil or omitted, don't display interpreted list buffer. If it is pop call 'pop-to-buffer', if it is switch call 'switch-to-buffer'.	
EDTS/Erlang Node				
Display EDTS Erlang Node Name	<f12> N</f12>	(edts-buffer-node-name)	Print the node sname of the erlang node connected to current buffer. • The node is either: • The module's project node, if current buffer is an erlang module, or • The buffer's erlang node if buffer is an edts-shell buffer. • The project-node of the buffer that was current buffer before jumping to the current buffer if the file of the current buffer is located outside any project (eg. an "externally" loaded module such as an otp-module or a module loaded by ~/.erlang).	
Start an EDTS controlled Erlang Shell	<f12> x</f12>	(edts-shell &optional PWD SWITCH-TO)	Start an interactive erlang shell.	
Start EDTS server	<f12> X</f12>	(edts-api-start-server)	Starts an edts server-node in a comint-buffer (if not already running).	
Rendering markup embedded in comments		The following commands are used to create images from specific markup code embedded inside Erlang source code comments. This can be useful when using these markup languages to describe UML diagrams or finite-state machines for example.		
Preview UML diagram	<f12> u</f12>	(pel-render-commented-	Render the PlantUML markup embedded in current mode comment.	
from plantUML source in current plantUML region of commented source code See also: M PlantUML	<f11> SCP e u</f11>	plantumi PREFIX &optional POS)	Use region if identified otherwise use PlantUML block at point. Uses prefix (as PREFIX) to choose where to display it: 4 (when prefixing the command with C-u) -> new window 16 (when prefixing the command with C-u C-u) -> new frame. else -> new buffer This can be used inside buffer using any major mode, when PlantUML markup is embedded inside source code comment.	
	Use this in source code to describe your code architecture with PlantUML markup, then generate the UML rendering by moving point inside the PlantUML block and issuing this command. Requires the plantuml-mode external package, activated by pel-use-plantuml user option being non-nil.			
Development Tool	The following commands are u	<u>-</u>		
Show syntactic	C-c C-s	(erlang-show-syntactic-	Show syntactic information for current line.	
information	100 // 0 0 0	information)	Display semantic Lisp data structure in the echo line. Not useful for writing Erlang.	
LSP support: • lsp-mode • erlang ls	The <u>erlang Is</u> Erlang server Electric Erlang Is can be	sp external package APEL a for LSP. You must install this configured using a YAML file	activates it when the pel-use-erlang-is user-option is turned on (set to t). manually. You will need Git, Erlang, rebar3 and make. The instructions are on the web-site. erlang is.config file that must be placed at the root of the Erlang project. erwise you may not be able to take advantage of several of the cross-reference features	
erlang Is required environment		ing executables. See <u>Installin</u> g_ls follow the instruction on t	ng Erlang if you need to learn how to install Erlang and its tools. The erlang Is GitHub page: git clone it, then run make and make install.	
• <u>S Customize</u> Isp-mode	Several Isp-mode settings are customizable in the Isp-mode customization group. With PEL you can access it via <f12> L <f3>. The following settings are probably what you may want to customize: • Isp-log-io : control whether the LSP process is logging its I/O. Useful for debugging LSP support. • Isp-ui-sideline-enable : control whether LSP display information about the current code line. • Isp-ui-doc-enable : control whether LSP display documentation about the current code symbol. You can also use the PEL commands to modify them dynamically using the following commands.</f3></f12>			
Toggle code documentation display	<f11> SCP e L D <f12> L D</f12></f11>	(pel-toggle-lsp-ui-doc &optional LOCALLY)	Toggle the display of code documentation. The initial state is set by the 'Isp-ui-doc-enable' user-option. By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.	
Toggle LSP I/O logging	<f11> SCP e L I <f12> L I</f12></f11>	(pel-toggle-lsp-log-io &optional LOCALLY)	Toggle the logging of LSP I/O. • The initial state is set by the 'Isp-log-io' user-option. • By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.	
Toggle display of information on current line	<f11> SCP e L L <f12> L L</f12></f11>	(pel-toggle-lsp-ui-sideline &optional LOCALLY)	Toggle the display of information of the current line. • The initial state is set by the 'lsp-ui-sideline-enable' user-option. • By default this command impact is global unless an argument prefix is specified, in which case it is applied to the current buffer only.	
Erlang LS Features	Overview of the features provide Code completion Go to Definition Go to Implementation of OTP Behaviours	Edoc support Navigation to Included Files Find/Peek References	LSP Lenses: Isp-avy-lens LSP sideline: enable with: (setq Isp-ui-sideline-enable t) Use M-x Isp-execute-copde-action to trigger quick-fix actions	

Impure to the control of the contr	<u>Description</u>	<u>Keystroke</u>	Function	<u>Note</u>
Comparison Dissipations Control Code Singleton Professional		Signature Suggestions Diagnostics on file open/	Outline of Module Workspace Symbols	Erlang Project-Specific LS Configuration:
Confection all parties Confection all part				
Completion of points of the contraction of the co		 Dialyzer Diagnostics 	 Suggest Type Specs 	placed in the root directory of the project.
Positive property and Posi		EIVIO DIAGIIUSIIUS		
Light particularities Description Descri	<u>Isp-mode features</u>			
Security		company-mode	Use the Isp-headerline	-breadcrumb-mode command to toggle their display. The Isp-headerline-breadcrumb-
- Symbol Indignations - Service-Indicating space (Earls) Service in the cost for of early interesting a part deposit in page-month indignations - Service-Indicating individuals for devotion in page-month indignations - Service-Indicating in the cost of the		Isp-find-definition	Code Lenses . The Erlang	LS configuration provides
December of interestions December of control interestion with Plant Antivolation when places havin-high is furned on Plant Antivolation when places havin-high when places Plant Antivolation when places havin-high is furned on Plant Antivolation when places have been within high antivolation when places in the work place is furned and Plant Antivolation when places have been preferred when places have been placed with high antivolation when places in the work place is discovered when places have been placed when places have been placed with the control of the plant and the places when places have been placed with the plant and p			 server-info: display sor 	ne Erlang LS server info on top of each module. For debug only.
- Competition/input - December by uning beliansing in the control or an important or an import	lan made intermetions			es: show the number of modules implementing a behaviour.
- 2. Filed Ambies - 9 Placements by viring lips (now) - 1. Filed Ambies - 1. Filed A	see also:	11		rhen pel-use-helm-lsp is turned on.
Liber bringing - Company by using tips original in the second or company or control or company or company in the second or company			=	
See Note Section Sec	• <u>∑ Hide/Show</u>			
- Issemedia - Secure Acceptance of the Park of the Acceptance of the Committee of the Commi	LSP key bindings:			
Size above	• Isp-mode	Since the <u>super modifier ke</u>	ey is not always available, it o	an be modified through customization: change the lsp-keymap-prefix value. This can be done
1 1 1 1 1 1 1 1 1 1		_		
Volkidate LSP Volkidate LSP Volkidate performance settings and write report in a "top-performance" buffer.	<u> </u>			
Professionance settings and write-report in a "ap-performance" tolline.		s-1 L		Display the log buffer of WORKSPACE.
Reformat Erlang file s-1 = 9sp-format-buffer Add the server to format this document.	Validate LSP	s-1 d	,	Validate performance settings and write report in a *lsp-performance* buffer.
Part		s-1 = =	(Isp-format-buffer)	Ask the server to format this document.
Remove directory from the workspace blackflist remove PROJECT-ROOT from the workspace blackflist remove PROJECT-ROOT from the list of workspace folders. Remove directory from the flat of workspace folders. Remove PROJECT-ROOT from the list of workspace f		s-1 F a		·
Remove Girectory from the list of workspace of loders Remove PROJECT-ROOT from the list of workspace folders Remove Project From the list of workspace folder	·	c l p b	,	
Find symbol implementation continues. Find symbol implementation and implementation of the symbol at point. Find symbol implementation and implementation of the symbol at point. Find symbol implementation and implementation of the symbol at point. Find symbol implementation and implementation of the symbol at point. Find symbol implementation and implementation of the symbol at point. Find symbols and a continue symbol implementation of the symbol at point. Find symbols and a continue symbol implementation of the symbol at point. Find symbols and a continue symbol implementation of the symbol at point. Find symbols and a continue symbol implementation of the symbol at point. Find symbols and a continue symbol implementation of the symbol at point. Find symbols are found matching PATTERN. Find symbols are found matching patterns. Find symbols are found matching pATTERN. Find symbols are found matching pATTERN. Find symbols are found matching patterns. Find symbols are found matching pATTERN. Find symbo	from the workspace	S-1 F D		Nemove Phodeci-noot from the workspace blacklist.
Efficiency End symbol implementation Estrator Espaid-peak-find-mighementation Estrator Espaid-peak-find-references & espaid Espaid-peak-find-reference & espaid Espaid-peak-find	the list of workspace	s-1 F r		Remove PROJECT-ROOT from the list of workspace folders.
implementation implementation & implementation		s-1 G g	definitions &optional	Find definitions to the IDENTIFIER at point.
Find symbols	implementation	s-1 G i	implementation &optional	Find implementation locations of the symbol at point.
Workspace-symbol PATTERN & Soptional EXTRA PATTERN & Soptional EXTRA	Find references	s-1 G r	references &optional INCLUDE-DECLARATION	Find references to the IDENTIFIER at point.
diagnostics-mode diagnostics-mode Acoptional ARG Toggle LSP protocol logging S-1 T L (lsp-toggle-trace-lo) Toggle client-server protocol logging Toggle current-line S-1 T S (lsp-to-ggle-trace-lo) Toggle code action on roggle code action on modelline Soptional ARG Sop	Find symbols	s-1 G s	workspace-symbol	
Toggle current-line status information Toggle code action on modelling S=1 T S (Isp-ui-sideline-code-actions-mode & Aprilonal ARIG) Toggle code action on modelling S=1 T B (Isp-ui-sideline-code-actions-mode & Aprilonal ARIG) Toggle headline breadcrumbs S=1 T B (Isp-headerline-breadcrumb-mode & Aprilonal ARIG) Toggle headline breadcrumbs S=1 T d (Isp-ui-doc-mode & Aprilonal ARIG) Toggle hover information S=1 T d (Isp-ui-doc-mode & Aprilonal ARIG) Toggle symbol highlighting S=1 T B (Isp-ui-doc-mode & Aprilonal ARIG) Toggle symbol highlighting S=1 T B (Isp-ui-doc-mode & Aprilonal ARIG) Toggle symbol highlighting S=1 T B (Isp-ui-doc-mode & Aprilonal ARIG) S=1 T B (Isp-toggle-symbol-highlighting-hig		s-1 T D	diagnostics-mode	Toggle diagnostics modeline.
Toggle code action on modelline Toggle code action on modelline Toggle code action on modelline Toggle have rinformation Toggle have rinformation S=1 T d (Isp-headerline-breadcrumb-mode & optional ARG) Toggle have rinformation S=1 T d (Isp-id-doc-mode & optional ARG) Toggle have rinformation S=1 T d (Isp-id-doc-mode & optional ARG) S=1 T d (Isp-id-gole-symbol-highlighting) Toggle symbol highlighting Toggle symbol		s-1 T L	(Isp-toggle-trace-io)	
Toggle headline breadcrumbs S-1 T b		s-1 T S		
breadcrumbs breadcrumb-mode & optional ARG) Toggle hover information S-1 T d (Isp-ui-doc-mode & optional ARG) Soptional ARG) Minor mode for showing hover information in child frame. When active, information in child frame. When active, information in child frame. When active information in child frame. When active, information in child frame. When active information in child frame. When active, information in child frame. When active, information in child frame. When active information in child frame. Toggle symbol highlightip. Toggle symbol highlightip. Toggle symbol highlightip.		s-1 T a	actions-mode &optional	Toggle code actions on modeline.
Soptional ARG Soptional ARG*** ***When active, information about symbol at point is shown in a pop-up overlay area. In graphics mode the information has links that can be used to open web-located information. • For small window the information may cover too much code, use this command to toggle in and out of view. Also note that when the point is toward the bottom of a window the information window may not show completely and you may have to scroll your window. **Toggle symbol highlighting** Toggle code-lens **S-1 T 1** (Isp-lens-mode & optional ARG) **Execute code action** **S-1 T 1** (Isp-execute-code-action INPUTO) **In ACTION** **Request code action ACTION.* **Request code-action ferences to symbol at point.* **Highlight all relevant references to the symbol under point.* **Highlight all relevant references to the symbol under point.* **Click LSP lens via avy** **S-1 a 1** (Isp-avy-lens) **Click Isp lens using 'avy' package.* **The code lens must be active. Use s-1 T 1 to activate it if it's not active.* **Apropos search for symbol/regexp** **In a graphics mode the information has links that can be used to search symbol under point.* **Find all meaningful symbols that match PATTERN.* **Can be used to search symbol outside project.* **The result is shown in a "xref" buffer.* **Find definitions of the symbol under point.* **Find definitions of the symbol under point.* **Find definitions of the symbol under point.*		s-1 T b	breadcrumb-mode	When active the list of directories are listed on the header line. In graphics mode these are
highlighting highlight) Toggle code-lens s-1 T 1 (Isp-lens-mode & optional ARG) Toggle code-lens overlays. • Code-lens show information like # times a specific function is referenced. Execute code action s-1 a a (Isp-execute-code-action INPUTO) Execute code action ACTION. • If ACTION is not set it will be selected from 'isp-code-actions-at-point'. • If ACTION is not set it will be selected from 'isp-code-actions-at-point'. • Request codeAction/resolve for more info if server supports. Highlight all relevant references to symbol at point s-1 a h (Isp-document-highlight) Click LSP lens via avy point s-1 a 1 (Isp-avy-lens) Click lsp lens using 'avy' package. • The code lens must be active. Use s-1 T 1 to activate it if it's not active. Apropos search for symbol oludide project. • Can be used to search symbol outside project. • The argument has the same meaning as in 'apropos'. • The result is shown in a 'xref' buffer. Find definitions of s-1 g g (Isp-find-definition &key		s-1 T d		 When active, information about symbol at point is shown in a pop-up overlay area. In graphics mode the information has links that can be used to open web-located information. For small window the information may cover too much code, use this command to toggle in and out of view. Also note that when the point is toward the bottom of a window the
Execute code action S-1 a a (Isp-execute-code-action INPUTO) Highlight all relevant references to symbol at point Click LSP lens via avy Apropos search for symbol/regexp S-1 g a (Isp-avy-lens) Apropos search for symbol/regexp Find definitions of S-1 g g (Isp-find-definition & key) (Isp-find-definition & key) Find definitions of the symbol under point. Code-lens show information like # times a specific function is referenced. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-action and isperver supports. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-action and isperver supports. Execute code action ACTION. It ACTION is not set it will be selected from 'Isp-code-action ACTION. It ACTION is not set it will be selected from 'Isp-code-action ACTION. It ACTION is not set it will be selected f		s-1 T h		Toggle symbol highlighting.
INPUTO INPUTO If ACTION is not set it will be selected from 'Isp-code-actions-at-point'. Request codeAction/resolve for more info if server supports. Highlight all relevant references to symbol at point S-1 a h (Isp-document-highlight) Highlight all relevant references to the symbol under point. Click LSP lens via avy S-1 a l (Isp-avy-lens) Click Isp Iens using 'avy' package. The code Iens must be active. Use s-1 T l to activate it if it's not active. Apropos search for symbol/regexp S-1 g a (xref-find-apropos PATTERN) Find all meaningful symbols that match PATTERN. Can be used to search symbol outside project. The argument has the same meaning as in 'apropos'. The result is shown in a 'xref' buffer. Find definitions of S-1 g g (Isp-find-definition &key) Find definitions of the symbol under point.	Toggle code-lens	s-1 T 1		
references to symbol at point Click LSP lens via avy S-1 a 1 (Isp-avy-lens) Click lsp lens using 'avy' package. • The code lens must be active. Use s-1 T 1 to activate it if it's not active. Apropos search for symbol/regexp S-1 g a (xref-find-apropos PATTERN) Find all meaningful symbols that match PATTERN. • Can be used to search symbol outside project. • The argument has the same meaning as in 'apropos'. • The result is shown in a *xref* buffer. Find definitions of S-1 g g (Isp-find-definition &key) Find definitions of the symbol under point.	Execute code action	s-1 a a		Execute code action ACTION. If ACTION is not set it will be selected from 'lsp-code-actions-at-point'.
The code lens must be active. Use s-1 T 1 to activate it if it's not active. Apropos search for symbol/regexp S-1 g a (xref-find-apropos PATTERN) Find all meaningful symbols that match PATTERN. • Can be used to search symbol outside project. • The argument has the same meaning as in 'apropos'. • The result is shown in a *xref* buffer. Find definitions of S-1 g g (Isp-find-definition &key) Find definitions of the symbol under point.	references to symbol at	s-1 a h	(Isp-document-highlight)	Highlight all relevant references to the symbol under point.
PATTERN) • Can be used to search symbol outside project. • The argument has the same meaning as in 'apropos'. • The result is shown in a *xref* buffer. Find definitions of s-1 g g (Isp-find-definition &key) Find definitions of the symbol under point.	Click LSP lens via avy	s-1 a 1	(Isp-avy-lens)	
		s-1 g a		 Can be used to search symbol outside project. The argument has the same meaning as in 'apropos'.
		s-1 g g		Find definitions of the symbol under point.

Description	<u>Keystroke</u>	Function	<u>Note</u>
Find implementations of symbol at point	s-1 g i	(Isp-find-implementation &key DISPLAY-ACTION)	Find implementations of the symbol under point.
Find references of symbol at point	s-1 g r	(Isp-find-references &optional INCLUDE- DECLARATION &key DISPLAY-ACTION	Find references of the symbol under point. • The result is shown in a *xref* buffer.
Trigger display hover information	s-1 h g	(Isp-ui-doc-glance)	Trigger display hover information popup and hide it on next typing.
Display documentation of symbol at point in *lsp-help*	s-1 h h	(Isp-describe-thing-at- point)	Display the type signature and documentation of the thing at point. • Display help about symbol at point inside a *lsp-help* buffer. • Useful in terminal mode as you can navigate inside the buffer and used other functions to open identified URL references.
Refactor source import	s-1 r o	(Isp-organize-imports)	Perform the source.organizeImports code action, if available.
Rename symbol at point See also: <u>Search/Replace</u>	s-1 r r	(Isp-rename NEWNAME)	Rename the symbol (and all references to it) under point to NEWNAME. For renaming the arguments of a function, the <u>iedit mode</u> is more appropriate. It supports restricting the scope to the current function. See <u>Search/Replace</u>
Disconnect LSP	s-1 w D	(Isp-disconnect)	Disconnect the buffer from the language server.
Describe LSP session	s-1 w d	(Isp-describe-session)	Describes current 'Isp-session'. • Show available tools and the available capabilities • Shows the information inside a LspBrowser buffer.
Shut LSP workspace down	s-1 w q	(Isp-workspace-shutdown WORKSPACE)	Shut the workspace WORKSPACE and the language server associated with it
Restart LSP workspace	s-1 w r	(Isp-workspace-restart WORKSPACE)	Restart the workspace WORKSPACE and the language server associated with it
Activate LSP	s-1 w s	(Isp &optional ARG)	Entry point for the server startup. When ARG is t the lsp mode will start new language server even if there is language server which can handle current language. When ARG is nil current file will be opened in multi folder language server if there is such. When 'lsp' is called with prefix argument ask the user to select which language server to start.
Treemacs support • ∑X Treemacs	provide extra features that help	Erlang development. When	respectively activated by PEL user-options pel-use-treemacs and pel-use-lsp-treemacs , these are activated PEL provides bindings for the lsp-treemacs features. ustomization group. With PEL use f12> w state from an Erlang buffer.
Open LSP Treemacs error list window.	<f12> w e</f12>	(Isp-treemacs-errors-list)	Display an error list window at the bottom of the frame. • The buffer uses the treemacs-mode and supports its commands and key bindings. • See ∑X Treemacs for the list of commands and key bindings. • To close the window, kill its buffer with C-x k
Quick fix	x	(Isp-treemacs-quick-fix &rest ARGS)	If possible, proposes a quick code fix for the error at point.
Open LSP Treemacs symbol window	<f12> w s</f12>	(Isp-treemacs-symbols)	Show symbols view. • To close the window, kill its buffer with C-x k
Open LSP Treemacs references window	<f12> w x</f12>	(Isp-treemacs-references ARG)	Show the references for the symbol at point. Issue from an Erlang buffer. With a prefix argument, select the new window and expand the tree of references automatically. To close the window, kill its buffer with C-x k
Open LSP Treemacs <u>implementations</u> <u>window</u>	<f12> w i</f12>	(Isp-treemacs- implementations ARG)	Show the implementations for the symbol at point. Issue this command from an Erlang buffer. With a prefix argument, select the new window expand the tree of implementations automatically. To close the window, kill its buffer with C-x k
Open LSP Treemacs call hierarchy window	<f12> w c</f12>	(Isp-treemacs-call- hierarchy OUTGOING)	Show the incoming call hierarchy for the symbol at point. • With a prefix argument, show the outgoing call hierarchy. This does not seem to have been implemented for Erlang.
Open LSP Treemacs type hierarchy window	<f12> w t</f12>	(Isp-treemacs-type- hierarchy DIRECTION)	Show the type hierarchy for the symbol at point. With prefix 0 show sub-types. With prefix 1 show super-types. With prefix 2 show both. This is not implemented for Erlang.

Emacs & Erlang - References

Document	Notes
Erlang/OTP	Erlang/OTP home page. This is Erlang's official site.
Erlang versions	Erlang Versions - Version Scheme Erlang Support, Compatibility, Deprecations, and Removal
Erlang/OTP @ Github	Erlang source code
Erlang Community	Links to various topics including how to develop Erlang, learning Erlang, Community mailing lists and chats, contribution, Erlang Issue Tracker, events.
Erlang Mailing Lists	The mailing lists still exist but unfortunately seem to be used less and less.
Erlang/BEAM	Erlang was the first of one of several programming language that runs on the BEAM VM.
Good introduction presentations on Erlang	The soul of Erlang and Elixir Saša Jurić GOTO 2019 A very good presentation that captures the essence of why Erlang is so important. Fast pace. A must see. A great presentation to show people that may be reluctant to use the technology. The Do's and Don'ts of Error Handling Joe Armstrong GOTO 2018
Erlang References	
Erlang Reference Manual User's Guide	The official Erlang language reference. Lists the BIFs (Built-in functions), reserved words, and all language reference info.
Erlang Code Guidelines	
Erlang Programming Rules and Conventions	Official Ericsson AB Erlang guidelines.
Inaka's Erlang Coding Standards & Guidelines	Guideline used at Inaka, published on Github.
EDoc User's Guide	Describes how to document code.

Document	Notes
Erlang Books	There are several printed and online Erlang books. Erlang's FAQ lists several of them. The following lists some extra ones.
Adopting Erlang	A great and recent (2019 and later) online books on Erlang Development that provides information not available in the Erlang introduction books. Describes how to install Erlang, and how to setup editing tools. A must read to setup Erlang development. This is still work in progress as of May 2020. Each page has a date time stamp.
Erlang Information Sites	
How to setup a local Erlang & Elixir dev environment on Mac from source	LambdaCat post on August 2015. Describes how to use Kerl to install Erlang. Also describes tools to install Elixir. However to get kerl on a macOS machine, using Homebrew is simpler.
about-erlang trying-erlang	These are 2 projects of mine, that I am currently building to centralize some information on Erlang. • <u>about-erlang</u> provides general information about Erlang, including: • <u>Learning Erlang</u> , a table with links to resources to learn Erlang. • <u>Installing Erlang</u> , describes various ways to install Erlang on macOS. • <u>Tools for Erlang</u> , describes tools you can use for Erlang development.
Emacs and Erlang Man files	
How to create a local whatis file	Show how to create a missing whatis file for a set of man pages.
The Erlang mode for Emacs (user guide) Erlang mode for Emacs (man page)	On the erlang.org site. Start here. Describes the 2 files (erlang.el and erlang-start.el) provided by the Erlang mode support, how to set them up for various operating systems. Note, however, that PEL provides the setting for you. It also provides an overview of the various features the package provides. • If found bugs in the erlang man page in the Edit- Moving the marker section. 1) it's the point that is moved, not the marker, 2) C-a is not an Emacs key prefix, so their key binding descriptions like C-a M-a and C-a M-e are invalid. Reported as ERL-1314. • There's missing information in this. I will identify later as I find out how to get the system going. One aspect to learn more is related to the various erlang-electric functions and variables. • The variable erlang-electric-commands was set to (erlang-electric-comma erlang-electric-semicolon erlang-electric-gt) at first, which does not include the erlang-electric-newline function. I tried adding erlang-electric-newline and activated it, but that made things worse: the newline was no longer automatic after a -> on a function definition line. • Another issue: inside the OS-level erlang shell, we can tab-completion a module:function string, but that does not work inside the emacs erlang shell.

Emacs tools for Erlang	
EDTS	EDTS: stands for: The Erlang Development Tool Suite. See also: • EDTS Tool Suite - Making Your Life Easier - Thomas Järvstrand presentation @ Youtube • EDTS: • configure your project • One Primary EDTS node • 1 node per open project • To setup an Erlang project: a .edts file in the project: : name "my-project" : otp-path "path/to/otp" : node-name "project-node-name" : lib-dirs '("lib" "deps")
How to install EDTS	Describes some aspects of EDTS and links that may be useful. Lists the requirements. After installing EDTS, I got several compile errors, and had to install the following other modules: - auto-complete (v1.5.1) - have to read doc and configure. And perhaps disable company mode?
Language Server Protocol	Language Server Protocol @ Wikipedia Language Server Protocol Specifications web site Language Server Protocol @ Github
LSP for Erlang	LSP support for Erlang is done using the following: The lsp-mode Emacs Lisp package The erlang ls Erlang server
company-mode ; Modular in-buffer completion framework for Emacs	
Using Tags with Erlang	
Etags with Erlang @ erlang.org	Describes how to use tags with Erlang source code and how to create the TAGS file.
Troubleshooting	This section describes how to solve some of the problems you may encounter with Erlang on Emacs.
How to prevent Erlang shell echo	On some systems the Erlang shell annoyingly echoes every command typed at the shell. The Emacs manual describes a method to prevent shells inside Emacs from echoing and it describes it as affecting Windows systems. None of the Emacs shells on my system that runs on macOS echo commands, but the Erlang shell does. And the described fix works. PEL activates the fix if the pel-erlang-shell-prevent-echo is set to t. To activate after setting it: execute pel-init or restart Emacs.