## **Text Modes**

<u>Operation</u>	<u>Keystroke</u>	Function	Note		
Text Modes			and symbols, and the concept of "words" can be modified to include or exclude underscores and		
See also:  • <u>∑ Search/Replace</u> • <u>∑ Whitespace</u>	hyphens. It supports the following special mode:  • <u>superword-mode</u> that treats words separated by hyphen and underscores as a single entity, useful for programming languages using <u>snake_case</u> like C, C++, Erlang.  • <u>subword-mode</u> that treats sections of <u>camelCase</u> and <u>PascalCase</u> as distinct words. That is useful when editing portions of these longer symbols.  • As of Emacs 23.2 the CC Mode c-subword-mode is obsolete and has been replaced by the more general subword-mode.				
	PEL provides the ability to activate these modes automatically for various major modes by identifying the major modes in the following user option lists:  • pel-modes-activating-superword-mode  • pel-modes-activating-subword-mode  Emacs also has:				
	<ul> <li>several modes that deal with whitespace,</li> <li>drawing modes that allow you to draw in text and navigate over 'void' space</li> <li>different way of handling the concept of marking text in a buffer.</li> </ul>				
			able, starting with the commands to get help in Emacs and customize these features.		
Open this PDF file. See also: <u>∑ Help/Info</u>	<f11> t m <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the local copy of the <u>Text Modes</u> PDF file unless a command prefix (like <b>C-u</b> ) was used. In that case it opens the Github-hosted file instead.		
<u>∑ Customize</u> Text Mode support	<f11> t m <f2></f2></f11>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL cross-reference support: what modes automatically activate superword-mode and subword-mode.  • If OTHER-WINDOW is non-nil (use <b>C-u</b> ), display in other window.		
Switch Insert/Overwrite mode	<pre></pre>	( <b>overwrite-mode</b> &optional ARG)	Toggles the overwrite mode on/off  • With a prefix argument ARG, enable Overwrite mode if ARG is positive, and disable it otherwise.  • ► The <insert> key is not available in macOS keyboards.  • For keyboards with numerical keyboards the <esc><kp-0> is quite close since <kp-0> is often used as the insert key.</kp-0></kp-0></esc></insert>		
Binary file overwrite only mode	<f11> t 0</f11>	(nhexl-overwrite-only-mode &optional ARG)	Minor mode where text is only overwritten. Insertion/deletion is avoided where possible and replaced by overwriting existing text, if needed with 'nhexl-overwrite-clear-byte'.  The nhexl mode must first be activated to edit the file in binary mode.  Requires the <a href="mailto:nhexl-mode">nhexl-mode</a> package.  PEL activates this when the <a href="mailto:pel-use-nhexl">pel-use-nhexl</a> user option is set to t.		
Make Info control text visible/invisible (toggle visible mode)	<f11> t m v</f11>	(visible-mode &optional ARG)	Toggle making all invisible text temporarily visible (Visible mode).  With a prefix argument ARG, enable Visible mode if ARG is positive, and disable it otherwise.  Useful for developing info files, where some characters are not visible by default. Same in Orgmode (for example to show everything, or to show the syntax of links without expanding anything).		
Toggle subword-mode	• <f11> t m b • <f12> M-b</f12></f11>	(subword-mode &optional ARG)	Toggle subword-mode: a minor mode that treats sections of <u>camelCase</u> and <u>PascalCase</u> as distinct words.		
See also: <u>Search/Replace</u>	• <m-f12> M-b</m-f12>	741.6)	<ul> <li>With a prefix argument ARG, enable Subword mode if ARG is positive, and disable it otherwise.</li> <li>PEL provides the <f12> M-b key for the programming language modes where camelCase and PascalCase are popular.</f12></li> </ul>		
Toggle superword-mode	• <f11> t m p</f11>	(superword-mode &optional ARG)	Toggle superword-mode: a minor mode that treats <u>snake_case</u> as one word. In Lisp, '-' and '_' are treated part of words.		
See also: <u>Search/Replace</u>	• <f12> M-p • <m-f12> M-p</m-f12></f12>		<ul> <li>With a prefix argument ARG, enable Superword mode if ARG is positive, and disable it otherwise.</li> <li>PEL provides the <f12> M-p key for the programming language modes where <a href="snake case">snake case</a> is popular (Emacs Lisp, C, C++, Erlang, Python, etc)</f12></li> </ul>		
Toggle sentence separators between 1 or 2 spaces	<f11> t m s</f11>	(pel-toggle-sentence-end)	Toggle definition of end of sentence between 2 and 1 space character (to help text filling). This has an impact on the commands that deal with sentences (navigation such as (backwardsentence) and (forward-sentence), kill such as (kill-sentence) and (backward-kill-sentence).		
Toggle local electric quote mode	<f11> t m '</f11>	(electric-quote-local-mode &optional ARG)	Toggle 'electric-quote-mode' only in this buffer. Useful to insert nicer-looking quote characters.		
Show state of text modes	<f11> t m ?</f11>	(pel-show-text-modes)	Display the state of the various text modes in the mini buffer.		
Text Whitespace Modes	The following Emacs command control how whitespace is shown or hidden. The following commands are also described in the <b>Text Whitespace</b> table.				
Toggle Whitespace Mode See also: Whitespace	• <f11> t m w • <f11> t w m</f11></f11>	(whitespace-mode &optional ARG)	Toggle whitespace visualization (Whitespace mode). With a prefix argument ARG, enable Whitespace mode if ARG is positive, and disable it otherwise. The kind of whitespace visualized is determined by the list variable <b>whitespace-style</b> , <b>whitespace-newline</b> .		
Hide/Show trailing whitespaces See also: ∑ Whitespace	<f11> t w T</f11>	(pel-toggle-show-trailing- whitespace)	Toggle highlight of the trailing whitespaces in current buffer.  Toggles the value of the variable <b>show-trailing-whitespace</b> .		
Hide/Show trailing empty	<f11> t w e</f11>	(pel-toggle-indicate-empty-	Toggle highlight of empty lines.		
lines See also: <b>∑ Whitespace</b>		lines)	Toggles the value of the variable <i>indicate-empty-lines</i> .		
Toggle individual elements of whitespace-style	<f11> t w o</f11>	(whitespace-toggle- options ARG)	<ul> <li>If local whitespace-mode is off, toggle the option given by ARG and turn on local whitespace-mode.</li> <li>If local whitespace-mode is on, toggle the option given by ARG and restart local whitespace-mode</li> </ul>		
See also: Whitespace		mode.  The argument, which is a single character and must be typed following the <f11> t w o, can be:  • f toggle face visualization  • t toggle TAB visualization  • s toggle SPACE and HARD SPACE visualization  • r toggle trailing blanks visualization  • 1 toggle "long lines" visualization  • 1 toggle "long lines" visualization  • n toggle NEWLINE visualization  • n toggle nempty line at bob and/or eob visualization  • c-i toggle indentation SPACEs visualization (via 'indent-tabs-mode')  • I toggle indentation SPACEs visualization  • C-t toggle indentation TABs visualization  • C-a toggle SPACEs after TAB visualization  • C-a toggle SPACEs after TAB: SPACEs visualization  • C-b toggle SPACEs after TAB: TABs visualization  • C-b toggle SPACEs before TAB: SPACEs visualization  • C-b toggle SPACEs before TAB: SPACEs visualization  • C-b toggle SPACEs before TAB: SPACEs visualization  • Show the above list of options.</f11>			

<u>Operation</u>	<u>Keystroke</u>	Function	<u>Note</u>		
Mark and Region See also: <u>&gt; Cut &amp; Paste</u> <u>&gt; Marking</u>	With most editors when you type over a "selected" region, the text in the selection is automatically replaced by the new text. By default Emacs does not behave like this; instead it allows typing text while there is an active a marked region. If you want Emacs behave like other editors and automatically replace the text activate the "delete-selection-mode" with the following command.				
Toggles delete selection mode	<f11> t m d</f11>	(delete-selection-mode)	Toggles delete selection-mode on/off. In delete-selection-mode typing a character while a region is active replaces the entire region with what is typed. By default delete selection-mode is off.		
Drawing ASCII in Emacs	Emacs provides the picture-mode and artist-mode to draw ASCII-based pictures. Both are available when Emacs runs in graphics and terminal mode. However, I have not been able to use artist-mode with the mouse, even with xterm-mouse-mode active: each click just prints an ANSI sequence code. Two modes are available:  • Artist Mode  • Picture Mode  The Picture mode can be very useful to type text in vertical fashion when for example, writing reStructuredText table or writing code in tabular fashion.				
Artist Mode	Although you can get some commands to work in terminal mode, it's best to use artist-mode when running Emacs in graphics mode.				
Toggle artist mode See also: <u>∑ Drawing</u>	<f11> D a</f11>	(artist-mode &optional ARG)	Toggle Artist mode.  • With argument ARG, turn Artist mode on if ARG is positive.  • Artist lets you draw lines, squares, rectangles and poly-lines, ellipses and circles with your mouse and/or keyboard.		
Picture Mode	Emacs supports the picture mode that allow you to move your cursor freely anywhere inside the window, which greatly simplify creating rectangular shapes for tables or even <i>drawing</i> ASCII-art. This work well in both graphics and terminal mode.				
Enter picture mode  See also: Drawing	• <f11> D p • <f11> t p</f11></f11>	(picture-mode)	Switch to Picture mode, in which a quarter-plane screen model is used.  Very useful to type text in vertical fashion when for example, writing reStructuredText table.  Type C-c C-c to exit picture-mode and return to the mode previously used in the buffer.		

## **Text Modes — References**

Topic & Link	Notes
GNU Emacs Manual: Text - Words	
GNU Emacs Manual: Text - Sentences	
GNU Emacs Manual: Text - Paragraphs	
GNU Emacs Manual: Text - Quotation Marks	
GNU Emacs Manual: Modes - Minor Modes	
GNU Emacs Manual: Programs - Other Features Useful for Editing Programs	
GNU Info Manual: Getting Started - Invisible text in Emacs Info	