Unity Composition Reference

PiRho Soft

AnimationClipVariableSource
Description. 1
AnimationPlayer
Description
Public Properties
Public Methods
AnimationType
Description
Values
AssetLocation 4
Description 4
Values
AssignmentOperator
Description
Protected Methods
AudioClipVariableSource
Description6
AudioPlayer
Description
Public Properties
Public Methods
AxisInput
Description8
Public Fields
BarBinding
Description9
Public Fields
BindingAnimationStatus. 10
Description
Public Methods 11
BindingFormatter
Description
Public Fields
Public Methods 12
BindingRoot
Description
Public Fields
Public Properties
Public Methods 13
BoolVariableSource
Description

Constructors	14
BoundsVariableSource	15
Description	15
Constructors	15
BranchNode	16
Description	16
Public Fields	16
BreakNode	17
Description	17
ButtonGraphTrigger	18
Description	18
Public Fields	18
ButtonInput	19
Description	19
Public Fields	19
ButtonState	20
Description	20
Constructors	20
Public Fields	20
ButtonType	21
Description	21
Values	21
ClassMap	22
Description	22
Static Methods	22
ClassMap	23
Description	23
Public Methods	23
ClickGraphTrigger	24
Description	24
CollisionGraphTrigger	25
Description	25
Public Fields	25
CollisionNotifier	26
Description	26
Colors	27
Description	27
Static Fields	27
ColorVariableSource	29
Description	29
Constructors	29

Command
Description
Public Fields
Public Methods 30
CommandEvaluationException
Description
Static Methods
Constructors 32
Public Fields
CommentNode
Description
Public Fields
CompositionManager
Description
Static Fields
Public Properties
Public Methods
ConditionalNode
Description
Public Fields
ConnectionData
Description
ConstrainedStore
Description
Constructors
Public Properties
CreateGameObjectNode
Description
Public Fields
CreateInstructionGraphNodeMenuAttribute
Description
Constructors
CreateScriptableObjectNode
Description
Public Fields
CutoffTransition
Description
Protected Methods
DependentObjectList
Description
DestroyObjectNode

Description	44
Public Fields	44
DisableObjectNode	45
Description	45
Public Fields	45
DissolveTransition	46
Description	46
Public Fields	46
EnableBinding	47
Description	47
Public Fields	47
EnableGraphTrigger	48
Description	48
EnableObjectNode	49
Description	49
Public Fields	49
EnumVariableConstraint	50
Description	50
Public Fields	50
ExitNode	51
Description	51
Expression	52
Description	52
Public Properties	52
Public Methods	52
ExpressionBinding	54
Description	54
Public Fields	54
ExpressionCompilationResult	55
Description	55
Public Fields	55
ExpressionDisplayAttribute	56
Description	56
Public Fields	56
ExpressionEvaluationException	57
Description	57
Constructors	57
ExpressionLexer	58
Description	58
Static Methods.	58
ExpressionNode	59

Description	9
Public Fields	9
ExpressionParseException 6	0
Description 6	0
Constructors 6	0
Public Fields 6	0
ExpressionParser 6	1
Description 6	1
Static Methods6	1
Public Methods 6	1
ExpressionToken 6	3
Description 6	3
Public Fields 6	3
ExpressionTokenType	4
Description 6	4
Values 6	4
Fade Transition 6	6
Description 6	6
Public Fields 6	6
FloatVariableConstraint	7
Description 6	7
Public Fields 6	7
FloatVariableSource	8
Description 6	8
Constructors 6	8
FocusBindingRoot6	9
Description 6	9
Public Fields 6	9
FormatType	0
Description	0
Values	0
GameObjectVariableSource	1
Description	1
GlobalBehaviour75	2
Description	2
Static Properties	2
Static Methods	2
GraphTriggerBinding	3
Description	3
Public Fields	3
HideControlNode	4

Description	. 74
Public Fields	. 74
IAssignableOperation	. 75
Description	. 75
Public Methods	. 75
IClassMap	. 76
Description	. 76
Public Methods	. 76
ICollisionTrigger	. 77
Description	. 77
Public Methods	. 77
ICommand	. 78
Description	. 78
Public Methods	. 78
ICompletionNotifier	. 79
Description	. 79
Public Properties	. 79
ILoopNode	
Description	. 80
ImageBinding	. 81
Description	. 81
Public Fields	. 81
Public Properties	. 81
ImageColorBinding	. 82
Description	. 82
Public Fields	. 82
Public Properties	. 82
InfixOperation	. 83
Description	. 83
Public Properties	. 83
Protected Fields	. 83
Protected Methods	. 83
InputHelper	. 84
Description	. 84
Static Methods	. 84
InputNode	. 87
Description	. 87
Public Fields	. 87
InputNodeButton	. 88
Description	. 88
Public Fields	. 88

39
39
90
90
90
90
90
91
92
92
92
92
93
93
93
93
)4
95
95
95
95
95
8
8
9
9
0
0
0
)1
)1
)1
)2
)2
)2
)3
)3
)3
)4
)4
)4

InstructionSource	105
Description	105
Values	105
InstructionStore	106
Description	106
Static Fields	106
Static Methods	106
Public Properties	106
Public Methods	107
InstructionTrigger	109
Description	109
Public Fields	109
Public Methods	109
Int2VariableSource	110
Description	110
Constructors	110
Int3VariableSource	111
Description	111
Constructors	111
IntBoundsVariableSource	112
Description	112
Constructors	112
InterfaceControl	113
Description	113
Public Fields	113
Public Properties	113
Public Methods	113
Protected Methods	113
IntRectVariableSource	114
Description	114
Constructors	114
IntVariableConstraint	115
Description	115
Public Fields	115
IntVariableSource	116
Description	116
Constructors	116
ISchemaOwner	117
Description	117
Public Properties	117
Public Methods	117

ISequenceNode	118
Description	118
IterateNode	119
Description	119
Public Fields	119
IVariableList	120
Description	120
Public Properties	120
Public Methods	120
IVariableListener	121
Description	121
Public Methods	121
IVariableReset	122
Description	122
Public Methods	122
IVariableStore	123
Description	123
Public Methods	123
ListAdapter	124
Description	124
Static Methods	124
ListBinding	125
Description	125
Public Fields	125
ListVariableConstraint	126
Description	126
Public Fields	126
ListVariableSource	127
Description	127
LoadSceneNode	128
Description	128
Public Fields	128
LogNode	129
Description	129
Public Fields	129
LoopNode	130
Description	130
Public Fields	130
MappedVariableAttribute	131
Description	131
Constructors	131

Public Properties	. 131
MappedVariableStore	. 132
Description	. 132
Public Properties	. 132
Public Methods	. 132
Material Animation	. 133
Description	. 133
Public Fields	. 133
Public Properties	. 133
Protected Methods	. 133
Menu	. 134
Description	. 134
Public Fields	. 134
Public Properties	. 134
Public Methods	. 135
Protected Methods	. 135
MenuInput	. 136
Description	. 136
Public Fields	. 136
Public Methods	. 137
MenuInputPointerAction	. 139
Description	. 139
Values	. 139
MenuItem	. 140
Description	. 140
Public Fields	. 140
Public Properties	. 140
Public Methods	. 140
MenuItemTemplate	. 141
Description	. 141
Public Fields	. 141
Public Properties	. 141
Message	. 142
Description	. 142
Public Fields	. 142
Public Properties	. 142
Public Methods	. 142
MessageBinding	. 143
Description	. 143
Public Fields	
MessageControl	. 144

Description	4
Public Fields	4
Public Properties	4
Public Methods	4
Protected Methods 14	4
MessageInput	:5
Description	:5
Public Fields	:5
Protected Properties	:5
MessageNode	6
Description	6
Public Fields	:6
MockupConnection	:7
Description	.7
Public Fields	.7
MockupConnectionList	8
Description	
MockupGraph	9
Description	9
Public Fields	9
MockupNode	0
Description	0
Public Fields	0
NodeData	1
Description	1
NumberBinding	2
Description	2
Public Fields	2
NumberFormatType	3
Description	3
Values	3
ObjectBindingRoot	4
Description	4
Public Fields	4
ObjectPositioning	5
Description	5
Values	5
ObjectPositioning	6
Description	6
Values	6
ObjectSource	7

Description	157
Values	157
ObjectVariableConstraint	158
Description	158
Public Fields	158
ObjectVariableSource	159
Description	159
Operation	160
Description	160
Public Methods	160
OperatorPrecedence	161
Description	161
Static Fields	161
Static Methods	162
Public Properties	162
Parameter	163
Description	163
Public Fields	163
ParameterList	164
Description	164
PixelateTransition	165
Description	165
Public Fields	165
PlayAnimationNode	166
Description	166
Public Fields	166
PlayAnimationStateNode	167
Description	167
Public Fields	167
PlaybackState	168
Description	168
Values	168
PlayEffect	169
Description	169
Public Fields	169
PlaySoundNode	170
Description	170
Public Fields	170
PlayTimelineNode	171
Description	171
Public Fields	171

PlayTransitionNode	. 172
Description	. 172
Public Fields	. 172
PrefixOperation	. 173
Description	. 173
Public Fields	. 173
Protected Methods	. 173
PrimaryAxis	. 174
Description	. 174
Values	. 174
QuaternionVariableSource	. 175
Description	. 175
Constructors	. 175
ReadOnlyStore	. 176
Description	. 176
RectVariableSource	. 177
Description	. 177
Constructors	. 177
ResetTagNode	. 178
Description	. 178
Public Fields	. 178
ResetVariableList	. 179
Description	. 179
ResetVariablesNode	. 180
Description	. 180
Public Fields	. 180
SceneReference.	. 181
Description	. 181
Static Fields	. 181
Public Fields	. 181
Public Properties	. 181
Public Methods	. 181
SceneReferenceAttribute	. 182
Description	. 182
Public Fields	. 182
SceneSource	. 183
Description	. 183
Values	. 183
SceneSource	. 184
Description	. 184
Values	. 184

SceneVariableStore	185
Description	185
Public Methods	185
ScopedGraph	186
Description	186
Public Fields	186
SelectionControl	187
Description	187
Public Properties	187
Public Methods	188
Protected Methods	188
SelectionNode	189
Description	189
Public Fields	189
SelectionNodeItem	190
Description	190
Public Fields	190
SelectionNodeItemList	191
Description	191
SequenceNode	192
Description	192
Public Fields	192
SerializedDictionary	193
Description	193
Public Methods	193
SerializedList	194
Description	194
SetAnimationParameterNode	195
Description	195
Public Fields	195
SetBindingNode	196
Description	196
Public Fields	196
SetVariableResult	197
Description	197
Values	197
ShowControlNode	198
Description	198
Public Fields	198
ShuffleNode	199
Description	199

Public Fields)
SimpleGraph)
Description)
Public Fields)
SortConditionList	L
Description	L
SortNode	2
Description	2
Public Fields	2
SpriteBinding	3
Description	3
Public Fields	3
Public Properties	3
SpriteColorBinding	1
Description	1
Public Fields	1
Public Properties	1
StartGraphTrigger	5
Description	õ
StopTransitionNode	3
Description	3
Public Fields	3
StoreVariableConstraint	7
Description	7
Public Fields	7
StoreVariableSource	3
Description	3
StringBinding)
Description)
Public Fields)
Public Properties)
Protected Methods 209)
StringVariableConstraint)
Description)
Public Fields)
StringVariableSource	L
Description	L
Constructors	L
TagList	2
Description	2
TextBinding	3

Description	213
Public Fields	213
TextColorBinding	214
Description	214
Public Fields	214
Public Properties	214
TextInputBinding	215
Description	215
Public Fields	215
Public Properties	215
TimeFormatType	216
Description	216
Values	216
TimelineVariableSource	217
Description	217
TimeScaleNode	218
Description	218
Public Fields	218
TransformNode	219
Description	219
Public Fields	219
Transition	221
Description	221
Public Fields	221
Public Methods.	221
Protected Properties	221
Protected Methods	221
TransitionList	222
Description	222
TransitionManager	223
Description	223
Public Properties	223
Public Methods	223
TransitionPhase	224
Description	224
Values	224
TransitionRenderer	225
Description	225
TransitionVariableSource	226
Description	226
UnloadSceneNode	227

Description	227
Public Fields	227
UpdateBindingNode	228
Description	228
Public Fields	228
ValueDefinition	229
Description	229
Static Methods	229
Public Properties	230
Public Methods	230
ValueDefinitionList	231
Description	231
Variable	232
Description	232
Static Properties	232
Static Methods	232
Public Properties	232
VariableBinding	233
Description	233
Static Methods	233
Public Fields	233
Public Properties	234
Public Methods	234
Protected Methods	234
VariableConstraint	236
Description	236
Public Methods	236
VariableConstraintAttribute	237
Description	237
Constructors	237
VariableDefinition	238
Description	238
Public Fields	238
VariableDefinitionList	239
Description	239
VariableHandler	240
Description	240
Static Methods	240
VariableInitializerType	243
Description	243
Values	243

VariableLink	44
Description	44
Public Fields	44
VariableList	45
Description	45
Constructors	45
Public Properties	45
Public Methods	45
VariablePool	46
Description	46
Public Fields	46
Public Methods	46
VariablePoolAsset	47
Description	47
Public Fields	47
Public Methods	47
VariablePoolComponent	48
Description	248
Public Fields	48
Public Methods	48
VariableReference	49
Description	249
Static Fields	49
Public Properties	249
Public Methods 2	249
VariableSchema	251
Description	251
Public Fields	251
Public Properties	251
Public Methods	251
VariableSet	253
Description	253
Public Properties	253
Public Methods	253
VariableSetAsset	255
Description	255
Public Fields	255
Public Properties	255
Public Methods	255
VariableSetComponent	256
Description	256

Public Fields	256
Public Properties	256
Public Methods	256
VariableSource	257
Description	257
Public Fields	257
Public Methods	257
Protected Methods	257
VariableSource	258
Description	258
Public Fields	258
VariableSourceType.	259
Description	259
Values	259
VariableStore	260
Description	260
Public Properties	260
Public Methods	260
Protected Methods	261
VariableType	262
Description	262
Values	262
VariableValue	264
Description	264
Static Properties	264
Static Methods	264
Public Properties	266
Public Methods	269
VariableValueSource	271
Description	271
Constructors	
Public Fields	271
Vector2VariableSource	272
Description	272
Constructors	272
Vector3VariableSource	273
Description	273
Constructors	
Vector4VariableSource	274
Description	274
Constructors	

aitNode	75
Description	75
Public Fields	75
ritableStore	76
Description	76
eldNode2	77
Description	77
Public Fields	77

AnimationClipVariableSource

PiRhoSoft. Composition Engine. Animation Clip Variable Source : Variable Source < Animation Clip > 100 - 1

Description

A VariableSource for AnimationClips.

AnimationPlayer

PiRhoSoft.CompositionEngine.AnimationPlayer: MonoBehaviour, ICompletionNotifier

Description

Add this to any GameObject to provide an interface for playing AnimationClips.

Public Properties

bool *IsComplete* (read only)

This will return true as soon as the animation has completed. If the animation has not yet started, it is not considered complete, so this will return false. If the animation is set to loop, this will always return false.

Public Methods

void PlayAnimation(AnimationClip animation)

Plays animation and returns immediately.

IEnumerator PlayAnimationAndWait(AnimationClip animation)

Plays *animation* and returns an enumerator so it can be run as or from a coroutine. The enumerator will yield until *animation* has completed. If *animation* is set to loop, the enumerator will break immediately and an error will be printed. Call *PlayAnimation* instead to run looping animations.

void Pause()

Pauses playback of the currently running animation.

void Unpause()

Resumes playback of the currently running animation.

AnimationType

PiRhoSoft.CompositionEngine.AnimationType

Description

Defines the available options for the *AnimationMethod* of a TransformNode.

Values

AnimationType *None*

The Transform will be updated immediately without any animation.

AnimationType Speed

Position, rotation, and scale will each animate according to an individually set number of units per second.

AnimationType *Duration*

The animation will take a set amount of time with position, rotation, and scale advancing linearly to their target.

AssetLocation

PiRhoSoft.UtilityEngine.AssetLocation

Description

Defines the settings available to SaveLocation on SceneReferenceAttribute.

Values

AssetLocation None

A scene cannot be created via the SceneReference.

AssetLocation AssetRoot

A scene created via the SceneReference will be placed at the root of the "Assets" directory.

AssetLocation Selectable

The location for a scene created via the SceneReference will be user specified with a "Save As" dialog.

AssignmentOperator

PiRhoSoft. Composition Engine. Assignment Operator: In fix Operation

Description

A base class for InfixOperations that perform assignment of VariableValues.

Protected Methods

VariableValue Assign(IVariableStore variables, VariableValue value)

Call this from a subclass to assign value to a variable on variables based on the result of evaluating the Left operation.

AudioClipVariableSource

PiRhoSoft. Composition Engine. Audio Clip Variable Source: Variable Source < Audio Clip > 100 for the control of the control

Description

A VariableSource for AudioClips.

AudioPlayer

PiRhoSoft.CompositionEngine.AudioPlayer: MonoBehaviour, ICompletionNotifier

Description

Add this to any GameObject to provide an interface for playing AudioClips.

Public Properties

bool *IsComplete* (read only)

This will return true as soon as the sound has completed. If the sound has not yet started, it is not considered complete, so this will return false. If the sound is set to loop, this will always return false.

Public Methods

void PlaySound(AudioClip sound, float volume)

Plays sound at volume and returns immediately.

IEnumerator PlaySoundAndWait(AudioClip sound, **float** volume)

Plays *sound* at *volume* and returns an enumerator so it can be run as or from a coroutine. The enumerator will yield until *sound* has completed. If *sound* is set to loop, the enumerator will break immediately and an error will be printed. Call *PlaySound* instead to run looping sounds.

AxisInput

PiRhoSoft.CompositionEngine.AxisInput : MonoBehaviour, IEventSystemHandler, IPointerDownHandler, IPointerUpHandler

Description

Add this to a Graphic or Collider to set the value of an axis on the InputHelper when the object is clicked or touched.

Public Fields

string AxisName

The name of the axis that is set to AxisValue when the object is clicked or touched.

float AxisValue

The value to set *AxisName* to when the object is clicked or touched.

BarBinding

PiRhoSoft.CompositionEngine.BarBinding: VariableBinding

Description

Add this to an Image to set the *fillAmount* and *color* based on two bound values.

Public Fields

VariableReference AmountVariable

The int or float variable indicating the amount the bar should be filled.

VariableReference TotalVariable

The int or float variable indicating the 'full' amount. Image.fillAmount is set to the result of AmountVariable / TotalVariable.

Gradient FillColors

The color to set Image.color to depending on the current fill amount.

float Speed

If this is greater than 0, the fill amount will animate when it changes. The value specifies the speed of the animation in percent per second. So, for example, a value of 0.1 would cause the bar to change its fill at a rate of 10% every second.

bool *UseScaledTime*

If this is set, *Speed* will be based on scaled time, otherwise it will be based on real time.

BindingAnimationStatus

PiRhoSoft.CompositionEngine.BindingAnimationStatus

Description

Used with VariableBinding to provide feedback for binding updates that are animated or otherwise completed asynchronously. Callers, such as UpdateBindingNode, can pass an instance of this type to the UpdateBinding method and query it to determine when the binding has completed.

VariableBindings, such as BarBinding, use the *Increment* and *Decrement* methods to indicate when an animation has started and finished respectively.

```
using PiRhoSoft.CompositionEngine
using UnityEngine;
namespace PiRhoSoft.CompositionExample
{
    public class ExampleBinding: VariableBinding
        private WaitForSeconds _wait = new WaitForSeconds(1);
        protected override void UpdateBinding(IVariableStore variables,
BindingAnimationStatus status)
            // update the binding
            StartCoroutine(Animate(status));
        }
        private IEnumerator Animate(BindingAnimationStatus status)
            status.Increment();
            yield return _wait; // do animation stuff
            status.Decrement();
    }
}
```

Public Methods

void Reset()

Call this method before passing a BindingAnimationStatus instance to a binding method to reinitialize it.

bool IsFinished()

Call this method to determine if all animations resulting from a bindings update have completed.

void Increment()

Call this method from a VariableBinding implementation to indicate the binding is starting an animation. This can be called multiple times if the binding is performing multiple animations. Each call to *Increment* should have a corresponding call to *Decrement* when the animation completes.

void Decrement()

Call this method from a VariableBinding implementation to indicate the binding has finished an animation. This should be called one time for each time *Increment* is called.

BindingFormatter

PiRhoSoft.CompositionEngine.BindingFormatter

Description

A type to use for fields on text VariableBindings to provide number formatting support.

Public Fields

string Format

The format of the resulting string. Use "{0}" to indicate the location in the string to insert the formatted number.

FormatType Formatting

Whether to format the number as a time or number, or skip formatting altogether.

TimeFormatType TimeFormatting

If *Formatting* is set to *Time*, specifies the format to use for the number.

NumberFormatType NumberFormatting

If Formatting is set to Number, specifies the format to use for the number.

string ValueFormat

If Formatting is set to Time and TimeFormatting is set to Custom or Formatting is set to Number and NumberFormatting is set to Custom, specifies the custom format to use. The syntax is the same as the .net DateTime format strings for Formatting Time and numeric format strings for Formatting Number.

Public Methods

string GetFormattedString(float number)

Returns *number* as a string based on the configured properties. For *Formatting Time number* is interpreted as a number of seconds.

string GetFormattedString(int number)

Returns *number* as a string based on the configured properties. For *Formatting Time number* is interpreted as a number of seconds.

BindingRoot

PiRhoSoft.CompositionEngine.BindingRoot: MonoBehaviour, IVariableStore

Description

Add this to any GameObject to insert a VariableValue into the scene hierarchy that can be accessed by sibling or child VariableBindings.

See the *Binding Roots* section in the *Bindings* topic for more information.

Public Fields

string ValueName

The name for VariableBindings to use to look up Value.

Public Properties

Variable Value (virtual)

The value to return when ValueName is looked up.

Public Methods

IList<string> GetVariableNames() (virtual)

Returns a list with ValueName as its only item.

VariableValue GetVariable(string name) (virtual)

If *name* is *ValueName*, returns *Value*, otherwise calls *GetVariable* on the next BindingRoot up in the object hierarchy. If this is the highest BindingRoot, *DefaultStore* on CompositionManager is used instead.

SetVariableResult SetVariable(string name, VariableValue value) (virtual)

If name is ValueName, returns ReadOnly, otherwise calls SetVariable on the next BindingRoot up in the object hierarchy. If this is the highest BindingRoot, DefaultStore on CompositionManager is used instead.

BoolVariableSource

PiRhoSoft. Composition Engine. Bool Variable Source: Variable Source
 variable So

Description

A VariableSource for bools.

Constructors

BoolVariableSource(bool defaultValue)

Initializes Value to defaultValue

BoundsVariableSource

PiRhoSoft. Composition Engine. Bounds Variable Source : Variable Source < Bounds >

Description

A VariableSource for Bounds.

Constructors

Bounds Variable Source (Bounds default Value)

Initializes Value to defaultValue

BranchNode

PiRhoSoft. Composition Engine. Branch Node: Instruction Graph Node

Description

Add this to an InstructionGraph to run an InstructionGraphNode based on the result of an Expression.

Public Fields

Expression Switch

The Expression to execute to determine which of the InstructionGraphNodes in Outputs to run.

InstructionGraphNodeDictionary Outputs

The set of InstructionGraphNodes to run depending on the result of Switch.

InstructionGraphNode *Default*

If the result of *Switch* is not found in *Outputs*, this *InstructionGraphNode* will be run.

BreakNode

PiRhoSoft. Composition Engine. BreakNode: Instruction GraphNode

Description

Add this to an InstructionGraph to return execution to the closest parent InstructionGraphNode that is an ILoopNode.

ButtonGraphTrigger

PiRhoSoft. Composition Engine. Button Graph Trigger: Instruction Trigger

Description

Add this to any GameObject to run *Graph* (declared on InstructionTrigger) when a button is pressed.

Public Fields

string Button

The name of the button that is checked for presses. The name corresponds to those recognized by InputHelper.

ButtonInput

PiRhoSoft.CompositionEngine.ButtonInput : MonoBehaviour, IEventSystemHandler, IPointerDownHandler, IPointerUpHandler

Description

Add this to a Graphic or Collider to set the pressed state of a button on the InputHelper when the object is clicked or touched.

Public Fields

string ButtonName

The name of the button whose state will be changed when this object is clicked or released.

ButtonState

PiRhoSoft.UtilityEngine.ButtonState: ValueType

Description

Describes the current state of an input on the InputHelper. This could be a virtual button press, mouse button, touch, key, controller button, or controller axis. The properties on this class are set when the state is queried from the InputHelper rather than updating automatically, so the state needs to be looked up every frame to get up to date results.

Constructors

ButtonState(bool pressed, bool held, bool released)

Initializes the state to specific values.

ButtonState(string button)

Initializes the state to the current state of *button* where *button* is a virtual button defined in the InputManager.

ButtonState(KeyCode *key*)

Initializes the state to the current state of key.

ButtonState(int touch)

Initializes the state to the current state of the touch with index *touch*.

Public Fields

bool Pressed

If this is true, the queried input was not pressed on the previous frame and is on the current frame.

bool Held

If this is true, the queried input is currently pressed. This will be true on the first frame (i.e when *Pressed* is true).

bool Released

If this is true, the queried input is no longer pressed but it was pressed on the previous frame.

ButtonType

PiRhoSoft. Composition Engine. Button Type

Description

Defines the available input types for an InputNodeButton in an InputNode.

Values

ButtonType Axis

The InputNodeButton. Name refers to the name of an axis on the InputHelper.

ButtonType Button

The InputNodeButton. Name refers to the name of a button on the InputHelper.

ButtonType *Key*

The InputNodeButton. Key is used instead of InputNodeButton. Name.

ClassMap

PiRhoSoft.CompositionEngine.ClassMap

Description

Manages registration of IClassMaps.

Static Methods

void Add<T>(ClassMap<T> map)

Adds *map* as the IClassMap for the type *T*.

bool Get(Type type, IClassMap map (out))

If the Type *type* has an IClassMap registered, sets *map* to that IClassMap and returns true. Otherwise, returns false.

ClassMap

PiRhoSoft.CompositionEngine.ClassMap<T>: IClassMap

Description

Derive from this class to implement an IClassMap for type *T*. The derived class should be registered with ClassMap.Add in a static constructor or a RuntimeInitializeOnLoadMethod.

Public Methods

IList<string> GetVariableNames() (abstract)

This method should return the list of variable names that are accessible in *GetVariable*.

VariableValue GetVariable(T obj, string name) (abstract)

This method should return a Variable Value containing the value of the property name on obj.

SetVariableResult SetVariable(T obj, **string** name, **VariableValue** value) (abstract)

This method should set the property *name* on *obj* to *value*.

ClickGraphTrigger

PiRhoSoft. Composition Engine. Click Graph Trigger : Instruction Trigger, I Event System Handler, I Pointer Up Handler : Instruction Trigger, I Event System Handler, I Pointer Up Handler : Instruction Trigger, I Event System Handler, I Pointer Up Handler : I Pointer Up Han

Description

Add this to a Graphic or Collider to to run *Graph* (declared on InstructionTrigger) when the object is clicked or touched.

CollisionGraphTrigger

PiRhoSoft. Composition Engine. Collision Graph Trigger: MonoBehaviour, I Collision Trigger

Description

Add this to a Collider to to run an InstructionGrap when a CollisionNotifier informs this object that it has collided.

Public Fields

${\bf Instruction Caller}\ Enter Graph$

The InstructionGraph to run when a CollisionNotifier begins colliding with this object.

InstructionCaller *ExitGraph*

The InstructionGraph to run when a CollisionNotifier stops colliding with this object.

CollisionNotifier

 $PiRhoSoft. Composition Engine. Collision Notifier: {\color{blue}MonoBehaviour}$

Description

Add this to a Collider to notify an ICollisionTrigger when this object has started or stopped colliding with it.

Colors

PiRhoSoft.CompositionEngine.Colors

Description

Defines several colors that can be used by InstructionGraphNode.*NodeColor* derivations to indicate the color of the node in the graph editor. Using an appropriate color frome here can improve the consistency in the editor and make it easier to quickly identify the function of a node.

Static Fields

Color Start

The color of the entry point node.

Color Default

The color used for nodes that don't implement InstructionGraphNode.NodeColor.

Color *ExecutionLight*

The color used for nodes that defer execution to other systems.

Color ExecutionDark

The color used for nodes that perform a specific execution process.

Color Animation

The color used for nodes that interact with Unity's animation systems.

Color Sequence

The color used for nodes that perform many actions in a sequence.

Color Loop

The color used for nodes that repeat an action many times.

Color Branch

The color used for nodes that select an action to perform based on some input.

Color Break

The color used for nodes that alter the control flow of the graph.

Color Sequencing

A color used for nodes that are used in making scripted sequences.

Color SequencingLight

A color used for nodes that are used in making scripted sequences.

Color SequencingDark

A color used for nodes that are used in making scripted sequences.

Color Interface

A color used for nodes that interact with the user interface.

Color InterfaceLight

A color used for nodes that interact with the user interface.

Color *InterfaceDark*

A color used for nodes that interact with the user interface.

Color InterfaceCyan

A color used for nodes that interact with the user interface.

Color InterfaceTeal

A color used for nodes that interact with the user interface.

ColorVariableSource

PiRhoSoft. Composition Engine. Color Variable Source: Variable Source < Color >

Description

A VariableSource for colors.

Constructors

 $\textbf{ColorVariableSource}(\textcolor{red}{\textbf{Color}}\ \textit{defaultValue})$

Initializes Value to defaultValue

Command

PiRhoSoft.CompositionEngine.Command: ScriptableObject, ICommand

Description

Defines an Expression that can be called from other Expressions.

See the *Writing Custom Commands* topic for more information.

Public Fields

string Name

The name to use in an Expression to run this command.

ParameterList Parameters

The list of CommandParameters that should be passed to the command.

Expression Expression

The Expression that is evaluated when this command is called.

Public Methods

VariableValue Evaluate(IVariableStore variables, string name, List<Operation> parameters)

Validates *parameters* against the types defined in *Parameters* and, if valid, evaluates *Expression*. The result of executing *Expression* is returned. If the *parameters* are not valid, a CommandEvaluationException will be thrown. If execution of *Expression* fails, an ExpressionEvaluationException will be thrown.

CommandEvaluationException

PiRhoSoft.CompositionEngine.CommandEvaluationException: Exception

Description

The Exception type that is thrown during execution of Commands.

Static Methods

CommandEvaluationException WrongParameterCount(string *commandName*, **int** *got*, **int** *expected*)

Returns an exception that can be thrown to indicate the command *commandName* was passed an incorrect number of parameters (*got*) when an exact amount (*expected*) is expected.

CommandEvaluationException WrongParameterCount(string *commandName*, **int** *got*, **int** *expected1*, **int** *expected2*)

Returns an exception that can be thrown to indicate the command *commandName* was passed an incorrect number of parameters (*got*) when one of two amounts (*expected1* or *expected2*) were expected.

CommandEvaluationException WrongParameterRange(string commandName, int got, int expectedMinimum, int expectedMaximum)

Returns an exception that can be thrown to indicate the command *commandName* was passed a number of parameters (*got*) outside of an expected range (*expectedMinimum* and *expectedMaximum*)

CommandEvaluationException TooFewParameters(string commandName, int got, int expected)

Returns an exception that can be thrown to indicate the command *commandName* was passed fewer parameters (*got*) than expected (*expected*).

CommandEvaluationException TooManyParameters(string commandName, int got, int expected)

Returns an exception that can be thrown to indicate the command *commandName* was passed more parameters (*got*) than expected (*expected*).

CommandEvaluationException WrongParameterType(string commandName, int index, VariableType got, VariableType expected)

Returns an exception that can be thrown to indicate the command *commandName* was passed a parameter at index *index* with the type *got* instead of the type *expected*.

CommandEvaluationException WrongParameterType(string commandName, int index, VariableType got, VariableType expected1, VariableType expected2)

Returns an exception that can be thrown to indicate the command *commandName* was passed a parameter at index *index* with type *got* instead of either of the types *expected1* or *expected2*.

CommandEvaluationException WrongParameterType(string commandName, int index, VariableType got, VariableType[] expected)

Returns an exception that can be thrown to indicate the command *commandName* was passed a parameter at index *index* with type *got* instead of any of the types in *expected*.

Constructors

CommandEvaluationException(string command, **string** error)

Creates an exception indicating the command command failed with error error.

CommandEvaluationException(string command, **string** errorFormat, **Object[]** arguments)

Creates an exception indicating the command *command* failed with error built from *errorFormat* formatted with *arguments*.

Public Fields

string Command

The name of the Command that threw this exception.

CommentNode

PiRhoSoft. Composition Engine. Comment Node: Instruction Graph Node

Description

Add this to an InstructionGraph to add notes in the editor. This InstructionGraphNode has no outputs or runtime functionality.

Public Fields

string Comment

The text of the comment that will be displayed directly in the graph window.

CompositionManager

PiRhoSoft.CompositionEngine.CompositionManager: GlobalBehaviour<CompositionManager>

Description

Globally manages execution of Instructions. A single instance of this MonoBehaviour will be created automatically and can be accessed from the static *Instance* property.

Static Fields

string GlobalStoreName

The name to use to access *GlobalStore* from *DefaultStore* or any <u>InstructionStore</u>.

string SceneStoreName

The name to use to access SceneStore from DefaultStore or any InstructionStore.

string CommandFolder

The name of the folder that any custom Commands are placed in. By default this is "Commands". All folders with this name that are inside a folder called "Resources" will be loaded when the CompositionManager is created.

bool LogTracking

When this is true, information gathered in editor builds about the execution of Instructions will be logged to the console. This will include the number of enumerator iterations, the number of frames, and the amount of time it took to complete execution of each Instruction. The <<topics/graphs-5.html,Watch Window> in the editor exposes this variable as a toggle.

Public Properties

IVariableStore DefaultStore (read only)

An IVariableStore that exposes *GlobalStore* under the name *GlobalStoreName* and *SceneStore* under the name *SceneStoreName*.

VariableStore GlobalStore (read only)

An IVariableStore that stores user defined values which can be arbitrarily added, changed, and removed.

SceneVariableStore *SceneStore* (read only)

An IVariableStore implementation that allows scene objects to be looked up by name.

Public Methods

void RunInstruction(Instruction instruction, VariableValue context)

Runs an Instruction, usually an InstructionGraph without setting any inputs other than *context* or reading any outputs.

void RunInstruction(InstructionCaller caller, IVariableStore store, VariableValue context)

Runs an Instruction, usually an InstructionGraph, reading the inputs specified in *caller* from *store* to an InstructionStore that is passed to the instruction, and reading the outputs from that InstructionStore to *store* when *caller* has completed.

Read more about Instruction inputs and outputs in the Instruction Store topic.

ConditionalNode

 $PiRhoSoft. Composition Engine. Conditional Node: \underline{Instruction Graph Node}$

Description

Add this to an InstructionGraph to run an InstructionGraphNode based on the result of a conditional Expression.

Public Fields

InstructionGraphNode OnTrue

If *Condition* evaluates to true, this node will run.

InstructionGraphNode OnFalse

If *Condition* evaluates to false, this node will run.

Expression Condition

The expression to execute to determine which InstructionGraphNode should run. The expression should return a Bool, otherwise an error will be logged.

ConnectionData

PiRhoSoft. Composition Engine. Connection Data

Description

Stores data about a connection between two InstructionGraphNodes. This is managed automatically by the editor and can be ignored.

ConstrainedStore

PiRhoSoft. Composition Engine. Constrained Store: Writable Store, IS chema Owner

Description

Holds a set of Variables that are defined in a VariableSchema.

Constructors

ConstrainedStore(VariableSchema schema)

Adds the variables defined in *schema* to this store.

Public Properties

VariableSchema Schema (read only)

The VariableSchema that was used to initialize this store.

CreateGameObjectNode

PiRhoSoft. Composition Engine. Create Game Object Node: Instruction Graph Node

Description

Add this to an InstructionGraph to create a GameObject from a prefab.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

GameObjectVariableSource Prefab

The prefab to use as a template for the GameObject that will be created.

StringVariableSource ObjectName

The name to assign to the newly created GameObject.

VariableReference ObjectVariable

The variable to assign the newly created GameObject to.

ObjectPositioning Positioning

The way the value of *Position* and *Rotation* should be interpreted.

VariableReference *Object*

When *Positioning* is Relative, specifies the GameObject the created GameObject should be positioned relative to.

VariableReference Parent

When *Positioning* is Child, specifies the GameObject the created GameObject should be added to as a child.

Vector3VariableSource Position

The position at which to place the newly created GameObject.

Vector3VariableSource Rotation

The rotation to set the newly created GameObject to.

CreateInstructionGraphNodeMenuAttribute

PiRhoSoft. Composition Engine. Create Instruction Graph Node Menu Attribute: Attribute

Description

This attribute should be added to custom InstructionGraphNodes to add them to the create list in the graph editor window.

Constructors

CreateInstructionGraphNodeMenuAttribute(string menuName, int order)

The name to use for this InstructionGraphNode in the menu. Submenus will be created for each section of *menuName* that precedes a backslash. *order* specifies the relative order of entries in the lowest submenu.

CreateScriptableObjectNode

 $PiRhoSoft. Composition Engine. Create Scriptable Object Node: \underline{Instruction Graph Node}$

Description

Add this to an InstructionGraph to create a ScriptableObject of the specified type.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

string *ScriptableObjectType*

The AssemblyQualifiedName of the type of object to create. This type should be a concrete type with a default constructor that is derived from ScriptableObject.

VariableReference ObjectVariable

The variable to assign the newly created ScriptableObject to.

CutoffTransition

PiRhoSoft.CompositionEngine.CutoffTransition: Transition

Description

Provides a custom Shader with an interface to fade, distort, and dissolve the screen image over time using an input texture. FadeTransition, DissolveTransition, and DistortTransition derive from this class to provide specific Transition functionality.

Protected Methods

void SetTexture(Texture2D texture)

Sets the *TransitionTexture* property of the material which is used to lookup the animation properties according to the description in the manual.

void SetColor(Color color)

Sets the _Color property of the material.

void SetCutoff(float cutoff)

Sets the _Cutoff property of the material which specifies the portion of the texture that is used as the mask based on the current elapsed time.

void SetFade(float fade)

Sets the _Fade property of the material which specifies the interpolated position between the color from the input texture and the value set to _Color.

void SetDistort(bool distort)

Sets the _Distort property which indicates whether or not the material should distort the input texture based on the R and G channels in _TransitionTexture.

void Setup() (virtual)

Override this in subclasses to set additional material properties. The base implementation sets *TransitionTexture* to Texture2D.blackTexture, *color* to black, and *Distort* to false. *Cutoff* and *Fade* are set in *Process* to the percentage of *Duration* that has elapsed.

DependentObjectList

 $PiRhoSoft. Composition Engine. Dependent Object List: {\tt SerializedList} {\tt <GameObject} {\tt >}$

Description

Used by InterfaceControl to store a list of GameObjects.

DestroyObjectNode

PiRhoSoft. Composition Engine. Destroy Object Node: Instruction Graph Node

Description

Add this to an InstructionGraph to destroy a GameObject.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference *Target*

The object to destroy. The object can be any Object. If it is a MonoBehaviour, the owning GameObject will be destroyed.

DisableObjectNode

PiRhoSoft. Composition Engine. Disable Object Node: Instruction Graph Node

Description

Add this to an InstructionGraph to deactivate a GameObject or disable a Behaviour or Renderer.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference *Target*

The object to deactivate. If the object is a GameObject it will be deactivated, if it is a Behaviour it will be disabled, and if it is a Renderer it will be disabled (effectively made invisible).



To deactivate a GameObject from a Component reference use as GameObject (see the Accessing Variables topic).



If the object is already inactive or disabled there will be no effect.

DissolveTransition

 $PiRhoSoft. Composition Engine. Dissolve Transition: {\color{blue}Cutoff Transition}$

Description

Performs a dissolve effect to or from a solid color from or to the rendered scene using a custom texture or perlin noise.

Public Fields

Color Color

The Color to dissolve the screen to.

Texture2D *Texture*

The input Texture that gives the dissolve pattern. If this is null, a texture filled with perlin noise will be generated and used.

Vector2Int *TextureSize*

If *Texture* is null, the size of the *Texture* to generate.

float NoiseScale

If *Texture* is null, the scale value of the perlin noise generated as the *Texture*.

EnableBinding

PiRhoSoft.CompositionEngine.EnableBinding: VariableBinding

Description

Add this to any GameObject to enable or disable a GameObject, Behaviour, or Renderer based on the result of an Expression.

Public Fields

Object Object

The GameObject, Behaviour, or Renderer to enable or disable based on Condition.

Expression Condition

The Expression to evaluate when updating the binding. If this evaluates to true, *Object* will be enabled otherwise it will be disabled (if it is not already).

EnableGraphTrigger

PiRhoSoft. Composition Engine. Enable Graph Trigger: Instruction Trigger

Description

Add this to any GameObject to to run an InstructionGrap when the object is enabled.

EnableObjectNode

PiRhoSoft. Composition Engine. Enable Object Node: Instruction Graph Node

Description

Add this to an InstructionGraph to activate a GameObject or enable a Behaviour or Renderer.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference *Target*

The object to activate. If the object is a GameObject it will be activated, if it is a Behaviour it will be enabled, and if it is a Renderer it will be enabled (effectively made visible).



To activate a GameObject from a Component reference use as GameObject (see the Accessing Variables topic).



If the object is already active or enabled there will be no effect.

EnumVariableConstraint

 $PiRhoSoft. Composition Engine. Enum Variable Constraint: {\color{blue}Variable Constraint}$

Description

Specifies the enum type for VariableValues using this constraint.

Public Fields

Type *Type*

The enum type.

ExitNode

PiRhoSoft. Composition Engine. ExitNode: Instruction GraphNode

Description

Add this to an InstructionGraph to force the currently running branch of the graph to exit and stop running.

Expression

PiRhoSoft.CompositionEngine.Expression

Description

Add this as a field on a class to provide an interface for specifying simple, repeatable operations in the editor. The full expression syntax and a guide on writing and using expressions can be found in the Expressions topic.

Public Properties

ExpressionCompilationResult CompilationResult (read only)

This will hold the result of the most recent expression compilation. If *HasError* is true, this can be queried to retrieve more information about the error. That same information will be visible in the editor when viewing the expression, and any expressions that are loaded with an invalid statement will have this information logged.

Operation LastOperation (read only)

The last Operation that was evaluated when evaluating the expression. If an ExpressionEvaluationException is thrown, this will be the Operation that was being evaluated when the error occurred. If the evaluation is successful this will hold the last Operation in the expression.

bool IsValid (read only)

This will be true if *Statement* has been set and was parsed successfully.

bool *HasError* (read only)

This will be true if *Statement* has been set but failed to parse correctly.

string *Statement* (read only)

The statement containing the text of the expression.

Public Methods

ExpressionCompilationResult SetStatement(string statement)

Sets Statement to statement and attempts to parse it. The parse result is returned.

void GetInputs(IList<VariableDefinition> inputs, string source)

Analyzes the expression to determine the variables that are being accessed on the variable store identified with name *source* and adds them to *inputs*.

void GetOutputs(IList<VariableDefinition> outputs, string source)

Analyzes the expression to determine the variables that are being set on the variable store identified with name *source* and adds them to *outputs*.

VariableValue Execute(Object context, IVariableStore variables)

Evaluates the expression using *Evaluate* and catches any <u>ExpressionEvaluation</u> or <u>CommandEvaluation</u> exceptions that are thrown and logs them. *context* should be the object that owns the expression and is passed along to the log.

VariableValue Execute(Object context, IVariableStore variables, VariableType expectedType)

Evaluates the expression using *Evaluate* and catches any <u>ExpressionEvaluation</u> or <u>CommandEvaluation</u> exceptions that are thrown and logs them. Additionally, the result is checked to ensure it has the <u>VariableType</u> expectedType and an error is logged if it does not. *context* should be the object that owns the expression and is passed along to the log.

VariableValue Evaluate(IVariableStore variables)

Evaluates the expression using *variables* as the root store for resolving VariableReferences. The return value is the result of the last statement in the expression. If an error is encountered an ExpressionEvaluation or CommandEvaluation exception will be thrown.

ExpressionBinding

PiRhoSoft.CompositionEngine.ExpressionBinding: StringBinding

Description

Add this to a TextMeshPro to set the text to the result of an Expression.

Public Fields

BindingFormatter Formatting

Specifies how the result of *Expression* should be formatted. This is only relevant if *Expression* results in an Int or Float Variable.

Expression Expression

The *Expression* to evaluate when the binding is updated. The result will be applied to the sibling TextMeshPro component. If the result is an Int or Float it will be formatted according to *Formatting*. If it is a string, it will be used directly. If it is any other type, ToString() will be used.

ExpressionCompilationResult

PiRhoSoft. Composition Engine. Expression Compilation Result

Description

Stores the results of compiling an Expression.

Public Fields

bool Success

true if the Expression was compiled successfully.

int Location

If compilation failed, the index in the source text where the error was encountered.

string Token

If compilation failed, the text of the token in the source text where the error was encountered.

string Message

If compilation failed, a message giving details about why it failed.

ExpressionDisplayAttribute

 $PiRhoSoft. Composition Engine. Expression Display Attribute: {\tt PropertyAttribute}$

Description

Apply this to an Expression field to customize the way the editor displays the Expression. If an Expression is not given this attribute, it is interpreted as if all the following properties have been set to their default value.

Public Fields

bool Foldout

If this is true the expression will be expandable and collapsable with a foldout. The default is false.

bool FullWidth

If this is true the text area for the Expression will appear beneath its label and expanded to the full width of the inspector. Otherwise it will appear to the right of its label. The default is true.

int MinimumLines

This specifies the minimum number of lines that will be shown in the text area regardless of the length of the Expression. The default is 2.

int *MaximumLines*

This specifies the number of lines the text area will grow to as the Expression gets longer before using a scroll bar. The default is 8.

ExpressionEvaluationException

PiRhoSoft. Composition Engine. Expression Evaluation Exception: Exception

Description

The exception type that is thrown when the evaluation of an Expression fails.

Constructors

ExpressionEvaluationException(string *error*)

Specifies the message that gives more information about why evaluation failed.

ExpressionEvaluationException(string *errorFormat*, **Object[]** *arguments*)

Specifies the message that gives more information about why evaluation failed by formatting *errorFormat* with *arguments*.

ExpressionLexer

PiRhoSoft.CompositionEngine.ExpressionLexer

Description

Converts Expression statements into a series of tokens for processing by the ExpressionParser. Expression handles this process automatically.

Static Methods

List<ExpressionToken> Tokenize(string input)

Converts *input* into a list of tokens that can then be processed by the ExpressionParser. This method will always successfully convert *input*, with any unknown character sequences being given ExpressionTokenType Unknown. It is the responsibility of the ExpressionParser to report these errors as well as errors for invalid token sequences.

void AddConstant(string text, VariableValue value)

Adds the string *text* as a sequence of characters the lexer should identify as a Constant token that is always parser as VariableValue *value*.

void AddKeyword(string text)

Adds the string *text* as a sequence of characters the lexer should identify as an Operator token. The parser should be given an operator with *symbol text* using AddPrefixOperator or AddInfixOperator to define the functionality for the keyword.

VariableValue GetConstant(string *text***)**

Returns the Variable Value that was assigned to text using AddConstant.

ExpressionNode

 $PiRhoSoft. Composition Engine. Expression Node: {\color{blue}Instruction Graph Node}$

Description

Add this to an InstructionGraph to run an Expression.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

Expression Expression

The Expression to run. The result of the Expression is ignored.

ExpressionParseException

PiRhoSoft. Composition Engine. Expression Parse Exception: Exception

Description

The exception type thrown by the ExpressionParser or Operations when encountering an error during parsing.

Constructors

ExpressionParseException(ExpressionToken token, string error)

Specifies *token* as the token that caused the error and sets the exception message to *error*.

ExpressionParseException(ExpressionToken token, string errorFormat, Object[] arguments)

Specifies *token* as the token that caused the error and sets the exception message to *errorFormat* formatted with *arguments*.

Public Fields

ExpressionToken Token

The token at which the error was encountered.

ExpressionParser

PiRhoSoft.CompositionEngine.ExpressionParser

Description

Converts a sequence of ExpressionTokens as interpreted by the ExpressionLexer into an executable Operation.

Static Methods

List<Operation> Parse(string input, **List<ExpressionToken>** tokens)

Performs the conversion. *input* is the entire source text that was sent to the ExpressionLexer for use in printing friendly error messages. *tokens* is the set of tokens interpreted by the ExpressionLexer. If the tokens cannot be parsed, an ExpressionParseException will be thrown.

void AddCommand(string name, ICommand command)

Associates the name *name* with *command*. When this name is encountered in an Expression *command* will be executed. If a Command has already been added with name *name* an error will be logged.

void RemoveCommand(string name)

Removes the Command registered with name *name*. If no Command has been added with name *name* an error will be logged.

ICommand GetCommand(string name)

Returns the Command that was registered with name *name*, or null if no command has been registered with that name.

void AddPrefixOperator<OperatorType>(string symbol)

Associates the string *symbol* with the PrefixOperation *OperatorType*. If a PrefixOperation has already been registered with *symbol* an error will be logged.

void AddInfixOperator<OperatorType>(string symbol, OperatorPrecedence precedence)

Associates the string *symbol* with the InfixOperation *OperatorType*. If an PrefixOperation has already been registered with *symbol* an error will be logged.



A PrefixOperation and InfixOperation can be added with the same symbol.

Public Methods

Operation ParseLeft(OperatorPrecedence precedence)

This should only be called from Operation.Parse implementations to parse the next sequence of tokens with the given *precedence* using left associativity.

Operation ParseRight(OperatorPrecedence)

This should only be called from Operation.Parse implementations to parse the next sequence of

tokens with the given *precedence* using right associativity.

string GetText(ExpressionToken token)

Gets the text that *token* was parsed from.

bool HasText(ExpressionToken token, string text)

Returns true if token has the text text

bool HasToken(ExpressionTokenType type)

Returns true if the next token in the current parse has type *type*.

void SkipToken(ExpressionTokenType type, string expected)

Skips the next token in the current parse. If the next token does not have type *type*, an ExpressionParseException will be thrown. *expected* is the text that was expected at the current location and is used to provide a friendlier error message.

ExpressionToken

PiRhoSoft.CompositionEngine.ExpressionToken

Description

Stores the data for a sequence of characters as identified by the ExpressionLexer.

Public Fields

ExpressionTokenType Type

Specifies how the ExpressionParser should interpret this token.

int Location

The index in the source text that identifies the beginning of this token.

int Start

The index in the source text that identifies the beginning of the relevant text of this token. As opposed to *Location* this will not include any introductory characters and instead identifies the index relevant to the ExpressionParser.

int End

The index in the source text that identifies the beginning of the relevant text of this token. Similarly to *Start*, this will not include any trailing characters in the token that are not relevant to the ExpressionParser.

ExpressionTokenType

PiRhoSoft.CompositionEngine.ExpressionTokenType

Description

Specifies the set of ExpressionTokens the ExpressionLexer and ExpressionParser understand.

Values

ExpressionTokenType Sentinel

Seperates for two distinct statements. This is either; or a line break with multiple of these concatenated into a single token.

ExpressionTokenType Constant

A VariableValue that has been added to the ExpressionLexer with AddConstant.

ExpressionTokenType *Type*

A VariableType for use with testing the type of values.

ExpressionTokenType Int

A literal value that should be interpreted as an int. An int is any continuous sequence of digits.

ExpressionTokenType Float

A literal value that should be interpreted as a float. A float is any continuous sequence of digits that includes a decimal point.

ExpressionTokenType String

A literal value that should be interpreted as a string. A string is a sequence of characters bounded by double quotes (")

ExpressionTokenType Color

A literal value that should be interpreted as a color. A color is a sequence of 6 digits following a hash (#)

ExpressionTokenType *Identifier*

A name that is used to look up variable values. Identifiers can be any sequence of letters, numbers, spaces, or underscores beginning with a letter or underscore.

ExpressionTokenType Command

A name that is used to look up a Command that has been registered with the ExpressionParser using *AddCommand*. A command is an *Identifier* that is followed by an opening paren (().

ExpressionTokenType Operator

An operator that is used to look up a PrefixOperation or InfixOperation that has been registered with the ExpressionParser using AddPrefixOperator or AddInfixOperator. Valid operator characters are any of +-!^*/%<>=\$|?. in any sequence and any character sequence that has been

registered with the ExpressionLexer using AddKeyword.

ExpressionTokenType StartLookup

Indicates the following tokens should be interpreted as part of a variable lookup. This is the [character.

ExpressionTokenType EndLookup

Indicates the following tokens are no longer part of a variable lookup. This is the] character.

ExpressionTokenType StartGroup

Indicates the following tokens should be isolated and evaluated as a group, just as would be done in a math expression. This is the (character.

ExpressionTokenType EndGroup

Ends a group that was started with a *StartGroup* token or a command that was started with a *Command* token. This is the) character.

ExpressionTokenType Separator

Seperates parameters in a *Command* token. This is the , character.

ExpressionTokenType Alternation

This is the character used as the separator for the true and false statements of a ternary expression. This is the : character.

ExpressionTokenType *Unknown*

Any token that does not meet the requirements for one of the preceding types will be given this type.

Fade Transition

 $PiRhoSoft. Composition Engine. Fade Transition: {\color{blue}Cutoff Transition}$

Description

Performs a linear fade to or from a solid color.

Public Fields

Color Color

The color to fade in to or out from.

FloatVariableConstraint

PiRhoSoft. Composition Engine. Float Variable Constraint: Variable Constraint

Description

A VariableConstraint for Float VariableValues that restricts the value to a range.

Public Fields

float Minimum

The smallest value allowed.

float *Maximum*

The largest value allowed.

FloatVariableSource

PiRhoSoft. Composition Engine. Float Variable Source : Variable Source < float > 1000 for the control of the

Description

A VariableSource for Float VariableValues

Constructors

FloatVariableSource(float defaultValue)

Initializes the source to *Type* Value with *Value* _defaultValue.

Focus Binding Root

 $PiRhoSoft. Composition Engine. Focus Binding Root: {\color{red}Binding Root}$

Description

Add this to any GameObject to add the focused item of a Menu to the BindingRoot hierarchy.

Public Fields

Menu Menu

The Menu to query for the currently focused item, which will then be used as *Value* for this BindingRoot.

FormatType

PiRhoSoft.CompositionEngine.FormatType

Description

Defines the types available to set for the *Format* of a BindingFormatter.

Values

FormatType *None*

The BindingFormatter will not apply any formatting and instead return the result of ToString directly.

FormatType *Time*

The BindingFormatter will apply formatting while interpreting the input value as a TimeSpan

FormatType Number

The BindingFormatter will apply formatting while interpreting the input value as a number

GameObjectVariableSource

 $PiRhoSoft. Composition Engine. Game Object Variable Source: {\tt Variable Source < Game Object > the Composition of the Composi$

Description

A VariableSource for Object VariableValues that hold GameObjects.

GlobalBehaviour

PiRhoSoft.UtilityEngine.GlobalBehaviour<T>: MonoBehaviour

Description

Derive from this class to ensure only a single instance of the derived class will be created. The instance will be created on demand (when *Instance* is first accessed) and should not be added to a scene.

Pass the derived class itself as T: public class CompositionManager GlobalBehaviour<CompositionManager> $\{\}$

Static Properties

bool Exists (read only)

Checks if the instance has been created.

T Instance (read only)

The instance of the class. This will create the instance if it hasn't been already.

Static Methods

void Destroy()

Destroys the created instance.

GraphTriggerBinding

PiRhoSoft.CompositionEngine.GraphTriggerBinding: VariableBinding

Description

Add this to any GameObject to run an InstructionGraph when a variable value changes.

Public Fields

InstructionCaller *Graph*

The graph to run when the value referenced by *Variable* changes.

VariableReference Variable

The variable to watch for changes.

HideControlNode

 $PiRhoSoft. Composition Engine. Hide Control Node: \underline{Instruction Graph Node}$

Description

Add this to an InstructionGraph to hide an InterfaceControl.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference Control

The InterfaceControl to hide.

IAssignableOperation

PiRhoSoft. Composition Engine. IAs signable Operation

Description

Implement this interface in an Operation subclass to support assigning values when the Operation appears on the left hand side of an assignment.

Public Methods

SetVariableResult SetValue(IVariableStore *variables*, **VariableValue** *value*) (*abstract*) Implement this method to assign *value* to a variable in *variables* and return the result.

IClassMap

PiRhoSoft.CompositionEngine.IClassMap

Description

Implement this interface to expose properties as Variables in a class that is not an IVariableStore. Generally deriving from ClassMap is a better option than implementing this interface directly.

Public Methods

IList<string> GetVariableNames() (abstract)

This method should return the list of variable names that are accessible in *GetVariable*.

VariableValue GetVariable(object obj, string name) (abstract)

This method should return a Variable Value containing the value of the property name on obj.

SetVariableResult SetVariable(Object *obj*, **string** *name*, **VariableValue** *value*) (*abstract*) This method should set the property *name* on *obj* to *value*.

ICollisionTrigger

PiRhoSoft. Composition Engine. I Collision Trigger

Description

Implement this interface on a MonoBehaviour to allow an object to respond to collisions between itself and a CollisionNotifier.

Public Methods

void Enter() (abstract)

Called by a CollisionNotifier to indicate a collision has started.

void Exit() (abstract)

Called by a CollisionNotifier to indicate a collision has ended.

ICommand

PiRhoSoft.CompositionEngine.ICommand

Description

Implement this interface to create a custom command that can be added to the ExpressionParser and ultimately called from Expressions.

Public Methods

VariableValue Evaluate(IVariableStore *variables*, **string** *name*, **List<Operation>** *parameters*) (abstract)

Implement this method to perform the command's function. *variables* contains the IVariableStore that should be passed to each Operation in *parameters* when evaluating them as well as to look up any custom variables. *name* is the name that was used to call this command and *parameters* is the parsed expressions that were passed to the command.

Throw a CommandEvaluationException to indicate any errors in execution.

ICompletionNotifier

PiRhoSoft. Composition Engine. I Completion Notifier

Description

Implement this interface in a MonoBehaviour subclass to add support for using the behaviour as an *Effect* for a PlayEffectNode in an InstructionGraph.

Public Properties

bool *IsComplete* (read only) (abstract)

This property should return true when the effect has completed.

ILoopNode

PiRhoSoft.CompositionEngine.ILoopNode

Description

Implement this interface in an InstructionGraphNode subclass to inform an InstructionGraph that the node should be run repeatedly. The graph will continue to run the node until the node does not call InstructionGraph.GoTo (or calls GoTo(null)) or a BreakNode is encountered.

ImageBinding

PiRhoSoft. Composition Engine. Image Binding: Variable Binding

Description

Add this to an Image to bind *sprite* to a variable.

Public Fields

VariableReference Variable

The Sprite that should be set on Image.

Public Properties

Image Image (read only)

The Image that will be updated.

ImageColorBinding

PiRhoSoft.CompositionEngine.ImageColorBinding: VariableBinding

Description

Add this to an Image to bind color to a variable.

Public Fields

VariableReference Variable

The Color that should be set on *Image*.

Public Properties

Image Image (read only)

The Image that will be updated.

InfixOperation

PiRhoSoft.CompositionEngine.InfixOperation: Operation

Description

Derive from this class to implement an Operations that has a left and right side.

Public Properties

OperatorPrecedence *Precedence* (read only) (abstract)

The OperatorPrecedence of the operation relative to other operations.

Protected Fields

Operation Left

The Operation that makes up the left hand side.

string Symbol

The symbol identifying this Operation.

Operation Right

The Operation that makes up the right hand side.

Protected Methods

ExpressionEvaluationException TypeMismatch(VariableType *left*, **VariableType** *right*)

Creates an exception to be thrown by the caller indicating the Operation cannot operate on values with types *left* and *right*.

InputHelper

PiRhoSoft.UtilityEngine.InputHelper

Description

Provides a static interface for accessing user input in a consistent manner independent of how the input was set up.

Static Methods

void LateUpdate()

This is called by the CompositionManager to update the input state and can be ignored.

void SetButton(string button, bool down)

Performs a virtual press (down = true) or release (down = false) of a button named button. button can be any string, including those defined in InputManager. This is used by ButtonInput to provide on screen control support.

void RemoveButton(string button)

Removes the tracking data for the virtual button named button.

void SetAxis(string axis, float value)

Sets the value of a virtual access named *axis* to *value*. *axis* can be any string, including those defined in InputManager. This is used by AxisInput to provide on screen control support.

void RemoveAxis(string axis)

Removes the tracking data for the virtual axis named axis.

ButtonState GetKeyState(KeyCode *key*)

Returns the ButtonState for the keyboard key key.

bool GetKeyDown(KeyCode key)

Returns true if the keyboard key key is currently pressed.

bool GetWasKeyPressed(KeyCode key)

Returns true if the keyboard key *key* is currently pressed and was not pressed on the previous frame.

bool GetWasKeyReleased(KeyCode key)

Returns true if the keyboard key *key* is not currently pressed and was pressed on the previous frame.

bool GetIsPointerDown()

Returns true if the left mouse button is currently pressed or touch with index 0 is touching the screen

bool GetWasPointerPressed()

Returns true if the left mouse button is currently pressed or touch with index 0 is currently touching the screen but neither was happening on the previous frame.

bool GetWasPointerReleased()

Returns true if the left mouse button or touch with index 0 is not currently pressed and was pressed on the previous frame.

ButtonState GetTouchState(int touch)

Returns the ButtonState for the touch with index touch.

Nullable<TouchPhase> GetTouchPhase(int touch)

Returns the TouchPhase for the touch with index *touch*. If the touch is not currently tracked, null will be returned.

bool GetIsTouching(int touch)

Returns true if the touch with index touch is currently touching the screen.

bool GetTouchStarted(int touch)

Returns true if the touch with index *touch* is currently touching the screen but was not on the previous frame.

bool GetTouchEnded(int touch)

Returns true if the touch with index *touch* is not currently touching the screen but was on the previous frame.

bool IsButtonAvailable(string button)

Returns true if *button* exists either as a virtual button created with *SetButton* or in the InputManager.

ButtonState GetButtonState(string button)

Returns the ButtonState of the virtual button or InputManager axis named *button*. If *button* is defined as both, the virtual button state will be used.

bool GetButtonDown(string button)

Returns true if the virtual button or InputManager axis named button is pressed.

bool GetWasButtonPressed(string button)

Returns true if the virtual button or InputManager axis named button was pressed this frame.

bool GetWasButtonReleased(string button)

Returns true if the virtual button or InputManager axis named button was released this frame.

float GetAxis(string axis)

Returns the value of the virtual axis or InputManager axis named *axis*. If *axis* is defined in both places, the value with the greater magnitude will be returned.

ButtonState GetAxisState(string axis, **float** magnitude)

Returns the ButtonState of the virtual axis or InputManager axis named axis according to the same rules defined in the following 3 methods.

bool GetAxisDown(string axis, **float** magnitude)

Returns true if the value of the virtual axis or InputManager axis named *axis* matches the sign of and is farther from 0 than *magnitude*. If *axis* is defined in both places, the value with the greater magnitude will be used.

bool GetWasAxisPressed(string axis, **float** magnitude)

Returns true if the value of the virtual axis or InputManager axis named *axis* matches the sign of and is farther from 0 than *magnitude* and wasn't the previous frame. If *axis* is defined in both places, the value with the greater magnitude will be used.

bool GetWasAxisReleased(string axis, **float** magnitude)

Returns true if the value of the virtual axis or InputManager axis named *axis* matched the sign of and was farther from 0 than *magnitude* on the previous frame and isn't this frame. If *axis* is defined in both places, the value with the greater magnitude will be used.

InputNode

PiRhoSoft. Composition Engine. Input Node: Instruction Graph Node

Description

Add this to an InstructionGraph to wait for user input then run an InstructionGraphNode depending on the input.

Public Fields

InputNodeButtonList Buttons

The list of InputNodeButtons that indicate the InstructionGraphNode to advance to when a particular input is triggered.

InputNodeButton

PiRhoSoft.CompositionEngine.InputNodeButton

Description

Holds data for a button or key in an InputNode.

Public Fields

ButtonType Type

The type of input to use for this button.

string Name

The name of the button if *Type* is Button or the name of the axis if *Type* is Axis as defined by the InputHelper.

float Value

If *Type* is Axis, the minimum amount of the axis value for it to be considered pressed. If this value is negative, the axis value must be more negative than this value.

KeyCode Key

If *Type* is Key, the keyboard key for the button.

InstructionGraphNode OnSelected

The InstructionGraphNode to go to when this input is triggered.

Input Node Button List

PiRhoSoft. Composition Engine. Input Node Button List: Serialized List < Input Node Button >

Description

The serializable list of InputNodeButtons in an InputNode.

Instruction

PiRhoSoft.CompositionEngine.Instruction: ScriptableObject

Description

Implements the core functionality for an InstructionGraph or any other asset to allow it to be run by the CompositionManager.

Public Fields

string ContextName

The name to assign to the variable that is passed as *context* to either of the CompositionManager.*Run* methods.

ValueDefinition ContextDefinition

The definition to use to validate the variable passed as *context* to either of the CompositionManager.Run methods. If the definition specifies a MonoBehaviour type and the *context* value is not that behaviour type, it will be converted by attempting to look up a sibling behaviour.

VariableDefinitionList Inputs

The list of definitions for the input variables this instruction expects to be set when called from an InstructionCaller. This list will be automatically populated by the editor and each definition can optionally be set to constrain the corresponding input. If the definition is set, the input will be validated at runtime to ensure the correct data was passed, with a message being logged if it is not.

VariableDefinitionList Outputs

The list of definitions for the output variables indicating the values this instruction will set for an InstructionCaller when it has completed. The outputs are not validated because it is not required that they are set by the instruction, but setting these will improve the editor experience.

Public Properties

IVariableStore Variables (read only)

The InstructionStore that was passed to the *Execute* method. This will be null if the instruction is not currently running.

bool *IsRunning* (read only)

This will return true while the *Execute* coroutine is running.

Public Methods

IEnumerator Execute(VariableValue context)

Executes the instruction. When inside an existing coroutine this can be called directly as part of

a yield return statement. When outside a coroutine, the CompositionManager. RunInstruction methods should be used.

IEnumerator Execute(InstructionStore variables)

Executes the instruction. When inside an existing coroutine this can be called directly as part of a yield return statement. When outside a coroutine, the CompositionManager.RunInstruction methods should be used.

void RefreshInputs()

Used by the editor to refresh the input list when necessary. This will happen automatically and can be ignored.

void RefreshOutputs()

Used by the editor to refresh the input list when necessary. This will happen automatically and can be ignored.

Protected Methods

void OnEnable() (virtual)

Performs important setup for the instruction. If overridden make sure to call the base implementation.

void OnDisable() (virtual)

Performs important teardown for the instruction. If overridden make sure to call the base implementation.

void GetInputs(IList<VariableDefinition> inputs) (virtual)

Implement this in subclasses to populate the *inputs* list with definitions for values the instruction expects to be available when called.

void GetOutputs(IList<VariableDefinition> outputs) (virtual)

Implement this in subclasses to populate the *outputs* list with definitions for values the instruction will set after it finishes running.

IEnumerator Run(InstructionStore variables) (abstract)

Implement this in subclasses to perform the function of the instruction.

InstructionCaller

PiRhoSoft.CompositionEngine.InstructionCaller

Description

Add this as a field on a MonoBehaviour or ScriptableObject to serve as a bridge between code and an InstructionGraph. This class will automatically manage configuring and applying input and output values to the InstructionGraph and enable full editor support. Read the Running Graphs From Script topic for more information.

Public Properties

Instruction Instruction

The instruction, usually an InstructionGraph, to run when this caller is executed.

IList<InstructionInput> Inputs (read only)

The list of InstructionInputs to add to the InstructionStore when running Instruction.

IList<InstructionOutput> Outputs (read only)

The list of InstructionOutputs to read from the InstructionStore after running Instruction.

bool *IsRunning* (read only)

This will return true when *Instruction* is being executed. *Instructions* that are already running cannot be run again until they have completed.

Public Methods

IEnumerator Execute(IVariableStore store, VariableValue context)

Call this as a Coroutine or from another coroutine to run *Instruction*.

void UpdateVariables()

This is an editor support function.

VariableDefinition GetInputDefinition(InstructionInput input)

This is an editor support function.

VariableDefinition GetOutputDefinition(InstructionOutput output)

This is an editor support function.

InstructionGraph

PiRhoSoft.CompositionEngine.InstructionGraph: Instruction

Description

The main piece of the composition system, implementing all the functionality necessary to manage and execute a set of InstructionGraphNodes. Read the graph topic for a more thorough breakdown of creating and using graphs.

Static Fields

bool IsDebugBreakEnabled

Indicates the editor should pause graph execution when it encounters a breakpoint. This is on (true) by default but can be turned off in the graph editor window to disable all node breakpoints. The breakpoints are not removed, so when this setting is re-enabled, any previously set breakpoints will continue to function.



This setting is saved with EditorPrefs so it will persist across Unity launches on the local machine for all projects.

bool IsDebugLoggingEnabled

Enable this setting to log execution events when running a graph. The events that will be logged are:

- · A branch has started
- · A branch has been manually stopped
- · Execution of a branch has completed
- Execution has paused at a breakpoint or after a step
- A connection has been followed to a new node

The current frame number is printed with the log message to make it easy to determine how many frames a particular node has taken to complete (since they are run as coroutines). Additional profiling and debugging information can be enabled with CompositionManager.LogTracking.



This setting is saved with EditorPrefs so it will persist across Unity launches on the local machine for all projects.

Public Methods

void GoTo(InstructionGraphNode node, string name)

Call this from a node to tell the graph to traverse to *node*. *name* should be the name of the property the node was assigned to for use in log messages.

The following two overloads perform the same task but can be used to provide more information in

log messages when *node* comes from a list (*index* would be the index of *node*) or dictionary (*key* would be the key of *node*).

- void GoTo(InstructionGraphNode node, string name, int index)::
- void GoTo(InstructionGraphNode node, string name, string key)::

void Break()

Call this from a node to tell the graph to return to the closest node in the call stack that is an ILoopNode. The BreakNode calls this.

void BreakAll()

Call this from a node to tell the graph to stop running is current branch.

Protected Methods

IEnumerator Run(InstructionStore variables, InstructionGraphNode root, string source)

Editor Support

The following properties and methods are exposed for use by the editor and only available in editor builds. They can be ignored.

- Action<InstructionGraph, InstructionGraph> OnBreakpointHit::
- Vector2 StartPosition::
- InstructionGraphNodeList Nodes (read only)::
- PlaybackState DebugState (read only)::
- bool CanDebugPlay (read only)::
- bool CanDebugPause (read only)::
- bool CanDebugStep (read only)::
- bool CanDebugStop (read only)::
- void DebugPlay()::
- void DebugPause()::
- void DebugStep()::
- void DebugStop()::
- int IsInCallStack(InstructionGraphNode node)::
- bool IsInCallStack(InstructionGraphNode node, string source)::
- bool IsExecuting(InstructionGraphNode node)::
- void GetConnections(NodeData data) (virtual)::
- void SetConnection(ConnectionData connection, InstructionGraphNode target) (virtual)::

InstructionGraphNode

PiRhoSoft.CompositionEngine.InstructionGraphNode: ScriptableObject

Description

Derive from this class to implement a custom node for use in an InstructionGraph.

Public Fields

string Name

The name of the node. This is used to display the node in the graph editor and in log messages to identify the node the message is related to.

Vector2 GraphPosition

Used by the editor to store the location of the node in the graph editor.

bool IsBreakpoint

Used by the editor to indicate whether this node has been marked as a breakpoint in the graph editor for debugging.

Public Properties

Color NodeColor (read only) (virtual)

The color the node should be displayed with in the graph editor. By default this will use InstructionGraphNode.Colors.Default but can be customized as a way to visually differentiate nodes in the graph editor.

Public Methods

IEnumerator Run(InstructionGraph graph, InstructionStore variables, int iteration) (abstract)

Implement this method in derived classes to perform the execution of the node. Read the graphs topic for a complete overview of writing and using custom nodes.

Resolve

This collection of methods will lookup the value referenced by a VariableReference or VariableSource. The resolved value is set to the ouput parameter *result* and the return value will indicate whether the value was resolved successfully. The *variables* parameter should be the *variables* parameter passed to the *Run* method. If the resolution fails, either due to the variable not being found or it being an invalid type, a warning will be printed to the Console.

- bool Resolve(IVariableStore variables, VariableValueSource source, VariableValue result (out))
- bool Resolve(IVariableStore variables, VariableReference reference, VariableValue result (out))
- bool Resolve(IVariableStore variables, BoolVariableSource source, bool result (out))
- bool Resolve(IVariableStore variables, VariableReference reference, bool result (out))::

- bool Resolve(IVariableStore variables, IntVariableSource source, int result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, int result (out))::
- bool Resolve(IVariableStore variables, FloatVariableSource source, float result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, float result (out))::
- bool Resolve(IVariableStore variables, Int2VariableSource source, Vector2Int result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector2Int result (out))::
- bool Resolve(IVariableStore variables, Int3VariableSource source, Vector3Int result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector3Int result (out))::
- bool Resolve(IVariableStore variables, IntRectVariableSource source, RectInt result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, RectInt result (out))::
- bool Resolve(IVariableStore variables, IntBoundsVariableSource source, BoundsInt result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, BoundsInt result (out))::
- bool Resolve(IVariableStore variables, Vector2VariableSource source, Vector2 result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector2 result (out))::
- bool Resolve(IVariableStore variables, Vector3VariableSource source, Vector3 result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector3 result (out))::
- bool Resolve(IVariableStore variables, Vector4VariableSource source, Vector4 result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector4 result (out))::
- bool Resolve(IVariableStore *variables*, QuaternionVariableSource *source*, Quaternion *result* (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Quaternion result (out))::
- bool Resolve(IVariableStore variables, RectVariableSource source, Rect result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Rect result (out))::
- bool Resolve(IVariableStore variables, BoundsVariableSource source, Bounds result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Bounds result (out))::
- bool Resolve(IVariableStore variables, ColorVariableSource source, Color result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Color result (out))::
- bool Resolve(IVariableStore variables, StringVariableSource source, string result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, string result (out))::
- bool Resolve<EnumType>(IVariableStore variables, VariableSource<EnumType> source, EnumType result (out))::
- bool Resolve<EnumType>(IVariableStore variables, VariableReference reference, EnumType result (out))::
- bool Resolve(IVariableStore variables, StoreVariableSource source, IVariableStore result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, IVariableStore result (out))::

- bool Resolve(IVariableStore variables, ListVariableSource source, IVariableList result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, IVariableList result (out))::
- bool ResolveObject<ObjectType>(IVariableStore variables, VariableSource<ObjectType> source, ObjectType result (out))::
- bool ResolveObject<ObjectType>(IVariableStore variables, VariableReference reference, ObjectType result (out))::
- bool ResolveStore<StoreType>(IVariableStore *variables*, VariableReference *reference*, StoreType *result (out)*)::
- bool ResolveList<ListType>(IVariableStore variables, VariableReference reference, ListType result (out))::
- bool ResolveInterface<InterfaceType>(IVariableStore variables, VariableReference reference, InterfaceType result (out))::
- bool ResolveReference(IVariableStore variables, VariableReference reference, Object result (out))::

void Assign(IVariableStore variables, VariableReference reference, VariableValue value)

Assigns *value* to the variable referenced by *reference*. The *variables* parameter should be the *variables* parameter passed to the *Run* method. If the assignment fails, a warning will be logged.

void GetInputs(IList<VariableDefinition> inputs) (virtual)

Implement this method to customize the set of variables the node expects to have available as inputs on the InstructionStore when it is run. This rarely needs to be implemented as the base implementation should be sufficient most of the time. The base implementation will automatically find all VariableReferences, VariableSources, and Expressions.

void GetOutputs(IList<VariableDefinition> outputs) (virtual)

Implement this method to customize the set of variables this node will set as outputs on the InstructionStore when it is run. This rarely needs to be implemented as the base implementation should be sufficient most of the time. The base implementation will automatically find all VariableReferences and Expressions.

void GetConnections(NodeData data) (virtual)

Implement this method to specify the nodes this node has connections to. This rarely needs to be implemented as the base implementation should be sufficient most of the time.

void SetConnection(ConnectionData connection, InstructionGraphNode target) (virtual)

Used by the editor to update a connection. This only needs to be overridden if *GetConnections* is overridden.

InstructionGraphNodeDictionary

 $PiRhoSoft. Composition Engine. Instruction Graph Node Dictionary \\ : Serialized Dictionary < string, \\ string >$

Description

Use this class as a field on an InstructionGraphNode to store an editable list of nodes that are accessed by name.

Instruction Graph Node List

PiRhoSoft. Composition Engine. Instruction Graph Node List: Serialized List < Instruction Graph Node > 1.00% and 1

Description

Use this class as a field on an InstructionGraphNode to store an editable list of nodes that are accessed by index.

InstructionInput

PiRhoSoft. Composition Engine. Instruction Input

Description

Used by InstructionCaller to store the data for an input Variable.

Public Fields

string Name

The name used to access the value on the *Input* store from a VariableReference or Expression.

InstructionInputType *Type*

Specifies how the value of the input is retrieved.

VariableReference Reference

If *Type* is Reference, holds the VariableReference used to look up the value.

Variable Value Value

If *Type* is Value, holds the value directly.

InstructionInputType

PiRhoSoft. Composition Engine. Instruction Input Type

Description

Defines the available types for an InstructionInput.

Values

InstructionInputType Reference

The input is looked up using a VariableReference.

InstructionInputType Value

The input Variable Value is set directly.

InstructionNode

PiRhoSoft. Composition Engine. Instruction Node: Instruction Graph Node

Description

Add this to an InstructionGraph to run an external InstructionGraph.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

InstructionSource Source

Indicates how the InstructionGraph to run is specified.

InstructionCaller Instruction

If *Source* is Value, the <u>InstructionGraph</u> to run when this node is entered. <u>InstructionStore.Local</u> variables available to this node are not transferred to this graph - to share variables use the <u>InstructionStore.Global</u> store, <u>InstructionStore.Input</u> store, or <u>Context</u>.

VariableReference Reference

If *Source* is Reference, the reference to the <u>InstructionGraph</u> to run when this node is entered. <u>InstructionStore.Local</u> variables available to this node are not transferred to this graph - to share variables use the <u>InstructionStore.Global</u> store, <u>InstructionStore.Input</u> store, or <u>Context</u>.

Variable Value Source Context

The variable to use as the InstructionStore. Context for Instruction.

bool WaitForCompletion

If true, *Next* will not be run until execution of *Instruction* is complete. If false, *Next* will be run immediately and continue in parallel with *Instruction*.

InstructionOutput

PiRhoSoft. Composition Engine. Instruction Output

Description

Used by InstructionCaller to store the data for an output Variable.

Public Fields

string Name

The name used to access the value on the *Output* store from a VariableReference or Expression.

InstructionOutputType *Type*

Specifies how the value of the output is handled.

VariableReference Reference

If *Type* is Reference, holds the VariableReference that specifies where the output value should be stored after execution of the instruction finishes.

Instruction Output Type

PiRhoSoft. Composition Engine. Instruction Output Type

Description

Defines the available types for an InstructionOutput.

Values

InstructionOutputType *Ignore*

The output will be ignored.

InstructionOutputType *Reference*

The input is set using a VariableReference.

InstructionSource

PiRhoS oft. Composition Engine. Instruction Source

Description

Defines the options for the *Source* of a InstructionGraph in an InstructionNode.

Values

InstructionSource Value

The InstructionGraph is specified directly in Instruction.

InstructionSource Reference

The InstructionGraph is resolved from the VariableReference Reference.

InstructionStore

PiRhoSoft.CompositionEngine.InstructionStore: IVariableStore

Description

The IVariableStore used with InstructionGraphs to provide a robust interface for accessing and isolating variables for use by InstructionGraphNodes. When using an InstructionCaller all management of the store will be handled automatically including creation of the store, reading input variables, and writing output variables.

Static Fields

string *InputStoreName*

The name used to access the *Input* store from a VariableReference or Expression. This is set to "input".

string OutputStoreName

The name used to access the *Output* store from a VariableReference or Expression. This is set to "output".

string *LocalStoreName*

The name used to access the *Local* store from a VariableReference or Expression. This is set to "local".

Static Methods

bool IsInput(VariableReference *variable*)

Determines if *variable* reads from the *Input* store. This can be used from overridden implementations of *GetInputs* in rare cases where the default implementation isn't sufficient.

bool IsOutput(VariableReference *variable*)

Determines if *variable* writes to the *Output* store. This can be used from overridden implementations of *GetOutputs* in rare cases where the default implementation isn't sufficient.

bool IsInput(InstructionInput input)

Determines if *input* reads from the *Input* store. This can be used from overridden implementations of *GetInputs* in rare cases where the default implementation isn't sufficient.

bool IsOutput(InstructionOutput output)

Determines if *inputs* writes to the *Output* store. This can be used from overridden implementations of *GetOutputs* in rare cases where the default implementation isn't sufficient.

Public Properties

string *ContextName* (read only)

The name used to access the *Context* from a VariableReference or Expression.

VariableValue *Context* (read only)

The value sent as *context* in the InstructionStore constructor.

VariableStore Input (read only)

The variable store, accessed with *InputStoreName*, that holds variables passed from the caller. Variables in this store can be accessed and changed, but new variables cannot be added.

VariableStore *Output* (read only)

The variable store, accessed with *OutputStoreName*, that holds variables set by the instruction and returned to the caller. Variables in this store can be accessed and changed, but new variables cannot be added. The store will be pre-populated with variables specified as *Outputs* on the caller.

VariableStore Local (read only)

The variable store, accessed with *LocalStoreName*, that holds variables that are isolated to the execution of the *instruction* this store was created with. When execution begins, this store will be empty, but variables can be added or changed on this store at any time without affecting any other stores.



It is not required to use *LocalStoreName* when accessing the local store but it can improve readability or resolve ambiguities in some cases.

Public Methods

void WriteInputs(InstructionCaller instruction, **IList<InstructionInput>** inputs, **IVariableStore** caller)

Takes each of the InstructionInputs from *inputs*, resolves them using *caller* if they are VariableReferences, and adds them to the *Input* store.

void WriteOutputs(IList<InstructionOutput> outputs)

Takes each of the InstructionOutputs from outputs and adds them to the Output store.

void ReadOutputs(IList<InstructionOutput> outputs, IVariableStore caller)

Takes each of the InstructionOutputs from *outputs* and resolves them using this store if they are VariableReferences, and adds them to *caller*.

VariableValue GetVariable(string name)

Returns the value of the variable with name *name* on this store. If *name* is not found, the *Local* store will be searched.

SetVariableResult SetVariable(string name, **VariableValue** value)

Each of the names exposed by this store are read only, but if *name* is unrecognized, this will attempt to set *value* on the *Local* store.

IList<string> GetVariableNames()

Returns the names of all variables exposed by this store. This is *InputStoreName*, *OutputStoreName*, *LocalStoreName*, CompositionManager.*GlobalStoreName*,

CompositionManager.SceneStoreName, and ContextName.	

InstructionTrigger

PiRhoSoft.CompositionEngine.InstructionTrigger: MonoBehaviour

Description

Add this to an object to provide an interface for specifying an InstructionGraph in the editor that can be run from code. This is also used as a base class for behaviours that run graphs on certain events. Built in implementations are:

- ButtonGraphTrigger
- ClickGraphTrigger
- EnableGraphTrigger
- StartGraphTrigger

Additionally, InstructionGraphTrigger and CollisionGraphTrigger are included that, while not deriving from this class, perform a similar function.

Public Fields

InstructionCaller *Graph*

The InstructionGraph to execute when Run is called.

Public Methods

void Run()

Runs *Graph* using the CompositionManager. CompositionManager. *DefaultStore* is used to read input variables from and this is used as the *Context*

Int2VariableSource

Description

A VariableSource for Vector2Int.

Constructors

 $\textbf{Int2VariableSource}(\textcolor{red}{\textbf{Vector2Int}} \ \textit{defaultValue})$

Int3VariableSource

Description

A VariableSource for Vector3Int.

Constructors

 $\textbf{Int3VariableSource}(\textcolor{red}{\textbf{Vector3Int}} \ \textit{defaultValue})$

IntBoundsVariableSource

PiRhoSoft. Composition Engine. Int Bounds Variable Source : Variable Source < Bounds Int > 1000 for the control of the contr

Description

A VariableSource for BoundsInt.

Constructors

IntBoundsVariableSource(BoundsInt defaultValue)

InterfaceControl

PiRhoSoft.CompositionEngine.InterfaceControl: MonoBehaviour

Description

Add this to any MonoBehaviour to provide support for enabling and disabling the object from an InstructionGraph using ShowControlNode and HideControlNode. Read the Interface Control topic for more information on how and when to use InterfaceControls.



An InterfaceControl will always start inactive.

Public Fields

DependentObjectList DependentObjects

A list of GameObjects whose enabled state should always match the enabled state of this object.

Public Properties

bool *IsActive* (read only)

true if the control is currently enabled, false otherwise.

Public Methods

void Activate()

Enables the control (and *DependentObjects*) if it is not already enabled. *Setup* will be called only if the control is not already enabled.

void Deactivate()

Disables the control (and *DependentObjects*) regardless of how many times *Activate* was called. *Teardown* will be called only if the control is not already disabled.

Protected Methods

void Setup() (virtual)

Implement this method in a subclass to perform setup when the object becomes enabled. The base implementation does nothing.

void Teardown() (virtual)

Implement this method in a subclass to perform clean up when the object becomes disabled. The base implementation does nothing.

IntRectVariableSource

PiRhoSoft. Composition Engine. Int Rect Variable Source : Variable Source < Rect Int > 100 for the control of the control of

Description

A VariableSource for RectInt.

Constructors

 $\textbf{IntRectVariableSource}(\textbf{RectInt}\ defaultValue)$

IntVariableConstraint

PiRhoSoft. Composition Engine. Int Variable Constraint: Variable Constraint

Description

A VariableConstraint for Int VariableValues that restricts the value to a range.

Public Fields

int *Minimum*

The smallest value allowed for the value.

int *Maximum*

The largest value allowed for the value.

IntVariableSource

PiRhoSoft. Composition Engine. Int Variable Source: Variable Source < int > 1000 for the control of the contr

Description

A VariableSource for ints.

Constructors

IntVariableSource(int defaultValue)

ISchemaOwner

PiRhoSoft. Composition Engine. IS chema Owner

Description

Implement this interface on a class that also implements IVariableStore to indicate to other systems that this store is constrained by a VariableSchema. This is used to improve the editing experience and enable runtime serialization of the store data. The built in classes ConstrainedStore, VariableSetComponent, and VariableSetAsset implement this and should be sufficient for most use cases.

Public Properties

VariableSchema Schema (read only) (abstract)

The VariableSchema that is constraining this store.

Public Methods

void SetupSchema() (abstract)

This method should apply the schema to the store.

ISequenceNode

PiRhoS of t. Composition Engine. I Sequence Node

Description

Implement this interface in an InstructionGraphNode subclass to inform an InstructionGraph that the node should be run repeatedly. The graph will continue to run the node until the node does not call InstructionGraph.GoTo (or calls GoTo(null)).

IterateNode

PiRhoSoft. Composition Engine. IterateNode: Instruction Graph Node, ILoop Node

Description

Add this to an InstructionGraph to execute an InstructionGraphNode repeatedly for each VariableValue in an IVariableList.

Public Fields

VariableReference Container

The IVariableList holding each of the VariableValues to iterate.

VariableReference *Index*

The variable to set to the current number of times the node has been repeated.

VariableReference Value

The variable to set to the current value being iterated.

InstructionGraphNode Loop

The InstructionGraphNode to run for each VariableValue in Container.

IVariableList

PiRhoSoft.CompositionEngine.IVariableList

Description

Implement this interface on a class to allow the class to be stored with type List in a VariableValue. VariableList provides an implementation that is sufficient for most use cases.

Public Properties

int Count (read only) (abstract)

The number of items in the list.

Public Methods

VariableValue GetVariable(int index) (abstract)

Returns the value at the index *index* in the list.

SetVariableResult SetVariable(int index, **VariableValue** value) (abstract)

Sets the value at index index to value.

SetVariableResult AddVariable(VariableValue value) (abstract)

Adds the value value to the end of the list.

SetVariableResult RemoveVariable(int index) (abstract)

Removes the value at index index from the list.

IVariableListener

PiRhoSoft. Composition Engine. IV ariable Listener

Description

Implement this in a class that uses a MappedVariableStore to receive notifications whenever a variable in the store changes.

Public Methods

void VariableChanged(int index, VariableValue value) (abstract)

Called by MappedVariableStore to indicate the value at index index was changed to value.

IVariableReset

PiRhoSoft.CompositionEngine.IVariableReset

Description

Implement this interface to add support for the class to be resolved from *Object* in a ResetTagNode or ResetVariablesNode. Although there is no restriction on how this interface can be used, it is intended as a way to reset Variables in a VariableSchema based on the ValueDefinition. *Tag* (with *ResetTag*) or Variable. *Name* (with *ResetVariables*).

Public Methods

void ResetTag(string tag) (abstract)

Called from ResetTagNode with *tag* as the tag that should be reset.

void ResetVariables(IList<string> variables) (abstract)

Called from ResetVariablesNode with variables as the list of names that should be reset.

IVariableStore

PiRhoSoft.CompositionEngine.IVariableStore

Description

Implement this interface on a class to allow the class to be stored with type Store in a VariableValue. Many built in implementations are provided for various use cases:

- VariableStore
- ConstrainedStore
- ReadOnlyStore
- WritableStore
- SceneVariableStore
- MappedVariableStore



This interface is one of the most important pieces to the variable system. Read the variables topic for a complete description of this interface and how it interacts with the rest of the system.

Public Methods

VariableValue GetVariable(string name) (abstract)

Returns the value of the variable with name *name*.

SetVariableResult SetVariable(string name, **VariableValue** value) (abstract)

Sets the value of the variable with name name to value

IList<string> GetVariableNames() (abstract)

Returns the complete list of variable names that exist in this store.

ListAdapter

PiRhoSoft. Composition Engine. List Adapter: IVariable List

Description

This serves as a base class for several internal classes that wrap specific IList types so they can be accessed as a VariableValue with *Type* List. To use a ListAdapter call the static *Create* method.

Static Methods

IVariableList Create(IList list)

Creates an IVariableList that wraps and modifies *list* when it is accessed.

ListBinding

PiRhoSoft.CompositionEngine.ListBinding: VariableBinding

Description

Add this to any GameObject to add child objects instantiated from a prefab for each item in an IVariableList.

Public Fields

VariableReference Variable

The IVariableList to bind to.

BindingRoot Template

The prefab that will be instantiated as a child of this object for each item in the list referenced by *Variable*.

ListVariableConstraint

PiRhoSoft. Composition Engine. List Variable Constraint: Variable Constraint

Description

A VariableConstraint for List VariableValues that specifies the VariableType of VariableValues that can be added to the list.

Public Fields

VariableType *ItemType*

The type of items in the list. If this is Empty, any value can be added.

VariableConstraint ItemConstraint

The constraint to enforce for each item in the list.

ListVariableSource

PiRhoSoft. Composition Engine. List Variable Source : Variable Source < IVariable List > 100 for the control of the control

Description

A VariableSource for IVariableLists.

LoadSceneNode

PiRhoSoft.CompositionEngine.LoadSceneNode: InstructionGraphNode

Description

Add this to an InstructionGraph to load a scene.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

SceneSource Source

Specifies how the scene to load is retrieved.

SceneReference Scene

If Source is Value, holds the scene to load.

VariableReference SceneVariable

If *Source* is Variable, references the scene to load. If the resolved value is an Int, the scene will be loaded by build index. If it is a String, it will be loaded by name.

string SceneName

If *Source* is Name, the name of the scene to load.

int SceneIndex

If Source is Index, the build index of the scene to load.

bool WaitForCompletion

If this is true (the default), the node will block until the scene has been loaded. Otherwise the scene will be loaded and the graph will continue in parallel.

bool CleanupAssets

If this is true (the default), Resources. Unload Unused Assets will be called after the scene has been loaded.

bool Additive

If this is true (the default), the scene will be loaded in additive mode, meaning all other loaded scenes will remain loaded. If this is false, all currently loaded scenes will be unloaded first.

LogNode

PiRhoSoft. Composition Engine. LogNode: Instruction Graph Node

Description

Add this to an InstructionGraph to log a message to the console to aid in debugging.

Public Fields

Message Message

The message to log.

${\bf Instruction Graph Node}\ Next$

The InstructionGraphNode to run when this node finishes.

LoopNode

PiRhoSoft. Composition Engine. Loop Node: Instruction Graph Node, ILoop Node

Description

Add this to an InstructionGraph to executes an InstructionGraphNode repeatedly until a condition Expression evaluates to false.

Public Fields

InstructionGraphNode Loop

The InstructionGraphNode to run repeatedly while Condition is true.

VariableReference *Index*

The variable to set to the current number of times the node has been repeated.

Expression Condition

The Expression to evaluate to determine if the node should continue to repeat.

MappedVariableAttribute

PiRhoSoft. Composition Engine. Mapped Variable Attribute: Attribute

Description

Add this to a property or field on a VariableSetComponent or VariableSetAsset to expose it to the variables system.

Constructors

MappedVariableAttribute(bool readOnly)

Pass true as *readOnly* to indicate the property or field cannot be set by the variables system. If the default constructor is used the variable is allowed to be set.

Public Properties

bool ReadOnly (read only)

If this is true, the property or field cannot be set through a MappedVariableStore.

MappedVariableStore

PiRhoSoft.CompositionEngine.MappedVariableStore: IVariableStore

Description

An IVariableStore implementation that provides an attribute based interface for exposing properties and fields defined in code to the variables system. This is used by VariableSetComponent and VariableSetAsset.

Public Properties

int VariableCount (read only)

The total number of variables in the store.

Public Methods

void Setup(Object owner, VariableSchema schema, VariableSet variables)

Initializes the store with MappedVariables from *owner* and Variables defined by *schema*. *variables* is initialized with *schema* as well.

VariableValue GetVariable(string name)

Returns the value of the variable with name *name*.

SetVariableResult SetVariable(string name, VariableValue value)

Sets the value of the variable with name *name* to _value.

IList<string> GetVariableNames()

Returns a list of the names of all the variables in this store.

string GetVariableName(int index)

Returns the name of the variable at index index.

Variable Value Get Variable Value (int index)

Returns the value of the variable at index *index*.

SetVariableResult SetVariableValue(int index, **VariableValue** value)

Sets the value of the variable at index index to value.

Material Animation

PiRhoSoft.CompositionEngine.MaterialAnimation: MonoBehaviour, ICompletionNotifier

Description

Add this to a Renderer to animate a _Progress material property. This can be used standalone but is most useful when used with the PlayEffectNode.

Public Fields

bool AutoAdvance

If this is true (the default), *Progress* will be automatically updated every frame according to the values set for *UseScaledTime* and *Duration*.

float Progress

The value that is set on the _Progress material property for a sibling Renderer.

bool *UseScaledTime*

If *AutoAdvance* is true, specifies how *Progress* will be updated when Time.timeScale is changed. When true, Time.deltaTime is used, otherwise Time.unscaledDeltaTime is used.

float Duration

If *AutoAdvance* is true, specifies the total duration of the animation. The _Progress material property will be set to _Progress_/_Duration.

Public Properties

bool *IsComplete* (read only)

Returns true as soon as the animation has completed. When AutoAdvance is true, the animation is complete when Progress >= Duration. When AutoAdvance is false, the animation is complete when Progress >= 1.0

Protected Methods

void LateUpdate() (virtual)

Performs the update of the _Progress material property.

Menu

PiRhoSoft.CompositionEngine.Menu: MonoBehaviour, IVariableStore

Description

Add this to any GameObject to manage a list of child MenuItems. Additionally add a MenuInput to manage input. MenuItems can be added directly as children in the editor or at runtime, or by using ListBinding. Additionally, this can be used with a SelectionControl to automate the process of selecting from a menu in an InstructionGraph.

Public Fields

Action < MenuItem > OnItem Added

Subscribe to this callback to receive a notification any time a MenuItem is added to this menu.

Action < MenuItem > OnItemRemoved

Subscribe to this callback to receive a notification any time a MenuItem is removed from this menu.

Action < MenuItem > OnItemMoved

Subscribe to this callback to receive a notification any time a MenuItem's position in the menu changes.

Action < MenuItem > OnItemBlurred

Subscribe to this callback to receive a notification any time a MenuItem loses focus.

Action < MenuItem > OnItemFocused

Subscribe to this callback to receive a notification any time a MenuItem gains focus.

Action < MenuItem > OnItem Selected

Subscribe to this callback to receive a notification any time a MenuItem is selected.

Action OnCancelled

Subscribe to this callback to receive a notification any time the menu is closed without a selection being made.

Public Properties

List<MenuItem> *Items* (read only)

The MenuItems in this menu. This is automatically updated to reflect the current set of MenuItems that are children of this object.

MenuItem FocusedItem

The MenuItem that has focus.

int FocusedIndex

The index of the MenuItem that has focus.

Public Methods

void SelectItem(MenuItem item)

Selects *item*. The result of an item being selected is only that *OnItemSelected* will be triggered. Selection is most commonly used indirectly through a SelectionControl.

void Cancel()

Triggers *OnCancelled* with no other effect.

IList<string> GetVariableNames()

Returns the names of the Variables exposed by this IVariableStore. These are "FocusedItem" and "FocusedIndex".

VariableValue GetVariable(string name)

Returns the variable with name name.

SetVariableResult SetVariable(string name, **VariableValue** value)

Sets the value of the variable with *name* to *value*.

Protected Methods

void ItemAdded(MenuItem item) (virtual)

Called when a MenuItem (item) is added to the menu. The base implementation triggers OnItemAdded.

void ItemRemoved(MenuItem item) (virtual)

Called when a MenuItem (item) is removed from the menu. The base implementation triggers OnItemRemoved.

void ItemMoved(MenuItem item) (virtual)

Called when a MenuItem (item)'s position ith menu changes. The base implementation triggers OnItemMoved.

void ItemFocused(MenuItem item) (virtual)

Called when a MenuItem (item) gains focus. The base implementation triggers OnItemFocused.

void ItemBlurred(MenuItem item) (virtual)

Called when a MenuItem (item) loses focus. The base implementation triggers OnItemBlurred.

void ItemSelected(MenuItem item) (virtual)

Called when a MenuItem (item) is selected. The base implementation triggers OnItemSelected.

void Cancelled() (virtual)

Called when the menu is cancelled. The base implementation triggers OnCancelled.

MenuInput

PiRhoSoft.CompositionEngine.MenuInput: MonoBehaviour

Description

Add this to a Menu to provide navigation and selection of MenuItems.

Public Fields

string HorizontalAxis

The name of the axis, as used by InputHelper, that moves focus left and right through the Menu.

string VerticalAxis

The name of the axis, as used by InputHelper, that moves focus up and down through the Menu.

string SelectButton

The name of the button, as used by InputHelper, that will select the focused item on the Menu.

string *CancelButton*

The name of the button, as used by InputHelper, that will cancel the menu.

MenuInputPointerAction HoverAction

The action to perform when the mouse moves over an item in the Menu.

MenuInputPointerAction ClickAction

The action to perform when the mouse is clicked while over an item in the Menu.

PrimaryAxis PrimaryAxis

Specifies how MenuItems are laid out in the Menu relative to their child index in the object. If items are laid out top to bottom (potentially with multiple columns), use Column. If items are laid out left to right (potentially with multiple rows), use Row.

int RowCount

If *PrimaryAxis* is Row, specifies the number of rows of MenuItems in the Menu.

int ColumnCount

If *PrimaryAxis* is Column, specifies the number of columns of MenuItems in the Menu.

MenuInput NextLeft

Specifies the menu to transfer focus to when moving past the left most MenuItem in the Menu. This can be set to this menu input to cause focus to wrap back to the right. If this is not set, focus will be clamped to the left most column.

MenuInput NextRight

Specifies the menu to transfer focus to when moving past the right most MenuItem in the Menu. This can be set to this menu input to cause focus to wrap back to the left. If this is not set, focus

will be clamped to the right most column.

MenuInput NextUp

Specifies the menu to transfer focus to when moving past the top most MenuItem in the Menu. This can be set to this menu input to cause focus to wrap back to the bottom. If this is not set, focus will be clamped to the top most row.

MenuInput NextDown

Specifies the menu to transfer focus to when moving past the bottom most MenuItem in the Menu. This can be set to this menu input to cause focus to wrap back to the top. If this is not set, focus will be clamped to the bottom most row.

bool FocusOnLoad

Set this to true to have the first MenuItem gain focus when this behaviour is loaded.

float ScrollPadding

When inside a https://docs.unity3d.com/Manual/script-ScrollRect.html, indicates the amount of padding to maintain around the focused item when menu navigation causes the menu to scroll.

Public Methods

void EnterFromBeginning()

Focuses the first MenuItem.

void EnterFromEnd()

Focuses the last MenuItem.

void EnterFromLeft(int fromRow)

Focuses the left most MenuItem in row fromRow.

void EnterFromRight(int fromRow)

Focuses the right most MenuItem in row fromRow.

void EnterFromTop(int fromColumn)

Focuses the top most MenuItem in column fromColumn.

void EnterFromBottom(int fromColumn)

Focuses the bottom most MenuItem in column fromColumn.

void Leave()

Clear focus so no MenuItem has focus.

void MoveFocusUp(int amount)

Focus the MenuItem *amount* rows above the current focused item.

void MoveFocusDown(int amount)

Focus the MenuItem amount rows below the current focused item.

void MoveFocusLeft(int amount)

Focus the MenuItem amount columns to the left of the current focused item.

void MoveFocusRight(int amount)

Focus the MenuItem amount columns to the right of the current focused item.

void RefreshLayout()

Re-layout the MenuItems. Layout is maintained automatically when MenuItems are added, moved, or removed, but if *PrimaryAxis*, *ColumnCount*, or *RowCount* changes without altering the MenuItems, this should be called.

MenuItem GetItem(Vector2 screenPoint)

Returns the MenuItem at position *screenPoint*. *screenPoint* is in the same coordinate system as Input.mousePosition.

void ScrollToItem(MenuItem item)

When inside a https://docs.unity3d.com/Manual/script-ScrollRect.html, ensures *item* is visible with *ScrollPadding* space around it on all sides.

MenuInputPointerAction

PiRhoSoft. Composition Engine. MenuInputPointer Action

Description

Defines the available options for mouse actions on MenuInput.

Values

MenuInputPointerAction *None*

The action will have no effect.

${\bf MenuInputPointerAction}\ Focus$

The action will focus the MenuItem.

MenuInputPointerAction Select

The action will select the MenuItem.

MenuItem

PiRhoSoft.CompositionEngine.MenuItem: BindingRoot

Description

Add this to any GameObject that is a child of a Menu to indicate the object should be managed by the Menu.

Public Fields

string ItemName

The name to use to access the this item from child VariableBindings. Available variables are Index, Column, Row, Label, and Focused.

Public Properties

int Index (read only)

The index of the item in the Menu.

int Column (read only)

The index of the column the item is in in the Menu.

int Row (read only)

The index of the row the item is in in the Menu.

string *Label* (read only)

The label assigned to the item by a SelectionControl.

bool Focused (read only)

true when this item is the focused item in its Menu

MenuItemTemplate *Template (read only)*

The template this item was generated from or initialized with.

bool Generated (read only)

true if this item was generated from a prefab set by a MenuItemTemplate.

Public Methods

void Setup(MenuItemTemplate template, bool generated)

Initializes Template and Generated after the item has been associated with a Menu.

void Move(int index)

Moves the item in its Menu.

MenuItemTemplate

PiRhoSoft.CompositionEngine.MenuItemTemplate

Description

Holds information about how a MenuItem should be setup in a Menu.

Public Fields

VariableReference Variables

The variable that should be used as the BindingRoot Value for the MenuItem.

ObjectSource Source

Specifies whether the MenuItem should be looked up in the scene using *Name* (Scene) or created from a prefab using *Template* (Asset).

string Name

When Source is Name, the name of the GameObject containing the MenuItem in the loaded scenes.

MenuItem Template

When Source is Asset, the prefab to create the MenuItem from.

string Label

When Source is Asset, the label to assign to the MenuItem.

bool Expand

When *Source* is Asset, this is true, and *Variables* references a List, a MenuItem will be created from *Template* for each item in the List.

Public Properties

string Id (read only)

The identifier used for the item when referenced by string. If *Source* is Scene this will be *Name*. If *Source* is Asset this will be *Label*.

Message

PiRhoSoft.CompositionEngine.Message

Description

Add this as a field of a class to provide an editable text field that can be formatted with VariableReferences.

Public Fields

string *Text*

The string that will be formatted at runtime. VariableReferences to resolve can be inserted in the text by surrounding it with braces ({ and }). Access the resolved text with the *GetText* method. An example message is shown in the Messages topic.

Public Properties

bool HasText (read only)

Indicates that *Text* has been set and *GetText* will return a non-empty string.

Public Methods

void GetInputs(IList<VariableDefinition> inputs)

Adds a definition for each VariableReference in *Text* to *inputs* if the VariableReference accesses InstructionStore.*Input*.

string GetText(IVariableStore variables, bool suppressErrors)

Formats and returns *Text*, looking up any VariableReferences on *variables*. If *suppressErrors* is false, an error will be logged when a VariableReference cannot be resolved.

MessageBinding

 $PiRhoSoft. Composition Engine. Message Binding: {\color{blue}StringBinding}}$

Description

Add this to a TextMeshPro to set the text to the string retrieved from a Message.

Public Fields

Message Message

The Message to resolve and apply to the TextMeshPro when the binding is updated.

MessageControl

PiRhoSoft. Composition Engine. Message Control: Interface Control

Description

Add this to a TextMeshPro to display messages from a MessageNode. Add a MessageInput to support dismissing the control with a button press.

Public Fields

TMP_Text DisplayText

The TextMeshPro that the text will be displayed on. This component will be enabled and disabled along with this MessageControl.

Public Properties

bool *IsRunning* (read only)

Returns true when this MessageControl is displaying text.

bool IsAdvancing

Returns true when this MessageControl should have its text advanced. This can be set from subclasses to reset the flag after it has been consumed.

Public Methods

void Show(string text)

Activates the MessageControl if necessary, sets *text* on *DisplayText*, and enables *DisplayText*. If this is called a second time before it is hidden, the text will simply be replaced and the control will continue to function as normal.

void Advance()

Sets the *IsAdvancing* flag so the text will advance on the next frame.

Protected Methods

IEnumerator Run() (virtual)

This method can be overridden to perform custom handling of advancement. By default, the control will be dismissed when *Advance* is called, but this could be changed to add support for, for example, paging.

MessageInput

 $PiRhoSoft. Composition Engine. Message Input: {\color{blue}MonoBehaviour}$

Description

Add this to a MessageControl to add support for advancing the text when a button is pressed.

Public Fields

string AcceptButton

The name of the button that advances the MessageControl as defined in InputHelper.

Protected Properties

MessageControl Message (read only)

The MessageControl attached as a sibling to this component.

MessageNode

PiRhoSoft.CompositionEngine.MessageNode: InstructionGraphNode

Description

Add this to an InstructionGraph to display a Message on a MessageControl.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference Control

The MessageControl to display Message on.

bool WaitForCompletion

When true, this InstructionGraphNode will not complete until the MessageControl has been dismissed.

bool AutoHide

When true, the MessageControl will be automatically dismissed after WaitTime seconds.

float WaitTime

When *AutoHide* is true, the number of seconds to wait before dismissing the MessageControl.

Message Message

The Message to display on the MessageControl.

MockupConnection

PiRhoSoft. Composition Engine. Mockup Connection

Description

Holds data for a connection in a MockupNode.

Public Fields

string Name

The name to display in the graph window for this connection.

InstructionGraphNode Node

The node this connection is connected to.

Mockup Connection List

Description

The serializable list of MockupConnections for a MockupGraph or MockupNode.

MockupGraph

PiRhoSoft. Composition Engine. Mockup Graph: Instruction Graph

Description

Performs no function but can have an arbitrary number of entry points for quickly making InstructionGraph blueprints.

Public Fields

MockupConnectionList EntryPoints

The list of MockupConnections to show as entry points in the start node of the graph editor window.

MockupNode

 $PiRhoSoft. Composition Engine. Mockup Node: {\color{blue}Instruction Graph Node}$

Description

Add this to a MockupGraph to quickly make an InstructionGraph blueprint.

Public Fields

MockupConnectionList Connections

The connections that have been added to this node.

Color DisplayColor

The color of the node in the graph editor window.

NodeData

PiRhoSoft. Composition Engine. No de Data

Description

Stores data about an InstructionGraphNode. This is managed automatically by the editor and can be ignored.

NumberBinding

PiRhoSoft.CompositionEngine.NumberBinding: StringBinding

Description

Add this to a TextMeshPro to set the text to a formatted number.

Public Fields

BindingFormatter Format

Specifies how the number in *Variable* should be interpreted and formatted when converting it to a string.

VariableReference Variable

The Int or Float that will be formatted and applied when the binding is updated.

NumberFormatType

PiRhoSoft.CompositionEngine.NumberFormatType

Description

Defines the number formats available to set for the *NumberFormatting* of a BindingFormatter.

Values

NumberFormatType Percentage

The number will be formatted as a percentage. Equivalent to setting the custom format string to "0.#%".

NumberFormatType Commas

The number will be formatted as a number with commas separating every 3 digits. Equivalent to setting the custom format string to ",,0".

NumberFormatType Rounded

The number will be rounded before converting it to a string. Equivalent to setting the custom format string to "0".

NumberFormatType Decimal

The number will be rounded to 2 decimal places before converting it to a string. Equivalent to setting the custom format string to "0.00".

NumberFormatType Custom

The format string will be read from the *ValueFormat* property of the *BindingFormatter*.

ObjectBindingRoot

 $PiRhoSoft. Composition Engine. Object Binding Root: {\color{blue}Binding Root}$

Description

Add this to any GameObject to add a specified object to the BindingRoot hierarchy.

Public Fields

Object Object

The Object to return in Value for this BindingRoot.

ObjectPositioning

PiRhoSoft.CompositionEngine.ObjectPositioning

Description

Defines the available settings for the *Positioning* property of PlayEffectNode.

Values

ObjectPositioning Absolute

The created object will be placed at the scene root and positioned at the value of PlayEffectNode. *Position* in world space.

ObjectPositioning Relative

The created object will be placed at the scene root and positioned at the value of PlayEffectNode. Position relative to PlayEffectNode. Object.

ObjectPositioning Child

The created object will be placed as a child of PlayEffectNode. Parent and positioned at the value of PlayEffectNode. Parent's coordinates.

ObjectPositioning

PiRhoSoft.CompositionEngine.ObjectPositioning

Description

Defines the available settings for the *Positioning* property of CreateGameObjectNode.

Values

ObjectPositioning Absolute

The created GameObject will be placed at the scene root and positioned at the value of CreateGameObjectNode. *Position* in world space.

ObjectPositioning Relative

The created GameObject will be placed at the scene root and positioned at the value of CreateGameObjectNode. *Position* relative to CreateGameObjectNode. *Object*.

ObjectPositioning Child

The created GameObject will be placed as a child of CreateGameObjectNode. Parent and positioned at the value of CreateGameObjectNode. Position in CreateGameObjectNode. Parent's coordinates.

ObjectSource

PiRhoS of t. Composition Engine. Object Source

Description

Defines the available options for the *Source* property of MenuItemTemplate.

Values

ObjectSource Scene

The MenuItem should be looked up by name in the loaded scenes.

ObjectSource Asset

The MenuItem should be instantiated from a prefab.

ObjectVariableConstraint

PiRhoSoft. Composition Engine. Object Variable Constraint: Variable Constraint

Description

A VariableConstraint for Object VariableValues that restricts the value to a specific type.

Public Fields

Type *Type*

The type the object must be or be derived from..

ObjectVariableSource

PiRhoSoft. Composition Engine. Object Variable Source: Variable Source < Object > 100 George (Composition Engine Composition Engine Composition

Description

A VariableSource for Object VariableValues.

Operation

PiRhoSoft.CompositionEngine.Operation

Description

The base class for all operations in an Expression. Custom operations should derive from either PrefixOperation or InfixOperation rather than deriving from this class directly.

Public Methods

void Parse(ExpressionParser parser, ExpressionToken token) (abstract)

Implement this in a subclass to initialize the operation by reading ExpressionTokens from *parser. token* is the ExpressionToken that led to the creation of this operation.

VariableValue Evaluate(IVariableStore variables) (abstract)

Implement this in a subclass to perform the execution of the operation. Any VariableReferences should use *variables* for lookups and assignments.

void ToString(StringBuilder builder) (abstract)

Writes a reversible representation of this operation to builder.

void GetInputs(IList<VariableDefinition> inputs, string source) (virtual)

Implement this in a subclass to add VariableDefinitions to *inputs* that access an IVariableStore named *source*.

void GetOutputs(IList<VariableDefinition> outputs, string source) (virtual)

Implement this in a subclass to add VariableDefinitions to *outputs* that write VariableValues to an IVariableStore named *source*.

OperatorPrecedence

PiRhoSoft.CompositionEngine.OperatorPrecedence: ValueType

Description

Specifies the necessary information to determine the evaluation order for different Operations. Lower values will have lower precedence, meaning they will be evaluated first. The static values defined on this class follow the same precedence rules as math and other programming languages and are listed here in order of lowest precedence to highest.

Static Fields

OperatorPrecedence *Default*

This should be the precedence passed to ExpressionParser. ParseLeft when parsing a new statement or sub-statement.

OperatorPrecedence Assignment

The precedence for all assignment operations. This is right associative so assignments can be chained..

OperatorPrecedence Ternary

The precedence for a ternary (condition? trueStatement: falseStatement) statement.

OperatorPrecedence Or

The precedence for a logical or.

OperatorPrecedence And

The precedence for a logical and.

OperatorPrecedence Equality

The precedence for an equality or inequality check.

OperatorPrecedence Comparison

The precedence for comparisons.

OperatorPrecedence Addition

The precedence for addition and subtraction.

OperatorPrecedence Multiplication

The precedence for multiplication and division.

OperatorPrecedence Exponentiation

The precedence for exponents.

OperatorPrecedence Prefix

The precedence for all prefix operations.

OperatorPrecedence Postfix

The precedence for all postfix operations.

OperatorPrecedence *MemberAccess*

The precedence for all member access operations.

Static Methods

OperatorPrecedence LeftAssociative(int value)

Creates a precedence with left associativity meaning operations with the same precedence will be evaluated left to right.

OperatorPrecedence RightAssociative(int value)

Creates a precedence with right associativity meaning operations with the same precedence will be evaluated right to left.

Public Properties

int Value (read only)

The precedence value when parsed standalone or as the left hand side of an InfixOperation.

int AssociativeValue (read only)

The precedence value when parsed as the right hand side of an InfixOperation.

Parameter

PiRhoSoft.CompositionEngine.Parameter

Description

Holds the name and VariableType of a parameter passed to a Command.

Public Fields

string Name

The name the Command uses to reference the parameter in its Expression.

VariableType *Type*

The VariableType the Command is expecting for the parameter.

ParameterList

PiRhoSoft.CompositionEngine.ParameterList: SerializedList<Parameter>

Description

A SerializedList for CommandParameters.

PixelateTransition

 $PiRhoSoft. Composition Engine. Pixelate Transition: {\color{blue}Transition}$

Description

Animates the resolution of the rendered image by making it more and more pixelated over time. The material property _Amount will be set to a number between 1 and _MaxAmount_, with the number incrementing (or decrementing if the phase is In) every frame.

Public Fields

int *MaxAmount*

The number of pixels for the dimension of the pixelation when the Transition is at its extreme.

PlayAnimationNode

PiRhoSoft. Composition Engine. Play Animation Node: Instruction Graph Node

Description

Add this to an InstructionGraph to play an AnimationClip on an AnimationPlayer.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference AnimationPlayer

The AnimationPlayer to play Animation on.

AnimationClipVariableSource Animation

The AnimationClip to play on AnimationPlayer.

bool WaitForCompletion

If this is true, this node will not complete until *Animation* has completed. Otherwise, this node will complete immediately.

PlayAnimationStateNode

PiRhoSoft. Composition Engine. Play Animation State Node: Instruction Graph Node

Description

Add this to an InstructionGraph to activate a trigger using SetTrigger on an Animator.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference Animator

The Animator to set State on.

StringVariableSource *State*

The name of the trigger to set on *Animator* using *SetTrigger*

PlaybackState

PiRhoSoft. Composition Engine. Playback State

Description

Used internally be the editor to determine the current execution state of an InstructionGraph.

Values

PlaybackState Running

The graph is running.

PlaybackState Paused

The graph has stopped at a breakpoint.

PlaybackState Step

The graph is running a single node before pausing again.

PlaybackState Stopped

The graph has been manually stopped.

PlayEffect

PiRhoSoft.CompositionEngine.PlayEffectNode: InstructionGraphNode

Description

Add this to an InstructionGraph to instantiate a prefab containing one or more ParticleSystems or ICompletionNotifiers.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

GameObjectVariableSource Effect

The prefab to instantiate.

StringVariableSource *EffectName*

The name to assign to the instantiated prefab.

VariableReference EffectVariable

The variable to assign the instantiated prefab to.

ObjectPositioning Positioning

The way the value of *Position* and *Rotation* should be interpreted.

VariableReference Object

When *Positioning* is Relative, specifies the object the created object should be positioned relative to.

VariableReference Parent

When *Positioning* is Child, specifies the object the created object should be added to as a child.

Vector3VariableSource Position

The position at which to place the newly created object.

Vector3VariableSource Rotation

The rotation to set the newly created object to.

bool WaitForCompletion

If this is true, this node will not complete until all ParticleSystems and ICompletionNotifiers in *Effect* have completed. Otherwise, this node will complete immediately.

bool DestroyOnComplete

If this is true, the GameObject created from *Effect* will be destroyed when it finishes playing.

PlaySoundNode

PiRhoSoft. Composition Engine. Play Sound Node: Instruction Graph Node

Description

Add this to an InstructionGraph to play an AudioClip on an AudioPlayer.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference AudioPlayer

The AudioPlayer to play Sound on.

AudioClipVariableSource Sound

The AudioClip to play on AudioPlayer.

FloatVariableSource Volume

The volume to set on *AudioPlayer* when playing *Sound*.

bool WaitForCompletion

If this is true, this node will not complete until *Sound* has completed. Otherwise, this node will complete immediately.

PlayTimelineNode

 $PiRhoSoft. Composition Engine. Play Timeline Node: \underline{Instruction Graph Node}$

Description

Add this to an InstructionGraph to play a TimelineAsset on a PlayableDirector.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference *Director*

The PlayableDirector to play Timeline on.

TimelineVariableSource *Timeline*

The TimelineAsset to play.

DirectorWrapMode *Mode*

The DirectorWrapMode to play Timeline with.

bool WaitForCompletion

If this is true, this node will not complete until *Timeline* has completed. Otherwise, this node will complete immediately.

PlayTransitionNode

PiRhoSoft.CompositionEngine.PlayTransitionNode: InstructionGraphNode

Description

Add this to an InstructionGraph to start a Transition on the TransitionManager.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

TransitionVariableSource Transition

The Transition to play.

TransitionPhase Phase

The TransitionPhase to play the Transition in.

bool AutoFinish

If this is true, the Transition will be ended as soon as it has completed. If this is false, the Transition will persist in its final state until another Transition (perhaps the same one with a different TransitionPhase) is started.

bool WaitForCompletion

If this is true, this node will not complete until *Transition* has completed. Otherwise, this node will complete immediately.

PrefixOperation

PiRhoSoft.CompositionEngine.PrefixOperation: Operation

Description

The base class for all Operations that have a right side.

Public Fields

string Symbol

The symbol for this operation.

Operation Right

The operation that makes up the right hand side.

Protected Methods

ExpressionEvaluationException TypeMismatch(VariableType *type*)

Creates an exception to be thrown by the caller indicating the operation cannot operate on a value with type *type*.

PrimaryAxis

PiRhoSoft.CompositionEngine.PrimaryAxis

Description

Defines the options available for the *PrimaryAxis* property of MenuInput

Values

PrimaryAxis Column

MenuItems are laid out in column order, meaning each MenuItem is visually below its predecessor before optionally wrapping to new columns.

PrimaryAxis Row

MenuItems are laid out in row order, meaning each MenuItem is visually to the right of its predecessor before optionally wrapping to new rows.

QuaternionVariableSource

PiRhoSoft. Composition Engine. Quaternion Variable Source: Variable Source < Quaternion > 1000 and 1

Description

A VariableSource for Quaternion VariableValues.

Constructors

QuaternionVariableSource(Quaternion defaultValue)

Initializes the source to *Type* Value with *Value* _defaultValue.

ReadOnlyStore

 $PiRhoSoft. Composition Engine. Read Only Store: {\color{blue}Variable Store}$

Description

An IVariableStore implementation that disallows contained VariableValues to be assigned or added.

RectVariableSource

PiRhoSoft. Composition Engine. Rect Variable Source : Variable Source < Rect >

Description

A VariableSource for Rect VariableValues.

Constructors

RectVariableSource(Rect defaultValue)

Initializes the source to *Type* Value with *Value* _defaultValue.

ResetTagNode

PiRhoSoft. Composition Engine. Reset TagNode: Instruction Graph Node

Description

Add this to an InstructionGraph to reset all Variables on an object implementing IVariableReset with a given tag. To reset a specific set of Variables use ResetVariablesNode.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference *Object*

The IVariableReset to call ResetTag on.

string *Tag*

The tag to reset on *Object*.

ResetVariableList

 $PiRhoSoft. Composition Engine. Reset Variable List: {\tt SerializedList}{<\tt string}{>}$

Description

The list of variables for a ResetVariablesNode.

ResetVariablesNode

 $PiRhoSoft. Composition Engine. Reset Variables Node: \underline{Instruction Graph Node}$

Description

Add this to an InstructionGraph reset a specific set of Variables on an object implementing IVariableReset. To reset Variables by tag use ResetTagNode.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference *Object*

The IVariableReset to call ResetVariables on.

ResetVariableList Variables

The list of variable names that should be reset.

SceneReference

PiRhoSoft.UtilityEngine.SceneReference

Description

Add this as a field on a class to expose an editor selectable scene.

Static Fields

Action<string, string> SceneMoved

This is exposed for editor support and should be ignored.

Public Fields

string Path

The path to the scene in the "Assets" directory.

Public Properties

bool IsAssigned (read only)

true if the scene has been assigned.

bool IsLoaded (read only)

true if the scene is currently loaded.

Scene *Scene* (read only)

The Scene at Path.

int Index (read only)

The build index of the Scene at Path.

Public Methods

void Setup(Object owner)

This should be called in the setup method of the class this is a field on (for example OnEnable if it is a ScriptableObject). This is necessary for the editor to update the scene when it is moved, renamed, or deleted.

void Teardown()

This should be called in the destroy method of the class this is a field on (for example OnDisable if it is a ScriptableObject). This is necessary for the editor to update the scene when it is moved, renamed, or deleted.

SceneReferenceAttribute

PiRhoSoft.UtilityEngine.SceneReferenceAttribute: Attribute

Description

Apply this to a SceneReference to indicate to the editor how scene creation should be handled. If this attribute is not applied to a SceneReference field, it will act as if *SaveLocation* is None.

Public Fields

AssetLocation SaveLocation

The folder to save the newly created scene in. Set this to None to disable scene creation.

string DefaultName

The name to assign to new scenes by default. If *SaveLocation* is Selectable, the name can be set when picking the save location. If *SaveLocation* is AssetRoot, this name will automatically have a number appended if a scene with the same name already exists.

string Creator

The name of a method on the owning object that can add objects to the newly created scene. The method should be static, return void, and take no parameters. The created scene will be the active scene so any objects created in this method will be added to the new scene. If this is not specified, an empty scene will be created.

SceneSource

PiRhoSoft. Composition Engine. Scene Source

Description

Defines how the scene to load is retrieved in a LoadSceneNode.

Values

SceneSource Value

The scene is specified directly in LoadSceneNode. Scene.

SceneSource Variable

The scene is resolved from the LoadSceneNode. Scene Variable Variable Reference.

SceneSource Name

The scene is loaded by name as specified by LoadSceneNode. SceneName.

SceneSource *Index*

The scene is loaded by build index as specified by LoadSceneNode. SceneIndex.

SceneSource

PiRhoSoft.CompositionEngine.SceneSource

Description

Defines how the scene to unload is retrieved in an UnloadSceneNode.

Values

SceneSource Value

The scene is specified directly in UnloadSceneNode. Scene.

SceneSource Variable

The scene is resolved from the UnloadSceneNode. Scene Variable Variable Reference.

SceneSource Name

The scene is unloaded by name as specified by UnloadSceneNode.SceneName.

SceneSource *Index*

The scene is unloaded by build index as specified by UnloadSceneNode.SceneIndex.

SceneVariableStore

PiRhoSoft. Composition Engine. Scene Variable Store: IVariable Store

Description

An IVariableStore implementation that allows the retrieval of GameObjects from the loaded scenes.

Public Methods

VariableValue GetVariable(string name)

Returns a VariableValue containing the GameObject with name *name*. The GameObject does not need to be enabled in order to access it with this method. If no GameObject is found with name *name*, VariableValue. *Empty* will be returned.

SetVariableResult SetVariable(string name, **VariableValue** value)

This will always return ReadOnly.

IList<string> GetVariableNames()

This will always return an empty list.

ScopedGraph

PiRhoSoft. Composition Engine. Scoped Graph: Instruction Graph

Description

An InstructionGraph with an entry branch, a main branch, and an exit branch. These branches will run in sequence but for organization purposes it is useful to think of *Enter* as a setup branch and *Exit* a cleanup branch that reverses any changes made in *Enter*.

Public Fields

InstructionGraphNode *Enter*

The branch that will run when the InstructionGraph is first run.

InstructionGraphNode *Process*

The branch that will run after *Enter* has completed.

InstructionGraphNode *Exit*

The branch that will run after *Process* has completed.

SelectionControl

PiRhoSoft. Composition Engine. Selection Control: Interface Control

Description

Add this to a Menu with a MenuInput to allow a MenuItem to be selected.

Public Properties

bool IsRunning (read only)

This will be true when a selection is in progress.

bool IsSelectionRequired (read only)

This will be true if the current selection requires an item to be selected.

bool IsClosing (read only)

This will be true when the selection will be closed on the next frame.

bool HasFocusedItem (read only)

This will be true when the Menu has a focused MenuItem.

bool HasSelectedItem (read only)

This will be true when a selection has been made.

MenuItem FocusedItem (read only)

The MenuItem that currently has focus, or null if there is no focused item.

int FocusedIndex (read only)

The index of the MenuItem that currently has focus, or -1 if there is no focused item.

VariableValue FocusedValue (read only)

The value associated with the MenuItem that currently has focus, or VariableValue. Empty if there is no focused item.

MenuItem SelectedItem (read only)

The MenuItem that has been selected, or null if no selection has been made.

int SelectedIndex (read only)

The index of the MenuItem that has been selected, or -1 if no selection has been made.

VariableValue *SelectedValue* (read only)

The value associated with the MenuItem that has been selected, or VariableValue. Empty if no selection has been made.

Public Methods

void Show(IVariableStore *variables*, **IEnumerable<MenuItemTemplate>** *items*, **bool** *isSelectionRequired*, **bool** *resetIndex*)

Show *items* on the sibling Menu. This will start a coroutine that waits for a selection to be made. If *isSelectionRequired* is true, the Menu will be required to have a selection made. If *resetIndex* is true, the Menu's focus will be set to the first item, otherwise the focus will not change. *variables* is used with *items* to resolve any VariableReferences.

void Select(MenuItem item)

Makes *item* the selected item and closes the menu.

void Close()

Closes the menu. If *IsSelectionRequired* is true, this will only succeed if a selection has been made.

Protected Methods

Transform GetItemParent() (virtual)

Implement this in subclasses to specify the Transform that created items should be added to. By default this is the Transform of this object.

void OnInitialize() (virtual)

Implement this in subclasses to perform setup when *Show* is called after the items have been created and menu has been set up.

void OnCreate() (virtual)

Implement this in subclasses to perform setup when *Show* is called after the items have been created but before the menu has been set up.

IEnumerator Run() (virtual)

Implement this in subclasses to perform custom handling for waiting for a selection. The default implementation will do nothing but yield until the control closes.

SelectionNode

PiRhoSoft. Composition Engine. Selection Node: Instruction Graph Node

Description

Add this to an InstructionGraph to show a SelectionControl and retrieve a selection from it.

Public Fields

InstructionGraphNode OnCanceled

The InstructionGraphNode to run when the selection is cancelled.

VariableReference Control

The SelectionControl to perform the selection with.

VariableReference SelectedItem

The variable to store the selected item in.

VariableReference SelectedIndex

The variable to store the index of the selected item in.

bool IsSelectionRequired

If this is true, a selection must be made before the node will complete.

bool AutoHide

If this is true, *Control* will be hidden once a selection has been made.

SelectionNodeItemList *Items*

The list of SelectionNodeItems available to be selected.

SelectionNodeItem

 $PiRhoSoft. Composition Engine. Selection Node Item: {\color{blue}MenuItemTemplate}$

Description

The information for an item in a SelectionNode.

Public Fields

InstructionGraphNode OnSelected

The InstructionGraphNode to run when this item is selected.

SelectionNodeItemList

PiRhoSoft. Composition Engine. Selection Node I tem List: Serialized List < Selection Node I tem Selection Node

Description

A list of SelectionNodeItems used by SelectionNode.

SequenceNode

PiRhoSoft. Composition Engine. Sequence Node: Instruction Graph Node, I Sequence Node

Description

Add this to an InstructionGraph to run a set of InstructionGraphNodes one after the other.

Public Fields

InstructionGraphNodeList Sequence

The list of InstructionGraphNodes to run.

SerializedDictionary

PiRhoSoft.UtilityEngine.SerializedDictionary<KeyType, KeyType>: Dictionary<KeyType, KeyType>

Description

Adds serialization and editor support to the built in Dictionary class.

Public Methods

void PrepareForEdit()

This is an editor support function and can be ignored.

void ApplyEdits()

This is an editor support function and can be ignored.

SerializedList

PiRhoSoft.UtilityEngine.SerializedList<*T*> : ICollection, IEnumerable<T>, IList<T>, IEnumerable, IReadOnlyCollection<T>, IReadOnlyList<T>, IList, ICollection<T>

Description

Adds improved editor support to the built in List class.

SetAnimationParameterNode

 $PiRhoSoft. Composition Engine. Set Animation Parameter Node: \underline{Instruction Graph Node}$

Description

Add this to an InstructionGraph to set a parameter on an Animator.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

StringVariableSource Parameter

The name of the parameter to set.

AnimatorControllerParameterType *Type*

The type of parameter to set.

VariableReference Animator

The Animator to set the parameter on.

BoolVariableSource BoolValue

If *Type* is Bool, the value to set using *SetBool*

IntVariableSource *IntValue*

If *Type* is Bool, the value to set using *SetInteger*

FloatVariableSource FloatValue

If *Type* is Float, the value to set using *SetFloat*

SetBindingNode

PiRhoSoft. Composition Engine. Set Binding Node: Instruction Graph Node

Description

Add this to an InstructionGraph to change the Value of a BindingRoot.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference *Object*

The BindingRoot to change Value on.

VariableReference Binding

The IVariableStore to set as the Value on Object.

SetVariableResult

PiRhoSoft.CompositionEngine.SetVariableResult

Description

The result returned from calls to IVariableStore. SetVariable indicating if a VariableValue was set successfully or why it failed.

Values

SetVariableResult Success

The Variable Value was set.

SetVariableResult *NotFound*

The Variable Value was not set because it could not be found and values cannot be added.

SetVariableResult *ReadOnly*

The Variable Value was not set because it is not allowed to be changed.

SetVariableResult *TypeMismatch*

The VariableValue was not set because the VariableType is not allowed to be changed.

ShowControlNode

 $PiRhoSoft. Composition Engine. Show Control Node: {\color{blue}Instruction Graph Node}$

Description

Add this to an InstructionGraph to show an InterfaceControl.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference Control

The InterfaceControl to show.

ShuffleNode

 $PiRhoSoft. Composition Engine. Shuffle Node: {\color{blue} Instruction Graph Node}$

Description

Add this to an InstructionGraph to shuffle the VariableValues in an IVariableList.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference Variable

The IVariableList to shuffle.

SimpleGraph

PiRhoSoft. Composition Engine. Simple Graph: Instruction Graph

Description

A basic InstructionGraph with a single branch.

Public Fields

InstructionGraphNode *Process*

The InstructionGraphNode to run when this graph runs.

SortConditionList

PiRhoSoft. Composition Engine. Sort Condition List: Serialized List < Variable Reference > 1000 MeV (Condition List)

Description

The list of VariableReferences used as conditions for a SortNode.

SortNode

PiRhoSoft.CompositionEngine.SortNode: InstructionGraphNode

Description

Sorts the Variable Values in an Variable List.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference List

The VariableList to sort.

bool SortByProperty

If this is true, *SortConditions* is used to sort the VariableValues by properties on each value. Otherwise the VariableValues are sorted directly.

SortConditionList SortConditions

The Variables on each item in *List* to sort by. When sorting by more than one property, the result will be fully sorted by the last property with equal values sorted by each previous property.

SpriteBinding

PiRhoSoft. Composition Engine. Sprite Binding: Variable Binding

Description

Add this to a SpriteRenderer to bind sprite to a variable.

Public Fields

VariableReference Variable

The Sprite that will be applied when the binding is updated.

Public Properties

SpriteRenderer *Sprite* (read only)

The component to set the sprite on.

SpriteColorBinding

PiRhoSoft.CompositionEngine.SpriteColorBinding: VariableBinding

Description

Add this to a SpriteRenderer to bind *color* to a variable.

Public Fields

VariableReference Variable

The Color Variable Value that will be applied when the binding is updated.

Public Properties

SpriteRenderer *Sprite* (read only)

The component to set the color on.

StartGraphTrigger

PiRhoSoft. Composition Engine. Start Graph Trigger: Instruction Trigger

Description

Add this to any GameObject to run an InstructionGraph when Start is called.

Stop Transition Node

 $PiRhoSoft. Composition Engine. Stop Transition Node: \underline{Instruction Graph Node}$

Description

Add this to an InstructionGraph to end the Transition currently running on the TransitionManager. If there is no Transition running this has no effect.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

StoreVariableConstraint

PiRhoSoft. Composition Engine. Store Variable Constraint: Variable Constraint

Description

A VariableConstraint for Store VariableValues that specifies the Variables that are available in the store.

Public Fields

VariableSchema Schema

The schema defining the Variables that are in the store.

StoreVariableSource

PiRhoSoft. Composition Engine. Store Variable Source: Variable Source < IVariable Store > 100 for the control of the control

Description

A VariableSource for IVariableStores.

StringBinding

PiRhoSoft.CompositionEngine.StringBinding: VariableBinding

Description

Derive from this class to implement a VariableBinding that sets the text on a TextMeshPro.

Public Fields

bool AutoSizeContainer

Set this to true to set *autoSizeTextContainer* on *Text*. This property is otherwise not exposed to the editor, but is necessary in some situations to ensure an Auto Layout ui is sized correctly.

Public Properties

TMP_Text Text (read only)

The component to set the text on.

Protected Methods

void SetText(string text, bool enabled)

Call this from subclasses to set *Text*'s text to *text*. *Text* will also be enabled or disabled according to the *enabled* parameter.

StringVariableConstraint

 $PiRhoSoft. Composition Engine. String Variable Constraint: {\bf Variable Constraint}$

Description

A VariableConstraint for String VariableValues that restricts the value to one of a set of values.

Public Fields

string[] Values

The allowed values.

StringVariableSource

 $PiRhoSoft. Composition Engine. String Variable Source: {\tt Variable Source {\tt <string {\tt >}}}$

Description

A VariableSource for String VariableValues.

Constructors

StringVariableSource(string *defaultValue***)**

Initializes the source to *Type* Value with *Value* _defaultValue.

TagList

PiRhoSoft. Composition Engine. Tag List: Serialized List < string >

Description

The serializable list of tags in a VariableSchema.

TextBinding

PiRhoSoft.CompositionEngine.TextBinding: StringBinding

Description

Add this to a TextMeshPro to bind the text to a variable.

Public Fields

VariableReference Variable

The VariableValue that will be converted to a string and applied when the binding is updated. To perform custom formatting for Int or Float VariableValues use NumberBinding.

TextColorBinding

PiRhoSoft.CompositionEngine.TextColorBinding: VariableBinding

Description

Add this to a TextMeshPro to bind the text color to a variable.

Public Fields

VariableReference Variable

The Color Variable Value that will be applied when the binding is updated.

Public Properties

TMP_Text Text (read only)

The component to set the color on.

TextInputBinding

PiRhoSoft.CompositionEngine.TextInputBinding: VariableBinding

Description

Add this to a TMP_InputField to apply entered text to a variable.

Public Fields

VariableReference Variable

The variable to apply the text to when it changes.

Public Properties

TMP_InputField Text (read only)

The component to get the text from.

TimeFormatType

PiRhoSoft.CompositionEngine.TimeFormatType

Description

Defines the time formats available to set for the *TimeFormatting* of a BindingFormatter.

Values

TimeFormatType SecondsMilliseconds

The number will be printed in seconds and milliseconds. Equivalent to setting the custom format string to "s\.fff".

TimeFormatType *MinutesSeconds*

The number will be printed in minutes and seconds. Equivalent to setting the custom format string to "m\:ss".

TimeFormatType *MinutesSecondsMilliseconds*

The number will be printed in minutes, seconds, and milliseconds. Equivalent to setting the custom format string to "m\:ss\.fff".

TimeFormatType *HoursMinutes*

The number will be printed in hours and minutes. Equivalent to setting the custom format string to "h\:mm".

TimeFormatType Custom

The format string will be read from the *ValueFormat* property of the *BindingFormatter*.

TimelineVariableSource

PiRhoSoft. Composition Engine. Timeline Variable Source: Variable Source < Timeline Asset > 1000 for the control of the cont

Description

A VariableSource for Object VariableValues that must be TimelineAssets.

TimeScaleNode

PiRhoSoft. Composition Engine. Time Scale Node: Instruction Graph Node

Description

Add this to an InstructionGraph to set timeScale.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

FloatVariableSource TimeScale

The value to set *timeScale* to.

TransformNode

PiRhoSoft.CompositionEngine.TransformNode: InstructionGraphNode

Description

Add this to an InstructionGraph to animate the Transform of a GameObject.

Public Fields

InstructionGraphNode Next

Add this to an InstructionGraph to run an Expression.

VariableReference Transform

The Transform to animate.

bool UseRelativePosition

If this is true, *TargetPosition* will be added to the position of the *Transform* when the node starts. Otherwise, *TargetPosition* will be used directly.

bool UseRelativeRotation

If this is true, *TargetRotation* will be added to the rotation of the *Transform* when the node starts. Otherwise, *TargetRotation* will be used directly.

bool UseRelativeScale

If this is true, *TargetScale* will be multiplied with the scale of the *Transform* when the node starts. Otherwise, *TargetScale* will be used directly.

Vector3VariableSource TargetPosition

The position to move *Transform* toward.

Vector3VariableSource *TargetRotation*

The rotation to rotate *Transform* toward.

Vector3VariableSource TargetScale

The size to scale *Transform* toward.

AnimationType AnimationMethod

Specifies the advancement method of the animation.

bool WaitForCompletion

If this is true, this node will not complete until the animation has completed. Otherwise, this node will complete immediately.

FloatVariableSource Duration

If AnimationMethod is Duration, the number of seconds the animation will take.

FloatVariableSource MoveSpeed

If *AnimationMethod* is Speed, the number of units per second to move the Transform.

FloatVariableSource RotationSpeed

If *AnimationMethod* is Speed, the number of radians per second to rotate the Transform.

FloatVariableSource ScaleSpeed

If *AnimationMethod* is Speed, the number of units per second to scale the Transform.

Transition

PiRhoSoft.CompositionEngine.Transition: ScriptableObject

Description

The base class for assets that perform postprocessing of the rendered scene over a time period.

Public Fields

Shader Shader

The Shader that the transition will use to display its effect

float Duration

The time in seconds the transition should last.

Public Methods

void Begin(TransitionPhase phase) (virtual)

Implement this to setup properties when the transition is started.

void Process(float time, TransitionPhase phase) (virtual)

Implement this to animate properties of the transition as time advances.

void End() (virtual)

Implement this to perform any clean up of the transition.

void Render(RenderTexture source, RenderTexture destination) (virtual)

Renders the transition using *source* as the input scene and *destination* as the target. The Graphics. *Blit* methods are used to copy the texture using *Material*. To fully customize rendering, this can be overridden, but for must situations updating properties of *Material* in *Update* is sufficient.

Protected Properties

Material Material (read only)

The Material the effect will be rendered with. This is created with a call to SetShader.

Protected Methods

void SetShader(string name)

Creates the material using the specified shader. *name* is the name set for the shader at the beginning of the shader script. This should be called from subclasses during initialization.

void Update() (virtual)

Implement this to update the material properties of Material.

TransitionList

 $PiRhoSoft. Composition Engine. Transition List: {\tt SerializedList{\-Composition}\-Engine.}$

Description

A serializable list of Transitions.

TransitionManager

PiRhoSoft.CompositionEngine.TransitionManager: GlobalBehaviour<TransitionManager>

Description

Manages the loaded TransitionRenderers for playback of Transitions. This is created on demand and should not be added to a scene.

Public Properties

Transition CurrentTransition (read only)

The Transition that is currently running, or null if no Transition is running.

Public Methods

IEnumerator RunTransition(Transition transition, **TransitionPhase** phase)

Runs *transition* in TransitionPhase *phase* and ends it when it has completed - *EndTransition* will not need to be called.



If a Transition is already running, it will be ended.

IEnumerator StartTransition(Transition transition, **TransitionPhase** phase)

Runs transition in TransitionPhase phase. EndTransition (or a subsequent call to StartTransition) should be called manually later.



If a Transition is already running, it will be ended.

void EndTransition()

Ends the currently running Transition if one is running.

TransitionPhase

PiRhoSoft.CompositionEngine.TransitionPhase

Description

Defines the phases of a Transition to allow a Transition to perform differently depending on how it is being used.

Values

TransitionPhase Out

The Transition should transition away from the rendered scene into its obscured state (fade out for example).

TransitionPhase Obscure

The Transition should obscure the rendered scene for an indeterminate amount of time while the loaded content is changing.

TransitionPhase In

The Transition should transition from its obscured state into the rendered scene (fade in for example).

TransitionRenderer

 $PiRhoSoft. Composition Engine. Transition Renderer: {\color{blue}MonoBehaviour}$

Description

Add this to a Camera to have any running Transition include the cameras rendered output in its post processing.

TransitionVariableSource

PiRhoSoft. Composition Engine. Transition Variable Source: Variable Source < Transition > 1000 and 1

Description

A VariableSource for Object VariableValues that must be Transitions.

UnloadSceneNode

PiRhoSoft.CompositionEngine.UnloadSceneNode: InstructionGraphNode

Description

Add this to an InstructionGraph to unload a scene.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

SceneSource Source

Specifies how the scene to unload is retrieved.

SceneReference Scene

If Source is Value, holds the scene to unload.

VariableReference SceneVariable

If *Source* is Variable, references the scene to unload. If the resolved value is an Int, the scene will be uloaded by index. If it is a String, it will be unloaded by name.

string SceneName

If *Source* is Name, the name of the scene to unload.

int SceneIndex

If Source is Index, the build index of the scene to unload.

bool WaitForCompletion

If this is true, this node will not complete until the scene has completed unloading. Otherwise, this node will complete immediately and the InstructionGraph will continue.

bool CleanupAssets

If this is true (the default), Resources. Unload Unused Assets will be called after the scene has been unloaded.

UpdateBindingNode

PiRhoSoft.CompositionEngine.UpdateBindingNode: InstructionGraphNode

Description

Add this to an InstructionGraph to update the VariableBindings on a GameObject and its descendants.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

VariableReference Object

The GameObject containing the VariableBindings to update.

string Group

The *BindingGroup* of VariableBindings to update. If this is empty, all VariableBindings in *Object* will be updated.

bool WaitForCompletion

If this is true, this node will not complete until any animated bindings have finished animating. Otherwise, this node will complete immediately.

ValueDefinition

PiRhoSoft.CompositionEngine.ValueDefinition: ValueType

Description

Defines properties for how a VariableValue is initialized and can be used, usually as part of a VariableSchema. The *Generate* method can be used to create a VariableValue that satisfies the properties of the definition.

Static Methods

ValueDefinition Create(VariableType *type***)**

Creates a definition for a Variable Value with type type and no other constraints.

ValueDefinition Create(int *minimum*, **int** *maximum*)

Creates a definition for a VariableValue with type Int and with a constraint restricting it to values between *minimum* and *maximum*.

ValueDefinition Create(float minimum, float maximum)

Creates a definition for a VariableValue with type Float and with a constraint restricting it to values between *minimum* and *maximum*.

ValueDefinition Create(string[] *values***)**

Creates a definition for a VariableValue with type String and with a constraint restricting it to one of the values in *values*.

ValueDefinition Create<T>()

Creates a definition for a VariableValue with type Object whose value can be set to any Object that is type *T* or is derived from type *T*.

ValueDefinition Create(Type *type***)**

Creates a definition for a Variable Value with type determined by Variable Value. Get Type.

ValueDefinition Create(VariableType type, VariableConstraint constraint)

Creates a definition for a VariableValue with type type and VariableConstraint constraint constraint.



The caller must ensure *constraint* is a VariableConstraint of the appropriate type for *type*.

ValueDefinition Create(VariableType type, VariableConstraint constraint, string tag, Expression initializer, bool isTypeLocked, bool isConstraintLocked)

Creates a definition with the given properties.



The caller must ensure *constraint* is a VariableConstraint of the appropriate type for *type*.

Public Properties

VariableType Type (read only)

The VariableType to assign to VariableValues created by *Generate* or to test against with *IsValid*. If this is Empty, the VariableValue can be any type.

VariableConstraint *Constraint (read only)*

The VariableConstraint laying out *Type* dependent requirements for VariableValues using this definition. This can be null, and in that case, the only constraint for VariableValues will be *Type*.

string *Tag* (read only)

An arbitrary string that can be used to group different definitions in the same VariableSchema. This has no impact on the validity of a VariableValue or how it is generated. It is most commonly used to indicate a set of variables that should be saved (for runtime saves) or group variables for resetting to their defaults (i.e by VariableSetComponent.ResetTag) or any other class that implements IVariableReset.ResetTag).

Expression *Initializer* (read only)

The Expression to evaluate when calling *Generate* to determine the initial value of the VariableValue. If the Expression is not set, a VariableValue with the default for *Type* will be generated.

bool IsTypeLocked (read only)

Indicates to the editor that this definition cannot have *Type* changed.

bool *IsConstraintLocked* (read only)

Indicates to the editor that this definition cannot have *Constraint* changed. The properties of *Constraint* can be changed, but the *Constraint* itself cannot.

Public Methods

VariableValue Generate(IVariableStore variables)

Generates a VariableValue that satisfies the constraints laid out by this definition with initial value determined by *Initializer*.

bool IsValid(VariableValue value)

Returns true if *value* satisfies the runtime constraints specified by this definition.

ValueDefinitionList

PiRhoSoft. Composition Engine. Value Definition List: Serialized List < Value Definition >

Description

A serializable list of ValueDefinitions.

Variable

PiRhoSoft.CompositionEngine.Variable: ValueType

Description

Associates a name with a Variable Value.

Static Properties

Variable Empty (read only)

A Variable with an empty Name and Value with VariableType Empty.

Static Methods

Variable Create(string name, VariableValue value)

Creates a Variable with Name name and _Value value.

Public Properties

string Name (read only)

The name assigned to the variable.

VariableValue Value (read only)

The value assigned to the variable.

VariableBinding

PiRhoSoft.CompositionEngine.VariableBinding: MonoBehaviour

Description

Derived from this class to provide support for automatically updating properties of loaded GameObjects (for instance, user interface elements) based on VariableValues stored in the Variables System.

Read the Bindings Topic for a complete overview of how to use bindings and how to implement custom bindings.

Static Methods

void UpdateBinding(GameObject obj, string group, BindingAnimationStatus status)

Triggers an update for bindings on *obj* and its descendants. If *group* is null or empty, all bindings will be updated, otherwise all bindings with *BindingGroup* matching *group* will be updated. Optionally pass a *BindingAnimationStatus* instance as *status* to access information about bindings that perform an animation or otherwise take multiple frames to complete.

void UpdateBinding(GameObject *obj*, **string** *group*, **BindingAnimationStatus** *status*, **List** <**VariableBinding>** *bindings*)

Performs the same function as the other *UpdateBinding* method but uses *bindings* as a location to store the VariableBindings looked up on *obj*. It is not necessary to use this overload exception when called from the *UpdateBinding* instance method of a VariableBinding subclass.

Public Fields

string BindingGroup

An arbitrary string used to allow the binding to be targeted by calls to *UpdateBinding*. This has two common uses: for performance, if a GameObject has many bindings that don't all need to be updated at the same time, different bindings can be updated individually or as a group. And, if the value behind a binding is updated but that update shouldn't be indicated to the player until some point in the future, the update can be deferred until that time.

bool AutoUpdate

If this is true, the binding will be updated every frame, thus always keeping it up to date with the Variable Values it is bound to.

bool SuppressErrors

If this is true, failure to resolve VariableReferences when updating the binding will be considered a valid condition and therefore not log error messages.



Errors when executing Expressions will not be suppressed. This is because Expressions handle errors with exceptions which result in allocations.

Public Properties

IVariableStore Variables (read only)

Returns the IVariableStore to use to resolve VariableReferences for this binding. The IVariableStore will be found using BindingRoot.FindParent.

Public Methods

void UpdateBinding(string group, BindingAnimationStatus status)

Use this method to update this specific binding when *group* is either null, empty, or matches *BindingGroup*. To update all bindings on an GameObject, use the static *UpdateBinding* method instead. Optionally pass a *BindingAnimationStatus* instance as *status* to access information about bindings that perform an animation or otherwise take multiple frames to complete.

Protected Methods

void UpdateBinding(IVariableStore variables, BindingAnimationStatus status) (abstract)

Implement this in subclasses to perform the binding. *variables* is the IVariableStore VariableReferences should be looked up with. For bindings that take multiple frames to complete, *status* should be updated to indicate when the binding has started and finished.



status will always be a valid instance so does not need to be checked for null.

Resolve

This collection of methods will lookup the value referenced by a VariableReference. The resolved value is set to the ouput parameter *result* and the return value will indicate whether the value was resolved successfully. The *variables* parameter should be the *variables* parameter passed to the *UpdateBinding* method. If the resolution fails, either due to the variable not being found or it being an invalid type, a warning will be printed to the Console.

- bool Resolve(IVariableStore variables, VariableReference reference, VariableValue result (out))
- bool Resolve(IVariableStore variables, VariableReference reference, bool result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, int result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, float result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector2Int result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector3Int result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, RectInt result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, BoundsInt result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector2 result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector3 result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Vector4 result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Quaternion result (out))::

- bool Resolve(IVariableStore variables, VariableReference reference, Rect result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Bounds result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, Color result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, string result (out))::
- bool Resolve<EnumType>(IVariableStore variables, VariableReference reference, EnumType result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, IVariableStore result (out))::
- bool Resolve(IVariableStore variables, VariableReference reference, IVariableList result (out))::
- bool ResolveObject<ObjectType>(IVariableStore variables, VariableReference reference ObjectType result (out))::
- bool ResolveStore<StoreType>(IVariableStore variables, VariableReference reference, StoreType result (out))::
- bool ResolveList<ListType>(IVariableStore variables, VariableReference reference, ListType result (out))::
- bool ResolveInterface<InterfaceType>(IVariableStore variables, VariableReference reference, InterfaceType result (out))::
- bool ResolveReference(IVariableStore variables, VariableReference reference, Object result (out))::

void Assign(IVariableStore variables, VariableReference reference, VariableValue value)

Assigns *value* to the variable referenced by *reference*. The *variables* parameter should be the *variables* parameter passed to the *UpdateBinding* method. If the assignment fails, a warning will be logged.

VariableConstraint

PiRhoSoft. Composition Engine. Variable Constraint

Description

VariableConstraint is the base class for constraints applied to ValueDefinitions. For each relevent VariableType an implementation of this class is provided. These are:

Туре	Constraint	
Enum	EnumVariableConstraint	
Float	FloatVariableConstraint	
Int	IntVariableConstraint	
List	ListVariableConstraint	
Object	ObjectVariableConstraint	
Store	StoreVariableConstraint	
String	StringVariableConstraint	

Public Methods

bool IsValid(VariableValue value) (abstract)

Returns true if *value* satisfies the rules of this constraint.

VariableConstraintAttribute

PiRhoSoft.CompositionEngine.VariableConstraintAttribute: Attribute

Description

Add this to a VariableReference or VariableSource field to inform the editor of the type of VariableValue the code is expecting, thereby providing a more useful editor for the field.

Constructors

VariableConstraintAttribute(VariableType type)

Specifies the corresponding field should have VariableType type.

VariableConstraintAttribute(int minimum, int maximum)

Specifies the corresponding field should have VariableType Int and value between *minimum* and *maximum*.

VariableConstraintAttribute(float minimum, float maximum)

Specifies the corresponding field should have VariableType Float and value between *minimum* and *maximum*.

VariableConstraintAttribute(string[] values)

Specifies the corresponding field should have VariableType String and value one of the options in *values*.

VariableConstraintAttribute(Type *type***)**

Specifies the corresponding field should have VariableType as determined by VariableValue. *GetType*.

VariableDefinition

PiRhoSoft. Composition Engine. Variable Definition: Value Type

Description

Extends a ValueDefinition by associating it with a name. All of the heavy lifting for for constraining VariableValues is provided by ValueDefinition.

Public Fields

string Name

The name of *Definition*.

ValueDefinition *Definition*

The ValueDefinition being given Name.

VariableDefinitionList

PiRhoSoft. Composition Engine. Variable Definition List: Serialized List < Variable Definition > 1.00% and 1.00% a

Description

A serializable list of VariableDefinitions.

VariableHandler

PiRhoSoft.CompositionEngine.VariableHandler

Description

A utility class for working with VariableValues independent of their VariableType.

Static Methods

string ToString(VariableValue value)

Returns the string representation of *value* depending on the VariableType it is holding.

VariableValue CreateDefault(VariableType type, VariableConstraint constraint)

Creates and returns a variable with type *type* whose value meets the requirements of *constraint*. If *constraint* is null, the default value for type *type* is returned.

void ToString(VariableValue value, StringBuilder builder)

Appends the string representation of *value* to *builder*.

List<string> SaveVariables(IList<Variable> variables, **List** objects (ref))

Converts the Variables in *variables* to a representation that can be serialized by Unity. The returned list of strings, as well as *objects*, should be assigned to serializable fields an an object.

List<Variable> LoadVariables(List data (ref), List objects (ref))

Creates a set of variables from the serialized representation in *data* and *objects*. *data* and *objects* will be cleared.

string SaveVariable(Variable variable, List objects (ref))

Converts *variable* to a representation that can be serialized by Unity. The returned string and *objects* should be assigned to serializable fields on an object.

Variable LoadVariable(string data (ref), List objects (ref))

Creates a variable from the serialized representation in *data* and *objects*. *data* and *objects* will be cleared.

string SaveValue(VariableValue value, List objects (ref))

Converts *value* to a representation that can be serialized by Unity. The returned string and *objects* should be assigned to serializable fields on an object.

Variable Value Load Value (string data (ref), List objects (ref))

Creates a value from the serialized representation in *data* and *objects*. *data* and *objects* will be cleared.

string SaveConstraint(VariableType type, VariableConstraint constraint, List objects (ref))

Saves *constraint* with type *type* to a representation that can be serialized by Unity. The returned string and *objects* should be assigned to serializable fields on an object.

VariableConstraint LoadConstraint(string data (ref), List objects (ref))

Creates a constraint from the serialized representation in *data* and *objects*. _*data* and *objects* will be cleared.

VariableValue Add(VariableValue left, VariableValue right)

Returns the result of adding *left* to *right*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Subtract(VariableValue left, VariableValue right)

Returns the result of subtracting *right* from *left*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Multiply(VariableValue left, VariableValue right)

Returns the result of multiplying *left* and *right*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Divide(VariableValue left, VariableValue right)

Returns the result of dividing *left* by *right*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Modulo(VariableValue left, VariableValue right)

Returns the remainder of dividing *left* by *right*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Exponent(VariableValue left, VariableValue right)

Returns the result of raising *left* to the *right* power. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

VariableValue Negate(VariableValue value)

Returns the result of inverting *value*. If the result cannot be computed due to invalid or incompatible types, VariableValue.Empty will be returned.

Nullable < bool > Is Equal (Variable Value left, Variable Value right)

Returns true if *left* and *right* are equal, false if *left* and *right* can be legally compared but are not equal, and null if the types cannot be compared.

Nullable<int> Compare(VariableValue *left*, **VariableValue** *right*)

Returns -1 if *left* is less than *right*, 1 if *left* is greater than *right*, 0 if *left* is equal to *right*, and null if the types cannot be compared.

VariableValue Lookup(VariableValue owner, VariableValue lookup)

Returns a value contained in *owner* based on the value of *lookup*. If *lookup* is not found, VariableValue.Empty will be returned.

SetVariableResult Apply(VariableValue owner (ref), VariableValue lookup, VariableValue value)

Sets a value contained in *owner* based on *lookup* to *value*. *owner* will be updated to the new value. If *owner* is not holding a reference as determined by VariableValue.IsReference it must be reassigned to the container it is being held in. The return value indicates success or the reason

for failure.

VariableValue Cast(VariableValue owner, string type)

Returns the value of *owner* converted to type *type*. For object values, this is used to lookup sibling components.

bool Test(VariableValue owner, string type)

Determines if a *Cast* to *type* would be successful.

VariableInitializerType

PiRhoSoft. Composition Engine. Variable Initializer Type

Description

Defines the options for how a VariableValue will be initialized when created from a ValueDefinition in a VariableSchema.

Values

VariableInitializerType Expression

The Variable Value will be initialized with the result of an Expression.

VariableInitializerType DefaultValue

The Variable Value will be initialized to a specific value set in the editor.

VariableInitializerType None

The Variable Value will be initialized to the default value for its type.

VariableLink

 $PiRhoSoft. Composition Engine. Variable Link: {\color{blue}MonoBehaviour}$

Description

Add this to any GameObject to add a custom set of Variables to CompositionManager. Global.

Public Fields

VariablePool Variables

The Variables to add to CompositionManager. Global while this MonoBehaviour is enabled.

VariableList

PiRhoSoft.CompositionEngine.VariableList: IVariableList

Description

An implementation of IVariableList that has no constraints on the ValueValues it can hold.

Constructors

VariableList(int count)

Adds count Empty ValueValues to the list.

Public Properties

List<VariableValue> Values (read only)

The Variable Values in the list.

int Count (read only)

The number of Variable Values in the list.

Public Methods

VariableValue GetVariable(int index)

Returns the VariableValue at index *index* in the list. If *index* is not between 0 and *Count*, VariableValue.*Empty* will be returned.

SetVariableResult AddVariable(VariableValue *value*)

Adds value to the list. This will always succeed and return Success.

SetVariableResult RemoveVariable(int index)

Removes the Variable Value at index index from the list.

SetVariableResult SetVariable(int index, VariableValue value)

Changes the Variable Value at index index to value.

VariablePool

PiRhoSoft.CompositionEngine.VariablePool: VariableStore

Description

An IVariableStore that allows an arbitrary set of VariableValues to be added in the editor with a ValueDefinition.

Public Fields

List<ValueDefinition> *Definitions*

Provides the editor access to the definitions. This should not be accessed at runtime.

Public Methods

void ChangeName(int index, string name)

This is an editor support function that can be ignored.

void ChangeDefinition(int index, ValueDefinition definition)

This is an editor support function that can be ignored.

SetVariableResult SetVariable(int index, **VariableValue** value)

This is an editor support function that can be ignored.

VariablePoolAsset

PiRhoSoft. Composition Engine. Variable Pool Asset: Scriptable Object, IV ariable Store

Description

An asset for storing an arbitrary set of Variables using a VariablePool.

Public Fields

VariablePool Variables

The Variables stored by this asset.

Public Methods

VariableValue GetVariable(string *name*)

The names of all the Variables stored by this asset.

SetVariableResult SetVariable(string name, VariableValue value)

Returns the Variable Value with name name.

IList<string> GetVariableNames()

Sets the Variable Value with name name to _value.

VariablePoolComponent

 $PiRhoSoft. Composition Engine. Variable Pool Component: {\color{red}MonoBehaviour, IVariable Store}$

Description

Add this to any GameObject to define an arbitrary set of Variables using a VariablePool.

Public Fields

VariablePool Variables

The Variables stored by this behaviour.

Public Methods

IList<string> GetVariableNames()

The names of all the Variables stored by this behaviour.

VariableValue GetVariable(string *name*)

Returns the Variable Value with name name.

SetVariableResult SetVariable(string name, **VariableValue** value)

Sets the Variable Value with name name to _value.

VariableReference

PiRhoSoft.CompositionEngine.VariableReference

Description

Specifies the name and location of a VariableValue for lookup or assignment. Read the Accessing Variables topic for more information.

Static Fields

string Cast

The text to use in *Variable* to lookup a sibling Component when referencing a Component or GameObject. This is set to as.

Char Separator

The character to use to separate the variable names in *Variable*. This is set to '.'.

Char LookupOpen

The character to use in *Variable* to specify an index. This is set to '['.

Char LookupClose

The character to use in *Variable* after specifying an index. This is set to ']'.

Public Properties

bool IsValid (read only)

Returns true if *Variable* contains a valid statement. This only verifies the syntax, it does not check if the variable exists.

bool IsAssigned (read only)

Returns true if *Variable* has been assigned regardless of if it's valid or not.

string StoreName (read only)

The first part of *Variable* (i.e the section before the first *Separator*).

string RootName (read only)

The second part of *Variable* (i.e the section between the first and second *Separator*).

string Variable

The reference to the Variable Value.

Public Methods

VariableValue GetValue(IVariableStore variables)

Returns the referenced Variable Value by looking up Variable on variables.

SetVariableResult SetValue(IVariableStore variables, VariableValue value)			
Sets the referenced VariableValue by looking up Variable on variables and assigning it value	•		

VariableSchema

PiRhoSoft.CompositionEngine.VariableSchema: ScriptableObject

Description

A VariableSchema is used to define the variables that are available to a variable store object - usually a VariableSetComponent or VariableSetAsset. This improves the editor experience for working with those object types along with enforcing constraints so typos or other mistaken accesses can be caught and reported at runtime.

Public Fields

VariableInitializerType InitializerType

Specifies how the initializer for each ValueDefinition will be displayed in the editor and ultimately how VariableValues created by this schema will be initialized.

TagList Tags

Specifies the set of tags that can be selected in the editor for each ValueDefinition added to this schema.

Public Properties

int Version (read only)

The current version of the schema. This is incremented every time any change is made to the schema so objects using it know to update themselves. These updates are automatically managed by VariableSetComponent and VariableSetAsset and any class derived from them.

int Count (read only)

The number of VariableDefinitions that have been added to this schema.

VariableDefinition this[int *index*]

Sets or returns the VariableDefinition at index index.



VariableDefinition is a struct so any changes made to the returned definition will not change the actual schema. Reassign the definition using this indexer to apply the change.

Public Methods

int GetIndex(string name)

Returns the index of the VariableDefinition with *Name name* or -1 if no VariableDefinition has been added with that name.



Variable names are case sensitive.

bool HasDefinition(string name)

Returns true if this schema has a VariableDefinition with *Name name*.

bool AddDefinition(string name, VariableType type)

Adds a new VariableDefinition to the schema with *Name name* and *Type type*. If a definition with that name has already been added, nothing will happen and this method will return false. If the definition is successfully added this method will return true.

void RemoveDefinition(int index)

Removes the VariableDefinition at index index from this schema.

VariableSet

PiRhoSoft.CompositionEngine.VariableSet: IVariableReset

Description

Holds a serializable list of Variables that are defined by a VariableSchema. This is most often used with a MappedVariableStore.

Public Properties

VariableSchema Schema (read only)

The VariableSchema that defines the Variables in the set.

IVariableStore Owner (read only)

The IVariableStore that this is a member of.

bool NeedsUpdate (read only)

This will be true if *Schema* has changed since the last time this set was updated.

int VariableCount (read only)

The number of Variables in the set.

Public Methods

void LoadFrom(VariableSet variables, string tag)

Copy all the Variables in variables with Tag tag into this set. This is for runtime persistence of game state.

void SaveTo(VariableSet variables, string tag)

Copy all the Variables in this set with *Tag tag* into *variables*. This is for runtime persistence of game state.

void Setup(VariableSchema schema, IVariableStore owner)

Associate this set with *schema* and *owner*. If *schema* has changed since the last time this was called, the Variables will be updated.

void Update()

This is an editor support function and can be ignored.

void Reset(int index)

Resets the Variable at index to its default value defined in Schema.

void Clear()

Disassociates this set with Schema and Owner and removes all its Variables.

string GetVariableName(int index)

Returns the name of the Variable at index index.

VariableValue GetVariableValue(int index)

Returns the Variable Value of the Variable at index index

SetVariableResult SetVariableValue(int index, **VariableValue** value)

Sets the Variable Value of the Variable at index index to value.

void ResetTag(string tag)

Resets all Variables with Tag tag to their default value defined in Schema.

void ResetVariables(IList<string> variables)

Resets all Variables in variables to their default value defined in Schema.

VariableSetAsset

PiRhoSoft.CompositionEngine.VariableSetAsset: ScriptableObject, ISchemaOwner, IVariableReset, IVariableStore

Description

An asset for storing Variables that are defined by a VariableSchema. This can also be used as a base class for assets that need to expose variables defined in code to the variables system.

Public Fields

VariableSet Variables

The Variables stored by this asset that are defined in *Schema*.

Public Properties

VariableSchema Schema (read only)

The VariableSchema used to define Variables.

MappedVariableStore Store (read only)

The store providing the mapping for all the Variables in this asset - both *Variables* and those defined in code using VariableMapping.

Public Methods

void SetupSchema()

One time setup to initialize Store. This is managed automatically.

VariableValue GetVariable(string name)

Returns the variable, defined by either *Schema* or with Variable Mappings with name *name*.

SetVariableResult SetVariable(string name, **VariableValue** value)

Sets the variable, defined by either *Schema* or with VariableMappings, with name *name* to value.

IList<string> GetVariableNames()

Returns the names of all the variables, defined by either Schema or with VariableMappings.

void ResetTag(string tag)

Resets all the variables defined in *Schema* with with tag *tag*.

void ResetVariables(IList<string> variables)

Resets all the variables in variables.

VariableSetComponent

PiRhoSoft.CompositionEngine.VariableSetComponent : MonoBehaviour, ISchemaOwner, IVariableReset, IVariableStore

Description

Add this to any GameObject to store Variables that are defined by a VariableSchema. This can also be used as a base class for behaviours that need to expose variables defined in code to the variables system.

Public Fields

VariableSet Variables

The Variables stored by this asset that are defined in Schema.

Public Properties

VariableSchema Schema (read only)

The VariableSchema used to define Variables.

MappedVariableStore Store (read only)

The store providing the mapping for all the Variables in this asset - both *Variables* and those defined in code using VariableMapping.

Public Methods

void SetupSchema()

One time setup to initialize *Store*. This is managed automatically.

VariableValue GetVariable(string name)

Returns the variable, defined by either *Schema* or with VariableMappings with name *name*.

SetVariableResult SetVariable(string name, **VariableValue** value)

Sets the variable, defined by either *Schema* or with VariableMappings, with name *name* to *value*.

IList<string> GetVariableNames()

Returns the names of all the variables, defined by either *Schema* or with VariableMappings.

void ResetTag(string tag)

Resets all the variables defined in *Schema* with with tag tag.

void ResetVariables(IList<string> variables)

Resets all the variables in variables.

VariableSource

PiRhoSoft.CompositionEngine.VariableSource

Description

A wrapper type for fields that allows a value to be set directly or set to a VariableReference. VariableSource<_T_> provides a generic implementation that is sufficient for all use cases.

Public Fields

VariableSourceType *Type*

Whether this source has a value or VariableReference. If this is set to *Value* the subclass will include the value field of the correct type.

VariableReference Reference

If *Type* is set to *Reference*, this holds the VariableReference where the VariableValue should be looked up.

Public Methods

void GetInputs(IList<VariableDefinition> inputs)

If *Type* is set to *Reference* and *Reference* accesses <u>InstructionStore</u>. *Inputs*, adds the definition for *Reference* to *inputs*.

Protected Methods

ValueDefinition GetInputDefinition() (abstract)

Implement this in a subclass to return a definiton for the represented type.

VariableSource

PiRhoSoft.CompositionEngine.VariableSource<T>: VariableSource

Description

An implementation of VariableSource that exposes the value to use when *Type* is set to *Value*. Because Unity cannot serialize fields of generic types this class is defined as abstract. Therefore, concrete types for each value type must be implemented. The following built in variable sources are included:

	Туре
BoolVariableSource	bool
IntVariableSource,	int
FloatVariableSource,	float
Int2VariableSource,	Vector2Int
Int3VariableSource,	Vector3Int
IntRectVariableSource,	RectInt
IntBoundsVariableSource,	BoundsInt
Vector2VariableSource,	Vector2
Vector3VariableSource,	Vector3
Vector4VariableSource,	Vector4
QuaternionVariableSource,	Quaternion
RectVariableSource,	Rect
BoundsVariableSource,	Bounds
ColorVariableSource,	Color
StringVariableSource,	string
ObjectVariableSource,	Object
GameObjectVariableSource,	GameObject
StoreVariableSource,	IVariableStore
ListVariableSource,	IVariableList
VariableValueSource,	VariableValue

Variable sources for additional types can be added by deriving from this class.

Public Fields

T Value

If *Type* is set to *Value*, this holds the value the owner should use for this variable.

VariableSourceType

PiRhoSoft. Composition Engine. Variable Source Type

Description

Used by VariableSource to specify how a VariableValue is retrieved.

Values

VariableSourceType Value

The value is specified directly.

VariableSourceType Reference

The value is looked up from a VariableReference.

VariableStore

PiRhoSoft.CompositionEngine.VariableStore: IVariableStore

Description

An IVariableStore that allows an arbitrary set of VariableValues to be added.

Public Properties

List<string> Names (read only)

The names of the Variable Values in the store.

List<VariableValue> Variables (read only)

The Variable Values in the store.

Dictionary<**string**, **string**> *Map* (read only)

The dictionary that maps names to indexes of the Variable Values.

Public Methods

void AddVariable(string name, VariableValue value) (virtual)

Adds *value* to the store and assigns it the name *name*.

bool RemoveVariable(string name)

Removes the Variable Value with name *name* from the store. If *name* does not exist, false is returned.

void RemoveVariable(int index)

Removes the Variable Value at index index from the store.

void VariableMoved(int from, int to) (virtual)

This is an editor support function that can be ignored.

void Clear() (virtual)

Removes all Variable Values from the store.

IList<string> GetVariableNames() (virtual)

Returns Names.

VariableValue GetVariable(string name) (virtual)

Returns the Variable Value with name name.

SetVariableResult SetVariable(string name, **VariableValue** value) (virtual)

Sets the Variable Value with name name to value. If name does not exist, it will be added.

Protected Methods

void RemoveVariable(string name, int index) (virtual)

Removes the variable with *name* name and index *index*.

SetVariableResult SetVariable(string name, VariableValue value, bool allowAdd)

Sets the VariableValue with *name* name to *value*. If *name* does not exist, it will be added only if *allowAdd* is true.

VariableType

PiRhoSoft.CompositionEngine.VariableType

Description

Defines the set of types a Variable Value can hold.

Values

VariableType *Empty*

The Variable Value has no value.

VariableType Bool

The Variable Value is a bool.

VariableType Int

The Variable Value is an int.

VariableType Float

The Variable Value is a float.

VariableType Int2

The VariableValue is a Vector2Int.

VariableType Int3

The VariableValue is a Vector3Int.

VariableType *IntRect*

The VariableValue is a RectInt.

VariableType *IntBounds*

The Variable Value is a Bounds Int.

VariableType Vector2

The Variable Value is a Vector 2.

VariableType Vector3

The VariableValue is a Vector3.

VariableType Vector4

The VariableValue is a Vector4.

VariableType Quaternion

The Variable Value is a Quaternion.

VariableType Rect

The Variable Value is a Rect.

VariableType Bounds

The VariableValue is a Bounds.

VariableType Color

The Variable Value is a Color.

VariableType String

The VariableValue is a string.

VariableType Enum

The Variable Value is an enum. The type of enum is stored in *EnumType* on Variable Value.

VariableType Object

The VariableValue is an Object. If the type is constrained the base type is stored in *ReferenceType* on VariableValue.



If a value is both an Object and IVariableStore, its *Type* will be Object.

VariableType Store

The VariableValue is an IVariableStore.

VariableType List

The VariableValue is an IVariableList.

VariableValue

PiRhoSoft.CompositionEngine.VariableValue: ValueType

Description

Stores a value or object in a generic fashion without boxing value types (except enums). The possible types that can be stored are defined in VariableType.

Static Properties

VariableValue Empty (read only)

Creates a value with VariableType Empty.

Static Methods

VariableType GetType(**Type** *type*)

Returns the VariableType that would be used to store a value of Type *type*. If *type* is not supported, Empty will be returned.

Variable Value Create (bool value)

Creates a Variable Value with Type Bool that holds value.

Variable Value Create (int value)

Creates a Variable Value with Type Int that holds value.

Variable Value Create (float value)

Creates a Variable Value with Type Float that holds value.

Variable Value Create (Vector 2 Int value)

Creates a Variable Value with Type Int2 that holds value.

VariableValue Create(Vector3Int value)

Creates a Variable Value with Type Int3 that holds value.

VariableValue Create(RectInt value)

Creates a Variable Value with Type RectInt that holds value.

Variable Value Create (Bounds Int value)

Creates a Variable Value with Type Bounds Int that holds value.

Variable Value Create (Vector 2 value)

Creates a Variable Value with Type Vector 2 that holds value.

VariableValue Create(Vector3 value)

Creates a Variable Value with Type Vector3 that holds value.

Variable Value Create (Vector 4 value)

Creates a Variable Value with Type Vector 4 that holds value.

Variable Value Create (Quaternion value)

Creates a Variable Value with Type Quaternion that holds value.

Variable Value Create (Rect value)

Creates a Variable Value with Type Rect that holds value.

Variable Value Create (Bounds value)

Creates a Variable Value with Type Bounds that holds value.

Variable Value Create (Color value)

Creates a Variable Value with Type Color that holds value.

VariableValue Create(string *str***)**

Creates a Variable Value with Type String that holds str.

VariableValue Create(Enum *e*)

Creates a Variable Value with Type Enum and Enum Type the type of e that holds e.

VariableValue Create(Object obj)

Creates a Variable Value with Type Object that holds obj.

VariableValue Create(IVariableStore store)

Creates a Variable Value with Type Store that holds store.

VariableValue Create(IVariableList list)

Creates a Variable Value with Type List that holds list.

VariableValue CreateValue<T>(T value)

Creates a VariableValue with *Type* determined from *T* that holds *value*. This can be used for all VariableTypes except Enum, Object, Store, and List.

Variable Value Create Reference (object reference)

Creates a VariableValue with *Type* determined from the type of *reference* that holds *reference*. This can be used for the VariableTypes Enum, Object, Store, and List.



If *reference* is both an IVariableStore and an Object, the value will have type Object.

VariableValue CreateAny(object obj)

Creates a VariableValue with *Type* determined from the type of *obj*. This can be used for any VariableType when it is unknown whether *obj* is a value or reference type.

Public Properties

VariableType Type (read only)

The VariableType of the value.

bool *IsEmpty* (read only)

Returns true if *Type* is Empty.

bool IsNull (read only)

Returns true if *Type* is Object, Store, or List and no value is stored.

bool *HasValue* (read only)

Returns true if *Type* is a value type (i.e anything other than String, Enum, Object, Store, or List).

bool HasString (read only)

Returns true if *Type* is String.

bool HasEnum (read only)

Returns true if *Type* is Enum.

bool HasReference (read only)

Returns true if *Type* is Object, Store, or List.

bool *HasObject* (read only)

Returns true if the stored object is an Object or derived from Object.

bool HasStore (read only)

Returns true if the stored object is an IVariableStore.



Even if *Type* is Object, this will still return true if the stored object is also an IVariableStore.

bool *HasList* (read only)

Returns true if the stored object is an IVariableList.



Even if *Type* is Object, this will still return true if the stored object is also an IVariableList.

bool HasNumber (read only)

Returns true if *Type* is Int or Float.

bool *HasNumber2* (read only)

Returns true if *Type* is Int2 or Vector2.

bool *HasNumber3* (read only)

Returns true if *Type* is Int3, Vector3, Int2, or Vector2.

bool HasNumber4 (read only)

Returns true if *Type* is Vector4, Int3, Vector3, Int2, or Vector2.

bool HasRect (read only)

Returns true if *Type* is IntRect or Rect.

bool HasBounds (read only)

Returns true if *Type* is IntBounds or Bounds.

bool Bool (read only)

Returns the stored value if *Type* is Bool or an undefined value if it is not.

int Int (read only)

Returns the stored value if *Type* is Int or an undefined value if it is not.

float Float (read only)

Returns the stored value if *Type* is Float or an undefined value if it is not.

Vector2Int Int2 (read only)

Returns the stored value if *Type* is Int2 or an undefined value if it is not.

Vector3Int Int3 (read only)

Returns the stored value if *Type* is Int3 or an undefined value if it is not.

RectInt *IntRect* (read only)

Returns the stored value if *Type* is IntRect or an undefined value if it is not.

BoundsInt *IntBounds* (read only)

Returns the stored value if *Type* is IntBounds or an undefined value if it is not.

Vector2 *Vector2* (read only)

Returns the stored value if *Type* is Vector2 or an undefined value if it is not.

Vector3 *Vector3* (read only)

Returns the stored value if *Type* is Vector3 or an undefined value if it is not.

Vector4 *Vector4 (read only)*

Returns the stored value if *Type* is Vector4 or an undefined value if it is not.

Quaternion Quaternion (read only)

Returns the stored value if *Type* is Quaternion or an undefined value if it is not.

Rect Rect (read only)

Returns the stored value if *Type* is Rect or an undefined value if it is not.

Bounds Bounds (read only)

Returns the stored value if *Type* is Bounds or an undefined value if it is not.

Color *Color (read only)*

Returns the stored value if *Type* is Color or an undefined value if it is not.

string *String* (read only)

Returns the stored value if *Type* is String or null if it is not.

Enum Enum (read only)

Returns the stored value if *Type* is Enum or null if it is not.

Object Object (read only)

Returns the stored object if *Type* is Object or null if it is not.

IVariableStore Store (read only)

Returns the stored object if the object is an IVariableStore or null if it is not.

IVariableList List (read only)

Returns the stored object if the object is an IVariableList or null if it is not.

float Number (read only)

Returns the stored value if *Type* is Int or Float or 0.0 if it is not.

Vector2 Number2 (read only)

Returns the stored value if *Type* is Int2 or Vector2 or (0.0, 0.0) if it is not.

Vector3 Number3 (read only)

Returns the stored value if Type is Int3 or Vector3, Number2 with z = 0.0 if Type is Int2 or Vector2, or (0.0, 0.0, 0.0) otherwise.

Vector4 Number4 (read only)

Returns the stored value if Type is Vector4, Number3 with w = 1.0 if Type is Int3, Vector3, Int2, or Vector2, or (0.0, 0.0, 0.0, 1.0) otherwise.

Rect NumberRect (read only)

Returns the stored value if Type is IntRect or Rect or a 0 sized rect at (0.0, 0.0) if it is not.

Bounds NumberBounds (read only)

Returns the stored value if Type is IntBounds or Bounds or a 0 sized bounds at (0.0, 0.0, 0.0) if it is not.

Object Reference (read only)

The stored reference value whether *Type* is Object, Store, or List.

Type *EnumType* (read only)

The type of the stored *Enum* if *Type* is Enum or null if it is not.

Type ReferenceType (read only)

The type of the stored *Object* if *Type* is Object or null if it is not.

Public Methods

bool HasEnumType<Type>()

true if *Type* is Enum and *EnumType* is *Type*.

bool HasReferenceType<Type>()

true if *Type* is Object and *ReferenceType* is *Type* or is derived from *Type*.

bool HasEnumType(Type type)

true if *Type* is Enum and *EnumType* is *type*.

bool HasReferenceType(Type type)

true if *Type* is Object and *ReferenceType* is *type* or is derived from *type*.

object GetBoxedValue()

Returns the stored value, regardless of *Type*. Value types will be boxed.

bool TryGetBool(bool value (out))

If *Type* is Bool, sets *value* to the stored value and returns true. Otherwise sets *value* to false and returns false.

bool TryGetInt(int value (out))

If *Type* is Int, sets *value* to the stored value and returns true. Otherwise sets *value* to 0 and returns false.

bool TryGetFloat(float value (out))

If *Type* is Float, sets *value* to the stored value and returns true. Otherwise sets *value* to 0.0 and returns false.

bool TryGetInt2(Vector2Int value (out))

If *Type* is Int2, sets *value* to the stored value and returns true. Otherwise sets *value* to (0, 0) and returns false.

bool TryGetInt3(Vector3Int value (out))

If *Type* is Int3, sets *value* to the stored value and returns true. Otherwise sets *value* to (0, 0, 0) and returns false.

bool TryGetIntRect(RectInt value (out))

If Type is IntRect, sets value to the stored value and returns true. Otherwise sets value to a 0 sized rect at (0, 0) and returns false.

bool TryGetIntBounds(BoundsInt value (out))

If Type is IntBounds, sets value to the stored value and returns true. Otherwise sets value to a 0 sized bounds at (0, 0, 0) and returns false.

bool TryGetVector2(Vector2 value (out))

If Type is Vector2, sets value to the stored value and returns true. Otherwise sets value to (0.0, 0.0) and returns false.

bool TryGetVector3(Vector3 value (out))

If Type is Vector3, sets value to the stored value and returns true. Otherwise sets value to (0.0, 0.0) and returns false.

bool TryGetVector4(Vector4 value (out))

If Type is Vector4, sets value to the stored value and returns true. Otherwise sets value to (0.0, 0.0, 1.0) and returns false.

bool TryGetQuaternion(Quaternion value (out))

If *Type* is Quaternion, sets *value* to the stored value and returns true. Otherwise sets *value* to Quaternion.*identity* and returns false.

bool TryGetRect(Rect value (out))

If *Type* is Rect, sets *value* to the stored value and returns true. Otherwise sets *value* to a 0 sized rect at (0.0, 0.0) and returns false.

bool TryGetBounds(Bounds value (out))

If Type is Bounds, sets value to the stored value and returns true. Otherwise sets value to a 0 sized bounds at (0.0, 0.0, 0.0) and returns false.

bool TryGetColor(Color value (out))

If *Type* is Color, sets *value* to the stored value and returns true. Otherwise sets *color* to white and returns false.

bool TryGetString(string s (out))

If *Type* is String, sets *s* to the stored value and returns true. Otherwise sets *s* to an empty string and returns false.

bool TryGetEnum<EnumType>(EnumType value (out))

If *Type* is Enum and *EnumType* is *EnumType*, sets *value* to the stored value and returns true. Otherwise sets *value* to 0 and returns false.

bool TryGetObject(Object obj (out))

If *Type* is Object, sets *obj* to the stored object and returns true. Otherwise sets *obj* to null and returns false.

bool TryGetStore(IVariableStore store (out))

If the stored object is an IVariableStore, sets *store* to the stored object and returns true. Otherwise sets *store* to null and returns false.

bool TryGetList(IVariableList list (out))

If the stored object is an IVariableList, sets *list* to the stored object and returns true. Otherwise sets *list* to null and returns false.

bool TryGetReference<T>(T t (out))

If Type is Object, Store, or List and the stored object has type T or is derived from type T, sets t to the stored object and returns true. Otherwise sets t to null and returns false.

VariableValueSource

PiRhoSoft.CompositionEngine.VariableValueSource: VariableSource<VariableValue>

Description

A VariableSource for any VariableValue.

Constructors

VariableValueSource(VariableType type, ValueDefinition definition)

Initializes the source to *Type* Value with *Value* a VariableValue with VariableType type and initialized with definition.

Public Fields

ValueDefinition *Definition*

The ValueDefinition the source was initialized with.

Vector2VariableSource

PiRhoSoft. Composition Engine. Vector 2 Variable Source: Variable Source < Vector 2 Vector 2 Variable Source < Vector 2 Vector

Description

A VariableSource for Vector2 VariableValues.

Constructors

Vector2VariableSource(Vector2 *defaultValue***)**

Initializes the source to *Type* Value with *Value* _defaultValue.

Vector3VariableSource

PiRhoSoft. Composition Engine. Vector 3 Variable Source: Variable Source < Vector 3

Description

A VariableSource for Vector3 VariableValues.

Constructors

Vector3VariableSource(Vector3 *defaultValue***)**

Initializes the source to *Type* Value with *Value* _defaultValue.

Vector4VariableSource

 $PiRhoSoft. Composition Engine. Vector 4 Variable Source: Variable Source < Vector 4 \\ > 1 \\ > 2 \\ > 2 \\ > 3 \\ > 4 \\ >$

Description

A VariableSource for Vector4 VariableValues.

Constructors

Vector4VariableSource(Vector4 *defaultValue***)**

Initializes the source to *Type* Value with *Value* _defaultValue.

WaitNode

PiRhoSoft. Composition Engine. Wait Node: Instruction Graph Node

Description

Add this to an InstructionGraph to delay execution for a specified amount of time.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.

FloatVariableSource Time

The number of seconds to delay the InstructionGraph.

bool *UseScaledTime*

If this is set, the delay will be based on scaled time, otherwise it will be based on real time.

WritableStore

PiRhoSoft. Composition Engine. Writable Store: Variable Store

Description

An IVariableStore implementation that disallows contained VariableValues to be added. Variables that already exist in the store can have their value changed.

YieldNode

 $PiRhoSoft. Composition Engine. Yield Node: {\color{blue} Instruction Graph Node}$

Description

Add this to an InstructionGraph to delay execution for one frame.

Public Fields

InstructionGraphNode Next

The InstructionGraphNode to run when this node finishes.