PCF Tile Developer Guide

v1.12

Published: 8 April 2019

© 2019 Pivotal Software, Inc. All Rights Reserved.

Table of Contents

lable of Contents	2
PCF Tile Developer Guide	3
PCF v1.12 Partners Release Notice	6
Tile Basics	9
How PCF and PCF Services Work	10
How Tiles Work	12
Configuring Disk and VM Type Defaults for On-Demand Service Tiles	17
Managing Runtime Configs	18
Testing Tiles	22
Types of Integration	24
User-Provided Service	26
Brokered Service	27
Service Brokers	28
Managed Service	29
BOSH Releases	30
Errands	31
On-Demand Service	33
Buildpacks	34
CredHub	35
Creating New Variables in CredHub	37
Migrating Existing Credentials to CredHub	39
Fetching Variable Names and Values	41
Embedded Agents	43
Logs, Metrics, and Nozzles	44
Development Tools	50
Development Environments	51
Tile Generator	52
pcf Command Line Utility	63
Concourse	67
Pivotal Cloud Foundry Services SDK	68
Publish and Update	69
Tile Documentation	70
Partner Software Product Release Cycle	73
Upgrading Tiles	76
References	82
Development Workflow Reference	83
Product Template Reference	84
Property Reference	100
Contact Us	111



PCF Tile Developer Guide



Note: PCF Tile Developer Guide v1.12 is not designed for use with the current versions of Ops Manager. For your tiles to stay up to date with the latest software, features, and security updates, use the latest version of the PCF Tile Developer Guide.

Page last updated:

This topic exists to help Pivotal Cloud Foundry (PCF) Partners learn the high-level process of building and publishing a tile on Pivotal Network ...

For advanced developers with previous experience building tiles, see Product Template Reference and Development Workflow Reference.

What is a Tile?

Tiles are packaged software that can be integrated into PCF. PCF operators can install tiles on PCF. PCF developers can use these services once they are installed

Tile developers can publish tiles on Pivotal Network, where services and tiles are available for download.

Tile Structure

Tiles are packaged as compressed files with a _pivotal file extension. These compressed files require three subdirectories: _metadata , _migrations , and _releases .

When you package your software with Tile Generator, it generates these subdirectories for you. You can perform different actions within each subdirectory:

Directory	Description	
metadata	Configure settings for your software in a YAML file.	
Track changes across different releases in a js file. Only tiles with multiple releases use this subdirectory. Do not modify the files in this subdirectory during your first tile release.		
releases	Deploy your service source code and other inputs for your build, such as a BOSH release.	

Why Build a Tile?

There are multiple reasons to build and publish a tile on Pivotal Network. Tiles can help you:

- Find the widest possible audience for your service.
- Join a growing ecosystem that can easily integrate your service.
- Enable operators and app developers to interact with your service in an accessible and standardized way.

Building Your First Tile

There are two options for building your first tile. You can either attend partner days or develop independently. However, Pivotal strongly recommends attending Partner Days for hands-on guidance.

Attending Partner Days

Partner Days are the single best resource to introduce you to PCF and tile development. During these three-day workshops, Pivotal and partner Independent Software Vendor (ISV) engineers collaborate to prototype and build a software integration with PCF.

These events streamline your development process by providing hands-on guidance, giving you a head start for publishing a tile on Pivotal Network. The workshop is free for all Pivotal partners.

Pivotal recommends any interested partner to register for Partner Days . If you are not a Pivotal partner yet, you can sign up for the partner program .



You can see footage of previous Partner Days in this brief YouTube video ...

Developing Independently

If you want to build a tile without attending Partner Days, follow the procedure below to minimize the learning curve for tile development.

Creating a tile is a complex process and can be time consuming to complete on your own. You can message the Pivotal Partners Slack channel with questions if you register for the Pivotal Partner program .

1. Decide What to Build

If you use Tile Generator to package your software you also need to determine the inputs you need to build before development. Inputs for your tile also depend on the service you are providing.

Before starting tile development, see How PCF and PCF Services Work.

Depending on what you build, you might need to install the following tools:

- Tile Generator: Used to package your software into a tile.
- Cloud Foundry Command Line Interface (cf CLI) ☑: A CLI for deploying and managing apps on Cloud Foundry. If you are developing on Cloud Foundry, you use cf CLI when building your tile.
- Kubernetes Command Line Tool (kubectl) 🗷: A command line interface for deploying and managing apps on Kubernetes. If you are developing on Kubernetes, you use kubectl when building your tile.
- CF Dev 🗷 (optional): A lightweight PCF installation for deploying and debugging apps locally. You can use CF Dev if you want to run PCF on your local workstation.

2. Generate a Tile

Tile Generator is a tool that simplifies the building process for tiles. To use Tile Generator, upload your software components, such as the service broker, buildpack, and Docker image, and the tool generates a base tile.

For information on setting up Tile Generator and building a base tile, see Tile Generator.

3. Test Your Tile

Before you publish your tile, you can test it manually using a Partner Integration Environment (PIE). In PIE you can see how the tile functions on an laaS, such as Amazon Web Services (AWS) or Google Cloud Platform (GCP). You can upload, configure, and install your tile in PIE just like an operator would.

To gain access to your PIE, reach out to your contact at Pivotal or register as a partner ...

If you already have access to your PIE, for information on how to log in, see Shared PCF Development Environments.

4. Document Your Tile

When you are ready to publish your tile, write documentation. Documentation is valuable for operators who use your tile.

For more information on how to write and publish documentation for your tile, see <u>Tile Documentation</u>.

5. Publish Your Tile on Pivotal Network

Contact your Pivotal representative who can guide you through the process of uploading your tile to Pivotal Network. When you upload your tile to Pivotal Network, it becomes available for operators and developers to do the following:

Audience	Benefits	
	Download and install your service as a tile.	



Operators	Configure your service using a UI.		
	Update your service with a single click.		
	See your service on Pivotal Network.		
Developers	Select service plans to which they would like to subscribe.		
Developers	Create instances of your service and call them from their apps.		
	Support a continuous and fast development cycle.		

For information on the release cycle for Partner tiles, see Partner Software Release Cycle.

Contact Us

If you want to learn more about the Pivotal ISV Partner Program or request assistance with your integration project, see Contact Us.



PCF v1.12 Partners Release Notice

Page last updated:

This topic describes the changes that Pivotal Cloud Foundry (PCF) v1.12 introduces which may be relevant to partner service tiles.

Additional Credential Migrations

Version 1.11.0 of PCF introduced CredHub for credential management, and PCF v1.11.1 added support for migrating secret credentials to CredHub.

Ops Manager v1.12 added support for migrating additional credential types, including rsa_pkey_credential and simple_credential types in the v1.12 Alpha release and salted_credential in the v1.12 Beta release. Tile developers can migrate these credential types using the same JavaScript migration process as secret credentials.



Preaking Change: When migrating salted_credentials, CredHub does not retain the salt. If your tile depends on the salt, refactor before migrating to

See Migrating Existing Credentials to CredHubfor more information.

Ternary Operator Evaluates Boolean Constants

Ops Manager v1.12 adds support for evaluating boolean constants using ternary operators. Previously, the ternary operator supported string constants, property references, or named_manifest declarations.



Preaking Change: If you define true and false in any property_blueprint names, as shown in the workaround below, update your job manifest to use boolean constants.

In previous versions of Ops Manager, to expose a property to operators as a checkbox that is checked by default, a tile author defined the true and false properties in the job manifest as a workaround. In the following example, the disable security protocols job spec property takes a boolean value:

```
property_blueprints:
 name: true
 type: boolean
 configurable: false
 default: true
type: boolean
 configurable: false
default: false
manifest:
disable security protocols: '(( .properties.secure the system ? .properties.false : .properties.true ))
```

In Ops Manager v1.12, the ternary operator manages boolean values natively. A tile author can rewrite the above example using the following syntax:

```
disable_security_protocols: '(( .properties.secure_the_system ? false : true ))'
```

When using this syntax, enclose everything following the initial colon with either single or double quotation marks and include the space between the boolean expression and the question mark, as shown above.

Support for Empty Arrays in Double Parentheses

Ops Manager now supports empty arrays in double parentheses. For more information, see the Double-Parentheses Expressions section of the Property Reference topic.

Resource Config Pane Hides Zero-Instance Jobs



A service tile's Resource Config pane lists the jobs that the service runs and lets operators allocate resources to the jobs that are configurable.

Tiles can define a job as non_configurable and set its instance count to 0. This prevents the job from running, but lets external services access the job properties. The Ops Manager 1.12 Resource Config pane and API endpoints 2 do not include these zero-instance jobs.

Elastic Runtime Tile Property Changes

Properties in the Elastic Runtime tile have changed. Tile developers must change any ((..ef.PROPERTY.NAME)) calls accordingly if their tiles access Elastic Runtime property values.

The following tables list the properties that Pivotal removed, added, renamed, and retyped between Elastic Runtime v1.11 and v1.12:

```
Removed Properties

.ccdb.credentials

.diego_database.skip_consul_locks

.etcd_tls_server.election_timeout_in_milliseconds

.etcd_tls_server.heartbeat_interval_in_milliseconds

.properties.cf_etcd_client_cert

.properties.cf_etcd_peer_cert

.properties.cf_etcd_server_cert

.properties.container_networking.disable.garden_network_pool

.uaadb.credentials
```

.uaddp.credentiais
Added Properties
.cloud_controller.staging_timeout_in_seconds
<pre>.ha_proxy.internal_only_domains</pre>
.ha_proxy.trusted_domain_cidrs
.properties.container_networking_log_traffic
.properties.container_networking_log_traffic.enable.iptables_accepted_udp_logs_per_sec
.properties.container_networking_log_traffic.enable.iptables_denied_logs_per_sec
.properties.doppler_ssl_ciphers
<pre>.properties.enable_grootfs</pre>
.properties.garden_image_plugin
<pre>.properties.garden_image_plugin_empty</pre>
<pre>.properties.garden_image_plugin_empty_args</pre>
.properties.garden_image_plugin_extra_args
<pre>.properties.haproxy_forward_tls</pre>
<pre>.properties.haproxy_forward_tls.enable.backend_ca</pre>
<pre>.properties.loggregator_client_cert</pre>
.properties.metron_ssl_ciphers
.properties.nfs_volume_driver.enable.ldap_server_host
.properties.nfs_volume_driver.enable.ldap_server_port
.properties.nfs_volume_driver.enable.ldap_service_account_password
.properties.nfs_volume_driver.enable.ldap_service_account_user
.properties.nfs_volume_driver.enable.ldap_user_fqdn
.properties.rep_preloaded_rootfses_garden
.properties.rep_preloaded_rootfses_grootfs
.properties.router_backend_max_conn
.properties.routing_minimum_tls_version



```
.properties.secure_diego_communication
.router.enable_isolated_routing
```

Renamed Properties			
v1.11 Name	v1.12 Name		
.properties.container_networking.enable.network_cidr	.properties.container_networking_network_cidr		
.properties.container_networking.enable.vtep_port	.properties.container_networking_vtep_port		
.properties.networking_point_of_entry.external_ssl.ssl_ciphers	.properties.gorouter_ssl_ciphers		
.properties.networking_point_of_entry.external_ssl.ssl_rsa_certificate	.properties.networking_poe_ssl_cert		
.properties.networking_point_of_entry.haproxy.disable_http	.properties.routing_disable_http		
.properties.networking_point_of_entry.haproxy.max_buffer_size	.properties.haproxy_max_buffer_size		
.properties.networking_point_of_entry.haproxy.ssl_ciphers	.properties.haproxy_ssl_ciphers		
.properties.networking_point_of_entry.haproxy.ssl_rsa_certificate	.properties.networking_poe_ssl_cert		
.push-apps-manager.secret_token	.push-usage-service.secret_token		

Retyped Properties			
Property	v1.11 Type	v1.12 Type	
.autoscaling.broker_credentials	salted_credentials	simple_credentials	
.autoscaling.encryption_key	salted_credentials	secret	
.properties.mysql_backups.s3.region	dropdown_select	string	
.properties.system_blobstore.external.region	dropdown_select	string	

Product Dependency Syntax

Tile authors can specify product version dependencies in tile metadata using ____. Ops Manager interprets this operator based on the context in the metadata. For example:

```
- name: cf
version: "~> 1.8"
- name: example-product
version: "~> 1,12.1"
```

If the version number contains only two segments, Ops Manager interprets \longrightarrow as >= . In the example above, this includes all versions of cf greater than 1.8 .

If the version number contains more than two segments, Ops Manager evaluates of the final segment. In the example above, this includes versions only of example-product.



Tile Basics

Page last updated:

This section gives a high-level overview of how tiles, Pivotal Cloud Foundry (PCF), and PCF service brokers work together.

Cloud Foundry Service Brokers and PCF Tiles

Service brokers let developers create service instances in their development spaces that they can call from their code. To do this, the brokers provide an interface between the Cloud Controller and the add-on software service that they represent. The service can run internal or external to a CF deployment, but the service broker always runs inside the cloud.

The service broker works by providing an API which the Cloud Controller calls to create service instances, bind them to apps, and perform other operations. Cloud Foundry service brokers are implemented as HTTP servers that conform to the service broker API ...

In addition to providing an API, a service broker publishes a service catalog that may include multiple service plans, such as a free tier and a metered tier.

Brokers register their service plans with the Cloud Controller to populate the Marketplace, which developers access with or through the marketplace

Pivotal Cloud Foundry (PCF) Apps Manager.

On PCF, cloud operators make software services available to developers by finding them on Pivotal Network of and then installing and configuring them through a tile interface in the Ops Manager Installation Dashboard. Installing a service tile creates a service broker, registers it with the Cloud Controller, and publishes the service plans that the broker offers. Developers can then create service instances in their spaces and bind them to their apps.

See the following topics:

- How PCF and PCF Services Work
- How Tiles Work



How PCF and PCF Services Work

Page last updated:

There are many ways to integrate services with Pivotal Cloud Foundry (PCF). The right one for each service depends on what the service does, and how customer applications consume it. To determine the best way to integrate your service, you'll need a good understanding of PCF concepts like applications, containers, services, brokers, and buildpacks.

This page provides a collection of links to documentation for the most relevant concepts. If you prefer to learn through guided training, ask us about available training options.

General Overview

For general overview of PCF, and the various ways to interact with it, use the following links:

- Cloud Foundry Subsystems C provides high-level descriptions of internal functions performed by different PCF components.
- Cloud Foundry Command Line Interface (cf CLI) Inks to topics that explain how to direct PCF deployment from your local command line.
- Pivotal Ops Manager describes the Ops Manager and Installation Dashboard interfaces, where cloud operators see, install, configure, and deploy service tiles.
- Pivotal Apps Manager describes the Apps Manager interface, where app developers create and configure service instances and bind them to their apps.

Applications

Cloud Foundry is primarily a cloud native application platform. To understand how to integrate your services with Cloud Foundry, you should understand how your customers are using the platform to develop, deploy, and operate their applications.

- Developer Guide C explains how to push an app to run on PCF and enable it to use services.
- Logging and Monitoring 🗷 describes how PCF aggregates and streams logs and metrics from the apps it hosts and from internal system components.

Services

Most value-add integrations are done by exposing your software to customer applications as services. To understand the service concepts, and what a service integration looks like, read the following documentation:

- Services Overview 🗗 explains how developers provision and use existing services in their apps.
- Cloud Foundry Service Brokers and PCF Tiles & briefly describes the two main elements of PCF service integration: the service broker API, which connects the service to PCF internally by taking commands from the Cloud Controller; and the tile, a packaged interface that cloud operators use to install and configure a service within PCF.
- Custom Services explains how service authors package their service as a Managed Service that is available for use by PCF operators and developers, and which runs locally on PCF rather than running remotely.

Buildpacks

When application code is deployed to Cloud Foundry, it is processed by a language-specific buildpack. Language buildpacks provide a convenient integration hook for any service that needs to inspect or embellish application code. Supplying buildpacks also provides a language-agnostic way to inject your code into the application container image.

- Application Staging Process explains how PCF packages and deploys apps in containers with buildpacks so that they can run on multiple VMs interchangeably.
- Language Buildpacks 🗷 describes the language-specific buildpacks support PCF apps.
- Custom Buildpacks describes how to use supply buildpacks to add dependencies or code without having to change (multiple) language-sepcific buildpacks.

Embedded Agents

Some integrations depend on the ability to inject code into the application container. We refer to these injected components as "container-embedded agents". Buildpacks provide a mechanism to inject components into the application container image, and the profiled directory provides a way to start agents before or alongside the customer application.

- Agent Injection with a supply buildpack ♂
- Using .profile.d ☑

Nozzles

Cloud Foundry's logging system, Loggregator, has a feature named **firehose**. The firehose includes the combined stream of logs from all apps, plus metrics data from Cloud Foundry components, and is intended to be used by operators and administrators.

A nozzle takes this data and forwards it to an external logging and/or metrics solution.

Loggregator system ☑



How Tiles Work

Page last updated:

Product tiles make it easy for cloud operators to offer new and upgraded software services to developers in a Pivotal Cloud Foundry (PCF) deployment.

Pivotal Network distributes these tiles as zipped code directories, with filename extension pivotal, that contain or point to all of the software elements that perform the tile's functions.

This topic explains what each functional element of a tile does and how you create or specify it as input to the Tile Generator tool that creates __pivotal files.

This topic also describes the typical structure of a tile directory. This is useful information for modifying generated tiles or legacy tiles that were created without the Tile Generator.

Tile Functions

PCF service tiles perform multiple functions that streamline the use of software services on PCF, including:

- Deploy a service broker that interfaces between the Cloud Controller, PCF's main executive component, and the service.
- Publish a catalog of available service plans to the Services Marketplace.
- Define an interface for configuring service properties in Ops Manager.
- Generate a BOSH manifest for deploying instances of the service, populating it with both user-configured and fixed properties.
- Run BOSH errands: deploy errands that set PCF up to run the service when an operator first deploys the service, and delete errands that clean up when an operator deletes the service.
- Define dependencies for the tile, to prevent Ops Manager from installing the service when its dependencies are missing.
- Support one-click installation and upgrading from previous versions.

These functions are described in more detail below.

Service Broker

Service brokers integrate services with PCF by providing an API for the Cloud Controller to create service instances, bind them to apps, and perform other operations. The Service Broker API v2.10 Ct topic specifies requirements for this API.

Each service tile acts as a wrapper for a service broker. Installing the tile creates its service broker, registers it with the Cloud Controller, and <u>publishes</u> the service plans that the broker offers.

You can write a service broker in any language, and it can run anywhere, inside your PCF installation or external. See Example Service Brokers of for sample code in Ruby, Java, and Go.

Specify the service broker for a tile in the tile directory's tile.yml file, as a package with type: set to app-broker, docker-app-broker, or external-broker. The external-broker type requires a uri value, for the service broker location.

Catalog

Service brokers include catalog metadata that list their service plans. This information publishes to the Marketplace that app developers use to browse and select services.

Developers on either PCF or open-source Cloud Foundry see a plain-text version of the Marketplace by running of marketplace by running of marketplace.

graphical Marketplace, and PCF service brokers support this Marketplace with additional catalog metadata fields for display names, logo images, and links to more information and documentation.

Define this catalog metadata for your service by writing your service broker to return the API calls listed in the Catalog Metadata 🗷 topic.


Configuration

In the Ops Manager Installation Dashboard, service tiles present a form-based interface that cloud operators use to configure the service. These

configured properties become part of the BOSH manifest that PCF uses to deploy instances of the service.

You define this configuration interface in the forms: section of the tile.yml configuration file that you pass to the Tile Generator. Each named form element defines a configuration pane accessible under the tile's **Settings** tab.

A left-side menu lists all configuration panes and indicates with check marks which ones have been configured. The menu lists service-specific panes, defined by the tile developer, between system-level panes like Assign AZs and Networks and Resource Config that all PCF products and services use.



Each form, or configuration pane, has label for the menu text, a description to appear up top, and property_inputs that define the configuration fields themselves. Construct your forms by following the Product Template Reference topic and the Property Blueprint Reference section of the About PCF Tiles topic.

For each property, you can combine specifications for name, type, default, configurable, options, and constraints, under both the [Form Properties] (./product-template-reference.html#form-properties] and Property Blueprints sections of the topic.



Note: In the tile installer will that Tile Generator creates, form properties appear in two locations: a form_types section that defines the contents and layout of the configuration interface, and a property_blueprints section that defines the corresponding field value types and constraints.

Tile Appearance

In the Ops Manager Installation Dashboard, your service tile bears an identifying label, description, and logo icon. Specify these at the top of your tile.yml configuration file as label, description, and icon_file. The value of icon_file should be the name of a 128×128 pixel PNG image.



Fixed Properties

A tile also writes fixed, unconfigurable properties into the BOSH manifest that it creates. You specify these properties in your tile.yml configuration file using Double-Paren Expressions format.

Credentials

Include credentials to pass into a BOSH manifest as salted_credentials in your tile.yml file. But you need not include credentials that already exist in other tiles, such as Elastic Runtime. BOSH automatically generates these for any packages that require them.

Errands

Tile Generator automatically generates deploy and delete lifecycle errands for packages that deploy to PCF. These errand scripts deploy the service to PCF and publish its plans in the Marketplace, and remove the service from PCF and the Marketplace.

You can also define additional post_deploy and pre_delete errand scripts in tile.yml that prepare PCF to host the service or clean up before deleting it. You can configure these errands to run on their own dedicated VMs or co-locate them on existing errand VMs.

For bosh-release and docker-bosh packages, which run jobs directly on BOSH rather than on the PCF layer, you need to include post_deploy and pre_delete errands with their package definitions in tile.yml . Label them as lifecycle errands using lifecycle: errand and either post_deploy: true or pre_delete: true .

Tile Generator writes the bosh-release errands into the main BOSH release that it creates for the service, and adds docker-bosh errands into a separate Docker BOSH release that the main release depends on.

Dependencies

Include product dependencies under requires_product_versions at the top of your tile.yml file.

Update Rules

Tile Generator automatically generates the JavaScript migration file that enables one-click updates from Ops Manager. This file describes how to change existing tile property names and values in order to match the new version of the tile.

A mature tile may contain several of these _is files, from previous versions and the current one, to enable tile updates to automatically chain together in sequence.

You can add custom update code in the tile.yml Tile Generator configuration file, following the properties documented in the Migrating Tile Versions topic.

Tile File Format and Structure

Tile directories contain the following components, which include each other as shown:

- BOSH release
 - o Service source code
 - o Service broker
 - Language-specific buildpack(s)
 - o Errands (service start and stop scripts)
 - o BOSH manifest (deployment properties for service)
 - Packages
 - Dependencies
- Tile manifest template (adds properties into BOSH manifest)
 - o Configuration forms and properties
 - o Catalog metadata (for the Marketplace)
- Migrations

The three required top-level subdirectories in a pivotal tile directory are:

- metadata high-level information for configuring and publishing your service.
- migrations rules that govern tile upgrades.
- releases the BOSH releases that deploy your service.

The tile manifest template defines these subdirectory locations, so they can reside anywhere in the directory, but the typical structure looks like this:

.pivotal File Format

Within the tile directory, the BOSH release exists as a gzipped tarfile.

The entire tile directory is also a gzipped tarfile, with the <code>.tgz</code> extension renamed to <code>.pivotal</code> .

You can use any zip utility to create a .pivotal file. Ensure that the top-level subfolders as seen above in the example-product folder remain.

Example Workflow

```
$ cd example-product pivotal metadata/ migrations/ releases/
$ unzip -l example-product.pivotal
Archive: example-product.pivotal
Length Date Time Name

0 08-09-16 16:10 metadata/
89458 08-09-16 16:10 metadata/example-product.yml
0 07-08-16 09:32 migrations/
0 07-08-16 09:32 migrations/v1/
423 07-08-16 09:32 migrations/v1/201512301616_convert_14_transmogrifier_rules.js
1228 07-08-16 09:32 migrations/v1/201512301631_convert_15_16_transmogrifier_rules.js
582 07-08-16 09:32 migrations/v1/201611060205_example_migration.js
0 08-09-16 16:11 releases/
0 07-12-16 17:19 releases/example-release-18.tgz
```

GitHub Repository Structure

Tile developers typically develop and archive their code on GitHub, and their Concourse build pipeline pulls from GitHub to perform continuous integration.

Tile Generator does not dictate any directory structure for a GitHub repository, but by convention your tile repository might look like this:

```
/tile.yml
/src # source code for all components deployed by the tile
/resources # other resources, such as icon images and imported Docker images or bosh releases
/release # generated bosh release(s)
/product # generated tile
```

Packages

PCF services typically require multiple component job processes to run concurrently, such as a main app, a helper app, and a service broker. They also

require buildpacks that run as one-time compilation tasks. Services also require components such as external brokers or storage, which do not run as jobs, but nevertheless need to remain available.

The tile yml file that you pass to Tile Generator defines these service components it its packages: section. Each package has a name and a package type. The list of possible package types to pass to Tile Generator is in the Tile Generator code ... It includes:

- app cf push ed to PCF
- docker-app cf push ed to PCF (image will not be embedded so requires Docker registry access)
- app-broker cf push ed to PCF and registered as a broker
- docker-app-broker of push ed to PCF and registered as a broker (image is not embedded, so requires Docker registry access)
- external-broker Registered as a broker
- buildpack installed with cf create-buildpack; runs as a one-time task rather than a long-running process
- docker-bosh describes a collection of Docker images that embed in the tile and run on BOSH-managed VMs, not PCF
- bosh-release a pre-existing BOSH release wrapped in a tile, to run on BOSH-managed VMs, not PCF; requires you to describe all jobs (long-running processes and errands)

Packages typically contain a single process, but can include more than one, packaged to run in the same location.


Where Package Processes Run

Where packaged processes run depends on their package type, as follows:

- app , docker-app , app-broker , and docker-app-broker packages call of push to run processes in containers on a Diego cell.
- docker-bosh and bosh-release packages run their processes on VMs in the underlying BOSH layer.
- external-broker and buildpack packages run one-time tasks, not long-running processes, on Diego cells.

Package VM Resources

The service tile's **Resource Config** pane lets the operator configure resources individually for each package. This pane also lets operators provision resources for VMs that handle one-time tasks, with the acceptance-tests, deploy-all, and delete-all rows.





Configuring Disk and VM Type Defaults for On-Demand Service Tiles

Page last updated:



Note: Ops Manager 2.0 and later supports defining VM and disk type defaults and constraints.

This topic describes how tile authors can configure the dropdown menu items for VM types and persistent disk types in their tile.

On-demand service tiles have a configuration pane for each service plan. Operators use dropdown menus on the plan configuration pane to set the VM type and persistent disk type for each instance of that plan.

Ops Manager populates the menus with options based on the VM and disk options available on the current IaaS. Setting default values for VMs and disk types helps operators to choose the right resources for on-demand service broker (ODB) services when using on-demand plans.

VM and Persistent Disk Types

The property that defines the VM type options is vm_type_dropdown |, and the menu options for disk type come from the | disk_type_dropdown | property. Tile authors do not specify the menu items in the product template.

Because VM and disk options differ by laaS, Ops Manager uses a best-fit algorithm to match defaults to their closest equivalents on the laaS, similar to how the Resource Config pane handles its VM Type and Persistent Disk Type options.

If a tile developer does not include a default value for a VM or disk resource, and then an operator configuring the tile does not choose a value from the dropdown, Ops Manager by default sets the resource to the smallest option available on the IaaS.

Set VM Type Defaults

For vm_type_dropdown the resources are ram , ephemeral_disk , and cpu . Tile authors can also apply constraints to any of these resources. Constraints can include min or power_of_two . For example:

- name: example vm type type: vm type dropdown configurable: true resource definitions: - name: ram default: 1024 constraints min: 1024 power_of_two: true - name: ephemeral_disk default: 1024 - name: cpu default: 1

Set Persistent Disk Type Defaults

For disk_type_dropdown the resource is persistent_disk . Tile authors can also apply constraints to this resource. Constraints can include min or power_of_two . For example:

- name: example_disk_type_dropdown type: disk_type_dropdown configurable: true resource_definitions - name: persistent_disk default: 2000 min: 50 power_of_two: false



Managing Runtime Configs

Page last updated:



Note: Ops Manager 2.0 Alpha introduces support for runtime configs.

This topic explains how to define and manage named runtime configs with your service tile for Pivotal Cloud Foundry (PCF).


Tile authors can create a new runtime config in an existing product tile, delete a runtime config from a tile, or add a tile that contains a runtime config

See the BOSH documentation of for more information about runtime configs.

Overview

A runtime config is a section of the tile metadata that can define global deployment configurations. When a tile author includes a runtime config as a toplevel key in the tile metadata, BOSH applies the runtime config to every VM in the deployment.

To the operator, a runtime config appears in Ops Manager as a tile with minimal configuration options. Runtime config tiles contain no stemcell, network, availability zone (AZ), or resource config information.



When you click Apply Changes, Ops Manager combines the runtime config information from every tile in the deployment and assigns each named runtime config a unique identifier. Ops Manager creates the name using the tile name, a generated GUID, and the runtime config name defined in the metadata in the following format:

TILE_NAME-GUID-RUNTIME_CONFIG_NAME

Create a Runtime Config

Tile authors can add runtime_configs as a top-level key in tile metadata. In this key, the tile author defines configuration properties that Ops Manager applies to all deployments. A tile can support any number of runtime configs.

A named runtime config, such as MY-RUNTIME-CONFIG in the example below, can contain any number of addons. Each addon can contain any number of jobs.

To add a runtime config to a tile, add the following section to the tile metadata:



```
runtime_configs:
- name: MY-RUNTIME-CONFIG
runtime_config: |
releases:
- name: os-conf
version: 15
addons:
- name: MY-ADDON-NAME
jobs:
- name: MY-RUNTIME-CONFIG-JOB
release: os-conf
properties:
MY-ADDON-NAME:
...
```

Replace the text in the example above with the following:

- MY-RUNTIME-CONFIG: Choose a name for the runtime config.
- MY-ADDON-NAME: Choose a name for the addon that contains the runtime config job.
- MY-RUNTIME-CONFIG-JOB: Choose a name for the job the runtime config describes.



Important: The names you choose must be unique across a deployment. Pivotal recommends appending your product name or another unique identifier to each of the named items in the runtime_configs | section.

Define the runtime config job properties in the properties section.

Delete a Runtime Config

Tile authors can remove an existing runtime config from a tile by uploading a blank runtime config in its place. Remove the configuration for the named runtime config from the tile metadata, leaving the name in place.

The following example deletes example-runtime-config:

```
runtime_configs:
- name: example-runtime-config
runtime_config:
```

Create a Runtime Config-Only Tile

Tile authors can create a tile that only contains a runtime config. The only release that a tile author must include in a runtime config tile is os-conf. When creating a runtime config-only tile, a tile author is not required to define the following top-level keys:

```
post_deploy_errands
```


- pre delete errands
- job_types

Example Runtime Config-Only Tile

The following example shows a runtime config-only tile with minimal configuration:



In the example runtime config above, the login-banner job prints a banner when a user logs into any VM in the deployment. The operator can use the default value defined in the form_types section of the metadata or configure the banner by editing the **Example string** value in Ops Manager.





Testing Tiles

Page last updated:

This topic explains recommended testing practices for tile developers.

Tile Testing

Good testing assures tile developers that their product installs and runs properly on diverse platforms and assures PCF platform operators that the tile they install can provide its service successfully on their platform.

Pivotal recommends a pyramid structure for testing, starting with unit tests and stepping up to successively broader and more automated levels of integration. Pivotal uses and recommends Concourse for creating build pipelines that follow this test structure. Other continuous integration tools should also support a pyramid testing approach.

Tile Test Pyramid

For PCF tiles, a typical test pyramid progresses as follows:

- 1. Unit tests for each tile component (e.g. service components, broker, adapter, and metrics emitter), manual by developer and in automated pipeline.
- 2. System tests of the tile's BOSH release, including:
 - Functional tests covering the main features of the service. The main features typically interact with almost all important external integration points, so these tests confirm product functionality.
 - Smoke tests (lifecycle tests) for service instances that create and bind a service instance, call it from a test app, check the logs it generates, and delete it. For a typical end-to-end test sequence, see Smoke Tests below.
- 3. System tests of ${f tile}$ operation within Ops Manager.
 - o These include:
 - Configuration checks that test every external configurable integration point and connection to remote servers using configured credentials
 - **Default checks** that confirm "happy path" functionality.
 - Use the Ops Manager API to verify that property blueprints in the tile metadata are correct and that they translate correctly to the BOSH manifest that Ops Manager generates.
 - Use the Om Tool to call the Ops Manager API programmatically from Go. Avoid the unsupported opsmgr gem that called the Ops Manager API from Ruby.
 - $\circ \ \ Confirm manually that the tile wires property blueprints to the expected pane and form controls in the UI.$
 - Test your environment using one of the environments described in Development Environments



Note: System tests might incur costs from using third party services, IaaS resources, etc.

Smoke Tests

Smoke tests are end-to-end lifecycle tests for service instances that you can include as post-deploy errands within a tile and also automate in Concourse or other integration platforms.

A typical smoke test runs as follows:

- 1. Create an org and space for the test to run in.
- 2. Register the tile's service broker.
- 3. Enable service access for the created org.
- - a. Create a service instance for the plan.



- b. Push a test app.
- c. Bind the service instance to the app.
- d. Use the app in a way that exercises the service instance. For a data service, for example, write and read from the service instance.
- e. Unbind the service instance.
- f. Delete the service instance.
- g. Delete the test app.
- 5. Delete the service broker.
- 6. Delete the test org and space.

General Recommendations

The following are general recommendations for designing and running tests on PCF tiles:

- Clean up after yourself. Leave the environment exactly as it was before the test was run.
- Generate verbose logging with lots of contextual data to make troubleshooting easier.
- $\bullet \ \ \text{Design test suites for re-usability by making them highly parameterizable. Important parameters include:}$
 - External settings such as domains, creds, and certs
 - Plans to test against. For example, the Redis for PCF smoke tests use identical code for two different service plans, pre-provisioned and ondemand.
 - o Timeouts, numbers of retries, and other things that you need to adjust for different environments
 - Switches to include or exclude portions of the tests such as generating metrics or backups
- Re-use tests that exist already, for example in Concourse.
- Use an example CF app that uses your service. This app can serve for testing, demoing your tile capabilities, and as a code code example. See the MySQL Test App 🗗 an example.
- When testing manually, using the UI is better than calling the underlying API directly. Use UIs and APIs the way a customer would.



Types of Integration


Page last updated:

Integration Levels

A service can integrate with PCF at four levels, shown here in order of increasing integration. In general, user-experience and production-readiness improves as the integration level increases. But none of the higher levels is required. You can stop service integration and declare it complete (enough) after any of these:

When integrating third-party software with Cloud Foundry, the effort typically progresses through increasing levels of integration. We recommend this staged approach because it enables early feedback on the value and the design of the integration, which helps make better decisions about future stages.

For non-service integrations (such as applications or buildpacks), a similar staged integration approach is often possible and desirable.



Level 1. User-Provided Service

The service runs external to PCF and has no service broker or tile. To use a service with an app, the developer creates a service broker by running of create-user-provided from the Cloud Foundry Command-Line Interface (cf CLI).

Configuring, running, upgrading, and paying for a user-provided service are all up to the developer.

Level 2. Brokered Service

A brokered service runs external to PCF, but has a tile on Pivotal Network (PivNet).

PivNet designates brokered services by including "Service Broker for PCF" in the name.

Operators install, configure, and upgrade the tile through the Ops Manager Installation Dashboard. Developers can then see your service plans and create service instances in Apps Manager, or by running of and of create-service marketplace and of create-service from the command-line.

The Brokered Service topic has more information about brokered service tiles and how to create them.



Level 3. Managed Service

With a managed service, both the service broker and the service itself run within PCF. This enables PCF to manage, monitor, and increase service performance.

As with the brokered service, the service has a service broker and a tile listed on PivNet. PivNet lists managed services as "for PCF," without "Service Broker" in the name.

When the operator installs the tile, they allocate a block of VMs to run service instances and provisions their CPU and memory resources uniformly.

The Managed Service topic has more information about managed service tiles and how to create them.

Level 4. On-Demand (Dynamic) Service

As with a managed service, an on-demand service and broker both run within PCF, and PivNet lists the service tile without "Service Broker" in the name. But unlike a managed service, an on-demand service does not limit the number of service instance VMs. The operator does not have to pre-allocate and provision VM resources for the service.

When a developer creates an instance of an on-demand service, they provision its resources (within an allowed range) and BOSH dynamically creates a new, dedicated VM for the instance.

The On-Demand Service topic has more information about On-Demand service tiles and how to create them.



User-Provided Service

Page last updated:

This topic explains how to create a user-provided service for PCF.

Overview

A PCF developer can call your service from their app code, even if the service runs outside of PCF and has no service broker. Use cases for this include:

- Your software is available as a SaaS.
- You already have a way to install your software on-premises at a customer site.
- Your customer already uses your software, is now adopting PCF, and wants to consume your software from applications that they deploy on PCF.

This do-it-yourself solution represents the lowest level of PCF service integration. It works only for services running external to PCF, and does not publish the services to the Services Marketplace or make them available to anyone outside the space of the developer who runs these commands. See the User-Provided Service Instances of the developer who runs these commands.

Running apps with a user-provided service is a great way to determine what information needs to be passed in the credential structure (useful in higher integration levels), verify that the integration works, and develop a test app that can continue to be used at higher levels. From the app developer perspective, once a user-provided service works, later integrations of the service will not require any further code changes. User-provided service bindings are fully forward-compatible with brokered service bindings.

Using a User-Provided Service

To use an external service that has no tile, they do the following from the Cloud Foundry Command-Line Interface (cf CLI).

- 1. Run cf create-user-provided-service MY-SERVICE-NAME -p CREDENTIALS (or cf cups) to create a service instance. The CREDENTIALS argument should be a valid JSON string that contains the URL and credentials necessary to connect to your externally-deployed service.
- 2. Run cf bind-service to bind the service instance to their app.

By doing this, app developers can bind their apps to your service and write all code necessary to access it through a Cloud Foundry service binding.



Brokered Service

Page last updated:

The topics in this subsection explain how to integrate your software service with Pivotal Cloud Foundry (PCF) to create a brokered service and service tile for PCF.

Overview

You can achieve the first real improvement in your PCF customers user experience by creating a Service Broker for your service.

A brokered service runs external to PCF, but it has a tile on Pivotal Network (PivNet). Operators install, configure, and upgrade the tile through the Ops Manager Installation Dashboard.

The service broker eliminates the need for your customers to know the URLs and credentials for your services; they are managed automatically by the broker.

Building a broker for a (still) externally deployed service is generally a good way to publish a first tile that adds real value for customers who have both your software and PCF.

Create a Brokered Service

- A brokered service requires a service broker, which publishes an API to the Cloud Controller.
 Service Brokers explains how to create one.
- Route Services explains how to create a route service, for use in the routing layer of PCF rather than by hosted PCF apps.
- Catalog explains how to design the part of your service broker API that publishes service plan information to the Services Marketplace.
- You can write your service broker in the language of your choice.
 Buildpacks explains how to create a language-specific buildpack that compiles and packages your service broker to run on PCF.
- Once you have the individual components for your brokered service integration, you can work through Building Your First Tile 🗗 to create your tile.

At any level of integration, Pivotal recommends and supports using Concourse for continuous integration during development.



Service Brokers

Page last updated:

This topic provides resources for building service brokers and routing services.

Service Broker Resources

- The Custom Services Overview ** topic gives a high-level description of how service brokers work in Pivotal Cloud Foundry (PCF).
- Service Broker API of gives a more detailed explanation of PCF service brokers, and provides a full specification for the endpoints, requests, responses, and status codes that a service broker must support.
- Example Service Brokers 🗷 offers example brokers written in Ruby, Java, and Go.

Route Services Resources

- Route Services 🗗 explains how route services work, and what are the different architectures for using them in a Cloud Foundry deployment.
- Example Route Services of gives examples of a logging route service, a rate-limiting route service, and another logging service written in Spring Boot. It also offers a tutorial on setting up the logging route service.

Catalog Resources

• Catalog Metadata C* explains how to publish service plan information to the Services Marketplace, including the icons, display names, and links that appear in the PCF Apps Manager UI but not the plain text output of cf marketplace.



Managed Service

Page last updated:

The topics in this subsection explain how to integrate your brokered service more closely with Pivotal Cloud Foundry (PCF) to create a managed service and service tile for PCF.

Overview

The next level of integration is to get your service to be deployed on PCF rather than externally, on the same IaaS that your particular Cloud Foundry instance is deployed on, and by the same orchestration tool, BOSH ...

This is usually one of the more involved integrations, as you will have to change your packaging to allow your service components to be deployed by BOSH 🗷 onto the PCF infrastructure.

Offering your software as a managed service means that your PCF customers will not have to learn different ways to deploy, manage, and monitor different components of their application platform.

As with the brokered service, the service has a service broker and a tile listed on PivNet. PivNet lists managed services as "for PCF," without "Service Broker" in the name.

To integrate your service at this level, you will have to learn about stemcells, BOSH releases, and manifests. You will also have to decide how your service maps to virtual machines and how persistent storage is managed.

Minimal Viable Product

For a Minimal Viable Product (MVP) version of a managed service, we typically recommend that you aim for a single, shared service instance, and don't yet worry too much about High Availability of this instance. This integration level is mostly about getting the BOSH packaging, deployment, and monitoring working correctly.

High Availability

Once you have a managed service, you may decide to prioritize either on-demand provisioning of service instances, or making your single shared service instance more highly available.

When properly configured, BOSH monitors and restarts any failing processes and virtual machines that are part of your service deployment. But to further increase availability, you will have to think about spreading your resources across multiple availability zones or even regions, and replicating your persistent storage across those as well.

Create a Managed Service

- For BOSH to manage your service, you need to create a BOSH release for it.
 BOSH Releases explains how to do this, and how to use your already-existing Docker image as a shortcut.
- Once you have created a BOSH release for your managed service integration, you can work through Building Your First Tile 🗷 to create your tile.
- The <u>Tile Generator</u> tool automatically creates the lifecycle errands that can run after a PCF tile is deployed or before it is removed. PCF operators control which errands run the next time they click **Apply Changes** to redeploy. See the <u>Errands</u> topic for how PCF operators control when errands run, and how to set default errand run rules in the tile.

 $At any level of integration, Pivotal \, recommends \, and \, supports \, using \underline{\textbf{Concourse}} \, for \, continuous \, integration \, during \, development.$



BOSH Releases

Page last updated:

This topic provides resources for creating a BOSH release that integrates a software service with Pivotal Cloud Foundry (PCF) at the managed service level.

Overview

A BOSH release is a directory that contains the source code for your service along with everything else that BOSH needs to deploy it reproducibly to cloud VMs running a specified operating system (stemcell). These contents include but are not limited to buildpacks, start up scripts, binary artifacts, and a BOSH manifest containing configuration and deployment properties.

The BOSH manifest specifies the following major components:

- Packages that can be installed on PCF stemcells to create virtual machine images
- Jobs that describe how to install, run, and remove your software
- A Monitor script, that describes how to monitor the health of your service components and stop or restart them

BOSH Resources

These topics give more details on BOSH and BOSH releases:

- BOSH Documentation is the top-level contents page for BOSH documentation.
- BOSH Problem Statement ☑ explains what BOSH does.
- BOSH Basic Workflow ♂ lists the high-level steps for creating a BOSH deployment.

Creating a BOSH Release

These topics explain how to create a BOSH release:

- Defining your Jobs ☑
- Defining your VMs
- Defining your Runtime Configs ☑
- Monitoring the Health of your Service 🗷

Shortcut: Start with Docker Images

If you have already packaged your service as Docker images, you can emulate a managed service deployment using the Tile Generator's support for docker-bosh packages. This feature lets you deploy pre-existing Docker images into BOSH managed virtual machines on the PCF infrastructure.

While this is a great, easy way to deploy your service on PCF, we don't recommend this as a long-term, production-ready solution. There is really no benefit of running your service in containers on the VMs, and it does have a number of operational ("day 2") drawbacks:

- You introduce more software (Docker) which needs to be kept up-to-date, and has the potential for bugs, downtime, and security vulnerabilities.
- You can no longer take advantage of the patching capabilities of PCF for stemcells and application dependencies, like frameworks and libraries. Instead, you become directly responsible for managing all software that is in the Docker images you deploy.



Errands

Page last updated:

Lifecycle errands are BOSH errands (scripts) that run at the beginning and end of an installed product's availability time. Product teams create errands as part of a product package, and a product can only run errands it includes.

For more information about BOSH errands, see BOSH documentation \mathbb{Z} , and for more information about errands in Pivotal Cloud Foundry (PCF), see Managing Errands in Ops Manager \mathbb{Z} .

Products can have two kinds of errands. Post-deploy errands run after a product installs but before Ops Manager displays makes it available for use. Predelete errands run after an operator chooses to delete a product, but before Ops Manager finishes removing it from use.


To save deployment time, operators can set errand run rules that dictate whether or not errands run. Tile authors can set defaults for these run rules.

Post-Deploy Errands

Post-deploy errands run after a product installs, but before Ops Manager makes it available for use.

Typical post-install errands include smoke or acceptance tests, database initialization or database migration, and service broker registration.

Post-deploy errands run by default. An operator can prevent a post-deploy errand from running by setting its run rule to Off under Pending Changes in the Ops Manager Installation Dashboard or on the product tile's Settings tab Errands pane, before installing the product.



For example, Redis has a **Broker Registrar** post-deploy errand that the Elastic Runtime tile uses to register its service broker with the Cloud Controller and publish its service plans.

If an operator chooses Off in the drop-down menu for Elastic Runtime's Broker Registrar errand before installation, Elastic Runtime's service broker is not registered with the Cloud Controller and its service plans are not made public.



Pre-Delete Errands

Pre-delete errands run after an operator chooses to delete a product, but before Ops Manager actually finishes deleting it.

Typical pre-delete errands include clean up of application artifacts and service broker de-registration. For example, Pivotal MySQL has a Broker Deregistrar pre-delete errand that:

- Purges the service offering
- Purges all service instances
- Purges all application bindings
- Deletes the service broker from the Cloud Controller

When an operator chooses to delete the Pivotal MySQL product, Ops Manager first runs the Broker Deregistrar pre-delete errand, then deletes the product.

Pre-delete errands run by default. An operator can prevent a pre-delete errand from running by setting its run rule to Off under Pending Changes in the Ops Manager Installation Dashboard or on the product tile's Settings tab Errands pane, before installing the product.

Errand Run Rules




🛕 warning: In Ops Manager v1.10.0 and later, errands set to the When Changed rule do not always run when the tile has relevant changes. Instead of using When Changed, Pivotal recommends that tile developers leave the default run rule for errands as On and let operators use one-time rules

to turn errands off and save deploy time.

The same of the save deploy time.

Some errands do not always need to run. For example, installing a minor patch to a existing service might not require re-registering its broker. Ops Manager lets operators save installation time by turning errands off or on. They set these errand run rules in two places:

• One-Time Rules under Pending Changes in the Ops Manager Installation Dashboard. These rules only apply to the next time you run Apply Changes and do not persist after the next successful installation.



Persistent Rules in the tile's Errands pane. These rules persist through subsequent installations, until changed in the Errands pane.

For more information, see Configure Run Rules in Ops Manager .



On-Demand Service

Page last updated:

This topic explains how to integrate your software as an on-demand service and service tile for PCF.

Overview

Brokered service and managed service integrations assume that you have a single VM instance deployed for your software deployed, or a limited number of VMs.

These VMs can be multi-tenant, and you can possibly scale them manually to accommodate many concurrent applications. But for real production deployments, most of your customers will want dedicated VM instances of your service for each application.

On-demand (dynamic) services enable this flexibility in a scalable way. When an operator deploys the service, do not pre-allocate VM resources for service instances. Instead, they define an allowable range of VM memory and CPU sizes and create a dedicated network on the laaS to host any required number of service instance VMs.

When a developer creates an instance of an on-demand service, they provision its resources within the allowed range, and BOSH dynamically creates a new, dedicated VM for the instance.

Create an On-Demand Service

The best way to create an on-demand service is to use the On-Demand Services SDK ♂.

The on-demand services SDK provides a generic on-demand service broker (ODB) that Tile Generator can consume like any other service broker.

The on-demand service author does not write a service broker. Instead, they write a service adapter component that takes requests from the ODB and interfaces with their service software to fulfill requests from the ODB.

To create their tile, the tile author then feeds their service adapter and the BOSH release of the ODB to Tile Generator.

- [On-Demand Services SDK] documentation explains how to write a service adapter for an on-demand service that uses the ODB.
- Once you have the individual components for your brokered service integration, you can work through Building Your First Tile 🗷 to create your tile.

At any level of integration, Pivotal recommends and supports using Concourse for continuous integration during development.

High Availability

If you had not already configured your service for High Availability as a managed service, the final step would be to consider how you can make each of your dynamically-provisioned service instances more highly available.

Buildpacks

Page last updated:

Buildpacks compile and package apps to run on Pivotal Cloud Foundry (PCF). This topic lists resources for using and deploying buildpacks with PCF apps, and for creating your own custom buildpack.

Official Buildpacks

- Java buildpack ☑ (by far the most complicated!)
- Ruby buildpack ☑
- Node.js buildpack ☑
- PHP buildpack ☑
- Static file buildpack ☑ (for static web content)

Other Buildpacks

Buildpacks can also be used to inject additional code into the application container. For more information, see the following:

- The PCF documentation topic Creating Custom Buildpacks
- The github repo Eureka Registrar Sidecar 🗷
- The github repo Spring Config Injection 🗷

Custom Buildpacks

Creating a Custom Buildpack ♂

CredHub

Page last updated:

CredHub is a secure credential management component that runs on the BOSH VM to minimize the surface area where credentials can be compromised. This topic provides resources for configuring service tiles to use CredHub, instead of encoding credentials in product template and job template files.

See the CredHub documentation ☐ for more information.

Overview

Many PCF components use credentials to authenticate connections, and PCF installations often have hundreds of active credentials. Secure credential management is essential to prevent data and security breaches.

In Pivotal Cloud Foundry (PCF) v1.11.0, CredHub runs on the BOSH VM, alongside the BOSH Director and UAA. Ops Manager v1.11 stores its credentials in CredHub, and users can retrieve them using the CredHub API or the **Credentials** tab of the Ops Manager Director tile. Tile developers can embed CredHub calls in manifest snippets and PCF apps can retrieve credentials using the CredHub API.

See Fetching Variable Names and Values for how to fetch variable names and values using the CredHub API.

CredHub Credential Types

CredHub stores and retrieves the following types of credentials:

- value single string value
- json arbitrary JSON object
- password password string
- certificate object containing certificate authority (CA), certificate, and private key
- ssh object containing SSH public key and private key
- rsa object containing RSA public key and private key

For more information, read CredHub Credential Types .

Creating New Variables

To use CredHub in your deployment, you must create new variables and store them in CredHub. By default, variable namespaces are written to prevent collision across deployments, but you can type variable names precisely if you wish.

For more information, read Creating New Variables in CredHub.

Migrating Credentials

To migrate existing non-configurable credentials to CredHub, such as blobstore secrets and backup encryption keys, use the JavaScript migration process. After a successful migration, Ops Manager deletes the migrated credentials from installation.yml.

For more information, read Migrating Existing Credentials to CredHub.

Fetching Variable Names and Values

API endpoints are available to help you find variable names and values for products known to the Ops Manager Director.

For more information, read Fetching Variable Names and Values.



CredHub in Manifest Snippets

Tile developers can embed CredHub in product template and job template manifest snippets using triple-parenthesis notation:

```
manifest: |
credhub:
concatenated_password: prefix-((( credhub-password )))-suffix
password: ((( credhub-password )))
```

PCF v1.11.0 Limitations

PCF v1.11.0 supports CredHub for credential storage, but it does not support the following:

- Automatic backup and restore for CredHub, along with other PCF system components.
- Automatic tile upgrades that migrate all types of credentials defined in property blueprints in previous tile versions, to storage in CredHub.
- Using CredHub to generate new credentials.

Tile authors may choose to wait until PCF supports some or all of these features before incorporating CredHub into their service.



Creating New Variables in CredHub

Page last updated:

This topic explains how CredHub manages variables in the context of a larger deployment, and how to create new variables for use in CredHub.

Background

When a tile author defines a top-level variables section in the product template, Ops Manager passes the variables section to the product manifest. tile authors can define variables in the product template as follows:

variables

- name: EXAMPLE-CREDHUB-PASSWORD type: password

You can reference these variables in the manifest snippets in their tile metadata using a triple parentheses syntax:

(((EXAMPLE-CREDHUB-PASSWORD)))

Using triple parentheses lets Ops Manager identify CredHub variables while still supporting the BOSH double parentheses syntax. A variable referenced within triple parentheses is replaced by double parentheses in the generated manifest. After contacting CredHub, BOSH populates that variable value internally.

The benefit of this approach is that the Ops Manager YAML file does not contain sensitive credentials when the metadata manifest snippets have triple parentheses. The resulting manifest file contains variables within double parentheses, rather than unobscured credentials.

For example, a tile author adds credentials to a manifest snippet in the following format:

 $\label{eq:key: (((EXAMPLE-CREDHUB-PASSWORD\)))} key: prefix-(((ANOTHER-CREDHUB-PASSWORD\)))-suffix$

Ops Manager evaluates the above example to generate the following section in the product manifest:

((EXAMPLE-CREDHUB-PASSWORD))
prefix-((ANOTHER-CREDHUB-PASSWORD))-suffix

How CredHub Works Within a Deployment

CredHub is distributed as a BOSH release. As part of this installation, Ops Manager co-locates the CredHub release on the Ops Manager Director, including the CredHub job configurations, and the Director is configured to point to the CredHub API.

Once CredHub has been deployed and configured on the Director, any Director deployment can use CredHub variables in place of credential values. Using variables, rather than values, provides an extra layer of security when transmitting credentials within your deployment.

Changing Your Deployment Manifest to Include CredHub Variables

The Ops Manager Director interpolates credential values into manifests that use the ((variables)) syntax. When the Director encounters a variable using this syntax, it requests the credential value from CredHub. If the credential does not exist and the release or manifest contains generation properties, the credential value is generated automatically.

The manifest excerpt below includes references to two credentials, EXAMPLE-PASSWORD and EXAMPLE-TLS .

When this manifest is deployed, the Ops Manager Director retrieves the stored variables and replaces them with the credential values associated with each variable. The EXAMPLE-TLS variables include property accessors, so only the certificate and private key components are interpolated.

```
name: demo-deploy

instance_groups:
    jobs:
    - name: demo
    release: demo
    properties:
    demo:
    password: ((EXAMPLE-PASSWORD))
    tls:
        certificate: ((EXAMPLE-TLS.certificate))
        private_key: ((EXAMPLE-TLS.private_key))
```

Ops Manager configures the Director to generate a credential if it does not exist. The manifest includes generation parameters that define how the credential should be generated. These generation parameters are defined in the variables section as shown below.

```
name: demo deploy
variables:
- name: EXAMPLE-PASSWORD
type: password
- name: EXAMPLE-CA
 type: certificate
 options:
  is_ca: true
  common_name: 'Example Certificate Authority'
 name: EXAMPLE-TLS
type: certificate
 options:
 ca: EXAMPLE-CA
 common name: example.com
instance_groups:
 jobs:
 - name: demo
  release: demo
  properties:
    password: (( EXAMPLE-PASSWORD ))
    certificate: (( EXAMPLE-TLS.certificate ))
     private_key: (( EXAMPLE-TLS.private_key ))
```

Variable Namespacing

Deployment manifests often use common variable names; for example, ((PASSWORD)). To avoid variable name collisions between deployments, the Ops Manager Director automatically stores variables with the Ops Manager Director name and deployment name. For example, the variable ((EXAMPLE-PASSWORD)) is stored in CredHub as /Ops-Manager-Director-name/deployment-name/example-password.

Other Namespacing Options

Use a BOSH link to share credentials across deployments. Alternatively, if you want to use an exact name, prefixing the variable with a forward slash (/) will cause the Director to use the exact name you type. An example of a precisely typed variable follows.

((/EXAMPLE-PASSWORD))

Migrating Existing Credentials to CredHub

Page last updated:

This topic explains how to migrate non-configurable secrets from Ops Manager into CredHub.

CredHub Credential Types

CredHub uses BOSH credential types, which may have different names from Ops Manager credential types. The following table lists the Ops Manager credential types you can migrate to CredHub and the corresponding CredHub credential types.

Ops Manager Credential Type	CredHub Credential Type	Supported Ops Manager Version
secret	password	1.11.1
simple_credential	user	1.12 Alpha 1
salted_credential	user	1.12 Beta 1
rsa_pkey_credential	rsa	1.12 Alpha 1



Note: CredHub does not retain the salt when migrating salted_credentials.

See Property Reference for more information about credential types.

Use the JavaScript Migration Process

Tile authors can write a JavaScript migration to move their existing non-configurable secrets into CredHub. After a successful migration, Ops Manager deletes credentials from installation.yml.

1. Use the following example to write the JavaScript migration. Save the JavaScript file to the PRODUCT/migrations/v1 directory of your .pivotal tile, following the naming conventions discussed in the Update Values or Property Names Using JavaScripttopic.

```
exports.migrate = function(input) {
 input.variable migrations.push({
 from: input.properties['.PROPERTY-REFERENCE.EXAMPLE-SECRET'],
 to variable: 'SECRET-VARIABLE'
 return input;
```

In the code block above, replace the example text as follows:

- PROPERTY-REFERENCE: Replace with the property reference that corresponds to the metadata file, such as properties. See Tile Upgrades for more information about migrating properties.
- EXAMPLE-SECRET: Replace with the name of the key.
- SECRET-VARIABLE: Choose a variable name for the migrated secret.
- 2. Remove the property blueprint for the secret and replace it with a CredHub variable.
 - o In your metadata, remove the block that includes the credential. For example, remove the block that includes -name: EXAMPLE-SECRET and type: secret .

```
property_blueprints:
 - name: EXAMPLE-SECRET
  type: secret
 - name: generated_uuid
 type: uuid
 - name: configured secret
  type: secret
  configurable: true
  optional: true
 - name: configured_simple_credentials
  type: simple_credentials
  configurable: true
  optional: true
```



• In handcraft.yml, add a variables section and include the variable name and type:

variables: - name: SECRET-VARIABLE type: password



Note: While the property blueprint refers to the above type as secret, BOSH refers to the type as password. See the CredHub Credential Types table at the beginning of this topic for more information about credential types.

- ${\it 3. \ \, In your manifest snippet, replace the existing secret value with the new triple-parenthesis syntax.}$
 - Remove the existing secret from the manifest snippet:

```
secret: (( .PROPERTY-REFERENCE.SECRET-VARIABLE.SECRET-VALUE ))
```

• Add the new CredHub variable to the manifest snippet:

secret: (((SECRET-VARIABLE)))

- 4. Run a test deploy of your tile.
- 5. Use an API endpoint to confirm that the credential is stored in the variable. For more information about the endpoint, see Fetching Variable Names and Values.



Fetching Variable Names and Values

Page last updated:

Overview

CredHub has two API endpoints to identify and re-use variables. Operators who want to see all the credentials associated with their product, or support engineers who want to troubleshoot issues specific to one virtual machine (VM), can use these APIs for those purposes.

The API endpoints perform these functions:

- Identifying and printing the name of a variable
- Using the name of the variable to identify and print the value of the variable

Using the API Endpoints

Use these endpoints to view variables for any product in Ops Manager, except the Ops Manager Director. These endpoints are read-only. You cannot use them to add, remove, or rotate variables.

Fetching Variables

This endpoint returns the list of variables associated with a product that are stored in CredHub. Not all variables are stored in CredHub. If you call a variable that is not stored in CredHub, the call returns an empty value.

```
$ curl "https://OPS-MAN-FQDN/api/v0/deployed/products/product-guid/variables" \
-X GET \
-H "Authorization: Bearer EXAMPLE_UAA_ACCESS_TOKEN"
```

Example Response

```
HTTP/1.1 200 OK

{
    "variables": ["FIRST-EXAMPLE-VARIABLE", "SECOND-EXAMPLE-VARIABLE", "THIRD-EXAMPLE-VARIABLE"]
}
```

Query Parameters

Parameter	Description
product_guid	The unique product identifier, formatted as a text string

This endpoint returns a variable's name. Use the name in the next endpoint to return the variable's value.

Fetching Variable Values

This endpoint returns the value of a variable stored in CredHub. Not all variables are stored in CredHub, so if you call a variable that isn't in CredHub, the call will return an empty value.

```
$ curl "https://OPS-MAN-FQDN/api/v0/deployed/products/product-guid/variables?name=EXAMPLE-VARIABLE-NAME" \
-X GET \
-H "Authorization: Bearer UAA_ACCESS_TOKEN"
```



Example Response

```
HTTP/1.1 200 OK

{
  "credhub-password": "EXAMPLE-PASSWORD"
}
```

Query Parameters

Parameter	Description
variable_name	The name of the variable, formatted as a text string
product_guid	The unique product identifier, formatted as a text string



Embedded Agents

Page last updated:

This topic provides resources for configuring services that use software agents embedded in application containers.

Overview

Some service integrations depend on the ability to inject code into application containers. Examples include:

- Application Performance Monitoring (APM) agents for monitoring services
- Container-embedded API gateways
- Client-side routers

We refer to these injected components as "container-embedded agents."

Embedded Agents Resources

- Buildpacks provide a mechanism to inject components into the application container image, and the <code>.profile.d</code> directory provides a way to start agents before or alongside the customer application.
- Using .profile.d ☑



Logs, Metrics, and Nozzles

Page last updated:

This topic explains how to integrate PCF services with Cloud Foundry's logging system, the *Loggregator*, by writing to and reading from its *Firehose* endpoint.

Overview

Cloud Foundry's Loggregator logging system collects logs and metrics from PCF apps and platform components and streams them to a single endpoint, the Firehose. Your tile can integrate its service with the Loggregator system in two ways:

- By sending your service component logs and metrics to the Firehose, to be streamed along with PCF core platform component logs and metrics.
- By installing a nozzle on the Firehose that directs Firehose data to be consumed by external services or apps. A built-in nozzle can enable a service to:
 - o Drain metrics to an external dashboard product, for system operators
 - o Send HTTP request details to search or analysis tools
 - o Drain app logs to an external system
 - ∘ Auto-scale itself ☑ based on Firehose metrics

Firehose-to-syslog

is a real world, production example of a nozzle.

is a real world, production example of a nozzle.

Firehose Communication

PCF components publish logs and metrics to the Firehose through Metron agent processes that run locally on the component VMs. Metron agents input the data to the Loggregator system by writing it to Loggregator's etcd & key-value store via a gRPC proxy. The topic Overview of the Loggregator System shows how logs and metrics travel from PCF system components to the Firehose.

Component VMs running PCF services can publish logs and metrics the same way, by including a Metron agent that writes to etcd. In PCF v1.10 and later, components only communicate with etcd via secure, encrypted https protocol. Earlier versions of PCF allow both encrypted https and unencrypted https communications with etcd.

Secure HTTPS Protocol: PCF 1.10+

To enable a service component to supply logs and metrics to the Firehose through encrypted communications, you need to include a Metron agent and a Consul agent in its template definitions.

The Metron definition includes double-paren properties defining a keypair for accessing etcd. The Consul definition includes double-paren properties for securely looking up the internal IP addresses of the etcd nodes at cf-etcd.service.cf.internal . This avoids hard-coding any etcd server addresses.

For example:

```
name: service
label: Service
templates:
 - name: consul
  release: consul
 - name: metron_agent
 release: loggregator
 release: service
manifest:
metron agent
 deployment: cf-my-service
  etcd:
   client cert: (( ..cf.properties.cf etcd client cert.cert pem ))
   client key: (( ..cf.properties.cf etcd client cert.private key pem ))
 metron endpoint:
  shared\_secret: ((\ ..cf.doppler.shared\_secret\_credentials.password\ ))
 loggregator:
  etcd:
   require_ssl: true
   machines: ['cf-etcd.service.cf.internal']
   ca_cert: (( $ops_manager.ca_certificate ))
 consul:
  encrypt_keys:
  - (( ..cf.properties.consul_encrypt_key.value ))
  ca_cert: (( $ops_manager.ca certificate ))
  agent_cert: (( ..cf.properties.consul_agent_cert.cert_pem ))
  agent\_key: ((\ ..cf.properties.consul\_agent\_cert.private\_key\_pem\ ))
   domain: cf.internal
   servers:
    lan: (( ..cf.consul_server.ips ))
```

Metron versions v72 and later do not use etcd to communicate with Loggregator, but the configuration above works with any version of Metron. If the Metron agent does not need values for etcd, it safely ignores them.

HTTP Protocol: PCF 1.9 and Earlier

In PCF v1.9, service components can send logs and metrics to the Firehose encrypted or unencrypted. In v1.8 and earlier releases, components only communicate their log and metrics data unencrypted.

To enable unencrypted communications with etcd, define a Metron agent and list the addresses of the etcd servers in the template definitions as follows:

```
name: service
label: Service
templates:
- name: metron_agent
release: loggregator
- name: service
release: service
manifest: |
metron_agent
deployment: cf-my-service
metron_endpoint:
shared_secret: (( ..cf.doppler.shared_secret_credentials.password ))
loggregator:
etcd:
machines: (( ..cf.etcd_server.ips ))
```

Nozzles

A nozzle is a component dedicated to reading and processing data that streams from the Firehose. A service tile can install a nozzle as either a managed service, with package type | bosh-release |; or as an app pushed to Elastic Runtime, with the package type | app |.

Develop a Nozzle

Pivotal recommends developing a nozzle in Go, to leverage the NOAA library . NOAA does the heavy lifting of establishing an authenticated websocket connection to the logging system as well as de-serializing the protocol buffers.

Draining the logs consists of:

- 1. Authenticating
- 2. Establishing a connection to the logging system
- 3. Forwarding events on to their ultimate destination

Authenticate against the API (https://github.com/cloudfoundry-community/go-cfclient 🗷) with a user in the doppler.firehose group:

```
import "github.com/cloudfoundry-community/go-cfclient"
...

config := &cfclient.Config {
    ApiAddress: apiUrl,
    Username: username,
    Password: password,
    SkipSsIValidation: ssISkipVerify,
}
```

Using the client's token, create a consumer and connect to the Firehose with a subscription id. The id is important, since the Firehose looks for connections having the same id and only sends an event to one of those connections. This is how a nozzle developer can prevent message loss during upgrades an other deployments: run at least two instances.

```
token, err := client.GetToken()

consumer := consumer.New(config.TrafficControllerURL, &tls.Config{
    InsecureSkipVerify: config.SkipSSL,
    }, nil)
    events, errors := consumer.Firehose(firehoseSubscriptionID, token)
```

Firehose will give back two channels: one for events and a second for errors.

The events channel receives six different types of events.

- ValueMetric: Some platform metric at a point in time, emitted by platform components. For example, how many 2xx responses the router has sent out.
- CounterEvent: An incrementing counter, emitted by platform components. For example, a Diego cell's remaining memory capacity.
- Error: An error.
- HttpStartStop: HTTP request details, including both app and platform requests.
- LogMessage: A log message for an individual app.
- ContainerMetric: Application container information. For example, memory used.

For the full details on events, see the dropsonde protocol ♂.

The above events show how this data targets two different personae: platform operators and app developers. Keep this in mind when designing an integration.

Having doppler.firehose scope gets a nozzle data for every app as well as the platform. Any filtering based on the event payload is the nozzle implementor's responsibility. An advanced integration could do something like combine a service broker with a nozzle to:

- Let app developers opt-in to logging (implementing filtering in the nozzle)
- Establish SSO c'exchange for authentication such that developers only can access logs for their space's apps

For a full working example (suitable as an integration starting point), see firehose-nozzle ...

Deploy a Nozzle

Once you've build a nozzle, you can deploy it as either a managed service or as an app.

As a Managed Service



Visit managed service for more details on what it means to be a managed service.

See also this example nozzle BOSH release .

As an App

You can also deploy the nozzle as an app on Elastic Runtime. Visit the Tile Generator's section on pushed apps for more details.

Example Nozzles

There are several open source examples you could use as a reference for building your nozzle

firehose-nozzle 2

- Example that simply writes to standard out
- Useful starting point: scaffolding, tests, etc are in place

example-nozzle ♂

• A single file implementation with no tests: as minimal as things can get

gcp-tools-release ♂

- In addition to Nozzle data, it drains component syslogs and health data
- Shows how to do a bosh-addon (for additional data outside a nozzle)
- Nozzle is managed through BOSH
- Raw logs and metrics data take different paths in the source

firehose-to-syslog ☑

- Includes implementation code that adds additional metadata, which might be needed for an access control list (ACL)
 - App name
 - Space UUID and name
 - o Org UUID and name
- logsearch-for-cloudfoundry ☑ packages this nozzle as a BOSH release

splunk-firehose-nozzle ♂

- Source code based on firehose-to-syslog
- Packaged to run an app on PCF

datadog-firehose-nozzle ☑

• Another real world implementation

Log Format for PCF Components

 $< \{PRI\} > \{VERSION\} \ \{TIMESTAMP\} \ \{HOST_IP\} \ \{APP_NAME\} \ \{PROD_ID\} \ \{MSG_ID\} \ \{SD-ELEMENT-instance\} \ \{MESSAGE\}$

The Syslog Message Elements table immediately below describes each element of the log, and the Structured Instance Data Format table describes the contents of the structured data element that carries Cloud Foundry VM instance information.

Syslog Message Elements

This table describes each element of a standard PCF syslog message.



Syslog Message Element	Meaning or Value
	Priority value (PRI) ☑, calculated as 8 × Facility Code + Severity Code
\${PRI}	Pivotal uses a Facility Code value of 1, indicating a user-level facility. This adds 8 to the RFC-5424 Severity Codes, resulting in the numbers listed in the table below. If in doubt, default to 13, to indicate Notice-level severity.
\${VERSION}	
\${TIMESTAMP}	The timestamp of when the log message is forwarded; typically slightly after it was generated. Example: 2017-07-24T05:14:15.000003Z
\${HOST_IP}	Internal IP address ☑ of origin server
\${APP_NAME}	Process name of the program the generated the message. Prefixed with vcap. For example: • vcap.rep • vcap.garden • vcap.cloud_controller_ng You can derive this process name from either the program name configured for the local Metron agent or the program that blackbox derives from the folder that syslog-release forwards logs into.
\${PROD_ID}	The Process ID of the syslog process doing the forwarding. If this is not easily available, default to - (hyphen) to indicate unknown.
\${MSG_ID}	The type 🗷 of log message. If this is not easily available, default to 🔁 (hyphen) to indicate unknown.
\${SD-ELEMENT- instance}	Structured data (SD) relevant to PCF about the source instance (VM) that originates the log message. See the Structured Instance Data Format table below for content and format.
\${MESSAGE}	The log message itself, ideally in JSON

RFC-5424 Severity Codes

PCF components generate log messages with the following severity levels. The most common severity level is 13.

Severity Code	Meaning
8	Emergency: system is unusable
9	Alert: action must be taken immediately
10	Critical: critical conditions
11	Error: error conditions
12	Warning: warning conditions
13	Notice: normal but significant condition
14	Informational: informational messages
15	Debug: debug-level messages

Structured Instance Data Format

The RFC-5424 syslog protocol includes a <u>structured data element or</u> that people can use as they see fit. Pivotal uses this element to carry VM instance information as follows:

SD-ELEMENT-instance element	Meaning
\${ENTERPRISE_ID}	Your Enterprise Number, as <u>listed</u> by the Internet Assigned Numbers Authority (IANA)



\${DIRECTOR}	The BOSH director managing the deployment.
\${DEPLOYMENT}	BOSH spec.deployment value
\${INSTANCE_GROUP}	BOSH instance_group, currently spec.job.name
\${AVAILABILITY_ZONE}	BOSH spec.az value
\${ID}	BOSH spec.id value. This is a GUID, not an index. Necessary because BOSH Availability Zone index values are not always unique or sequential.

Making Sense of Metrics

Monitoring Pivotal Cloud Foundry ☑ has a great rundown of the various metrics and how to make them useful.

Other Resources

- CF Summit Video Monitoring Cloud Foundry: Learning about the Firehose 🗷
- Loggregator GitHub repository ♂
- Loggregator's Slack Channel 🗷



Development Tools

Page last updated:

The topics in this section describe tools that Pivotal uses and recommends for tile development.

- Tile Generator takes a service software, a service broker, optional other components, and a simple configuration file and creates a tile and everything else required to deploy your software into PCF.
- The pcf Command Line Utility provides a command line interface for deploying and testing PCF tiles, to avoid the longer process of going through the Ops Manager GUI.
- Concourse is a continuous integration (CI) platform where you can create build pipelines that automate and streamline your tile development and integration with PCF.
- The Services SDK is a suite of tools designed to help you build enterprise-ready service offerings for the Marketplace. The SDK includes the On Demand Service Broker , Service Metrics for PCF , and Service Backups for PCF .



Development Environments

Page last updated:

This topic explains how to set up tile development environments, from simple standalone tools to a full PCF development environment. As you progress through the stages of tile development, you will likely also progress through these environments.

PCF Dev and BOSH Lite

Pivotal provides a lightweight (vagrant packaged) instance of PCF with some basic services as a free product named PCF Dev. This is a great environment to develop and test everything that runs in the Cloud Foundry Elastic Runtime.

Either of these environments allow you to develop the first three levels of service for Pivotal Cloud Foundry (PCF): a User-Provided Service, a Brokered Service, and a Managed Service.

If your integration includes managed services, you will also need an instance of BOSH that can manage virtual machines and BOSH releases for you. BOSH-Lite works well for that purpose.

Between these two components, you will have everything you need to develop tiles, except for Pivotal's Ops Manager. But if you followed the recommended workflow in Building Your First Tile C you will not need an actual full PCF environment until the later phases of your development.

Setting up BOSH-Lite



💡 Note: For this type of development environment, you only need BOSH-Lite itself to deploy managed service releases. You do not need to follow the instructions to Deploy Cloud Foundry in BOSH-Lite, as Cloud Foundry is provided by the PCF Dev installation above.

Setting up PCF Dev

PWS or Other Supported CF Infrastructure

Set Up Your PWS Account and Download the cf CLI 🗗 explains how to get started with Pivotal Web Services (PWS), a highly-available, production-scale PCF environment hosted by Pivotal.

PCF with Ops Manager

Partners who participate in our program have access to a number of shared PCF environments that are operated and managed by Pivotal. If you are not (yet) in our program, need a dedicated environment, or want to be able to work offline, you can set up your own environment. Often, a developer environment is sufficient for the early phases of an integration effort. But eventually, you will need access to a complete environment that includes Pivotal's Ops Manager on one of the supported infrastructures:

- Installing Pivotal Cloud Foundry ♂
- Operating Pivotal Cloud Foundry




Tile Generator

Page last updated:

This topic describes the Tile Generator tool, which helps tile authors develop, package, test, and deploy services and other add-ons to Pivotal Cloud Foundry (PCF).

Overview

Tiles are the installation package format used by Pivotal Ops Manager to deploy services and other add-ons to both public and private cloud deployments. Tile Generator uses templates and patterns that are based on years of experience integrating third-party services into Cloud Foundry and eliminates much of the need for you to have intimate knowledge of all the tools involved.



Tile Generator takes your software components and a simple configuration file that provides the minimal amount of information to describe and customize your tile. It then creates everything that's required to deploy your software into PCF:

- BOSH errands to deploy and delete your software, including blue/green deployments for zero-downtime upgrades
- A BOSH release suitable for deploying your software to the Elastic Runtime or open-source Cloud Foundry
- A Pivotal Ops Manager Tile that can be imported into Ops Manager, installed, configured, and deployed, including UI forms and automatic upgrades
 from previous versions
- A Concourse pipeline configuration to enable Continuous Integration of your software with the latest versions of PCF

Use Tile Generator in combination with the pcf utility to enable rapid deploy and test cycles of your software.

The current release of Tile Generator supports tiles that have any combination of the following package types:

- Cloud Foundry Applications
- Cloud Foundry Buildpacks
- Cloud Foundry Service Brokers (both inside and outside the Elastic Runtime)
- Docker images (both inside and outside the Elastic Runtime)

Legacy Tiles and OSS-Compatible Service Brokers

 $Many\ tile\ authors, in\ both\ Pivotal-internal\ teams\ and\ at\ external\ partner\ companies,\ built\ their\ PCF\ tiles\ before\ Tile\ Generator\ existed.$

Many other tile authors serve two markets with their service integrations, offering both a Cloud Foundry-compatible service broker to open-source users and corresponding PCF tile for PCF users. They want to continue serving both sets of users.

All of these tile authors can now use Tile Generator to simplify and speed up their development. Tile Generator can generate an OSS-compatible BOSH release service broker BOSH release in addition to a PivNet-ready PCF tile.



Screencast

For a 7-minute introduction into what Tile Generator is and does, see this screencast .

How to Use

1. Install the tile-generator python package.



Note: The tile-generator requires Python 2 and does not work with Python 3.

Pivotal recommends using a virtualenv 🗗 environment to avoid conflicts with other Python packages. A virtualenv is simply a directory containing dependencies for a project. When a virtual environment is active, packages install into the virtualenv instead of the system-wide Python installation. Create a virtualenv with the virtualenv command:

virtualeny -p python2 tile-generator-eny

To activate the virtualenv, source the bin/activate script in the virtualenv directory:

source tile-generator-env/bin/activate

Then install the tile-generator package inside the virtualenv with:

pip install tile-generator

This puts the tile and pef commands in your PATH when the virtualenv is active. To deactivate the virtualenv, simply run the command deactivate .



Note: To upgrade Tile Generator, run the following command with the virtualenv activated: pip install tile-generator --upgrade

- 2. Install the BOSH CLI
- 3. From within the root directory of the project for which you want to create a tile, initialize it as a tile repository. Pivotal recommends that you use a git repository:

cd YOUR-PROD-DIRECTORY tile init

- 4. Edit the generated tile.yml file to define your tile.
- 5. Build your tile:

tile build

The generator first creates a BOSH release in the release subdirectory, then wrap that release into a Pivotal tile (in the product subdirectory). If required for the installation, it automatically pulls down the latest release version of the Cloud Foundry CLI.

Tile Generator is also available pre-installed in a Docker image on Docker Hub . This image contains the tile-generator tile and pcf commands, all the necessary Python dependencies, as well as the BOSH CLI.

You can use this in Concourse pipelines by specifying it as the base image for your tasks:

- task: tile-build config: image: cfplatformeng/tile-generator

Or, you can derive your own Docker images from this one by using it as the base image in your Dockerfile:

FROM cfplatformeng/tile-generator



Build the Sample

The tile-generator repository of includes a sample tile of that exercises most of the features of Tile Generator. This sample tile is used by Tile Generator's CI pipeline to verify that things work correctly. You can build this sample using the following steps:

- 1. Download the Redis BOSH release 🗗 and save it to sample/resources/redis-13.1.2.tgz
- 2. Run the following commands:

cd sample src/build.sh tile build



Note: The sample tile includes a Python app that is re-used in several packages, sometimes as an app, sometimes as a service broker. One of the deployments (app3) uses the sample app inside a Docker image that is currently only modified by the CI pipeline. If you modify the sample app, you have to build your own Docker image using the provided Dockerfile and change the image name in sample/tile.yml to include the modified code in app3.

Define your Tile in tile.yml

All required configuration for your tile is in the file called tile.yml. tile creates an initial version for you that can serve as a template. The first section in initial version for you that can serve as a template.

the file describes the general properties of your tile:

name: tile-name # Match Pivotal Network product name, lowercase with dashes icon_file: resources/icon.png label: Brief Text for the Tile Icon description: Longer description of the tile's purpose

The name should be informative, for example, your company name followed by the product name, e.g., acme-anvil. The name should match your product slug on Pivotal Network, which enables update notifications for customers. Coordinate with your product team to agree upon a name; marketing teams often care about the name because it shows up in Pivotal Network URLs.

The icon_file should be a 128x128 pixel image that appears on your tile in the Ops Manager GUI. By convention, any resources used by the tile should be placed in the resources sub-directory of your repository, although this is not mandatory. The label text appears on the tile under your icon.

Packages

Next you can specify the packages to be included in your tile. The format of each package entry depends on the type of package you are adding.

Pushed Apps

Apps (including service brokers) that are being cf push ed into the Elastic Runtime use the following format:



```
- name: mv-application
 type: app # or app-broker
 manifest:
  # any options that you would normally specify in a cf manifest.yml, including</i>
  build pack: \#required
  command:
  domain:
  host:
  instances
  memory:
 path:
  env:
 services:
 health check: none
                            # optional
 configurable_persistence: true # optional
 needs_cf_credentials: true
                            # optional
                         # optional
 auto_services:
 - name: p-mysql
 plan: 100MB
 - name: p-redis
 plan: shared-vm
 consumes:
                          # optional
  redis
   from: redis
```

For apps that are normally pushed as multiple files (node.js for example) zip up the project files plus all dependencies into a single ZIP file, then edit tile.yml to point to the zipped file:

```
cd <your project dir>
zip -r resources/<your project name>.zip <list of file and dirs to include in the zip>
```

If your app is a service broker, use app-broker as the type instead of just app . The app is then automatically registered as a broker on install, and deleted on uninstall.

health_check lets you configure the value of the cf cli --health_check_type option. Expect this option to move into the manifest as soon as CF supports it there. Currently, the only valid options are none and port.

configurable persistence: true results in the user being able to select a backing service for data persistence. If there is a specific broker you want to use, you can use the auto-services feature described below. If you want to bind to an already existing service instance, use the services property of the manifest instead.

needs_cf_credentials causes the app to receive two additional environment variables named CF_ADMIN_USER and CF_ADMIN_PASSWORD with the admin credentials for the Elastic Runtime into which they are being deployed. This allows apps and services to interact with the Cloud Controller.

The auto_services feature is described in more detail below.

consumes specifies the BOSH links It to consume and presents the hosts and properties from the links as environment variables on the app:

- <LINK>_HOST : The address of the first instance of the link.
- <LINK>_HOSTS: A JSON array of the addresses of all instances of the link.
- <LINK>_PROPERTIES : A JSON object of the properties on the link.

Service Brokers

Most modern service brokers are pushed into the Elastic Runtime as normal CF apps. For these types of brokers, use the Pushed Application format specified above, but set the type to app-broker or docker-app-broker instead of just app or docker-app :



```
- name: mv-broker
type: app-broker
 manifest:
 buildpack: # required
  command:
 domain:
 path:
 needs_cf_credentials: true
                               # optional
                           # optional
 auto services:
 - name: p-mysql
 plan: 100MB
 - name: p-redis
 plan: shared-vm
 enable_global_access_to_plans: true # optional
```



💡 Note: Unless you specify the enable_global_access_to_plans: true option, your broker's services do not appear in the user's Marketplaces. Operators have to use the of enable-service-access command to allow specific users, orgs, and spaces to access your services.

Your broker is automatically registered with the Cloud Controller. The Cloud Controller invokes your broker's endpoints, and it uses basic authentication to secure those API calls. The credentials it uses are passed to your broker in two environment variables:

```
SECURITY_USER_NAME
SECURITY_USER_PASSWORD
```

Your broker is expected to accept those credentials. If it doesn't, automatic broker registration fails.

Some service brokers support operator-defined service plans, for instance when the plans reflect customer license keys. To allow operators to add plans from the tile configuration, add the following section at the top level of your tile.yml:

```
service_plan_forms:
- name: service_plans_1
label: Service 1 Plans
description: Specify the plans you want Service 1 to offer
properties:
 - name: description
  type: string
  description: "Some Description"
  configurable: true
 - name: license_key1
  type: string
  configurable: true
  description: The license key for this plan
 - name: num_seats1
 type: integer
  configurable: true
  description: The number of available seats for this license
  default: 1
  constraints
   min: 1
   max: 500
```

Name and GUID fields are supplied by default for each plan, but all other fields are optional and customizable. Multiple forms are supported. The operator-configured plans are passed to your service broker in JSON format in an environment variable named after your form but in ALL CAPS (in this case SERVICE PLANS 1).

For an external service broker, use:

```
- name: my-application
type: external-broker
uri: http://broker3.example.com
username: user
 password: #secret
 internal_service names: 'service1,service2'
```

BOSH Releases

You can include BOSH releases 🗷 in your tile with the bosh-release package type. For example, here is a package definition to include a Redis BOSH release:

```
- name: redis
type: bosh-release
 path: resources/redis-13.1.2.tgz
jobs:
 - name: redis
  templates:
  - name: redis
   release: redis
  memory: 512
  ephemeral_disk: 4096
  persistent disk: 4096
  instances: 2
  cpu: 2
  static_ip: 0
  dynamic_ip: 1
  default_internet_connected: false
  max in flight: 1
  properties:
  password: red!s
 - name: sanity-tests
  templates:
  - name: sanity-tests
   release: redis
  lifecycle: errand
  post deploy: true
  run_post_deploy_errand_default: when-changed
  memory: 512
  ephemeral disk: 4096
  persistent_disk: 0
  cpu: 2
  dynamic_ip: 1
```

To include BOSH links $\@model{C}$ in your bosh-release package's deployment manifest, you can include the consumes and/or provides declarations as strings in the job's templates section, e.g.:

```
# ...
jobs:
- name: job_name
templates:
- name: template_name
consumes: |
    consumed_link: {from: foo}
provides: |
    provided_link: {as: bar}
```

Buildpacks

```
- name: my-buildpack
type: buildpack
path: resources/buildpack.zip
buildpack_order: 99 # optional, 99 means end of the list
```

Docker Images

Apps packages as Docker images can be deployed inside or outside the Elastic Runtime. To push a Docker image as a CF app, use the Pushed Application format specified above, but use the docker-app or docker-app-broker type instead of just app or app-broker. The Docker image to be used is then specified using the image property:

```
- name: app1
type: docker-app
image: test/dockerimage
manifest:
...
```

If this app is also a service broker, use docker-app-broker instead of just docker-app . This option is appropriate for Docker-wrapped 12-factor apps that delegate their persistence to bound services.

Docker apps that require persistent storage can not be deployed into the Elastic Runtime. These can be deployed to separate BOSH-managed VMs instead by using the docker-bosh type:

```
- name: docker-bosh1
type: docker-bosh
 cpu: 5
 memory: 4096
 ephemeral_disk: 4096
 persistent_disk: 2048
 instances: 1
 manifest: |
  containers
   image: "redis"
   command: "--dir /var/lib/redis/ --appendonly yes"
   bind ports:
   - "6379:6379"
   bind volumes:
   - "/var/lib/redis'
   entrypoint: "redis-server"
   memory: "256m"
   env_vars:
   - "EXAMPLE_VAR=1"
  - name: mysql
   image: "google/mysql"
   bind_ports:
    - "3306:3306"
   bind_volumes:
   - "/mysql"
  - name: elasticsearch
   image: "bosh/elasticsearch"
   links:
   - mysql:db
   depends_on:
   - mysql
   bind_ports
   - "9200:9200"
```

If a Docker image cannot be downloaded by BOSH dynamically, provide a ready-made Docker image and package it as part of the BOSH release. In that case, specify the image as a local file.

```
- name: docker-bosh2
type: docker-bosh
files:
- path: resources/cfplatformeng-docker-tile-example.tgz
cpu: 5
memory: 4096
ephemeral_disk: 4096
persistent_disk: 2048
instances: 1
manifest: |
containers:
- name: test_docker_image
image: "cfplatformeng/docker-tile-example"
env_vars:
- "EXAMPLE_VAR=1"
# See below on custom forms/variables and binding it to the Docker env variable
- "custom_variable_name=((.properties.customer_name.value))"
```

To expose a container via gorouter , for example, one of the Docker containers hosts an admin webapp interface, use routes to choose a port and prefix. The external URL is [prefix]-[package.name].[system-domain] . In this case, the URL is https://admin-docker-bosh3.sys.example.com , where sys.example.com is the PCF system domain. routes is a list, so multiple containers can be exposed.



```
- name: docker-bosh3
type: docker-bosh
docker images:
- "cfplatformeng/database"
- "cfplatformeng/admin_ui"
routes:
 - prefix: admin
  port: 8080
 cpu: 5
memory: 4096
ephemeral disk: 4096
 instances: 1
manifest:
 containers
 - name: database
  image: "cfplatformeng/database"
  bind_ports:
   - "5432:5432"
  - name: admin_ui
  image: "cfplatformeng/admin_ui"
   bind_ports:
   - "8080:8080"
```

Custom Forms and Properties

You can pass custom properties to all apps deployed by your tile by adding the to the properties section of tile.yml:

```
properties:
- name: author
type: string
label: Author
value: Tile Ninja
```

If you want the properties to be configurable by the tile installer, place them on a custom form instead:

```
- name: custom-form1
label: Test Tile
description: Custom Properties for Test Tile
properties:
- name: customer_name
 type: string
 label: Full Name
- name: street address
 type: string
 label: Street Address
 description: Address to use for junk mail
- name: city
 type: string
 label: City
- name: zip_code
 type: string
 label: ZIP+4
 default: '90310'
- name: country
 type: dropdown_select
 label: Country
 options:
 - name: country_us
  label: US
  default: true
 - name: country_elsewhere
  label: Elsewhere
- name: account-info-1
description: Example Account Information Form
properties:
- name: username
 type: string
 label: Username
- name: password
 type: secret
 label: Password
```

Properties defined in either section are passed to all pushed apps as environment variables (the name of the environment variable is the same as the



property name but in ALL_CAPS). They can also be referenced in other parts of the configuration file by using ((.properties.property-name instead of a

hardcoded value.

All properties supported by Ops Manager may be used. The syntax is the same as used by Ops Manager, except that for simplicity property blueprints for form fields do not need to be declared separately. Instead, the declaration is included in the form itself. For a complete list of supported property types and syntax, see the Ops Manager Product Template Reference.

Properties of type | secret | have their value hidden on the forms and obfuscated in the installation logs (all but the first two characters are replaced by | secret | have their value hidden on the forms and obfuscated in the installation logs (all but the first two characters are replaced by | secret | have their value hidden on the forms and obfuscated in the installation logs (all but the first two characters are replaced by | secret | have their value hidden on the forms and obfuscated in the installation logs (all but the first two characters are replaced by | secret | have their value hidden on the forms and obfuscated in the installation logs (all but the first two characters are replaced by | secret | have their value hidden on the forms and obfuscated in the installation logs (all but the first two characters are replaced by | secret | have their value hidden on the forms and obfuscated in the installation logs (all but the first two characters are replaced by | secret | have their value hidden on the forms and obfuscated hidden on the first two characters are replaced by | secret | have their value hidden on the forms and obfuscated hidden on the first two characters are replaced by | secret | have their value hidden on the first two characters are replaced by | secret | have the first two characters are replaced by | secret | have the first two characters are replaced by | secret | have the first two characters are replaced by | secret | have the first two characters are replaced by | secret | have the first two characters are replaced by | secret | have the first two characters are replaced by | secret | have the first two characters | have the first tw

Automatic Provisioning of Services

Tile Generator automates the provisioning of services. Any app (including service brokers and Docker-based apps) that are being pushed into the Elastic Runtime can automatically be bound to services through the auto_services | feature:

- name: app1 type: app auto_services: - name: p-mysql plan: 100mb-dev - name: p-redis

You can specify any number of service names, optionally specifying a specific plan. During deployment, the generated tile creates an instance of each service if one does not already exist and then bind that instance to your package.

Service instances provisioned this way survive updates, but are deleted when the tile is uninstalled.



Note: The name is the name of the provided *service*, *not the broker*. In many cases these are not the same, and a single broker may even offer multiple services. Use of service-access to see the services and plans offered by installed service brokers.

If you do not specify a plan, Tile Generator uses the first plan listed for the service in the broker catalog. It is a good idea to always specify a service plan. If you *change* the plan between versions of your tile, Tile Generator attempts to update the plan while preserving the service (thus not causing data loss during upgrade). If the service does not support plan changes, this causes the upgrade to fail.

configurable persistence is really just a special case of auto_services , letting the user choose between some standard brokers.

Declaring Product Dependencies

When your product has dependencies on others, you can have Ops Manager enforce that dependency by declaring it in your tile.yml file as follows:

requires_product_versions:
- name: p-mysql
version: '-> 1.7'

and refuses to install your tile until that dependency is satisfied.

When using automatic provisioning of services as described above, it is often appropriate to add those products as a dependency. Tile Generator can not do this automatically as it can't always determine which product provides the requested service.

Orgs and Spaces

By default, Tile Generator creates a single new org and space for any packages that install into the Elastic Runtime, using the name of the tile and appending org and organic org and organic organic

org: test-org
org_quota: 4096
space: test-space



Security

If your cf packages need outbound access (including access to other packages within the same tile), you need to apply an appropriate security group. The following option removes all constraints on outbound traffic:

```
apply_open_security_group: true
```

Stemcells

Tile Generator defaults to a recent stemcell supported by Ops Manager. In most cases the default is fine, because the stemcell is only used to execute CF command lines and/or the Docker daemon. But if you have specific stemcell requirements, you can override the defaults in your tile.yml file by including a stemcell-criteria section and replacing the appropriate values:

```
stemcell_criteria:
os: 'ubuntu-trusty'
version: '3146.5' #NOTE: You must quote the version to force the type to be string
```

Custom Errands

Tile Generator supplies standard errands to deploy and delete CF type packages. You can replace or augment those errands by specifying errand shell commands in your tile.yml file. Here is an example of a custom deploy errand to install a buildpack only if a newer version of that same buildpack is not already present:

```
packages:
- name: my-buildpack
 type: buildpack
 buildpack_order: 0 # Go to head of list
 path: my_buildpack.zip
 cp my_buildpack.zip my_buildpack-v{{context.version}}.zip
  existing='cf buildpacks | grep '^my_buildpack'
  if [ -z "$existing" ]; then
   cf\ create-buildpack\ my\_buildpack\ my\_buildpack-v\{\{context.version\}\}.zip\ 0
   if is_newer "{{context.version}}" "$semver"; then
    cf.update-buildpack.my\_buildpack-p.my\_buildpack-v\{\{context.version\}\}.zip
    echo "Newer version ($semver) of my_buildpack is already present"
   fi
   cf update-buildpack my_buildpack -i 0
 delete:
  # Intentional no-op, as others may have a dependency on this
```

deploy and delete completely replace the standard errand commands for the package in which you include them. If you want to keep the standard commands, but add additional commands to execute before or after the standard errand, use pre_deploy | post_deploy | pre_delete |, and/or post_delete instead.

Versioning

Tile Generator uses semver versioning . By default, tile build generates the next patch release. Major and minor releases can be generated by explicitly specifying tile build or tile build minor . Or to override the version number completely, specify a valid semver version on the build command, e.g. tile build 3.4.5.

No-op content migration rules are generated for every prior release to the current release, so that Ops Manager allows tile upgrades from any version to any newer version. This depends on the existence of the file tile-history.yml. In a pinch, if you need to be able to upgrade from a random old version to a new one, you can edit that file, or do:

```
tile build <old-version>
tile build <new-version>
```



The new tile then supports upgrades from old-version.

Upgrades

By default, Tile Generator produces all code necessary to do a blue/green, zero-downtime deployment of all tile components when installing a newer version over an older one. For most tile versions this is all that is needed.

Ops Manager has support for performing upgrade actions, like database migrations, during a tile upgrade, but this capability is not yet exposed through tile generator.

Example

\$ tile build name: tibco-bwce icon: icon.png label: TIBCO BusinessWorks Container Edition description: BusinessWorks edition that supports deploying to Cloud Foundry version: 0.0.2 bosh init-release --dir=cf bosh generate-package cf_cli bosh generate-package bwce_buildpack bosh generate-job install_bwce_buildpack bosh generate-job remove_bwce_buildpack bosh create-release --final --tarball=cf_incubator --version 0.0.2 tile generate release tile generate metadata tile generate errand install bwce buildpack tile generate errand remove bwce buildpack tile generate content-migrations created tile tibco-bwce-0.0.2.pivotal

This tile includes a single large buildpack and takes less than 15 seconds to build including the CF CLI download and the BOSH release generation.

Supported Commands

tile init [<tile-name>]
tile build [patch|minor|major|<version>]

Credits

- 🔹 sparameswaran 🗷 supplied most of the actual template content, originally built as part of cf-platform-eng/bosh-generic-sb-release 🗷
- frodenas 🗗 contributed most of the Docker content through cloudfoundry-community/docker-boshrelease 🗗
- joshuamckenty ♂ suggested the jinja template approach he employed in opencontrol ♂



pcf Command Line Utility

Page last updated:

The per utility provides a command line interface to Pivotal Cloud Foundry for the purpose of deploying and testing tiles. Its primary reason for existence is to enable Ops Manager access from CI pipelines, but developers also find it convenient to use this CLI rather than the Ops manager GUI.

The per utility also allows you to test your tile's BOSH errands directly from your CLI, without going through Ops Manager and BOSH. This greatly reduces the time it takes to deploy/test each iteration of your software components.

Installation

The pcf utility comes bundled with the Tile Generator tool. To install the pcf utility, follow the Tile Generator installation instructions.

Authentication

The per utility looks for a file called metadata in the current directory. This file is expected to provide the URL and credentials to connect to Ops Manager, in the following format:

opsmgr: url: https://opsmgr.example.com username: admin password: <redacted>

The reason for this file naming is because this is how Concourse passes credentials of a "claimed" PCF pool resource to the CI pipeline scripts. For interactive use, this means that you will have to create a metadata file in the directory where you run the pcf command.



💡 Pivotal recommends that you do 🛚 not create this file inside your git or other version control system repository, as you do not want to accidentally commit these credentials to version control.

Commands

The pcf utility implements many different commands. To see available commands:

```
Usage: pcf [OPTIONS] COMMAND [ARGS]...
Options:
--help Show this message and exit.
Commands
 apply-changes
cf-info
changes
 delete-unused-products
 import
 install
 is-available
 is-installed
logs
 products
 settings
 test-errand
 uninstall
```

Checking Ops Manager Settings

To see which products are currently available and installed in Ops Manager:

```
S pef products
- p-bosh 1.7.0.0 (installed)
- cf 1.7.0-build.258 (installed)
- test-tile 0.3.95
```

To test if a specific product is available or installed from within a script:

```
$ pcf is-available test-tile && echo "Product test-tile is available"
$ pcf is-installed test-tile && echo "Product test-tile is installed"
```

You can retrieve the settings for a specific product (this will give you a *lot* of json):

Deploying Tiles

After your software works and correctly deploys using test-errand, you can go through the real Ops Manager deployment process from the CLI, as you would normally do through the Ops Manager GUI.

Import your .pivotal file into Ops Manager:

```
$ pcf import sample/product/test-tile-0.0.2.pivotal
```

Install the uploaded version of your product:

```
$ pcf install test-tile 0.0.2
```

Where you would normally configure the tile settings in the GUI, the configure command lets you pass in any user-specified properties as a .yml file. This command also sets the stemcell for the tile to the same one used by your Elastic Runtime, to avoid the need to upload a tile-specific stemcell.

```
S pef configure test-tile sample/missing-properties.yml
- Using stemcell bosh-vsphere-esxi-ubuntu-trusty-go_agent version 3215
```

The property file looks like this:

```
customer name: Jimmy's Johnnys
street_address: Cartaway Alley
city: New Jersey
country: US
username: SpongeBob
password: { 'secret': Square'Pants }
app2:
persistence_store_type: none
#In PCF 1.8+, BOSH-job-specific configuration is supported.
jobs:
a job:
  # Job resource configuration
  resource config:
   persistent_disk:
    size_mb: "10240"
  \# \textit{Job-specific property configuration}
  job_property: property_value
```

You must define any secret type property value as a hash, in curly brackets. Specifying a simple string value for a field of this type results in a 500 System being returned from pcf configure. The secret type property values can contain special characters.

To see what changes are ready to be applied:

```
$ pcf changes
install: test-tile-207b165fcb7dc8b2597b
delete:
```

To apply these changes:

```
$ pcf apply-changes

==== 2016-04-21 18:45:05 UTC Running "bosh-init deploy /var/tempest/workspaces/default/deployments/bosh.yml"

Deployment manifest: '/var/tempest/workspaces/default/deployments/bosh.yml'

Deployment state: '/var/tempest/workspaces/default/deployments/bosh-state.json'

Started validating

Validating release 'bosh'... Finished (00:00:08)

Validating release 'bosh-vsphere-cpi'... Finished (00:00:00)

Validating release 'uaa'... Finished (00:00:00)

Validating cpi release... Finished (00:00:00)

Validating deployment manifest... Finished (00:00:00)
```

pcf apply-changes automatically tails the logs for the installation process it started. If this gets aborted for any reason, you can always tail the logs of the most recent installation:

\$ pcf logs

Removing Tiles

To uninstall a tile:

\$ pcf uninstall test-tile

If you accumulate a lot of uninstalled tiles or old versions, you can clean up Ops Manager's available products (and disk space):

\$ pcf delete-unused-products

Accessing Elastic Runtime

To see details about the Elastic Runtime of your PCF environment:

\$ pcf cf-info - admin_password: <redacted> - admin_username: admin - apps_domain: cfapps-04.example.com - system_domain: run-04.example.com - system_services_password: <redacted> - system_services_username: system_services

To target your cf command line at this PCF environment:

```
Spcf target
Setting api endpoint to api.example.com...
OK

API endpoint: https://api.example.com (API version: 2.52.0)
User: admin
Org: my-org
Space: my-space
API endpoint: https://api.example.com
Authenticating...
OK
...
```



Concourse

Page last updated:

This topic explains how to use Concourse of continuous integration (CI) to help develop and integrate apps for Pivotal Cloud Foundry (PCF).

Overview

PCF is a fast moving platform as we are constantly extending and enhancing it. When you integrate your software with PCF, you should make sure that your integration continues to work with every new release of the platform. One way to ensure that is to set up a CI pipeline for your tile against a PCF deployment that is constantly updated with the latest Alpha release of the platform.

Our tool of choice for setting up CI is concourse . While you are of course free to use whatever system you are familiar with, our tools and documentation are built to make concourse CI as easy as possible.

Set Up a Concourse Server

You will need a concourse server to host your pipeline. If you partner with us, we have servers that can host your pipeline, and S3 storage that can be used to transfer artifacts to and from your servers. If you choose to set up your own, instructions can be found here:

Setting up concourse ♂

Create a Concourse Pipeline for Your Tile

A typical CI pipeline for a tile consists of the following jobs:

- Build the tile
- Deploy it to PCF
- Run a set of deployment tests to verify that it deployed and works correctly
- Remove it from PCF

You describe this pipeline in a pipeline.yml file that is then uploaded to the concourse server. Tile Generator contains a sample pipeline that you can clone for your own tile. We are working on automating the process of generating a pipeline template for you.

Set Up PCF for Your CI Pipeline

Pivotal partners who have us host their pipeline have access to a pool of PCF instances that are managed by us and are regularly updated with the latest (pre-)release versions of PCF. If you set up your own concourse server, you will have to target your pipeline at a PCF instance you have setup.

Concourse has a resource type to manage a pool of resources that are shared between pipelines, which is what we use to serialize PCF access between the partner pipelines that run on our concourse server.



Pivotal Cloud Foundry Services SDK

Page last updated:

Dynamic Provisioning, Metrics, and Backups

The Pivotal Cloud Foundry (PCF) Services SDK is designed to help you build enterprise-ready service offerings for the Marketplace. The SDK includes the following components:

- The On Demand Service Broker 🗗 enables dynamic provisioning of your service using BOSH 2.0.
- Service Metrics for PCF C* integrates your service into the PCF Logging and Metrics system, empowering platform operators to gain immediate insight into system health based on live service metrics.
- Service Backups for PCF or runs regular backups for your service, triggering and uploading backup artifacts to a range of destinations, including S3 and Azure.

Active Pivotal partners and customers can use the PCF Services SDK by agreeing to the Pivotal SDK EULA when downloading the products on https://network.pivotal.io/ 🗗.



Publish and Update

Page last updated:


This topic provides resources to help you publish and update your service tile for Pivotal Cloud Foundry (PCF).

Publish Your Tile

The Pivotal Partner Software Product Release Cycle explains how Pivotal works with partners to release PCF products, from the private alpha and closed beta phases, to general availability and publication on Pivotal Network ...

After you've packaged your product's BOSH releases, stemcell, metadata, and other tile components into a single zipped download file, post it to Pivotal Network in one of two ways:

- Use the Pivotal Network API command 🗷 POST /api/v2/products/:product_slug/product_files .
- Use the Pivotal Network product upload form.



Update Your Tile

Most tile updates originate with the tile developer, but new releases of PCF can also necessitate tile changes to maintain compatibility with the current version of the platform.

- Tile Generator automates tile versioning and upgrades.
 For more information, see Versioning in the Tile Generator documentation.
- Tile Upgrades explains how to write and include a JavaScript file that automates tile upgrades by migrating property names and values from one tile version to another.
- When changes to PCF require tile changes, Pivotal distributes instructions to all of its partners:
 - ∘ Pivotal Cloud Foundry v2.2 Partners Release Notice ♂
 - ∘ Pivotal Cloud Foundry v2.1 Partners Release Notice ♂
 - Pivotal Cloud Foundry v2.0 Partners Release Notice

 ✓
 - ∘ Pivotal Cloud Foundry v1.12 Partners Release Notice ☑



Tile Documentation

Page last updated:

This topic explains how to document your service tile for Pivotal Cloud Foundry (PCF).

Overview

When a PCF service tile launches on Pivotal Network , Pivotal publishes corresponding documentation at https://docs.pivotal.io under Partner Services for Pivotal Cloud Foundry.

This documentation is formatted in Markdown C, stored in a GitHub repository that Pivotal creates, and is published with the bookbinder C platform.

Partner Documentation Template

The PCF Partner Documentation Template \mathcal{C} is a GitHub repository that you can clone to create documentation for your service tile that follows Pivotal's format and works with its documentation publishing platform, bookbinder \mathcal{C} .

Documentation content resides in the \(\frac{1}{\text{docs-content}}\) folder of the repository, as skeleton pages with embedded prompts for content that you should fill in, approximately following the \(\content\) descriptions below.

See the repository README.md of for how to use the template with bookbinder to develop your documentation.

Documentation Content

While the specifics of your documentation will vary depending on the product, we have provided a basic blueprint below. At minimum, documentation should include #1 (Overview) and #2 (Installing/Configuring).

For a good example of a partner service document, see the JFrog Artifactory documentation ...

If you have questions or want to collaborate on drafting the documentation, feel free to hop on our Slack channel #pcf-docs. We're always happy to help!

Index/Landing Page

General overview of Partner Product. What does it do? What are its features?

Key Features

- Feature one
- Feature two
- Feature three

Partner Service Broker

A Service Broker allows Cloud Foundry applications to bind to services and consume the services easily from App Manager UI or command line. The Partner Service Broker will enable you to use one or more Partner accounts and is deployed as a Java Application on Cloud Foundry. The Broker exposes the Partner service on the Cloud Foundry Marketplace and allows users to directly create a service instance and bind it to their applications either from the Pivotal Apps Manager Console or from the command line.

The Pivotal Cloud Foundry (PCF) Tile for Partner installs the Partner Service Broker as an application and registers it as a Service Broker on Cloud Foundry and exposes its service plans on the Marketplace. This makes the installation and subsequent use of Partner on your Cloud Foundry applications simple and easy.

If a trial license available, customers interested in using Partner can obtain a 60 day free trial license from edit link here.



Product Snapshot

Current Partner Tile for Pivotal Cloud Foundry Details:

- Version:
- · Release Date:
- Software components versions: Partner product version
- Compatible Ops Manager Version(s): 1.5.x, 1.6.x
- Compatible Elastic Runtime Version(s): 1.4.x, 1.5.x, 1.6.x

Requirements

(or Prerequisites, Packaging Dependencies for Offline Buildpacks, etc.)

Provide any general or specific requirements here. A general requirement might be something like, "An AppDynamics account." A specific requirement might be something like, "Packaging Dependencies for Offline Buildpacks."

Limitations

Any known limitations.

Please provide any bugs, feature requests, or questions to the Pivotal Cloud Foundry Feedback list.

Installing / Configuring the Tile

This topic provides instructions for how to install and configure the tile. Typically this includes procedures for how to download the tile from Pivotal Network, install it on Ops Manager, configure the tile, and do any required third-party configuration. Screenshots should be provided where necessary. Consult the following format:

Install Using the Pivotal Ops Manager

- Download the product file from Pivotal Network.
- Upload the product file to your Ops Manager installation.
- Click Add next to the uploaded product description in the Ops Manager Available Products view to add this product to your staging area.
- Click the newly added tile to review any configurable options.
- Click Apply Changes to install the service.

Upgrading to the Latest Version

If there are any specific instructions for upgrading the tile, you can include those here. If the procedures are complicated, create a new Upgrading topic.

Configuring the Partner Tile

(add snapshots for each step when possible or add details as required)

- Login into Pivotal Ops Manager
- Click Import a Product and import the Partner Tile
- Select the Partner option
- Click Add on the Partner Tile
- Select the Partner Tile
- Configure the Partner Tile
- Apply your changes.

On completion of Partner Tile install, check Services Marketplace in Apps Manager



- View Partner Service Plans
- Bind the Partner Service to an Application
- Check the service or dashboard for the partner for more data...

Other Configurations / Third-Party Configurations

Provide information for specific configurations like configuring for HTTP proxy, or doing any necessary configurations on a third-party service portal.

Using the Tile

This topic provides instructions for how to use the tile. Typically this includes procedures for how to perform the different functions offered by the service. Screenshots should be provided where necessary. You can also include information about Architecture here if necessary.

Troubleshooting

This topic provides troubleshooting information for known errors, following the Symptom/Explanation format used here: https://docs.pivotal.io/p-identity/okta/troubleshooting.html

Release Notes

Include the release notes as the final topic, following the format in the docs-partners-template .



Partner Software Product Release Cycle

Page last updated:

This topic describes the four phases of product release to Pivotal Cloud Foundry (PCF).

Phase 1: Alpha

A product begins development in the Alpha phase. The product undergoes constant churn and refactoring, and may not be feature-complete.

Customers do not have exposure to a product during Alpha, and there are no quality requirements in this phase. Instead, developers use this stage for internal testing.

Phase 2: Closed Beta

During Closed Beta, a limited pool of users gains access and provides feedback to a product. This feedback drives further development. A status of Closed (Private) Beta informs users that the product may be unstable and should not be used in production.

A product should remain in Closed Beta while:

- Changes may break product function or cause loss of data.
- Users may experience major bugs.
- Users may need to delete and reinstall tiles rather than upgrading them.

Developers make products in Closed Beta available to specific groups or individual customers on Pivotal Network 🗷.

Requirements

To enter Closed Beta, a product must meet the following requirements:

- The product must run properly on at least one laaS, so that customers can install and try it out. Supported infrastructures are AWS, vSphere and OpenStack.
- Customers must be able to install the product error-free through a tile in Pivotal Ops Manager, and delete the product there without any traces remaining.
- The product tile must target the latest released stemcell version, as listed on Pivotal Network .
- The release notes must make clear the following constraints:
 - Potential data loss and lack of support make the beta version of the product unsuitable for use in production.
 - Users will need to delete the old tile and install a new one in order to move to the next version of the product. No upgrade path exists.
- The product must fulfill its promised feature set, and perform as desired.

Pivotal also recommends that any Closed Beta product include an easy way for users to provide feedback to the product developer.

Steps to Release

The following steps create a new Closed Beta release for your product:

- 1. Log into Pivotal Network .
- 2. Create a new release for your product and populate all of the required fields.
- 3. Check that the release version states BETA.
- 4. Clearly state in the release description that the product cannot be upgraded, and that users may suffer data loss.
- 5. Email your Pivotal contact to request product validation and Closed Beta release. Please provide basic instructions on how to validate the new feature set. Pivotal will verify that the release meets all requirements, then make it accessible to invited customers.

Phase 3: Public Beta

Your product will be made available to the general public in **Public Beta**. The wider pool of users increases public awareness and feedback and facilitates marketing and advertising. As development continues, you may publish a series of product versions in Public (Open) Beta.

Your product is a good candidate for the **Public Beta** stage if:

- You have high confidence that further development will not break the product or incur data loss for users.
- The tile can be upgraded.
- You still want user feedback to discover minor bugs and evaluate existing features.
- The product does not contain the full set of features intended for the final release.
- You feel comfortable supporting this tile for customers.

Requirements

Products in Public Beta must meet the following requirements:

- The product meets all requirements for Closed Beta.
- The tile can be upgraded to subsequent versions without requiring the customer to uninstall the previous version.
- The product supports upgrade paths from any minor version or patch to the next minor version and any patches.
- Tile version upgrades result in no data or configuration loss, and maintain service functionality and availability.
- Where appropriate, PCF integrations work properly, including:
 - Registered routes
 - o UAA
 - Service brokers
- You can respond to discovery of a security flaw on the Common Vulnerabilities and Exposures (CVE) list 🗷 within a reasonable time frame. Security flaws include vulnerabilities in your stemcell or within one of the components of your tile.



Note: Pivotal attempts to respond to all critical CVEs within 48 hours.

Steps to Release

- 1. Log into Pivotal Network ♂.
- 2. Create a new release for your product and populate all of the required fields.
- 3. Check that the release version states BETA.
- 4. Email your Pivotal contact to request product validation and Public Beta release. Please provide basic instructions on how to validate the new feature set. Pivotal will also validate the upgrade scenario and data persistence. After verifying that the release meets all requirements, Pivotal will make it visible to customers.

Phase 4: General Availability

A product qualifies for General Availability when:

- It is production-ready.
- You can charge money for this product and provide support guarantees to your customers.
- The product's full set of features meets the standards of quality that you wish to uphold.

Requirements

Products must meet the following requirements for General Availability:

- The product meets all requirements for Public Beta.
- You consider the product production-ready, and you have adequate unit and functional tests to ensure high quality.
- You can provide customer support.
- Your business team can "Go to market."
- The product can scale vertically, by increasing the amount of RAM or CPU. Vertical scaling improves performance and does not result in data loss.
- If appropriate, the product can scale horizontally for high availability.
 - Scaled-out nodes (application VMs) function correctly.
 - Removing a node does not result in downtime.
- If appropriate, the product supports zero downtime deployment.
- Product installation does not require an internet connection, after initial product download.

Steps to Release

- 1. Log into Pivotal Network .
- 2. Create a new release for your product and populate all of the required fields.
- 3. Email your Pivotal contact to request product validation and General Availability release. Please provide basic instructions on how to validate the new feature set. Pivotal will also validate the upgrade scenario and data persistence.



Upgrading Tiles

Page last updated:

This topic discusses product tile migrations, which refers to changing the name and values of properties when a customer upgrades tile versions. Tile authors supply a JavaScript file to trigger chaining migrations. Chaining migrations allows for multiple migrations to run sequentially.



Note: In order to use JS migrations, ensure you are using Ops Manager 1.7 or later.



Note: Changing the value of single_az_only for jobs launched by your tile can cause data loss for customers who upgrade to Ops Manager v1.7 versions older than v1.7.20, or v1.8 versions older than v1.8.12. Contact Pivotal Support ' for help avoiding this.

Update Values or Property Names Using JavaScript

To update a product tile, tile authors must complete the following steps:

- 1. In a single is file, write JavaScript functions which return a hash of the tile's properties.
- 2. Name the file in the format TIMESTAMP_NAME.js . TIMESTAMP must be in the form "YYYYMMDDHHMM" to indicate when the author created the migration. NAME is a human-readable name for the migration, for example, 201606150900_example-product.js .
- 3. Copy the TIMESTAMP_NAME.js file to the PRODUCT/migrations/v1 directory.

Example JavaScript Migration File

The functions below display an example migration file:

```
exports.migrate = function(input) {
  // Append text to a string
  input.properties['.web server.example string']['value'] += '!';
  // Delete property 'legacy property' that's removed in new tile version
  delete input.properties['.properties.legacy_property'];
  // Rename property 'example_port' to 'example_port_renamed',
  // retaining the previous value
  input.properties['.properties.example_port_renamed'] =
    input.properties ['.properties.example\_port'];
  delete input.properties['.properties.example_port'];
  // Append text to a string list
  input.properties['.properties.example string list']['value'].push(
    'new-string-append-by-migration');
  return input;
```

The properties object passed to your anonymous JavaScript migration functions are composed of properties at the job-level and product-level. Review the property names in the example metadata file in Tutorial Tile V3 & for more information about job-level and product-level properties. The tile author must update migrations to match the corresponding product metadata file.

Each property's key in the properties object is its property reference from the metadata file. Property references use one of the following forms:

- .properties.{property_name} for product-level properties
- .{job_name}.{property_name} for job-level properties
- .properties.{property_name}.options.{option_name} or .{job_name}.{property_name}.options.{option_name} for selector option

The object accessed through the property reference contains a value key whose structure is specific to the type of the property. Objects may be a string, an array, or a hash. Review the reference below for the structure of each type of property.



JavaScript Migrations API

Inside a JavaScript migration function, the system provides the following functions for your code:

```
console.log(string)
Arguments: string
Return value: none
Description: Prints the string to the Rails log
Example:
console.log("Hello World");
getCurrentProductVersion()
Arguments: none
Return value: string (example: 1.7.1.0)
Description: Returns the version of the product that is currently installed
Example:
console.log(getCurrentProductVersion());\\
generateGuid()
Arguments: none
Return value: string (example: 115f9ced-3167-4c7c-959b-d52c07f32cbf)
Description: Returns a globally unique identifier (GUID) that can be used as the unique identifier for each element of a Collections property. When updating a Collection property blueprint, you as the migration a
Notes: This function can be called a maximum of 100 times per '.js' file. If you need more than 100 GUIDs, break your migration into two '.js' files.
Example:
console.log("Here's a GUID: "+generateGuid())
abortMigration(string)
Arguments: string containing error message
Return value: none (never returns)
Description: Causes the migration to fail immediately. Rolls back all migrations in the current chain, i.e, no changes will be committed.
Example:
  abortMigration("Can't upgrade tile when the value of something is more than 5")
```

Property Type	Value Structure	Example
single-value properties	Single value, but type-specific	<pre>properties['.properties.my-prop'].value = 'my-string'; properties['.properties.other- prop'].value = true</pre>
dropdown	Array of options	<pre>properties['.properties.my-prop'].value = ['option1', 'option2']</pre>
rsa_cert_cre dentials	Object	<pre>properties['.properties.my-prop'].value = {'private_key_pem' => 'a-private-key', 'cert_pem' => 'a-cert-pem'}</pre>
rsa_pkey_cre dentials	Object	<pre>properties['.properties.my-prop'].value = {'private_key_pem' => 'a-private-key'}</pre>
salted_crede ntials	Object	<pre>properties['.properties.my-prop'].value = {'identity' => 'an-identity', 'salt' => 'mortons',</pre>
simple_crede ntials	Object	<pre>properties['.properties.my-prop'].value = {'identity' => 'an-identity', 'password' => 'secret'}</pre>
collections	Array of objects	<pre>properties['.properties.my-prop'].value = [{name: {value: 'foo'}, record_id: {value: 1}},</pre>
selectors Selected value	String	<pre>properties['.properties.my-prop'].value = 'selected option label'</pre>
selectors {selector option name.property name}	Value object specific to property type	<pre>properties['.properties.selector.option1.prop1'].value = 'foo' properties['.properties.selector.option1.prop2'].value = 2 properties['.properties.selector.option2.prop3'].value = ['bar', 'baz']</pre>

Single value properties refer to properties whose type are any of the following: boolean, ca_certificate, domain, dropdown_select, email, http_url, integer, ip_address, ip_ranges, ldap_url, multi_select_options, network_address, network_address_list, port, smtp_authentication, string, string_list, text, uuid.


Refer to the example properties below when writing your own tile migration JS file:

```
properties: {
  '.properties.example_boolean': { value: false } ,
  '.properties.example ca certificate': { value: 'simple-typed-value'},
  '.properties.example_domain': { value: 'simple-typed-value'}
  '.properties.example_dropdown_select': { value: 'simple-typed-value'},
  '.properties.example_email': { value: 'simple-typed-value'},
  '.properties.example_http_url': { value: 'simple-typed-value'},
  '.properties.example_integer': { value: 111},
  '.properties.example_ip_address': { value: 'simple-typed-value'},
'.properties.example_ip_ranges': { value: 'simple-typed-value'},
  '.properties.example_ldap_url': { value: 'simple-typed-value'},
  '.properties.example_multi_select_options': { value: ['simple-typed-value']},
  '.properties.example_network_address': { value: 'simple-typed-value'},
  '.properties.example_network_address_list': { value: 'simple-typed-value'},
  '.properties.example_port': { value: 22},
  '.properties.example_smtp_authentication': { value: 'simple-typed-value'},
  '.properties.example string': { value: 'simple-typed-value'},
  '.properties.example_string_list': { value: 'simple-typed-value'},
  '.properties.example_text': { value: 'simple-typed-value'},
  '.properties.example_uuid': { value: 'simple-typed-value'},
  '.properties.example_rsa_cert_credentials': {
   value: {'private_key_pem': 'a-private-key', 'cert_pem':'a-cert-pem'},
  '.properties.example_rsa_pkey_credentials': {
    value: {'private_key_pem':'a-private-key'},
  '.properties.example_salted_credentials': {
   value: {'identity':'an-identity', 'salt':'mortons', 'password':'books'},
  '.properties.example simple credentials': {
   value: {'identity':'an-identity', 'password':'secret'},
  '.properties.example_collection': [
    {name: {value: 'foo'}, record_id: {value: 1}},
    {name: {value: 'bar'}, record_id: {value: 2}}
  '.properties.example_selector': {value: 'option1'},
  '.properties.selector.option1.prop1': {value: 'foo'},
  '.properties.selector.option1.prop2': {value: 2},
  '.properties.selector.option2.prop3': {value: 'bar,baz'}
```

🗣 Note: If your product uses Ops Manager 1.6 or earlier metadata, you need to write a transmogrifier content migration for customers using your product on 1.6, and a JavaScript migration for those on Ops Manager 1.7 or later. Review the transmogrifier example in the Tile Tutorial V1 🗷.

Examples Demonstrating Chaining Migrations

Migration chaining allows for multiple migrations to run sequentially when an upgrade is performed that skips an intermediate version. For example, suppose you have three versions of your product: 1.6.0, 1.7.0, and 1.7.1. The 1.6.0 product contains 1.6 metadata, so it does not contain any JavaScript migrations.



The following customer upgrade scenarios illustrate chaining migrations in more detail, and use the example product versions described above.


Scenario A: Upgrading from 1.6.0 -> 1.7.0 -> 1.7.1

In this scenario, the customer starts with the 1.6.0 product installed. After upgrading to Ops Manager 1.7 or higher, they decide to upgrade the product to 1.7.0. This causes the migration 201606010000_a.js to run. Several weeks later, the customer decides to upgrade from 1.7.0 to 1.7.1. Now the 201607010000_b.js migration runs. Even though the 1.7.1 product includes both migrations, Ops Manager does not re-run 201606010000_a.js because it maintains a record of migrations.




Scenario B: Upgrading Directly from 1.6.0 -> 1.7.1

In this scenario, the customer also starts with 1.6.0 installed, but they decide to upgrade directly to 1.7.1, skipping the 1.7.0 version. Both migrations run in lexicographical order.



Scenario C: Installing 1.7.0, Then Upgrading to 1.7.1

In this scenario, the customer starts with nothing installed. They perform a clean install of version 1.7.0 of the product. On install of 1.7.0, no migrations run because migrations only run on upgrades. Later, the customer decides to upgrade to 1.7.1 of the product. Because 1.7.1 contains both migrations, and because no migrations have run on this system, only the second migration 201607010000_b.js runs. The system recorded the fact that 1.7.0 includes 201606010000_a.js , so that migration does not run.



Scenario D: Installing 1.7.1

In this scenario, the customer performs a clean install of 1.7.1, with no previous versions of the product installed. Since migrations are only triggered by upgrade events, no migrations run.



💡 Note: Do not omit a migration from a later version of your tile. This breaks the "chaining" nature of migrations. Using the example above, if you

 $\label{eq:control_co$

References

Page last updated:

This topic collects API, configuration property, and other references for building Pivotal Cloud Foundry (PCF) tiles.

Troubleshooting

Sooner or later you will run into problems that require digging a little bit deeper. Here are some great resources on how to best troubleshoot more complex issues:

- Troubleshooting PCF ☑
- Troubleshooting Applications 🗷
- Advanced Troubleshooting with BOSH ☑

API

- Service Broker API v2.10 🗷 lists the requests, responses, and status codes required for a service broker.
- Catalog Metadata 🗗 lists the metadata fields that a service broker must publish to create listings in the Services Marketplace.
- Subcommands If from the On-Demand Services SDK documentation lists the subcommands that ODB service adapter must respond to.

Configuration Properties

- Product Template Reference catalogs how top-level properties, form properties, property blueprints, configurable properties, and job types are defined in tile installer _yml files, such as those generated by the Tile Installer or hand-coded legacy tiles.
- Property Blueprint Reference compiles another list of accessors and values for configuration properties in the property_blueprints section of a tile installer .yml file.
- Referencing Properties explains how to specify the locations of tile configuration properties in a tile installer .yml file.

Command Line Tools

- $\bullet \quad \underline{\text{Cloud Foundry CLI Reference Guide $ \underline{C} } \text{ catalogs the cf CLI.} } \\$
- pcf Command Line Utility catalogs the pcf utility, which you can use to bypass Ops Manager.
- The Fly CLI 🗗 catalogs the fly command-line interface to Concourse.

Partners Release Notices

- Pivotal Cloud Foundry v2.2 Partners Release Notice ☑
- Pivotal Cloud Foundry v2.1 Partners Release Notice ♂
- Pivotal Cloud Foundry v2.0 Partners Release Notice 🗷
- Pivotal Cloud Foundry v1.12 Partners Release Notice ☑



Development Workflow Reference

Page last updated:

This document references topics that follow Pivotal's recommended tile development workflow.

Development Workflow

The following topics can help you learn the necessary background information to publish and maintain a finished tile product:

- PCF Tile Developer Guide ♂
- Tile Basics describes how PCF, service brokers, and tiles work together, and how tiles are structured.
- Types of Intergrations gives a high-level view of a staged tile development process that iterates through increasing levels of integration:
 - User-Provided Service
 - Brokered Service
 - Managed Service
 - On-Demand Service
- Development Environments describes how to set up development environments for different stages and levels in the tile development process.
- Development Tools describes three tools that streamline the tile development process: <u>Tile Generator</u>, the <u>pcf Command Line</u> utility, and <u>Concourse</u> continuous integration (CI).
- Types of Integrations takes you through the staged tile development process, explaining the components and steps required for each level of service integration: user-provided, brokered, managed, and on-demand.
- Tile Documentation explains how to document your tile as part of PCF documentation ...
- Publish and Update explains how to publish your tile on Pivotal Network (PivNet) and package upgrade information into your new versions.
- Reference provides language references for tile elements such as the Service Broker API and the Properties list for tile configuration.
- Contact Us lists contacts to learn more about the Pivotal ISV Partner Program or request our assistance with your integration project, and explains where you can contribute to this documentation.



Product Template Reference

Page last updated:

This document defines the separate pieces of a product template. For the purpose of explanation we use the PCF example tile , a functional tile provided by the Ops Manager engineering team that deploys the NGINX web server.

The product template, a .yml file in the tile's metadata subdirectory, includes or points to the following:

- Metadata: high level information about your tile
- Dependencies: how to specify product dependencies
- Property Blueprints: the building blocks of representing values
- Form Types: exposing property blueprints into generated forms
- Jobs

Top Level Properties

The following is an example of the properties that appear at the top of a product template. Following this example are definitions of each property.

```
name: example-product
product_version: <%= version.inspect %>
minimum_version_for_upgrade: "1.7.0'
metadata_version: "1.11"
label: 'Ops Manager: Example Product'
description: An example product to demonstrate Ops Manager product-author features
service_broker: false # Default value
stemcell criteria:
  os: ubuntu-trustv
  version: <%= stemcell_version.inspect %>
  enable patch security updates: true
releases:
  - name: example-release
    file: <%= release_file_name.inspect %>
    version: <%= release_file_name.match(/^example-release-(.*)\.tgz$/)[1].inspect %>
variables:
   name: credhub-password
    type: password
post deploy errands:
  - name: example-errand
pre delete errands:
  - name: example-errand
```

name

String. Required. The internal name of the product. You must keep the name of your product consistent for migrations to function properly. Changing the name indicates the installation of a completely different product.

product_version

String. Required. The version of the product. At present you can only import this version into Ops Manager once. If you intend to import the same product / version, you must delete the existing one from the /metadata folder and delete the installation files from Ops Manager's disk. The version number is important for migrations.

minimum_version_for_upgrade

String. Required. You must set a minimum version for upgrading to your current product version. This example shows a current product version of v1.7

that only upgrades from a v1.6.x version of the same product:

```
- product_version: 1.7.0.0
minimum_version_for_upgrade: 1.6.0.0
```

metadata_version

String. Required. The versioned structure of the product template (the file you are editing). Changing the version number can unlock new properties, and also break properties that changed from previous versions. The metadata version does not always correlate to Ops Manager version number and depends on what, or if, new metadata properties were introduced.

label

String. Optional. The label that appears in the product tile when it displays in the Ops Manager Dashboard.

description

String. Optional. A description of the product. This is not currently used but may be displayed in a future version of Ops Manager.

rank

Integer. Required. The order in which a product tile appears on the dashboard. The Ops Manager Director always appears at rank 100. For your product to appear to the right of Ops Manager Director (preferable), you must set this value to an integer less than 100. Pivotal recommends that you set it to 1. Ops Manager sorts tiles alphabetically if all tiles have the same rank. This is a known weak point.

stemcell_criteria

Hash. Required. For a list of stemcells, including OS and version, see the BOSH hub . You do not specify which IaaS the Stemcell targets. This keeps your product template IaaS agnostic so that one product template can be deployed on any IaaS. At the time of this writing, none of the BOSH stemcells require a Cloud Provider Interface (CPI). This is expected to change in a future release of BOSH.

enable_patch_security_updates allows you to automatically use the latest patched version of a stemcell. This is by default set to true. For products using static compilations, you can disable this feature. If you set the property to false, your product does not receive security patches through automatic stemcell updates.

```
stemcell_criteria
os: ubuntu-trusty
version: <%= stemcell_version.inspect %>
enable_patch_security_updates: true
```

releases

Array of Hashes. Required. The list of releases contained in your product's releases directory. The version of the release must be exactly the same as the version contained in the release (BOSH releases are versioned and signed by BOSH).

Each release requires the following keys:

- name
- file
- version

variables

Array of Hashes. Optional. A list of variables, that are generated after a deploy succeeds. You can reference variables in a manifest snippet using triple-parentheses expressions.

Each variable requires a name and a type.

post_deploy_errands

Array of Hashes. Optional. A list of errands that run after a deploy succeeds.

Set the run_post_deploy_errand_default: property to on or off to set the default for the errand's run rule selector in Ops Manager. See Lifecycle Errands. If this property is not supplied, the selector defaults to On .

pre_delete_errands

Array of Hashes. Optional. A list of errands that run before a deployment is deleted.

Set the run_pre_delete_errand_default: property to on or off to set the default for the errand's run rule selector in Ops Manager. See Lifecycle Errands. If this property is not supplied, the selector defaults to On.

icon_image

Base64 Image. Required. This is the icon that displays on the tile in the Ops Manager Installation Dashboard.

Form Properties

The following is an example of the properties that appear in the form_types section of a product template. These forms appear on the left hand side, as links, after a user clicks on the tile itself.

As shown in a later section, form properties reference property_blueprints for the definition of the type of data (URL, IP address, list, etc.) being saved. Form properties are themselves referenced in the manifest section of the job_types section, which will also be explained later in this document. The eventual purpose of these properties is to hydrate a BOSH manifest, which Ops Manager generates on the user's behalf.

Following this example are definitions of each property.

```
form types
 - name: example-form
  label: Configurable Properties
  description: All the properties that you can configure!
  markdown:
   ## I am markdown, hear me _roar_
   ![Alt text](http://placekitten.com/g/400/200)
   Things to do:
   1. Learn [markdown](https://daringfireball.net/projects/markdown/).
   1. Profit!
  property_inputs:
    - reference: .web server.example string
    label: Example string
    description: 'Configure a property of type string'
    - reference: .web_server.example_string_with_placeholder
    label: Example string containing Placeholder text
     description: 'Optional field. Configuration not necessary'
    placeholder: 'Ghost text. Spooky!'
    - reference: .web_server.example_migrated_integer
    label: Example integer
    description: 'Configure a property of type integer'
   - reference: .web server.example boolean
    label: Example boolean
    description: 'Configure a property of type boolean'
   - reference: .web_server.example_dropdown
    label: Example dropdown
    description: 'Configure a property of type dropdown'
    - reference: .web_server.example_domain
    label: Example domain
    description: 'Configure a property of type domain'
    - reference: .web_server.example_wildcard_domain
     label: Example wildcard_domain
    description: 'Configure a property of type wildcard_domain'
    - reference: .web server.example string list
    label: Example string list
    description: 'Configure a property of type string_list'
   - reference: .web server.example text
    label: Example text
    description: 'Configure a property of type text (setting to "magic value" causes the web server job instance count to go to 0)'
   - reference: .web_server.example_ldap_url
    label: Example ldap_url
    description: 'Configure a property of type ldap_url'
    - reference: .web_server.example_email
     label: Example email
    description: 'Configure a property of type email'
   - reference: .web server.example http url
    label: Example http url
    description: 'Configure a property of type http_url'
   - reference: .web\_server.example\_ip\_address
    label: Example ip address
    description: 'Configure a property of type ip_address'
   - reference: .web_server.example_ip_range
    label: Example ip_ranges
    description: 'Configure a property of type ip_ranges'
    - reference: .web_server.example_multi_select_options
     label: Example multi_select_options
    description: 'Configure a property of type multi_select_options'
    - reference: .web_server.example_network_address_list
    label: Example network address list
    description: 'Configure a property of type network address_list (this property was marked with freeze_on_deploy, and so will not be editable after changes are first applied)'
   - reference: .web server.example network address
    label: Example network address
    description: 'Configure a property of type network_address'
   - reference: .web_server.example_port
    label: Example port
     description: 'Configure a property of type port'
    - reference: .web_server.example_smtp_authentication
    label: Example smtp_authentication
    description: 'Configure a property of type smtp_authentication'
    - reference: .web_server.client_certificate
    label: Example certificate
    description: 'Configure a certificate'
```

name



String. Required. The internal name of the form.

label

String. Required. The label of the form as it appears as a link on the left hand side of each form.

description

String. Optional. The description of the form. Appears at the top of the form as a header.

markdown

Markdown. Optional. Provide a block of markdown to display at the top of the form. Includes image support. You can use this property to document the tile and provide explanations or references.

property_inputs

Array of Hashes. Required. References to properties defined in the property_blueprints section of the product template.

placeholder

String. Optional. Specify placeholder text for a field. The text appears in light gray to show an example value for the user. The text disappears when the user types in the field and reappears if the user leaves the field empty.

The placeholder attribute displays for the following form types:


- string
- integer
- domain
- wildcard_domain
- string_list
- text
- ldap_url
- email
- http_url
- ip_address
- ip_ranges
- network_address_list
- network_address
- port

Simple vs. Complex Inputs (Selectors and Collections)


 $Most\ properties\ are\ simple\ values\ such\ as\ strings, integers,\ URL\ addresses,\ or\ IP\ addresses.\ Others\ are\ complex,\ such\ as\ selectors\ or\ collections.$

Selectors are a means of giving the user a choice of a set of inputs. Collections are a means of giving the user the ability to enter an array of values to create a hash.

Selectors appear as follows:



Collections appear as follows:



Property Blueprints

The following is an example of the property_blueprints that appear in a product template. These blueprints define anything that will eventually end up in the BOSH manifest generated by Ops Manager.

Note that one of these blueprints references a migrated value, which came from the Example Product v1.6 using $\frac{\text{migrations}}{\text{migrations}}$.

```
property_blueprints:
 - name: example_selector
 type: selector
  configurable: true
  default: Pizza
  freeze_on_deploy: true
  option_templates:
   - name: pizza_option
    select_value: Pizza
    named_manifests:
     - name: my_snippet
       manifest: |
       pizza toppings:
         pepperoni: ((\ .properties.example\_selector.pizza\_option.pepperoni.value\ ))
          pineapple: ((\ .properties.example\_selector.pizza\_option.pineapple.value\ ))
         other: ((\ .properties.example\_selector.pizza\_option.other\_toppings.value\ ))
     - name: provides_section
       manifest:
        as: 'pizza_link_web_server_job'
      - name: consumes_section
       manifest: |
        from: 'pizza_link_web_server_job'
    property_blueprints:
      - name: pepperoni
      type: boolean
       configurable: true
       freeze_on_deploy: true
      - name: pineapple
      type: boolean
       configurable: true
       default: true
      - name: other_toppings
       type: string
       configurable: true
       optional: true
       constraints:
       - must_match_regex: '\A[^!@#$%^&*()]*\z'
        error message: 'This name cannot contain special characters.'
   - name: filet mignon option
    select value: Filet Mignon
    named manifests
     - name: my_snippet
       manifest:
        rarity: ((\ .properties.example\_selector.filet\_mignon\_option.rarity\_dropdown.value\ ))
        review: ((\ .properties.example\_selector.filet\_mignon\_option.review.value\ ))
        secret\_sauce: ((\ .properties.example\_selector.filet\_mignon\_option.secret\_sauce.value\ ))
      - name: provides_section
      manifest:
        as: 'filet mignon link web server job'
     - name: consumes section
      manifest:
       from: 'filet_mignon_link_web_server_job'
    property_blueprints:
      - name: rarity_dropdown
      type: dropdown_select
       configurable: true
       default: rare
       options:
        - name: rare
         label: 'Rare'
        - name: medium
        - name: well-done
         label: 'Well done
```

configurable

No property will be viewable in a form if unless configurable is set to true. Rather than giving the user the ability to enter a value, the value is generated by Ops Manager.


must_match_regex

Regular Expression. Optional. Create a validator that runs on the form save event. If the user input does not match the must_match_regex constraint, the form displays the specified error_message. Multiple must_match_regex constraints for a single property blueprint are evaluated in the order listed.



Configurable Properties

Many of these properties are strings, but can be used with validators in order to check that the user typed in the correct format for a URL, IP, address, domain, etc.



email

An email address.

ip_ranges

A range of IP addresses, with dashes and commas allowed. Example: 1.1.1.1-1.1.1.4,2.2.2.1-2.2.2.4





An integer representing a network port.

network_address

A single IP address or domain. Example: 1.1.1.1

network_address_list

A list of IP addresses or domains. Example: 1.1.1.1,example.com,2.2.2.2

Generated Properties (can also be configurable)

The following properties are configurable, but can also be generated by Ops Manager if configurable is false or the configurable key is omitted. The exceptions are the uuid and salted credentials properties, which are never configurable.

rsa_cert_credentials

An RSA certificate.

rsa_pkey_credentials

An RSA private key.

salted credentials

Username and password created using a non-reversible hash algorithm.

simple_credentials

Username and password.

secret

A random string or password.

uuid

A universal unique identifier.

Complex Properties (Selectors and Collections)

The selector and collections inputs are referenced by their selector and collection property blueprints. These are more complicated than simple properties in that they contain manifest snippets, which are further referenced in other manifest snippets. We will learn about manifest snippets in the next section.

Job Types

The following is an example of the <code>job_types</code> section that appears in a product template. This section defines the jobs that end up in a BOSH manifest. Those jobs are defined in your BOSH release. Jobs require many different settings in order to function properly, and that is the crux of what Ops Manager does for you: it asks a user for values to those settings and generates a manifest based on what was entered.

Ops Manager does not require product authors to provide vm_credentials in the property_blueprints for each job_type. This is because vm_credentials are generated automatically, and you can find them in the release manifest.

```
job_types:
 - name: web_server
  resource_label: Web Server
  templates:
   - name: web_server
    release: example-release
   - name: time_logger
    release: example-release
  release: example-release
  static ip: 1
  dynamic_ip: 0
  max in flight: 1
  single az only: true
  instance definition:
   name: instances
   type: integer
   configurable: true
   default: 1
   constraints
    max: 1
    property reference: '.web server.example text'
    property value: 'magic value'
  resource definitions:
    - name: ram
    type: integer
    configurable: true
    default: 1024
    - name: ephemeral disk
    type: integer
     configurable: true
    default: 2048
    - name: persistent_disk
    type: integer
    configurable: true
    default: 1024
    constraints
     min: 1024
    - name: cpu
    type: integer
    configurable: true
    default: 1
  property_blueprints:
  - name: static_ips
   type: ip_ranges
   configurable: true
   optional: true
  - name: generated_rsa_cert_credentials
   type: rsa cert credentials
  - name: generated_rsa_pkey_credentials
   type: rsa_pkey_credentials
  - name: generated salted credentials
   type: salted credentials
  - name: generated simple credentials
   type: simple_credentials
  - name: generated_secret
   type: secret
  - name: generated_uuid
   type: uuid
  - name: example_string_with_placeholder
   type: string
   configurable: true
   optional: true
   placeholder: 'Configure me!'
  - name: example_string
   type: string
   configurable: true
   default: 'Hello world'
    - must_match_regex: '^[^!@\#$\%^&*()]*$'
    error_message: 'This name cannot contain capital digits.'
   - must_match_regex: '^[^0-9]*$'
```

```
error_message: 'This name cannot contain digits.'
- name: example_migrated_integer
 type: integer
 configurable: true
- name: example_boolean
 type: boolean
 configurable: true
 default: true
- name: example_dropdown
 type: dropdown_select
 configurable: true
 default: kiwi
 options:
  - name: kiwi
   label: 'label for kiwi'
  - name: lime
   label: 'label for lime'
  - name: avocado
   label: 'label for avocado'
- name: example domain
type: domain
 configurable: true
 default: www.example.com
- name: example wildcard domain
 type: wildcard_domain
 configurable: true
 default: 'example.com'
- name: example_string_list
type: string_list
 configurable: true
default: 'a,list,of,strings'
- name: example_text
 type: text
 configurable: true
 default: 'some text'
- name: example_ldap_url
 type: ldap_url
 configurable: true
 default: 'ldap://example.com'
- name: example_email
 type: email
 configurable: true
 default: foo@example.com
- name: example http_url
 type: http url
 configurable: true
 default: 'http://www.example.com'
- name: example_ip_address
 type: ip_address
 configurable: true
 default: '192.168.0.1'
 name: example_ip_ranges
 type: ip_ranges
 configurable: true
 default: '1.1.1.1-1.1.1.4,2.2.2.1-2.2.2.4'
- name: example_multi_select_options
 type: multi_select_options
 configurable: true
 default: ['earth', 'jupiter']
 options:
  - name: mercury
   label: 'label for mercury'
  - name: venus
   label: 'label for venus'
  - name: earth
   label: 'label for earth'
   label: 'label for mars'
  - name: jupiter
   label: 'label for jupiter'
  - name: saturn
   label: 'label for saturn'
  - name: uranus
   label: 'label for uranus'
  - name: neptune
   label: 'label for neptune'
- name: example_network_address_list
 type: network_address_list
 configurable: true
 default: '1.1.1.1, example.com, foo.bar.example.com'
- name: example_network_address
 type: network address
 configurable: true
```

```
- name: example_port
type: port
 configurable: true
 default: 1111
- name: example_smtp_authentication
 type: smtp_authentication
 configurable: true
 default: plain
- name: client_certificate
type: ca_certificate
 configurable: true
 optional: true
manifest:
 generated:
  root_rsa_certificate: (( $ops_manager.ca_certificate ))
  rsa cert credentials
   public key pem: (( generated rsa cert credentials.public key pem ))
   cert\_and\_private\_key\_pems: ((\ generated\_rsa\_cert\_credentials.cert\_and\_private\_key\_pems\ ))
  rsa_pkey_credentials:
   public\_key\_pem: ((\ generated\_rsa\_pkey\_credentials.public\_key\_pem\ ))
    private\_key\_pem: ((\ generated\_rsa\_pkey\_credentials.private\_key\_pem\ ))
   public\_key\_openssh: ((\ generated\_rsa\_pkey\_credentials.public\_key\_openssh\ ))
   public_key_fingerprint: (( generated_rsa_pkey_credentials.public_key_fingerprint ))
   sha512_hashed_password: (( generated_salted_credentials.sha512_hashed_password ))
    \stackrel{-}{identity}: ((\ generated\_salted\_credentials.identity\ ))
   salt: (( generated salted credentials.salt ))
   password: ((\ generated\_salted\_credentials.password\ ))
   simple credentials:
   identity: (( generated_simple_credentials.identity ))
    password: (( generated simple credentials.password ))
  secret: (( generated_secret.value ))
  uuid: (( generated_uuid.value ))
 configured:
   string: (( example_string.value ))
  integer: (( example_migrated_integer.value ))
  record\_collection: ((\ .properties.example\_collection.value \ \|\ []\ ))
  selector: ((\ .properties.example\_selector.selected\_option.parsed\_manifest(my\_snippet)\ ))
 ops_manager_provided_accessors:
  name: (( name ))
  ram: (( ram ))
  ephemeral disk: (( ephemeral disk ))
  persistent_disk: (( persistent_disk ))
  instances: (( instances ))
  availability_zone: (( availability_zone ))
  first_ip: (( first_ip ))
  ips_by_availability_zone: (( ips_by_availability_zone ))
  bosh_job_partition_stats: (( bosh_job_partition_stats ))
```

name

String. Required. The name of the job as it will be created in the Ops Manager generated BOSH manifest.

resource_label

String. Required. The label of the job as it will appear in the resources page of the tile.

templates

Array of Hashes. Required. Each element has the following fields:

name

The name of the job template to use. Required.

release



The name of the release the template is from. Required.

consumes

A YAML string defining BOSH links of this job consumes. Optional.

provides

A YAML string defining BOSH links I this job provides. Optional.

This is a BOSH feature (creating jobs from different releases). See the BOSH documentation ☑ for more information.

release

String. Required. The name of the BOSH release contained in your product archive (.pivotal file).

static_ip

Boolean. Required. Sets whether the BOSH job should have a static or dynamic IP. Static IPs are set by the user, and reserved, while Dynamic IPs are set by BOSH. Both are, in effect, static, in that they should not change between deployments.

dynamic_ip

Boolean. Required. Set the opposite of static ip. This will eventually be eliminated as a property as it is obviously redundant and unnecessary.

single_az_only

Boolean. Required. You can give users control of balancing jobs across availability zones (AZs) by setting single az only to false. To limit a job to a single AZ, set this to true.



warning: If you change the single_az_only setting, your VMs may switch AZs. This change can cause an orphaned disk.

max in flight

Integer. Required. A BOSH setting that controls the number of instances of this job that BOSH will deploy in parallel.

resource_definitions

Array of Hashes. Required. A set of resource settings for the job along with max and min constraints, defaults, and whether or not the user can configure (change) the setting. The resources that can be set are:

- ram
- ephemeral_disk
- persistent_disk
- cpu

💡 Note: If you set the default property for persistent_disk to 0, users cannot edit this value and the Resource Config page in Ops Mananger displays None under the persistent disk field.



instance_definition

Hash. Required. The number of default instances for a job along with max, min, odd, and the ability to decrease sizing after deploy constraints.

If your product uses an external service that performs the same job as a service in Elastic Runtime, you can reduce resource usage by setting the instance count of a job to 0 with the zero_if property. For example, your product uses Amazon Relational Database Service (RDS) instead of MySQL, which is the default system database for Elastic Runtime. Set property to property to property value to magic value to change the instance reference

counts of all MySQL jobs to 0.

manifest

Text snippet, prefaced by pipe symbol: . Optional. Ops Manager generates a BOSH manifest that defines properties for each job that the manifest deploys. Some of these properties are not set until the user clicks **Apply Changes**, because the user configures them in the tile or because Ops Manager has to generate them.

To include these properties in a manifest snippet, use "double-parens" syntax, which consists of a variable name surrounded by two sets of parentheses:

```
manifest: |
pizza_toppings:
peppers: (( .properties.example_selector.pizza_option.peppers.value ))
```

When Ops Manager parses a product template and BOSH parses a manifest, they both fill in properties designated by double-parens syntax. Some property values in a product template, such as CredHub credentials, must be filled in by BOSH on the BOSH Director VM, rather than by Ops Manager. To include these BOSH deploy-time properties in a manifest snippet, use "triple-parens" notation:

```
manifest: |
credhub:
concatenated_password: prefix-((( credhub-password )))-suffix
password: ((( credhub-password )))
```

Ops Manager strips the outer parentheses from these expressions and includes the resulting double-parens expressions in the manifest it generates, for BOSH to evaluate at deploy time.

Selector Manifest Snippets

Selector snippets are evaluated twice. As you saw in the property_blueprint, the selector has a manifest snippet for both sets of inputs that the user might choose. Only one of these sets is evaluated and inserted into the job's manifest.

Ops Manager Provided Snippets

The following double-parens accessors retrieve your job properties:

```
name: (( name ))
ips: (( ips ))
ram: (( ram ))
ephemeral_disk: (( ephemeral_disk ))

persistent_disk: (( persistent_disk ))
ips_by_availability_zone: (( ips_by_availability_zone )) (deprecated)
instances: (( instances ))
availability_zone: (( availability_zone )) (deprecated)
bosh_job_partition_stats: (( bosh_job_partition_stats )) (deprecated)
first_ip: (( first_ip )) (deprecated)
first_network_deprecated: (( first_network_deprecated )) (deprecated)
subnet_cidrs: (( subnet_cidrs ))
```

The following is a list of all typed values with the accessor "value":

- collection
- ldap_url
- domain
- wildcard_domain
- ip_ranges
- ip_address
- email
- port
- integer
- string
- boolean
- text
- smtp_authentication
- network_address
- network_address_list
- string_list
- ca_certificate
- multi_select_options
- dropdown_select
- vm_type_dropdown
- disk_type_dropdown
- uuid
- service_network_az_multi_select
- service_network_az_single_select
- secret

The following list shows typed values with multiple accessors:

- simple_credentials: identity, password
- rsa_cert_credentials: private_key_pem, cert_pem, public_key_pem, cert_and_private_key_pems
- rsa_pkey_credentials: private_key_pem, public_key_pem, public_key_openssh, public_key_fingerprint
- salted_credentials: salt, identity, password
- selector: value, selected_option, nested context

In addition, Ops Manager supports accessors that are global to the entire installation rather than job specific.

- \$ops_manager.ca_certificate: The internal SSL CA certificate used to sign all SSL certificates generated by this Ops Manager instance, such as when the user clicks a **Generate Self-Signed RSA Certificate** link
- \$ops_manager.trusted_certificates
- \$ops_manager.http_proxy
- \$ops_manager.https_proxy
- \$ops_manager.no_proxy
- \$director.deployment_ip
- \$director.hostname
- \$director.username
- \$director.password
- \$director.ntp_servers
- \$director.ca_public_key
- \$director.tld
- \$director.bosh_metrics_forwarder_client_name
- \$director.bosh_metrics_forwarder_client_secret

- \$self.uaa_client_name
- \$self.uaa_client_secret
- \$self.service_network
- \$self.stemcell_version
- ..PRODUCT-NAME.properties
- ..PRODUCT-NAME.deployment_name



Property Reference

Page last updated:

This topic explains how PCF Tiles describe properties.

Double-Parentheses Expressions

The product template .yml file in a tile's metadata subdirectory defines how the tile interface collects configurable properties from the user, and how Ops Manager incorporates these properties into the deployment manifest that it creates.

The product template contains manifest snippets in both the form_types section that defines the tile interface, and the job_types section describing the jobs that the manifest deploys. Within these snippets, you can use special expressions to include property values that are otherwise not known ahead of time, such as configurable properties or system properties:

- Double-parentheses expressions designate property values that Ops Manager fills in when it generates the deployment manifest, after the user clicks Apply Changes. These values include configurable properties and properties supplied by Ops Manager.
- Triple-parentheses expressions designate property values that BOSH supplies when it deploys instances of the tile service, such as CredHub credentials.

Referencing Properties

Evaluating a property can be represented by piecing two segments together:

- The location of the property
- What information from the property you are looking to access, or accessors

Together, the double-parentheses expression can be written as:

```
(( LOCATION_OF_PROPERTY.ACCESSOR ))
```

The method of referencing the location of the property varies. Here is a complete list of ways to reference a property with some help text to indicate the situation.

.properties.top_level_property	Refers to the property blueprint whose name is "top_level_property" found in the global list of properties of the same product
.job_one.job_level_property	Refers to the property blueprint whose name is "job_level_property" found in the list of properties of the job "job_one" of the same product
job_level_property	Refers to the property blueprint whose name is "top_level_property" found in the same product and job whose manifest is currently being evaluated
other_product.properties.top_level_property	Refers to the property blueprint whose name is "top_level_property" found in the global list of properties of the product "other_product"
other_product.job_two.job_level_property	Refers to the property blueprint whose name is "job_level_property" found in the list of properties of the job "job_one" of the product "other_product"

Accessors vary between property blueprint types. See the Property Blueprint Reference for available properties and their accessors.

The following example uses the property blueprint type string with its one accessor, value . A valid double-parentheses expression to access the value of this property (assuming it is top-level, and has the name example-string) would look like:

((.properties.example-string.value))

Ops Manager allows empty arrays in double-parentheses expressions. For example:

 $((\ .properties.example-string.value \, || \, [] \,))$



Note: Ops Manager 1.12 and later support using empty arrays in double-parentheses syntax.



Dollar Contexts

Outside of properties, you can also retrieve information about various configuration details of your product and Ops Manager.

- \$ops_manager: used by any product to obtain information about specific OpsManager
- \$director: used by any product to obtain information about the Director
- \$self: used by your own product to obtain information about your product's configuration

\$ops_manager

ca_certificate	Provides the root CA cert that is used to sign the Director VM
trusted_certificates	Provides a list of certs that are applied by the Director to all VMs
http_proxy	Provides the comma separated values that are entered if OpsManager traffic is directed to an HTTP Proxy
https_proxy	Provides the comma separated values that are entered if OpsManager traffic is directed to an HTTPS Proxy
no_proxy	Provides a the comma separated values that should not go through a proxy

\$director

deployment_ip	Provides the IP address that the BOSH Director is deployed on
username	Provides the username for the Director VM
password	Provides the password for the Director VM
ntp_servers	Provides a list of ntp servers that are deployed by the Director
ca_public_key	Provides the public key that is used to sign the Director VM
hostname	Provides the hostname for the Director VM
tld	Returns the string bosh as the top-level domain (TLD) of the BOSH Director
bosh_metrics_forwarder_client_name	Provides the BOSH Metrics Forwarder client name
bosh_metrics_forwarder_client_secret	Provides the BOSH Metrics Forwarder client secret



🗣 Note: Support for the Sdirector.username and Sdirector.password accessors will be removed in future versions of Ops Manager.

\$self

uaa_client_name	Provides the UAA client name created for your Product to communicate with the BOSH Director
uaa_client_secret	Provides the UAA client secret created for your Product to communicate with the BOSH Director
service_network	Provides the name of the service network that has been assigned to your product
stemcell_version	Provides the stemcell version that is being used by your product

Property Blueprint Reference

string

Holds a single string value

Accessors:

value Returns the string value	
--------------------------------	--

Product template example:

```
- name: example_string
type: string
configurable: true
default: 'Hello world'
constraints:
- must_match_regex: '\A[^!@#$%^&*()]*\z'
error_message: 'This name cannot contain special characters.'
- must_match_regex: '\A[^0-9]*\z'
error_message: 'This name cannot contain digits.'
```

boolean

Holds a single boolean value

Accessors:

value Returns the boolean value

Example:

- name: example_boolean type: boolean configurable: true default: false

collection

Collections represent the ability to hold multi-property entries. Each "record" will contain values for the configured set of property blueprints.

Accessors:

```
value

An array of hashes whose key are the property name.

Example: [{album: 'my-album', artist: 'some-artist', explicit: true, genre: 'rock'}]
```

Example:

```
- name: example_collection
type: collection
configurable: true
property_blueprints:
  - name: album
   type: string
   freeze_on_deploy: true
  - name: artist
   type: string
   freeze_on_deploy: true
  - name: explicit
  type: boolean
  - name: genre
  type: dropdown_select
   configurable: true
   optional: true
   options:
    - name: rock
     label: 'Rock'
    - name: country
     label: 'Country'
    - name: edm
     label: 'Beep Boop PSH'
 default:
  - album: Christmas Carols
   artist: Ops Manatee
   explicit: true
   genre: edm
```

Selector



Provides the ability to switch between groups of properties.

Selectors are unique in the way that property information is accessed. Ops Manager provides accessors available at the top-level selector property, accessors for retrieving a specific property in an option group, and the ability to provide manifest snippets for a selector option group.

Each selector group may provide manifest snippets. This is because Ops Manager does not support conditionally adding manifest snippets. Therefore, it's difficult to be able to write manifest sections for a selector. A manifest snippet should be present within all option groups, and can

Accessors on Selector Property:

value	Returns a string of the currently selected option group. Example: "Filet Mignon"
selected_option	Scopes the accessor to the currently selected option group. Does not return meaningful information alone. Must be chained with an accessor available to a Selector Option Group.
SPECIFIC_SELECTOR_OPTION_GROUP	Scopes the accessor to a specific selector option group. Does not return meaningful information alone. Must be followed with the name and accessor of a specific property in the option group.

Example, value:

 $.properties.example_selector.filet_mignon_option.review.value$

Accessors on Selector Option Group:

parsed_manifest(manifest_snippet_name)	Returns a hash of the specific manifest snippet

Example, selected_option:

.properties.example_selector.selected_option.parsed_manifest(my_snippet)

Here, my_snippet corresponds to the name of an entry within each option_template's named_manifests section.

Example, option group:



```
- name: example selector
type: selector
configurable: true
default: Pizza
 freeze_on_deploy: true
 option_templates:
  - name: pizza_option
   select_value: Pizza
   named_manifests:
    - name: my_snippet
     manifest:
      pizza toppings:
        pepperoni: ((\ .properties.example\_selector.pizza\_option.pepperoni.value\ ))
        pineapple: ((\ .properties.example\_selector.pizza\_option.pineapple.value\ ))
        other: ((\ .properties.example\_selector.pizza\_option.other\_toppings.value\ ))
   property_blueprints:
     - name: pepperoni
     type: boolean
      configurable: true
     freeze_on_deploy: true
     - name: other_toppings
     type: string
     configurable: true
     optional: true
     constraints:
     - must_match_regex: '\A[^!@#$%^&*()]*\z'
       error_message: 'This name cannot contain special characters.'
  - name: filet mignon option
   select_value: Filet Mignon
   named_manifests:
    - name: my_snippet
     manifest:
      rarity: ((\ .properties.example\_selector.filet\_mignon\_option.rarity\_dropdown.value\ ))
       review: (( .properties.example_selector.filet_mignon_option.review.value ))
       secret_sauce: (( .properties.example_selector.filet_mignon_option.secret_sauce.value ))
   property_blueprints:
    - name: rarity_dropdown
     type: dropdown select
     configurable: true
     default: rare
     options:
       - name: rare
       label: 'Rare'
       - name: medium
       label: 'Medium'
       - name: well-done
        label: 'Well done'
     - name: secret_sauce
     type: secret
     configurable: true
     optional: true
```

ldap_url

Ensures the inputted string matches a URL of the LDAP protocol

Accessors:

value Returns a string

Example:

- name: example_ldap_url type: ldap_url configurable: true default: 'ldap://example.com'

domain

Ensures the string value is a domain

Accessors:



value Returns a string

Example:

 name: example_domain type: domain configurable: true default: 'example.com'

wildcard_domain

Ensures the string value is a domain prefixed with "*."

Accessors:

value	Returns a string
to_wildcard	Returns a string of the value prefixed with "*." if not present

Example:

 name: example_wildcard_domain type: wildcard_domain configurable: true default: '*.example.com'

ip_ranges

Holds an array of strings and ensure the values are IP ranges

Accessors:

value	Returns a string containing a comma-separated list of IP ranges
parsed_ip_ranges	Returns an array of strings for each IP range

Example:

- name: example_ip_ranges type: ip_ranges configurable: true default: '1.1.1.1-1.1.14,2.2.2.1-2.2.2.4'

ip_address

Ensures the string value is an IP address

Accessors:

value	Returns a string
-------	------------------

Example:

- name: example_ip_address type: ip_address configurable: true default: '192.168.0.1'

email

Ensures the string value is formatted as an email address

Accessors:

value Returns a string

Example:

name: example_string
 type: email
 configurable: true
 default: 'john@example.com'

port

Holds a single integer value

Accessors:

value Returns an integer

Example:

- name: example_port type: port configurable: true default: 3000

integer

Holds a single integer value

Accessors:

value Returns an integer

Example:

- name: example_integer type: integer configurable: true default: 100

text

Holds a single string value

Accessors:

value Returns a string

Example:

- name: example_text type: text configurable: true default: | Example Text

smtp_authentication

Holds string with a possible value of plain, login, or cram_md5

Accessors:

Returns a string with possible value of plain , login , cram_	lue	Returns a string with possible value of plain, log	gin ,

Example:

- name: example_smtp_authentication type: smtp_authentication configurable: true default: plain

network_name

Ensure the string is a network name

Accessors:

Example:

 name: example_network_name type: network_name configurable: true default: 'ExampleNetwork'

network_address

Ensure the string is a network address

Accessors:

value	Returns a string
-------	------------------

Example:

name: example_network_address
 type: network_address
 configurable: true
 default: 'localhost'

network_address_list

Holds an array of new addresses

Accessors:

value	Returns a string containing a comma separated list of network addresses
parsed_network_addresses	Returns an array of strings for each network address

Example:

- name: example_network_address_list type: network_address_list configurable: true default: 'localhost,1.1.1.1'



string_list

Holds an array of strings

Accessors:

value	Returns a string
parsed_strings	Returns an array of strings for each string entry
parsed_regex	Returns a string containing a regex of the format "^(string1 string2 string3)\$" where the value of this property is "string1,string2,string3"

Example:

- name: example_string_list type: string_list configurable: true default: 'foo,bar,baz'

ca_certificate

Holds a string value

Accessors:

	value		Returns a string
--	-------	--	------------------

Example:

- name: example_ca_certificate type: ca-certificate configurable: true default: |

-- BEGIN FAKE CERT --

-- END FAKE CERT --

multi_select_options

Holds an array of selected string values

Accessors:

value Returns an array of strings for the selected options
--

Example:

- name: example_multi_select_options type: multi_select_options configurable: true default: ['earth', 'mercury'] options: - name: mercury label: 'label for mercury'

- name: venus label: 'label for venus'

- name: earth label: 'label for earth'

dropdown_select

Holds an array of strings selected string values

Accessors:

value Returns a string

Example:

- name: example_dropdown type: dropdown_select configurable: true default: kiwi options:
 - name: kiwi label: 'label for kiwi'
 - name: limelabel: 'label for lime'name: avocadolabel: 'label for avocado'

vm_type_dropdown

Holds single string value selected from allowed vm_types

Accessors:

value Returns a string

Example:

 name: example_vm_type_dropdown type: vm_type_dropdown configurable: true

disk_type_dropdown

Holds single string value selected from allowed disk_types

Accessors:

value Returns a string

Example:

 name: example_disk_type_dropdown type: disk_type_dropdown configurable: true

uuid

Holds a string uuid value

Accessors:

value Returns a string

Example:

- name: example_uuid type: uuid configurable: true

service_network_az_multi_select

Holds an arrays of string value selected from allowed azs

Accessors:

value Returns an array of strings for the selected options

Example:

- name: example_service_network_az_multi_select type: service_network_az_multi_select configurable: true

service_network_az_single_select

Holds a single string value selected from allowed azs

Accessors:

value Returns a string

Example:

name: example_service_network_az_single_select
 type: service_network_az_single_select
 configurable: true

secret

Holds a single string value

Accessors:

value Returns a string

Example:

 name: example_secret type: secret configurable: true

Contact Us

Page last updated:

To learn more about the Pivotal ISV Partner Program, or to request our assistance with your integration project, please contact us at one of the following addresses:

• Program Manager: Marina Joseph

• Business Development: Nima Badiey

• Platform Engineering: Guido Westenberg

Contributions

The source code for this site is in a public GitHub repository ♂.

We greatly appreciate contributions to the content in the form of pull requests, as well as GitHub issues with corrections, comments, or suggestions.