Funcons-beta: Controlling *

The PLanCompS Project

Controlling.cbs | PLAIN | PRETTY

Controlling

```
[ Datatype continuations 

Funcon continuation 

Entity plug-signal 

Funcon hole 

Funcon resume-continuation 

Entity control-signal 

Funcon control 

Funcon delimit-current-continuation 

Alias delimit-cc ] 

Meta-variables T, T_1, T_2 <: values 

Datatype continuations(T_1, T_2) ::= continuation(\_: abstractions(() \Rightarrow T_2))
```

continuations(T_1 , T_2) consists of abstractions whose bodies contain a hole, and which will normally compute a value of type T_2 when the hole is plugged with a value of type T_1 .

```
Entity \_ \xrightarrow{\text{plug-signal}(V?:\text{values?})}
```

A plug-signal contains the value to be filled into a hole in a continuation, thereby allowing a continuation to resume.

```
Funcon hole : ⇒ values
```

A hole in a term cannot proceed until it receives a plug-signal containing a value to plug the hole.

```
Rule hole \xrightarrow{\text{plug-signal}(V)} V
```

```
Funcon resume-continuation(K: continuations(T_1, T_2), V : T_1): \Rightarrow T_2
```

resume-continuation (K, V) resumes a continuation K by plugging the value V into the hole in the continuation.

^{*}Suggestions for improvement: plancomps@gmail.com.
Reports of issues: https://github.com/plancomps/CBS-beta/issues.

Rule
$$X \xrightarrow{\text{plug-signal}(V)} X'$$

resume-continuation(continuation(abstraction(X)), $V: T$) $\xrightarrow{\text{plug-signal}()} X'$

Entity $\xrightarrow{\text{control-signal}(F?:(functions(continuations(T_1,T_2),T_2))?)}$

A control-signal contains the function to which control is about to be passed by the enclosing delimit-current-continuation(X).

Funcon control(
$$F$$
: functions(continuations(T_1, T_2), T_2)): $\Rightarrow T_1$

control(F) emits a control-signal that, when handled by an enclosing delimit-current-continuation(X), will apply F to the current continuation of control(F), (rather than proceeding with that current continuation).

Rule
$$\operatorname{control}(F:\operatorname{functions}(_,_)) \xrightarrow{\operatorname{control-signal}(F)} \operatorname{hole}$$

Funcon $\operatorname{delimit-current-continuation}(X:\Rightarrow T):\Rightarrow T$

Alias $\operatorname{delimit-cc} = \operatorname{delimit-current-continuation}$

 $\operatorname{delimit-current-continuation}(X)$ delimits the scope of captured continuations.

Rule
$$\frac{X \xrightarrow{\text{control-signal()}} X'}{\text{delimit-current-continuation}(X) \xrightarrow{\text{control-signal()}} X'} \\ \text{delimit-current-continuation}(X) \xrightarrow{\text{control-signal()}} \\ \text{delimit-current-continuation}(X') \\ \frac{X \xrightarrow{\text{control-signal(F)}} X'}{\text{delimit-current-continuation}(X) \xrightarrow{\text{control-signal()}}} \\ \text{delimit-current-continuation}(apply(F, \text{continuation closure}(X')))}$$