# R-Group Analysis

Schrödinger Suite 2012 Update 2



R-Group Analysis Copyright © 2012 Schrödinger, LLC. All rights reserved.

While care has been taken in the preparation of this publication, Schrödinger assumes no responsibility for errors or omissions, or for damages resulting from the use of the information contained herein.

BioLuminate, Canvas, CombiGlide, ConfGen, Epik, Glide, Impact, Jaguar, Liaison, LigPrep, Maestro, Phase, Prime, PrimeX, QikProp, QikFit, QikSim, QSite, SiteMap, Strike, and WaterMap are trademarks of Schrödinger, LLC. Schrödinger and MacroModel are registered trademarks of Schrödinger, LLC. MCPRO is a trademark of William L. Jorgensen. DESMOND is a trademark of D. E. Shaw Research, LLC. Desmond is used with the permission of D. E. Shaw Research. All rights reserved. This publication may contain the trademarks of other companies.

Schrödinger software includes software and libraries provided by third parties. For details of the copyrights, and terms and conditions associated with such included third party software, see the Legal Notices, or use your browser to open \$SCHRODINGER/docs/html/third\_party\_legal.html (Linux OS) or %SCHRODINGER%\docs\html\third\_party\_legal.html (Windows OS).

This publication may refer to other third party software not included in or with Schrödinger software ("such other third party software"), and provide links to third party Web sites ("linked sites"). References to such other third party software or linked sites do not constitute an endorsement by Schrödinger, LLC or its affiliates. Use of such other third party software and linked sites may be subject to third party license agreements and fees. Schrödinger, LLC and its affiliates have no responsibility or liability, directly or indirectly, for such other third party software and linked sites, or for damage resulting from the use thereof. Any warranties that we make regarding Schrödinger products and services do not apply to such other third party software or linked sites, or to the interaction between, or interoperability of, Schrödinger products and services and such other third party software.

Revision A, September 2012

# **Document Conventions**

In addition to the use of italics for names of documents, the font conventions that are used in this document are summarized in the table below.

Font	Example	Use
Sans serif	Project Table	Names of GUI features, such as panels, menus, menu items, buttons, and labels
Monospace	\$SCHRODINGER/maestro	File names, directory names, commands, environment variables, command input and output
Italic	filename	Text that the user must replace with a value
Sans serif uppercase	CTRL+H	Keyboard keys

Links to other locations in the current document or to other PDF documents are colored like this: Document Conventions.

In descriptions of command syntax, the following UNIX conventions are used: braces { } enclose a choice of required items, square brackets [ ] enclose optional items, and the bar symbol | separates items in a list from which one item must be chosen. Lines of command syntax that wrap should be interpreted as a single command.

File name, path, and environment variable syntax is generally given with the UNIX conventions. To obtain the Windows conventions, replace the forward slash / with the backslash \ in path or directory names, and replace the \$ at the beginning of an environment variable with a % at each end. For example, \$SCHRODINGER/maestro becomes \*SCHRODINGER\*\maestro.

Keyboard references are given in the Windows convention by default, with Mac equivalents in parentheses, for example CTRL+H (%H). Where Mac equivalents are not given, COMMAND should be read in place of CTRL. The convention CTRL-H is not used.

In this document, to *type* text means to type the required text in the specified location, and to *enter* text means to type the required text, then press the ENTER key.

References to literature sources are given in square brackets, like this: [10].

# **R-Group Analysis**

If you have a set of structures that are built on a common or similar scaffold, by attaching different groups at one or more points on the scaffold, you might want to see the properties of the structures as a function of the groups at the various attachment points. The R-Group Analysis facility provides tools for identifying the scaffolds, the attachment points, and the R groups at each point, and displaying the R groups and property information in various forms.

# 1 Analyzing a Set of Structures

The analysis and display of R groups is done in the R-Group Analysis panel. The panel is available from Maestro, from Canvas, and from the command line.

- To open the R-Group Analysis panel from Maestro, choose Tools → R-Group Analysis in the main window.
- To open the R-Group Analysis panel from Canvas, choose Applications → R-Group Analysis in the master view.
- To open the R-Group Analysis panel from the command line, type the following command in a terminal window:

\$SCHRODINGER/run r group analysis.py [input-file]

# 1.1 Specifying the Structures to Analyze

First, you must specify the source of the structures to analyze, which you can do by selecting Analyze structures from and choosing a source from the option menu. The sources are:

- Project Table (selected entries)—Use the structures that are selected in the Project Table. Only available from Maestro.
- All Rows—Use all rows in the spreadsheet. Only available from Canvas.
- Selected Rows—Use the rows that are selected in the spreadsheet. Only available from Canvas.
- File—Use the structures in a specified file. Enter the name of the structure file in the text box, or click Browse and navigate to the file in the file selector that opens. The file must be in Maestro or SD format, and can be compressed or uncompressed. The file name is displayed in the text box when you click Open.




Figure 1. R-Group Analysis panel.

## 1.2 Defining the Core

The second step in the analysis is to choose a method for the definition of the core of the structures. The analysis determines the R groups that are attached to this core. The core can be taken from CombiGlide attachment-bond labeling, specified by a SMARTS pattern, or determined by the maximum common substructure obtained from a Canvas MCS run. The options available under Core definition from are:

Canvas maximum common substructure—Use the maximum common substructure as
determined from a Canvas MCS calculation. When you choose this option, you must also
choose a definition of equivalent atoms from the Atom equivalences option menu. The
options are described in Table 5.7 of the Canvas User Manual and also in the help message for canvasMCS, which you can view with the following command:

```
$SCHRODINGER/utilities/canvasMCS -h
```

- SMARTS—Specify a SMARTS pattern for the core in the text box. From Maestro, you can also select atoms in the Workspace and click Get from Workspace Selection to load a SMARTS pattern into the text box. You can edit the SMARTS pattern in the text box.
- CombiGlide annotation in structures—Use the core definition that has been added by CombiGlide. You should use this option only if you are using structures that were generated by CombiGlide.

The CombiGlide annotation for determining the core provides a unique definition, and one that is restricted to singly bonded terminal attachments. The use of SMILES or Canvas MCS to determine the core can result in cores with different atomic composition, multiply bonded R groups, R groups that are attached to the core in more than one location, and multiple core structures.

When Canvas MCS methods that allow different atom or bond types to be treated as equivalent are used, some cores may have attachment points to which no R group is attached. For example, the core might contain a pyridine ring in one structure, but a benzene ring in another. An attachment point in the benzene ring might be at the carbon atom corresponding to the nitrogen in the pyridine. In this case, the attachment at the nitrogen is considered a "null" attachment, and a dummy atom is used with the label "Null".

R groups that are attached with multiple bonds are treated as any other group. You might, for example have a carbonyl group (XC=OX') in one structure where there is a substituted methylene group (e.g.  $XCHCH_3X'$ ) in another. In the first structure the R group is =O, in the second it is  $=CH_3$ . The core in both structures involves the X-C-X' framework.

R groups that are attached at multiple attachment points (thus forming rings) are listed as groups for each attachment point.

These two methods can also produce multiple possible core structures, so the analysis must select the best match. This is done to minimize the number of attachment points and the total number of R groups.

# 1.3 Running the Analysis

When you have selected the input structures and chosen a method for defining the core, click Start to run the analysis. Once the analysis finishes, the R-Group Viewer panel opens. In this panel you can view the groups, export them, and open other panels that display various analyses of the properties. These panels are described in the following sections.

# 1.4 Saving and Loading Results of an Analysis

If you want to save the results of the analysis, click Save Results, and navigate to a location and save the results (as a zip file) in the file selector that opens. You can then read the results of this analysis back in at a later time, by selecting Restore state from previous run, then clicking Browse and browsing to the zip file. When the results are read, you can click View Results to view the results of the analysis, as explained below. The analysis controls are dimmed when you select Restore state from previous run.

# 2 Viewing and Exporting R-Groups

If you want to view the results of the analysis by displaying the structures with the R groups marked, you can do so in the R-Group Viewer panel. This panel displays the structures and the R groups for each structure. It also allows you to choose R groups at each position and display only the input structures containing them, and then export the restricted list of input structures. You can also export the R groups as individual molecules, capped with methyl groups.




Figure 2. R-Group Viewer panel.

To open the R-Group Viewer panel, click View Results in the R-Group Analysis panel. This panel opens automatically when the analysis of the structures in the R-Group Analysis panel finishes.

In the Input Structures section, you can view the individual input structures, annotated to display the attachments to the core. To step through the structures, click the arrow buttons. To display a particular structure, enter the structure index in the text box.

The structures are displayed as 2D images. The attachment points are marked with arrows pointing toward the R groups. The arrows are color-coded to match the rows in the Attachments table. The arrow is outlined for the current attachment, which is the attachment that is selected in the Attachments table, and whose R groups are displayed in the R Groups section.

In the R Groups section, you can view the R groups for a given attachment position, and restrict the structures that are shown by selecting R groups. The bond that connects an R group

to the core is colored the same way and oriented in the same direction as the attachment bond in the input structure. You can export the structures or the R groups. The table in this section displays the 2D structures of the R groups at the current attachment position. The table cell for the R group that is displayed in the Input Structures section is outlined in black. When you pause the pointer over the table cell, an enlarged image of the R group is displayed. You can select cells in the table when restricting the visible input structures.

The Attachments table lists the attachment positions that were located in the analysis. The first column is an index and is color-coded to match the positions marked in the Input Structures display area. The remaining columns show the name given to the attachment, the number of R groups selected at the attachment position, and the name of the temporary file that stores the R groups. Selecting a table row populates the table in the R Groups section with the R groups found at that attachment position. The table is noneditable.

### 2.1 Restricting the Structures Displayed

To restrict the structures that are shown in the Input Structures section, select Restrict visible input structures by selecting R-groups. By default, all R groups are selected for display at each position. For each position you can choose the R groups that you want to display by selecting them in the table. To change the position whose R groups are shown in the table, select the position in the Attachments table.

There are two ways of combining the restrictions at each position, determined by the option chosen for the Positional combining rule:

- AND—Display only those structures that have a selected R group (fragment) at all attachment positions.
- OR—Display only those structures that have a selected R group (fragment) at one or more of the attachment positions.

To return to the default selection, click Select All R-Groups, All Positions. To remove the restrictions, deselect Restrict visible input structures by selecting R-groups.

# 2.2 Exporting Structures

If you want to export the input structures, click Export Input Structures. A dialog box opens, in which you can make the following choices:

- Export the structures to a file or to the Project Table (only available from Maestro).
- Export all structures or only the visible structures.
- Superimpose the structures by aligning the cores to that of the first input structure.

If the structures are exported to a Maestro file or to the Project Table, the annotations that identify the attachment points are kept; for file types other than Maestro, they are discarded. The allowed file types are Maestro (.mae, .maegz), SD (.sdf), and SMILES (.smi); the file type written is determined by the extension that you provide for the file name.

### 2.3 Exporting R-Groups

To export the R groups as separate molecules, capped with methyl groups, to a set of Maestro files or to the Project Table, click Export R-Group Structures. The set of R groups at each position is exported to a separate file or entry group. The base name of the file or the entry group is given in the Filename text box. To this name is added the suffix <code>\_rga-N</code>, where N is the position number. This name is used for the entry group name, and the <code>.mae</code> extension is added to it for the file name. The titles of the structures are set to R-group M, where M is the index of the R group in the list for the given attachment.

There are two options that you can select:

- Save MCS .csv output—export the CSV output file produced by canvasMCS, if you ran a
  Canvas MCS calculation to define the core.
- Export for use in CombiGlide—Create the necessary extra files so that the R groups can be used in CombiGlide as reagents.

# 3 Analyzing Molecular Properties

The R-group analysis facility offers several ways of displaying information on molecular properties and their relationship to the R-groups and the cores: an activity cliff plot, importance analysis, a heat map, R-group QSAR, and an SAR table, in separate panels. These features are described in the following subsections.

# 3.1 Activity Cliffs

When examining structure-activity relations, you may want to identify "activity cliffs", where a small change in structure produces a large change in a property. This can be done in the Activity Cliffs panel, which you open by clicking Activity Cliffs in the R-Group Viewer panel.

The first task is to select the property, which you can do from the Property option menu. Next, choose whether to examine property variations at a single attachment point (One R-group), or at up to two attachment points (Up to two R-groups). The latter is useful for analyzing the activity variation with structure when groups are exchanged between two sites, possibly resulting in different binding modes.




Figure 3. Activity Cliffs panel.

The structural differences are calculated using fingerprints, with a given similarity metric. There are three choices for the fingerprint settings:

- Ignore atom-type differences—Evaluate the fingerprint differences using radial fingerprints with no atom or bond type information, and exclude hydrogens. This choice means that the variations in structure that are considered are purely in the connectivity.
- Observe atom type differences—Evaluate the fingerprint differences using radial fingerprints, with atoms distinguished by element, and bonds distinguished by bond order and aromaticity. This choice produces larger variations in fingerprint differences, and distinguishes between similar structures that might differ only in the atom type, e.g. substitution of Cl for F, or NH<sub>2</sub> for OH.
- Use custom fingerprints—Choose the fingerprint type and precision, the atom typing scheme, and the similarity metric to use, from those available in Canvas. This choice allows the greatest flexibility in setting up the analysis. This button opens the Activity Cliffs Options dialog box, in which you can make the choices described.

After making settings, click Run to run the analysis. The settings you used are listed in the Last run settings section at the top of the panel.

As the calculation runs, a progress bar is displayed at the bottom of the panel. The calculation time varies quadratically with the number of structures. When the job finishes, the plot of change in property against fingerprint difference is displayed, and the table of structures and values is populated.

The plot displays the difference in property for pairs of structures as a function of the finger-print difference. The points in the plot are colored by the Mahalanobis distance of the points from the centroid of all the points. Points within two standard deviations of the centroid are colored purple. Points outside this range with a larger property difference than average are colored red-purple if they lie within 4 standard deviations of the centroid, and red if they are outside 4 standard deviations. Likewise, points outside this range with a smaller property difference than the average are colored blue-purple if they lie within 4 standard deviations of the centroid, and blue if they are outside 4 standard deviations. The legend for the color scheme in the plot is displayed in the Legend section.

You can select points in the plot by clicking on them. The points are marked with an X, and the corresponding rows are selected in the table. To add points to the selection, use shift-click; to change the selection of one point without affecting the others, use control-click.

The plot toolbar contains a standard set of tools for adjusting the view of the plot, stepping through different views, and saving a plot image. The toolbar buttons are described below.



#### Reset

Reset the plot to the original pan and zoom settings.



#### Back

Display the previous view of the plot in the view history



#### Next

Display the next view of the plot in the view history



#### Pan/zoom

Pan the plot with the left mouse button, zoom with the right mouse button.



#### Zoom to rectangle

Drag out a rectangle on the plot to zoom in to that rectangle.



#### Configure subplots

Configure the margins and spacing of each plot in the panel.



#### Edit axis and curve parameters

Make settings for the title, range, labeling, and scale of the axes; the color, style, and width of lines; and the color, style, and size of markers.



#### Save image

Save an image of the plot to file. Opens a file selector in which you can browse to a location, select the image format, and name the image.

The structure and property table shows the pairs of structures represented in the plot and the relevant properties for each of the structures. You can select rows in the table, and the corresponding points are marked in the plot. You can show only the table rows that are selected, and hide the unselected rows. You can sort the rows by clicking in any of the column headings. The columns are described in Table 1.

You can export the contents of the table either as a CSV file, by clicking Export CSV, or as an image, by clicking Export Image. The structures in the CSV file are represented by the SMILES string for the structure. The SMILES string includes stereochemistry, and marks the attachment points with [Xe] and [Kr]. The image format can be one of PNG, TIFF, or JPEG.

Table 1. Columns in the structure and property table of the Activity Cliffs panel.

Column	Description	
Deviation	Signed Mahalanobis distance from the centroid of the points in the plot. The significates the relation of the activity difference to the activity difference of the crowd. The table cells are colored with the same scheme as the points in the plot.	
Structure 1 Structure 2	2D structures. Pausing the pointer over the cell displays an enlarged image of the structure in a tool tip. The value of the property for the structure is shown at the top left.	
$\Delta$ Fingerprint	Fingerprint distance between the two structures.	
$ \Delta$ Property	Absolute value of the difference in properties.	
Substitutions	Number of positions at which the two structures differ. The range of values depends on the choice made for showing the position variation.	

# 3.2 Importance Analysis

Importance analysis addresses the question of how sensitive the property of interest is to R-group variation at that position. A position is more important than another if varying the R group at that position leads to greater property differences than are observed when the R group at the other position is varied. The importance value of a position is the range of the property




Figure 4. The Importance Analysis panel.

over the R groups at that position, averaged over all structures containing a given R group at that position. As an example of its use, a position in which the range of the property does not vary much as the R group is changed may not be very important for improving the potency of a lead compound, whereas a position in which the property varies a great deal may be considered much more important.

The Importance Analysis panel presents the results of importance analysis and also displays the average of the property for each R group. You can open the Importance Analysis panel by clicking Importance Analysis in the R-Group Viewer panel, or by choosing Show R Groups from the shortcut menu in the histogram display of the Heat Map panel.

The panel shows a histogram of the importance value of a chosen property for each position, normalized to one for the most important position. It also contains a table showing the values of a selected function of that property for each R group at a selected position. You can choose the property and the function in the Displayed property section. To select the position, click the

position in the histogram. The current position is marked in the histogram with an asterisk. When you select a property, the current position is set to the most important position.

The properties for each R group are displayed as a heat map, colored by value. You can choose how the values in the cells is displayed from the Cell Display option menu. The choices are the same as in the Heat Map panel (see below). Likewise, you can set the color range and the numerical display by clicking Legend and Settings, and you can set the cell size. You can sort the property values in ascending or descending order, by clicking on the column heading.

If you want to make a copy of the results, you can export them. Clicking Export Graph exports an image of the histogram in PNG, TIFF, or JPEG format; likewise clicking Export Image exports an image of the table, with the same choice of formats. Clicking Export CSV exports the table data to a CSV file, with a SMILES string for the structure. The SMILES string includes stereochemistry, and marks the attachment points with [Xe] and [Kr] (as the nominal capping group).

Ideally, we would like to interpret the importance measure as characteristic of a position. For example, positions that make intimate contact with a receptor might be expected to exhibit greater variation of a binding property when its R groups are altered than one which protrudes into the solvent. However, there are several caveats to this interpretation. Most SAR data sets have very different numbers of structures at the various positions. Even if all else were equal, we would expect positions with more R groups to exhibit greater property variation and therefore to appear more important. Even if all positions had the same number of R groups, we would expect positions whose R groups exhibit greater chemical variability to exhibit a greater range of property values upon variation and hence a greater importance. For example, the chemists designing the SAR study might have had reason to believe that it is important to place hydrogen-bond donors at a given position. They might then sample only such R groups there, and this could in some cases lead to minimal property variation and low importance. These possibilities should be kept in mind when interpreting the importance measure.

# 3.3 Heat Maps

You can display a heat map of a selected property for R groups at two positions, as a function of the values at all other positions, in the Heat Map panel. To open the Heat Map panel, click Heat Map in the R-Group Viewer panel.

You can choose the property used in the heat map in the Displayed property section. Choose the property from the Property option menu. This option menu lists the properties that are available for the input structures. The way in which these properties are combined and displayed (the "function") is chosen from the Average, minimum, maximum option menu. You can display the average, the maximum, the minimum, or the median. You can also display the average and standard deviation, and color cells by either the average or the standard deviation.




Figure 5. The Heat Map panel.

Both values are displayed in each cell when you choose to display values. The heat map is updated when you choose a property or a function.

In addition to the heat map, a histogram displaying the importance value of each position is displayed at the top right of the panel. The importance value of a position is the range of the property over the R groups at that position, averaged over all other positions. For more detail on the property values for each R group at that position, click on the position and choose Show R Groups from the shortcut menu, to open the Importance Analysis panel (see Section 3.2 on page 13).

By default, the positions that are selected for the axes are those that have the greatest importance value. If you deselect Always show most important positions on x and y axes, the selection of positions for the axes does not change when you change the property or function.

This histogram can be used for selecting the positions, by clicking on a position and choosing Set as X Axis or Set as Y Axis from the shortcut menu. (It does not matter where you click on the plot: in the bar, above the bar, or on the label.) When you choose a new position, the R groups on the chosen axis are replaced with those for the new position, and the heat map is updated.

In the heat map, the top left cell of the table displays the core. Pausing the pointer above the core displays an enlarged image of the core in a tool tip. The rest of the first row displays the R groups at the position chosen for the x axis, and the rest of the first column displays the R groups at the position chosen for the y axis. You can adjust the size of the cells with the Cell size slider and text box, or you can ensure that the entire heat map is always visible by selecting Always fit to screen. To export an image of the heat map, click Export Image, and select the image format and name the file in the file selector that opens.

The remainder of the table displays the value of the selected property, evaluated over all R groups at the positions that are not selected for the two axes. If you click in a cell, the Structure panel opens, and allows you to display each of the structures represented in that cell, with the value of the property that is chosen for display in the heat map. Cells that do not have any structures are not colored, except when the number of structures is the property displayed.

The way in which the property value is displayed in the cells can be chosen from a range of possibilities, on the Cell display option menu:

- Values and colors—show the property value and the color.
- Cartwheels and colors—show a cartwheel colored by unique property values (see below), with the cell background colored by the average property value.
- Cartwheels only—show a "cartwheel" in which the sectors of the circle represent unique values of the property and are colored according to the property value.
- Values only—show the property value only.
- Colors only—show only the color corresponding to the property value.

When values are displayed, the number of structures for which the property is evaluated and the total number of structures for that cell are displayed in parentheses below the value.

You can configure the cell display by clicking Legend and Settings. In the Display Settings dialog box, you can set the number of decimals for the value and choose between floating point and scientific notation; you can adjust the range of values represented by the color ramp; and you can invert the ramp.

If you want to restrict the R groups that are included in the averaging of the property, or displayed on the axes, click in the histogram and choose Restrict structures. The Select R Groups panel opens, in which you can choose the position and select the R groups shown at that position, or to select all R groups at all positions. The heat map is updated when you make selections: for the displayed positions, rows or columns are removed from the table; for the undisplayed positions, the values of the properties are recomputed to reflect the selection.

#### 3.4 R-QSAR

If you want some idea of what kinds of groups are most important at each attachment position, you can generate a QSAR model. The QSAR model is built using counts of pharmacophore features present in the R groups at each position as the independent variables. The pharmacophore features are the standard features used in Phase QSAR models: hydrogen-bond acceptor (A), hydrogen-bond donor (D), hydrophobic (H), negatively-charged (N), positively-charged (P), and aromatic (R).

A partial-least-squares (PLS) procedure is used to fit the data, assigning 75% of the data to the training set and 25% to the test set at random. The fitting is repeated many times, each time picking the best model that does not overfit the data (which occurs when the standard deviation of the fit is smaller than the error in the property being fit). The mean of the coefficients from all of these trials is used to determine whether a feature at a given position contributes significantly to the property, either positively or negatively: if the absolute value of the mean is greater than the supplied cutoff, the contribution is considered significant.




Figure 6. The R-QSAR panel.




Figure 7. R-QSAR Summary dialog box.

When the calculation finishes, the attachment positions are labeled with a list of the six pharmacophore features, colored by significance: red for significant positive contributions, blue for significant negative contributions, and gray for insignificant contributions. If a pharmacophore feature is absent from an attachment position, a lower-case letter is used for the pharmacophore feature type.

#### To generate a QSAR model:

- Choose a property from the Property option menu.
   The number of structures that have this property is reported to the right.
- 2. Specify the error in the property in the Error box.
- 3. Specify the cutoff for significant contributions in the Importance cutoff box.
- 4. Click Start.

You can examine the data produced by the QSAR model by clicking Display Summary. In the panel that opens, for each pharmacophore type at each position, the minimum, maximum, mean, and standard deviation for the PLS coefficient is given, and the assessed effect on the activity is listed, as weak, positive, or negative. If you want a copy of this summary, click Export CSV in the R-QSAR panel, and name the file in the file selector that opens.

To save an image of the annotated core structure in PNG, TIFF, or JPEG format, click Export Image, and choose the image format and the file name in the file selector that opens.




Figure 8. The SAR Table panel.

#### 3.5 SAR Table

If you want to view the property values in tabular form along with the R groups, click SAR Table in the R-Group Viewer panel. The SAR Table panel shows the 2D structures of the cores, at the top, with the R groups and properties below. The attachment positions on the core structures have labels  $R_n$ , where n is the position index. You can change the size of the core structures with the Core Size slider and box.

The first column in the table is a structure index, and the second contains the name of the input structure. Next come the R groups for each position, labeled Rn, followed by the index of the core for each structure. Multiple cores can arise from the use of Canvas MCS methods that allow different atom or bond types to be treated as equivalent. The R groups can be viewed either as SMILES strings or as 2D structures. To change the representation, click View SMILES or View 2D Images. When you pause the pointer over a table cell, an enlarged image of the R group is displayed. To change the size of the structure, use the Structure cell size slider and box.




Figure 9. Select Properties dialog box.

Following the R groups and the core index are columns containing the index of the R-group families for each attachment position. An R-group family is a set of structures for which the R group varies at only one position. Each compound therefore only belongs to one such family at each position. The families are numbered in decreasing order of size. Sorting on one of these columns arranges the structures by family.

The remaining columns of the table list the property values for each structure. You can select the properties that are shown by clicking Select Properties, and choosing which properties to display in the dialog box that opens. You can click the column heading to sort the rows by a single property. If you want to sort by multiple properties, click Sort, and choose the properties and the order in which they are used in the Sort Multiple Columns dialog box.

You can limit the display to show only the selected structures, by making a selection and selecting Show selected structures. Rows can be selected with the usual shift-click and control-click for multiple row selection. To display all structures again, select Show all structures. To clear the row selection, click Clear Selection.

If you want to make a copy of the results, you can do so either in a CSV file or as an image. To export a CSV file, in which the input structures and the R groups are included as SMILES strings, click Export CSV. The SMILES string includes stereochemistry, and marks the attachment points with [Xe] and [Kr] (as the nominal capping group). The properties are exported for only the visible rows. To export an image, that contains the cores table and the main table (but not the controls), click Export Image. Both of these buttons open a file selector, in which you can navigate to a location and name the file. For images, the format is determined by the file extension.

# **Getting Help**

Information about Schrödinger software is available in two main places:

- The docs folder (directory) of your software installation, which contains HTML and PDF documentation. Index pages are available in this folder.
- The Schrödinger web site, <a href="http://www.schrodinger.com/">http://www.schrodinger.com/</a>, particularly the Support Center, <a href="http://www.schrodinger.com/supportcenter">http://www.schrodinger.com/supportcenter</a>, and the Knowledge Base, <a href="http://www.schrodinger.com/kb">http://www.schrodinger.com/supportcenter</a>, and the Knowledge Base, <a href="http://www.schrodinger.com/kb">http://www.schrodinger.com/supportcenter</a>, and the Knowledge Base, <a href="http://www.schrodinger.com/kb">http://www.schrodinger.com/supportcenter</a>, and the Knowledge Base, <a href="http://www.schrodinger.com/kb">http://www.schrodinger.com/supportcenter</a>,</a>

# **Finding Information in Maestro**

Maestro provides access to nearly all the information available on Schrödinger software.

#### To get information:

- Pause the pointer over a GUI feature (button, menu item, menu, ...). In the main window, information is displayed in the Auto-Help text box, which is located at the foot of the main window, or in a tooltip. In other panels, information is displayed in a tooltip.
  - If the tooltip does not appear within a second, check that Show tooltips is selected under General  $\rightarrow$  Appearance in the Preferences panel, which you can open with CTRL+, ( $\mathfrak{A}$ ,). Not all features have tooltips.
- Click the Help button in a panel or press F1 for information about a panel or the tab that is displayed in a panel. The help topic is displayed in your browser.
- Choose Help → Online Help or press CTRL+H (\mathbb{H}H) to open the default help topic in your browser.
- When help is displayed in your browser, use the navigation links or search the help in the side bar.
- Choose Help → Manuals Index, to open a PDF file that has links to all the PDF documents. Click a link to open the document.
- Choose Help → Search Manuals to search the manuals. The search tab in Adobe Reader opens, and you can search across all the PDF documents. You must have Adobe Reader installed to use this feature.

#### For information on:

- Problems and solutions: choose Help → Knowledge Base or Help → Known Issues → product.
- Software updates: choose Maestro → Check for Updates.
- New software features: choose Help → New Features.
- Scripts available for download: choose Scripts → Update.
- Python scripting: choose Help → Python Module Overview.
- Utility programs: choose Help → About Utilities.
- Keyboard shortcuts: choose  $\mathsf{Help} \to \mathsf{Keyboard}$  Shortcuts.
- Installation and licensing: see the *Installation Guide*.
- Running and managing jobs: see the *Job Control Guide*.
- Using Maestro: see the *Maestro User Manual*.
- Maestro commands: see the Maestro Command Reference Manual.

# **Contacting Technical Support**

If you have questions that are not answered from any of the above sources, contact Schrödinger using the information below.

E-mail: <u>help@schrodinger.com</u>

USPS: Schrödinger, 101 SW Main Street, Suite 1300, Portland, OR 97204

Phone: (503) 299-1150 Fax: (503) 299-4532

WWW: <a href="http://www.schrodinger.com">http://www.schrodinger.com</a>
FTP: ftp://ftp.schrodinger.com

Generally, e-mail correspondence is best because you can send machine output, if necessary. When sending e-mail messages, please include the following information:

- All relevant user input and machine output
- R-Group Analysis purchaser (company, research institution, or individual)
- Primary R-Group Analysis user
- Installation, licensing, and machine information as described below.

# **Gathering Information for Technical Support**

This section describes how to gather the required machine, licensing, and installation information, and any other job-related or failure-related information, to send to technical support.

#### For general enquiries or problems:

- 1. Open the Diagnostics panel.
  - Maestro: Help → Diagnostics
  - Windows: Start → All Programs → Schrodinger-2011 → Diagnostics
  - Mac: Applications → Schrodinger2011 → Diagnostics
  - Command line: \$SCHRODINGER/diagnostics
- 2. When the diagnostics have run, click Technical Support.

A dialog box opens, with instructions. You can highlight and copy the name of the file.

3. Attach the file specified in the dialog box to your e-mail message.

#### If your job failed:

1. Open the Monitor panel in Maestro.

Use Applications  $\rightarrow$  Monitor Jobs or Tasks  $\rightarrow$  Monitor Jobs.

2. Select the failed job in the table, and click Postmortem.

The Postmortem panel opens.

- 3. If your data is not sensitive and you can send it, select Include structures and deselect Automatically obfuscate path names.
- 4. Click Create.

An archive file is created in your working directory, and an information dialog box with the name of the file opens. You can highlight and copy the name of the file.

- 5. Attach the file specified in the dialog box to your e-mail message.
- 6. Copy and paste any log messages from the window used to start Maestro (or the job) into the email message, or attach them as a file.
  - Windows: Right-click in the window and choose Select All, then press ENTER to copy the text.
  - Mac: Start the Console application (Applications → Utilities), filter on the application that you used to start the job (Maestro, BioLuminate, Elements), copy the text.

#### If Maestro failed:

- 1. Open the Diagnostics panel.
  - Windows: Start → All Programs → Schrodinger-2011 → Diagnostics
  - Mac: Applications  $\rightarrow$  Schrodinger2011  $\rightarrow$  Diagnostics
  - Linux/command line: \$SCHRODINGER/diagnostics
- 2. When the diagnostics have run, click Technical Support.

A dialog box opens, with instructions. You can highlight and copy the name of the file.

- 3. Attach the file specified in the dialog box to your e-mail message.
- 4. Attach the file maestro error.txt to your e-mail message.

This file should be in the following location:

- Windows: %LOCALAPPDATA%\Schrodinger\appcrash
   (Choose Start → Run and paste this location into the Open text box.)
- Mac: Documents/Schrodinger
- **Linux:** Maestro's working directory specified in the dialog box (the location is given in the terminal window).
- 5. On Windows, also attach the file maestro.EXE.dmp, which is in the same location as maestro error.txt.

120 West 45th Street 17th Floor New York, NY 10036

155 Gibbs St Suite 430 Rockville, MD 20850-0353

Quatro House Frimley Road Camberley GU16 7ER United Kingdom

101 SW Main Street Suite 1300 Portland, OR 97204

Dynamostraße 13 D-68165 Mannheim Germany

8F Pacific Century Place 1-11-1 Marunouchi Chiyoda-ku, Tokyo 100-6208

Japan

245 First Street Riverview II, 18th Floor Cambridge, MA 02142

Zeppelinstraße 73 D-81669 München Germany

No. 102, 4th Block 3rd Main Road, 3rd Stage Sharada Colony Basaveshwaranagar Bangalore 560079, India

8910 University Center Lane Suite 270 San Diego, CA 92122

Potsdamer Platz 11 D-10785 Berlin Germany

SCHRÖDINGER.