# A Resolvent Framework for Global and Local Nonlinear Semigroups

### Patrick S. Mahon

### September 29, 2024

### Contents

Sy	ymbols	1
1	Definitions	2
2	Introduction 2.1 $C_t$ as a globally linear map	<b>2</b> 2
	$2.2  C_t^{\theta}$ as a locally linear map	3
<b>3</b>	One Parameter Semigroups	3
	3.1 $C_t$ as a one parameter semigroup	4
	3.2 $C_0$ -semigroup	4
	3.3 $C_0^n$ -semigroup	5
	3.3 $C_0^n$ -semigroup	5
4	Applications	6
	4.0.1 Factorization of $C_t^{\theta}$	6
	4.0.2 P <sub>U</sub> : The reverberation of $C_t^{\theta}$	7
	4.0.3 P <sub>\(\text{2}\)</sub> : The reverberative map of $C^{\text{\text{$\graphi$}}}_{\text{\text{$\graphi$}}}$	

## Symbols

 $X \qquad \qquad \text{Banach space } (X,||\cdot||)$   $w(x,x_t,\theta): X\times X\times \mathbb{R}\to \mathbb{R} \quad \text{Weighting kernel at } x_t \text{, parameterized by } \theta\in \mathbb{R}, x_t\in X$ 

### 1 Definitions

**Definition 1.** The process-t matrix, read "process until t matrix" or more simply "process until t", is

$$X_t = \begin{bmatrix} x_t \\ x_{t-h} \\ x_{t-2h} \\ \vdots \end{bmatrix}$$

where rows belong to X.

**Definition 2.** The t-weighting matrix of the process-i is given by

$$W(X_i, x_t, \theta) = \begin{bmatrix} w(x_j, x_t, \theta) & 0 & 0 & \cdots \\ 0 & w(x_{j-h}, x_t, \theta) & 0 & \cdots \\ 0 & 0 & w(x_{j-2h}, x_t, \theta) & \cdots \\ \vdots & \vdots & \vdots & \ddots \end{bmatrix}$$

 $W_t^{\theta} X_i$  is short hand for the product  $W(X_i, x_t, \theta) X_i$ 

$$W_t^{\theta} X_i := W(X_i, x_t, \theta) \cdot X_i = \begin{bmatrix} w(x_i, x_t, \theta) \cdot x_i \\ w(x_{i-h}, x_t, \theta) \cdot x_{i-h} \\ w(x_{i-2h}, x_t, \theta) \cdot x_{i-2h} \\ \vdots \end{bmatrix}$$

which is the t-weighting of the process-i.

### 2 Introduction

### 2.1 $C_t$ as a globally linear map

Consider the map

$$C: x_t \mapsto x_{t+h}$$

for  $x_i \in X_t \subset X$  and

$$x_{t+h} = Cx_t$$

C may be state dependent, C(x(t)), non-autonomous, C(t), or both, C(t, x(t)). We denote the possibility of any such case as  $C_t$ .

If  $C_t$  is globally linear then

$$X_{t+h} = X_t C_t$$

which is solved via,

$$C_t = X_t^{-1} X_{t+h}$$

In an applied time series setting this solution for  $C_t$  is the auto-regressive or AR model for the process  $X_t$ .

## 2.2 $C_t^{\theta}$ as a locally linear map

If C is not globally linear than the t-weighting can be introduced such that

$$W_t^{\theta} X_{t+h} = W_t^{\theta} X_t C_t^{\theta}$$

where the weighting kernel, w, of  $W_t^{\theta}$  is parameterized by  $\theta$ . The exact local weighting at  $x_t$  is achieved as,

$$\lim_{\theta \to \infty} w(x_i, x_t, \theta) = \delta(x_i - x_t)$$

for all  $x_i \in X_t$ . Typically the kernel is chosen so  $w \sim e^{-\theta}$ . The solution for  $C_t^{\theta}$  is

$$C_t^{\theta} = (W_t^{\theta} X_t)^{-1} W_t^{\theta} X_{t+h}$$
  
=  $X_t^{-1} (W_t^{\theta})^{-1} W_t^{\theta} X_{t+h}$ 

Taking the limit,  $W_t^{\theta}$  reduces to,

$$\lim_{\theta \to \infty} W_t^{\theta} = \begin{cases} \delta(x_i - x_t) = 1 & \text{if } i = j \land x_i = x_t \\ 0 & \text{if } i \neq j \lor x_i \neq x_t \end{cases}$$

which is a diagonal matrix whose only non-zero entries are 1's corresponding to states arbitrarily close to  $x_t$ . If  $X_t$  never returns to states arbitrarily close to  $x_t$  then  $W_t^{\theta}$  reduces to the rank-1 matrix with a single non-zero entry,

$$(W_t^{\theta})_{1,1} = 1$$

If  $X_t$  is periodic at frequency k the set of all indices i on the diagonal where  $(W_t^{\theta})_{i=j} = 1$ , is

$$\{W_t^{\theta}\}_1 = \{n \in \mathbb{N} : i = 1 + nk\}$$

If  $X_t$  is ergodic than the rank depends on the nature and frequency of close returns to neighbourhoods containing  $x_t$ , e.g.

$$U = \{x \in X, \delta = a \in \mathbb{R} : w(x, x_t, \theta) < \delta\}$$

could be used to define "close".

## 3 One Parameter Semigroups

Placing  $C_t^{\theta}$  in the theory of semigroups can help us understand the relationship between locality,  $\theta$ , and the potential higher order terms for some generating process of the elements of  $X_t$ . The study of one parameter semigroups provides useful tools that connect the operators which generate the semigroup to the semigroups themselves, by way of *generating theorems*. We start by generalizing  $C_t$  as a semigroup.

### 3.1 $C_t$ as a one parameter semigroup

We define  $C_t$ 

$$C(t): t \to \mathbb{G}$$
  $t \in \mathbb{R}_{\geq 0}$ 

where we take the group  $\mathbb{G}$  as  $\{X_t\}_{t\geq 0}$ 

$$C(t): t \to X_{t+h}$$
  $X_{t+h} \in X$ 

with  $(X, ||\cdot||)$  being Banach.

 $\{C(t)\}_{t>0}$  forms a one parameter semigroup if the the following requirements are met:

Associativity:

$$\forall t, s \ge 0 : C(t+s) = C(t)C(s) \tag{1}$$

Identity:

$$C(0) = I (2)$$

### 3.2 $C_0$ -semigroup

Continuity for one parameter semigroups are often defined by the following properties:

Strongly Continuous:

For the *infinitesimal generator*, A, defined on the domain D(A)

$$Ax = \lim_{t \to 0} \frac{1}{t} (C(t) - I)x \tag{3}$$

the limit must exist.

The strongly continuous one parameter semigroups is denoted as the  $C_0$ -semigroup. This semigroup provides a generalization of the exponential in the case where it is also uniformly continuous;

Uniform continuity:

$$\lim_{t\downarrow 0} ||C(t)x(0) - x(0)|| \to 0 \qquad \forall x(0) \in X$$
 (4)

The linear operator A is the infinitesimal generator of a uniformly continuous semigroup if and only if A is a bounded linear operator. In this case the infinitesimal generator A of the semigroup C(t) must satisfy

$$C(t) = e^{At} := \sum_{0}^{\infty} \frac{A^k}{k!} t^k$$

However if C(t) is strongly but not uniformly continuous then A is not bounded and  $e^{At}$  need not converge.

The  $C_0$ -semigroup provides a good, however insufficient, basis for understanding the relationships of locality and the higher order terms of the generator for  $X_t$ .

### 3.3 $C_0^n$ -semigroup

 $C_0$ -semigroup to be a special case of a more general strongly continuous one parameter semigroup, the nonlinear  $C_0^n$ -semigroup, whose infinitesimal generator expresses higher order effects in the limit of ever smaller finite differences.

We both guide and justify the definition such a semigroup on the basis that the exponential of the infinitesimal generator yields a well known generalization of the Taylor series that uses the infinitesimal limit of finite differences. This is the Hille series.

The upshot is that the  $C_0^n$ -semigroup and it's infinitesimal generator can carry intuition regarding continuity and nonlinearity over to pragmatic operator theory approaches, wherein we are better suited to investigate locality.

#### 3.3.1 The Hille Operator for nonlinear semigroups

We can relate the forward differences to the map of C where,

$$\Delta_h^1 x(t) = x(t+h) - x(t) = C_h^1 x(t) - x(t)$$

For higher order differences the difference operator series is

 $\Delta_h^n x(t) = \sum_{k=0}^n (-1)^{n-k} \binom{n}{k} x(t+kh)$   $= \sum_{k=0}^n (-1)^{n-k} \binom{n}{k} C_h^k x(t)$ (5)

If we define the n-order generator,

$$A_h^n = \frac{\Delta_h^n}{h^n}$$

The the *n*-order generators of the semigroup,  $A_h^n$ , describe higher-order terms of the expansion when viewed as finite-difference corrections to the first-order dynamics,  $A_h^1$ , capturing more detailed behavior of the system.

A semigroup can be defined over the sum of the n-order generators,

$$C_h(t) = e^{A_h t} := \sum_{n=0}^{\infty} \frac{t^n}{n!} A_h^n$$

$$:= \sum_{n=0}^{\infty} \frac{t^n}{n!} \frac{\Delta_h^n}{h^n}$$
(6)

In the limit of difference size h we get

$$\lim_{h \to 0^{+}} C_{h}(t) = \lim_{h \to 0^{+}} \sum_{n=0}^{\infty} \frac{t^{n}}{n!} \frac{\Delta_{h}^{n}}{h^{n}}$$

$$H(t) = \lim_{h \to 0^{+}} \sum_{n=0}^{\infty} \frac{t^{n}}{n!} \frac{\Delta_{h}^{n}}{h^{n}}$$

where we call H(t) the Hille operator. On application to x(t), this operator yields the Hille series expansion

$$H(t)x(t) = \lim_{h \to 0^+} \sum_{n=0}^{\infty} \frac{t^n}{n!} \frac{\Delta_h^n x(t)}{h^n}$$

Thus, the Hille Operator provides a way to generalize the semigroup dynamics to include higher-order effects via the Hille Series, defining a strongly and uniformly continuous one parameter nonlinear semigroup. We denote the order of the semigroup as  $C_0^n$ -semigroup. Where n is non finite we have the strongly nonlinear  $C_0^\infty$ -semigroup.

We can reintroduce (5) so,

$$H(t) = \lim_{h \to 0^{+}} \sum_{n=0}^{\infty} \frac{t^{n}}{n!} \frac{\Delta_{h}^{n}}{h^{n}}$$
$$= \lim_{h \to 0^{+}} \sum_{n=0}^{\infty} \frac{t^{n}}{n!} \frac{\sum_{k=0}^{n} (-1)^{n-k} \binom{n}{k} C_{h}^{k}}{h^{n}}$$

We can now reintroduce a parameterization of local dependencies to H(t). We have

$$x(t+kh) = C_h^k(t)x(t)$$

where

$$W_t^{\theta} X_{t+kh} = W_t^{\theta} X_t C_h^k(t)$$
$$X_t^{-1} W_t^{\theta-1} W_t^{\theta} X_{t+kh} = C_h^k(t)$$

Therefor

$$\begin{split} H(t) &= \lim_{h \to 0^+} \sum_{n=0}^{\infty} \frac{t^n}{n!} \frac{\sum_{k=0}^n (-1)^{n-k} \binom{n}{k} C_h^k}{h^n} \\ &= \lim_{h \to 0^+} \sum_{n=0}^{\infty} \frac{t^n}{n!} \frac{\sum_{k=0}^n (-1)^{n-k} \binom{n}{k} X_t^{-1} W_t^{\theta^{-1}} W_t^{\theta} X_{t+kh}}{h^n} \\ &= \lim_{h \to 0^+} X_t^{-1} W_t^{\theta^{-1}} W_t^{\theta} \sum_{n=0}^{\infty} \frac{t^n}{n!} \frac{\sum_{k=0}^n (-1)^{n-k} \binom{n}{k}}{h^n} X_{t+kh} \end{split}$$

## 4 Applications

#### 4.0.1 Factorization of $C_t^{\theta}$

Considering,

$$C_t^{\theta} = (X_t)^{-1} (W_t^{\theta})^{-1} (W_t^{\theta} X_{t+h}) \tag{7}$$

we take the pseudoinverse of the t-weighting,

$$(W_t^{\theta})^{-1} = (W_t^{\theta^T} W_t^{\theta})^{-1} W_t^{\theta^T}$$

and eigen decompose the covariance term and invert for

$$(W_t^{\theta})^{-1} = (Q_{\mathbf{w}_t} \Lambda_{\mathbf{w}_t}^{-1} Q_{\mathbf{w}_t}^T) W_t^{\theta^T}$$

We can perform the same operations for  $X_t$ ,

$$(X_t)^{-1} = (Q_{\mathbf{x}_t} \Lambda_{\mathbf{x}_t}^{-1} Q_{\mathbf{x}_t}^T) X_t^T$$

Substituting into (7) gives

$$C_{t}^{\theta} = (Q_{\mathbf{x}_{t}} \Lambda_{\mathbf{x}_{t}}^{-1} Q_{\mathbf{x}_{t}}^{T}) X_{t}^{T} \cdot (Q_{\mathbf{w}_{t}} \Lambda_{\mathbf{w}_{t}} Q_{\mathbf{w}_{t}}^{T}) W_{t}^{\theta^{T}} \cdot W_{t}^{\theta} X_{t+h}$$

$$= (Q_{\mathbf{x}_{t}} \Lambda_{\mathbf{x}_{t}}^{-1} Q_{\mathbf{x}_{t}}^{T}) X_{t}^{T} \cdot (Q_{\mathbf{w}_{t}} \Lambda_{\mathbf{w}_{t}}^{-1} Q_{\mathbf{w}_{t}}^{T}) \cdot (W_{t}^{\theta^{T}} W_{t}^{\theta}) \cdot X_{t+h}$$
(8)

where (·) is simply added for readability and is not the dot product.

### **4.0.2** P<sub>U</sub>: The reverberation of $C_t^{\theta}$

We refer to the covariance of the t-weighting as the **reverberation** of  $X_t$  at t.

$$P_U(X_t, t, \theta, \omega) = Cov(W_t^{\theta}) = W_t^{\theta T} W_t^{\theta}$$

where P is the Greek capital rho.

 $P_U(X_t, t, \theta, \omega)$  can be thought of as defining a fuzzy elliptic neighbourhood about  $x_t$  that describes close returns to  $x_t$ . It is "fuzzy" not in the set theoretic sense, although that could be an interesting extension, but for  $\theta < \infty$  all  $x \in X$  are included with some x having a greater weight than others.

For example, given the kernel

$$w \sim e^{-\theta||x-x_t||} \quad \theta \in \mathbb{R}$$

when  $\theta = 0$  all members of X are weighted equally where

$$W_t^0 = \begin{bmatrix} w(x_t, x_t, 0) & 0 & \dots \\ 0 & w(x_t, x_{t-h}, 0) & \dots \\ \vdots & \vdots & \ddots \end{bmatrix}$$
$$= \begin{bmatrix} 1 & 0 & \dots \\ 0 & 1 & \dots \\ \vdots & \vdots & \ddots \end{bmatrix}$$
$$= I$$

which gives us the global linear map

$$C_t^0 = (X_t)^{-1} (W_t^0)^{-1} W_t^0 X_{t_t+h}$$
$$= (X_t)^{-1} X_{t_t+h}$$

Conversely, in the  $\lim \theta \to \infty$  the only elements that are prominent members of the neighbourhood are those that can be made arbitrarily close;  $\epsilon - \delta$  reasoning clarifies.

We may define some small and bounded reverberative neighbourhood centered on  $x_t$ ,

$$\{x_i \in X : x_i \in U(x_t, \epsilon) \leftrightarrow ||x_i - x_t|| < \epsilon\}$$

whose members are prominent in  $x_t$ 's neighbourhood. For any  $\epsilon > 0$ , it can be shown there exists a  $\theta_0$  such that  $\forall \theta > \theta_0$  the reverberation of states  $x_j$  outside the bounded neighborhood  $U(x_t, \epsilon)$  are less participatory for some level  $\delta > 0$ 

$$\sup_{x_j \in U(x_t, \epsilon)} ||(W_t^{\theta^T} W_t^{\theta}) x_j|| < \delta$$

In all cases, in the limit we have  $w(x_i) = \delta(x_i - x_t)$  and the measure of the members comprising the reverberation collapses to 0.

$$\inf_{\theta \to \infty} \mu(\{x \in X : Px_i = 0\}) = 0$$

We assume the parties aren't very fun.

#### 4.0.3 $P_{\lambda}$ : The reverberative map of $C_t^{\theta}$

In 8, the modulating term of the reverberation is the inverse of the the reverberation,

$$P_{\lambda}(X_t, t, \theta, \omega) = Q_{\mathbf{w}_t} \Lambda_{\mathbf{w}_t}^{-1} Q_{\mathbf{w}_t}^T$$

which we refer to as the *reverberative map* of  $X_t$  at t. Here,  $Q_{\mathbf{w}_t}$  determines the directions in X along which  $X_t$  reverberates more or less strongly with  $\Lambda_{\mathbf{w}_t}$  corresponding to the magnitude of reverberation along such directions

Taking the inverse of the reverberation re-scales the eigenvalues by the reciprocal. The result is an amplification of the weakest effects of the reverberation and a reduction in the strongest.

The effect of the product of the reverberative map and the reverberation,

$$I = (Q_{\mathbf{w}_t} \Lambda_{\mathbf{w}_t}^{-1} Q_{\mathbf{w}_t}^T) (W_t^{0}^{-1} W_t^0)$$

ensures no one is left behind when placing greater emphasis on the more prominent members of the reverberative neighbourhood.