Lazy Foo' Productions

SDL Forums SDL Tutorials Articles OpenGL Forums



News

Os

Games

Contact

Donations

Mutexes and Conditions

Running producer and consumer...

Last Updated 6/14/15

Not only can you lock <u>critial sections</u> in threads, but with mutexes and conditions it is possible for threads to tell each other when to unlock.

```
//Our worker functions
int producer( void* data );
int consumer( void* data );
void produce();
void consume();
```

For this demo we'll have two threads: a producer which fills a buffer and a consumer that empties a buffer. Not only can the two threads not use the same buffer at the same time, but a consumer can't read from an empty buffer and a producer can't fill a buffer that's already full.

We'll use a mutex (mutually exclusive) to prevent the two threads from grabbing the same piece of data and conditions to let the threads know when they can consume and can produce.

```
//The protective mutex
SDL_mutex* gBufferLock = NULL;

//The conditions
SDL_cond* gCanProduce = NULL;
SDL_cond* gCanConsume = NULL;

//The "data buffer"
int gData = -1;
```

Here we're globally declaring the mutex and conditions that will be used by the threads.

```
bool loadMedia()
{
    //Create the mutex
    gBufferLock = SDL_CreateMutex();

    //Create conditions
```

```
gCanProduce = SDL_CreateCond();
gCanConsume = SDL_CreateCond();

//Loading success flag
bool success = true;

//Load splash texture
if( !gSplashTexture.loadFromFile( "49_mutexes_and_conditions/splash.png" ) )
{
    printf( "Failed to load splash texture!\n" );
    success = false;
}

return success;
}
```

To allocate mutexes and conditons we use <u>SDL CreateMutex</u> and <u>SDL CreateCond</u> respectively.

```
oid close()
 //Free loaded images
 gSplashTexture.free();
 //Destroy the mutex
 SDL_DestroyMutex( gBufferLock );
 gBufferLock = NULL;
 //Destroy conditions
 SDL_DestroyCond( gCanProduce );
 SDL DestroyCond( gCanConsume );
 gCanProduce = NULL;
 gCanConsume = NULL;
 //Destroy window
 SDL_DestroyRenderer( gRenderer );
 SDL_DestroyWindow( gWindow );
 gWindow = NULL;
 gRenderer = NULL;
 //Quit SDL subsystems
 IMG Quit();
 SDL_Quit();
```

And to deallocate mutexes and conditions we use SDL DestroyMutex and SDL DestroyCond.

```
int producer( void *data )
{
    printf( "\nProducer started...\n" );

//Seed thread random
    srand( SDL_GetTicks() );

//Produce
    for( int i = 0; i < 5; ++i )
{
        //Wait
        SDL_Delay( rand() % 1000 );

        //Produce
        produce();
    }

    printf( "\nProducer finished!\n" );
    return 0;
}

int consumer( void *data )
{
    printf( "\nConsumer started...\n" );
</pre>
```

```
//Seed thread random
srand( SDL_GetTicks() );

for( int i = 0; i < 5; ++i )
{
    //Wait
    SDL_Delay( rand() % 1000 );

    //Consume
    consume();
}

printf( "\nConsumer finished!\n" );

return 0;
}</pre>
```

So here are our two worker threads. The producer tries to produce 5 times and the consumer tries to consume 5 times.

```
oid produce()
 //Lock
 SDL_LockMutex( gBufferLock );
 //If the buffer is full
 if( gData != -1 )
   //Wait for buffer to be cleared
   printf( "\nProducer encountered full buffer, waiting for consumer to empty buffer...\n" );
   SDL_CondWait( gCanProduce, gBufferLock );
 //Fill and show buffer
 gData = rand() % 255;
 printf( "\nProduced %d\n", gData );
 //Unlock
 SDL_UnlockMutex( gBufferLock );
 //Signal consumer
 SDL_CondSignal( gCanConsume );
oid consume()
 //Lock
 SDL_LockMutex( gBufferLock );
 //If the buffer is empty
 if( gData == -1 )
   //Wait for buffer to be filled
   printf( "\nConsumer encountered empty buffer, waiting for producer to fill buffer...\n" );
   SDL_CondWait( gCanConsume, gBufferLock );
 //Show and empty buffer
 printf( "\nConsumed %d\n", gData );
 gData = -1;
 //Unlock
 SDL_UnlockMutex( gBufferLock );
 //Signal producer
 SDL CondSignal( gCanProduce );
```

Here are the functions that produce and consume. Producing a buffer means generating a random number and consuming a buffer mean reseting the generated number. The best way to show how this works is go through an example.

Let's say the producer fires first and locks the mutex with <u>SDL_LockMutex</u> much like it would a semaphore with a value of one:



Consumer

```
SDL_mutexP( gBufferLock );
if( gData != -1 )
{
     SDL_CondWait( gCanProduce, gBufferLock );
}
gData = rand() % 255;
SDL_mutexV( gBufferLock );
SDL_CondSignal( gCanConsume );
```

```
SDL_mutexP( gBufferLock );

if( gData == -1 )
{
         SDL_CondWait( gCanConsume, gBufferLock );
}

gData = -1;

SDL_mutexV( gBufferLock );

SDL_CondSignal( gCanProduce );
```

The buffer is empty so it goes through and produces:

Producer

Consumer

```
SDL_mutexP( gBufferLock );
if( gData != -1 )
{
    SDL_CondWait( gCanProduce, gBufferLock );
}
gData = rand() % 255;
SDL_mutexV( gBufferLock );
SDL_CondSignal( gCanConsume );
```

```
SDL_mutexP( gBufferLock );

if( gData == -1 )
{
      SDL_CondWait( gCanConsume, gBufferLock );
}

gData = -1;

SDL_mutexV( gBufferLock );

SDL_CondSignal( gCanProduce );
```

It then exits the function to unlock the critical section with <u>SDL_UnlockMutex</u> so the consumer can consume:

```
SDL_mutexP( gBufferLock );

if( gData != -1 )
{
         SDL_CondWait( gCanProduce, gBufferLock );
}

gData = rand() % 255;

SDL_mutexV( gBufferLock );

SDL_CondSignal( gCanConsume );
```

Consumer

```
SDL_mutexP( gBufferLock );
if( gData == -1 )
{
        SDL_CondWait( gCanConsume, gBufferLock );
}
gData = -1;
SDL_mutexV( gBufferLock );
SDL_CondSignal( gCanProduce );
```

Ideally, we would want the consumer to consume, but imagine if the producer fired again:

Producer

Consumer

```
SDL_mutexP( gBufferLock );

if( gData != -1 )
{
      SDL_CondWait( gCanProduce, gBufferLock );
}

gData = rand() % 255;

SDL_mutexV( gBufferLock );

SDL_CondSignal( gCanConsume );
```

```
SDL_mutexP( gBufferLock );

if( gData == -1 )
{
     SDL_CondWait( gCanConsume, gBufferLock );
}

gData = -1;

SDL_mutexV( gBufferLock );

SDL_CondSignal( gCanProduce );
```

And after the producer locked the critical section the consumer tries to get it but the critical section is already locked to the producer:

Consumer

```
SDL_mutexP( gBufferLock );
if( gData != -1 )
{
     SDL_CondWait( gCanProduce, gBufferLock );
}
gData = rand() % 255;
SDL_mutexV( gBufferLock );
SDL_CondSignal( gCanConsume );
```

With just a binary semaphore, this would be a problem because the producer can't produce into a full buffer and the consumer is locked behind a mutex. However, mutexes have the ability to be used with conditions.

What the condition allows us to do is if the buffer is already full, we can wait on a condition with <u>SDL_CondWait</u> and unlock the mutex for other threads:

Producer

```
SDL_mutexP( gBufferLock );
if( gData != -1 )
{
        SDL_CondWait( gCanProduce, gBufferLock );
}
gData = rand() % 255;
SDL_mutexV( gBufferLock );
SDL_CondSignal( gCanConsume );
```

Consumer

```
SDL_mutexP( gBufferLock );
if( gData == -1 )
{
     SDL_CondWait( gCanConsume, gBufferLock );
}
gData = -1;
SDL_mutexV( gBufferLock );
SDL_CondSignal( gCanProduce );
```

Now that the consumer is unlocked it can go through and consume:

Consumer

```
SDL_mutexP( gBufferLock );
```

```
if( gData != -1 )
{
    SDL_CondWait( gCanProduce, gBufferLock );
}
gData = rand() % 255;
SDL_mutexV( gBufferLock );
SDL_CondSignal( gCanConsume );
```

```
SDL_mutexP( gBuff<mark>er</mark>Lock );
```

```
if( gData == -1 )
{
     SDL_CondWait( gCanConsume, gBufferLock );
}
gData = -1;
SDL_mutexV( gBufferLock );
SDL_CondSignal( gCanProduce );
```

And once it's done it signals the producer with <u>SDL_CondSignal</u> to produce again:

Producer

```
SDL_mutexP( gBufferLock );
if( gData != -1 )
{
     SDL_CondWait( gCanProduce, gBufferLock );
}
gData = rand() % 255;
SDL_mutexV( gBufferLock );
SDL_CondSignal( gCanConsume );
```

Consumer

```
SDL_mutexP( gBufferLock );
if( gData == -1 )
{
     SDL_CondWait( gCanConsume, gBufferLock );
}
gData = -1;
SDL_mutexV( gBufferLock );
SDL_CondSignal( gCanProduce );
```

And then it can continue through:

Consumer

```
SDL_mutexP(gBufferLock);

if(gData != -1) {
    SDL_CondWait(gCanProduce, gBufferLock);
}

gData = rand() % 255;

SDL_mutexV(gBufferLock);

SDL_mutexV(gBufferLock);

SDL_condSignal(gCanConsume);

SDL_CondSignal(gCanProduce);
```

With the critical section protected by a mutex and the ability of the threads to talk to each other, the worker threads will work even through we do not know in which order they will execute.

Download the media and source code for this tutorial here.

Back to SDL Tutorials



Copyright Lazy Foo' Productions 2004-2015