# **PONDICHERRY UNIVERSITY**

(A Central university)



# SCHOOL OF ENGINEERING AND TECHNOLOGY DEPARTMENT OF COMPUTER SCIENCE

**M.Sc. Computer Science** 

NAME : GUGULOOTH POOJITHA

REG. NO. : 23370023

SEMESTER : 3<sup>rd</sup> Semester

SUBJECT : CSSC 513 - WEB TECHNOLOGY AND COMPUTER NETWORKS

LAB

# **PONDICHERRY UNIVERSITY**

(A Central university)



# SCHOOL OF ENGINEERING AND TECHNOLOGY DEPARTMENT OF COMPUTER SCIENCE

M.Sc. Computer Science

PRACTICAL LAB RECORD

#### **BONAFIDE CERTIFICATE**

This is to certify that this is a Bonafide record of practical work done by **GUGULOOTH POOJITHA**, having Reg. No. **23370023** semester - III from the month July 2024 to December 2024.

**FACULTY IN-CHARGE** 

SUBMITTED FOR THE PRACTICAL EXAM HELD ON:

**INTERNAL EXAMINER** 

**EXTERNAL EXAMINER** 

# **NETWORKTOPOLOGY**

**AIM:** To configure a basic Network Topology using Cisco Packet Tracer.

#### PROCEDURE:

#### 1. Place the devices:

- From the **Devices menu**, select **Routers** and choose the **1841 Router**.
   Place it in the center.
- Go to **Switches**, select two **2960 switches**, and place them on the left and right of the router.
- From **End Devices**, select **PC** and place three PCs connected to the left switch and three PCs connected to the right switch.

#### 2. Configure Connections:

- Router to Switches:
  - o Use the **Copper Straight-Through Cable** tool to connect:
    - **Router FastEthernet0/0** to **Switch0 FastEthernet0/1** (left switch).
    - **Router FastEthernet0/1** to **Switch1 FastEthernet0/1** (right switch).
- Switches to PCs:
  - o For Switch0, connect each of its FastEthernet ports (e.g., FastEthernet0/2, FastEthernet0/3, and FastEthernet0/4) to PC0, PC1, and PC2.
  - For Switch1, connect its FastEthernet ports (e.g., FastEthernet0/2, FastEthernet0/3, and FastEthernet0/4) to PC3, PC4, and PC5.

#### 3. Configure IP Addresses:

- Router Interfaces:
  - o Click on **Router0**, go to **Config > FastEthernet0/0**, and set:

■ **IP Address:** 192.168.10.1

■ **Subnet Mask:** 255.255.255.0

■ **Turn on** the interface by clicking on **Port Status**.

o Go to **FastEthernet0/1** and set:

■ **IP Address:** 192.168.11.1

■ **Subnet Mask:** 255.255.255.0

■ **Turn on** the interface by clicking on **Port Status**.


• PCs:

- o For **PC0**, **PC1**, and **PC2** (connected to the left switch):
  - Set IP addresses within the 192.168.10.0 network (e.g., 192.168.10.2, 192.168.10.3, 192.168.10.4) with a **Subnet Mask** of 255.255.255.0.
  - Set the **Default Gateway** to 192.168.10.1.
- o For **PC3**, **PC4**, and **PC5** (connected to the right switch):
  - Set IP addresses within the 192.168.11.0 network (e.g., 192.168.11.2, 192.168.11.3, 192.168.11.4) with a **Subnet Mask** of 255.255.255.0.
  - Set the **Default Gateway** to 192.168.11.1.

# 4. Test Connectivity:

• Use the **Ping Tool** from **PC0** to **PC3** (or any PC on a different subnet) to verify connectivity.

# **DIAGRAM:**



# **RESULT**:

Thus the configuration of the basic Network Topology is successfully pings indicate proper configuration and connectivity between the subnets.

# **VLAN**

#### AIM:

To configure VLANs on a switch and router in Cisco Packet Tracer to enable communication between devices in different VLANs through inter-VLAN routing.

#### **PROCEDURE:**

#### **Step 1: Set Up the Devices**

- Place the **Router**, **Switch**, and **PCs** in the workspace.
- Connect the **Router to the Switch** using a cross-over cable from **Router FastEthernet0/0** to **Switch FastEthernet0/20**.
- Connect each **PC** to the Switch:
  - o PC1 and PC2 will be in VLAN 10 (connect to any ports like Fa0/1 and Fa0/2).
  - o PC3 and PC4 will be in VLAN 20 (connect to any ports like Fa0/3 and Fa0/4).

#### Step 2: Configure VLANs on the Switch

#### 1. Access the Switch CLI:

o Click on the switch, go to the **CLI** tab.

## 2. Enter Configuration Mode:

config# enable

config# configure terminal

#### 3. Create VLANs:

#### o VLAN 10:

config# vlan 10

config# name

VLAN10 config# exit

#### o VLAN 20:

config# vlan 20

config# name

VLAN20 config# exit

## 4. Assign Ports to VLANs:

## o For VLAN 10 (PC1 and PC2):

config# interface FastEthernet0/1
config# switchport mode access
config# switchport access vlan 10
config# exit
config# interface FastEthernet0/2
config# switchport mode access
config# switchport access vlan 10
config# exit

# o For **VLAN 20 (PC3 and PC4)**:

config# interface FastEthernet0/3
config# switchport mode access
config# switchport access vlan 20
config# exit
config# interface FastEthernet0/4
config# switchport mode access
config# switchport access vlan 20
config# exit

# 5. Configure the Trunk Port:

o Set the port connected to the router as a trunk port (e.g., FastEthernet0/20).

config# interface FastEthernet0/20
config# switchport mode trunk
config# exit

## Step 3: Configure the Router for Inter-VLAN Routing

#### 1. Access the Router CLI:

o Click on the router, go to the **CLI** tab.

## 2. Enter Configuration Mode:

config# enable

config# configure terminal

# 3. Configure Subinterfaces for Each VLAN:

o Subinterface for VLAN 10:

config# interface FastEthernet0/0.10

config# encapsulation dot1Q 10

config# ip address 192.168.1.100

255.255.255.0 config# exit

o Subinterface for VLAN 20:

config# interface FastEthernet0/0.20

config# encapsulation dot1Q 20

config# ip address 192.168.2.100

255.255.255.0 config# exit

#### 4. Enable the Main Interface:

o Make sure the main interface **FastEthernet0/0** is

up. config# interface FastEthernet0/0

config# no shutdown

config# exit

## **Step 4: Configure IP Addresses on PCs**

• For **PC1 (VLAN 10)**:

o IP Address: 192.168.1.1

o Subnet Mask: 255.255.255.0

o Default Gateway: 192.168.1.100

For PC2 (VLAN 10):

o IP Address: 192.168.1.2

o Subnet Mask: 255.255.255.0

o Default Gateway: 192.168.1.100

• For **PC3 (VLAN 20)**:

o IP Address: 192.168.2.1

o Subnet Mask: 255.255.255.0

o Default Gateway: 192.168.2.100

• For **PC4 (VLAN 20)**:

o IP Address: 192.168.2.2

o Subnet Mask: 255.255.255.0

o Default Gateway: 192.168.2.100


# **Step 5: Test Connectivity**

• **Ping** from PC1 to PC2 within VLAN 10 (should succeed).

• **Ping** from PC3 to PC4 within VLAN 20 (should succeed).

• **Ping** between PCs in different VLANs (e.g., PC1 to PC3) to verify inter-VLAN routing (should also succeed).

#### **DIAGRAM:**



## **RESULT:**

Thus the configuration of VLAN is successfully done and the ping from one PC to other PCs is verified.

# **FIREWALL**

AIM:

To setup an network based firewall using Cisco Packet Tracer.

#### **PROCEDURE:**

# Step 1: Replace Router\_A with Firewall\_1

- a. Remove **Router\_A** and replace it with **Firewall\_1**.
- **b.** Connect the **FastEthernet 0/0** interface on **Firewall\_1** to the **FastEthernet 0/1** interface on **Switch A**.

Connect the **FastEthernet 0/1** interface on **Firewall\_1** to the **Ethernet 6** interface of the **ISP cloud**.

(*Use straight-through cables for both connections.*)

- **c.** Confirm that the host name of **Firewall\_1** is **Firewall\_1**.
- **d.** On **Firewall\_1**, configure the WAN IP address and subnet mask for the **FastEthernet 0/1** interface as **209.165.200.225** and **255.255.255.224**.
- **e.** Configure the LAN IP address and subnet mask for the **FastEthernet 0/0** interface on **Firewall\_1** as **192.168.1.1** and **255.255.25.0**.

# Step 2: Verify the Firewall\_1 Configuration

• **a.** Use the **show run** command to verify your configuration. This is a partial example of the output:

```
Firewall_1#show run

Building configuration...

hostname Firewall_1
!

interface FastEthernet0/0

ip address 192.168.1.1 255.255.255.0

ip nat inside

duplex auto

speed auto
!

interface FastEthernet0/1
```

```
ip address 209.165.200.225 255.255.255.224
 ip access-group 100 in
 ip nat outside
 duplex auto
 speed auto
interface
 Vlan1 no ip
 address
 shutdown
!
ip nat inside source list 1 interface FastEthernet0/0 overload
ip classless
ip route 192.168.2.0 255.255.255.0 192.168.1.2
ip route 192.168.3.0 255.255.255.0 192.168.1.3
!
access-list 1 permit 192.168.0.0 0.0.255.255
access-list 100 deny ip any host
209.165.200.225
<output omitted>
!
end
```

• **b.** From **PC\_B**, ping **209.165.200.225** to verify that the internal computer can access the Internet.

```
PC>ping 209.165.200.225

Pinging 209.165.200.225 with 32 bytes of data:

Reply from 209.165.200.225: bytes=32 time=107ms TTL=120

Reply from 209.165.200.225: bytes=32 time=98ms TTL=120

Reply from 209.165.200.225: bytes=32 time=104ms TTL=120
```

Reply from 209.165.200.225: bytes=32 time=95ms TTL=120

Ping statistics for 209.165.200.225:


Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds: Minimum

= 95ms, Maximum = 107ms, Average = 101ms

• **c.** From privileged EXEC mode on **Firewall\_1**, save the running configuration to the startup configuration using the **copy run start** command.

#### **DIAGRAM:**



#### **RESULT:**

Hence, the firewall setup is configured within the network interface.

# **ROUTER CONFIGURATION**

#### AIM:

Basic configuration of Router using Cisco Packet Tracer.

#### PROCEDURE:

#### 1. Place the Router:

 From the Devices menu, go to Routers and select a router model (e.g., 1841 Router). Place it on the workspace.

#### 2. Add Network Devices (Optional):

• Add switches and PCs if you want to connect multiple devices to the router, creating different networks or subnets.

#### 3. Connect Devices:

- Use Copper Straight-Through Cable to connect the router to other devices.
- Connect **Router's FastEthernet or GigabitEthernet ports** to the switches or directly to PCs, depending on the setup.

## 4. Enter Router Configuration Mode:

- Click on the router, then go to the CLI (Command Line Interface) tab.
- When prompted, type no if it asks if you want to enter the initial configuration dialog.

#### 5. Access the Router's Global Configuration Mode:

- Type enable to enter **privileged EXEC mode**.
- Type configure terminal to enter **global configuration mode**.

#### **6.** Configure Router Interfaces:

 Enter interface configuration mode for each interface you want to configure:

#### o For FastEthernet0/0:

config# interface FastEthernet0/0

o Set the IP address and subnet mask:

config# ip address 192.168.10.1 255.255.255.0

o Turn on the interface:

config# no shutdown

o Exit the interface configuration:

config# exit

• Repeat the process for **FastEthernet0/1** (or any other

```
interface): config# interface FastEthernet0/1
config# ip address 192.168.11.1 255.255.255.0
config# no shutdown
config# exit
```

## 7. Configure Routing (Optional, if using multiple networks):

• For **static routing**, type:

config# ip route 192.168.11.0 255.255.255.0 192.168.10.2

• This step is optional if you only need basic routing between directly connected networks.

#### **8.** Save the Configuration:

- To save the configuration, exit global configuration mode by typing exit until you return to the privileged EXEC mode.
- Type:


config# write memory

• Alternatively, use copy running-config startup-config to save the configuration to non-volatile memory.

## 9. Test Connectivity:

- Connect PCs to the router via switches or directly.
- Assign IP addresses and default gateways to each PC in their respective network.
- Use the **Ping Tool** to test communication between devices in different networks.

# **DIAGRAM**:



# **RESULT**:

The basic router configuration is made using PCs, Switches and Router which connects all seamlessly.