Anandha Gopalan

(with the pks to D. Rueckert, P. Pietzelch A. Tannerhaum and axgopala@imperial.ac.uk

Add WeChat powcoder

Allocation of dedicated devices

Explosite to the Explosite terms of the policy conditions of the policy conditions of the policy of

Provide uniform simple view of I/O

- Hide complexity of device handling wooder

Block Devices

Stores information in fixed-size Assignment Project Exam Transfers are in units of entire blocks character perices powcoder.com Buffer Cache Delivers or accepts stream of Character Block characters, without regard to power the character block structure echat power terms.

 Not addressable, does not have any seek operation

How does the OS actually communicate with the hardware?

CPU and **Devices** Communication

Each <u>hardware controller</u> has a few registers used for communication with the CPU

Assignment Project Exam Help

- Deliver data
- : http://powcoder.com
- Perform some action

OS carrendo me estrate po estrate

- State of the device
- Whether it is ready to accept commands
- ...

I/O Software

Device independence from

Assignment g. Register Exam Help

Uniform naming \to name of a file should be a string or integer and not depend on the device in any way

Devications://powcoder.com


- Unit of data transfer: character or block
- Supported operations: e.g. read, write, seek
- Madus Wsedrohatepowcoder
- Speed differences
- Sharable (e.g. disks) or single user (e.g. printer, DVD-RW)
- Error handling
- Buffering


Interrupt Driven I/O

https://powcoder.com

Example of Province Charles powered at power and province Charles and province Charles are provinced at power and provinced at power and provinced at power and provinced at power and provinced at power at power

Programmed I/O





The connections between the devices and the interrupt controller actually use interrupt lines on the bus rather than dedicated wires


```
copy_from_user (buffer, p, count);
enable_interrupts ();
while (*printer_status_reg != READY);
ASSignature ();
Help
```

Code executed at the time the print system call is made

intensity powcoder.com
unblock_user ();
} else {
 printer_data_register = p[i];
 Audi = court - C. Lat powcoder
 i++;
}
acknowledge_interrupt ();
return_from_interrupt ();

Interrupt service procedure for the printer

Direct Memory Access (DMA)




Operation of a DMA transfer


Assignment Pfer pecune count am Help scheduler ();

https://powcoder.com

```
acknowledge_interrupt ();
unblock_user ();
result powcoder
```

Interrupt service procedure







- 2 Driver blocks itself doing down on a semaphore, a wait on a contition sariable process contenting similar.
- When interrupts happens, the interrupt procedure does whatevedt has vow order to hand the Weer of CET
- Then it will unblock the driver that started it

Device Drivers

Device-specific code for controlling an I/O device

A driver for a mouse differs from a driver for a HDD

Assignmente, Projecti Excamellelp

Part of kernel → a buggy driver can cause crash of the system

Position of the system controllers

Part of kernel → a buggy driver can cause crash of the system cause crash of the system controllers.

Most OSs define a standard interface (between OS and the driver) for blood revices and the driver) Must be flexible and be able to handle errors, several interrupts, etc.

Allowed to call only a handful of system calls, e.g. to allocate memory for a buffer


Device-Independent I/O Software

Some parts are device-specific but others are device independent

ssignmenta Projecte Exame vi Help independent software and varies between OSs

Most common devide/independent functions COM

- Uniform interfacing for device drivers
- Buffering
- Exercitative Chat powcoder
 Allocating and releasing dedicated devices
- Providing a device-independent block size



Add We Chat powcoder

- (a) Without a standard driver interface
- (b) With a standard driver interface

Uniform Interfacing for Device Drivers II

Interface between the driver and OS is defined

OS can install new driver easily and the writer of the driver knows what it can expect from the OS

SSIGNMENTS Projectic Extame Help

small number of device types

For each class of devices (e.g. disks or printers) the OS defines a set of function that the driver public coder.com


Often the driver contains a table with pointers into itself for these functions

OS records the iddless of the talle when the driver is loaded ind makes indirect calls what this table

Another aspect of having a uniform interface is how I/O devices are named: each device has a major device number and minor device number

Closely related to naming is protection \to devices appear as files in the file system, so usual protection rules could be used

Buffering I



- (b) Buffering in user space
- (c) Buffering in the kernel followed by copying to user space
- (d) Double buffering in the kernel

Buffering II


Ways to handle data streams from I/O devices

Assignment space of the buffer is full. What happens if the buffer is paged out when a character arrives?

then copies data to user's space. What happens it a character arrives at the time when the buffer is being copied to user's space?

Aprole buffering Chat powcoder

 \bullet Buffering is also important for output \to e.g. when sending data over a slow telephone line



Networking may involve multiple copies of a packet

Error Reporting

Errors are far more common in the context of I/O than in other contexts

A Systygring an expersperical mest be langed by appropried policy but the framework for error handling is device independent

Classes of errors

• Intensity of the party of the

Actual 1/0 errors — write to a disk block that has been damaged or read from a camera that is turned off

 Solution → it is up to the driver to decide what to do, whether to try to solve the problem or report back the error code

It is up to the device-independent software to hide this fact and provide trips: block with the left. Com

Some devices deliver data one byte at a time (e.g. modems), while others deliver theirs in larger units (e.g. network interfaces)

Add WeChat powcoder

Imperial College London

User-Space I/O Software I

Most of the I/O software is within the OS

A SSAIL OCTION TEST STATE OF THE CORE OF THE PROPERTY OF THE P

Example -> count = write (fd, buffer, nbytes) | https://powcoder.com

Procedure puts parameters in the appropriate place for the system call

Other produces MY & Ctuhatk: power of effing

Not all user-level I/O software consists of library procedures \rightarrow another important category is the spooling system

User-Space I/O Software II

Some devices, such as CD-ROM recorders, can be used only by a single process at any given moment and cannot be shared


Assignment Project Exam Help

Spool to intermediate medium (disk file)

Spooling is a way of dealing with dedicated I/O devices in a multiple of the page system WCOCET.COM

Spooled devices (e.g. printers)

- Printer output saved to disk file
- Add Weshatmowcoder
 - Printer only allocated to spooler daemon
 - No normal process allowed direct access
 - Provides sharing of non-sharable devices
 - ullet Reduces I/O time o gives greater throughput



Layers of the I/O system and the main functions of each layer

Loadable kernel modules provide device drivers

Assignimiented Projection Exam Help

- Provided by hardware vendors or independent developers
- Require high respective coder.com
 Modules written for different kernel versions may not work

*Kernel subsystem managing modules without user intervention

- Determines module dependencies
- Loads modules on demand

Every LKM consists of two basic functions (minimum)

```
Assignment Projecte Exam Help

int Ent module (void) {

https://powcoder.com

void cleanup module (void) {

Add WeChat powcoder

Add WeChat powcoder
```

Load module by using the insmod command \rightarrow normally restricted to root

Kernel provides common interface for I/O system calls

Assignment Project Exam Help

- Members of each device class perform similar functions
- Allows kernel to address performance needs of certain devices at the series of period of the series of the serie

Major and minor identification numbers

- · Addavi Wie to hearty province oder
- Devices with same major number controlled by same driver
- Minor numbers enable system to distinguish between devices of same class

Most devices represented by device special files

Device files accessed via virtual file system (VFS) (/dev)

SSI Systemmall exprest to Prophic in turn issues gath no design properties of the pr

Hardware

e.g. read, write, seek

List of devices in system of the control of the con

ightarrow retrieving status information from printer

Add We chat powcoder

| dev/mouse | dev/cdrom | dev/console | Virtual file system |
| Bus mouse | Generic | Generic

I/O subsystem overview

Character Device

Assignmentsteroject Exam Help Represented by device_struct structure, which contains


- - Driver name

https://powcoder.com

All registered drivers referenced by chrdevs vector

Add We Chat powcoder Maintains operations supported by device driver

- Stores functions called by VFS when system call accesses device special file



 Modularise block I/O operations by placing common code in ach layer https://powcoder.com

Two primary strategies used by kernel to minimise amount of time spent accessing block devices

- . Add WeChat powcoder
- Clustering I/O operations

Otherwise, typically added to request queue

https://powcoder.com

- Driver bypasses kernel cache when accessing device
- In portant for caraba es and other applications of carrier caching mappropriate and may reduce performance/consistency

Character (unstructured) File and devices Pipes (message) POWCOder.com
Interprocess communication Socket (message) Network interface

Add WeChat powcoder

- Opens file for reading/writing
- fd is the index to the file descriptor
- · https://powcoder.com

```
fd = open (filename, mode)
```

· Mdd Wedhatepwwwcoder

```
close (fd)
```

- Read numbytes from file or device referenced by fd into memory buffer
- · https://powwoodeir.comead

numbyteswritten = write (fd, buffer, numbytes)

- · Mitadeby Wie Cremated power one Prifer
- Returns number of bytes actually written in numbytesread

```
pipe (&fd[2])
```

Assignment in Perojector Expans Help

```
newf he dup (oldfd), dup2 (oldfd newfd)

Duplicate file desgriptor


Duplicate file desgriptor
```

```
ioctl (fd, operation, &termios)
```

• Isatt dent Weeks: naterpown Gode Tirol chars

```
fd = mknod (filename, permission, dev)
```

• Creates new special file e.g. character or block device



By default, all three file descriptors refer to terminal from which program was started

Blocking I/O

Assignment Project Exam Help

- Process suspended → I/O appears "instantaneous"
- Easy to understand but leads to multi-threaded code https://powcoder.com

Non-blocking I/O

- I/O call returns as much as available (e.g. read with 0 bytes)
- · Add five that topowcoder
- Provides application-level polling for I/O

Asynchronous I/O

Process executes in parallel with I/O operation

Assignment Project Exam Help

I/O subsystems notifies process upon completion process upon completion process signal, other processing check/www.ife-O operation processing check/www.ife-O operation processing completed

Very flexible and efficient

Harder to use and potentially less secure