Instruction Representation

Assignment Project Exam Help

https://powcoder.com

Add WeChat powcoder

Review (1/2)

- ° Logical and Shift Instructions
 - Operate on bits individually, unlike arithmetic, which operate on entire word.
 - Use to isolate fields, either by masking or by shifting back and forth.
 - · Use shift leftplogreat, ser powers of 2 multiplication by powers of 2
 - shift right arithmetic, sra, close but wrong for divide by powers of 2 (negative numbers get wrong result: e.g., -5 sra 2 bits = -2 vs. -5 / 2² = -5 / 4 = -1)
- New Instructions: and, andi, or, ori, sll, srl, sra

Review (2/2)

- ° MIPS Signed v. Unsigned is an "overloaded" term
 - Do/Don't sign extend
 (lb, lbu) Ssignment Project Exam Help
 - · Don't overflow (addu, addiu, subu, multu, divu)
 - · Do signed/unsigned compare (slt,slti/sltu,sltiu)

Overview

- Big idea: stored program
 - consequences of stored program
- * MIPS instruction format for Add instructions and Project Exam Help
- ° MIPS instruction format for Immediate, Data transferdinstructions on State of the Control of t

Big Idea: Stored-Program Concept

- ° Computers built on 2 key principles:
 - 1) Instructions are represented as numbers.
 - 2) Therefore, entire programs can be stored interprocyclocbe read or written just like numbers (data).
- ° Simplifies SW/HW of computer systems:
 - Memory technology for data also used for programs

Consequence #1: Everything Addressed

- Since all instructions and data are stored in memory as numbers, everything has a memory address: instructions, data words
 - both branches and jumps use these Assignment Project Exam Help
- ° C pointers are just memory addresses: they can point to anything in memory
 - · Unconstrained use of addresses can lead to nasty bugs; up to you in C; limits in Java
- One register keeps address of instruction being executed: "Program Counter" (PC)
 - Basically a pointer to memory: Intel calls it Instruction Address Pointer, a better name

Consequence #2: Binary Compatibility

- Programs are distributed in binary form
 - Programs bound to specific instruction set
 - Different version for Macintosh and IBM PC
- New machines want to Fran blb programs ("binaries") as well as programs compiled to new instructions
- Chat powcoder Leads to instruction set evolving over time
- Selection of Intel 8086 in 1981 for 1st IBM PC is major reason latest PCs still use 80x86 instruction set (Pentium 4); could still run program from 1981 PC today

Instructions as Numbers (1/2)

- ° Currently all data we work with is in words (32-bit blocks):
 - Each register is a word.
 - 1w and signouth access memory one word at a time.

 https://powcoder.com
- ° So how do we representer instructions?
 - Remember: Computer only understands 1s and 0s, so "add \$t0,\$0,\$0" is meaningless.
 - MIPS wants simplicity: since data is in words, make instructions be words too

Instructions as Numbers (2/2)

- One word is 32 bits, so divide instruction word into "fields".
- Each field tells computer something about instruction Project Exam Help
- We could define different fields for each instruction, but MIPS is based on simplicity, soldefine 3 basic types of instruction formats:
 - R-format
 - · I-format
 - J-format (next lecture)

Instruction Formats

- I-format: used for instructions with immediates, lw and sw (since the offset counts as an immediate), and the branches (beq and bne),
 - · (but not the smitt Preside tion stellater)
- J-format: used for jand al
- ° R-format: used for all other instructions (stands for register format)
- It will soon become clear why the instructions have been partitioned in this way.

R-Format Instructions (1/5)

° Define "fields" of the following number of bits each: 6 + 5 + 5 + 5 + 6 = 32

| 6 | 5 | 5 | 5 | 5 | 6 |
|---|---|---|---|---|---|
| | |) | | | |

° For simplicitye each di Etahhaspa name:

|--|

- Important: On these slides and in book, each field is viewed as a 5- or 6-bit unsigned integer, not as part of a 32-bit integer.
 - Consequence: 5-bit fields can represent any number 0-31, while 6-bit fields can represent any number 0-63.

R-Format Instructions (2/5)

- ° What do these field integer values tell us?
 - opcode: partially specifies what instruction it is
 - Note: This number is equal to 0 for all R-Format instructions../powcoder.com
 - <u>funct</u>: combined with opcode, this number exactly specifies the instruction
 - Question: Why aren't opcode and funct a single 12-bit field?
 - Answer: We'll answer this later.

R-Format Instructions (3/5)

° More fields:

- rs (Source Register): generally used to specify register containing first operand
- rt (Target Register): generally used to specify register containing second operand (note: that name is misleading)
- rd (Destination Register) ogenerally used to specify register which will receive result of computation

R-Format Instructions (4/5)

Notes about register fields:

- Each register field is exactly 5 bits, which means that it can specify any unsigned integer in the range 0-31. Each of these fields specifies breiof the 32 registers by number.

 https://powcoder.com
- The word "generally" was used because there are exceptions that we'll see later. E.g.,
 - mult and div have nothing important in the rd field since the dest registers are hi and lo
 - mfhi and mflo have nothing important in the rs and rt fields since the source is determined by the instruction

R-Format Instructions (5/5)

° Final field:

- shamt: This field contains the amount a shift instruction will shift by. Shifting a 32-bit word by more than 31 is useless, so this field is only 5 bits (so it can represent the manbers 0.31).
- This field is set to a invalidant the shift instructions.
- ° For a detailed description of field usage for each instruction, see back cover of textbook.

R-Format Example (1/2)

° MIPS Instruction:

```
add $8,$9,$10
```

```
Assignment Project Exam Help
opcode = 0 (look up in table)
funct = 32 (look up in table)
rs = 9 (first operand) powcoder
rt = 10 (second operand)
rd = 8 (destination)
shamt = 0 (not a shift)
```

R-Format Example (2/2)

° MIPS Instruction:

add \$8,\$9,\$10

Decimal/field representation:

| Assignment Project Exam Help | | | | | | |
|------------------------------|---|----|-------|--------|----|--|
| 0 | 9 | 10 | fel8m | ento ' | 32 | |

Binary/field representation:

000000 01001 01010 01000 00000 100000

hex representation: 012A 4020_{hex}

decimal representation: 19,546,144_{ten}

Called a <u>Machine Language Instruction</u>

I-Format Instructions (1/5)

- What about instructions with immediates?
 - 5-bit field only represents numbers up to the value 31: immediates may be much larger thaigthist Project Exam Help
 - · Ideally, MIRS would have only one instruction format (for simplicity): unfortunately, We held to dompromise
- Define new instruction format that is partially consistent with R-format:
 - First notice that, if instruction has immediate, then it uses at most 2 registers.

I-Format Instructions (2/5)

Define "fields" of the following number of bits each: 6 + 5 + 5 + 16 = 32 bits

° Again, each field has a name:

Add WeChat powcoder

Key Concept: Only one field is inconsistent with R-format. Most importantly, opcode is still in same location.

I-Format Instructions (3/5)

- ° What do these fields mean?
 - opcode: same as before except that, since there's no funct field, opcode uniquely specifies an instruction in I-format Assignment Project Exam Help
 This also answers question of why
 - This also answers question of why R-format has two 6-bit fields to identify instruction instead of a single 12-bit field: in order to be consistent with other formats.

I-Format Instructions (4/5)

- ° More fields:
 - <u>rs</u>: specifies the *only* register operand (if there is one)
 - <u>rt</u>: specifies register which will receive result of computation (this is why it's called the *target* register rt")

Add WeChat powcoder

I-Format Instructions (5/5)

° The Immediate Field:

- addi, slti, sltiu, the immediate is sign-extended to 32 bits. Thus, it's treated as a signed integer.
- 16 bits Assignment Project Exam Help can be used to represent immediatehup to 200 clifferent values
- This is large enough to handle the offset in a typical lw or sw, plus a vast majority of values that will be used in the slti instruction.

I-Format Example (1/2)

MIPS Instruction:

```
addi $21,$22,-50
```

```
opcode =8 (100k up in table) Help

rs = 22 (register/containing operand)

rt = 21 (targetdregister) owcoder

immediate = -50 (by default, this is decimal)
```

I-Format Example (2/2)

MIPS Instruction:

```
addi $21,$22,-50
```

Decimal/field representation:

```
8 22 21 20 -50
```

Binary/field representation.er

```
001000 10110 10101 1111111111001110
```

hexadecimal representation: 22D5 FFCE_{hex} decimal representation: $584,449,998_{ten}$

I-Format Problems (1/3)

Problem 1:

· Chances are that addi, lw, sw and slti will use immediates small enough to fit in the immediate field.

Assignment Project Exam Help

• What if too big?

- We need a way to deal with a 32-bit immediate in any I-format instruction.

I-Format Problems (2/3)

- Solution to Problem 1:
 - Handle it in software + new instruction
 - Don't change the current instructions: instead, add a new instruction to help out
- ° New instruction powcoder.com

lui requistechat immediate

- stands for Load Upper Immediate
- takes 16-bit immediate and puts these bits in the upper half (high order half) of the specified register
- sets lower half to 0s

I-Format Problems (3/3)

- Solution to Problem 1 (continued):
 - So how does lui help us?
 - Example:

```
Assignment Project Exam Help becomes:

lui https://powcoder.com
lui sat, 0xABAB

ori Add$atch$at 0xGDCD
add $t0,$t0,$at
```

- Now each I-format instruction has only a 16bit immediate.
- Wouldn't it be nice if the assembler would do this for us automatically?
 - Next lecture: pseudoinstructions

In conclusion, ...

- Simplifying MIPS: Define instructions to be same size as data word (one word) so that they can use the same memory (compiler can use 1w and sw).
- Assignment Project Exam Help
 Machine Language Instruction: 32 bits
 representing smyteding fruction

| R | opcode | rs | l WeCha rt | rd rd | shamt | funct |
|---|--------|----|---------------|-----------|-------|-------|
| ı | opcode | rs | rt | immediate | | |

° Computer actually stores programs as a series of these 32-bit numbers.