# A Practical Analysis of UEFI threats against Windows 11

Joshua Machauer

*June 21, 2022* Version: Draft 1.0

#### Technische Universität Berlin



Electrical Engineering and Computer Science
Institute of Software Engineering and Theoretical Computer Science
Security in Telecommunications (SecT)

#### Bachelor's Thesis

# A Practical Analysis of UEFI threats against Windows 11

#### Joshua Machauer

1. Reviewer Prof. Dr. Jean-Pierre Seifert

Electrical Engineering and Computer Science

Technische Universität Berlin

2. Reviewer Prof. Dr.-Ing. Friedel Gerfers

Electrical Engineering and Computer Science

Technische Universität Berlin

Supervisors Jane Doe and John Smith

June 21, 2022

#### Joshua Machauer

A Practical Analysis of UEFI threats against Windows 11

Bachelor's Thesis, June 21, 2022

Reviewers: Prof. Dr. Jean-Pierre Seifert and Prof. Dr.-Ing. Friedel Gerfers

Supervisors: Jane Doe and John Smith

#### Technische Universität Berlin

Security in Telecommunications (SecT)

Institute of Software Engineering and Theoretical Computer Science

Electrical Engineering and Computer Science

Ernst-Reuter-Platz 7

10587 and Berlin

## Eigenständigkeitserklärung

Hiermit erkläre ich, dass ich die vorliegende Arbeit selbstständig und eigenhändig sowie ohne unerlaubte fremde Hilfe und ausschließlich unter Verwendung der aufgeführten Quellen und Hilfsmittel angefertigt habe.

Berlin, den 10. Juli 2022	
	Joshua Machauer

## **Abstract**

In Computer Security one of the most feared threats is a bootkit, executing at the beginning of a computers boot chain, before the operating system and accompanying antivirus programs. With the widespread adaption of standardized UEFI firmware these threats have become less machine dependent and can now target a host of systems at once. Past analyses about bootkits have been case studies of their appearances in the wild, this thesis instead aims to be a more practical approach by developing a bootkit and analyzing the challenges doing so. We restrict our analysis by assuming an attacker has already gained read and write access to the BIOS image and is thus only facing security mechanisms involved during and with execution of the bootkit. Our bootkit was able to achieve elevated execution on Windows 11 by exploiting unrestricted hard drive access to edit Windows Registries, this was also possible on BitLocker encrypted hard drives by keylogging the Recovery Key. UEFI makes it very easy for an attacker who has gained access to the System Firmware to leverage its powers and gain full control over the system.

## Abstract (different language)

Hello, here is some text without a meaning. This text should show what a printed text will look like at this place. If you read this text, you will get no information. Really? Is there no information? Is there a difference between this text and some nonsense like "Huardest gefburn"? Kjift – not at all! A blind text like this gives you information about the selected font, how the letters are written and an impression of the look. This text should contain all letters of the alphabet and it should be written in of the original language. There is no need for special content, but the length of words should match the language.

## Acknowledgement

## Contents

1	Intr	oduction	1
2	Bacl	kground	3
	2.1	Security Principles	3
	2.2	UEFI/PI	3
		2.2.1 Boot Sequence	4
		2.2.2 UEFI/PI Firmware Images	6
		2.2.3 UEFI Images	8
		2.2.4 Firmware Core	9
		2.2.5 edk2	10
		2.2.6 Security	10
	2.3	Windows	12
		2.3.1 User Access Control (UAC)	12
		2.3.2 Signing	12
		2.3.3 BitLocker	12
3	Rela	ted Work	15
4	Atta	cks	17
	4.1	Test Setup	17
	4.2	Neither Secure Boot nor Bitlocker	17
	4.3	Secure Boot	21
	4.4	Secure Boot and Bitlocker	21
5	Disc	ussion	23
	5.1	Rootkit classification	23
	5.2	Mitigations	24
		5.2.1 User awareness	24
	5.3	Future work	24
6	Con	clusion	25
	<i>c</i> 1	Achieved Coals	25

	6.2	Future work	25
Bib	liog	raphy	27
A	App	endix	35
В	Acro	onyms	37

Introduction

A rootkit is a collection of software designed to grant a threat actor control over a system, typically with malicious intend. Rootkits set up a backdoor exploit and may deliver additional malware while leveraging their privileges to remain hidden. There are different types of rootkits such as User Mode, Kernel Mode, Bootkits (bootloader rootkits), Hypervisor level and Firmware rootkits. [cro; Tec] [TODO consult abstract for similar definition, how easy uefi makes it to write hardware independent payload] Firmware rootkits targets the software running during the boot process, which is responsible for the system initialization. This is done before the operating system is executed making them particularly hard to find, they are also persistent across operating system installation or hard drive replacements. [cro] goals

Background

The following introduces the background information necessary to understand the employment of a Unified Extensible Firmware Interface (UEFI) rootkit. This includes the general workings of the Platform Initialization (PI) and UEFI, the UEFI programming model and interface itself; as well as its security mechanisms. It is also necessary to understand our target's defenses, for this, we briefly describe the Window's security mechanisms faced when performing our attacks.

## 2.1 Security Principles

trust root of trust core root of trust static root of trust dynamic root of trust signing, key pairs


### 2.2 UEFI/PI

"The UEFI specifications define a new model for the interface between personal-computer Operating System (OS) and Platform Firmware (PF). [...] Together, these provide a standard environment for booting an OS and running pre-boot applications" [For].

UEFI is pure interface spec [ZRM17] It was designed to replace the legacy Boot Firmware Basic Input/Ouput System (BIOS), while also often offering a backwards compatible mode with the Compatibility Support Module (CSM). The specification is a pure interface specification thus merely states what interfaces and structures a PF has to offer and what an OS may use. how it is implemented by PF what is used by OS boot- and runttime service functions for the bootloader and os to call datatables containing platform-related information - complete solution describing all features and capabilities - abstract interfaces to support a range of processors without the need for knowledge about underlying hardware for the bootloader - sharable persistent storage for platform support code security

### 2.2.1 Boot Sequence

focus will be on dxe and transient system load



#### 1. Security (SEC)

ref to PSP

inductive security design integrity of next module checked by the previous module

handles all platform restart events applying power to system from unpowered state restarting from active state receiving exception conditions

creates temporary memory store possibly CPU Cache as RAM (CAR) cache behaves as linear store of memory no evictions mode every memory access is a hit eviction not supported as main memory is not set up yet and would lead to platform failure

final step Pass handoff information to the Pre-EFI Initialization (PEI) Foundation

- · state of platform
- location and size of the Boot Firmware Volume (BFV)
- location and size of the temporary RAM

- location and size of the stack
- optionally one or more Hand-off Blocks (HOBs) via the SEC HOB Data PEIM-to-PEIM Interface (PPI)

Part of this process is a so called HOB with a function pointer to a procedure to verify PE modules.

SEC Platform Information PPI information about the health of the processor

SEC HOB Data PPI

#### 2. Pre-EFI Initialization (PEI)

- · init permanent memory
- · describe memory in HOBs
- describe FV! (FV!) in HOBs
- pass control to Driver Execution Environment (DXE)

crisis recovery (what is this?) resuming from S3 sleep state linear array of RAM Pre-EFI Initialization Module (PEIM) provides a framework to allow vendors to supply separate initialization modules for each functionally distinct piece of system hardware that must be initialized prior to the DXE phase [For20]

maintenance of chain of trust, protection against unauthorized updates to the PEI phase or modules authentication of the PEI Foundation and its modules provide core PEI module (PEI foundation) processor architecture independent, supports add-in moudles from vendors for processors, chipsets, RAM

Locating, validating, and dispatching PEIMs Facilitating communication between PEIMs Providing handoff data to subsequent phases

#### 3. Driver Execution Environment (DXE)

dxe core/foundation platform independent is implementation of UEFI UEFI Boot Services UEFI Runtime Services DXE Services

dxe dispatcher discover drivers stored in firmware volumes and execute in proper order apriori file optionally in FV or depex of driver after dispatching all drivers in the dispatch queue hands control over to BDS

dxe drivers init processor, chipset and platform produce arichtectural protocols and i/o abstractions for consoles and boot devices

initializing the processor, chipset, and platform components providing software abstractions for system services, console devices, and boot devices.

#### 4. Boot Device Selection (BDS)

DXE arichtectural protocol one function entry platform boot

attempts to connect boot devices required to load the os discovers volumes containing new drivers calls DXE dispatcher doesnt return when successfully booting OS

UEFI itself only specifies the NVRAM variables used in selecting boot options leaves the implementation of the menu system as value added implementation space [For21]

[For20]

- Initializing console devices
- · Loading device drivers
- Attempting to load and execute boot selections
- 5. Transient System Load (TSL)

boottime and runtime services/driver bootloader ExitBootServices()

6. Runtime (RT)


runtime services/driver

7. Afterlife (AL)

hibernation sleep

## 2.2.2 UEFI/PI Firmware Images

[For 20, Volume 3, 2.1]



firmware device persistent physical device contains firmware code and/or data typically flash may be divided into smaller pieces to form multiple logical firmware devices multiple physical firmware devices may be aggregated into one larger logical firmware device

**FV!** (**FV!**) logical device organized into a file system attributes such as - size - formatting - read/write access

**FFS!** (**FFS!**) organization of files and free space no dierectory hierarchy all files flat in root dir parsing requires walking for beginning to end

firmware files types

some file types are sub-divided in file sections

file sections can be either encapsulation or leaf leaf sections such as PE32 RAW VERSION TE

dxe drivers files contain one PE32 executable section may contain version section may contain dxe depex section

freeform files can contain any combination of sections

PEI phase Service Table FfsFindNextFile, FfsFindFileByName and FfsGetFileInfo

DXE phase

depex

[Tiaa]

## 2.2.3 UEFI Images

files containing executable code subset of PE32+ file format with modified header signature to distinguish from normal PE32 Images + stands for addition of 64-bit relocation fix-up extension

relocatable fixed and dynamic address loading loaded fully into memory and reloaction fix ups

three different subsystems types: application, boot service driver and runtime service driver boot and runtime memory

application vs os loader vs driver memory they reside in unloaded on return unloaded on error

memory marked as code and data jump to entry point

what is the boot manager boot manager = bds

#### **UEFI Applications**

example efi shell loaded by boot manager or other applications return or calling exit specifically always unloaded from memory

#### **UEFI OS Loaders**

example windows boot manager normally take over control from the firmware upon load behaves like a normal UEFI application - only use memory allocated from the firmware - only use services/protocols to access devices that the firmware exposes - conform to driver specifications to access hardware on error can return allocated resources with Exit boot service with error specific information given in ExitData on success take full control with ExitBootServices boot service all boot services in the system are terminated, including memory management UEFI OS loader now responsible

#### **UEFI Drivers**

loaded by boot manager, UEFI firmware (DXE foundation), or other applications example payload unloaded only when returning error code presistent on success boot and runtime drivers only difference is that runtime are available after Exit-BootServices was called boottime drivers are terminated and memory is released runttime drivers are fixed up with virtual mappings upon SetVirtualAddressMap call has to convert its allocated memory

#### 2.2.4 Firmware Core

#### **Systemtable**

system tables offers boot and runtime services supplied by drivers implementing arichtectural protocols

#### **Handles**

[For21, 7.3 Protocol Handler Services]

#### **Protocols**

consists of GUID and protocol interface structure containing functions and instance data used to access a device

provide software abstractions for devices such as consoles, mass storage devices and networks They can also be used to extend the number of generic services that are available in the platform [For21, 2.4 Protocols] boot services provide function to install, locate, open, close and monitor protocols [For21, 7.3 Protocol Handler Services] identified with guids

#### **Boottime Services**

#### **Runtime Services**

#### 2.2.5 edk2

build system

BaseTools package process files compiled by third party tools, as well as text and Unicode files in order to create UEFI or PI compliant binary image files []

## 2.2.6 Security

others not discussed further user identification

PEI GuidedSection Extraction

#### **Secure Boot**

[Tiac]

driver signing executables may be located on un-secured media system provider can authenticate either origin or integrity

digital signature data to sign public/private key pair used to verify integrity

embedded within PE file calculating the pe image hash - hashing the pe header, omitting the file's checksum and the Certificate Table entry in Optional Header Data

Directories - sorting and hasing pe sections omitting attribute certifacte table and hash remaining data

[Mic]

guarantees only valid 3rd party firmware code can run in OEM firmware environment UEFI Secure Boot assumes the system firmware is a trusted entity any 3rd party firmware code is not trusted including bootloader/osloader, PCI option ROMs, UEFI shell tool

two parts verification of the boot image and verification of updates to the image security database [understanding-uefi-secure-boot-chain]

authenticated variables maybe

#### **Signed Capsule Update**

DXE SMM Ready to Lock Vol4

Capsule Architectural Protocol

provides CapsuleUpdate() QueryCapsuleCapabilities() of the runtime services table

flash device security

#### **TPM** measurements

A Trusted Platform Module (TPM) is a system component which enables trust in computing platforms helps verify if the Trusted Computing Base has been compromised securely storing passwords, certificates and encryption keys in separate state to host only communicating through a well defined interface. store platform measurements that help ensure that the platform remains trustworthy authentication attestation hardware and software implementations software special mode shielding TPM resources from normal execution [Gro08] [Gro19]

how are they used works with bitlocker to protect user data ensure computer has not been tampered with while offline

statically configured, unchangeable data not dynamic and changeable across the boot, [Tiab]

[Tiab]

## 2.3 Windows

### 2.3.1 User Access Control (UAC)

## 2.3.2 Signing

#### 2.3.3 BitLocker

BitLocker Drive Encryption (BDE) integrates with operating system encryption enabled per volume encrypt os and data drives supports removable data drives maximum protection with TPM 1.2 or later alternatively USB startup key or password, not system integrity verification optionally PIN or USB startup key required to unlock also network unlock and pin as fallback

- tpm only no additional user interaction - tpm with startup key additional usb - tpm with PIN - tpm with startup keyc and PIN protects against unauthorized data access

with tpm ensures integrity of early boot components and boot configuration

system requirement include support for TCG-specified Static Root of Trust Measurement

bitlocker device encryption if supported automatically enabled after clean install encrypted with clear key (bitlocker suspended state) non domain account -> recovery key uploaded to microsoft account domain account -> recovery key backed up to active directory domain services (AD DS) clear key removed

encryption on used disk space only or whole drive former security risk if turned on after drive was already in use, deleted data accessible with disk recovery tools latter the following is recommended encrypted hard drive support

two partitions - operating system partition with os and support files, all system files on the volume, including the paging files and hibernation files, bitlocker encrypted, ntfs - system partition with windows boot manager and minimal software required for decryption of the os, fat32, unencrypted, files needed

data is encrypted blockwise with Full Volume Encryption Key (FVEK) - AES 128-bit the key is 128-bit of size - AES 256-bit the key is 256-bit of size FVEK encrypted with Volume Master Key (VMK) 256 bit VMK encrypted by multiple protectors, default configuration: - TPM - Recovery Key

or - startup key/external key

#### **Recovery Key**

recovery key 48 digits of 8 blocks block is converted to a 16-bit value making up a 128-bit key

#### **Clear Key**

unprotected 256-bit key stored on the volume t decrypt vmk

#### **Startup Key**

stored in a .bek file with GUID name equaling key identifier in bitlocker meta data multiple possible for a single bitlocked volume

#### **Startup Key**

password with max 49 characters

Related Work

scholar ranking

Attacks 4

Our different attacks face three escalating levels of security mechanisms. The first is with Secure Boot and Bitlocker disabled, the second is just Secure Boot enabled and the third is both Secure Boot and Bitlocker enabled with the focus of the study on Bitlocker. All attacks share the requirement of being able to add DXE Drivers to the DXE Volume. This can be achieved by having read/write access to the SPI flash or using the Signed Capsule Update. Gaining read/write access to the SPI Flash is possible either through physical access to the device by using an SPI clamp on the chip itself or through exploits like for example the . Signed Capsule Updates can be leveraged with access to private vendor information by signing the payload to make it appear legitimate or by intercepting the distribution process and employing infected firmware.

## 4.1 Test Setup

[TODO describe test setup]

## 4.2 Neither Secure Boot nor Bitlocker

The first attack is performed without enabling any security mechanisms (e.g. Secure Boot, BitLocker). Our first step is to gain unrestricted access to the hard drive from the UEFI environment. Since Windows uses NTFS formatting for their hard drive volumes we need to use an NTFS driver, UEFI is not required to support NTFS and as such edk2 does not come with an NTFS driver.


Luckily open source NTFS drivers are readily available such as ntfs-3g from tuxera [tux] which allow for read and write access, on top of that there already exists a port to UEFI created by pbatard [pba].

We can compile this driver with edk2 following the listed steps and receive a .efi file.

[TODO better summary of UEFI shell] Part of the UEFI specifications is a shell specification which is a feature rich UEFI shell application to interact with the UEFI environment. [TODO better listing of capabilities] It offers commands for boot, configuration, device, driver, handle filesystem network memory scripting. For now driver loading and filesystem navigation are of relevance.

[TODO look up official guideline to booting into console] The UEFI shell can be part of the boot options or requires the user to supply the executable via a removable medium such as a USB stick.

Upon invocation, the shell application performs an initialization during which it **[TODO whats important for us here]** and produces output that is equivalent to the output of the execution of the commands ver and map -terse [For16, 3.3 Initialization]. ver displays the version of the UEFI specification the firmware conforms to [For16, 5.3 Shell Commands].



The map command is very interesting for file access with the shell, it displays a mapping table between user defined alias names and device handles. The aliases can be used instead of a device path when submitting commands via the command line interface. The UEFI shell also produces default mappings, notably for file systems

[For16, 3.7.2. Mappings]. These mappings are designed to be consistent across reboots as long as the hardware configuration stays the same, they are comparable to Windows partition letters. [For16, Appendix A]

[TODO find in spec what precise mapping mechanism] When we inspect the mapping table we can see FSx and BLKx aliases, FSx maps to file systems and BLKx to block devices. This identification is performed via instances of the Simple File System Protocol and [TODO double check] Block I/O Protocol which present the interfaces to access the devices they are installed to. The Simple File System Protocol [For21, 13.4 Simple File System Protocol] provides, together with the File Protocol, file-type access to the device it is installed on. The two protocols are independent of the underlying file system the media is formatted with. [TODO UEFI supported fule systems] By default UEFI supports

[TODO explain file system indepent abstraction better] Drivers providing these protocols use the Block I/O Protocol to access the underlying media.

Our NTFS UEFI Driver is one such abstraction and needs to be loaded now, this is done first entering alias, for the file system containing the NtfsDxe.efi, followed by a colon. [TODO alias for fs eingeben was macht das] This effectively switches the console's working directory to be the root of the entered file system, now we caninvoke load with the path to the executable. The output indicates whether loading the driver was successful. [TODO maybe better command here] With the command drivers, we can list all currently loaded drivers and some basic information about them, such as number of devices managed. We can see that the NTFS driver already manages devices.

[TODO reword maybe move the block device stuff up] We can now reset all default mappings with the map -r command to receive an updated list including the file system now provided by the NTFS driver. The mapping also shows us that the file system now sits on top of a device which previously was only listed as a block device indicating that the NTFS driver uses this block-wise access to offer the Simple File System Protocol.

As done before we now type the alias of the new file system followed with a colon to switch to NTFS formatted file system. With Is we can list the current directory's content and confirm by the presence of the Windows folder that we are on the volume containing the Windows installation.

We now navigate into the Windows folder to test whether we have unrestricted read and write access, since is not the case if done by an unprivileged user when performed from within Windows. Accessing folders and viewing their contents is possible but creation of a new folder fails.

Upon debugging the NTFS driver it appears to be that the drivers falls back to read only when it encounters a file that indicates that the Windows system is in hibernation mode. Windows seems to have hibernation enabled by default and as such our rootkit should not rely on it being disabled, we can change the code of the NTFS driver to not fallback when encountering this file.

We now know that provided we get to load the NTFS driver we can access a Windows installation and subsequently the entire data of unencrypted hard drives. Since our rootkit will not use the UEFI shell we need to have the NTFS driver load as part of the boot process. We can put the NTFS driver into the DXE Volume where the DXE Dispatcher of the DXE Core will automatically try to load it.

retrieve the image for qemu we can build it ourselves for hardware use spi clamp to dump image

we can open image with UEFITool an editor for firmware images conforming to the UEFI PI spec [Lon]

in UEFITool search for DXE Volume remove previous NTFS driver if present, for full control, might be read only etc in UEFITool search for string since files are part of file sections we cant drop in the .efi compile dxe driver within ovmf generate unused volume to receive .ffs file with version, depex, user interface and pe section add in NTFS driver .ffs file qemu just use path to modified image on hardware use write access with clamp

now upon opening uefi shell we instantly see the filesystem

try to use ntfs-driver in code this is our first rootkit iteration payload will also be DXE driver access to all drivers etc package payload in firmware image load after NTFS driver install tag protocol on NTFS driver and put into depex of rootkit steps read payload into RAM search for windows installation write payload

pack executable binary as uefi module edk2 produces freeform image with one raw section

iterate over FirmwareVolume2 protocol instances boottime services offer a function LocateHandleBuffer which returns all handles having a given protocol attached to them iterate over all handles and open the protocol call ReadSection with payload guid, to read raw section check size match was necessary on hardware when compiling payload a post build script generates a header for the rootkit dxe containing the size on disk for the payload

iterate over all FirmwareVolume2 Protocols read raw section of payload file GUID into memory

iterate over all SimpleFileSystem Protocols open volume open file to write to since we write into windows folder this also checks if the volume has a windows installation

achieved so far unrestricted file access but no automatic execution nor elevated privileges

dll proxying dll hijacking registry editing

Task Scheduler defined in xml cached in registry edit with start cmd.exe and trigger manually whoami

chntpw and reged [Nor] port to uefi edit Task in machine under Control maybe look if just adding a key would have also worked export target registry key modify so that registry key can differ and found via matching values import and override registry key on target machine payload whoami localsystem

## 4.3 Secure Boot

how does one enable it mostly comes with default keys OEM expectation: not to boot observation: no difference secure boot default policy snippet option roms and bootloader instead relies on Signed Capsule Updates assumes integrity

## 4.4 Secure Boot and Bitlocker

assumptions: secure boot or not bitlocker enabled with TPM auto decryption, no PIN, no startup key

observation: boot execution differs from executing rootkit tpm values different bitlocker auto decryption fails recovery key prompt

what is the reaction of the average user (ask admin for recovery password) type in recovery password alternative would be to remove drive and insert into safe device prompt is done by the OS Loader ergo still during transient system load phase required to use protocol services therefor uses uefi services for IO such as SimpleTextInputEx Protocol go over the two different input protocols find out which one is used

explain more in depth how protocols are returned to the end user one instance per controller/handle

explain basic hooking explain how we retain information of the hook in question map protocol pointer to hook information keylog recovery key key input advancment is weird and makes tracking tricky

alternatively screen shot still need hook to find when enter is pressed explain how screenshotting works some basic compression wait for recovery key send recovery key on enter press

on real hardware network stack wasn't installed onto handles when boot over ip was disabled compared loaded dxe drivers between both configurations with efi shell Realtek Family driver not loaded load manually reinstall all handle to controllers to enable network stack regardless

sending key out is only good for physical access attack vector dislocker linux utility [Aor] mount encrypted drive with decryption mean read and write access dual boot in vm enter recovery key and it works port to uefi bitlocker encrypts block-wise uefi protocol stack hook block io again hook data mapping dislocker validate block solves recovery key advancement issue

hook ExitBootServices enable hook write payload import registry key disable hook

next boot would require to input tpm values again update tpm values in payload caveat pin? look into this

persistence when part of root of trust fresh install / tpm update values hook Trusted Copmuting Group 2 (TCG2) Protocol TPM communication [Gro14, p. 6.7.3] receive bitlocker vmk key and send to dislocker

Discussion

attack assumption reflected to real world aplicability

social engineering aspekt

driver vorhanden und was mitbringen, debloating

boottime vs runtime rootkit

recovery guide

what causes bitlocker recovery - password wrong too often - TPM 1.2, changing the BIOS or firmware boot device order - Having the CD or DVD drive before the hard drive in the BIOS boot order and then inserting or removing a CD or DVD - Failing to boot from a network drive before booting from the hard drive. - Docking or undocking a portable computer - Changes to the NTFS partition table on the disk including creating, deleting, or resizing a primary partition. - Entering the personal identification number (PIN) incorrectly too many times - Upgrading critical early startup components, such as a BIOS or UEFI firmware upgrade - Updating option ROM firmware graphics card - Adding or removing hardware - REMOVING, INSERTING, OR COMPLETELY DEPLETING THE CHARGE ON A SMART BATTERY ON A PORTABLE COMPUTER - Pressing the F8 or F10 key during the boot process what does the recovery screen say

Enables end users to recover encrypted devices independently by using the Self-Service Portal

## 5.1 Rootkit classification

statisken zu bilocker und secureboot auf systemen

industrie standard zur system security in firmen

## 5.2 Mitigations

hardware validated boot
inaccessible spi flash
tpm + pin detectability
googeln wie legitime recovery key prompt reaktion aussieht
enterprise policy recovery key einschraenkbar?
enterprise policy on recovery key loss

#### 5.2.1 User awareness

## 5.3 Future work

exploit in tpm measruement chain that rsults in not being measured can exploit the tg2 hook directly to retrieve the vmk

Conclusion

#### 6.1 Achieved Goals

when we are already in the image we can gain full control over the system system cant be trusted anymore e.g. uefi services full file access escalate it to local system level execution bitlocker has the flaw of allowing to enter criticial information into an inherently untrustable system on the other hand one could force such a prompt themselves mere existence of a recovery key is a security flaw

#### 6.2 Future Work

tpm and pin capsule update

### Bibliography

[](Cit. on p. 10). [Aor] Aorimn. Dislocker (cit. on p. 22). [cro] crowdstrike. Rootkit Malware (cit. on p. 1). [For20] UEFI Forum. UEFI Platform Initialization (PI) Specification, Version 1.7 Errata A. 2020 (cit. on pp. 5, 6). [For16] UEFI Forum. UEFI Shell Specification, Revision 2.2. 2016 (cit. on pp. 18, 19). [For21] UEFI Forum. UEFI Specification, Version 2.9. 2021 (cit. on pp. 6, 9, 10, 19). UEFI Forum. UEFI Specifications Overview (cit. on p. 3). [For] [Gro14] Trusted Computing Group. TCG EFI Platform Specification, Version 1.22 Revision 15. 2014 (cit. on p. 22). [Gro08] Trusted Computing Group. Trusted Platform Module (TPM) Summary. 2008 (cit. on p. 11). [Gro19] Trusted Computing Group. Trusted Platform Module Library, Part 1: Architecture, Level 00 Revision 01.59. 2019 (cit. on p. 11). [Lon] LongSoft. UEFITool (cit. on p. 20). [Mic] Microsoft. Microsoft Windows Authenticode Portable Executable Signature Format, *Version 1.0* (cit. on p. 11). [Nor] Petter Nordahl-Hagen. Chntpw (cit. on p. 21). [pba] pbatard. ntfs-3g (cit. on p. 17). [Tec] Techtarget. Definition rootkit (cit. on p. 1). [Tiaa] TianoCore. EDKII Build Specification (cit. on p. 8). [Tiab] TianoCore. Trusted Boot Chain (cit. on p. 11). [Tiac] TianoCore. *Understanding UEFI Secure Boot Chain* (cit. on p. 10). [tux] tuxera. ntfs-3g (cit. on p. 17). [ZRM17] Vincent Zimmer, Michael Rothman, and Suresh Marisetty. Developing with the *Unified Extensible Firmware Interface, Third Edition.* Berlin, Boston: De | G Press, 2017 (cit. on p. 3).

# List of Figures

### List of Tables

# List of Listings

Appendix

Acronyms

BDS Boot Device Selection
BF Boot Firmware
BFV Boot Firmware Volume
BIOS Basic Input/Ouput System
CAR Cache as RAM
CSM Compatibility Support Module
DXE Driver Execution Environment
<b>EFI</b> Extensible Firmware Interface
HOB Hand-off Block
OS Operating System
PEI Pre-EFI Initialization
PEIM Pre-EFI Initialization Module
PF Platform Firmware
Pl Platform Initialization
PPI PEIM-to-PEIM Interface
RT Runtime
SEC Security
TSL Transient System Load
TPM Trusted Platform Module
<b>UEFI</b> Unified Extensible Firmware Interface

**AL** Afterlife