schwarz-lib Generated automatically from doc-setup

Generated by Doxygen 1.8.13

Contents

1	Mair	n Page	1
2	Insta	allation Instructions	3
3	Test	ing Instructions	5
4	Bene	chmarking.	7
5	Mod	ule Documentation	9
	5.1	Communicate	9
		5.1.1 Detailed Description	9
	5.2	Initialization	10
		5.2.1 Detailed Description	10
	5.3	Schwarz Class	11
		5.3.1 Detailed Description	11
	5.4	Solve	12
		5.4.1 Detailed Description	12
	5.5	Utils	13
		5.5.1 Detailed Description	13
6	Nam	nespace Documentation	15
	6.1	ProcessTopology Namespace Reference	15
		6.1.1 Detailed Description	15
	6.2	SchwarzWrappers Namespace Reference	15
		6.2.1 Detailed Description	16
	6.3	SchwarzWrappers::CommHelpers Namespace Reference	16
		6.3.1 Detailed Description	16
	6.4	SchwarzWrappers::ConvergenceTools Namespace Reference	16
		6.4.1 Detailed Description	16
	6.5	SchwarzWrappers::PartitionTools Namespace Reference	17
		6.5.1 Detailed Description	17
	6.6	SchwarzWrappers::SolverTools Namespace Reference	17
		6.6.1 Detailed Description	17

ii CONTENTS

7	Clas	s Docu	umentation	19
	7.1	BadDii	imension Class Reference	19
		7.1.1	Detailed Description	19
		7.1.2	Constructor & Destructor Documentation	19
			7.1.2.1 BadDimension()	19
	7.2	Schwa	arzWrappers::Settings::comm_settings Struct Reference	20
		7.2.1	Detailed Description	21
	7.3	Schwa	arzWrappers::Communicate< ValueType, IndexType >::comm_struct Struct Reference	21
		7.3.1	Detailed Description	22
		7.3.2	Member Data Documentation	22
			7.3.2.1 global_get	22
			7.3.2.2 global_put	23
			7.3.2.3 is_local_neighbor	23
			7.3.2.4 local_get	23
			7.3.2.5 local_put	24
			7.3.2.6 remote_get	24
			7.3.2.7 remote_put	24
	7.4	Schwa	arzWrappers::Communicate< ValueType, IndexType > Class Template Reference	25
		7.4.1	Detailed Description	25
		7.4.2	Member Function Documentation	26
			7.4.2.1 exchange_boundary()	26
			7.4.2.2 local_to_global_vector()	26
			7.4.2.3 setup_windows()	27
			7.4.2.4 update_boundary()	27
	7.5	Schwa	arzWrappers::Settings::convergence_settings Struct Reference	28
		7.5.1	Detailed Description	28
	7.6	CudaE	Error Class Reference	28
		7.6.1	Detailed Description	29
		7.6.2	Constructor & Destructor Documentation	29
			7.6.2.1 CudaError()	29

CONTENTS

7.7	Cuspar	rseError Class Reference	29
	7.7.1	Detailed Description	30
	7.7.2	Constructor & Destructor Documentation	30
		7.7.2.1 CusparseError()	30
7.8	Schwa	rzWrappers::device_guard Class Reference	30
	7.8.1	Detailed Description	30
7.9	Schwa	rzWrappers::Initialize< ValueType, IndexType > Class Template Reference	31
	7.9.1	Detailed Description	31
	7.9.2	Member Function Documentation	32
		7.9.2.1 generate_rhs()	32
		7.9.2.2 partition()	32
		7.9.2.3 setup_global_matrix_laplacian()	33
		7.9.2.4 setup_local_matrices()	34
		7.9.2.5 setup_vectors()	35
7.10	Schwa	rzWrappers::Metadata< ValueType, IndexType > Struct Template Reference	36
	7.10.1	Detailed Description	37
	7.10.2	Member Data Documentation	38
		7.10.2.1 local_solver_tolerance	38
		7.10.2.2 tolerance	38
7.11	MetisE	rror Class Reference	38
	7.11.1	Detailed Description	38
	7.11.2	Constructor & Destructor Documentation	38
		7.11.2.1 MetisError()	38
7.12	Schwa	rzWrappers::SchwarzBase< ValueType, IndexType > Class Template Reference	39
	7.12.1	Detailed Description	40
	7.12.2	Constructor & Destructor Documentation	40
		7.12.2.1 SchwarzBase()	40
	7.12.3	Member Function Documentation	42
		7.12.3.1 print_matrix()	42
		7.12.3.2 print_vector()	43

iv CONTENTS

		7.12.3.3 run()	43
7.13	Schwa	rzWrappers::Settings Struct Reference	45
	7.13.1	Detailed Description	46
	7.13.2	Member Data Documentation	46
		7.13.2.1 explicit_laplacian	46
		7.13.2.2 naturally_ordered_factor	47
7.14	Schwa	rzWrappers::Solve< ValueType, IndexType > Class Template Reference	47
	7.14.1	Detailed Description	47
7.15	Schwa	rzWrappers::SolverRAS< ValueType, IndexType > Class Template Reference	47
	7.15.1	Detailed Description	48
	7.15.2	Constructor & Destructor Documentation	48
		7.15.2.1 SolverRAS()	48
	7.15.3	Member Function Documentation	49
		7.15.3.1 exchange_boundary()	49
		7.15.3.2 setup_local_matrices()	50
		7.15.3.3 setup_windows()	53
		7.15.3.4 update_boundary()	55
7.16	Schwa	rzWrappers::Utils< ValueType, IndexType > Struct Template Reference	56
	7.16.1	Detailed Description	56

Index

59

Main Page

This is the main page for the Schwarz library pdf documentation. The repository is hosted on github. Documentation on aspects such as the build system, can be found at the Installation Instructions page.

Modules

The structure of the Schwarz Library code is divided into different ${\tt modules}$:

- Initialization: Handles the initialization of the problem and the solver.
- Communicate: Handles the communication.
- Solve: Handles the local solution and the convergence detection.
- Schwarz Class: The Classes related to the Schwarz solvers.
- Utils: Provides some basic utilities.

2 Main Page

Installation Instructions

Building

Use the standard cmake build procedure:

```
mkdir build; cd build
cmake -G "Unix Makefiles" [OPTIONS] .. && make
```

Replace [OPTIONS] with desired cmake options for your build. The library adds the following additional switches to control what is being built:

- -DSCHWARZ_BUILD_BENCHMARKING={ON, OFF} Builds some example benchmarks. Default is ON
- -DSCHWARZ_BUILD_METIS={ON, OFF} Builds with support for the METIS partitioner. User needs to provide the path to the installation of the METIS library in METIS_DIR, preferably as an environment variable. Default is OFF
- -DSCHWARZ_BUILD_CHOLMOD={ON, OFF} Builds with support for the CHOLMOD module from the Suitesparse library. User needs to set an environment variable CHOLMOD_DIR to the path containing the CHOLMOD installation. Default is OFF
- -DSCHWARZ_BUILD_CUDA={ON, OFF} Builds with CUDA support. Though Ginkgo provides most of the required CUDA support, we do need to link to CUDA for explicit setting of GPU affinities, some custom gather and scatter operations. Default is OFF.
- -DSCHWARZ_BUILD_CLANG_TIDY={ON, OFF} Builds with support for clang-tidy Default is OFF
- -DSCHWARZ_BUILD_DEALII={ON, OFF} Builds with support for the finite element library deal.ii
 Default is OFF
- -DSCHWARZ_WITH_HWLOC={ON, OFF} Builds with support for the hardware locality library used for binding hardware. hwloc is distributed as a part of the Open-MPI project. Default is ON
- -DSCHWARZ_DEVEL_TOOLS={ON, OFF} Builds with some developer tools support. Default is ON. In particular uses git-cmake-format to automatically format the source files with clang-format.

Tips

- If you are having CUDA problems and you are not using CUDA, then feel free to switch the CUDA module off with -DSCHWARZ_BUILD_CUDA=off.
- Installing CHOLMOD can be a bit annoying. TODO add some details on fixing Suitesparse compilation.
- When doing merge commits it is possible that make format does not work. You can run cmake -DSCH ← WARZ_DEVEL_TOOLS=OFF . . to temporarily switch off the formatting. Please switch it on again when committing normally.

4 Installation Instructions

Testing Instructions

Will be updated soon.

6 Testing Instructions

Benchmarking.

Benchmark example 1.

Poisson solver using Restricted Additive Schwarz with overlap.

The flag $-DSCHWARZ_BUILD_BENCHMARKING$ (default ON) enables the example and benchmarking snippets. The following command line options are available for this example. This is setup using gflags.

The executable is run in the following fashion:

"sh [MPI_COMMAND] [MPI_OPTIONS]

8 Benchmarking.

Module Documentation

5.1 Communicate

A module dedicated to the Communication interface in schwarz-lib.

Namespaces

• SchwarzWrappers::CommHelpers

The CommHelper namespace .

ProcessTopology

The ProcessTopology namespace.

Classes

class SchwarzWrappers::Communicate< ValueType, IndexType >

The communication class that provides the methods for the communication between the subdomains.

struct SchwarzWrappers::Metadata < ValueType, IndexType >

The solver metadata struct.

5.1.1 Detailed Description

A module dedicated to the Communication interface in schwarz-lib.

10 Module Documentation

5.2 Initialization

A module dedicated to the initialization and setup and usage of the solvers in schwarz-lib.

Namespaces

• SchwarzWrappers::PartitionTools

The PartitionTools namespace.

ProcessTopology

The ProcessTopology namespace .

Classes

• class SchwarzWrappers::device_guard

This class defines a device guard for the cuda functions and the cuda module.

class SchwarzWrappers::Initialize< ValueType, IndexType >

The initialization class that provides methods for initialization of the solver.

• struct SchwarzWrappers::Settings

The struct that contains the solver settings and the parameters to be set by the user.

struct SchwarzWrappers::Metadata < ValueType, IndexType >

The solver metadata struct.

5.2.1 Detailed Description

A module dedicated to the initialization and setup and usage of the solvers in schwarz-lib.

5.3 Schwarz Class

5.3 Schwarz Class

A module dedicated to the Schwarz solver classes in schwarz-lib.

Classes

- class SchwarzWrappers::SolverRAS< ValueType, IndexType >
 An implementation of the solver interface using the RAS solver.
- $\bullet \ \, {\sf class} \ \, {\sf SchwarzWrappers::SchwarzBase} < \ \, {\sf ValueType}, \ \, {\sf IndexType} > \\$

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

5.3.1 Detailed Description

A module dedicated to the Schwarz solver classes in schwarz-lib.

12 Module Documentation

5.4 Solve

A module dedicated to the solvers including local solution and convergence detection in schwarz-lib.

Namespaces

• SchwarzWrappers::ConvergenceTools

The Convergence Tools namespace.

• SchwarzWrappers::SolverTools

The SolverTools namespace .

Classes

struct SchwarzWrappers::Metadata < ValueType, IndexType >

The solver metadata struct.

class SchwarzWrappers::Solve < ValueType, IndexType >

The Solver class the provides the solver and the convergence checking methods.

5.4.1 Detailed Description

A module dedicated to the solvers including local solution and convergence detection in schwarz-lib.

5.5 Utils 13

5.5 Utils

A module dedicated to the utilities in schwarz-lib.

Classes

 $\bullet \ \, {\sf struct\ SchwarzWrappers::} \\ {\sf Utils} < {\sf ValueType,\ IndexType} > \\$

The utilities class which provides some checks and basic utilities.

5.5.1 Detailed Description

A module dedicated to the utilities in schwarz-lib.

14 Module Documentation

Namespace Documentation

6.1 ProcessTopology Namespace Reference

The ProcessTopology namespace.

6.1.1 Detailed Description

The ProcessTopology namespace.

proc_topo

6.2 SchwarzWrappers Namespace Reference

The Schwarz wrappers namespace.

Namespaces

CommHelpers

The CommHelper namespace .

ConvergenceTools

The Convergence Tools namespace.

PartitionTools

The PartitionTools namespace.

SolverTools

The SolverTools namespace .

Classes

· class Communicate

The communication class that provides the methods for the communication between the subdomains.

· class device_guard

This class defines a device guard for the cuda functions and the cuda module.

· class Initialize

The initialization class that provides methods for initialization of the solver.

struct Metadata

The solver metadata struct.

· class SchwarzBase

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

struct Settings

The struct that contains the solver settings and the parameters to be set by the user.

· class Solve

The Solver class the provides the solver and the convergence checking methods.

class SolverRAS

An implementation of the solver interface using the RAS solver.

struct Utils

The utilities class which provides some checks and basic utilities.

6.2.1 Detailed Description

The Schwarz wrappers namespace.

6.3 SchwarzWrappers::CommHelpers Namespace Reference

The CommHelper namespace .

6.3.1 Detailed Description

The CommHelper namespace .

comm_helpers

6.4 SchwarzWrappers::ConvergenceTools Namespace Reference

The ConvergenceTools namespace.

6.4.1 Detailed Description

The ConvergenceTools namespace.

conv_tools

6.5 SchwarzWrappers::PartitionTools Namespace Reference

The PartitionTools namespace.

6.5.1 Detailed Description

The PartitionTools namespace.

part_tools

6.6 SchwarzWrappers::SolverTools Namespace Reference

The SolverTools namespace.

6.6.1 Detailed Description

The SolverTools namespace.

solver_tools

Class Documentation

7.1 BadDimension Class Reference

BadDimension is thrown if an operation is being applied to a LinOp with bad dimensions.

```
#include <exception.hpp>
```

Public Member Functions

BadDimension (const std::string &file, int line, const std::string &func, const std::string &op_name, std::size
 _t op_num_rows, std::size_t op_num_cols, const std::string &clarification)
 Initializes a bad dimension error.

7.1.1 Detailed Description

BadDimension is thrown if an operation is being applied to a LinOp with bad dimensions.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 BadDimension()

Initializes a bad dimension error.

20 Class Documentation

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The function name where the error occurred
op_name	The name of the operator
op_num_rows	The row dimension of the operator
op_num_cols	The column dimension of the operator
clarification	An additional message further describing the error

The documentation for this class was generated from the following file:

• exception.hpp (d6ef4fd)

7.2 SchwarzWrappers::Settings::comm_settings Struct Reference

The settings for the various available communication paradigms.

```
#include <settings.hpp>
```

Public Attributes

• bool enable_onesided = false

Enable one-sided communication.

• bool enable_overlap = false

Enable explicit overlap between communication and computation.

• bool enable_put = false

Put the data to the window using MPI_Put rather than get.

• bool enable_get = true

Get the data to the window using MPI_Get rather than put.

• bool enable_one_by_one = false

Push each element separately directly into the buffer.

• bool enable_flush_local = false

Use local flush.

• bool enable flush all = true

Use flush all.

• bool enable_lock_local = false

Use local locks.

• bool enable_lock_all = true

Use lock all.

7.2.1 Detailed Description

The settings for the various available communication paradigms.

The documentation for this struct was generated from the following file:

settings.hpp (d6ef4fd)

The communication struct used to store the communication data.

```
#include <communicate.hpp>
```

Public Attributes

· int num_neighbors_in

The number of neighbors this subdomain has to receive data from.

· int num_neighbors_out

The number of neighbors this subdomain has to send data to.

std::shared_ptr< gko::Array< IndexType > > neighbors_in

The neighbors this subdomain has to receive data from.

 $\bullet \quad \mathsf{std} :: \mathsf{shared_ptr} < \mathsf{gko} :: \mathsf{Array} < \mathsf{IndexType} > > \mathsf{neighbors_out}$

The neighbors this subdomain has to send data to.

std::vector< bool > is_local_neighbor

The bool vector which is true if the neighbors of a subdomain are in one node.

int local_num_neighbors_in

The number of neighbors this subdomain has to receive data from.

· int local_num_neighbors_out

The number of neighbors this subdomain has to send data to.

std::shared_ptr< gko::Array< IndexType > > local_neighbors_in

The neighbors this subdomain has to receive data from.

std::shared_ptr< gko::Array< IndexType > > local_neighbors_out

The neighbors this subdomain has to send data to.

std::shared_ptr< gko::Array< IndexType * > > global_put

The array containing the number of elements that each subdomain sends from the other.

std::shared ptr< gko::Array< IndexType * > > local put

The array containing the number of elements that each subdomain sends from the other.

std::shared_ptr< gko::Array< IndexType * > remote_put

The array containing the number of elements that each subdomain sends from the other.

std::shared ptr< gko::Array< IndexType * > > global get

The array containing the number of elements that each subdomain gets from the other.

std::shared_ptr< gko::Array< IndexType * > > local_get

The array containing the number of elements that each subdomain gets from the other.

std::shared ptr< gko::Array< IndexType * > remote get

The array containing the number of elements that each subdomain gets from the other.

 $\bullet \quad \mathsf{std} :: \mathsf{shared_ptr} < \mathsf{gko} :: \mathsf{Array} < \mathsf{IndexType} > > \mathsf{window_ids} \\$

22 Class Documentation

The RDMA window ids.

std::shared ptr< gko::Array< IndexType > > windows from

The RDMA window ids to receive data from.

std::shared_ptr< gko::Array< IndexType > > windows_to

The RDMA window ids to send data to.

std::shared_ptr< gko::Array< MPI_Request >> put_request

The put request array.

std::shared ptr< gko::Array< MPI Request >> get request

The get request array.

std::shared_ptr< gko::matrix::Dense< ValueType >> send_buffer

The send buffer used for the actual communication for both one-sided and two-sided.

std::shared_ptr< gko::matrix::Dense< ValueType >> recv_buffer

The recv buffer used for the actual communication for both one-sided and two-sided.

std::shared_ptr< gko::Array< IndexType > > get_displacements

The displacements for the receiving of the buffer.

std::shared ptr< gko::Array< IndexType > > put displacements

The displacements for the sending of the buffer.

· MPI Win window recv buffer

The RDMA window for the recv buffer.

· MPI Win window send buffer

The RDMA window for the send buffer.

MPI_Win window_x

The RDMA window for the solution vector.

7.3.1 Detailed Description

```
template < typename ValueType, typename IndexType > struct SchwarzWrappers::Communicate < ValueType, IndexType >::comm struct
```

The communication struct used to store the communication data.

7.3.2 Member Data Documentation

7.3.2.1 global_get

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::global_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global_get[p][0] contains the overall number of elements to be received to subdomain p and global—_put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize(), SchwarzWrappers:: \leftarrow SchwarzBase< ValueType, IndexType >::SchwarzBase(), SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.2 global_put

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::global_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global_put[p][0] contains the overall number of elements to be sent to subdomain p and global_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize(), SchwarzWrappers::

SchwarzBase< ValueType, IndexType >::SchwarzBase(), SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.3 is_local_neighbor

```
\label{template} $$ \end{template} $$$ \end{template} $$ \end{template} $$ \end{template} $$$ \end{template} $$$ \end{template} $$$ \end{template} $$$ \end{template} $$$ \e
```

The bool vector which is true if the neighbors of a subdomain are in one node.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::SchwarzBase(), SchwarzWrappers \hookrightarrow ::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.4 local_get

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::local_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global_get[p][0] contains the overall number of elements to be received to subdomain p and global—_put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and Schwarz \leftarrow Wrappers::SolverRAS< ValueType, IndexType >::setup_windows().

24 Class Documentation

7.3.2.5 local_put

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::local_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global_put[p][0] contains the overall number of elements to be sent to subdomain p and global_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and Schwarz Wrappers::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.6 remote_get

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::remote_get
```

The array containing the number of elements that each subdomain gets from the other.

For example. global_get[p][0] contains the overall number of elements to be received to subdomain p and global—put[p][i] contains the index of the solution vector to be received from subdomain p.

Referenced by SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and Schwarz Wrappers::SolverRAS< ValueType, IndexType >::setup_windows().

7.3.2.7 remote_put

```
template<typename ValueType , typename IndexType >
std::shared_ptr<gko::Array<IndexType *> > SchwarzWrappers::Communicate< ValueType, IndexType
>::comm_struct::remote_put
```

The array containing the number of elements that each subdomain sends from the other.

For example. global_put[p][0] contains the overall number of elements to be sent to subdomain p and global_put[p][i] contains the index of the solution vector to be sent to subdomain p.

Referenced by SchwarzWrappers::SolverRAS< ValueType, IndexType >::setup_comm_buffers(), and Schwarz Wrappers::SolverRAS< ValueType, IndexType >::setup_windows().

The documentation for this struct was generated from the following file:

• communicate.hpp (d6ef4fd)

7.4 SchwarzWrappers::Communicate < ValueType, IndexType > Class Template Reference

The communication class that provides the methods for the communication between the subdomains.

#include <communicate.hpp>

Classes

· struct comm_struct

The communication struct used to store the communication data.

Public Member Functions

virtual void setup comm buffers ()=0

Sets up the communication buffers needed for the boundary exchange.

virtual void setup_windows (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared_ptr < gko::matrix::Dense < ValueType >> &main_buffer)=0

Sets up the windows needed for the asynchronous communication.

virtual void exchange_boundary (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared_ptr < gko::matrix::Dense < ValueType >> &solution_vector)=0

Exchanges the elements of the solution vector.

void local_to_global_vector (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, const std::shared_ptr < gko::matrix::Dense < ValueType >> &local_vector, std::shared_ptr < gko::matrix::
 Dense < ValueType >> &global_vector)

Transforms data from a local vector to a global vector.

virtual void update_boundary (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared_ptr < gko::matrix::Dense < ValueType >> &local_solution, const std::shared_ptr < gko::matrix::Dense < ValueType >> &solution_vector, std::shared_ptr < gko::matrix::Dense < ValueType >> &global_old_solution, const std ::shared_ptr < gko::matrix::Csr < ValueType, IndexType >> &interface_matrix)=0

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

• void clear (Settings &settings)

Clears the data.

7.4.1 Detailed Description

template < typename ValueType, typename IndexType > class SchwarzWrappers::Communicate < ValueType, IndexType >

The communication class that provides the methods for the communication between the subdomains.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

Communicate

26 Class Documentation

7.4.2 Member Function Documentation

7.4.2.1 exchange_boundary()

Exchanges the elements of the solution vector.

Parameters

settings	The settings struct.
metadata	The metadata struct.
solution_vector	The solution vector being exchanged between the subdomains.

Implemented in SchwarzWrappers::SolverRAS< ValueType, IndexType >.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::run().

7.4.2.2 local_to_global_vector()

Transforms data from a local vector to a global vector.

Parameters

settings	The settings struct.
metadata	The metadata struct.
local_vector	The local vector in question.
global_vector	The global vector in question.

```
(gko::Array<ValueType>::view(
               settings.executor, metadata.local_size,
78
               &global_vector->get_values()[metadata.first_row
79
                                                 ->get_data()[metadata.my_rank]])),
80
           1);
81
      auto temp_vector2 = vec::create(
82
           settings.executor, gko::dim<2>(metadata.local_size, 1),
           (gko::Array<ValueType>::view(settings.executor, metadata.local_size,
84
8.5
                                         &local_vector->get_values()[0])),
86
      if (settings.convergence_settings.convergence_crit ==
87
          Settings::convergence_settings::local_convergence_crit::
88
               residual_based) {
90
          local_vector->add_scaled(alpha.get(), temp_vector.get());
           temp_vector->add_scaled(alpha.get(), local_vector.get());
      } else {
    // TODO GPU: DONE
92
93
94
          temp_vector->copy_from(temp_vector2.get());
      }
```

7.4.2.3 setup_windows()

Sets up the windows needed for the asynchronous communication.

Parameters

settings	The settings struct.
metadata	The metadata struct.
main_buffer	The main buffer being exchanged between the subdomains.

Implemented in SchwarzWrappers::SolverRAS< ValueType, IndexType >.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::run().

7.4.2.4 update_boundary()

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

28 Class Documentation

Parameters

settings	The settings struct.
metadata	The metadata struct.
local_solution	The local solution vector in the subdomain.
local_rhs	The local right hand side vector in the subdomain.
solution_vector	The workspace solution vector.
global_old_solution	The global solution vector of the previous iteration.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.

Implemented in SchwarzWrappers::SolverRAS< ValueType, IndexType >.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::run().

The documentation for this class was generated from the following files:

- communicate.hpp (d6ef4fd)
- /home/runner/work/schwarz-lib/schwarz-lib/source/communicate.cpp (d6ef4fd)

7.5 SchwarzWrappers::Settings::convergence_settings Struct Reference

The various convergence settings available.

```
#include <settings.hpp>
```

7.5.1 Detailed Description

The various convergence settings available.

The documentation for this struct was generated from the following file:

• settings.hpp (d6ef4fd)

7.6 CudaError Class Reference

CudaError is thrown when a CUDA routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

CudaError (const std::string &file, int line, const std::string &func, int error_code)
 Initializes a CUDA error.

7.6.1 Detailed Description

CudaError is thrown when a CUDA routine throws a non-zero error code.

7.6.2 Constructor & Destructor Documentation

7.6.2.1 CudaError()

Initializes a CUDA error.

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the CUDA routine that failed
error_code	The resulting CUDA error code

```
137 : Error(file, line, func + ": " + get_error(error_code))
138 {}
```

The documentation for this class was generated from the following files:

- exception.hpp (d6ef4fd)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (d6ef4fd)

7.7 CusparseError Class Reference

CusparseError is thrown when a cuSPARSE routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

• CusparseError (const std::string &file, int line, const std::string &func, int error_code)

Initializes a cuSPARSE error.

30 Class Documentation

7.7.1 Detailed Description

CusparseError is thrown when a cuSPARSE routine throws a non-zero error code.

7.7.2 Constructor & Destructor Documentation

7.7.2.1 CusparseError()

Initializes a cuSPARSE error.

Parameters

file	The name of the offending source file
line	The source code line number where the error occurred
func	The name of the cuSPARSE routine that failed
error_code	The resulting cuSPARSE error code

```
159 : Error(file, line, func + ": " + get_error(error_code))
160 {}
```

The documentation for this class was generated from the following files:

- exception.hpp (d6ef4fd)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (d6ef4fd)

7.8 SchwarzWrappers::device_guard Class Reference

This class defines a device guard for the cuda functions and the cuda module.

```
#include <device_guard.hpp>
```

7.8.1 Detailed Description

This class defines a device guard for the cuda functions and the cuda module.

The guard is used to make sure that the device code is run on the correct cuda device, when run with multiple devices. The class records the current device id and uses <code>cudaSetDevice</code> to set the device id to the one being passed in. After the scope has been exited, the destructor sets the device_id back to the one before entering the scope.

The documentation for this class was generated from the following file:

• device_guard.hpp (d6ef4fd)

7.9 SchwarzWrappers::Initialize < ValueType, IndexType > Class Template Reference

The initialization class that provides methods for initialization of the solver.

#include <initialization.hpp>

Public Member Functions

void generate_rhs (std::vector< ValueType > &rhs)

Generates the right hand side vector.

Generates the 2D global laplacian matrix.

void partition (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, const std ←
 ::shared_ptr < gko::matrix::Csr < ValueType, IndexType >> &global_matrix, std::vector < unsigned int >
 &partition_indices)

The partitioning function.

void setup_vectors (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std
 ::vector < ValueType > &rhs, std::shared_ptr < gko::matrix::Dense < ValueType >> &local_rhs, std::shared
 _ptr < gko::matrix::Dense < ValueType >> &global_rhs, std::shared_ptr < gko::matrix::Dense < ValueType
 >> &local_solution, std::shared_ptr < gko::matrix::Dense < ValueType >> &global_solution)

Setup the vectors with default values and allocate mameory if not allocated.

virtual void setup_local_matrices (Settings &settings, Metadata
 ValueType, IndexType > &metadata, std::vector< unsigned int > &partition_indices, std::shared_ptr< gko::matrix::Csr< ValueType, IndexCype >> &global_matrix, std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> &local_matrix, std::shared_ptr< gko::matrix::Permutation< IndexType >> &local_perm, std::shared_ptr< gko::matrix::Permutation< IndexType >> &local_inv_perm)=0

Sets up the local and the interface matrices from the global matrix and the partition indices.

Public Attributes

std::vector< unsigned int > partition_indices

The partition indices containing the subdomains to which each row(vertex) of the matrix(graph) belongs to.

std::vector< unsigned int > cell_weights

The cell weights for the partition algorithm.

Additional Inherited Members

7.9.1 Detailed Description

template<typename ValueType = gko::default_precision, typename IndexType = gko::int32> class SchwarzWrappers::Initialize< ValueType, IndexType >

The initialization class that provides methods for initialization of the solver.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

Generated by Doxygen

Initialization

7.9.2 Member Function Documentation

7.9.2.1 generate_rhs()

Generates the right hand side vector.

Parameters

```
rhs The rhs vector.
```

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

```
79 {
80     std::uniform_real_distribution<double> unif(0.0, 1.0);
81     std::default_random_engine engine;
82     for (gko::size_type i = 0; i < rhs.size(); ++i) {
83         rhs[i] = unif(engine);
84     }
85 }</pre>
```

7.9.2.2 partition()

The partitioning function.

Allows the partition of the global matrix depending with METIS and a regular 1D decomposition.

Parameters

settings	The settings struct.
metadata	The metadata struct.
global_matrix	The global matrix.
partition_indices	The partition indices [OUTPUT].

References SchwarzWrappers::Metadata < ValueType, IndexType >::global_size, SchwarzWrappers::Metadata < ValueType, IndexType >::my_rank, SchwarzWrappers::Metadata < ValueType, IndexType >::num_subdomains, and SchwarzWrappers::Settings::write debug out.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

```
263 {
        partition_indices.resize(metadata.global_size);
264
265
        if (metadata.my_rank == 0) {
266
            auto partition_settings =
267
                 (Settings::partition_settings::partition_zoltan |
268
                  Settings::partition_settings::partition_metis |
269
                  Settings::partition_settings::partition_regular
270
                  Settings::partition_settings::partition_regular2d
271
                  Settings::partition_settings::partition_custom) &
                 settings.partition;
273
274
            if (partition_settings ==
                 Settings::partition_settings::partition_zoltan) {
SCHWARZ_NOT_IMPLEMENTED;
2.75
276
            } else if (partition_settings =
278
                        Settings::partition_settings::partition_metis) {
                 if (metadata.my_rank == 0)
279
280
                     std::cout << " METIS partition" << std::endl;</pre>
281
282
                 PartitionTools::PartitionMetis(
283
                     settings, global_matrix, this->cell_weights,
284
                     metadata.num_subdomains, partition_indices);
285
            } else if (partition_settings =
                        Settings::partition_settings::partition_regular) {
286
                 if (metadata.my_rank == 0) {
    std::cout << " Regular 1D partition" << std::endl;</pre>
287
288
289
290
                 PartitionTools::PartitionRegular(
291
                     global_matrix, metadata.num_subdomains, partition_indices);
292
            } else if (partition_settings ==
293
                        Settings::partition_settings::partition_regular2d) {
                 if (metadata.my_rank == 0) {
   std::cout << " Regular 2D partition" << std::endl;</pre>
294
295
296
                 PartitionTools::PartitionRegular2D(
298
                     global_matrix, settings.write_debug_out,
299
                     metadata.num_subdomains, partition_indices);
             } else if (partition_settings ==
300
301
                        Settings::partition_settings::partition_custom) {
302
                 // User partitions mesh manually
303
                 SCHWARZ_NOT_IMPLEMENTED;
304
305
                 SCHWARZ_NOT_IMPLEMENTED;
306
307
308 }
```

7.9.2.3 setup_global_matrix_laplacian()

Generates the 2D global laplacian matrix.

Parameters

oned_laplacian_size	The size of the one d laplacian grid.
global_matrix	The global matrix.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

```
201 {
202
         using index_type = IndexType;
         using value_type = ValueType;
203
2.04
         using mtx = gko::matrix::Csr<value_type, index_type>;
205
         gko::size_type global_size = oned_laplacian_size
       oned laplacian size:
206
207
         global_matrix = mtx::create(settings.executor->get_master(),
208
                                         gko::dim<2>(global_size), 5 * global_size);
         value_type *values = global_matrix->get_values();
209
         index_type *row_ptrs = global_matrix->get_row_ptrs();
index_type *col_idxs = global_matrix->get_col_idxs();
210
211
212
213
         std::vector<gko::size_type> exclusion_set;
214
215
         std::map<IndexType, ValueType> stencil_map = {
              {-oned_laplacian_size, -1}, {-1, -1}, {0, 4}, {1, -1}, {oned_laplacian_size, -1},
216
217
218
219
         for (auto i = 2; i < global_size; ++i) {</pre>
220
              gko::size_type index = (i - 1) * oned_laplacian_size;
221
              if (index * index < global_size * global_size) {</pre>
222
                  {\tt exclusion\_set.push\_back}\,(
223
                      linearize index(index, index - 1, global size));
224
                  exclusion set.push back(
225
                      linearize_index(index - 1, index, global_size));
226
227
228
229
         std::sort(exclusion_set.begin(),
                    exclusion_set.begin() + exclusion_set.size());
230
231
232
         IndexType pos = 0;
233
         IndexType col_idx = 0;
         row_ptrs[0] = pos;
234
235
         gko::size_type cur_idx = 0;
         for (IndexType i = 0; i < global_size; ++i) {
    for (auto ofs : stencil_map) {</pre>
236
237
238
                  auto in_exclusion_flag =
239
                      (exclusion_set[cur_idx] ==
240
                       linearize_index(i, i + ofs.first, global_size));
                  if (0 <= i + ofs.first && i + ofs.first < global_size &&
   !in_exclusion_flag) {</pre>
2.41
242
243
                      values[pos] = ofs.second;
244
                       col_idxs[pos] = i + ofs.first;
245
246
2.47
                  if (in_exclusion_flag) {
248
                       cur_idx++;
249
250
                  col_idx = row_ptrs[i + 1] - pos;
251
252
              row_ptrs[i + 1] = pos;
253
254 }
```

7.9.2.4 setup_local_matrices()

Sets up the local and the interface matrices from the global matrix and the partition indices.

Parameters

settings	The settings struct.
metadata	The metadata struct.
partition_indices	The array containing the partition indices.
global_matrix	The global system matrix.
local_matrix	The local system matrix.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.
local_perm	The local permutation, obtained through RCM or METIS.

Implemented in SchwarzWrappers::SolverRAS< ValueType, IndexType >.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

7.9.2.5 setup_vectors()

Setup the vectors with default values and allocate mameory if not allocated.

Parameters

settings	The settings struct.
metadata	The metadata struct.
local_rhs	The local right hand side vector in the subdomain.
global_rhs	The global right hand side vector.
local_solution	The local solution vector in the subdomain.
global_solution	The global solution vector.

References SchwarzWrappers::Settings::executor, SchwarzWrappers::Metadata < ValueType, IndexType > :: ::first_row, SchwarzWrappers::Metadata < ValueType, IndexType > :: :global_size, SchwarzWrappers::Metadata < ValueType, IndexType > :: indexType > :: :my_rank.

Referenced by SchwarzWrappers::SchwarzBase< ValueType, IndexType >::initialize().

```
319 {
320     using vec = gko::matrix::Dense<ValueType>;
321     auto my_rank = metadata.my_rank;
322     auto first_row = metadata.first_row->get_data()[my_rank];
323
324     // Copy the global rhs vector to the required executor.
325     gko::Array<ValueType> temp_rhs{settings.executor->get_master(), rhs.begin(),
```

```
rhs.end()};
        global_rhs = vec::create(settings.executor,
328
                                 gko::dim<2>{metadata.global_size, 1}, temp_rhs, 1);
329
       global_solution = vec::create(settings.executor->get_master(),
330
                                      gko::dim<2>(metadata.global_size, 1));
331
332
       local_rhs =
333
            vec::create(settings.executor, gko::dim<2>(metadata.local_size_x, 1));
334
        // Extract the local rhs from the global rhs. Also takes into account the
335
336
       SolverTools::extract_local_vector(settings, metadata, local_rhs, global_rhs,
337
                                          first row):
338
339
       local_solution =
340
            vec::create(settings.executor, gko::dim<2>(metadata.local_size_x, 1));
341 }
```

The documentation for this class was generated from the following files:

- initialization.hpp (d6ef4fd)
- /home/runner/work/schwarz-lib/schwarz-lib/source/initialization.cpp (d6ef4fd)

7.10 SchwarzWrappers::Metadata < ValueType, IndexType > Struct Template Reference

The solver metadata struct.

```
#include <settings.hpp>
```

Public Attributes

• MPI_Comm mpi_communicator

The MPI communicator.

• gko::size_type global_size = 0

The size of the global matrix.

• gko::size_type oned_laplacian_size = 0

The size of the 1 dimensional laplacian grid.

• gko::size_type local_size = 0

The size of the local subdomain matrix.

gko::size_type local_size_x = 0

The size of the local subdomain matrix + the overlap.

• gko::size_type local_size_o = 0

The size of the local subdomain matrix + the overlap.

• gko::size_type overlap_size = 0

The size of the overlap between the subdomains.

• gko::size_type num_subdomains = 1

The number of subdomains used within the solver.

· int my_rank

The rank of the subdomain.

int my_local_rank

The local rank of the subdomain.

• int local_num_procs

The local number of procs in the subdomain.

int comm_size

The number of subdomains used within the solver, size of the communicator.

· int num_threads

The number of threads used within the solver for each subdomain.

IndexType iter_count

The iteration count of the solver.

ValueType tolerance

The tolerance of the complete solver.

ValueType local_solver_tolerance

The tolerance of the local solver in case of an iterative solve.

IndexType max_iters

The maximum iteration count of the solver.

• unsigned int precond_max_block_size

The maximum block size for the preconditioner.

• ValueType current_residual_norm = -1.0

The current residual norm of the subdomain.

• ValueType min_residual_norm = -1.0

The minimum residual norm of the subdomain.

• std::vector< std::tuple< int, int, int, std::string, std::vector< ValueType >>> time_struct

The struct used to measure the timings of each function within the solver loop.

• std::vector< std::tuple< int, std::vector< std::tuple< int, int >>, std::vector< std::tuple< int, int >>, int, int >> comm_data_struct

The struct used to measure the timings of each function within the solver loop.

std::shared_ptr< gko::Array< IndexType > > global_to_local

The mapping containing the global to local indices.

std::shared_ptr< gko::Array< IndexType > > local_to_global

The mapping containing the local to global indices.

 $\bullet \quad std::shared_ptr < gko::Array < IndexType >> overlap_row$

The overlap row indices.

std::shared_ptr< gko::Array< IndexType > > first_row

The starting row of each subdomain in the matrix.

std::shared ptr< gko::Array< IndexType > > permutation

The permutation used for the re-ordering.

 $\bullet \quad std::shared_ptr < gko::Array < IndexType >> i_permutation \\$

The inverse permutation used for the re-ordering.

7.10.1 Detailed Description

template < typename ValueType, typename IndexType > struct SchwarzWrappers::Metadata < ValueType, IndexType >

The solver metadata struct.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

7.10.2 Member Data Documentation

7.10.2.1 local_solver_tolerance

```
template<typename ValueType, typename IndexType>
ValueType SchwarzWrappers::Metadata< ValueType, IndexType >::local_solver_tolerance
```

The tolerance of the local solver in case of an iterative solve.

The residual norm reduction required.

7.10.2.2 tolerance

```
template<typename ValueType, typename IndexType>
ValueType SchwarzWrappers::Metadata< ValueType, IndexType >::tolerance
```

The tolerance of the complete solver.

The residual norm reduction required.

The documentation for this struct was generated from the following file:

settings.hpp (d6ef4fd)

7.11 MetisError Class Reference

MetisError is thrown when a METIS routine throws a non-zero error code.

```
#include <exception.hpp>
```

Public Member Functions

MetisError (const std::string &file, int line, const std::string &func, int error_code)
 Initializes a METIS error.

7.11.1 Detailed Description

MetisError is thrown when a METIS routine throws a non-zero error code.

7.11.2 Constructor & Destructor Documentation

7.11.2.1 MetisError()

Initializes a METIS error.

Parameters

file	The name of the offending source file	
line	The source code line number where the error occurred	
func	The name of the METIS routine that failed	
error_code	The resulting METIS error code	

```
182 : Error(file, line, func + ": " + get_error(error_code))
183      {}
```

The documentation for this class was generated from the following files:

- exception.hpp (d6ef4fd)
- /home/runner/work/schwarz-lib/schwarz-lib/source/exception.cpp (d6ef4fd)

7.12 SchwarzWrappers::SchwarzBase< ValueType, IndexType > Class Template Reference

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

```
#include <schwarz_base.hpp>
```

Public Member Functions

SchwarzBase (Settings &settings, Metadata < ValueType, IndexType > &metadata)

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

• void initialize ()

Initialize the matrix and vectors.

void run (std::shared_ptr< gko::matrix::Dense< ValueType >> &solution)

The function that runs the actual solver and obtains the final solution.

void print_vector (const std::shared_ptr< gko::matrix::Dense< ValueType >> &vector, int subd, std::string name)

The auxiliary function that prints a passed in vector.

• void print_matrix (const std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> &matrix, int rank, std::string name)

The auxiliary function that prints a passed in CSR matrix.

Public Attributes

- std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > local_matrix
 The local subdomain matrix.
- std::shared_ptr< gko::matrix::Permutation< IndexType > > local_perm
 The local subdomain permutation matrix/array.
- std::shared_ptr< gko::matrix::Permutation< IndexType > > local_inv_perm
 The local subdomain inverse permutation matrix/array.
- std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > triangular_factor
 The local triangular factor used for the triangular solves.
- std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > interface_matrix
 The local interface matrix.
- std::shared_ptr< gko::matrix::Csr< ValueType, IndexType > > global_matrix
 The global matrix.
- std::shared_ptr< gko::matrix::Dense< ValueType >> local_rhs
 The local right hand side.
- std::shared_ptr< gko::matrix::Dense< ValueType > > global_rhs
 The global right hand side.
- std::shared_ptr< gko::matrix::Dense< ValueType >> local_solution
 The local solution vector.
- std::shared_ptr< gko::matrix::Dense< ValueType >> global_solution
 The global solution vector.

Additional Inherited Members

7.12.1 Detailed Description

 $template < typename\ ValueType = gko::default_precision,\ typename\ IndexType = gko::int32 > class\ SchwarzWrappers::SchwarzBase < ValueType,\ IndexType >$

The Base solver class is meant to be the class implementing the common implementations for all the schwarz methods.

It derives from the Initialization class, the Communication class and the Solve class all of which are templated.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

7.12.2 Constructor & Destructor Documentation

7.12.2.1 SchwarzBase()

```
template<trypename ValueType , typename IndexType >
SchwarzWrappers::SchwarzBase< ValueType, IndexType >::SchwarzBase (
```

```
Settings & settings,
Metadata< ValueType, IndexType > & metadata )
```

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

Parameters

settings	The settings struct.
metadata	The metadata struct.

References SchwarzWrappers::Metadata< ValueType, IndexType >::comm_size, SchwarzWrappers::Settings← SchwarzWrappers::Settings::executor, SchwarzWrappers::Settings::executor string, ::cuda device guard, SchwarzWrappers::Metadata < ValueType, IndexType >::first_row, SchwarzWrappers::Communicate < Value← Type, IndexType >::comm_struct::get_displacements, SchwarzWrappers::Communicate < ValueType, IndexType >::comm_struct::global_get, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::global_← put, SchwarzWrappers::Metadata< ValueType, IndexType >::global size, SchwarzWrappers::Metadata< Value ↔ Type, IndexType >::global_to_local, SchwarzWrappers::Metadata< ValueType, IndexType >::i_permutation, SchwarzWrappers::Communicate< ValueType, IndexType >::comm struct::is local neighbor, Schwarz⇔ Wrappers::Communicate< ValueType, IndexType >::comm struct::local neighbors in, SchwarzWrappers::← Communicate < ValueType, IndexType >::comm struct::local neighbors out, SchwarzWrappers::Metadata < $ValueType, \ \ IndexType \ > :: local_num_procs, \ \ SchwarzWrappers :: Metadata < \ \ ValueType, \ \ IndexType \ > :: local_ \hookleftarrow$ to_global, SchwarzWrappers::Metadata< ValueType, IndexType >::mpi_communicator, SchwarzWrappers↔ ::Metadata < ValueType, IndexType >::my_local_rank, SchwarzWrappers::Metadata < ValueType, IndexType >::my rank, SchwarzWrappers::Communicate< ValueType, IndexType >::comm struct::neighbors in, Schwarz Wrappers::Communicate< ValueType, IndexType >::comm_struct::neighbors_out, SchwarzWrappers::Metadata< ValueType, IndexType >::num_subdomains, SchwarzWrappers::Metadata < ValueType, IndexType >::permutation, and SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::put_displacements.

```
50
       : Initialize<ValueType, IndexType>(settings, metadata),
51
         settings (settings),
52
         metadata (metadata)
53 {
       using vec_itype = gko::Array<IndexType>;
55
       using vec_vecshared = gko::Array<IndexType *>;
56
       metadata.my_local_rank =
           Utils<ValueType, IndexType>::get_local_rank(metadata.mpi_communicator);
57
58
      metadata.local_num_procs = Utils<ValueType, IndexType>::get_local_num_procs(
          metadata.mpi communicator);
59
       auto my_local_rank = metadata.my_local_rank;
       if (settings.executor_string == "omp")
62
           settings.executor = gko::OmpExecutor::create();
63
          auto exec_info =
               static_cast<gko::OmpExecutor *>(settings.executor.get())
64
65
                    ->get_exec_info();
          exec_info->bind_to_core(metadata.my_local_rank);
68
       } else if (settings.executor_string == "cuda") {
69
           int num_devices = 0;
70 #if SCHW HAVE CUDA
           SCHWARZ_ASSERT_NO_CUDA_ERRORS(cudaGetDeviceCount(&num_devices));
71
72
  #else
           SCHWARZ_NOT_IMPLEMENTED;
73
74 #endif
7.5
           if (num_devices > 0) {
               if (metadata.my_rank == 0) {
   std::cout << " Number of available devices: " << num_devices</pre>
76
78
                              << std::endl;
80
           } else {
               std::cout << " No CUDA devices available for rank "
81
82
                         << metadata.my_rank << std::endl;
               std::exit(-1);
83
           settings.executor = gko::CudaExecutor::create(
               my_local_rank, gko::OmpExecutor::create());
87
           auto exec_info = static_cast<gko::OmpExecutor *>(
88
                                 settings.executor->get_master().get())
           ->get_exec_info();
exec_info->bind_to_core(my_local_rank);
89
90
           settings.cuda_device_guard =
```

```
std::make_shared<SchwarzWrappers::device_quard>(my_local_rank);
           std::cout << " Rank " << metadata.my_rank << " with local rank " \,
94
9.5
                      << my_local_rank << " has
96
                      << (static_cast<gko::CudaExecutor *>(settings.executor.get()))
                              ->get device id()
                      << " id of gpu" << std::endl;
98
99
           MPI_Barrier(metadata.mpi_communicator);
100
        } else if (settings.executor_string == "reference") {
101
            settings.executor = gko::ReferenceExecutor::create();
102
            auto exec_info =
103
               static_cast<qko::ReferenceExecutor *>(settings.executor.get())
104
                     ->get_exec_info();
105
            exec_info->bind_to_core(my_local_rank);
106
107
108
        auto my_rank = this->metadata.my_rank;
109
        auto comm_size = this->metadata.comm_size;
        auto num_subdomains = this->metadata.num_subdomains;
110
111
        auto global_size = this->metadata.global_size;
112
113
        // Some arrays for partitioning and local matrix creation.
114
        metadata.first_row = std::shared_ptr<vec_itype>(
115
            new vec_itype(settings.executor->get_master(), num_subdomains + 1),
            std::default_delete<vec_itype>());
116
        metadata.permutation = std::shared_ptr<vec_itype>(
117
118
            new vec_itype(settings.executor->get_master(), global_size),
119
            std::default_delete<vec_itype>());
120
        metadata.i_permutation = std::shared_ptr<vec_itype>(
121
            new vec_itype(settings.executor->get_master(), global_size),
        std::default_delete<vec_itype>());
metadata.global_to_local = std::shared_ptr<vec_itype>(
122
123
124
            new vec_itype(settings.executor->get_master(), global_size),
125
            std::default_delete<vec_itype>());
126
        metadata.local_to_global = std::shared_ptr<vec_itype>(
127
            new vec_itype(settings.executor->get_master(), global_size),
128
            std::default_delete<vec_itype>());
129
130
        // Some arrays for communication.
131
        comm_struct.local_neighbors_in = std::shared_ptr<vec_itype>(
132
            new vec_itype(settings.executor->get_master(), num_subdomains + 1),
133
            std::default_delete<vec_itype>());
        comm_struct.local_neighbors_out = std::shared_ptr<vec_itype>(
134
135
            new vec_itype(settings.executor->get_master(), num_subdomains + 1),
136
            std::default_delete<vec_itype>());
        comm_struct.neighbors_in = std::shared_ptr<vec_itype>(
137
138
           new vec_itype(settings.executor->get_master(), num_subdomains + 1),
139
            std::default_delete<vec_itype>());
        comm_struct.neighbors_out = std::shared_ptr<vec_itype>(
140
            new vec_itype(settings.executor->get_master(), num_subdomains + 1),
141
            std::default_delete<vec_itype>());
142
        comm_struct.is_local_neighbor = std::vector<bool>(
      num_subdomains + 1, 0);
144
        comm_struct.global_get = std::shared_ptr<vec_vecshared>(
145
            new vec_vecshared(settings.executor->get_master(), num_subdomains + 1),
        std::default_delete<vec_vecshared>());
comm_struct.global_put = std::shared_ptr<vec_vecshared>(
146
147
148
            new vec_vecshared(settings.executor->get_master(), num_subdomains + 1),
149
            std::default_delete<vec_vecshared>());
150
        \ensuremath{//} Need this to initialize the arrays with zeros
151
        std::vector<IndexType> temp(num_subdomains + 1, 0);
comm_struct.get_displacements = std::shared_ptr<vec_itype>(
152
153
            new vec_itype(settings.executor->get_master(), temp.begin(),
154
                           temp.end()),
            std::default_delete<vec_itype>());
155
156
        comm_struct.put_displacements = std::shared_ptr<vec_itype>(
157
            new vec_itype(settings.executor->get_master(), temp.begin(),
                           temp.end()),
158
159
            std::default delete<vec itvpe>());
160 }
```

7.12.3 Member Function Documentation

7.12.3.1 print_matrix()

```
template<trypename ValueType = gko::default_precision, typename IndexType = gko::int32>
void SchwarzWrappers::SchwarzBase< ValueType, IndexType >::print_matrix (
```

```
const std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> & matrix,
int rank,
std::string name )
```

The auxiliary function that prints a passed in CSR matrix.

Parameters

matrix	The matrix to be printed.
subd	The subdomain on which the vector exists.
name	The name of the matrix as a string.

7.12.3.2 print_vector()

The auxiliary function that prints a passed in vector.

Parameters

vector	The vector to be printed.
subd	The subdomain on which the vector exists.
name	The name of the vector as a string.

7.12.3.3 run()

The function that runs the actual solver and obtains the final solution.

Parameters

solution	The solution vector.

References SchwarzWrappers::Communicate< ValueType, IndexType >::exchange_boundary(), Schwarz Wrappers::Settings::executor, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::global_rhs, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::global_rhs, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local wrappers::SchwarzBase< ValueType, IndexType >::local_matrix, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_matrix, SchwarzWrappers::wrappers::wrappers::SchwarzBase< ValueType, IndexType >::local_perm, SchwarzWrappers::SchwarzBase< ValueType, IndexType

>::local_rhs, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_solution, SchwarzWrappers::Communicate< ValueType, IndexType >::setup_windows(), SchwarzWrappers::SchwarzBase< ValueType, IndexType >::triangular_factor, and SchwarzWrappers::Communicate< ValueType, IndexType >::update_
boundary().

```
335 {
336
        using vec_vtype = gko::matrix::Dense<ValueType>;
337
           The main solution vector
338
        std::shared_ptr<vec_vtype> solution_vector = vec_vtype::create(
339
            settings.executor, gko::dim<2>(metadata.global_size, 1));
340
        // A temp local solution
341
        std::shared_ptr<vec_vtype> init_guess =
            vec_vtype::create(settings.executor, this->local_solution->get_size());
342
        // A global gathered solution of the previous iteration.
343
        std::shared_ptr<vec_vtype> global_old_solution = vec_vtype::create(
344
345
             settings.executor, gko::dim<2>(metadata.global_size, 1));
346
        // Setup the windows for the onesided communication.
347
        this->setup_windows(settings, metadata, solution_vector);
348
349
        const auto solver_settings =
350
             (Settings::local_solver_settings::direct_solver_cholmod |
351
              Settings::local_solver_settings::direct_solver_ginkgo
352
              Settings::local_solver_settings::iterative_solver_dealii |
353
             Settings::local_solver_settings::iterative_solver_ginkgo) &
354
             settings.local_solver;
355
356
        ValueType local_residual_norm = -1.0, local_residual_norm0 = -1.0,
357
                   global_residual_norm = 0.0, global_residual_norm0 = -1.0;
358
        metadata.iter_count = 0;
359
        auto start_time = std::chrono::steady_clock::now();
360
        int num_converged_procs = 0;
361
362
        for (; metadata.iter_count < metadata.max_iters; ++(metadata.iter_count)) {</pre>
363
                Exchange the boundary values. The communication part.
             MEASURE_ELAPSED_FUNC_TIME(
364
365
                 this->exchange_boundary(settings, metadata, solution_vector), 0,
366
                 metadata.my_rank, boundary_exchange, metadata.iter_count);
367
368
             // Update the boundary and interior values after the exchanging from
369
             // other processes.
370
             MEASURE_ELAPSED_FUNC_TIME(
371
                 this->update_boundary(settings, metadata, this->
      local_solution,
372
                                         this->local_rhs, solution_vector,
                                         global_old_solution, this->interface_matrix),
373
374
                 1, metadata.my_rank, boundary_update, metadata.iter_count);
375
376
             // Check for the convergence of the solver.
377
             num_converged_procs = 0;
            MEASURE_ELAPSED_FUNC_TIME(
378
                 (Solve<ValueType, IndexType>::check_convergence(
379
                     settings, metadata, this->comm_struct, this->convergence_vector,
380
                     global_old_solution, this->local_solution, this->
      local_matrix,
382
                     local_residual_norm, local_residual_norm0, global_residual_norm,
383
                     global_residual_norm0, num_converged_procs)),
384
                 2, metadata.my_rank, convergence_check, metadata.iter_count);
385
             // break if the solution diverges.
386
387
             if (std::isnan(global_residual_norm) || global_residual_norm > 1e12) {
                 std::cout << " Rank " << metadata.my_rank << " diverged in ' << metadata.iter_count << " iters " << std::endl;
388
389
                 std::exit(-1);
390
391
392
393
             // break if all processes detect that all other processes have
394
             // converged otherwise continue iterations
395
             if (num_converged_procs == metadata.num_subdomains) {
396
                 break;
397
             } else {
398
                 MEASURE_ELAPSED_FUNC_TIME(
399
                     (Solve<ValueType, IndexType>::local_solve(
400
                         settings, metadata, this->triangular_factor,
401
                         this->local_perm, this->local_inv_perm, init_guess,
402
                         this->local_solution)),
                 3, metadata.my_rank, local_solve, metadata.iter_count);
// init_guess->copy_from(this->local_solution.get());
// Gather the local vector into the locally global vector for
403
404
405
                 // communication.
406
407
                 MEASURE_ELAPSED_FUNC_TIME(
408
                     (Communicate<ValueType, IndexType>::local_to_global_vector
409
                          settings, metadata, this->local_solution, solution_vector)),
410
                     4, metadata.my_rank, expand_local_vec, metadata.iter_count);
```

```
411
412
413
        MPI_Barrier(MPI_COMM_WORLD);
        auto elapsed_time = std::chrono::duration<ValueType>(
414
        415
416
417
        ValueType mat_norm = -1.0, rhs_norm = -1.0, sol_norm = -1.0, residual_norm = -1.0;
418
419
        \ensuremath{//} Compute the final residual norm. Also gathers the solution from all
420
421
        // subdomains.
        Solve<ValueType, IndexType>::compute_residual_norm(
422
             settings, metadata, global_matrix, global_rhs, solution_vector,
mat_norm, rhs_norm, sol_norm, residual_norm);
423
424
425
        gather_comm_data<ValueType, IndexType>(
426
            metadata.num_subdomains, this->comm_struct, metadata.comm_data_struct);
         // clang-format off
427
        if (metadata.my_rank == 0)
428
429
430
             std::cout
                    << " residual norm " << residual_norm << "\n"
<< " relative residual norm of solution " << residual_norm/rhs_norm << "\n"
<< " Time taken for solve " << elapsed_time.count()</pre>
431
432
433
434
                    << std::endl:
435
            if (num_converged_procs < metadata.num_subdomains)</pre>
436
                  std::cout << " Did not converge in " << metadata.iter_count << " iterations."
437
438
439
                             << std::endl;
440
               }
        }
// clang-format on
441
442
443
        if (metadata.my_rank == 0) {
444
             solution->copy_from(solution_vector.get());
445
446
        // Communicate<ValueType, IndexType>::clear(settings);
447
```

The documentation for this class was generated from the following files:

- schwarz_base.hpp (d6ef4fd)
- /home/runner/work/schwarz-lib/schwarz-lib/source/schwarz_base.cpp (d6ef4fd)

7.13 SchwarzWrappers::Settings Struct Reference

The struct that contains the solver settings and the parameters to be set by the user.

```
#include <settings.hpp>
```

Classes

• struct comm_settings

The settings for the various available communication paradigms.

struct convergence_settings

The various convergence settings available.

Public Types

· enum partition_settings

The partition algorithm to be used for partitioning the matrix.

enum local_solver_settings

The local solver algorithm for the local subdomain solves.

Public Attributes

· std::string executor_string

The string that contains the ginkgo executor paradigm.

std::shared_ptr< gko::Executor > executor = gko::ReferenceExecutor::create()

The ginkgo executor the code is to be executed on.

std::shared_ptr< device_guard > cuda_device_guard

The ginkgo executor the code is to be executed on.

• gko::int32 overlap = 2

The overlap between the subdomains.

• bool explicit_laplacian = true

Flag if the laplcian matrix should be generated within the library.

• bool enable random rhs = false

Flag to enable a random rhs.

• bool print_matrices = false

Flag to enable printing of matrices.

• bool debug print = false

Flag to enable some debug printing.

• bool naturally_ordered_factor = false

Disables the re-ordering of the matrix before computing the triangular factors during the CHOLMOD factorization.

• std::string metis_objtype

This setting defines the objective type for the metis partitioning.

bool use precond = false

Enable the block jacobi local preconditioner for the local solver.

• bool write debug out = false

Enable the writing of debug out to file.

• bool write_perm_data = false

Enable the local permutations from CHOLMOD to a file.

• int shifted_iter = 1

Iteration shift for node local communication.

· std::string reorder

The reordering for the local solve.

7.13.1 Detailed Description

The struct that contains the solver settings and the parameters to be set by the user.

settings

7.13.2 Member Data Documentation

7.13.2.1 explicit_laplacian

```
bool SchwarzWrappers::Settings::explicit_laplacian = true
```

Flag if the laplcian matrix should be generated within the library.

If false, an external matrix and rhs needs to be provided

 $Referenced \ by \ Schwarz Wrappers:: Schwarz Base < Value Type, \ Index Type > :: initialize ().$

7.13.2.2 naturally_ordered_factor

```
bool SchwarzWrappers::Settings::naturally_ordered_factor = false
```

Disables the re-ordering of the matrix before computing the triangular factors during the CHOLMOD factorization.

Note

This is mainly to allow compatibility with GPU solution.

The documentation for this struct was generated from the following file:

settings.hpp (d6ef4fd)

7.14 SchwarzWrappers::Solve ValueType, IndexType > Class Template Reference

The Solver class the provides the solver and the convergence checking methods.

```
#include <solve.hpp>
```

Additional Inherited Members

7.14.1 Detailed Description

template < typename ValueType = gko::default_precision, typename IndexType = gko::int32 > class SchwarzWrappers::Solve < ValueType, IndexType >

The Solver class the provides the solver and the convergence checking methods.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

Solve

The documentation for this class was generated from the following files:

- solve.hpp (d6ef4fd)
- · /home/runner/work/schwarz-lib/schwarz-lib/source/solve.cpp (d6ef4fd)

7.15 SchwarzWrappers::SolverRAS< ValueType, IndexType > Class Template Reference

An implementation of the solver interface using the RAS solver.

```
#include <restricted_schwarz.hpp>
```

Public Member Functions

SolverRAS (Settings &settings, Metadata < ValueType, IndexType > &metadata)

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

Sets up the local and the interface matrices from the global matrix and the partition indices.

void setup_comm_buffers () override

Sets up the communication buffers needed for the boundary exchange.

Sets up the windows needed for the asynchronous communication.

 void exchange_boundary (const Settings &settings, const Metadata < ValueType, IndexType > &metadata, std::shared_ptr < gko::matrix::Dense < ValueType >> &solution_vector) override

Exchanges the elements of the solution vector.

void update_boundary (const Settings &settings, const Metadata< ValueType, IndexType > &metadata, std::shared_ptr< gko::matrix::Dense< ValueType >> &local_solution, const std::shared_ptr< gko::matrix::Dense< ValueType >> &local_rhs, const std::shared_ptr< gko::matrix::Dense< ValueType >> &solution_vector, std::shared_ptr< gko::matrix::Dense< ValueType >> &global_old_solution, const std::shared_ptr< gko::matrix::Csr< ValueType, IndexType >> &interface_matrix) override

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

Additional Inherited Members

7.15.1 Detailed Description

template<typename ValueType = gko::default_precision, typename IndexType = gko::int32> class SchwarzWrappers::SolverRAS< ValueType, IndexType >

An implementation of the solver interface using the RAS solver.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

7.15.2 Constructor & Destructor Documentation

7.15.2.1 SolverRAS()

```
template<typename ValueType , typename IndexType >
SchwarzWrappers::SolverRAS< ValueType, IndexType >::SolverRAS (
```

```
Settings & settings,
Metadata< ValueType, IndexType > & metadata )
```

The constructor that takes in the user settings and a metadata struct containing the solver metadata.

Parameters

settings	The settings struct.
metadata	The metadata struct.
data	The additional data struct.

```
50 : SchwarzBase<ValueType, IndexType>(settings, metadata)
51 {}
```

7.15.3 Member Function Documentation

7.15.3.1 exchange_boundary()

Exchanges the elements of the solution vector.

Parameters

settings	The settings struct.
metadata	The metadata struct.
solution_vector	The solution vector being exchanged between the subdomains.

Implements SchwarzWrappers::Communicate < ValueType, IndexType >.

 $References\ Schwarz\ Wrappers:: Settings:: comm_settings:: enable_one sided.$

7.15.3.2 setup_local_matrices()

Sets up the local and the interface matrices from the global matrix and the partition indices.

Parameters

settings	The settings struct.
metadata	The metadata struct.
partition_indices	The array containing the partition indices.
global_matrix	The global system matrix.
local_matrix	The local system matrix.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.
local_perm	The local permutation, obtained through RCM or METIS.

Implements SchwarzWrappers::Initialize < ValueType, IndexType >.

References SchwarzWrappers::Metadata< ValueType, IndexType >::comm_size, SchwarzWrappers::Settings
::executor, SchwarzWrappers::Metadata< ValueType, IndexType >::first_row, SchwarzWrappers::SchwarzBase<
ValueType, IndexType >::global_matrix, SchwarzWrappers::Metadata< ValueType, IndexType >::global_size, SchwarzWrappers::Metadata< ValueType, IndexType >::global_to_local, SchwarzWrappers::Metadata< Value
Type, IndexType >::i_permutation, SchwarzWrappers::SchwarzBase< ValueType, IndexType, IndexType, IndexType >::interface_matrix, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_matrix, SchwarzWrappers::Metadata< Value
Type, IndexType >::local_size, SchwarzWrappers::Metadata< ValueType, IndexType >::local_size_o, Schwarz
Wrappers::Metadata< ValueType, IndexType >::local_size_x, SchwarzWrappers::Metadata< ValueType, IndexType >::my_rank, SchwarzWrappers::

Metadata< ValueType, IndexType >::num_subdomains, SchwarzWrappers::Settings::overlap, SchwarzWrappers
::Metadata< ValueType, IndexType >::overlap_row, SchwarzWrappers::Metadata< ValueType, IndexType, IndexType >::overlap_row, SchwarzWrappers::Metadata< ValueType, IndexType, IndexType >::overlap_size, and SchwarzWrappers::Metadata< ValueType, IndexType >::permutation.

```
63 {
64
       using mtx = gko::matrix::Csr<ValueType, IndexType>;
       using vec_itype = gko::Array<IndexType>;
using perm_type = gko::matrix::Permutation<IndexType>;
6.5
66
       using arr = gko::Array<IndexType>;
       auto my_rank = metadata.my_rank;
68
       auto comm_size = metadata.comm_size;
70
       auto num_subdomains = metadata.num_subdomains;
71
       auto global_size = metadata.global_size;
72
       auto mpi_itype = boost::mpi::get_mpi_datatype(*partition_indices.data());
73
       MPI_Bcast(partition_indices.data(), global_size, mpi_itype, 0,
75
                  MPI COMM WORLD);
76
77
       std::vector<IndexType> local_p_size(num_subdomains);
78
       auto global_to_local = metadata.global_to_local->get_data();
79
       auto local_to_global = metadata.local_to_global->get_data();
80
       auto first_row = metadata.first_row->get_data();
```

```
auto permutation = metadata.permutation->get_data();
        auto i_permutation = metadata.i_permutation->get_data();
83
84
8.5
        auto nb = (global_size + num_subdomains - 1) /
       num_subdomains;
86
       auto partition_settings =
            (Settings::partition_settings::partition_zoltan |
              Settings::partition_settings::partition_metis |
88
89
              Settings::partition_settings::partition_regular
90
             Settings::partition_settings::partition_regular2d |
91
             Settings::partition_settings::partition_custom) &
92
            settings.partition;
93
       IndexType *gmat_row_ptrs = global_matrix->get_row_ptrs();
IndexType *gmat_col_idxs = global_matrix->get_col_idxs();
94
9.5
        ValueType *gmat_values = global_matrix->get_values();
96
97
98
        // default local p size set for 1 subdomain.
        first_row[0] = 0;
99
        for (auto p = 0; p < num_subdomains; ++p) {</pre>
100
101
              local_p_size[p] = std::min(global_size - first_row[p], nb);
              first_row[p + 1] = first_row[p] + local_p_size[p];
102
103
        }
104
105
         if (partition_settings == Settings::partition_settings::partition_metis ||
106
             partition_settings ==
107
                  Settings::partition_settings::partition_regular2d) {
108
              if (num_subdomains > 1) {
                  for (auto p = 0; p < num_subdomains; p++) {</pre>
109
                      local_p_size[p] = 0;
110
111
                  for (auto i = 0; i < global_size; i++) {</pre>
112
113
                      local_p_size[partition_indices[i]]++;
114
                  first_row[0] = 0;
for (auto p = 0; p < num_subdomains; ++p) {
    first_row[p + 1] = first_row[p] + local_p_size[p];</pre>
115
116
117
118
119
                  // permutation
120
                  for (auto i = 0; i < global_size; i++) {</pre>
121
                      permutation[first_row[partition_indices[i]]] = i;
122
                       first_row[partition_indices[i]]++;
123
124
                  for (auto p = num_subdomains; p > 0; p--) {
                      first_row[p] = first_row[p - 1];
125
126
127
                  first_row[0] = 0;
128
                  // iperm
129
130
                  for (auto i = 0; i < global_size; i++) {</pre>
131
                      i_permutation[permutation[i]] = i;
132
133
134
             auto gmat_temp = mtx::create(settings.executor->get_master(),
135
136
                                              global_matrix->get_size(),
                                               global_matrix->get_num_stored_elements());
137
138
             auto nnz = 0;
139
             gmat_temp->get_row_ptrs()[0] = 0;
             for (auto row = 0; row < metadata.global_size; ++row) {
   for (auto col = gmat_row_ptrs[permutation[row]];</pre>
140
141
                       col < gmat_row_ptrs[permutation[row] + 1]; ++col) {</pre>
142
143
                      gmat_temp->get_col_idxs()[nnz] =
                           i_permutation[gmat_col_idxs[col]];
144
145
                      gmat_temp->get_values()[nnz] = gmat_values[col];
                      nnz++;
146
147
                  gmat_temp->get_row_ptrs()[row + 1] = nnz;
148
149
150
             global_matrix->copy_from(gmat_temp.get());
151
152
         for (auto i = 0; i < global_size; i++) {</pre>
153
              global_to_local[i] = 0;
              local_to_global[i] = 0;
154
155
156
         for (auto i = first_row[my_rank]; i < first_row[</pre>
157
      my_rank + 1]; i++) {
    global_to_local[i] = 1 + num;
158
              local_to_global[num] = i;
159
160
             num++;
161
         }
162
163
         IndexType old = 0;
         for (auto k = 1; k < settings.overlap; k++) {
   auto now = num;
   for (auto i = old; i < now; i++) {</pre>
164
165
166
```

```
167
                  for (auto j = gmat_row_ptrs[local_to_global[i]];
                        j < gmat_row_ptrs[local_to_global[i] + 1]; j++) {
    f (global_to_local[gmat_col_idxs[j]] == 0) {</pre>
168
169
                           local_to_global[num] = gmat_col_idxs[j];
170
171
                           global_to_local[gmat_col_idxs[j]] = 1 + num;
172
                           num++;
173
174
                  }
175
176
             old = now;
177
         metadata.local_size = local_p_size[my_rank];
178
         metadata.local_size_x = num;
metadata.local_size_o = global_size;
179
180
181
         auto local_size = metadata.local_size;
         auto local_size_x = metadata.local_size_x;
182
183
184
         metadata.overlap size = num - metadata.local size;
         metadata.overlap_row = std::shared_ptr<vec_itype>(
185
             new vec_itype(gko::Array<IndexType>::view(
186
187
                  settings.executor, metadata.overlap_size,
188
                  & (metadata.local_to_global->get_data()[metadata.local_size]))),
189
             std::default_delete<vec_itype>());
190
191
         auto nnz_local = 0;
         auto nnz_interface = 0;
192
193
194
         for (auto i = first_row[my_rank]; i < first_row[my_rank + 1]; ++i) {</pre>
              for (auto j = gmat_row_ptrs[i]; j < gmat_row_ptrs[i + 1]; j++) {
    if (global_to_local[gmat_col_idxs[j]] != 0) {</pre>
195
196
197
                       nnz local++;
198
                  } else {
199
                      std::cout << " debug: invalid edge?" << std::endl;</pre>
200
                  }
201
              }
202
203
         auto temp = 0;
         for (auto k = 0; k < metadata.overlap_size; k++) {</pre>
204
205
             temp = metadata.overlap_row->get_data()[k];
206
              for (auto j = gmat_row_ptrs[temp]; j < gmat_row_ptrs[temp + 1]; j++) {</pre>
207
                  if (global_to_local[gmat_col_idxs[j]] != 0) {
208
                       nnz_local++;
209
                  } else {
210
                       nnz_interface++;
211
212
              }
213
214
215
         std::shared_ptr<mtx> local_matrix compute;
216
         local_matrix_compute = mtx::create(settings.executor->get_master(),
217
                                                 gko::dim<2>(local_size_x), nnz_local);
         IndexType *lmat_row_ptrs = local_matrix_compute->get_row_ptrs();
IndexType *lmat_col_idxs = local_matrix_compute->get_col_idxs();
218
219
220
         ValueType *lmat_values = local_matrix_compute->get_values();
221
222
         std::shared ptr<mtx> interface matrix compute;
223
         if (nnz_interface > 0) {
224
              interface matrix compute :
                  mtx::create(settings.executor->get_master(),
225
226
                                gko::dim<2>(local_size_x), nnz_interface);
227
         } else {
             interface_matrix_compute = mtx::create(settings.executor->get_master());
228
229
230
         IndexType *imat_row_ptrs = interface_matrix_compute->get_row_ptrs();
231
232
         IndexType *imat_col_idxs = interface_matrix_compute->get_col_idxs();
233
         ValueType *imat_values = interface_matrix_compute->get_values();
234
235
         num = 0;
236
         nnz_local = 0;
237
         auto nnz_interface_temp = 0;
         lmat_row_ptrs[0] = nnz_local;
if (nnz_interface > 0) {
  imat_row_ptrs[0] = nnz_interface_temp;
238
239
240
241
242
         // Local interior matrix
243
         for (auto i = first_row[my_rank]; i < first_row[my_rank + 1]; ++i) {</pre>
244
              for (auto j = gmat_row_ptrs[i]; j < gmat_row_ptrs[i + 1]; ++j) {</pre>
245
                  if (global_to_local[gmat_col_idxs[j]] != 0) {
                       lmat_col_idxs[nnz_local] =
246
                       global_to_local[gmat_col_idxs[j]] - 1;
lmat_values[nnz_local] = gmat_values[j];
247
248
                       nnz_local++;
249
250
                  }
251
              if (nnz_interface > 0) {
2.52
                  imat_row_ptrs[num + 1] = nnz_interface_temp;
253
```

```
254
255
             lmat_row_ptrs[num + 1] = nnz_local;
256
             num++;
2.57
        }
258
259
        // Interface matrix
260
        if (nnz_interface > 0) {
261
            nnz_interface = 0;
262
             for (auto k = 0; k < metadata.overlap_size; k++) {
263
                 temp = metadata.overlap_row->get_data()[k];
                 for (auto j = gmat_row_ptrs[temp]; j < gmat_row_ptrs[temp + 1];</pre>
264
                       j++) {
265
                      if (global_to_local[gmat_col_idxs[j]] != 0) {
266
267
                          lmat_col_idxs[nnz_local] =
268
                              global_to_local[gmat_col_idxs[j]] - 1;
269
                          lmat_values[nnz_local] = gmat_values[j];
270
                          nnz_local++;
271
                     } else {
                         imat_col_idxs[nnz_interface] = gmat_col_idxs[j];
273
                          imat_values[nnz_interface] = gmat_values[j];
274
                          nnz interface++;
275
                     }
2.76
                 lmat_row_ptrs[num + 1] = nnz_local;
imat_row_ptrs[num + 1] = nnz_interface;
277
278
279
280
             }
281
282
        auto now = num;
283
        for (auto i = old; i < now; i++) {</pre>
284
            for (auto j = gmat_row_ptrs[local_to_global[i]];
                  j < gmat_row_ptrs[local_to_global[i] + 1]; j++) {</pre>
285
                    (global_to_local[gmat_col_idxs[j]] == 0) {
  local_to_global[num] = gmat_col_idxs[j];
286
287
288
                      global_to_local[gmat_col_idxs[j]] = 1 + num;
289
                     num++;
290
                 }
            }
292
293
294
        local_matrix = mtx::create(settings.executor);
295
        local_matrix->copy_from(gko::lend(local_matrix_compute));
296
        interface matrix = mtx::create(settings.executor):
297
        interface_matrix->copy_from(gko::lend(interface_matrix_compute));
```

7.15.3.3 setup_windows()

Sets up the windows needed for the asynchronous communication.

Parameters

settings	The settings struct.
metadata	The metadata struct.
main_buffer	The main buffer being exchanged between the subdomains.

Implements SchwarzWrappers::Communicate < ValueType, IndexType >.

References SchwarzWrappers::Settings::comm_settings::enable_get, SchwarzWrappers::Settings::comm_comm_settings::enable_lock_all, SchwarzWrappers::Settings::comm_settings::enable_one, SchwarzWrapperscomm_settings::enable_onesided, SchwarzWrappers::Settings::comm_settings::enable_overlap,

SchwarzWrappers::Settings::comm_settings::enable_put, SchwarzWrappers::Settings::executor, Wrappers::Communicate< ValueType, IndexType >::comm struct::get displacements, SchwarzWrappers::← Communicate < ValueType, IndexType >::comm_struct::get_request, SchwarzWrappers::Communicate < Value ← Type, IndexType >::comm_struct::global_get, SchwarzWrappers::Communicate< ValueType, IndexType >← ::comm_struct::global_put, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::is← local neighbor, SchwarzWrappers::Metadata< ValueType, IndexType >::iter count, SchwarzWrappers::↔ Communicate< ValueType, IndexType >::comm struct::local get, SchwarzWrappers::Communicate< Value ← Type, IndexType >::comm struct::local neighbors in, SchwarzWrappers::Communicate < ValueType, IndexType >::comm struct::local neighbors out, SchwarzWrappers::Communicate< ValueType, IndexType >::comm ← struct::local num neighbors in, SchwarzWrappers::Communicate< ValueType, IndexType >::comm struct ↔ ::local_num_neighbors_out, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::local ← _put, SchwarzWrappers::Metadata< ValueType, IndexType >::local_size_o, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_solution, SchwarzWrappers::Communicate< ValueType, IndexType >::comm← struct::neighbors in, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::neighbors_← out, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::num_neighbors_in, Schwarz← Wrappers::Communicate< ValueType, IndexType >::comm_struct::num_neighbors_out, SchwarzWrappers::← Metadata< ValueType, IndexType >::num subdomains, SchwarzWrappers::Communicate< ValueType, Index← Type >::comm struct::put displacements, SchwarzWrappers::Communicate< ValueType, IndexType >::comm

← _struct::put_request, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::recv_buffer, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct::remote_get, SchwarzWrappers::← Communicate < ValueType, IndexType >::comm struct::remote put, SchwarzWrappers::Communicate < Value ← Type, IndexType >::comm struct::send buffer, SchwarzWrappers::Communicate< ValueType, IndexType >← :::comm_struct::window_recv_buffer, SchwarzWrappers::Communicate< ValueType, IndexType >::comm_struct ← ::window_send_buffer, and SchwarzWrappers::Communicate < ValueType, IndexType >::comm_struct::window_x.

```
502 {
        using vec_itype = gko::Array<IndexType>;
using vec_vtype = gko::matrix::Dense<ValueType>;
503
504
505
        auto num_subdomains = metadata.num_subdomains;
        auto local_size_o = metadata.local_size_o;
506
        auto neighbors_in = this->comm_struct.neighbors_in->get_data();
507
508
        auto global_get = this->comm_struct.global_get->get_data();
509
        auto neighbors_out = this->comm_struct.neighbors_out->get_data();
510
        auto global_put = this->comm_struct.global_put->get_data();
511
512
        // set displacement for the MPI buffer
513
        auto get_displacements = this->comm_struct.get_displacements->get_data();
514
        auto put_displacements = this->comm_struct.put_displacements->get_data();
515
516
            std::vector<IndexType> tmp_num_comm_elems(num_subdomains + 1, 0);
            tmp_num_comm_elems[0] = 0;
517
            for (auto j = 0; j < this->comm_struct.num_neighbors_in; j++) {
518
                 if ((global_get[j])[0] > 0) {
                     int p = neighbors_in[j];
520
521
                     tmp_num_comm_elems[p + 1] = (global_get[j])[0];
522
                 }
523
524
            for (auto j = 0; j < num_subdomains; j++) {</pre>
525
                 tmp_num_comm_elems[j + 1] += tmp_num_comm_elems[j];
526
527
            auto mpi_itype = boost::mpi::get_mpi_datatype(tmp_num_comm_elems[0]);
528
529
            MPI_Alltoall(tmp_num_comm_elems.data(), 1, mpi_itype, put_displacements,
                          1, mpi_itype, MPI_COMM_WORLD);
530
531
        }
532
533
534
            std::vector<IndexType> tmp_num_comm_elems(num_subdomains + 1, 0);
            tmp_num_comm_elems[0] = 0;
for (auto j = 0; j < this->comm_struct.num_neighbors_out; j++) {
535
536
                 if ((global_put[j])[0] > 0) {
537
538
                     int p = neighbors_out[j];
539
                     tmp_num_comm_elems[p + 1] = (global_put[j])[0];
540
541
            for (auto j = 0; j < num subdomains; j++) {</pre>
542
543
                 tmp_num_comm_elems[j + 1] += tmp_num_comm_elems[j];
544
545
546
            auto mpi_itype = boost::mpi::get_mpi_datatype(tmp_num_comm_elems[0]);
547
            MPI_Alltoall(tmp_num_comm_elems.data(), 1, mpi_itype, get_displacements,
                          1, mpi_itype, MPI_COMM_WORLD);
548
549
        }
```

```
551
        // setup windows
552
        if (settings.comm_settings.enable_onesided) {
553
             // Onesided
554
            MPI_Win_create(main_buffer->get_values(),
                           main_buffer->get_size()[0] * sizeof(ValueType),
sizeof(ValueType), MPI_INFO_NULL, MPI_COMM_WORLD,
555
556
                            &(this->comm_struct.window_x));
557
558
559
560
561
        if (settings.comm_settings.enable_onesided) {
            // MPI_Alloc_mem ? Custom allocator ? TODO
562
            MPI_Win_create(this->local_residual_vector->get_values(),
563
                            (num_subdomains) * sizeof(ValueType), sizeof(ValueType),
564
565
                            MPI_INFO_NULL, MPI_COMM_WORLD,
566
                            &(this->window_residual_vector));
567
            std::vector<IndexType> zero_vec(num_subdomains, 0);
568
            gko::Array<IndexType> temp_array{settings.executor->get_master(),
569
                                              zero_vec.begin(), zero_vec.end()};
570
            this->convergence_vector = std::shared_ptr<vec_itype>(
571
                new vec_itype(settings.executor->get_master(), temp_array),
572
                std::default_delete<vec_itype>());
573
            this->convergence_sent = std::shared_ptr<vec_itype>(
574
                new vec_itype(settings.executor->get_master(), num_subdomains),
575
                std::default_delete<vec_itype>());
            this->convergence_local = std::shared_ptr<vec_itype>(
576
577
                new vec_itype(settings.executor->get_master(), num_subdomains),
578
                std::default_delete<vec_itype>());
579
            MPI_Win_create(this->convergence_vector->get_data(),
580
                            (num_subdomains) * sizeof(IndexType), sizeof(IndexType),
                            MPI_INFO_NULL, MPI_COMM_WORLD,
581
582
                            &(this->window_convergence));
583
584
585
        if (settings.comm_settings.enable_onesided && num_subdomains > 1) {
586
            // Lock all windows.
587
            if (settings.comm_settings.enable_get &&
588
                settings.comm_settings.enable_lock_all) {
                MPI_Win_lock_all(0, this->comm_struct.window_send_buffer);
590
            if (settings.comm_settings.enable_put &&
591
592
                settings.comm_settings.enable_lock_all) {
593
                MPI Win lock all(0, this->comm struct.window recv buffer);
594
595
            if (settings.comm_settings.enable_one_by_one &&
596
                settings.comm_settings.enable_lock_all) {
597
                MPI_Win_lock_all(0, this->comm_struct.window_x);
598
599
            MPI_Win_lock_all(0, this->window_residual_vector);
600
            MPI Win lock all(0, this->window convergence);
601
602 }
```

7.15.3.4 update_boundary()

Update the values into local vector from obtained from the neighboring sub-domains using the interface matrix.

Parameters

settings	The settings struct.

Parameters

metadata	The metadata struct.
local_solution	The local solution vector in the subdomain.
local_rhs	The local right hand side vector in the subdomain.
solution_vector	The workspace solution vector.
global_old_solution	The global solution vector of the previous iteration.
interface_matrix	The interface matrix containing the interface and the overlap data mainly used for exchanging values between different sub-domains.

Implements SchwarzWrappers::Communicate < ValueType, IndexType >.

References SchwarzWrappers::Settings::executor, SchwarzWrappers::SchwarzBase< ValueType, IndexType > ::interface_matrix, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_rhs, SchwarzWrappers::Metadata< ValueType, IndexType >::local_size_x, SchwarzWrappers::SchwarzBase< ValueType, IndexType >::local_solution, SchwarzWrappers::Metadata< ValueType, IndexType >::num_subdomains, and Schwarz Wrappers::Settings::overlap.

```
815 {
        using vec_vtype = gko::matrix::Dense<ValueType>;
816
        auto one = gko::initialize<gko::matrix::Dense<ValueType>>(
{1.0}, settings.executor);
817
818
819
        auto neg_one = gko::initialize<gko::matrix::Dense<ValueType>>(
        {-1.0}, settings.executor);
auto local_size_x = metadata.local_size_x;
820
821
        local_solution->copy_from(local_rhs.get());
823
        global_old_solution->copy_from(solution_vector.get());
824
        if (metadata.num_subdomains > 1 && settings.overlap > 0) {
825
            auto temp_solution = vec_vtype::create(
826
                 settings.executor, local_solution->get_size(),
827
                 gko::Array<ValueType>::view(
828
                     settings.executor, local_solution->get_size()[0],
829
                     &(global_old_solution->get_values()[0])),
830
                1);
831
             interface_matrix->apply(neg_one.get(), temp_solution.get(), one.get(),
832
                                       (local_solution).get());
833
        }
```

The documentation for this class was generated from the following files:

- restricted_schwarz.hpp (d6ef4fd)
- /home/runner/work/schwarz-lib/schwarz-lib/source/restricted schwarz.cpp (d6ef4fd)

7.16 SchwarzWrappers::Utils < ValueType, IndexType > Struct Template Reference

The utilities class which provides some checks and basic utilities.

```
#include <utils.hpp>
```

7.16.1 Detailed Description

template<typename ValueType = gko::default_precision, typename IndexType = gko::int32> struct SchwarzWrappers::Utils< ValueType, IndexType >

The utilities class which provides some checks and basic utilities.

Template Parameters

ValueType	The type of the floating point values.
IndexType	The type of the index type values.

Utils

The documentation for this struct was generated from the following files:

- utils.hpp (d6ef4fd)
- /home/runner/work/schwarz-lib/schwarz-lib/source/utils.cpp (d6ef4fd)

Index

BadDimension, 19	SchwarzWrappers::SchwarzBase, 43
BadDimension, 19	ProcessTopology, 15
Communicate, 9	remote_get
CudaError, 28	SchwarzWrappers::Communicate::comm_struct,
CudaError, 29	24
CusparseError, 29	remote_put
CusparseError, 30	SchwarzWrappers::Communicate::comm_struct,
exchange_boundary	run
SchwarzWrappers::Communicate, 26	SchwarzWrappers::SchwarzBase, 43
SchwarzWrappers::SolverRAS, 49	,
explicit_laplacian	Schwarz Class, 11
SchwarzWrappers::Settings, 46	SchwarzBase
,	SchwarzWrappers::SchwarzBase, 40
generate_rhs	SchwarzWrappers, 15
SchwarzWrappers::Initialize, 32	SchwarzWrappers::CommHelpers, 16
global_get	SchwarzWrappers::Communicate
SchwarzWrappers::Communicate::comm_struct,	exchange_boundary, 26
22	local_to_global_vector, 26
global_put	setup windows, 27
SchwarzWrappers::Communicate::comm_struct,	• —
22	update_boundary, 27
	SchwarzWrappers::Communicate < ValueType, Index ←
Initialization, 10	Type >, 25
is_local_neighbor	SchwarzWrappers::Communicate< ValueType, Index←
SchwarzWrappers::Communicate::comm_struct,	Type >::comm_struct, 21
23	SchwarzWrappers::Communicate::comm_struct
20	global_get, 22
local_get	global_put, 22
SchwarzWrappers::Communicate::comm_struct,	is_local_neighbor, 23
23	local_get, 23
local_put	local_put, 23
SchwarzWrappers::Communicate::comm_struct,	remote_get, 24
23	remote_put, 24
local solver tolerance	SchwarzWrappers::ConvergenceTools, 16
SchwarzWrappers::Metadata, 38	SchwarzWrappers::Initialize
	generate_rhs, 32
local_to_global_vector	partition, 32
SchwarzWrappers::Communicate, 26	setup_global_matrix_laplacian, 33
MetisError, 38	setup_local_matrices, 34
MetisError, 38	setup_vectors, 35
	SchwarzWrappers::Initialize< ValueType, IndexType >,
naturally_ordered_factor	SchwarzWrappers::Metadata
SchwarzWrappers::Settings, 46	local_solver_tolerance, 38
nartition	
partition Sobwer-Wronneroulnitialize 22	tolerance, 38
SchwarzWrappers::Initialize, 32	SchwarzWrappers::Metadata< ValueType, IndexType
print_matrix	>, 36
SchwarzWrappers::SchwarzBase, 42	SchwarzWrappers::PartitionTools, 17
print vector	SchwarzWrappers::SchwarzBase

60 INDEX

```
print_matrix, 42
    print_vector, 43
    run, 43
    SchwarzBase, 40
SchwarzWrappers::SchwarzBase < ValueType, \ Index \leftarrow
         Type >, 39
SchwarzWrappers::Settings, 45
    explicit_laplacian, 46
    naturally ordered factor, 46
SchwarzWrappers::Settings::comm settings, 20
SchwarzWrappers::Settings::convergence_settings, 28
SchwarzWrappers::Solve < ValueType, IndexType >, 47
SchwarzWrappers::SolverRAS< ValueType, IndexType
         >, 47
SchwarzWrappers::SolverRAS
    exchange_boundary, 49
    setup local matrices, 49
    setup windows, 53
    SolverRAS, 48
    update_boundary, 55
SchwarzWrappers::SolverTools, 17
SchwarzWrappers::Utils < ValueType, IndexType >, 56
SchwarzWrappers::device_guard, 30
setup_global_matrix_laplacian
     SchwarzWrappers::Initialize, 33
setup_local_matrices
    SchwarzWrappers::Initialize, 34
    SchwarzWrappers::SolverRAS, 49
setup vectors
    SchwarzWrappers::Initialize, 35
setup_windows
     SchwarzWrappers::Communicate, 27
     SchwarzWrappers::SolverRAS, 53
Solve, 12
SolverRAS
    SchwarzWrappers::SolverRAS, 48
tolerance
    SchwarzWrappers::Metadata, 38
update_boundary
    SchwarzWrappers::Communicate, 27
    SchwarzWrappers::SolverRAS, 55
Utils, 13
```