Deep strong coupling

Matt Lilley

March 7, 2025

1 Introduction

Coupling refers to the interaction between two systems, where the total energy is not a simple sum of the energies of each system. Instead, the total energy also depends on the combined states of both, with each system influencing the other in ways that cannot be separated. We often express the ideas through a Lagrangian or Hamiltonian.

The aim of these notes is to build some intuition for a quantum systems that have extremely strong coupling. In the <u>quantum optics literature</u>, the use the terms:

- Weak
- Strong
- Ultra strong
- Deep strong

to describe the different regimes.

We'll begin with a classical example and use the quantum optics language above. We choose the example of coupled pendulums because it turns out each quantum state with a well defined energy behaves like it's own pendulum (see e.g. <u>Briggs et.al</u>).

2 Coupled pendulums

For example, consider two identical pendulums of length l and mass m connected by a spring whose stiffness is characterised by k. In the small angle approximation $(\theta_1, \theta_1 \ll 1)$, the Hamiltonian is:

$$H_{\text{pen}} = \frac{ml^2}{2}\dot{\theta}_1^2 + \frac{mgl}{2}\theta_1^2 + \frac{ml^2}{2}\dot{\theta}_2^2 + \frac{mgl}{2}\theta_2^2 + \frac{1}{2}kl^2(\theta_1 - \theta_2)^2$$
 (1)

The first four terms are the simple sum of each individual pendulum. The third term arrises due to the coupling.

More abstractly, we can write:

$$H = H_1 + H_2 + V_{\text{coupling}} \tag{2}$$

and associate frequencies to the different parts:

- $\omega_1 = \sqrt{g/l}$
- $\omega_2 = \sqrt{g/l}$
- $\omega_{\text{coupling}} = \sqrt{k/m}$

The system behaves quite differently depending on the strength of the coupling which is proportional to the different frequencies.

2.1 Weak coupling

In reality, there is always dissipation which cannot be properly captured in a Hamiltonian description. We can however define a dissipation rate $\gamma_{\rm diss}$ whose magnitude also changes the system behaviour.

When $\omega_{\text{coupling}} \ll \gamma_{\text{diss}} \ll \omega_1, \omega_2$, the coupling is described as weak.

There are very small changes in the natural frequencies of the system as compared to the uncoupled case:

• $\omega_1 \to \omega_+ = \sqrt{g/l}$ • $\omega_2 \to \omega_- = \sqrt{g/l + 2k/m}$

The energy does not however move back and forwards between the pendulums because of the large dissipation.

2.2 Strong coupling

When the coupling is "strong" in the sense that $\gamma_{\rm diss} \ll \omega_{\rm coupling} \ll \omega_1, \omega_2$, dissipation is small enough to allow energy to be slowly exchanged between the two pendulums. The motion is characterised by individual swings happening with a frequency $\approx \sqrt{g/l}$ where the amplitude of those swings gradually undulates on a timescale characterised by $\omega_{\rm exchange} = k/2m\omega_p$. This exchange happens most effectively when the pendulums have the same length, so that their natural frequencies are the same .

Strong coupling allows us to still conceptually consider the pendulums as having well defined identities in the sense that they have their own natural frequencies. As the coupling becomes larger, this is no longer the case.

2.3 Ultra strong coupling

When the coupling is "ultra strong" in the sense that $\gamma_{\rm diss} \ll \omega_{\rm coupling} \sim 0.1 \times \omega_1, \omega_2$, energy exchange happens on the time scale of a single swing of one of the pendulums. The two natural natural frequencies can be noticeably

discerned, $\omega_{+} = \sqrt{g/l}$ when both pendulums move "in phase" (the spring is not stretched) with one another and $\omega_{-} = \sqrt{g/l + 2k/m}$ when the pendulums move "out of phase".

The coupling is getting strong enough so that more energy can be exchanged between pendulums of different lengths.

This exact boundary for this regime is somewhat artificial - there is nothing particularly special about the value $0.1\omega_1, \omega_2$. This value was first used as part of the quantum optics literature.

2.4 Deep strong coupling

When $\gamma_{\rm diss} \ll \omega_1, \omega_2 \lesssim \omega_{\rm coupling}$, the coupling begins to dominate over everything else and we enter into a regime called "Deep strong coupling". Energy transfer between the two pendulums is so fast that it's almost instantaneous and so it's not possible to move one pendulum without the other - they act as a single rigid body.

3 Rabi model

A canonical quantum example is a single two level system (TLS) interacting with a quantised field often called the Rabi model. The Hamiltonian can be written as:

$$H_{\text{Rabi}} = \frac{\Delta E}{2} \sigma_z + \hbar \omega \left(a^{\dagger} a + \frac{1}{2} \right) + U \left(a^{\dagger} + a \right) (\sigma_+ + \sigma_-)$$
 (3)

where ΔE is the transition energy between the 2 levels of the TLS, $\hbar \omega$ is the energy of each quantum of the field, and U is the coupling constant between the TLS and the field. The σ operators are the <u>Pauli spin matrices</u> that act on the TLS, where σ_+ and σ_- act as raising and lowering operators. The a^{\dagger} , a are the field creation and annihilation operators respectively.

It's worth noting that we're using the Pauli spin matrices as a mathematical tool to describe two levels. Just keep in mind that we're not really talking about spin angular momentum here.

Although a TLS has just 2 states (denoted $|\pm\rangle$), the quantised field has infinitely many states (denoted by the number of quanta $|n\rangle$). The combined state of the system (denoted $|n,\pm\rangle$) therefore has infinitely many states and so conceptually the system behaves like infinitely many pendulums coupled together. The frequency of these conceptual pendulums is determined by the energy of the states.

Much like the classical example, the dynamics depend on the relative sizes of the different terms in the Hamiltonian. For the quantum case however, it's not enough just to compare the various constants $U, \hbar\omega, \Delta E$, we must also consider how many field quanta n we have. This is because of how the field operators work:

$$a^{\dagger}|n,\pm\rangle = \sqrt{n+1}|n+1,\pm\rangle$$
 (4)

$$a|n,\pm\rangle = \sqrt{n}|n-1,\pm\rangle$$
 (5)

$$a^{\dagger}a|n,\pm\rangle = n|n,\pm\rangle$$
 (6)

The more field quanta we have, the larger the field and coupling terms will be compared to the TLS term.

3.1 Weak coupling

Much like the classical pendulums, the quantum states can suffer various forms of "dissipation". As the quantum systems interacts with outside systems, it can cause:

- Dephasing where the phase relationship between each of the quantum states starts to change over time
- Decoherence the system is forced out of a superposition state and into a well defined state aka "collapse of the wavefunction"

If we define $\hbar\gamma_{\rm diss}$ as a characteristic energy associated with the above processes, then $\sqrt{n}U \ll \hbar\gamma_{\rm diss} \ll \Delta E, n\hbar\omega$ defines the weak coupling regime. Spontaneous emission is the most characteristic feature of weak coupling where an excited TLS with less field quanta (e.g. $|n,+\rangle$) is coupled to a ground state TLS with more field quanta (e.g. $|n+1,-\rangle$). The coupling is however not so strong that the field quanta can get reabsorbed.

Note that truly irreversible spontaneous emission also relies on there being a continuum of states instead of discrete ones.

3.2 Strong coupling

As in the classical case, when the coupling is strong in the sense that $\hbar\gamma_{\rm diss} \ll \sqrt{n}U \ll \Delta E, \hbar\omega$, there is time for slow exchange between the different quantum states (remember each state is like it's own pendulum). Unlike the classical case, where it's energy that's exchanged, in the quantum case it's state occupation probability $|\psi|^2$ that's exchanged.

In order for exchange to occur effectively, the quantum states need to have the same energy. This is equivalent to the conceptual pendulums having the same length. Two such states are often described as "resonant" with one another.

Whether or not the system has any resonances depends on the relationship between $\hbar\omega$ and ΔE .

3.2.1 Matched field and TLS

When the field is matched to the TLS, $\Delta E = \hbar \omega$. This is the most widely discussed regime in which a transition of the TLS (often an atomic transition) results in the emission of a single field quantum (often a photon). In a cavity where discrete states can be arranged and field quanta can be confined, this results in occupation probability oscillating between states like $|n,+\rangle$ and $|n+1,-\rangle$. These oscillations are called Rabi oscillations which have a frequency $\Omega/\hbar\omega \sim \sqrt{n}U/\hbar\omega$

3.2.2 Mismatched field and TLS

When the field is mismatched to the TLS, $\Delta E \neq \hbar \omega$. If the mismatch is arbitrary, e.g. $\Delta E/\hbar \omega = 2.83677$ then Rabi oscillations cannot occur because the coupling term $(\sim \sqrt{n}U)$ is still very small compared to ΔE and $\hbar \omega$ and so it cannot accommodate any energy mismatch.

If however, $\Delta E = m\hbar\omega$ where m = 3, 5, 7... then $|n, +\rangle$ is resonant with, $|n+3, -\rangle$, $|n+5, -\rangle$, $|n+7, -\rangle$... and so Rabi oscillations can once again occur. The frequency is slower $\Omega/\hbar\omega \sim (\sqrt{n}U/\hbar\omega)^m$ and so for larger m the emission of multiple quanta becomes less and less likely.

3.3 Ultra strong coupling

When the coupling becomes a sizeable fraction of the TLS and field quantum, $\hbar\gamma_{\rm diss} \ll \sqrt{n}U \sim 0.1 \times \Delta E, \hbar\omega$, non-resonant states begin to gain significant occupancy. For example, a system can start out in state $|0,+\rangle$ with 100% probability and overtime a state $|1,+\rangle$ can gain a non-trivial amount of occupation probability. Although this superficially appears to violate energy conservation, the energy in the coupling is no longer small and so all terms in the Hamiltonian need to be considered when thinking about energy conservation.

The coupling term can also accommodate energy mismatches between the TLS and the oscillator, e.g. $\Delta E/\hbar\omega = 2.83677$ vs $\Delta E/\hbar\omega = 3$. This makes it easier to observe the emission of multiple quanta.

3.4 Deep strong coupling

When the coupling becomes on the same order or greater than the TLS and field quantum $\hbar \gamma_{\rm diss} \ll \Delta E, \hbar \omega \lesssim \sqrt{n}U$, then TLS transitions and creation/annihilation of field quanta can no longer be understood by simply thinking about the TLS and field exchanging energy with each other and the coupling as a kind of glue between the two. The coupling term has an "identity" all of its own.

This regime was first theoretically explored in 2010 by Casanova at.al where a simpler definition of "deep strong coupling" was given as:

$$\frac{U}{\hbar\omega}\gtrsim 1$$
 (7)

Indeed, if their condition is satisfied then $\hbar\omega \lesssim \sqrt{n}U$ is guaranteed.

Let's first consider the case (as Casanova did) that the TLS energy is small in the sense that $\Delta E < \hbar \omega$. If the coupling is in the deep storing regime so that $U/\hbar \omega \gtrsim 1$ then, from an energy conservation point of view, the coupling term can spontaneously create field quanta. When a quanta gets created, then n increases which means the coupling term $\sim \sqrt{n}U$ increases which means more quanta can be made. We can figure out how many can be made by equating the field energy to the coupling energy in the Hamiltonian:

$$n\hbar\omega \sim \sqrt{n}U\tag{8}$$

This gives us:

$$n \sim \left(\frac{U}{\hbar\omega}\right)^2 \tag{9}$$

When you work out the detailed maths, you end up with $n = 4(U/\hbar\omega)^2$.

When the TLS energy is not small ($\Delta E \gtrsim \hbar \omega$) then there is an additional energy equivalence to consider:

$$\Delta E \sim \sqrt{n}U\tag{10}$$

Eq. 8 and Eq. 10 can be solved simultaneously to eliminate n. This gives us a relationship between $U, \Delta E, \hbar \omega$:

$$\Delta E \sim \sqrt{\left(\frac{U}{\hbar\omega}\right)^2} U$$

$$\Delta E \sim \frac{U^2}{\hbar\omega}$$

$$U \sim \sqrt{\Delta E \hbar\omega}$$

$$\frac{U}{\hbar\omega} \sim \sqrt{\frac{\Delta E}{\hbar\omega}}$$
(11)

For the case when the TLS energy dominates over the field, $\Delta E \gg \hbar \omega$, Eq. 11 is a more appropriate coupling threshold to consider than Eq. 7. This regime

is sometimes called "dispersive deep strong coupling" as was first coined by Felicetti et.al in 2017. Again, when you do the detailed maths, you get an extra constant so that:

$$\frac{U}{\hbar\omega} \gtrsim \frac{1}{2} \sqrt{\frac{\Delta E}{\hbar\omega}} \tag{12}$$

In the extreme case when $\Delta E/\hbar\omega \to \infty$ then Eq. 12 represents a boundary of what's called a superradiant phase transition (detailed in 2015 by Hwang et.al). When you go above this critical coupling, the system undergoes a phase change where the lowest energy state involves a non-zero amount of field quanta. In other words, above this threshold the TLS freely exchanges energy with the field and the usual restrictions around having a matched TLS and field are not important. Superradiant phase transitions have been discussed for much longer times in relation to the Dicke model and we'll come back to look at this later on.

3.4.1 Relativistic phonon nuclear coupling

For acoustic phonons, we choose a notation $\omega \equiv \omega_A$. From notes on Coupling constants in nuclear physics, we derived the relativistic phonon nuclear coupling as:

$$\frac{U}{\hbar\omega_A} = \sqrt{\frac{2}{N}} \sqrt{\frac{\Delta E}{Mc^2}} \sqrt{\frac{\Delta E}{\hbar\omega_A}} \times 10^{-3}$$
 (13)

where N is the number of nuclei involved in the phonon motion, and M is the mass of the nucleus.

Typically, we imagine a phonon as being the quantised oscillatory motion of many nuclei in a lattice. However, it's possible to arrange systems in which the motion of an isolated nucleus is considered (see e.g. <u>Cat et.al 2021</u>) - in which case N=1.

Our example Hamiltonian in Eq. 3 is for a single TLS, so we'll consider Eq. 13 with N=1. We'll extend the Hamiltonian to many TLS later on.

For nuclear transitions mediated by phonons, $\Delta E \sim MeV$ and $\hbar\omega_A \sim 10neV$ and so $\Delta E/\hbar\omega \gg 1$. Therefore, Eq. 12 is the appropriate superradiant threshold condition.

Substituting the expression for coupling (Eq. 13) into the critical coupling expression (Eq. 12) gives the following condition:

$$2\frac{U}{\hbar\omega_A}\sqrt{\frac{\hbar\omega_A}{\Delta E}} \gtrsim 1$$

$$2\sqrt{2}\sqrt{\frac{\Delta E}{Mc^2}} \times 10^{-3} \ge 1$$
(14)

For nuclear transitions $\Delta E \sim MeV$ and for a single nucleon $Mc^2 \sim GeV$ so it's already clear that for any sized nucleus we won't enter the superradiant regime. For the sake of completeness, let's evaluate Eq. 14 for a transition with $\Delta E \approx 24 MeV$ and for a palladium nucleus with $Mc^2 \approx 100 GeV$

$$2\sqrt{2}\sqrt{\frac{24\times10^6}{10^{11}}}\times10^{-3}\approx4\times10^{-5}\ll1$$
 (15)

This confirms that a single nucleus cannot become superradiant using relativistic phonon nuclear coupling. Let's look at another type of coupling that's also associated with oscillatory phonon motion.

Electric dipole coupling

For electric dipole coupling associated with an oscillating electric field driving phonon motion, we continue to use the notation $\omega \equiv \omega_A$. From notes on Coupling constants in nuclear physics, we derived the electric dipole phonon coupling as:

$$\frac{U}{\hbar\omega_A} = \frac{2\pi\sqrt{2}}{Z\sqrt{N}} \sqrt{\frac{Mc^2}{\hbar\omega_A}} \frac{\hbar\omega_A}{E_L} A^{1/3} \times 6 \times 10^{-3}$$
 (16)

If we once again take N=1, then substituting the expression for coupling (Eq. 16) into the critical coupling expression (Eq. 12) gives the following condition:

$$2\frac{U}{\hbar\omega_A}\sqrt{\frac{\hbar\omega_A}{\Delta E}} \gtrsim 1$$

$$\frac{4\pi\sqrt{2}}{Z}\sqrt{\frac{Mc^2}{\Delta E}}\frac{\hbar\omega_A}{E_L}A^{1/3} \times 6 \times 10^{-3} \gtrsim 1$$
(17)

For palladium nuclear transitions mediated by acoustic phonons:

- A ≈ 106
- $\begin{array}{ll} \bullet & Z \approx 106 \\ \bullet & Mc^2 \approx 10^{11} \ \mathrm{eV} \end{array}$
- $\Delta E \approx 24 \times 10^6 \text{ eV}$
- $\hbar\omega_A \approx 10^{-8} \text{ eV}$

The localization energy E_L is:

$$E_L = \frac{\hbar c}{R_0} = \frac{6.6 \times 10^{-34} \times 3 \times 10^8}{10^{-15}}$$
 (18)

$$= 2 \times 10^{-10} \text{ J} = 1.2 \times 10^9 \text{ eV} \approx 10^9 \text{ eV}$$
 (19)

And so evaluating Eq. 17 gives:

$$\frac{4\pi\sqrt{2}}{106} \times \sqrt{\frac{10^{11}}{24 \times 10^6}} \times \frac{10^{-8}}{10^9} \times 6 \times 10^{-3} \times 106^{1/3} \approx 3 \times 10^{-18} \ll 1$$
 (20)

And so we're even further away from the superradiant regime when considering the electric dipole coupling associated with the phonon motion.

We've so far looked at the Rabi model where the number of TLS is N=1. How does the story change when we have many TLS?

3.5 Dicke model

When we have N identical TLS coupled to a single mode (i.e. single frequency) of a quantised field then Hamiltonian is called the Dicke Hamiltonian. It's a simple extension of the Rabi Hamiltonian in Eq. 3 in the sense that we just add N copies of the TLS terms as seen below:

$$H_{\text{Dicke}} = \frac{\Delta E}{2} \sum_{i=1}^{N} \sigma_z^{(i)} + \hbar \omega \left(a^{\dagger} a + \frac{1}{2} \right) + U \sum_{i=1}^{N} (a^{\dagger} + a) (\sigma_+^{(i)} + \sigma_-^{(i)})$$
 (21)

The states of this system are described by $|n, \pm, \pm, \pm, \pm, ...\rangle$.

It's worth emphasising that there is no spatial dependence of the field in Eq. 21. One way to understand this physically is that all the TLS are very close together in the sense that they are located in a region of space that is much smaller than the wavelength of the mode. In that situation, all the TLS will experience the same strength of field at any given moment - in other words the field appears constant in space. This is the how Dicke originally presented his ideas in his 1954 paper. It's also possible to use this Hamiltonian to describe many TLS arranged in a very special way so that they are placed at integer multiples of the mode wavelength.

What we really want to understand is how the extra TLS are going to affect the coupling term. Right now, Eq. 21 is not in a form that allows us to readily see this. We're going to rewrite it by appealing to the physics of spin.

We noted earlier that the use of the Pauli spin matrices is just a mathematical tool to describe two levels. Although we're not describing spin here, we are working with what is often called "pseudo spin". The <u>rules of angular momentum</u> work just as well for pseudo angular momentum. In particular, the rules of angular momentum addition and conservation.

This means that we can treat all the TLS together as if they are a single object with many levels whose energies are determined by the addition rules of pseudo angular momentum. The Hamilton then looks like:

$$H = \Delta E J_z + \hbar \omega \left(a^{\dagger} a + \frac{1}{2} \right) + 2U \left(a^{\dagger} + a \right) \left(J_+ + J_- \right)$$
 (22)

where the total pseudo total angular momentum operators (J) for N TLS are:

$$J_{+} + J_{-} = J_{x} = \frac{1}{2} \sum_{i=1}^{N} \sigma_{ix} \quad J_{z} = \frac{1}{2} \sum_{i=1}^{N} \sigma_{iz}$$
 (23)

and noting that i in σ_i means that this operator only acts on TLS number i.

When written in this way, states can now be described in terms of 3 numbers $|n,j,m\rangle$ where j describes the total pseudo angular momentum number (which is conserved) and m describes the z component of the total pseudo angular momentum (which can change). This notation allows us to conveniently describe situations where excitations are "delocalised" among the TLS. By far the most significant kind of delocalised states are called "Dicke states" which have the largest $j=j_{\rm max}=N/2$. Dicke states are symmetric in the sense that if you swap any of the TLS around, the state remains unchanged. For example, consider a single excitation in 4 TLS - the Dicke state looks like:

$$\Psi_{0} = \frac{1}{\sqrt{4}} (|0, +, -, -, -\rangle + |0, -, +, -, -\rangle + |0, -, -, +, -\rangle + |0, -, -, -, +\rangle)$$
(24)

Notice that if you swap any two TLS, the state looks the same.

The above state can instead be described by $j_{\rm max}=4/2=2$ and $m=1\times 1/2+3\times -1/2=-1$

$$\Psi_0 = |0, 2, -1\rangle \tag{25}$$

Dicke states with $j=j_{\rm max}$ are significant because of the acceleration properties that these Dicke states offer; something people often describe as superradiance. We can start to get a sense of where the super comes from by looking at the action of the ladder operators J_+ and J_- which excite and de-excite the TLS. This causes a raising and lowering of the m value like this:

$$J_{+}|n,j,m\rangle = \sqrt{j(j+1) - m(m+1)}|n,j,m+1\rangle$$
 (26)

$$J_{-}|n,j,m\rangle = \sqrt{j(j+1) - m(m-1)}|n,j,m-1\rangle$$
 (27)

These ladder operators are conceptually similar to the creation and annihilation operators of the field. The details are however more complicated due to the addition rules of angular momentum.

For the case with all TLS excited, m = N/2:

$$J_{-}|n, N/2, N/2\rangle = \sqrt{N}|n, N/2, N/2 - 1\rangle$$
 (28)

For the first de-excitation, the coupling terms gets enhanced by \sqrt{N} . This might not seem surprising at first glance because we have N TLS excited and so we should expect the rate of emission (which go as the square of the coupling) to be enhanced by N.

For the case of a single excitation , m = -N/2 + 1:

$$J_{-}|n, N/2, -N/2 + 1\rangle = \sqrt{N}|n, N/2, -N/2\rangle$$
 (29)

For this singe de-excitation the coupling term also gets enhanced by \sqrt{N} . This is more surprising because the rate of emission (which go as the square of the coupling) to be enhanced by N even though there is only a single excitation.

For the case of **50% excitation**, m = 0:

$$J_{-}|n, N/2, 0\rangle = \sqrt{N^2 + N}|n, N/2, -1\rangle$$
 (30)

For the first de-excitation, the coupling terms gets enhanced by $\sim \sqrt{N^2}$ for large N. In other words, the rate of emission (which go as the square of the coupling) to be enhanced by N^2 - this is where the super in superradiance comes from.

It's should be noted that the effect of Dicke superradiance and superradiant phase transitions are <u>not the same</u>. The former involves a transient enhancement in emission of N TLS which ultimately ends up with all the TLS in their ground state and the field quanta escape to infinity. The latter involves a permanent change in the ground state a cavity system in which field and TLS are both confined.

If we look back at the couplings in Eqs. 13 and 16, we can see a $1/\sqrt{N}$ term appears to reduce the coupling significantly for very large numbers of nuclei. However, if we are able to take advantage of Dicke effects, then the situation is very different:

- For fully excited systems, Dicke enhancement of the coupling scales like \sqrt{N} and so coupling for N nuclei is the same as for a single nuclei (from \sqrt{N}/\sqrt{N})
- For half excited systems, Dicke enhancement of the coupling scales like N and so coupling for N nuclei scales like \sqrt{N} (from N/\sqrt{N})

3.5.1 Deep strong coupling

We now understand that the coupling operators in Eq. 22 will produce terms like:

- \sqrt{n} from the field part
- At least \sqrt{N} and at most N from the TLS part due to Dicke effects

If we take the most conservative Dicke enhancement then the condition for deep strong coupling can be arrived at by simply replacing U in Eq. 12 with $U\sqrt{N}$:

$$\frac{U\sqrt{N}}{\hbar\omega} \gtrsim \frac{1}{2}\sqrt{\frac{\Delta E}{\hbar\omega}} \tag{31}$$

As $N \to \infty$ this condition triggers a superradiant phase transition similar to what we saw in the Rabi model when $\Delta E/\hbar\omega \to \infty$.

If we look back at the couplings in Eqs. 13 and 16, we can see a $1/\sqrt{N}$ terms will cancel with the \sqrt{N} in Eq. 31. This means that our earlier calculations with N=1 will apply to an arbitrary number of TLS and so we won't get closer to a superradiant phase transition by having more TLS involved.

If however, we could use the most optimistic Dicke enhancement, then we'd instead have:

$$\frac{UN}{\hbar\omega} \gtrsim \frac{1}{2} \sqrt{\frac{\Delta E}{\hbar\omega}} \tag{32}$$

And so for relativistic phonon nuclear coupling (Eq. 13) we'd have:

$$2\sqrt{2}\sqrt{N}\sqrt{\frac{\Delta E}{Mc^2}} \times 10^{-3} \ge 1 \tag{33}$$

Using the same numbers as before in Eq. 15 then:

$$2\sqrt{2}\sqrt{N}\sqrt{\frac{24\times10^6}{10^{11}}}\times10^{-3}\approx4\times10^{-5}\sqrt{N}\geq1$$
(34)

This gives us a condition on the number of nuclei that we need:

$$N \gtrsim 8 \times 10^8 \tag{35}$$

If we were instead to consider a different transition, e.g. the 14keV transition of $^{57}\mathrm{Fe}$ then:

$$2\sqrt{2}\sqrt{N}\sqrt{\frac{14\times10^3}{5\times10^{10}}}\times10^{-3}\approx1.5\times10^{-6}\sqrt{N}\geq1$$
 (36)

Which would gives us the following condition on the number of nuclei that we need:

$$N \gtrsim 4 \times 10^{11} \tag{37}$$