




B



# 

Simone Picelli<sup>1</sup>, Vincent Hahaut<sup>1</sup>

<sup>1</sup>Institute of Molecular and Clinical Ophthalmology Basel (IOB)



Mar 23, 2022

dx.doi.org/10.17504/protocols.io.kxygxzkrwv8j/v3

Human Cell Atlas Method Development Community The Single Cell Ninjas

Simone Picelli

Institute of Molecular and Clinical Ophthalmology Basel (IOB...

The single-cell RNA-sequencing (scRNA-seq) field has evolved tremendously since the first paper was published back in 2009. While the first methods analysed just a handful of cells, the throughput and performance rapidly increased over a very short timespan. However, it was not until the introduction of emulsion droplets methods, that the robust and reproducible analysis of thousands of cells became feasible. Despite generating data at a speed and a cost per cell that remains unmatched by full-length protocols like Smart-seq, scRNA-seq in droplets still comes with the drawback of addressing only the terminal portion of the transcripts, thus lacking the required sensitivity for comprehensively analyzing the transcriptome of individual cells. Building upon the existing Smart-seq2/3 workflows, we developed FLASH-seq (FS), a new full-length scRNA-seq method capable of detecting a significantly higher number of genes than both previous versions, requiring limited hands-on time and with a great potential for customization.

DO

dx.doi.org/10.17504/protocols.io.kxygxzkrwv8j/v3

https://www.biorxiv.org/content/10.1101/2021.07.14.452217v1

Simone Picelli, Vincent Hahaut 2022. FLASH-seq protocol . **protocols.io** https://dx.doi.org/10.17504/protocols.io.kxygxzkrwv8j/v3
Simone Picelli

fixed some errors in the pre-amplification PCR program

FLASH-Seq, single-cell, RNA-sequencing, full-length, tagmentation

\_\_\_\_\_ protocol,

Mar 23, 2022

Mar 23, 2022

59800

**REAGENTS - CELL LYSIS MIX** 

**⊠** dNTP-Set 1 **Carl** 

Roth Catalog #K039.2

XTriton X-100 Sigma

Aldrich Catalog #X100-100ML

Recombinant RNase Inhibitor (40 U/uL) Takara Bio USA,

Inc. Catalog #2313B

Scientific Catalog #10217016



1

Citation: Simone Picelli, Vincent Hahaut FLASH-seq protocol <a href="https://dx.doi.org/10.17504/protocols.io.kxygxzkrwv8j/v3">https://dx.doi.org/10.17504/protocols.io.kxygxzkrwv8j/v3</a>

```
REAGENTS - RT-PCR MIX
XKAPA HiFi HotStart ReadyMix
(2x) Roche Catalog #KK2602

    SuperScript™ IV Reverse Transcriptase Thermo Fisher

Scientific Catalog #18090050
Magnesium Chloride (1M Solution) Invitrogen - Thermo
Fisher Catalog #AM9530G
REAGENTS - MAGNETIC BEADS SOLUTION PREPARATION

    ⊠ Polyethylenglycol (MW=8000) Sigma

Aldrich Catalog #89510-1KG-F
Sodium chloride Sigma
Aldrich Catalog #59222C-1000ML
Sera-Mag SpeedBead Carboxylate-Modified Magnetic Particles (Hydrophobic), 15 mL Ge
Healthcare Catalog #65152105050250
Sodium azide Sigma
Aldrich Catalog #S2002-25G
⊠ EDTA (0.5 M), pH 8.0 Life
Technologies Catalog #AM9260G
Scientific Catalog #15568025
aldrich Catalog #P-7949
If a commercial solution for sample cleanup is preferred, choose the following product:
Coulter Catalog #A63880
REAGENTS - SAMPLE & LIBRARY QC
⊠ Quant-iT™ PicoGreen® dsDNA Assay Kit Life
Technologies Catalog #P11496
Nunc™ F96 MicroWell™ Polystyrene Plate black Thermo Fisher
Scientific Catalog #237105
IX Qubit™ 1X dsDNA HS Assay Kit Invitrogen - Thermo
Fisher Catalog #Q33231
⊠ Qubit<sup>™</sup> Assay Tubes Invitrogen - Thermo
Fisher Catalog #Q32856
Technologies Catalog #5067-4626
REAGENTS - TAGMENTATION WITH NEXTERA XT KIT
illumina Catalog #FC-131-1096
Nextera XT Index Kit v2 (set A B C
D) illumina Catalog #FC-131-2001; FC-131-2002; FC-131
REAGENTS - TAGMENTATION WITH IN-HOUSE Th5 TRANSPOSASE
X KAPA HiFi plus
dNTPs Roche Catalog #KK2102
```



2

⊠ NN-Dimethylformamide (DMF) solution Millipore

Sigma Catalog #D4551

SDS, 10% Solution Life

Technologies Catalog #AM9822

XTAPS Sigma

Aldrich Catalog #T9659-100G

Sodium Hydroxide (pellet purity 98%) Sigma

Aldrich Catalog #71690-1KG

#### **GENERAL CONSUMABLES**

Fisher Catalog #7002

Scientific Catalog #AB0558

International Catalog #391-1281

▼ Twin.Tec® PCR plates 384 (LoBind)

■ Twi

colourless) Eppendorf Catalog #EP0030129547

**⊠** UltraPure<sup>™</sup> DNase/RNase-Free Distilled Water **Thermo Fisher** 

Scientific Catalog #10977023

**⊠** DNA LoBind® 1.5 mL (PCR clean

colourless) Eppendorf Catalog #30108051

⊠ Ethanol for molecular biology Sigma

Aldrich Catalog #51976-500ML-F

#### **OLIGONUCLEOTIDES - RT-PCR**

Α	В	С
Oligo ID	Sequence (5' → 3')	Purification /
		synthesis scale
Smart	/5Biosg/AAGCAGTGGTATCAACGCAGAGTACTTTTTTTTTTTTTT	desalted or HPLC
dT30VN		
FS TSO	/5Biosg/AAGCAGTGGTATCAACGCAGAGTACrGrGrG	desalted or HPLC

/5Biosg/ = C6-linker biotin

#### **OLIGONUCLEOTIDES - IN-HOUSE Tn5 PROTOCOL ONLY**

A B		С
Oligo ID	Sequence (5' → 3')	Comments
TN5MErev	/5Phos/ CTGTCTCTTATACACATCT	2 μM scale - desalted*
TN5ME-A	TCGTCGGCAGCGTCAGATGTGTATAAGAGACAG	1 μM scale - desalted*
TN5ME-B	GTCTCGTGGGCTCGGAGATGTGTATAAGAGACAG	1 μM scale - desalted*

<sup>\*</sup> It is important to follow these recommendations. Ordering oligos at this scale but choosing "HPLC purification" will result in insufficient material for Tn5 loading. The scale indicated here is sufficient for producing 20-25 ml of loaded Tn5.

# OLIGONUCLEOTIDES - ALL TAGMENTATION PROTOCOLS (when not ordering the Nextera Index Kit)

One can order the 4 Nextera XT Index Kit v2 (set A, B, C, D) sets, as described above or, alternatively, get them manufactured by any oligonucleotide provider. Below is the list of 24 N7xx and 16 S5xx adaptors required to multiplex 384 samples. Prepare working dilution plates containing unique combinations of N7xx + S5xx adaptors, each with a final concentration of  $5 \mu M$ .



Α	В
Oligo ID	Sequence (5' → 3')
Nextera_v2_N714	/5Biosg/CAAGCAGAAGACGGCATACGAGATTCATGAGCGTCTCGTGGGCTCG*G
Nextera_v2_N715	/5Biosg/CAAGCAGAAGACGGCATACGAGATCCTGAGATGTCTCGTGGGCTCG*G
Nextera_v2_N716	/5Biosg/CAAGCAGAAGACGGCATACGAGATTAGCGAGTGTCTCGTGGGCTCG*G
Nextera_v2_N718	/5Biosg/CAAGCAGAAGACGGCATACGAGATGTAGCTCCGTCTCGTGGGCTCG*G
Nextera_v2_N719	/5Biosg/CAAGCAGAAGACGGCATACGAGATTACTACGCGTCTCGTGGGCTCG*G
Nextera_v2_N720	/5Biosg/CAAGCAGAAGACGGCATACGAGATAGGCTCCGGTCTCGTGGGCTCG*G
Nextera_v2_N721	/5Biosg/CAAGCAGAAGACGGCATACGAGATGCAGCGTAGTCTCGTGGGCTCG*G
Nextera_v2_N722	/5Biosg/CAAGCAGAAGACGGCATACGAGATCTGCGCATGTCTCGTGGGCTCG*G
Nextera_v2_N723	/5Biosg/CAAGCAGAAGACGGCATACGAGATGAGCGCTAGTCTCGTGGGCTCG*G
Nextera_v2_N724	/5Biosg/CAAGCAGAAGACGGCATACGAGATCGCTCAGTGTCTCGTGGGCTCG*G
Nextera_v2_N726	/5Biosg/CAAGCAGAAGACGGCATACGAGATGTCTTAGGGTCTCGTGGGCTCG*G
Nextera_v2_N727	/5Biosg/CAAGCAGAAGACGGCATACGAGATACTGATCGGTCTCGTGGGCTCG*G
Nextera_v2_N728	/5Biosg/CAAGCAGAAGACGGCATACGAGATTAGCTGCAGTCTCGTGGGCTCG*G
Nextera_v2_N729	/5Biosg/CAAGCAGAAGACGGCATACGAGATGACGTCGAGTCTCGTGGGCTCG*G
Nextera_v2_S502	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCTCTCTATTCGTCGGCAGCGT*C
Nextera_v2_S513	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTCGACTAGTCGTCGGCAGCGT*C
Nextera_v2_S503	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTATCCTCTTCGTCGGCAGCGT*C
Nextera_v2_S515	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTTCTAGCTTCGTCGGCAGCGT*C
Nextera_v2_S505	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGTAAGGAGTCGTCGGCAGCGT*C
Nextera_v2_S516	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCCTAGAGTTCGTCGGCAGCGT*C
Nextera_v2_S506	/5Biosg/AATGATACGGCGACCACCGAGATCTACACACTGCATATCGTCGGCAGCGT*C
Nextera_v2_S517	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGCGTAAGATCGTCGGCAGCGT*C
Nextera_v2_S507	/5Biosg/AATGATACGGCGACCACCGAGATCTACACAAGGAGTATCGTCGGCAGCGT*C
Nextera_v2_S518	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCTATTAAGTCGTCGGCAGCGT*C
Nextera_v2_S508	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCTAAGCCTTCGTCGGCAGCGT*C
Nextera_v2_S520	/5Biosg/AATGATACGGCGACCACCGAGATCTACACAAGGCTATTCGTCGGCAGCGT*C
Nextera_v2_S510	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCGTCTAATTCGTCGGCAGCGT*C
Nextera_v2_S521	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGAGCCTTATCGTCGGCAGCGT*C
Nextera_v2_S511	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTCTCTCCGTCGTCGGCAGCGT*C
Nextera_v2_S522	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTTATGCGATCGTCGGCAGCGT*C

All oligonucleotides carry a 5´-biotin (/5Biosg/) and a phosphorothioate bond (\*) between the last and the second last nucleotide. For cost reasons, we ordered desalted oligos and not HPLC purified.

## OLIGONUCLEOTIDES - ALL TAGMENTATION PROTOCOLS (when not ordering the Nextera Index Kit)

To increase the multiplex capabilities, we designed an additional set of 32 S5xx and 48 N7xx adaptors (non-UDI).

Α	В
Oligo ID	Sequence
Nextera_extra_i7_1	/5Biosg/CAAGCAGAAGACGGCATACGAGATGCCTATCAGTCTCGTGGGCTCG*G
Nextera_extra_i7_2	/5Biosg/CAAGCAGAAGACGGCATACGAGATCTTGGATGGTCTCGTGGGCTCG*G
Nextera_extra_i7_3	/5Biosg/CAAGCAGAAGACGGCATACGAGATAGTCTCACGTCTCGTGGGCTCG*G
Nextera_extra_i7_4	/5Biosg/CAAGCAGAAGACGGCATACGAGATCTCATCAGGTCTCGTGGGCTCG*G
Nextera_extra_i7_5	/5Biosg/CAAGCAGAAGACGGCATACGAGATTGTACCGTGTCTCGTGGGCTCG*G
Nextera_extra_i7_6	/5Biosg/CAAGCAGAAGACGGCATACGAGATAAGTCGAGGTCTCGTGGGCTCG*G
Nextera_extra_i7_7	/5Biosg/CAAGCAGAAGACGGCATACGAGATCACGTTGTGTCTCGTGGGCTCG*G
Nextera_extra_i7_8	/5Biosg/CAAGCAGAAGACGGCATACGAGATTCACAGCAGTCTCGTGGGCTCG*G
Nextera_extra_i7_9	/5Biosg/CAAGCAGAAGACGGCATACGAGATCTACTTGGGTCTCGTGGGCTCG*G
Nextera_extra_i7_10	/5Biosg/CAAGCAGAAGACGGCATACGAGATCCTCAGTTGTCTCGTGGGCTCG*G
Nextera_extra_i7_11	/5Biosg/CAAGCAGAAGACGGCATACGAGATTCCTACCTGTCTCGTGGGCTCG*G
Nextera_extra_i7_12	/5Biosg/CAAGCAGAAGACGGCATACGAGATATGGCGAAGTCTCGTGGGCTCG*G
Nextera_extra_i7_13	/5Biosg/CAAGCAGAAGACGGCATACGAGATCTTACCTGGTCTCGTGGGCTCG*G
Nextera_extra_i7_14	/5Biosg/CAAGCAGAAGACGGCATACGAGATCTCGATACGTCTCGTGGGCTCG*G
Nextera_extra_i7_15	/5Biosg/CAAGCAGAAGACGGCATACGAGATTCCGTGAAGTCTCGTGGGCTCG*G
Nextera_extra_i7_16	/5Biosg/CAAGCAGAAGACGGCATACGAGATTAGAGCTCGTCTCGT
Nextera_extra_i7_17	/5Biosg/CAAGCAGAAGACGGCATACGAGATTGACTGACGTCTCGTGGGCTCG*G
Nextera_extra_i7_18	/5Biosg/CAAGCAGAAGACGGCATACGAGATTAGACGTGGTCTCGTGGGCTCG*G
Nextera_extra_i7_19	/5Biosg/CAAGCAGAAGACGGCATACGAGATCCGGAATTGTCTCGTGGGCTCG*G
Nextera_extra_i7_20	/5Biosg/CAAGCAGAAGACGGCATACGAGATCTCCTAGAGTCTCGTGGGCTCG*G
Nextera_extra_i7_21	/5Biosg/CAAGCAGAAGACGGCATACGAGATCAACGGATGTCTCGTGGGCTCG*G
Nextera_extra_i7_22	/5Biosg/CAAGCAGAAGACGGCATACGAGATTGGCTATCGTCTCGTGGGCTCG*G
Nextera_extra_i7_23	/5Biosg/CAAGCAGAAGACGGCATACGAGATCGGTCATAGTCTCGTGGGCTCG*G
Nextera_extra_i7_24	/5Biosg/CAAGCAGAAGACGGCATACGAGATTCCAATCGGTCTCGTGGGCTCG*G
Nextera_extra_i7_25	/5Biosg/CAAGCAGAAGACGGCATACGAGATGAGCTTGTGTCTCGTGGGCTCG*G
Nextera_extra_i7_26	/5Biosg/CAAGCAGAAGACGGCATACGAGATGAAGGTTCGTCTCGTGGGCTCG*G
Nextera_extra_i7_27	/5Biosg/CAAGCAGAAGACGGCATACGAGATATCTCGCTGTCTCGTGGGCTCG*G
Nextera_extra_i7_28	/5Biosg/CAAGCAGAAGACGGCATACGAGATAGTTACGGGTCTCGTGGGCTCG*G
Nextera_extra_i7_29	/5Biosg/CAAGCAGAAGACGGCATACGAGATGTGTCTGAGTCTCGTGGGCTCG*G
Nextera_extra_i7_30	/5Biosg/CAAGCAGAAGACGGCATACGAGATTGACTTCGGTCTCGTGGGCTCG*G
Nextera_extra_i7_31	/5Biosg/CAAGCAGAAGACGGCATACGAGATTGGATCACGTCTCGTGGGCTCG*G
Nextera_extra_i7_32	/5Biosg/CAAGCAGAAGACGGCATACGAGATACACCAGTGTCTCGTGGGCTCG*G
Nextera_extra_i7_33	/5Biosg/CAAGCAGAAGACGGCATACGAGATCAGGTTAGGTCTCGTGGGCTCG*G
Nextera_extra_i7_34	/5Biosg/CAAGCAGAAGACGGCATACGAGATAGTTGGCTGTCTCGTGGGCTCG*G
Nextera_extra_i7_35	/5Biosg/CAAGCAGAAGACGGCATACGAGATTCAACTGGGTCTCGTGGGCTCG*G
Nextera_extra_i7_36	/5Biosg/CAAGCAGAAGACGGCATACGAGATCTGCACTTGTCTCGTGGGCTCG*G
Nextera_extra_i7_37	/5Biosg/CAAGCAGAAGACGGCATACGAGATACACGGTTGTCTCGTGGGCTCG*G
Nextera_extra_i7_38	/5Biosg/CAAGCAGAAGACGGCATACGAGATAATACGCGGTCTCGTGGGCTCG*G
Nextera_extra_i7_39	/5Biosg/CAAGCAGAAGACGGCATACGAGATTGCGAACTGTCTCGTGGGCTCG*G
Nextera_extra_i7_40	/5Biosg/CAAGCAGAAGACGGCATACGAGATGCTGACTAGTCTCGTGGGCTCG*G
Nextera_extra_i7_41	/5Biosg/CAAGCAGAAGACGGCATACGAGATGTGGTGTTGTCTCGTGGGCTCG*G
Nextera_extra_i7_42	/5Biosg/CAAGCAGAAGACGGCATACGAGATGTGCTTACGTCTCGTGGGCTCG*G
Nextera_extra_i7_43	/5Biosg/CAAGCAGAAGACGGCATACGAGATTCAAGGACGTCTCGTGGGCTCG*G
Nextera_extra_i7_44	/5Biosg/CAAGCAGAAGACGGCATACGAGATTGAACCTGGTCTCGTGGGCTCG*G
Nextera_extra_i7_45	/5Biosg/CAAGCAGAAGACGGCATACGAGATAGTGTTGGGTCTCGTGGGCTCG*G
Nextera_extra_i7_46	/5Biosg/CAAGCAGAAGACGGCATACGAGATGTACTCTCGTCTCGT
Nextera_extra_i7_47	/5Biosg/CAAGCAGAAGACGGCATACGAGATCCGTATCTGTCTCGTGGGCTCG*G
Nextera_extra_i7_48	/5Biosg/CAAGCAGAAGACGGCATACGAGATCGAAGAACGTCTCGTGGGCTCG*G

All oligonucleotides carry a 5´-biotin (/5Biosg/) and a phosphorothioate bond (\*) between the last and the second last nucleotide. For cost reasons, we ordered desalted oligos and not HPLC purified.

Prepare working dilution plates containing unique combinations of N7xx + S5xx adaptors, each with a final concentration of 5 µM.

Α	В
Oligo ID	Sequence
Nextera_extra_i5_1	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCGACCATTTCGTCGGCAGCGT*C
Nextera_extra_i5_2	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGATAGCGATCGTCGGCAGCGT*C
Nextera_extra_i5_3	/5Biosg/AATGATACGGCGACCACCGAGATCTACACAATGGACGTCGTCGGCAGCGT*C
Nextera_extra_i5_4	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCGCTAGTATCGTCGGCAGCGT*C
Nextera_extra_i5_5	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTCTCTAGGTCGTCGGCAGCGT*C
Nextera_extra_i5_6	/5Biosg/AATGATACGGCGACCACCGAGATCTACACACATTGCGTCGTCGGCAGCGT*C
Nextera_extra_i5_7	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTGAGGTGTTCGTCGGCAGCGT*C
Nextera_extra_i5_8	/5Biosg/AATGATACGGCGACCACCGAGATCTACACAATGCCTCTCGTCGGCAGCGT*C
Nextera_extra_i5_9	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCTGGAGTATCGTCGGCAGCGT*C
Nextera_extra_i5_10	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGTATGCTGTCGTCGGCAGCGT*C
Nextera_extra_i5_11	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTGGAGAGTTCGTCGGCAGCGT*C
Nextera_extra_i5_12	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCGATAGAGTCGTCGGCAGCGT*C
Nextera_extra_i5_13	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCTCATTGCTCGTCGGCAGCGT*C
Nextera_extra_i5_14	/5Biosg/AATGATACGGCGACCACCGAGATCTACACACCAGCTTTCGTCGGCAGCGT*C
Nextera_extra_i5_15	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGAATCGTGTCGTCGGCAGCGT*C
Nextera_extra_i5_16	/5Biosg/AATGATACGGCGACCACCGAGATCTACACAGGCTTCTTCGTCGGCAGCGT*C
Nextera_extra_i5_17	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCAGTTCTGTCGTCGGCAGCGT*C
Nextera_extra_i5_18	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTTGGTGAGTCGTCGGCAGCGT*C
Nextera_extra_i5_19	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCATTCGGTTCGTCGGCAGCGT*C
Nextera_extra_i5_20	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTGTGAAGCTCGTCGGCAGCGT*C
Nextera_extra_i5_21	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTAAGTGGCTCGTCGGCAGCGT*C
Nextera_extra_i5_22	/5Biosg/AATGATACGGCGACCACCGAGATCTACACACGTGATGTCGTCGGCAGCGT*C
Nextera_extra_i5_23	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGTAGAGCATCGTCGGCAGCGT*C
Nextera_extra_i5_24	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGTCAGTTGTCGTCGGCAGCGT*C
Nextera_extra_i5_25	/5Biosg/AATGATACGGCGACCACCGAGATCTACACATTCGAGGTCGTCGGCAGCGT*C
Nextera_extra_i5_26	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGATACTGGTCGTCGGCAGCGT*C
Nextera_extra_i5_27	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGCCTTGTTTCGTCGGCAGCGT*C
Nextera_extra_i5_28	/5Biosg/AATGATACGGCGACCACCGAGATCTACACTTGGTCTCTCGTCGGCAGCGT*C
Nextera_extra_i5_29	/5Biosg/AATGATACGGCGACCACCGAGATCTACACCCGACTATTCGTCGGCAGCGT*C
Nextera_extra_i5_30	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGTCCTAAGTCGTCGGCAGCGT*C
Nextera_extra_i5_31	/5Biosg/AATGATACGGCGACCACCGAGATCTACACACCAATGCTCGTCGGCAGCGT*C
Nextera_extra_i5_32	/5Biosg/AATGATACGGCGACCACCGAGATCTACACGATGCACTTCGTCGGCAGCGT*C

All oligonucleotides carry a 5'-biotin (/5Biosg/) and a phosphorothioate bond (\*) between the last and the second last nucleotide. For cost reasons, we ordered desalted oligos and not HPLC purified.

Prepare working dilution plates containing unique combinations of N7xx + S5xx adaptors, each with a final concentration of 5 µM.

The protocol should be carried out in a clean environment, ideally on a dedicated PCR workstation or on a separate bench used only for this purpose. Before starting, clean the bench and wipe any piece of equipment with RNAseZAP or 0.5% sodium hypochlorite. Rinse with nuclease-free water to avoid corrosion of delicate equipment.

Work quickly and preferably on ice.

Reagent mixes should be prepared shortly before use.

Mix thoroughly each mix before dispensing. For higher accuracy use liquid handling robots and/or nanodispensers whenever possible. In FLASH-Seq we use the I.DOT (Dispendix) for all the dispensing steps and the Fluent 780 liquid handling robot (Tecan) for sample cleanup, reagent transfers and pooling.

The protocol described below is meant to be carried out in 384-well plates. When using 96-well plates, we recommend using 5 times larger volume to quarantee successful cell sorting and prevent evaporation issues.

Always use LoBind plates and tubes (especially for long-term storage) to prevent the cDNA/DNA from sticking to plastic.



#### Prepare lysis mix

15m

1

Prepare the following lysis mix:

Α	В	С	D
Reagent	Reaction	Volume (µI)	384-well
	concentration		plate
Triton-X100 (10% v/v)	0.2%	0.020	8.448
dNTP mix (25 mM each)	6 mM	0.240	101.376
SMART dT30VN (100 μM)	1.8 µM	0.018	7.603
RNAse inhibitor (40 U/µL)	1.2 U/µl	0.030	12.672
DTT (100 mM)	1.2 mM	0.012	5.069
FS TSO (100 μM)	9.2 μΜ	0.092	38.861
dCTP (100 mM)	9 mM	0.090	38.016
Betaine (5 M)	1 M	0.200	84.480
Nuclease-free water	-	0.298	125.875
Total volume (µl)		1.000	422.400

Add 11 µL lysis mix to each well of a 384-well plate

Seal the plate with a PCR seal and quickly spin it down to collect the lysis mix to the bottom.

Proceed immediately to the next step or store the plate at § -20 °C long-term. Plates that are going to be used on the same day can be stored in the fridge or kept on ice.

SAFE STOPPING POINT - Plates containing lysis buffer can be stored for >6 months at 8 -20 °C

# Sample collection

10m

2 Sort single cells into 384-well plates containing  $\blacksquare 1 \mu L$  lysis mix.

Seal the plate with an aluminium seal. If processing multiple plates at once, keep each plate on dry ice until ready to transfer them all at 8-80 °C for long-term storage. Plates containing single cells should ideally be processed within 6 months.

## Cell lysis 3m

Remove the plates from the &-80 °C freezer and check that the aluminium seal is still intact. If damaged or not sticking to the plate anymore, wait a few minutes for the plate to partially thaw, remove the damaged foil and replace it with a new one.

Place the plate in a thermocycler with a heated lid and incubate for © 00:03:00 at & 72 °C , followed by a & 4 °C hold step.

Spin down any condensation droplets that may have formed during the incubation and return the plate to a cool rack. Proceed quickly to the next step. If not ready with the RT-PCR mix, keep the plate on the cool rack at all times.

#### RT-PCR reaction 15m

4 While the plate is in the thermocycler, prepare the following RT-PCR mix:

# protocols.io

A	В	С	D
Reagent	Reaction	Volume (µl)	384-well
	concentration		plate
DTT (0.1 M)	4.8 mM	0.238	100.531
MgCl2 (1 M)	9.2 mM	0.046	19.430
Betaine (5 M)	800 mM	0.800	337.920
RNAse inhibitor (40 U/µl)	0.8 U/µl	0.096	40.550
SuperScript IV (200 U/µI)	2.00 U/µl	0.050	21.120
KAPA HiFi HotStart ReadyMix (2 x)	1 x	2.500	1056.000
Nuclease-free water	-	0.270	114.048
Total volume (μl)		4.000	1689.600

Add  $\mathbf{\Box 4} \mu \mathbf{L}$  RT-PCR mix into each well of the 384-well plate.

Seal the plate with a PCR seal, gently vortex and spin down to collect the liquid at the bottom.

Place it in a thermocycler with heated lid and start the following RT-PCR program:

Α	В	С	D	Е
Step		Temperature	Time	Cycles
RT		50°C	60 min	1 x
PCR	initial	98°C	3 min	1 x
	denaturation			
	denaturation	98°C	20 sec	18-21 x*
	annealing	67°C	20 sec	
	elongation	72°C	6 min	
		15°C	Hold	

\*Adjust the number of cycles according to the cell type used. We recommend 18-19 cycles for HEK 293T cells and 21 cycles for hPBMC. As a rule of thumb, we typically start with 1-2 less PCR cycles compared to the Smart-seq2 protocol.

SAFE STOPPING POINT - Amplified cDNA before purification can be stored for several months at 8 -20 °C

1h

### Magnetic beads working solution preparation

5 You can either use AMPure XP beads, SPRI beads or prepare your own solution of SeraMag beads containing 18% w/v PEG to reduce costs. A detailed protocol for making your own magnetic bead solution is described in:

Picelli S (2019). Full-Length Single-Cell RNA Sequencing with Smart-seq2.. Methods in molecular biology (Clifton, N.J.).

https://doi.org/10.1007/978-1-4939-9240-9\_3

Below is a short description of how to prepare 50 ml of working solution:

Α	В	С
Reagent	Amount to add	Final concentration
Sodium chloride	2.92 gr	1 M
Tris-HCl, pH = 8.0 (1 M)	500 μl	10 mM
EDTA (500 mM)	100 μΙ	1 mM
PEG (MW=8000)	9.5 gr	18% w/v
Nuclease-free solution	to a final volume of 50 ml	-

Add all components to a 50-ml Falcon tube but do not add the total amount of nuclease-free water yet.

Solubilise the PEG by stirring and heating the solution at § 37 °C .

While the PEG is dissolving, prepare the Sera-Mag SpeedBeads™. Vortex thoroughly to ensure complete resuspension and then withdraw **□1 mL** Sera-Mag SpeedBeads™ stock solution. Transfer it into a new 1.5-ml tube.

Pellet the beads by placing the tube on a magnetic stand. Wait until the solution clears and then discard the supernatant.

Add 11 mL 10 mM Tris-HCl pH 8.0 + 1 mM EDTA (TE buffer) and resuspend the beads off the magnet.

Pellet the beads again, wait until the solution is clear, discard the supernatant and resuspend off the magnet with **Double 1** TE buffer.

Once the PEG solution is clear, add the resuspended beads prepared in the previous step.

Add  $\blacksquare 50~\mu L$  Tween-20 (10% v/v) and  $\blacksquare 250~\mu L$  sodium azide (NaN<sub>3</sub>, 10% w/v) and adjust the volume to  $\blacksquare 50~m L$  with nuclease-free water.

Store at & 4 °C . Do not freeze.

Confirm that the beads have been properly prepared by cleaning-up a control sample (i.e., amplified cDNA from total RNA) and running a High Sensitivity DNA chip on the Agilent Bioanalyzer. Batch-to-batch variations in PEG concentration will influence size-cutoffs.

Add Tween-20 at the end, to prevent foaming during PEG resuspension.



Sodium azide is extremely toxic and should be handled under a fume hood.

# cDNA purification 25m

6 Remove the Sera-Mag SpeedBeads™ working solution (or AMPure XP beads or SPRI beads when using a commercial solution) from the **§ 4 °C** storage and equilibrate it at room temperature for **© 00:15:00**.

29m

We recommend adding extra nuclease-free water to each sample, to increase the volume, simplify the handling and improve recovery rate. We generally add  $\Box 10~\mu L$  nuclease-free water to  $\Box 5~\mu L$  amplified cDNA.



Add a 0.8 x volume ratio Sera-Mag SpeedBeads<sup>M</sup> working solution to each well. Mix thoroughly by pipetting or vortexing.

Incubate the plate off the magnetic stand for  $\bigcirc$  00:05:00 at & Room temperature .

Place the plate on the magnetic stand and leave it for  $\odot 00:05:00$  or until the solution appears clear.

Remove the supernatant without disturbing the beads.

Remove the plate from the magnetic stand, add  $\Box 15~\mu L$  nuclease-free water and mix well by pipetting or vortexing to resuspend the beads. Do not let the bead pellet to dry completely, as it can decrease the final cDNA yield!

Incubate **© 00:02:00** off the magnetic stand.


Place the plate back on the magnetic stand and incubate for © 00:02:00 or until the solution appears clear.

SAFE STOPPING POINT - Amplified and purified cDNA can be stored for several months at & -20 °C . We recommend using LoBind plates to avoid material losses upon long-term storage.

# Quality control check (highly recommended!)

45m

7 Check the cDNA quality on Agilent Bioanalyzer High Sensitivity DNA chip. A good sample is characterised by a low proportion of fragments <400 bp, absence of residual primers (ca. 100 bp) and an average cDNA size of 1.8–2.2 Kb.</p>



m protocols.io

10

#### cDNA quantification (optional but recommended)

15m

8 Allow the Quant-iT PicoGreen reagent to warm to 8 Room temperature before opening the vial. PicoGreen is light sensitive; while thawing, wrap in aluminium foil.

Prepare a 1 x working solution TE using 20 x TE (supplied) and nuclease-free water.

Prepare a 1:400 dilution PicoGreen solution and always use a plastic vessel.

Prepare the standard curve using Lambda DNA standard (supplied at a concentration of [ $^{1}$ 100 ng/ $^{1}$ 1 , with the Pico Green kit) and 1 x TE in 8 tubes, as below. The stock tubes can be used multiple times, keep any leftover in the fridge at  $^{8}$ 4 °C between experiments.

Vortex well and spin down the DNA standards before every use. Not vortexing thoroughly the standards is going to negatively affect the standard curve and your readings! Serial dilutions should be prepared as shown in the table below

Α	В	С	D
Tube no.	Contents	Concentration	Final volume
1	90 μl TE + 10 μl Lambda DNA stock	10 ng/μl	100 μΙ
2	50 μl from Tube 1 + 50 μl TE	5 ng/μl	100 μΙ
3	50 μl from Tube 2 + 50 μl TE	2.5 ng/μl	100 μΙ
4	50 μl from Tube 3 + 50 μl TE	1.25 ng/µl	100 μΙ
5	50 μl from Tube 4 + 50 μl TE	0.625 ng/μl	100 μΙ
6	50 μl from Tube 5 + 50 μl TE	0.3125 ng/μl	100 μΙ
7	50 μl from Tube 6 + 50 μl TE	0.15625 ng/μl	100 μΙ
8	TE only	blank	-

Prepare the PicoGreen solution by pipetting  $\Box 0.5 \, \mu L$  PicoGreen dye +  $\Box 99.5 \, \mu L$  1 X TE for each sample. Vortex to mix

Pipette  $\blacksquare 1 \mu L$  each of the 7 standards + 1 Blank into a black, flat-bottom Nunc<sup>™</sup> F96 MicroWell<sup>™</sup> plate. Place the standards on one column.

Pipet □1 µL of your samples into the center of each well of the Nunc™ F96 MicroWell™ polystyrene plate.

Add 99 µL PicoGreen + TE mix into every well. There is no need to mix.

Cover the plate with the provided plastic (transparent) lid to prevent possible contaminations.

Allow © 00:02:00 for the dye to bind the DNA. Protect from light but keep at room temperature. For optimal results, the plate should be read within the next hour.

Use a plate reader to measure fluorescence (excitation: 485 nm; emission: 530 nm; read from top; endpoint reading).

### Plate normalisation 10n

9 Prepare a normalisation plate by adding **1 μL** purified cDNA and nuclease-free water to a final concentration of [M]150 pg/μl.

### protocols.io

#### **Tagmentation and enrichment PCR**

1h

This step can be carried out either by using the commercially available Nextera XT kit or a in-house Tn5 transposase, as described below. Indexing primers can be purchased from Illumina (Nextera XT index kit v2) or ordered from your local oligo manufacturer. In the "Materials" section we have added additional sequences for higher multiplexing.

### 10.1 Tagmentation with the Nextera XT kit

13m

Please note that the volumes described here are a mere suggestion. For example, decreasing the final volume by a factor 2 (while still using the same amount of cDNA and ATM) would give comparable results but significantly reduce costs.

Prepare the tagmentation mix as described below:

Α	В
Reagent	Volume (µl)
ATM (Amplification Tagment Mix)	0.250
TD (Tagmentation DNA buffer)	2.000
Nuclease-free water	0.500
Total volume (µl)	3.000

Dispense  $\square 3 \mu L$  tagmentation mix in a new 96-well or 384-well plate.

Add 11 μL normalized cDNA ([M]150 pg/μl) to each well containing the tagmentation mix.

Seal the plate, vortex, spin down, and carry out the tagmentation reaction: § 55 °C for © 00:08:00 , § 4 °C hold. Upon completion proceed immediately to the next step.

Add  $\blacksquare 1 \ \mu L$  NT buffer to each well. Seal the plate, vortex, spin down and incubate @00:05:00 at room temperature. Do not put the plate back on ice.

Add  $\Box 2 \mu L$  N7xx + S5xx index adaptors ([M]5 micromolar ( $\mu M$ ) each).

Add 3 µL NPM solution to each well.

Seal the plate, vortex, spin down, and place it in a thermocycler and carry out the enrichment PCR reaction. Adjust the number of PCR cycles according to the number of processed cells.

Α	В	С	D	Е
Step		Temperature	Time	Cycles
gap filling		72°C	3 min	1 x
enrichment PCR	initial denaturation	95°C	30 sec	1 x
	denaturation	95°C	10 sec	12-14 x
	annealing	55°C	30 sec	
	elongation	72°C	30 sec	
		15°C	hold	

SAFE STOPPING POINT - The final unpurified sequencing library can be stored for several months at  $\ \ \&\ -20\ ^{\circ}C$ 

## 10.2 Tagmentation with in-house Tn5 transposase

Please note that the Tn5 transposase amount indicated below is a suggested starting point for tagmenting [M]150 pg/ $\mu$ l cDNA. Optimisation might be necessary, depending on the specific activity of each batch of Tn5.

Prepare the tagmentation mix as described below:

Α	В	С	
Reagent	Volume (µI)	Final concentration	
TAPS-Mg buffer, pH=7.3 (5 x)	0.800	10 mM TAPS, 5 mM MgCl2	
Dimethylformamide (DMF) (100%)	0.800	20%	
Tn5 transposase (2 μM working dil.)	0.125	62.5 nmol	
Nuclease-free water	2.275		
Total volume (μl)	3.000		



Dimethylformamide (DMF) is toxic and should be handled under the hood according to local safety regulations.

Dispense 34-well plate.

Add  $\Box 1~\mu L~$  normalized cDNA ([M] 150 pg/ $\mu l~$ ) to each well containing the tagmentation mix.

Seal the plate, vortex, spin down, and carry out the tagmentation reaction: § 55 °C for © 00:08:00 , § 4 °C hold. Upon completion proceed immediately to the next step.

Add  $\Box 1~\mu L~$  0.2% SDS to each well. Seal the plate, vortex, spin down and incubate 5 min at room temperature. Do not put the plate back on ice.

Add  $\square 2 \mu L$  N7xx + S5xx index adaptors ([M]5 micromolar ( $\mu M$ ) each).

Add 3 µL enrichment PCR mix to each well:

Α	В	С	
Reagent	Volume (µl)	Final concentration	
KAPA HiFi enzyme (1 U/μl)	0.200	0.02 U/μl	
KAPA HiFi buffer (5 x)	2.000	1 x	
dNTPs (10 mM)	0.300	300 nM	
Nuclease-free water	0.500		
Total volume (µl)	3.000		

Seal the plate, vortex, spin down, and place it in a thermocycler and carry out the enrichment PCR reaction. Adjust the number of PCR cycles according to the number of processed cells.

Α	В	С	D	Е
St	ер	Temperature	Time	Cycles
gap f	illing	72°C	3 min	1 x
enrichment PCR	initial denaturation	98°C	30 sec	1 x
	denaturation	98°C	10 sec	12-14 x
	annealing	55°C	30 sec	
	elongation	72°C	30 sec	
		15°C	hold	

### Library cleanup and quantification

30m

Take an aliquot from each sample for the final library cleanup (i.e. 5 μl). and transfer it to a 1.5-ml Eppendorf tube.

The rest of the library can be stored long-term at δ -20 °C.

Remove the Sera-Mag SpeedBeads™ working solution from the § 4 °C storage and equilibrate it at room temperature for © 00:15:00 .

Add Sera-Mag SpeedBeads™ working solution to a final ratio of 0.8 x and mix well to homogenisation.

Incubate the tube off the magnetic stand for  $\bigcirc$  00:05:00 at 8 Room temperature.

Place the tube on the magnetic stand and leave it for © 00:05:00 or until the solution appears clear.

Remove the supernatant without disturbing the beads.

Recommended: wash the pellet with 1 mL 80% v/v ethanol. Incubate 00:00:30 without removing the tube from the magnetic stand.

Remove any trace of ethanol and let the bead pellet dry for  $\bigcirc$  **00:02:00** or until small cracks appear. Do not cap the tube or remove it from the magnetic stand during this time. Do not completely air-dry the beads.

Remove the tube from the magnetic stand, add  $\Box 50~\mu L$  nuclease-free water and mix well by pipetting or vortexing to resuspend the beads.

Incubate © 00:02:00 off the magnetic stand.

Place the tube back on the magnetic stand and incubate for © 00:02:00 or until the solution appears clear.

Remove  $\Box 49~\mu L$  of the supernatant and transfer it to a new 1.5-ml LoBind tube. Store the cDNA at & -20 °C long-term or until ready for sequencing.


Use Qubit fluorometer to quantify the library. Library yield can vary depending on the number of cells being pooled.

Check the final library size on the Agilent Bioanalyzer.

Use the average size indicated on the Bioanalyzer and the concentration reported after Qubit measurement to determine the exact molarity required for sequencing.







SAFE STOPPING POINT - The final purified sequencing library can be stored for several months at 8 -20 °C .

# Pooling and sequencing

12 The purified library can be sequenced on any Illumina sequencer. Follow the specifications reported for each instrument. Single-End 75 bp is generally sufficient but longer read modes or Paired-End sequencing can be an option, depending on the question at hand.

# Data processing

These instructions briefly describe the data processing of the sequencing results. The final pipeline will likely have to be adapted to the question at hand. The following lines assume that all the programs and their dependencies are installed on your machine and that the data are single-end reads (75 bp). Some values, such as the number of threads and RAM usage may have to be adapted to your machine settings.

It should be noted that there are many other ways to analyse full-length single-cell RNA-sequencing data. Pseudo-alignment tools (e.g., Salmon or Kallisto) or automatic pipelines (zUMIs) could be used as well.

Requirements (tested version):

- bcl2fastq (v2.20)
- STAR (v2.7.3)
- FeatureCounts (v1.6.5)
- BBMAP (v38.86)
- samtools (v1.9)
- IGV

# 13.1 Sample demultiplexing

Sequencing results will be delivered as demultiplexed FASTQ or raw bcl2 files. To convert bcl2 files



```
# 0. Variables
BASECALL_DIR="/path/to/flowcell/Data/Intensities/BaseCalls/"
OUTPUT_DIR="/path/to/output_folder/"
SAMPLESHEET="/path/to/Demultiplexing_SampleSheet.csv"
```

```
# 1. Bcl2fastq
ulimit -n 10000
cd /path/to/flowcell/
bcl2fastq --input-dir $BASECALL_DIR --output-dir $OUTPUT_DIR --sample-
sheet $SAMPLESHEET --create-fastq-for-index-reads --no-lane-splitting
```

When sequencing on a NextSeq550 instrument, the sample sheet should contain the following information in a csv file:

Illumina Experiment Manager can be used to assist you in creating the sample sheet.

We recommend exploring the barcode combinations left in the undetermined reads looking to confirm that all the cells have been properly demultiplexed.

```
zcat Undetermined_S0_I1_001.fastq.gz | awk -F' 1:N:0:' 'NR%4==1{print
$2}' | sort | uniq -c > left_index.txt
sort -k1,1 left_index.txt
```

as well as the read distribution between samples:

```
for file in ./out/*R1*
do
zcat $file | wc -l
done
```

#### 13.2 Index the genome

The reference genome needs to be indexed prior to any mapping. The FASTA and GTF references can be obtained from ENSEMBL, Gencode, UCSC, ...

# 0. Variables

OUTPUTREF="/path/to/STAR\_indexed\_genome/"

FASTA="GRCh38.primary\_assembly.genome.fa"

GTF="gencode.v34.primary\_assembly.annotation.gtf"

# 1. Genome indexing
# sjdbOverhang should be adapted based on the read length (read\_length 1)
mkdir \$OUTPUTREF

STAR --runThreadN 15 --runMode genomeGenerate --genomeDir \$OUTPUTREF --genomeFastaFiles \$FASTA --sjdbGTFfile \$GTF -sjdbOverhang 74

### 13.3 FASTQ trimming (optional)

If you observe sequencing primer left-overs the FASTQ files can be trimmed using BBDUK or Trimmomatic.

bbduk.sh -Xmx48g in=sample.fastq.gz out=cleaned.left.fastq t=32 ktrim=l ref=adapters.fa k=23 mink=7 hdist=1 hdist2=0 tbo bbduk.sh -Xmx48g in=cleaned.left.fastq out=cleaned.fastq t=32 ktrim=r ref=adapters.fa k=23 mink=7 hdist=1 hdist2=0 tbo

mv FASTQ/cleaned.fastq FASTQ/sample.R1.fastq.gz

# 13.4 Mapping

The FASTQ file can then be mapped onto the reference genome. Example for one sample, use a



loop or parallelise this task to process all the cells:

# 0. Variables

GENOME="/path/to/STAR\_indexed\_genome/"
FASTQ="/path/to/sample.R1.fastq.gz"
ID="sample\_id"

#### # 1. Mapping

STAR --runThreadN 30 --limitBAMsortRAM 2000000000 --genomeLoad LoadAndKeep --genomeDir "\$GENOME" --readFilesIn "\$FASTQ" -- readFilesCommand zcat --limitSjdbInsertNsj 2000000 -- outFilterIntronMotifs RemoveNoncanonicalUnannotated --outSAMtype BAM SortedByCoordinate --outFileNamePrefix "\$ID"\_

#### # 2. SAM to sorted BAM

# -F 260 filters out unmapped and secondary alignments samtools view -@ 30 -Sb -F 260 "\$ID"\_Aligned.sortedByCoord.out.bam > "\$ID"\_Aligned.sortedByCoord.filtered.bam samtools index "\$ID"\_Aligned.sortedByCoord.filtered.bam

### 13.5 Data visualization (optional)

Once the reads have been mapped we highly recommend using the Integrated Genome Viewer (IGV) to visualise the mapping results and ensure that the results make sense. As a quick check-up visualise a few housekeeping genes (i.e., ACTB, GAPDH, ...) and cell specific markers to look for reads mapping to exon, intron, exon-intron junctions. Look for abnormalities such as read piles falling in intergenic or centromeric regions.

No single-cell RNA sequencing protocol is perfect and non-specific priming, genomic DNA contaminations, ... can happen but should represent rare events.

Recurrent soft-clipping could also indicate the presence of sequencing adaptor left-overs that could affect the mapping rate.

### 13.6 Count matrix

Finally, the number of reads associated with each gene can be obtained as follows:

featureCounts -T 1 -t exon -g gene\_name --fracOverlap 0.25 -a "\$GTF" -o "\$ID"\_ReadCount.featureCounts.gencode.txt "\$ID"\_Aligned.sortedByCoord.filtered.bam



## 13.7 Post-processing

The post-processing steps will vary depending on the question at hand. The online book "Orchestrating Single-Cell Analysis with Bioconductor" (<a href="https://bioconductor.org/books/release/OSCA/">https://bioconductor.org/books/release/OSCA/</a>) is a gold mine of information that can be used to help you design your own pipeline. Alternatively, Seurat (R, <a href="https://satijalab.org/seurat/">https://satijalab.org/seurat/</a>) or scanpy (python, <a href="https://scanpy.readthedocs.io/en/stable/">https://scanpy.readthedocs.io/en/stable/</a>) provide tools compatible with FLASH-seq data. Given their similarities, we currently recommend using Smart-seq2 guidelines when processing FLASH-seq data.

19