

Jun 28, 2024

Preparation of SARS-CoV-2 Saliva Samples Using an ARTIC V4.1 Tiled Amplicon Approach for Sequencing on Illumina Platforms

This protocol is a draft, published without a DOI.

Leah Lariscy¹, Amanda Sullivan¹, Katie Dillon¹, Megan Lott¹, Travis Glenn¹, Erin Lipp¹

¹University of Georgia



Leah Lariscy

University of Georgia

OPEN ACCESS



Protocol Citation: Leah Lariscy, Amanda Sullivan, Katie Dillon, Megan Lott, Travis Glenn, Erin Lipp 2024. Preparation of SARS-CoV-2 Saliva Samples Using an ARTIC V4.1 Tiled Amplicon Approach for Sequencing on Illumina Platforms. **protocols.io**https://protocols.io/view/preparation-of-sars-cov-2-saliva-samples-using-an-df9e3r3e

License: This is an open access protocol distributed under the terms of the <u>Creative Commons Attribution License</u>, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's

working

Created: June 25, 2024

Last Modified: June 28, 2024

Protocol Integer ID: 102406

Funders Acknowledgement: Centers for Disease Control

and Prevention

Grant ID: 75D30121C11163



Abstract

This protocol describes how to prepare purified SARS-CoV-2 RNA from positive saliva samples for short-read sequencing. The initial targeted amplification utilizes the commercially available IDT ARTIC V4.1 tiled amplicon panel, followed by amplification with IDT custom-ordered fusion primers that follow the same amplicon scheme, allowing for further amplification of target molecules and eliminating the need for end repair and adapter ligation. Completion of this protocol should result in a clean, multiplexed DNA library pool ready for sequencing.



Materials

Reagents

LunaScript RT Supermix (NEB, E3010L)

Q5 Hot Start High-Fidelity 2X Master Mix (NEB, M0494)

Water, Molecular Biology Grade (Fisher, BP2819-1)

1X TE Solution pH 8.0 (IDT 11-05-01-09)

SpeedBead Magnetic Carboxylate (Cytiva, 65152105050250)

ARTIC V4.1 NCOV-2019 Panel (IDT, 10011442)

ARTIC V4.1 Fusion oPool Panel (IDT, Custom Order)

KAPA HiFi HotStart PCR Kit (Roche, 07958897001)

TBE Buffer Premix Powder (Bio Basic, A0024)

GelRed Nucleic Acid Gel Stain (Gold Bio, G-725-500)

GeneRuler DNA Ladder Mix (Thermo Scientific, SM0333)

Gel Loading Dye Purple 6X (NEB, B7024S)

Qubit 1X dsDNA HS Assay Kit (Invitrogen, Q33231)

Water, Deionized

Equipment

Micropipettes (p10, p20, p200, p1000)

Microcentrifuge

Microplate centrifuge

Vortex mixer

PCR thermal cycler (Bio-Rad, T100)

MagnaBotTM II Magnetic Separation Device (Promega, V8351)

DynaMagTM-2 Magnet (Invitrogen, 12321D)

Analytical balance

Graduated cylinder

Plastic carboy with spigot

250 mL Flask

Owl TM Wide Gel Electrophoresis System (Thermo Scientific, D3-14)

PowerPacTM Basic Power Supply (Bio-Rad, 1645050)

FastGeneTM FAS-V Gel Imaging System (Nippon Genetics, GP-FAS-V)

Qubit**TM** 4 Fluorometer (Invitrogen, Q33226)

Consumables

1.5 mL tubes, DNA/RNAse free

0.2 mL strip tubes, DNA/RNAse free

0.2 mL 96-well plates, DNA/RNAse free

Reagent reservoirs, DNA/RNAse free

TempPlate R Sealing Foil (USA Scientific, 2923-0100)

Microseal (R) 'F' Foil Seal (Bio-Rad, MSF1001)



cDNA Synthesis

Thaw reagents appropriately prior to use.

- Thaw purified RNA samples on ice
- LunaScript RT Supermix does not require thawing and should remain at -20°C
- 2 Gently vortex and spin down reagents and samples
- 3 Prepare the cDNA synthesis reactions as follows:
- 3.1 For purified RNA samples, combine the following components in a 96-well plate:

A	В	
Component	Volume (µl)	
RNA Sample	16	
LunaScript RT SuperMix	4	
Total Volume	20	

3.2 For no template controls, combine the following components in a 96-well plate:

A	В
Component	Volume (µl)
Nuclease-free Water	16
LunaScript RT SuperMix	4
Total Volume	20

4 Pipet up and down 10 times to mix.



- 5 Add plate seal and spin down.
- 6 Incubate reactions in a thermocycler under the following conditions:





A	В	С	D
Step	Temp (°C)	Duration	Cycles
Annealing	25	2 minutes	1
Synthesis	55	20 minutes	1
Inactivation	95	1 minute	1
Hold	4	∞	1

Set heated lid to 105°C

Note

Safe to stop. Store cDNA at -20°C for short-term storage or at -80°C for long-term storage prior to the next step.

Tiled Amplicon PCR 1

- 7 Thaw reagents appropriately prior to use.
 - Thaw amplicon primer pools at room temperature
 - Thaw cDNA on ice
 - Q5 Hot Start High-Fidelity 2X Master Mix does not require thawing and should remain at -20°C
- 8 Prepare the ARTIC V4.1 NCOV-2019 Panel by diluting each 100 µM primer pool 1:10 in Nuclease-free Water for a 10 µM working stock.
- 9 Gently vortex and spin down reagents and samples
- 10 Prepare the split pool amplification reactions as follows:
- 10.1 For Pool Set 1, combine the following components in a 96-well plate:

A	В	
Component	Volume (µl)	
cDNA	4.5	
Q5 Hot Start Master Mix	6.25	



	A	В
	Artic V4.1 Pool 1	1.75
	Total Volume	12.5

For Pool Set 2, combine the following components in a 96-well plate: 10.2

0

А	В	
Component	Volume (µl)	
cDNA	4.5	
Q5 Hot Start Master Mix	6.25	
Artic V4.1 Pool 2	1.75	
Total Volume	12.5	

11 Pipet up and down 10 times to combine.



- 12 Add plate seal and spin down.
- 13 Incubate reactions in a thermocycler under the following conditions:

=	- 4
\sim	- (
	- 1
	Z

A	В	С	D
Step	Temp (°C)	Duration	Cycles
Initial Denaturation	98	30 seconds	1
Denaturation	95	15 seconds	25
Annealing/ Extension	63	5 minutes	25
Hold	4	∞	1

Set heated lid to 105°C

Note

Do not combine split reactions. This will be done after Tiled Amplicon PCR 2 and subsequent gel electrophoresis.



Note

Safe to stop. Store at 4°C overnight or -20°C for short-term storage prior to the next step.

Tiled Amplicon PCR 2

- 14 Thaw reagents appropriately prior to use.
 - Thaw amplicon primer pools at room temperature
 - If needed, thaw PCR 1 products on ice
 - KAPA HiFi Enzyme does not require thawing and should remain at -20°C
 - All other KAPA components should be thawed on ice
- 15 Prepare the Custom ARTIC V4.1 Fusion oPool Panel by reconstituting each primer pool with Nuclease-free Water to a final concentration of 10 μM.
- 16 Gently vortex and spin down reagents and samples.
- 17 Prepare the split pool amplification reactions as follows:
- 17.1 For Pool Set 1, combine the following components in a 96-well plate

	A	В	
	Component	Volume (µl)	
	PCR 1 Pool 1 Product	5	
	Nuclease-free Water	5.5	
	KAPA dNTPs	0.45	
_	KAPA HiFi Enzyme	0.3	
	5X KAPA Buffer	3	
	Custom ARTIC V4.1 oPool 1	0.75	
	Total Volume	15	

17.2 For Pool Set 2, combine the following components in a 96-well plate

_		
	A	В
	Component	Volume (µl)
	PCR 1 Pool 2 Product	5
	Nuclease-free Water	5.5
	KAPA dNTPs	0.45
	KAPA HiFi Enzyme	0.3
	5X KAPA Buffer	3
	Custom ARTIC V4.1 oPool 2	0.75
	Total Volume	15

Pipet up and down 10 times to combine. 18



- 19 Add plate seal and spin down.
- 20 Incubate reactions in a thermocycler under the following conditions:



A	В	С	D
Step	Temp (°C)	Duration	Cycles
Initial Denaturation	98	2 minutes	1
Denaturation	95	30 seconds	6
Annealing	55	30 seconds	6
Extension	72	1 minute	6
Final Extension	72	5 minutes	1
Hold	4	∞	1

Set heated lid to 105°C

Quality Control of Tiled Amplicons

21 Prepare a 1.5% TBE agarose gel.



21.1 Follow manufacturer instructions to prepare a 10X TBE stock solution from TBE premix powder

21.2 Prepare 4 1 L of 0.5X TBE solution by combining the following reagents in a carboy:

	A	В
Г	Component	Amount
Г	10X TBE	50 mL
Г	DI Water	950 mL

21.3 Shake or mix the 0.5X TBE solution until homogenous.



21.4 Prepare a 1.5% TBE agarose gel large enough to fit 2x50-well combs (enough for 96 samples, plus DNA ladders) by combining the following reagents in a flask:

	А	В
ſ	Component	Amount
ſ	0.5X TBE	150 mL
	Agarose gel powder	2.25 g

21.5 Mix components in flask gently to combine.



21.6 Microwave the flask in short intervals, until the agarose powder if fully dissolved.

21.7 Allow the flask to cool briefly before adding 1.70 µl of the GelRed Nucleic Acid Stain and mixing gently to combine.



Note

Do not cool the agarose for more than a few minutes or it will begin to solidify.

21.8 Place the gel casting rig on a flat surface and slowly pour the liquid agarose into the rig, then add the well combs and allow the gel to fully solidify.

- 22 Run gel electrophoresis.
- 22.1 Remove the well combs and place the prepared gel in an appropriately sized electrophoresis
- 22.2 Fill the rig with 0.5X TBE solution until the gel is completely submerged.
- 22.3 Follow manufacturer instructions for preparing the DNA loading dye.
- 22.4 To prepare the samples for loading, combine $\Delta 3 \mu$ of each sample with $\Delta 3 \mu$ of prepared DNA loading dye and pipette gently to mix.



22.5 Use a p10 pipette to load Δ 6 μ L of sample-dye mixture into the prepared wells.



22.6 Connect the gel rig to the power supply and run gel electrophoresis at 100V for 00:40:00.



- 22.7 Visualize the DNA using a gel imager.
- 23 Check DNA concentrations using a Qubit Fluorometer (OPTIONAL)



23.1 Follow manufacturer instructions for how to prepare samples and calculate dsDNA concentrations using the Qubit 1X dsDNA HS Assay.

Combine Split Reactions

- 24 In a new 96-well plate, combine 🛕 6 µL of PCR 2 Pool 1 Product and 🗸 6 µL of PCR 2 Pool 2 Product for a total volume of \perp 12 μ L.
- 25 Add a plate seal, then vortex gently and spin down.

Cleanup of Combined Tiled Amplicon PCR 2 Product





26 Allow the bead solution to come to room temperature and vortex to resuspend.

Note

See the SpeedBead Preparation Protocol for instructions on how to prepare the beads.

- 27 Add $\perp 9.6 \,\mu$ L (0.8X) of resuspended beads to $\perp 12 \,\mu$ L of combined PCR product.
- 28 Mix well by pipetting up and down 10 times or vortex gently. Quickly spin down the samples after mixing, stopping before the beads settle out.

29 Incubate at room temperature for (5) 00:10:00 .



- 30 Place the samples on an appropriate magnetic stand to separate beads from the supernatant.
- 31 Once the solution is clear, carefully remove and discard the supernatant.

Note

Take care not to remove any beads, otherwise product may be lost.

32 While on the magnetic stand, add \perp 100 μ L of freshly prepared 80% ethanol to the tubes. Briefly incubate at room temperature for 00:00:30, then carefully remove and discard the supernatant without disturbing the beads.



- 33 While the beads are still dark brown and glossy, elute the samples in 🚨 12 µL of 0.1X TE buffer. Gently vortex and spin down the samples.



Note

Do not over-dry the beads, as this may result in lower recovery.



34 Incubate at room temperature for at least 00:10:00 before placing the samples back on the magnetic rack. Once solution is clear, remove the supernatant and transfer to a clean 96well plate.



Note

Safe to stop. Store at 4°C overnight or -20°C for short-term storage prior to the next step.

PCR Enrichment with Illumina TruSeq Primers

- 35 Thaw reagents appropriately prior to use.
 - Thaw TruSeq primers at room temperature
 - If needed, thaw clean PCR 2 products on ice
 - KAPA HiFi Enzyme does not require thawing and should remain at -20°C
 - All other KAPA components should be thawed on ice
- 36 Gently vortex and spin down reagents and samples.
- 37 For TruSeq PCR, combine the following components in a 96-well plate:

A	В	
Component	Volume (µl)	
Clean PCR 2 Product	10	
Nuclease-free Water	3.75	
KAPA dNTPs	0.75	
KAPA HiFi Enzyme	0.5	
5X KAPA Buffer	5	
i5 Primer (5 μM)	2.5	
i7 Primer (5 μM)	2.5	
Total Volume	25	

38 Pipet up and down 10 times to combine.





- 39 Add plate seal and spin down.
- 40 Incubate reactions in a thermocycler under the following conditions:



A	В	С	D
Step	Temp (°C)	Duration	Cycles
Initial Denaturation	98	2 minutes	1
Denaturation	95	30 seconds	6
Annealing	55	30 seconds	6
Extension	72	1 minute	6
Final Extension	72	5 minutes	1
Hold	4	∞	1

Set heated lid to 105 °C

Note

Safe to stop. Store at 4°C overnight or -20°C for short-term storage prior to the next step.

Quality Control of TruSeq Libraries

41 Prepare a 1.5% TBE agarose gel.

Note

See steps 21.1 through 21.8 for instructions on how to prepare the gel.

≣5 go to step #21

42 Run gel electrophoresis.



Note

See steps 22.1 through 22.7 for instructions on how to run gel electrophoresis and visualize the libraries. 30×10^{-2} 30×10^{-2}

43 Check DNA concentrations using a Qubit Fluorometer (**OPTIONAL**)



43.1 Follow manufacturer instructions for how to prepare samples and calculate dsDNA concentrations using the Qubit 1X dsDNA HS Assay.

Note

Safe to stop. Store at 4°C overnight or -20°C for short-term storage prior to the next step.

Pooling of TruSeq Libraries for Sequencing

- 44 Create a library pooling spreadsheet with the following information included from each sample to be pooled:
 - 1. Sample ID
 - 2. Average sample size (bp)
 - 3. Sample concentration (estimated from gel or calculated using Qubit)
 - 4. Desired number of reads
- Using the above information, calculate the appropriate volume (µI) from each library to be added to the final pool so that each sample receives the desired number of reads.
- 46 Combine the appropriate volume of each library into a clean 1.5 mL tube.



47 Vortex to combine and spin down.



Note

Safe to stop. Store at 4°C overnight or -20°C for short-term storage prior to the next step.

Final Cleanup of Pooled Libraries



- - 48 Add \perp 50 µL of the final pool to a clean 1.5 mL tube.
 - 49 Allow the bead solution to come to room temperature and vortex to resuspend.

Note

See the SpeedBead Preparation Protocol for instructions on how to prepare the beads

- 50 To the \perp 50 μ L of final pool, add \perp 45 μ L (0.9X) of resuspended beads.
- 51 Mix well by pipetting up and down 10 times or vortex gently. Quickly spin down after mixing, stopping before the beads settle out.
- 52 Incubate at room temperature for 00:10:00.
- 53 Place the samples on an appropriate magnetic stand to separate beads from the supernatant.
- 54 Once the solution is clear, carefully remove and discard the supernatant.

Note

Take care not to remove any beads, otherwise product may be lost.

- 55 While on the magnetic stand, add \perp 200 μ L of freshly prepared 80% ethanol to the tubes. Briefly incubate at room temperature for 00:00:30 , then carefully remove and discard the supernatant without disturbing the beads.
- 56 While the beads are still dark brown and glossy, elute the samples in $\perp \Delta$ 50 µL of 0.1X TE buffer. Gently vortex and spin down the samples.

Note

Do not over-dry the beads, as this may result in lower recovery.

10m

30s



57 Incubate at room temperature for at least 60 00:10:00 before placing the samples back on the magnetic rack. Once solution is clear, remove the supernatant and transfer to a clean 1.5 mL tube.





Note

Libraries are now ready to be sequenced. Store at -20°C for short-term storage or -80°C for long-term storage prior to sequencing.