

1 Namespace Index	1
1.1 Namespace List	1
2 Hierarchical Index	3
2.1 Class Hierarchy	3
3 Class Index	5
3.1 Class List	5
4 File Index	7
4.1 File List	7
5 Namespace Documentation	9
5.1 Common Namespace Reference	9
5.1.1 Function Documentation	
5.1.1.1 AreRawStringsEqual() [1/2]	10
5.1.1.2 AreRawStringsEqual() [2/2]	
5.1.1.3 CopyRawString() [1/2]	
5.1.1.4 CopyRawString() [2/2]	
5.1.1.5 GetIteratorDistance()	
5.1.1.6 GetRawStringLength() [1/2]	
5.1.1.7 GetRawStringLength() [2/2]	
5.1.1.8 MakePair()	
6 Class Documentation	15
6.1 Common::CDoesNotExist Class Reference	
6.1.1 Detailed Description	
6.1.2 Constructor & Destructor Documentation	
6.1.2.1 CDoesNotExist()	
6.2 Common::CException Class Reference	
6.2.1 Detailed Description	
6.2.2 Constructor & Destructor Documentation	
6.2.2 Constructor & Destructor Documentation	
6.2.2.2 ~CException()	
6.2.3 Member Function Documentation	
6.2.3.1 GetMessage()	
6.2.4 Member Data Documentation	
6.2.4.1 Message	
6.3 Common::COutOfRange Class Reference	
6.3.1 Detailed Description	
6.3.2 Constructor & Destructor Documentation	
6.3.2.1 COutOfRange() [1/2]	
6.3.2.2 COutOfRange() [2/2]	
6.3.3 Member Function Documentation	19

6.3.3.1 GetExpectedRange()	19
6.3.3.2 GetRequestedIndex()	19
6.3.4 Member Data Documentation	20
6.3.4.1 ExpectedIndex	20
6.3.4.2 RequestedIndex	20
$ 6.4 \ Common:: TOptional < T > Class \ Template \ Reference \ $	20
6.4.1 Detailed Description	20
6.4.2 Constructor & Destructor Documentation	21
6.4.2.1 TOptional() [1/2]	21
6.4.2.2 TOptional() [2/2]	21
6.4.3 Member Function Documentation	21
6.4.3.1 GetValue()	21
6.4.3.2 GetValueOr()	21
6.4.3.3 operator=()	22
6.4.3.4 SetValue()	22
6.4.3.5 ValueExists()	22
6.5 Common::TPair < T1, T2 > Class Template Reference	23
6.5.1 Detailed Description	23
6.5.2 Constructor & Destructor Documentation	23
6.5.2.1 TPair() [1/2]	23
6.5.2.2 TPair() [2/2]	23
6.5.3 Member Function Documentation	24
6.5.3.1 MakePair()	24
6.5.4 Member Data Documentation	24
6.5.4.1 First	24
6.5.4.2 Second	24
6.6 Common::TVector< T > Class Template Reference	25
6.6.1 Detailed Description	29
6.6.2 Member Typedef Documentation	29
6.6.2.1 CConstiterator	29
6.6.2.2 CConstReverselterator	29
6.6.2.3 Clterator	29
6.6.2.4 CReverselterator	30
6.6.2.5 CSafeConstIterator	30
6.6.2.6 CSafeConstReverseIterator	30
6.6.2.7 CSafeIterator	30
6.6.2.8 CSafeReverseIterator	30
6.6.3 Member Enumeration Documentation	30
6.6.3.1 EReservedCapacityRule	30
6.6.4 Constructor & Destructor Documentation	31
6.6.4.1 TVector() [1/8]	31
6.6.4.2 TVector() [2/8]	31

6.6.4.3 TVector() [3/8]	
6.6.4.4 TVector() [4/8]	
6.6.4.5 TVector() [5/8]	
6.6.4.6 TVector() [6/8]	
6.6.4.7 TVector() [7/8]	
6.6.4.8 TVector() [8/8]	
6.6.4.9 ~TVector()	
6.6.5 Member Function Documentation	
6.6.5.1 Assign()	
6.6.5.2 AutoAt()	
6.6.5.3 Back() [1/2]	
6.6.5.4 Back() [2/2]	
6.6.5.5 Begin()	
6.6.5.6 begin() [1/2]	
6.6.5.7 begin() [2/2]	
6.6.5.8 cbegin()	
6.6.5.9 cend()	
6.6.5.10 Clear()	
6.6.5.11 ConstBegin()	
6.6.5.12 ConstEnd()	
6.6.5.13 ConstReverseBegin()	
6.6.5.14 ConstReverseEnd()	
6.6.5.15 crbegin()	
6.6.5.16 crend()	
6.6.5.17 End()	
6.6.5.18 end() [1/2]	
6.6.5.19 end() [2/2]	3.
6.6.5.20 Erase()	3.
6.6.5.21 EraseMultiple()	3.
6.6.5.22 Front() [1/2]	
6.6.5.23 Front() [2/2]	
6.6.5.24 GetCapacity()	
6.6.5.25 GetCapacityRule()	
6.6.5.26 GetSize()	
6.6.5.27 Insert() [1/2]	
6.6.5.28 Insert() [2/2]	
6.6.5.30 operator"!=()	
6.6.5.31 operator=() [1/3]	
6.6.5.33 operator=() [3/3]	
6.6.5.34 operator==()	

6.6.5.35 operator[]() [1/2]		. 44
6.6.5.36 operator[]() [2/2]		. 45
6.6.5.37 Pop()		. 45
6.6.5.38 PopMultiple()		. 45
6.6.5.39 Push() [1/2]		. 46
6.6.5.40 Push() [2/2]		. 46
6.6.5.41 RawData() [1/2]		. 47
6.6.5.42 RawData() [2/2]		. 47
6.6.5.43 rbegin() [1/2]		. 47
6.6.5.44 rbegin() [2/2]		. 47
6.6.5.45 rend() [1/2]		. 47
6.6.5.46 rend() [2/2]		. 48
6.6.5.47 Reserve()		. 48
6.6.5.48 Resize()		. 48
6.6.5.49 ReverseBegin()		. 49
6.6.5.50 ReverseEnd()		. 49
6.6.5.51 SafeAt() [1/2]		. 49
6.6.5.52 SafeAt() [2/2]		. 49
6.6.5.53 SafeBack() [1/2]		. 50
6.6.5.54 SafeBack() [2/2]		. 50
6.6.5.55 SafeBegin()		. 50
6.6.5.56 SafeConstBegin()		. 50
6.6.5.57 SafeConstEnd()		. 51
6.6.5.58 SafeConstReverseBegin()		. 51
6.6.5.59 SafeConstReverseEnd()		. 51
6.6.5.60 SafeEnd()		. 51
6.6.5.61 SafeFront() [1/2]		. 52
6.6.5.62 SafeFront() [2/2]		. 52
6.6.5.63 SafePop()		. 52
6.6.5.64 SafeReverseBegin()		. 52
6.6.5.65 SafeReverseEnd()		. 52
6.6.5.66 SafeShift()		. 53
6.6.5.67 SetCapacityRule()		
6.6.5.68 Shift()		. 53
6.6.5.69 ShiftMultiple()		. 54
6.6.5.70 ShrinkToFit()		. 54
6.6.5.71 Swap()		. 54
7 File Documentation		55
7.1 CommonTypes/Exception.h File Reference		
7.2 CommonTypes/Optional.h File Reference		
7.3 CommonTypes/Pair.h File Reference		
	•	

7.4 CommonTypes/Private/BlockIterator.tpp File Reference	56
7.5 CommonTypes/Private/Vector.tpp File Reference	56
7.6 CommonTypes/Vector.h File Reference	56
7.7 CommonUtils/AdvancedIteration.h File Reference	57
7.8 CommonUtils/Assert.h File Reference	57
7.8.1 Macro Definition Documentation	57
7.8.1.1 ASSERT	57
7.9 CommonUtils/Private/AdvancedIteration.tpp File Reference	57
7.10 CommonUtils/Private/RawString.cpp File Reference	57
7.11 CommonUtils/RawString.h File Reference	58
7.12 x64/Debug/CodeAnalysisResultManifest.txt File Reference	58
7.13 x64/Debug/CommonLibs.vcxproj.FileListAbsolute.txt File Reference	58
Index	59

Namespace Index

1.1 Namespace List

ere is a list (of all nam	nespaces	with brief d	escriptions:		
Common					 	

2 Namespace Index

Hierarchical Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Common::CException				16
Common::CDoesNotExist				 15
Common::COutOfRange				 17
Common::TOptional < T >				20
Common::TPair $<$ T1, T2 $>$				23
${\sf Common::TPair} < {\sf size_t}, {\sf size_t} > \dots $				23
Common::TVector< T >				25

4 Hierarchical Index

Class Index

3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Common::CDoesNotExist	
Represents "Element does not exist" error. Stores message	15
Common::CException	
Basic exception class. C-style message is required	16
Common::COutOfRange	
Represents "Out of Range" error. Can hold message, requested and expected indices	17
Common::TOptional < T >	
Represents object that may not exist	20
Common::TPair < T1, T2 >	
Represents a pair of objects	23
Common::TVector< T >	
Container representing array that can change its size	25

6 Class Index

File Index

4.1 File List

Here is a list of all files with brief descriptions:

CommonTypes/Exception.h
CommonTypes/Optional.h
CommonTypes/Pair.h
CommonTypes/Vector.h
CommonTypes/Private/BlockIterator.tpp
CommonTypes/Private/Vector.tpp
CommonUtils/AdvancedIteration.h
CommonUtils/Assert.h
CommonUtils/RawString.h
CommonUtils/Private/AdvancedIteration.tpp
CommonUtils/Private/RawString.cpp

8 File Index

Namespace Documentation

5.1 Common Namespace Reference

Classes

· class CDoesNotExist

Represents "Element does not exist" error. Stores message.

class CException

Basic exception class. C-style message is required.

class COutOfRange

Represents "Out of Range" error. Can hold message, requested and expected indices.

class TOptional

Represents object that may not exist.

· class TPair

Represents a pair of objects.

class TVector

Container representing array that can change its size.

Functions

• template<typename T1 , typename T2 >

TPair < T1, T2 > MakePair (const T1 &First, const T2 &Second) noexcept

 $\bullet \ \ \text{template}{<} \text{typename IteratorType} >$

 $size_t \ \underline{GetIteratorDistance} \ (IteratorType \ Begin, \ IteratorType \ End)$

Counts elements between two iterators. Range: [Begin: End)

size_t GetRawStringLength (const char *NullTermString)

Calculates length of the C-string.

size_t GetRawStringLength (const char *NullTermString, size_t MaxLength)

Calculates length of the C-string. Stops when null character is reached or MaxLength elements have been counted. Useful with malformatted input.

void CopyRawString (const char *NullTermStringFrom, char *const RawStringTo)

Does the copy of C-style string (ended with '\0').

void CopyRawString (const char *NullTermStringFrom, char *RawStringTo, size_t MaxLength)

Does the copy of C-style string. Stops when null character is reached or MaxLength elements have been copied. Useful when string should be cut.

• bool AreRawStringsEqual (const char *NullTermString1, const char *NullTermString2)

Checks whether two C-style strings are equal.

bool AreRawStringsEqual (const char *NullTermString1, const char *NullTermString2, size_t MaxCompare ← Length)

Checks whether two C-style strings are equal. Use this to compare N first elements, even if strings are not null-terminated.

5.1.1 Function Documentation

5.1.1.1 AreRawStringsEqual() [1/2]

Checks whether two C-style strings are equal.

Parameters

NullTermString1	First null-terminated string
NullTermString2	Second null-terminated string

Returns

true if characters before '\0' are the same false otherwise

5.1.1.2 AreRawStringsEqual() [2/2]

Checks whether two C-style strings are equal. Use this to compare N first elements, even if strings are not null-terminated.

Parameters

NullTermString1	First string (whether null- terminated or limited with MaxCompareLength)	
NullTermString2	Second string (whether null- terminated or limited with MaxCompareLength)	
MaxComparedLength	Max amount of characters to compare; does not include trailing '\0'	

Returns

true if characters before '\0' are the same false otherwise

5.1.1.3 CopyRawString() [1/2]

Does the copy of C-style string (ended with '\0').

Parameters

NullTermStringFrom	Source: char array that ends with '\0'	
NullTermStringTo	Destination: Char array that is large enough to receive copied elements. May not end with '\0'	

5.1.1.4 CopyRawString() [2/2]

Does the copy of C-style string. Stops when null character is reached or MaxLength elements have been copied. Useful when string should be cut.

Parameters

NullTermStringFrom	Source: char array that ends with '\0' (or not, if you rely on MaxLength and buffer size)
NullTermStringTo	Destination: Char array that is large enough to receive copied elements. May not end with '\0'. After copying it gets '\0' anyway
MaxLength	Max amount of characters to copy; does not include trailing '\0'

5.1.1.5 GetIteratorDistance()

Counts elements between two iterators. Range: [Begin: End)

Template Parameters

<i>IteratorType</i>	Iterator with implemented ++, != and *

Parameters

Begin	Iterator referring to the first element
End	Iterator referring to the element after last one

Returns

Distance between iterators

Note

Begin must not be greater than end (negative results are not supported)

5.1.1.6 GetRawStringLength() [1/2]

Calculates length of the C-string.

Parameters

NullTermString	Char array that ends with '\0'
----------------	--------------------------------

Returns

Number of actual letters in string ('\0' is not counted)

5.1.1.7 GetRawStringLength() [2/2]

Calculates length of the C-string. Stops when null character is reached or MaxLength elements have been counted. Useful with malformatted input.

Parameters

NullTermString	Char array that ends with '\0' (or not, if you rely on MaxLength and buffer size)
MaxLength	Max amount of characters to count; does not include the trailing '\0'

Returns

Number of actual letters in string ('\0' is not counted)

5.1.1.8 MakePair()


Class Documentation

6.1 Common::CDoesNotExist Class Reference

Represents "Element does not exist" error. Stores message.

```
#include "CommonTypes/Exception.h"
```

Inheritance diagram for Common::CDoesNotExist:



Public Member Functions

CDoesNotExist (const char *Message) noexcept
 Pass only message, if other properties cannot be specified.

Additional Inherited Members

6.1.1 Detailed Description

Represents "Element does not exist" error. Stores message.

6.1.2 Constructor & Destructor Documentation

6.1.2.1 CDoesNotExist()

Pass only message, if other properties cannot be specified.

Parameters

ssage Description. Will be copied to the inner buff	er
-----------------------------------------------------	----

Note


If length of message > 40, first 40 symbols will be saved.

6.2 Common::CException Class Reference

Basic exception class. C-style message is required.

```
#include "CommonTypes/Exception.h"
```

Inheritance diagram for Common::CException:



Public Member Functions

- CException (const char *Message) noexcept
 - All exceptions must provide the message.
- virtual ∼CException ()
- virtual const char * GetMessage () const noexcept *Error message.*

Protected Attributes

• char Message [41]

6.2.1 Detailed Description

Basic exception class. C-style message is required.

6.2.2 Constructor & Destructor Documentation

6.2.2.1 CException()

All exceptions must provide the message.

Parameters

Message Error description. Will be copied to an inner buffer

Note

If length of message > 40, first 40 symbols will be saved.

6.2.2.2 \sim CException()

```
virtual Common::CException::~CException ( ) [inline], [virtual]
```

6.2.3 Member Function Documentation

6.2.3.1 GetMessage()

```
virtual const char* Common::CException::GetMessage ( ) const [inline], [virtual], [noexcept]
```

Error message.

Returns

C-style string with error description

6.2.4 Member Data Documentation

6.2.4.1 Message


```
char Common::CException::Message[41] [protected]
```

6.3 Common::COutOfRange Class Reference

Represents "Out of Range" error. Can hold message, requested and expected indices.

#include "CommonTypes/Exception.h"

Inheritance diagram for Common::COutOfRange:



Public Member Functions

COutOfRange (const char *Message) noexcept

Pass only message, if other properties cannot be specified.

COutOfRange (const char *Message, int RequestedIndex, const TPair< size_t, size_t > &ExpectedIndex)
noexcept

Describes valid range and errored value. Contains message.

- const TPair < size_t > & GetExpectedRange () const noexcept
 Specifies valid range.
- int GetRequestedIndex () const noexcept

Index that caused this exception.

Protected Attributes

```
• const int RequestedIndex = 0
```

```
    const TPair < size_t, size_t > ExpectedIndex = { 0,0 }
```

6.3.1 Detailed Description

Represents "Out of Range" error. Can hold message, requested and expected indices.

6.3.2 Constructor & Destructor Documentation

6.3.2.1 COutOfRange() [1/2]

Pass only message, if other properties cannot be specified.

Parameters

Message	Description. Will be copied to an inner buffer
---------	------------------------------------------------

Note

```
Range will be set to empty [0: 0), requested index to 0. If length of message > 40, first 40 symbols will be saved.
```

6.3.2.2 COutOfRange() [2/2]

```
int RequestedIndex,
const TPair< size_t, size_t > & ExpectedIndex ) [inline], [noexcept]
```

Describes valid range and errored value. Contains message.

Parameters

Message	Description. Will be copied to an inner buffer	
RequestedIndex	Errored index (out of range).	
ExpectedIndex	Pair of Min and Max+1 indexes, that were available. Range: [First: Second)	

Note

If length of message > 40, first 40 symbols will be saved.

6.3.3 Member Function Documentation

6.3.3.1 GetExpectedRange()

```
const TPair<size_t, size_t>& Common::COutOfRange::GetExpectedRange ( ) const [inline], [noexcept]
```

Specifies valid range.

Returns

Pair of Min and Max+1 indexes, that were available. Range: [First: Second)

Note

Returns 0 Index with [0: 0) range if constructed only with message.

6.3.3.2 GetRequestedIndex()

```
int Common::COutOfRange::GetRequestedIndex ( ) const [inline], [noexcept]
```

Index that caused this exception.

Returns

Value of index, that is not in expected range

Note

Returns 0 Index with [0: 0) range if constructed only with message.

6.3.4 Member Data Documentation

6.3.4.1 ExpectedIndex

```
const TPair<size_t, size_t> Common::COutOfRange::ExpectedIndex = { 0,0 } [protected]
```

6.3.4.2 RequestedIndex

```
const int Common::COutOfRange::RequestedIndex = 0 [protected]
```

6.4 Common::TOptional < T > Class Template Reference

Represents object that may not exist.

```
#include "CommonTypes/Optional.h"
```

Public Member Functions

• TOptional ()=default

No object by default.

TOptional (const T &Value) noexcept

Initialize optional with existing value (copy).

• void SetValue (const T &Value) noexcept

Set value to optional (copy).

TOptional < T > & operator= (const T & Value) noexcept

Set value to the optional (copy).

• bool ValueExists () const noexcept

Check if optional has value.

• const T & GetValue () const

Gets value if it exists or throws an exception.

const T & GetValueOr (const T &OtherVariant) const noexcept

Get value or passed value (if not possible)

6.4.1 Detailed Description

```
\label{template} \mbox{template} < \mbox{typename T} > \\ \mbox{class Common::TOptional} < \mbox{T} > \\
```

Represents object that may not exist.

6.4.2 Constructor & Destructor Documentation

6.4.2.1 TOptional() [1/2]

No object by default.

6.4.2.2 TOptional() [2/2]

Initialize optional with existing value (copy).

Parameters

Value Object to create copy from

6.4.3 Member Function Documentation

6.4.3.1 GetValue()

```
template<typename T >
const T& Common::TOptional< T >::GetValue ( ) const [inline]
```

Gets value if it exists or throws an exception.

Returns

Optional's value

6.4.3.2 GetValueOr()

Get value or passed value (if not possible)

Parameters

OtherVariant	Returned if optional is empty
--------------	-------------------------------

Returns

Optional value or provided value

6.4.3.3 operator=()

Set value to the optional (copy).

Parameters

Value	Object to create copy from
-------	----------------------------

Returns

Reference to this optional

6.4.3.4 SetValue()

Set value to optional (copy).

Parameters

```
Value Object to create copy from
```

6.4.3.5 ValueExists()

```
template<typename T >
bool Common::TOptional< T >::ValueExists ( ) const [inline], [noexcept]
```

Check if optional has value.

Returns

True if value exists

6.5 Common::TPair < T1, T2 > Class Template Reference

Represents a pair of objects.

```
#include "CommonTypes/Pair.h"
```

Public Member Functions

• TPair ()=default

Initialize pair with type default values.

• TPair (const T1 &First, const T2 &Second) noexcept

Creates a pair copying passed values.

· void MakePair (T1 First, T2 Second) noexcept

Assigns two values to pair at once (copy).

Public Attributes

```
• T1 First = T1{}
```

First value in pair.

• T2 Second = T2{}

Second value in pair.

6.5.1 Detailed Description

```
template < typename T1, typename T2> class Common::TPair < T1, T2 >
```

Represents a pair of objects.

6.5.2 Constructor & Destructor Documentation

6.5.2.1 **TPair()** [1/2]

```
template<typename T1 , typename T2 >
Common::TPair< T1, T2 >::TPair ( ) [default]
```

Initialize pair with type default values.

6.5.2.2 TPair() [2/2]

Creates a pair copying passed values.

Parameters

First	First value in pair
Second	Second value in pair

6.5.3 Member Function Documentation

6.5.3.1 MakePair()

Assigns two values to pair at once (copy).

Parameters

First	First value in pair
Second	Second value in pair

6.5.4 Member Data Documentation

6.5.4.1 First

```
template<typename T1 , typename T2 >
T1 Common::TPair< T1, T2 >::First = T1{}
```

First value in pair.

6.5.4.2 Second

```
template<typename T1 , typename T2 >
T2 Common::TPair< T1, T2 >::Second = T2{}
```

Second value in pair.

6.6 Common::TVector < T > Class Template Reference

Container representing array that can change its size.

```
#include "CommonTypes/Vector.h"
```

Public Types

 enum EReservedCapacityRule : uint8_t { EReservedCapacityRule::Exponential, EReservedCapacityRule::Linear, EReservedCapacityRule::NeverReserve }

Used to define how methods deal with Capacity.

typedef Tlterator< T *, T & > Clterator

```
Iterator. Implemented op-s: ++, +=, +, -, -=, -, ==, !=, =.
```

typedef Tlterator< const T *, const T & > CConstIterator

Version of CIterator for const values.

typedef TReverselterator< T *, T & > CReverselterator

Reverse iterator. Increment is actually decrement, etc.

typedef TReverselterator< const T *, const T & > CConstReverselterator

Version of TReverselterator for const values.

typedef TSafeIterator< T *, T & > CSafeIterator

Iterator that does bounds checking and throws OutOfRange().

typedef TSafeIterator< const T *, const T & > CSafeConstIterator

Version of TSafeIterator for const values.

typedef TSafeReverselterator< T *, T & > CSafeReverselterator

Reverse iterator that can throw OutOfRange().

typedef TSafeReverseIterator< const T *, const T & > CSafeConstReverseIterator

Version of TSafeReverseIterator for const values.

Public Member Functions

• TVector ()=default

Empty vector with no heap allocation.

TVector (EReservedCapacityRule CapacityRule) noexcept

Creates empty vector with Capacity preset predefined.

• TVector (size t Size, const T &DefaultValue={})

Vector with pre-allocated elements.

TVector (size_t Size, const T *const Array)

Vector constructed from raw dynamic array (copy).

• TVector (const std::initializer_list< T > &ValuesList)

Modern C++ initialization syntax: name = {...}.

template<typename IteratorType >

TVector (IteratorType Begin, IteratorType End, typename std::enable_if<!std::is_integral< IteratorType >← ::value >::type *=0)

Constructor to get values from another container.

TVector (const TVector < T > &Other)

Initialize by copying another TVector.

TVector (TVector < T > &&Other) noexcept

Move constructor.

∼TVector ()

• template<typename IteratorType >

void Assign (IteratorType Begin, IteratorType End, bool bAllowAutoShrink=false)

Allows to copy values from another container.

TVector< T > & operator= (const std::initializer list< T > &ValuesList)

Allows assignment with = {...} style.

TVector< T > & operator= (const TVector< T > &Other)

Assingment operator makes a copy of another vector.

TVector< T > & operator= (TVector< T > &&Other) noexcept

Move assignment.

T & operator[] (size_t Index)

Index operator that prodives access to the element.

const T & operator[] (size t Index) const

Index operator for const vectors.

T & SafeAt (size_t Index)

[] with range check.

- const T & SafeAt (size_t Index) const
- T & AutoAt (size_t Index, const T &DefaultValue={})

If element does not exist, this will resize vector and fill newly created elements with provided value.

T * RawData () noexcept

Provides access to the internal buffer.

const T * RawData () const noexcept

RawData() for const vectors.

bool operator== (const TVector < T > &Other) const noexcept

Checks if two vectors contain the same values by calling equality operator recursively.

bool operator!= (const TVector< T > &Other) const noexcept

Opposite to operator ==.

void Push (const T &Value)

Adds one element to the end of vector.

template<typename IteratorType >

void Push (IteratorType Begin, IteratorType End)

Adds elements to the end, uses iterators.

void Insert (size_t Position, const T &Value=T{}, const T &FillOnResizeWith=T{})

Inserts one elements to the specified position.

template<typename IteratorType >

void Insert (size_t Position, IteratorType Begin, IteratorType End, const T &FillOnResizeWith=T{}, typename std::enable if<!std::is integral< IteratorType >::value >::type *=0)

Inserts range of elements, starting at Position.

• T Pop (bool bAllowAutoShrink=false)

Removes one element from the end of vector.

T SafePop (bool bAllowAutoShrink=false)

Pop() with range check.

void PopMultiple (size_t ElementsCount, bool bAllowAutoShrink=false)

Removes N elements from the end of vector.

T Shift (bool bAllowAutoShrink=false)

Removes one element from the beginning of vector.

T SafeShift (bool bAllowAutoShrink=false)

Shift() with range check.

void ShiftMultiple (size_t ElementsCount, bool bAllowAutoShrink=false)

Removes N elements from the beginning of vector.

• void Erase (size t Position, bool bAllowAutoShrink=false)

Removes element with specified position.

void EraseMultiple (size_t PositionFrom, size_t PositionTo, bool bAllowAutoShrink=false)

Removes range of elements from vector.

void Reserve (size t NewCapacity)

Allocates elements internally for the future use.

void Resize (size_t NewSize, const T &DefaultValue={}, bool bAllowAutoShrink=false)

Changes size of vector.

void ShrinkToFit ()

Clears memory that was reserved for future use.

void Clear (bool bDoFreeMemory=false)

Removes all elements from the vector.

• size_t GetSize () const noexcept

Size is number of elements that you can use.

size_t GetCapacity () const noexcept

Capacity is Size + reserved space for the future use.

· bool IsEmpty () const noexcept

Simple check if size of this vector equals 0.

void SetCapacityRule (EReservedCapacityRule CapacityRule) noexcept

Set enum value that will describe how re-allocation works when elements are added / removed from vertor. Reallocation on removal happens only if bool bAllowAutoShrink was passed with supported operation.

• EReservedCapacityRule GetCapacityRule () const noexcept

Returns Capacity rule that is currently applied. It affects how elements are allocated & destructed.

• T & Front ()

Provides access to the first element.

const T & Front () const

Front() for const vectors.

T & SafeFront ()

Front() with range check.

· const T & SafeFront () const

SafeFront() for const vectors.

• T & Back ()

Provides access to the last element.

• const T & Back () const

Back() for const vectors.

• T & SafeBack ()

Back() with range check.

const T & SafeBack () const

SafeBack() for const vectors.

· Clterator Begin ()

Iterator pointing to the first elem.

• CConstIterator ConstBegin () const

Iterator pointing to the first elem (const).

CReverselterator ReverseBegin ()

Reverse iterator pointing to the first elem.

• CConstReverseIterator ConstReverseBegin () const

Reverse iterator pointing to the first elem (const).

• CSafeIterator SafeBegin ()

Safe iterator pointing to the first elem.

CSafeConstIterator SafeConstBegin () const

Safe iterator pointing to the first elem (const).

• CSafeReverseIterator SafeReverseBegin ()

Safe reverse iterator pointing to the first elem.

CSafeConstReverseIterator SafeConstReverseBegin () const

Safe reverse iterator pointing to the first elem (const).

· Clterator End ()

Iterator pointing to the elem after last.

• CConstIterator ConstEnd () const

Iterator pointing to the elem after last (const).

CReverseIterator ReverseEnd ()

Reverse iterator pointing to the elem after last.

• CConstReverseIterator ConstReverseEnd () const

Reverse iterator pointing to the elem after last (const).

CSafeIterator SafeEnd ()

Safe iterator pointing to the elem after last.

CSafeConstIterator SafeConstEnd () const

Safe iterator pointing to the elem after last (const).

· CSafeReverseIterator SafeReverseEnd ()

Safe reverse iterator pointing to the elem after last.

• CSafeConstReverseIterator SafeConstReverseEnd () const

Safe reverse it. pointing to elem after last (const).

· Clterator begin ()

Begin() alias (for compatibity)

· CConstIterator begin () const

ConstBegin() alias (overloaded, for compatibity)

· CConstIterator cbegin () const

ConstBegin() alias (for compatibity)

• CReverselterator rbegin ()

ReverseBegin() alias (for compatibity)

· CConstReverselterator rbegin () const

ConstReverseBegin() alias (overloaded, for compatibity)

· CConstReverselterator crbegin () const

ConstReverseBegin() alias (for compatibity)

· Clterator end ()

End() alias (for compatibity)

· CConstIterator end () const

ConstEnd() alias (overloaded, for compatibity)

· CConstIterator cend () const

ConstEnd() alias (for compatibity)

• CReverselterator rend ()

ReverseEnd() alias (for compatibity)

CConstReverselterator rend () const

ConstReverseEnd() alias (overloaded, for compatibity)

· CConstReverselterator crend () const

ConstReverseEnd() alias (for compatibity)

Static Public Member Functions

• static void Swap (TVector< T > &Vector1, TVector< T > &Vector2) noexcept

Swaps two vectors internally without deep copy.

6.6.1 Detailed Description

```
template<typename T> class Common::TVector< T>
```

Container representing array that can change its size.

Fast in accessing elements as offsets are used, but not very effective in terms of adding and removing elements. To minimize those drawbacks, there are memory reserving rules that you can manage.

Note

If the logical result of operation may not be determined, there are two methods: one that throws an exception ("Safe" prefix) and another one that does assertion in debug mode. Custom exception is COutOfRange, derived from CException

May throw std::bad_alloc if allocation fails. Allocation failure in assignment operations will cause the vector to be cleared (as you intended to remove old elements anyway). If allocation fails in insertions, resize, push/pop, etc. - vector will stay in the previous state.

Attention

Containing type must provide a default (or empty) constructor. This will be fixed in the future.

6.6.2 Member Typedef Documentation

6.6.2.1 CConstiterator

```
template<typename T >
typedef TIterator<const T*, const T&> Common::TVector< T >::CConstIterator
```

Version of Clterator for const values.

6.6.2.2 CConstReverselterator

```
template<typename T >
typedef TReverseIterator<const T*, const T&> Common::TVector< T >::CConstReverseIterator
```

Version of TReverselterator for const values.

6.6.2.3 Clterator

```
template<typename T >
typedef TIterator<T*, T&> Common::TVector< T >::CIterator

Iterator. Implemented op-s: ++, +=, +, -, -=, -, ==, !=, =.
```

6.6.2.4 CReverselterator

```
template<typename T >
typedef TReverseIterator<T*, T&> Common::TVector< T >::CReverseIterator
```

Reverse iterator. Increment is actually decrement, etc.

6.6.2.5 CSafeConstIterator

```
template<typename T >
typedef TSafeIterator<const T*, const T&> Common::TVector< T >::CSafeConstIterator
```

Version of TSafelterator for const values.

6.6.2.6 CSafeConstReverselterator

```
template<typename T >
typedef TSafeReverseIterator<const T*, const T&> Common::TVector< T >::CSafeConstReverseIterator
```

Version of TSafeReverselterator for const values.

6.6.2.7 CSafelterator

```
template<typename T >
typedef TSafeIterator<T*, T&> Common::TVector< T >::CSafeIterator
```

Iterator that does bounds checking and throws OutOfRange().

6.6.2.8 CSafeReverselterator

```
template<typename T >
typedef TSafeReverseIterator<T*, T&> Common::TVector< T >::CSafeReverseIterator
```

Reverse iterator that can throw OutOfRange().

6.6.3 Member Enumeration Documentation

6.6.3.1 EReservedCapacityRule

```
template<typename T >
enum Common::TVector::EReservedCapacityRule : uint8_t [strong]
```

Used to define how methods deal with Capacity.

Enumerator

Exponential	[ADD] allocates (NewSize-1)*2 if capacity exceed and vector is not small enough [DEL] allocates 2*Size if Capacity > 4 * Size and vector is not small enough
Linear	[ADD] allocates NewSize + 3 + 32 / sizeof(T) if capacity exceed
	[DEL] allocates Size + 4 + 32 / sizeof(T) if size exceeds capacity by more than 2*(8 + 64 /
	sizeof(T))
NeverReserve	[ADD, DEL] memory is never reserved automatically; if true bAllowAutoShrink was passed
	into another method, then ShrinkToFit() will be called

6.6.4 Constructor & Destructor Documentation

6.6.4.1 TVector() [1/8]

```
template<typename T >
Common::TVector< T >::TVector ( ) [default]
```

Empty vector with no heap allocation.

6.6.4.2 TVector() [2/8]

Creates empty vector with Capacity preset predefined.

Parameters

CapacityRule	Describes how memory will be reserved

See also

EReservedCapacityRule for more info about presets.

6.6.4.3 TVector() [3/8]

Vector with pre-allocated elements.

Parameters

Size	Number of elements to allocate
DefaultValue	Optional. Value to initialize with

See also

Use Reserve() on empty vector to avoid initialization.

6.6.4.4 TVector() [4/8]

Vector constructed from raw dynamic array (copy).

Parameters

Size	Number of elements in original array
Array	Pointer to heap with C-style array

Note

Array[0] to Array[Size-1] must exist and have the same type as vector. Raw array is not changed.

6.6.4.5 TVector() [5/8]

Modern C++ initialization syntax: name = $\{...\}$.

Valuest ist	Initializer list

6.6.4.6 TVector() [6/8]

Constructor to get values from another container.

Template Parameters

IteratorType	Iterator that implements ++, != and *
--------------	---------------------------------------

Parameters

Begin	Iterator referring to the beginning of container
End	Iterator referring to the end of container

6.6.4.7 TVector() [7/8]

Initialize by copying another TVector.

Parameters

```
Other vector to copy
```

6.6.4.8 TVector() [8/8]

Move constructor.

Other	Temporary object to get data from

6.6.4.9 ∼TVector()

6.6.5 Member Function Documentation

6.6.5.1 Assign()

Allows to copy values from another container.

Template Parameters

IteratorType	Iterator that implements ++, $!=$ and $*$
--------------	-------------------------------------------

Parameters

Begin	Iterator referring to the beginning of container
End	Iterator referring to the end of container

6.6.5.2 AutoAt()

If element does not exist, this will resize vector and fill newly created elements with provided value.

Index	aka offset value
DefaultValue	Value to initialize added elements

Returns

Reference to the requested element

See also

Use operator [] if you are sure, that element exists

6.6.5.3 Back() [1/2]

```
template<typename T >
T& Common::TVector< T >::Back ( )
```

Provides access to the last element.

Returns

Reference to the last element

Note

Vector must not be empty.

6.6.5.4 Back() [2/2]

```
template<typename T >
const T& Common::TVector< T >::Back ( ) const [inline]
```

Back() for const vectors.

6.6.5.5 Begin()

```
template<typename T > CIterator Common::TVector< T >::Begin ( )
```

Iterator pointing to the first elem.

Returns

Clterator iterator

6.6.5.6 begin() [1/2]

```
template<typename T >
CIterator Common::TVector< T >::begin ( ) [inline]
```

Begin() alias (for compatibity)

6.6.5.7 begin() [2/2]

```
template<typename T >
CConstIterator Common::TVector< T >::begin ( ) const [inline]
```

ConstBegin() alias (overloaded, for compatibity)

6.6.5.8 cbegin()

```
template<typename T > CConstIterator Common::TVector< T >::cbegin ( ) const [inline]
```

ConstBegin() alias (for compatibity)

6.6.5.9 cend()

```
template<typename T >
CConstIterator Common::TVector< T >::cend ( ) const [inline]
```

ConstEnd() alias (for compatibity)

6.6.5.10 Clear()

```
template<typename T >
void Common::TVector< T >::Clear (
          bool bDoFreeMemory = false )
```

Removes all elements from the vector.

Parameters

bDoForceDelete If set to true, will also update capacity. otherwise, actual delete operation will not be called

Attention

Set bool to true if you really want to free memory.

6.6.5.11 ConstBegin()

```
\label{template} \mbox{template<typename T >} \\ \mbox{CConstIterator Common::TVector< T >::ConstBegin ( ) const} \\
```

Iterator pointing to the first elem (const).

Returns

CConstIterator iterator

6.6.5.12 ConstEnd()

```
\label{template} $$ template < typename T > $$ $$ $$ CConstIterator Common:: TVector < T > :: ConstEnd ( ) const
```

Iterator pointing to the elem after last (const).

Returns

CConstIterator iterator

6.6.5.13 ConstReverseBegin()

Reverse iterator pointing to the first elem (const).

Returns

CConstReverseIterator iterator

6.6.5.14 ConstReverseEnd()

```
template<typename T >
CConstReverseIterator Common::TVector< T >::ConstReverseEnd ( ) const
```

Reverse iterator pointing to the elem after last (const).

Returns

CConstReverselterator iterator

6.6.5.15 crbegin()

```
template<typename T >
CConstReverseIterator Common::TVector< T >::crbegin ( ) const [inline]
```

ConstReverseBegin() alias (for compatibity)

6.6.5.16 crend()

```
template<typename T >
CConstReverseIterator Common::TVector< T >::crend ( ) const [inline]
```

ConstReverseEnd() alias (for compatibity)

6.6.5.17 End()

```
template<typename T >
CIterator Common::TVector< T >::End ( )
```

Iterator pointing to the elem after last.

Returns

CIterator iterator

6.6.5.18 end() [1/2]

```
template<typename T >
CIterator Common::TVector< T >::end ( ) [inline]
```

End() alias (for compatibity)

6.6.5.19 end() [2/2]

```
template<typename T >
CConstIterator Common::TVector< T >::end ( ) const [inline]
```

ConstEnd() alias (overloaded, for compatibity)

6.6.5.20 Erase()

Removes element with specified position.

Parameters

Position	Position of element to be removed
bAllowAutoShrink	Enables auto shrink according to the capacity rule. See: EReservedCapacityRule

Note

If Position is greater than max index, does nothing.

Attention

This method removes one element. To remove multiple, use EraseMultiple(). Your code with such a mistake will be compiled because of optional bool param.

6.6.5.21 EraseMultiple()

Removes range of elements from vector.

PositionFrom	Starting index for erase
PositionTo	End point for erase. Element with this index will also be removed
bAllowAutoShrink	Optional. Enables auto shrink according to the capacity rule. See: EReservedCapacityRule

Note

Ignores elements at unavailable positions.

Attention

This method removes multiple elements. To remove one, use Erase(). Your code with such a mistake will be compiled because of optional bool param.

6.6.5.22 Front() [1/2]

```
template<typename T >
T& Common::TVector< T >::Front ( )
```

Provides access to the first element.

Returns

Reference to the first element

Note

Vector must not be empty.

6.6.5.23 Front() [2/2]

```
template<typename T >
const T& Common::TVector< T >::Front ( ) const [inline]
```

Front() for const vectors.

6.6.5.24 GetCapacity()

```
template<typename T >
size_t Common::TVector< T >::GetCapacity ( ) const [noexcept]
```

Capacity is Size + reserved space for the future use.

Returns

Capacity of vector

6.6.5.25 GetCapacityRule()

```
template<typename T >
EReservedCapacityRule Common::TVector< T >::GetCapacityRule ( ) const [noexcept]
```

Returns Capacity rule that is currently applied. It affects how elements are allocated & destructed.

Returns

EReservedCapacityRule Current capacity rule

See also

EReservedCapacityRule for more info about presets.

6.6.5.26 GetSize()

```
template<typename T >
size_t Common::TVector< T >::GetSize ( ) const [noexcept]
```

Size is number of elements that you can use.

Returns

Size of vector

6.6.5.27 Insert() [1/2]

Inserts one elements to the specified position.

Position	Index where to insert
Value	Value to insert
FillOnResizeWith	If position is larger than vector size, elements that appear on resize will be initialized with
	this value

Note

If Position is greater than max index, vector is resized.

6.6.5.28 Insert() [2/2]

Inserts range of elements, starting at Position.

Template Parameters

IteratorType	Iterator with implemented ++, != and *
--------------	----------------------------------------

Parameters

Position	Index of the first inserted element
Begin	Iterator referring to the first element
End	Iterator referring to the element after last one
FillOnResizeWith	If position is larger than vector size, elements that appear on resize will be initialized with
	this value

Note

If Position is greater than max index, vector is resized.

6.6.5.29 IsEmpty()

```
template<typename T >
bool Common::TVector< T >::IsEmpty ( ) const [noexcept]
```

Simple check if size of this vector equals 0.

Returns

True if empty, false if not

6.6.5.30 operator"!=()

Opposite to operator ==.

6.6.5.31 operator=() [1/3]

Allows assignment with = {...} style.

Parameters

```
ValuesList Initializer list
```

Returns

Reference to this vector

6.6.5.32 operator=() [2/3]

```
template<typename T >  \begin{tabular}{ll} TVector < T > & Common:: TVector < T > :: operator = ( \\ const TVector < T > & Other ) \end{tabular}
```

Assingment operator makes a copy of another vector.

Parameters

```
Other vector
```

Returns

Reference to this vector

6.6.5.33 operator=() [3/3]

Move assignment.

Parameters

Returns

Reference to this vector

6.6.5.34 operator==()

Checks if two vectors contain the same values by calling equality operator recursively.

Parameters

Other Other vector to co	mpare
--------------------------	-------

Returns

True if sizes and values are equal, false otherwise

Note

Containing elements must implement == operator

6.6.5.35 operator[]() [1/2]

Index operator that prodives access to the element.

Index aka offset value

Returns

Reference to the requested element

Note

Element with requested index must exist in vector.

6.6.5.36 operator[]() [2/2]

Index operator for const vectors.

6.6.5.37 Pop()

Removes one element from the end of vector.

Parameters

bAllowAutoShrink Optional. Enables auto shrink according to the capacity rule. See: EReservedCapacityRule

Returns

Removed element (by value)

Note

Vector must not be empty.

6.6.5.38 PopMultiple()

Removes N elements from the end of vector.

Parameters

ElementsCount	Number of elements to be removed
bAllowAutoShrink	Optional. Enables auto shrink according to the capacity rule. See: EReservedCapacityRule

Note

If ElementsCount >= Size, clears vector

6.6.5.39 Push() [1/2]

Adds one element to the end of vector.

Parameters

ſ	Value	Element to add
---	-------	----------------

See also

Call ShrinkToFit() to clear reserved memory, Reserve() to increase it

6.6.5.40 Push() [2/2]

Adds elements to the end, uses iterators.

Template Parameters

<pre>IteratorType Iterator with implemented ++, != and *</pre>	
--------------------------------------------------------------------	--

Begin	Iterator referring to the first element
End	Iterator referring to the element after last one

6.6.5.41 RawData() [1/2]

```
template<typename T >
const T* Common::TVector< T >::RawData ( ) const [inline], [noexcept]
```

RawData() for const vectors.

6.6.5.42 RawData() [2/2]

```
template<typename T >
T* Common::TVector< T >::RawData ( ) [noexcept]
```

Provides access to the internal buffer.

Returns

Pointer to c-style heap array

6.6.5.43 rbegin() [1/2]

```
template<typename T >
CReverseIterator Common::TVector< T >::rbegin ( ) [inline]
```

ReverseBegin() alias (for compatibity)

6.6.5.44 rbegin() [2/2]

```
template<typename T >
CConstReverseIterator Common::TVector< T >::rbegin ( ) const [inline]
```

ConstReverseBegin() alias (overloaded, for compatibity)

6.6.5.45 rend() [1/2]

```
template<typename T >
CReverseIterator Common::TVector< T >::rend ( ) [inline]
```

ReverseEnd() alias (for compatibity)

6.6.5.46 rend() [2/2]

```
template<typename T >
CConstReverseIterator Common::TVector< T >::rend ( ) const [inline]
```

ConstReverseEnd() alias (overloaded, for compatibity)

6.6.5.47 Reserve()

Allocates elements internally for the future use.

Parameters

	NewCapacity	If greater than size, will update internal capacity
--	-------------	-----------------------------------------------------

See also

Call ShrinkToFit() to clear reserved memory.

Note

Passing bAllowAutoShrink to methods may cause shrink.

6.6.5.48 Resize()

Changes size of vector.

NewSize	New size of vector. If NewSize < Size, deletes last elements. Otherwise, creates new with passed value.	
DefaultValue	Optional. Value to initialize added elements	
bAllowAutoShrink	Optional. Enables auto shrink according to the capacity rule. See: EReservedCapacityRule	

6.6.5.49 ReverseBegin()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensuremath{\sf template}$ $$ \ensuremath{\sf T} > $$ \ensuremath{\sf CReverseIterator}$ $$ \ensuremath{\sf Common::TVector}$ $$ T > :: ReverseBegin ( ) $$
```

Reverse iterator pointing to the first elem.

Returns

CReverselterator iterator

6.6.5.50 ReverseEnd()

```
\label{template} \mbox{template$<$typename $T$} > $$ CReverseIterator Common::TVector< $T$ >::ReverseEnd ( )
```

Reverse iterator pointing to the elem after last.

Returns

CReverselterator iterator

6.6.5.51 SafeAt() [1/2]

[] with range check.

6.6.5.52 SafeAt() [2/2]

6.6.5.53 SafeBack() [1/2]

```
template<typename T >
T& Common::TVector< T >::SafeBack ( )
```

Back() with range check.

6.6.5.54 SafeBack() [2/2]

```
template<typename T >
const T& Common::TVector< T >::SafeBack ( ) const [inline]
```

SafeBack() for const vectors.

6.6.5.55 SafeBegin()

```
template<typename T >
CSafeIterator Common::TVector< T >::SafeBegin ( )
```

Safe iterator pointing to the first elem.

Returns

CSafelterator iterator

6.6.5.56 SafeConstBegin()

Safe iterator pointing to the first elem (const).

Returns

CSafeConstIterator iterator

6.6.5.57 SafeConstEnd()

```
\label{template} $$ template < typename T > $$ $$ CSafeConstIterator Common::TVector < T >::SafeConstEnd ( ) const
```

Safe iterator pointing to the elem after last (const).

Returns

CSafeConstIterator iterator

6.6.5.58 SafeConstReverseBegin()

```
\label{template} $$ $$ \text{CSafeConstReverseIterator Common::TVector} < T > :: SafeConstReverseBegin ( ) const
```

Safe reverse iterator pointing to the first elem (const).

Returns

CSafeConstReverseIterator

6.6.5.59 SafeConstReverseEnd()

```
\label{template} \mbox{template$<$typename T>$} $$ CSafeConstReverseIterator Common::TVector< T>::SafeConstReverseEnd ( ) const
```

Safe reverse it. pointing to elem after last (const).

Returns

CSafeConstReverseIterator

6.6.5.60 SafeEnd()

```
template<typename T >
CSafeIterator Common::TVector< T >::SafeEnd ( )
```

Safe iterator pointing to the elem after last.

Returns

CSafelterator iterator

6.6.5.61 SafeFront() [1/2]

```
template<typename T >
T& Common::TVector< T >::SafeFront ( )
```

Front() with range check.

6.6.5.62 SafeFront() [2/2]

```
template<typename T >
const T& Common::TVector< T >::SafeFront ( ) const [inline]
```

SafeFront() for const vectors.

6.6.5.63 SafePop()

Pop() with range check.

6.6.5.64 SafeReverseBegin()

```
template<typename T >
CSafeReverseIterator Common::TVector< T >::SafeReverseBegin ( )
```

Safe reverse iterator pointing to the first elem.

Returns

CSafeReverseIterator iterator

6.6.5.65 SafeReverseEnd()

```
\label{template} $$ template < typename T > $$ CSafeReverseIterator Common:: TVector < T >:: SafeReverseEnd ( ) $$
```

Safe reverse iterator pointing to the elem after last.

Returns

CSafeReverseIterator iterator

6.6.5.66 SafeShift()

Shift() with range check.

6.6.5.67 SetCapacityRule()

Set enum value that will describe how re-allocation works when elements are added / removed from vertor. Reallocation on removal happens only if bool bAllowAutoShrink was passed with supported operation.

Parameters

C	apacityRule	Preset value from EReservedCapacityRule
---	-------------	-----------------------------------------

Note

If bAllowAutoShrink was passed with operation, size that you have manually reserved may also be deallocated

6.6.5.68 Shift()

Removes one element from the beginning of vector.

Parameters

bAllowAutoShrink Optional. Enables auto shrink according to the capacity rule. See: EReservedCapacityRule

Returns

Removed element (by value)

6.6.5.69 ShiftMultiple()

Removes N elements from the beginning of vector.

Parameters

ElementsCount	Number of elements to be removed	
bAllowAutoShrink	Enables auto shrink according to the capacity rule. See: EReservedCapacityRule	

Note

If ElementsCount >= Size, clears vector

6.6.5.70 ShrinkToFit()

```
template<typename T >
void Common::TVector< T >::ShrinkToFit ( )
```

Clears memory that was reserved for future use.

See also

Methods that can reserve memory: push(), reserve(), etc.

6.6.5.71 Swap()

Swaps two vectors internally without deep copy.

Vector1	First vector
Vector2	Second vector

Chapter 7

File Documentation

7.1 CommonTypes/Exception.h File Reference

```
#include "Pair.h"
#include "../CommonUtils/RawString.h"
```

Classes

· class Common::CException

Basic exception class. C-style message is required.

• class Common::COutOfRange

Represents "Out of Range" error. Can hold message, requested and expected indices.

class Common::CDoesNotExist

Represents "Element does not exist" error. Stores message.

Namespaces

• Common

7.2 CommonTypes/Optional.h File Reference

```
#include "Exception.h"
```

Classes

class Common::TOptional < T >

Represents object that may not exist.

56 File Documentation

Namespaces

Common

7.3 CommonTypes/Pair.h File Reference

Classes

```
    class Common::TPair < T1, T2 >
Represents a pair of objects.
```

Namespaces

Common

Functions

```
    template<typename T1, typename T2 >

TPair< T1, T2 > Common::MakePair (const T1 &First, const T2 &Second) noexcept
```

7.4 CommonTypes/Private/BlockIterator.tpp File Reference

7.5 CommonTypes/Private/Vector.tpp File Reference

7.6 CommonTypes/Vector.h File Reference

```
#include <initializer_list>
#include <type_traits>
#include <new>
#include "Exception.h"
#include "../CommonUtils/Assert.h"
#include "../CommonUtils/AdvancedIteration.h"
#include "Private/BlockIterator.tpp"
#include "Private/Vector.tpp"
```

Classes

class Common::TVector< T >

Container representing array that can change its size.

Namespaces

• Common

7.7 CommonUtils/AdvancedIteration.h File Reference

```
#include "Private/AdvancedIteration.tpp"
```

Namespaces

• Common

Functions

```
    template<typename IteratorType >
        size_t Common::GetIteratorDistance (IteratorType Begin, IteratorType End)
        Counts elements between two iterators. Range: [Begin: End)
```

7.8 CommonUtils/Assert.h File Reference

```
#include <iostream>
```

Macros

• #define ASSERT(Condition, Message)

7.8.1 Macro Definition Documentation

7.8.1.1 ASSERT

7.9 CommonUtils/Private/AdvancedIteration.tpp File Reference

7.10 CommonUtils/Private/RawString.cpp File Reference

```
#include "../RawString.h"
```

58 File Documentation

Namespaces

Common

Functions

size t Common::GetRawStringLength (const char *NullTermString)

Calculates length of the C-string.

size_t Common::GetRawStringLength (const char *NullTermString, size_t MaxLength)

Calculates length of the C-string. Stops when null character is reached or MaxLength elements have been counted. Useful with malformatted input.

void Common::CopyRawString (const char *NullTermStringFrom, char *const RawStringTo)

Does the copy of C-style string (ended with '\0').

void Common::CopyRawString (const char *NullTermStringFrom, char *RawStringTo, size t MaxLength)

Does the copy of C-style string. Stops when null character is reached or MaxLength elements have been copied. Useful when string should be cut.

bool Common::AreRawStringsEqual (const char *NullTermString1, const char *NullTermString2)

Checks whether two C-style strings are equal.

bool Common::AreRawStringsEqual (const char *NullTermString1, const char *NullTermString2, size_
 t MaxCompareLength)

Checks whether two C-style strings are equal. Use this to compare N first elements, even if strings are not null-terminated.

7.11 CommonUtils/RawString.h File Reference

Namespaces

Common

Functions

• size_t Common::GetRawStringLength (const char *NullTermString)

Calculates length of the C-string.

size_t Common::GetRawStringLength (const char *NullTermString, size_t MaxLength)

Calculates length of the C-string. Stops when null character is reached or MaxLength elements have been counted. Useful with malformatted input.

void Common::CopyRawString (const char *NullTermStringFrom, char *const RawStringTo)

Does the copy of C-style string (ended with '\0').

void Common::CopyRawString (const char *NullTermStringFrom, char *RawStringTo, size_t MaxLength)

Does the copy of C-style string. Stops when null character is reached or MaxLength elements have been copied. Useful when string should be cut.

bool Common::AreRawStringsEqual (const char *NullTermString1, const char *NullTermString2)

Checks whether two C-style strings are equal.

bool Common::AreRawStringsEqual (const char *NullTermString1, const char *NullTermString2, size_

 t MaxCompareLength)

Checks whether two C-style strings are equal. Use this to compare N first elements, even if strings are not null-terminated.

7.12 x64/Debug/CodeAnalysisResultManifest.txt File Reference

7.13 x64/Debug/CommonLibs.vcxproj.FileListAbsolute.txt File Reference

Index

\sim CException	GetMessage, 17
Common::CException, 17	Message, 17
\sim TVector	Common::COutOfRange, 17
Common::TVector< T >, 34	COutOfRange, 18
	ExpectedIndex, 20
AreRawStringsEqual	GetExpectedRange, 19
Common, 10	GetRequestedIndex, 19
ASSERT	RequestedIndex, 20
Assert.h, 57	Common::TOptional $<$ T $>$, 20
Assert.h	GetValue, 21
ASSERT, 57	GetValueOr, 21
Assign	operator=, 22
Common::TVector< T >, 34	SetValue, 22
AutoAt	TOptional, 21
Common::TVector< T >, 34	ValueExists, 22
	Common::TPair< T1, T2 >, 23
Back	First, 24
Common::TVector< T >, 35	MakePair, 24
Begin	Second, 24
Common::TVector< T >, 35	TPair, 23
begin	•
Common::TVector < T >, 35, 36	Common::TVector< T >, 25
	~TVector, 34
cbegin	Assign, 34
Common::TVector< T >, 36	AutoAt, 34
CConstIterator	Back, 35
Common::TVector< T >, 29	Begin, 35
CConstReverselterator	begin, 35, 36
Common::TVector< T >, 29	cbegin, 36
CDoesNotExist	CConstIterator, 29
Common::CDoesNotExist, 15	CConstReverselterator, 29
cend	cend, 36
Common::TVector< T >, 36	Clterator, 29
CException	Clear, 36
Common::CException, 16	ConstBegin, 37
Clterator	ConstEnd, 37
Common::TVector< T >, 29	ConstReverseBegin, 37
Clear	ConstReverseEnd, 37
Common::TVector< T >, 36	crbegin, 38
Common, 9	crend, 38
AreRawStringsEqual, 10	CReverselterator, 29
CopyRawString, 10, 11	CSafeConstIterator, 30
GetIteratorDistance, 11	CSafeConstReverseIterator, 3
GetRawStringLength, 12	CSafeIterator, 30
MakePair, 12	CSafeReverselterator, 30
Common::CDoesNotExist, 15	End, 38
CDoesNotExist, 15	end, 38
Common::CException, 16	Erase, 39
~CException, 17	EraseMultiple, 39
CException, 16	EReservedCapacityRule, 30
OEXCEPTION, TO	Eneserveucapacitynule, 30

60 INDEX

Exponential, 31	Common::TVector< T >, 37
Front, 40	ConstReverseEnd
GetCapacity, 40	Common::TVector< T >, 37
GetCapacityRule, 40	CopyRawString
GetSize, 41	Common, 10, 11
Insert, 41, 42	COutOfRange
IsEmpty, 42	Common::COutOfRange, 18
Linear, 31	crbegin
NeverReserve, 31	Common::TVector< T >, 38
operator!=, 42	crend
operator=, 43	Common::TVector< T >, 38
operator==, 44	CReverselterator
operator[], 44, 45	Common::TVector< T >, 29
Pop, 45	CSafeConstIterator
PopMultiple, 45	Common::TVector< T >, 30
Push, 46	CSafeConstReverseIterator
RawData, 47	Common::TVector< T >, 30
rbegin, 47	CSafelterator
rend, 47	Common::TVector< T >, 30
	CSafeReverselterator
Reserve, 48	Common::TVector< T >, 30
Resize, 48	
ReverseBegin, 49	End
ReverseEnd, 49	Common::TVector< T >, 38
SafeAt, 49	end
SafeBack, 49, 50	Common::TVector< T >, 38
SafeBegin, 50	Erase
SafeConstBegin, 50	Common::TVector< T >, 39
SafeConstEnd, 50	EraseMultiple
SafeConstReverseBegin, 51	Common::TVector< T >, 39
SafeConstReverseEnd, 51	EReservedCapacityRule
SafeEnd, 51	Common::TVector< T >, 30
SafeFront, 51, 52	ExpectedIndex
SafePop, 52	Common::COutOfRange, 20
SafeReverseBegin, 52	Exponential Exponential
SafeReverseEnd, 52	Common::TVector< T >, 31
SafeShift, 52	
SetCapacityRule, 53	First
Shift, 53	Common::TPair< T1, T2 >, 24
ShiftMultiple, 53	Front
ShrinkToFit, 54	Common::TVector< T >, 40
Swap, 54	
TVector, 31–33	GetCapacity
CommonTypes/Exception.h, 55	Common::TVector< T >, 40
CommonTypes/Optional.h, 55	GetCapacityRule
CommonTypes/Pair.h, 56	Common::TVector< T >, 40
CommonTypes/Private/BlockIterator.tpp, 56	GetExpectedRange
CommonTypes/Private/Vector.tpp, 56	Common::COutOfRange, 19
CommonTypes/Vector.h, 56	GetIteratorDistance
CommonUtils/AdvancedIteration.h, 57	Common, 11
CommonUtils/Assert.h, 57	GetMessage
CommonUtils/Private/AdvancedIteration.tpp, 57	Common::CException, 17
CommonUtils/Private/RawString.cpp, 57	GetRawStringLength
CommonUtils/RawString.h, 58	Common, 12
ConstBegin	GetRequestedIndex
Common::TVector< T >, 37	Common::COutOfRange, 19
ConstEnd	GetSize GetSize
Common::TVector< T >, 37	Common::TVector< T >, 41
ConstReverseBegin	GetValue
<u> </u>	

INDEX 61

Common::TOptional $<$ T $>$, 21	Common::TVector $<$ T $>$, 50
GetValueOr	SafeConstBegin
Common::TOptional $<$ T $>$, 21	Common::TVector $<$ T $>$, 50
	SafeConstEnd
Insert	Common::TVector< T >, 50
Common::TVector< T >, 41, 42	SafeConstReverseBegin
IsEmpty	Common::TVector< $T >$, 51
Common::TVector< T >, 42	SafeConstReverseEnd
	Common::TVector $<$ T $>$, 51
Linear	
Common::TVector< T >, 31	SafeEnd
	Common::TVector $<$ T $>$, 51
MakePair	SafeFront
Common, 12	Common::TVector $<$ T $>$, 51, 52
Common::TPair < T1, T2 >, 24	SafePop
	Common::TVector $<$ T $>$, 52
Message	SafeReverseBegin
Common::CException, 17	Common::TVector< T >, 52
Mayay Dagay ya	SafeReverseEnd
NeverReserve	Common::TVector $<$ T $>$, 52
Common::TVector< T >, 31	SafeShift
	Common::TVector $<$ T $>$, 52
operator!=	
Common::TVector< T >, 42	Second
operator=	Common::TPair< T1, T2 >, 24
Common::TOptional $<$ T $>$, 22	SetCapacityRule
Common::TVector< T >, 43	Common::TVector< T >, 53
operator==	SetValue
Common::TVector< T >, 44	Common::TOptional $<$ T $>$, 22
operator[]	Shift
Common::TVector< T >, 44, 45	Common::TVector< T >, 53
0011110111 V00101 < 1 /, 44, 40	ShiftMultiple
Pop	Common::TVector $<$ T $>$, 53
Common::TVector< T >, 45	ShrinkToFit
PopMultiple	Common::TVector< T >, 54
Common::TVector< T >, 45	Swap
Push	Common::TVector $<$ T $>$, 54
Common::TVector $<$ T $>$, 46	TO ::
	TOptional
RawData	Common::TOptional $<$ T $>$, 21
Common::TVector $<$ T $>$, 47	TPair
rbegin	Common::TPair $<$ T1, T2 $>$, 23
Common::TVector< T >, 47	TVector
rend	Common::TVector $<$ T $>$, 31–33
Common::TVector< T >, 47	
RequestedIndex	ValueExists
Common::COutOfRange, 20	Common::TOptional < T >, 22
	,
Reserve	x64/Debug/CodeAnalysisResultManifest.txt, 58
Common::TVector< T >, 48	x64/Debug/CommonLibs.vcxproj.FileListAbsolute.txt, 58
Resize	No 1/2 Dadag/ CommonLiberroxproj.: 110 Lietz to Coluctorixt, Co
Common::TVector< T >, 48	
ReverseBegin	
Common::TVector< T >, 49	
ReverseEnd	
Common::TVector< T >, 49	
SafeAt	
Common::TVector< T >, 49	
SafeBack	
Common::TVector< T >, 49, 50	
SafeBegin	