# Module Interface Specification for OCRacle

Phillip Tran

April 8, 2025

# 1 Revision History

Date	Version	Notes
March 13, 2025	1.0	Initial Document Creation

# 2 Symbols, Abbreviations and Acronyms

See SRS Documentation at https://github.com/ptrandev/OCRacle/blob/main/docs/SRS/SRS.pdf for symbols, abbreviations and acronyms.

# Contents

1	Rev	ision l	History							
2	Symbols, Abbreviations and Acronyms									
3	Introduction									
4	Not	Notation 1								
5	Mo	dule D	Decomposition							
6	MIS	S of A <sub>1</sub>	pplication Module							
	6.1	Modu	ile							
	6.2	Uses								
	6.3	Syntax	X			•				
		6.3.1	Exported Constants							
		6.3.2	Exported Access Programs			•				
	6.4	Semar	$\operatorname{ntics}^{-}$							
		6.4.1	State Variables			•				
		6.4.2	Environment Variables							
		6.4.3	Assumptions			•				
		6.4.4	Access Routine Semantics			•				
		6.4.5	Local Functions							
7	MIS	S of In	nput Format Module							
	7.1	Modu	<u>lle </u>							
	7.2	Uses				•				
	7.3	Syntax	x							
		7.3.1	Exported Constants							
		7.3.2	Exported Access Programs							
	7.4	Semar	ntics							
		7.4.1	State Variables							
		7.4.2	Environment Variables							
		7.4.3	Assumptions			•				
		7.4.4	Access Routine Semantics							
		7.4.5	Local Functions							
8	MIS	S of M	Iodel Output Module							
	8.1		ıle							
	8.2									
	8.3		X							
		8.3.1	Exported Constants							
			Exported Access Programs			_				

	8.4	Seman	ntics						7
		8.4.1	State Variables						7
		8.4.2	Environment Variables						7
		8.4.3	Assumptions						7
		8.4.4	Access Routine Semantics					•	7
9	MIS	of Mo	odel Training Module						ç
	9.1	Module	le						Ć
	9.2	Uses .							Ć
	9.3	Syntax	x						Ć
		9.3.1	Exported Constants						Ć
		9.3.2	Exported Access Programs						Ć
	9.4	Seman	ntics						Ć
		9.4.1	State Variables						Ć
		9.4.2	Environment Variables						10
		9.4.3	Assumptions						10
		9.4.4	Access Routine Semantics						10
		9.4.5	Local Functions						10
10	MIS	of Pro	rediction Model Module						11
			le						11
									11
			x						11
			Exported Constants						11
			Exported Access Programs						11
	10.4		ntics						11
			State Variables						11
			Environment Variables						11
									11
			Access Routine Semantics						11
			Local Functions						12
11	MIS	of Im	nage Preprocessing Module						13
			le						13
									13
			X						13
	11.0	•	Exported Constants						13
			Exported Access Programs						13
	11.4		ntics						13
	11.1		State Variables						13
			Environment Variables						13
			Assumptions						13
			Agging Douting Computing	•	•	•	•	•	19

11.4.5 Local Functions	. 14
12 MIS of Accuracy Metrics Module	15
12.1 Module	
12.2 Uses	
12.3 Syntax	
12.3.1 Exported Constants	
12.3.2 Exported Access Programs	
12.4 Semantics	
12.4.1 State Variables	
12.4.2 Environment Variables	
12.4.3 Assumptions	
12.4.4 Access Routine Semantics	
12.4.5 Local Functions	
12.1.0 Booth I throughout	. 10
13 MIS of Data Loading Module	17
13.1 Module	. 17
13.2 Uses	. 17
13.3 Syntax	. 17
13.3.1 Exported Constants	. 17
13.3.2 Exported Access Programs	. 17
13.4 Semantics	. 17
13.4.1 State Variables	. 17
13.4.2 Environment Variables	. 17
13.4.3 Assumptions	. 17
13.4.4 Access Routine Semantics	. 17
13.4.5 Local Functions	. 18
14 MIS of Graphical User Interface Module	19
14.1 Module	
14.2 Uses	
14.3 Syntax	
14.3.1 Exported Constants	
14.3.2 Exported Access Programs	
14.4 Semantics	
14.4.1 State Variables	
14.4.2 Environment Variables	
14.4.3 Assumptions	
14.4.4 Access Routine Semantics	
14.4.5 Local Functions	. 20
15 Appendix	22

# 3 Introduction

The following document details the Module Interface Specifications for OCRacle, an optical character recognition (OCR) program for identifying Latin alphabet characters.

Complementary documents include the System Requirement Specifications and Module Guide. The full documentation and implementation can be found at <a href="https://github.com/ptrandev/OCRacle/">https://github.com/ptrandev/OCRacle/</a>.

# 4 Notation

The structure of the MIS for modules comes from Hoffman and Strooper (1995), with the addition that template modules have been adapted from Ghezzi et al. (2003). The mathematical notation comes from Chapter 3 of Hoffman and Strooper (1995). For instance, the symbol := is used for a multiple assignment statement and conditional rules follow the form  $(c_1 \Rightarrow r_1|c_2 \Rightarrow r_2|...|c_n \Rightarrow r_n)$ .

The following table summarizes the primitive data types used by OCRacle.

Data Type	Notation	Description
character	char	a single symbol or digit
integer	$\mathbb{Z}$	a number without a fractional component in $(-\infty, \infty)$
natural number	N	a number without a fractional component in $[1, \infty)$
real	$\mathbb{R}$	any number in $(-\infty, \infty)$
bounded real	$\mathbb{R}_{\min \leq x \leq \max}$	a real number in the range [min, max]
bounded integer	$\mathbb{Z}_{\min \leq x \leq \max}$	an integer in the range [min, max]
boolean	bool	a value that is either true or false

The specification of OCRacle uses some derived data types: sequences, strings, and tuples. Sequences are lists filled with elements of the same data type. Strings are sequences of characters. Tuples contain a list of values, potentially of different types. In addition, OCRacle uses functions, which are defined by the data types of their inputs and outputs. Local functions are described by giving their type signature followed by their specification.

To describe matrices, the dimensions of the matrix will be described in superscript (i.e.  $\mathbb{Z}^{w \times w}$ ). For all additional notation, reference Section 1.2 of the SRS Document. (Tran, 2025b).

# 5 Module Decomposition

The following table is taken directly from the Module Guide document for this project.

Level 1	Level 2	
Hardware-Hiding Module		
Behaviour-Hiding Module	Input Format Module Model Output Module Model Training Module Prediction Model Module Application Module Image Preprocessing Module Accuracy Metrics Module Data Loading Module	
Software Decision Module	Graphical User Interface Module	

Table 1: Module Hierarchy

# 6 MIS of Application Module

# 6.1 Module

main

# 6.2 Uses

- Input Format Module 7
- Model Output Module 8
- Graphical User Interface Module 14

# 6.3 Syntax

# 6.3.1 Exported Constants

N/A

# 6.3.2 Exported Access Programs

Name	In	Out	Exceptions
main	-	-	-

# 6.4 Semantics

# 6.4.1 State Variables

N/A

# 6.4.2 Environment Variables

• filePath: string. The path to the input image file from the user.

# 6.4.3 Assumptions

The Graphical User Interface module 14 is responsible for handling all user inputs and displaying outputs The Application module is responsible for coordinating the interaction between the GUI, Input Format, and Model Output modules.

#### 6.4.4 Access Routine Semantics

main():

• transition: The application is started and the user is able to interact with the GUI to input images and view the model's predictions.

# 6.4.5 Local Functions

# 7 MIS of Input Format Module

# 7.1 Module

input

# 7.2 Uses

• Image Preprocessing Module 11

# 7.3 Syntax

# 7.3.1 Exported Constants

N/A

# 7.3.2 Exported Access Programs

Name	In	Out	Exceptions	
input	filePath:	$\mathbb{Z}_{0 \le x \le 255}^{w \times w}$	DimensionsError,	FormatError,
	string		FileNotFound	

# 7.4 Semantics

#### 7.4.1 State Variables

N/A

#### 7.4.2 Environment Variables

• Image: The input image file to be processed by OCRacle.

# 7.4.3 Assumptions

N/A

#### 7.4.4 Access Routine Semantics

input(filePath):

• output: imageMatrix := preprocessing(filePath). After ensuring that all exceptions are handled, call the preprocessing module 11 to perform the necessary transformations on the input image. <sup>1</sup>

<sup>&</sup>lt;sup>1</sup>By splitting up the file handling concerns with the preprocessing concerns, we are able to ensure that AC3 and AC5 from the MG (Tran, 2025a) are met. This separation of concerns allows for better modularity and maintainability of the code. For instance, if we wanted to be able to support multiple preprocessing methods or allow input of files other than images.

# • exceptions:

- A DimensionsError exception is thrown if the input image exceeds the bounds of the  $n_{min}$ ,  $n_{max}$ ,  $m_{min}$ , and  $m_{max}$  parameters as specified by Table 4 in the SRS (Tran, 2025b, 4.2.6).
- A FormatError exception is thrown if the input image is not one of the supported formats specified by R1 in the SRS (Tran, 2025b, 5.1.1).
- A FileNotFound exception is thrown if the input file does not exist.

# 7.4.5 Local Functions

# 8 MIS of Model Output Module

# 8.1 Module

output

# 8.2 Uses

• Prediction Model Module 10

# 8.3 Syntax

# 8.3.1 Exported Constants

• LABELS: ['A'...'Z']

# 8.3.2 Exported Access Programs

Name	In	Out	Exceptions
output	imageMatrix: $\mathbb{Z}_{0 \le x \le 255}^{w \times w}$	char, $\mathbb{R}_{0\leq x\leq 1}^{1\times L}$	-

# 8.4 Semantics

# 8.4.1 State Variables

N/A

# 8.4.2 Environment Variables

N/A

# 8.4.3 Assumptions

We assume that the imageMatrix input has been processed by the Input Format Module 7 before being passed to the Model Output Module.

#### 8.4.4 Access Routine Semantics

output(imageMatrix):

- output:
  - confidenceMatrix := predict(imageMatrix). Call the prediction model module 10 to generate a confidence matrix for the input image.

- prediction := LABELS[argmax(confidenceMatrix)]. Return the character representing the highest confidence value in the confidence matrix.

# 9 MIS of Model Training Module

# 9.1 Module

train

# 9.2 Uses

- Input Format Module 7
- Model Output Module 8
- Prediction Model Module 10
- Accuracy Metrics Module 12

# 9.3 Syntax

#### 9.3.1 Exported Constants

N/A

# 9.3.2 Exported Access Programs

$\mathbf{Name}$	${f In}$	$\mathbf{Out}$	Exceptions
train	-	model: $\mathbb{R}^{m \times n}$	-

# 9.4 Semantics

# 9.4.1 State Variables

- dataset:  $(\mathbb{Z}_{0 \le x \le 255}^{w \times w}$ , char)[]. The dataset of images and their corresponding labels used for training the model.
- epochs: N. The number of epochs to train the model.
- batchSize: N. The number of images to train on in each batch.
- timeStep:  $\mathbb{R}$ . The time step for the ADAM optimizer.
- $\alpha$ :  $\mathbb{R}$ . The rate at which the model learns.
- $\epsilon$ :  $\mathbb{R}$ . A small value to prevent division by zero.
- $m_t$ :  $\mathbb{R}$ . The first moment for the ADAM optimizer.
- $v_t$ :  $\mathbb{R}$ . The second moment for the ADAM optimizer.

- $\beta_1$ :  $\mathbb{R}$ . The  $\beta_1$  parameter for the ADAM optimizer.
- $\beta_2$ :  $\mathbb{R}$ . The  $\beta_2$  parameter for the ADAM optimizer.
- $g_t$ :  $\mathbb{R}^{m \times n}$ . The gradient of the model.
- $\theta_t$ :  $\mathbb{R}^{m \times n}$ . The weights of the model.

#### 9.4.2 Environment Variables

N/A

# 9.4.3 Assumptions

N/A

# 9.4.4 Access Routine Semantics

train():

- transition: The model is trained on the dataset using the hyperparameters  $\alpha$ ,  $\beta_1$ ,  $\beta_2$ ,  $\epsilon$ ,  $m_t$ ,  $v_t$ ,  $g_t$ ,  $\theta_t$ , epochs, batchSize, and timeStep. The ADAM optimizer is used to minimize the cross-entropy loss as specified by TM:ADAM (Tran, 2025b, 4.2.2) and IM1 in the SRS (Tran, 2025b, 4.2.4). For each step, theta is updated using the gradient of the model.
- output:  $\theta$ . Once the model has been trained and loss has been minimized, the weights of the model are returned.

# 9.4.5 Local Functions

# 10 MIS of Prediction Model Module

# 10.1 Module

model

# 10.2 Uses

N/A

# 10.3 Syntax

# 10.3.1 Exported Constants

N/A

# 10.3.2 Exported Access Programs

Name	In	Out	Exceptions
predict	imageMatrix:	confidenceMatrix:	-
	$\mathbb{Z}_{0\leq x\leq 255}^{w\times w}$	$\mathbb{R}_{0\leq  ext{x}\leq 1}^{1 imes L}$	

# 10.4 Semantics

#### 10.4.1 State Variables

• model:  $\mathbb{R}^{m \times n}$ . The representation of the model's weights for the prediction model.

#### 10.4.2 Environment Variables

N/A

# 10.4.3 Assumptions

We assume that the input image has been preprocessed as specified in the SRS before being passed to the prediction model.

#### 10.4.4 Access Routine Semantics

predict(imageMatrix):

• output: confidenceMatrix. Where each element in the confidence matrix represents the model's confidence in the corresponding character. The model is used to generate a confidence matrix for the input image using a CNN as specified by GD3 in the SRS (Tran, 2025b, 4.2.3). GD3 provides a high-level description of the model's architecture, but the implemented model may differ.

# 10.4.5 Local Functions

# 11 MIS of Image Preprocessing Module

# 11.1 Module

preprocessing

# 11.2 Uses

N/A

# 11.3 Syntax

# 11.3.1 Exported Constants

N/A

# 11.3.2 Exported Access Programs

Name	In	Out	Exceptions
preprocessing	file: string	imageMatrix:	-
		$\mathbb{Z}_{0\leq x\leq 255}^{w\times w}$	

# 11.4 Semantics

# 11.4.1 State Variables

N/A

# 11.4.2 Environment Variables

N/A

# 11.4.3 Assumptions

All input data has been validated by the Input Format Module before being processed by the Image Preprocessing Module.

#### 11.4.4 Access Routine Semantics

preprocessing(file):

• output: imageMatrix := normalization(bicubicInterpolation(file)). The input file has been transformed such that it conforms to the preprocessing requirements as specified by A3 in the SRS (Tran, 2025b, 4.2.1).

# 11.4.5 Local Functions

bicubicInterpolation(imageMatrix):

• output: Perform bicubic interpolation such that the imageMatrix is transformed to a 28x28 matrix. as specified by TM:BI in the SRS (Tran, 2025b, 4.2.2).

normalization(imageMatrix):

• output: Perform normalization such that the image is turned into a greyscale image with pixel values in the range [0, 255]. as specified by TM:N in the SRS (Tran, 2025b, 4.2.2).

# 12 MIS of Accuracy Metrics Module

# 12.1 Module

performance

# 12.2 Uses

N/A

# 12.3 Syntax

# 12.3.1 Exported Constants

N/A

# 12.3.2 Exported Access Programs

Name	In	Out	Exceptions
crossEntropyLoss	prediction: $\mathbb{R}_{0\leq x\leq 1}^{1\times L}$ ,	loss: $\mathbb{R}_{0 \leq x \leq 1}$	DimensionsError
${\rm confusion Matrix}$	target: $\mathbb{R}_{0 \le x \le 1}^{1 \times L}$ prediction: $\mathbb{R}_{0 \le x \le 1}^{1 \times L}$ , target: $\mathbb{R}_{0 \le x \le 1}^{1 \times L}$	confusionMatrix:	DimensionsError

# 12.4 Semantics

# 12.4.1 State Variables

N/A

# 12.4.2 Environment Variables

N/A

# 12.4.3 Assumptions

N/A

#### 12.4.4 Access Routine Semantics

crossEntropyLoss(prediction, target):

• output: loss :=  $-\sum_{i=1}^{n} target_i \log(prediction_i)$ . The cross entropy loss is calculated for the model's predictions and the target values as specified by TM:CELF in the SRS (Tran, 2025b, 4.2.2).

# • exceptions:

 A DimensionsError exception is thrown if the dimensions of the prediction and target matrices do not match.

confusionMatrix(prediction, target):

- output: confusionMatrix := confusionMatrix<sub>i,j</sub> =  $\sum_{k=1}^{n} \operatorname{target}_{k,i} \times \operatorname{prediction}_{k,j}$ . A confusion matrix is generated for the model's predictions and the target values to fulfill NFR1 in the SRS (Tran, 2025b, 5.2).
- exceptions:
  - A DimensionsError exception is thrown if the dimensions of the prediction and target matrices do not match.

# 12.4.5 Local Functions

# 13 MIS of Data Loading Module

# 13.1 Module

data

13.2 Uses

N/A

# 13.3 Syntax

# 13.3.1 Exported Constants

N/A

# 13.3.2 Exported Access Programs

Name	In	Out	Exceptions
extractTestSamples	-	$\mathbb{R}_{0>x>1}^{w\times w}[], \mathbb{Z}[]$	-
extract Training Samples	-	$\mathbb{R}_{0\geq x\geq 1}^{w\overline{ imes}w\overline{ imes}}[],\ \mathbb{Z}[]$	-

# 13.4 Semantics

# 13.4.1 State Variables

N/A

# 13.4.2 Environment Variables

N/A

# 13.4.3 Assumptions

N/A

#### 13.4.4 Access Routine Semantics

extractTestSamples():

• output: (images, labels) := processSamples(testImages, testLabels). A tuple containing the test images and their corresponding labels. The test samples are extracted from the EMNIST letters dataset.

extractTrainingSamples():

• output: (images, labels) := processSamples(trainingImages, trainingLabels). A tuple containing the training images and their corresponding labels. The training samples are extracted from the EMNIST letters dataset.

# 13.4.5 Local Functions

processSamples():

• output: (images, labels). The images are normalized to have a pixel range between 0 and 1 inclusive, as specified by the SRS document (Tran, 2025b). The labels are scaled to start at 0 instead of 1 to align with the model architecture's output as specified by the SRS document (Tran, 2025b).

# 14 MIS of Graphical User Interface Module

# 14.1 Module

gui

# 14.2 Uses

• Hardware-Hiding Module

# 14.3 Syntax

# 14.3.1 Exported Constants

N/A

# 14.3.2 Exported Access Programs

View the Appendix 15 for more information the full range of interactions that the Graphical User Interface Module can have with the user.

Name	In	Out	Exceptions
displayOutput	-	-	-
acceptInput	-	-	-

# 14.4 Semantics

#### 14.4.1 State Variables

N/A

# 14.4.2 Environment Variables

• displayWindow: (dimensions:  $\mathbb{Z}_+ \times \mathbb{Z}_+$ )

• keyboard: (keypress: char)

• mouse: (location:  $\mathbb{Z}_+ \times \mathbb{Z}_+$ , click: bool)

# 14.4.3 Assumptions

This behavior will be significantly abstracted by the use of Python Notebook, which will handle all UI elements and interactions with the user. As a result, the GUI modules does not need to have any pre-defined state variables or access routines.




Figure 1: Example of the displayOutput() function. It will display the model's prediction and the confidence matrix to the user in a graphical format.

# 14.4.4 Access Routine Semantics

displayOutput():

- transition: The output of the model is displayed to the user in the GUI. acceptInput():
  - transition: The user is able to input images to the model in the GUI.

# 14.4.5 Local Functions




Figure 2: Example of the acceptInput() function. It allows users to input a file path and run the model on the input image.

# References

Carlo Ghezzi, Mehdi Jazayeri, and Dino Mandrioli. Fundamentals of Software Engineering. Prentice Hall, Upper Saddle River, NJ, USA, 2nd edition, 2003.

Daniel M. Hoffman and Paul A. Strooper. Software Design, Automated Testing, and Maintenance: A Practical Approach. International Thomson Computer Press, New York, NY, USA, 1995. URL http://citeseer.ist.psu.edu/428727.html.

Phillip Tran. Module guide. https://github.com/ptrandev/OCRacle/blob/main/docs/Design/SoftArchitecture/MG.pdf, 2025a.

Phillip Tran. System requirements specification. https://github.com/ptrandev/OCRacle/blob/main/docs/SRS/SRS.pdf, 2025b.

# 15 Appendix

- The Python Notebook documentation can be found at <a href="https://jupyter-notebook.readthedocs.">https://jupyter-notebook.readthedocs.</a> io/en/latest/user-documentation.html. This informs the full range of interactions that the Graphical User Interface Module 14 can have with the user.
- Generative AI Acknowledgement: ChatGPT-40 was used to generate valid LaTeX for mathematical expressions in this document.