

PyramidMap Geotools Visualized Toolset Instructions

PyramidMap Geotools Visualized Toolset Instructions

1 Introduction

- 1.1: Function overview
- 1.2 Contact us

2 Software deployment

- 2.1 Deployment mode
- 2.2 Running mode
- 2.3 System function

3 Map view

- 3.1 Load basemap
- 3.2 Load business layer
 - 3.2.1 Load local Shp layer
 - 3.2.2 Load Geodatabase layer
 - 3.2.3 Geodatabase node catalog and operation
 - 3.2.4 Load GeoServer layer
 - 3.2.5 GeoServer node catalog and operation
- 3.3 Visible layer node operations
 - 3.3.1 Layer control
 - 3.3.2 Symbol rendering
 - 3.3.3 Feature data table

4 Map editing

- 4.1 Create Shp
- 4.2 Graphical Editing
 - 4.2.1 Main view editor
 - 4.2.2 Independent view editor
- 4.3 Attribute data editing
 - 4.3.1 Editing in main map view
 - 4.3.2 Editing in individual map view

5 Geodatabase and GeoServer

- 5.1 Geodatabase connection pool

- 5.1.1 Geodatabase data source node
- 5.1.2 Geodatabase connection pool
- 5.2 GeoServer connection pool
 - 5.2.1 GeoServer data node
 - 5.2.2 GeoServer connection pool
 - 5.2.3 Manage GeoServer connections
- 5.3 GeoServer internal operate
 - 5.3.1 GeoServer Workspace
 - 5.3.2 GeoServer data storage
 - 5.3.3 GeoServer pool console

6 Map data and conversion

- 6.1 Vector layers pool
 - 6.1.1 Layer preview
 - 6.1.2 Data processing
- 6.2 Raster layers pool
 - 6.2.1 Layer preview
 - 6.2.2 Data processing
 - 6.2.3 Raster compress
 - 6.2.4 Raster slice
 - 6.2.5 Raster merge
 - 6.2.6 NoData processing
 - 6.2.7 Coordinate System Conversion
- 6.3 Geodatabase layers pool
 - 6.3.1 Importing Shp into Geodatabase
 - 6.3.2 Geodatabase exporting out shp
 - 6.3.3 Geodatabase layers preview and edit
- 6.4 GeoServer vector layers pool
 - 6.4.1 GeoServer layers preview
 - 6.4.2 GeoServer layers exporting
- 6.5 GeoServer raster layer pool
- 6.6 Coordinate System Conversion
- 6.8 Map Tile
 - 6.8.1 Tile pyramid model
 - 6.8.2 Tile coordinate system
 - 6.8.3 Tile representation
 - 6.8.4 Build Vector TMS tile
 - 6.8.5 Build Vector XYZ tile
 - 6.8.6 Build Vector MVT tile
 - 6.8.7 Build Vector MBTile tile
 - 6.8.8 Build Raster TMS tile
 - 6.8.9 Build Raster XYZ Tile
 - 6.8.10 Build Raster MBTiles

7 Map rendering and sld symbol

- 7.1 Define sld symbols at client
 - 7.1.1 Create sld on visualizing layer nodes
 - 7.1.2 Create map symbols in the sld resource pool
 - 7.1.3 Get GeoServer sld symbols
- 7.2 Map rendering effect with sld
- 7.3 Client sld symbols submitted to GeoServer

8 Publishing map service

- 8.1 Publish Shp vector layers
- 8.2 Publish raster layers
- 8.3 Publish Geodatabase layers
- 8.4 Manage GeoServer layers
 - 8.4.1 GeoServer layers preview

1 Introduction

1.1: Function overview

As the world enters the information and digital era, the development of communication and Internet technology has completely changed the way people communicate and perceive the world. GIS (Geographic Information System) has developed from original paper map to holographic digital electronic map. GIS is synchronized with the software and hardware support of operating system, communication interconnection and mobile terminal, and has penetrated into all aspects of social production and people's life. From space launch, satellite remote sensing, express delivery and bus service, almost every link is shining with the glory of GIS. GIS can integrate spatial and dynamic information into holographic digital visual effects, and provide timely and accurate visual services for geographical research, geographical decision-making and residents' lives. The rich and colorful services of GIS come from its massive data support and powerful analysis and processing capabilities. However, the production, storage, analysis, processing and service provision of map data is an extremely professional, arduous and complex work, which has professional requirements for workflow and operators, and the technical cost is very high. Therefore, many enterprises with this demand but weak technology are discouraged. PyramidMap is a simple and practical GIS data processing workflow platform for small and medium-sized enterprises to solve this problem.

PyramidMap GeoTools visual map tool set is launched by PyramidMap (www.Pyramidmap.com). It is based on GeoTools component technology, which can be used as an independent map processing tool, as well as oriented to GeoServer and used as its client. It constitutes a simple and easy-to-use map service system covering mapping, editing and assignment, rendering, database storage, service release and management. It is simple and easy to use, covering mapping, editing and assignment, rendering, database storage, service publishing, and management. The purpose of PyramidMap is to transform the professional and even daunting GIS data processing into an approachable, easy to use, relaxed and pleasant workflow. On this basis, the original complex process of GeoServer and Geodatabase connection and map service publishing is transformed into a fully guided visualization process, reducing the user threshold and improving the efficiency of map operation. Thus, GIS users are given the ability to independently complete the whole process from map mapping to web map services. Its ultimate goal is to provide efficient data processing process for WebGIS applications. That is to say, PyramidMap tool provides you with the most basic data assurance processing process for WebGIS applications. It belongs to the core layer of map data processing and is also the most complex process. PyramidMap is fully qualified for this work. The process is shown in Figure 1-1.




Figure 1-1: Diagram of PyramidMap Total Energy

PyramidMap is positioned at the key link of the whole WebGIS implementation process, and completes the processing and storage of key map data before the feasibility of WebGIS. Traditionally, it is highly dependent on the skills of professional GIS personnel. Now it can be easily completed by PyramidMap, which greatly reduces the access threshold for GIS users and improves the efficiency of map data processing.

1.2 Contact us

PyramidMap focuses on GIS application services and is committed to building a complete ecosystem of efficient GIS data processing, enterprise level geographic data storage, distributed map services, web and mobile map applications. It can help you achieve map data processing more easily and quickly, until the terminal displays the entire process of the application as a streamlined service. Welcome visiting to: <http://www.pyramidmap.com> obtaining beta software and technical information. For more technical support, please contact PyramidMap studio.

Email: service@pyramidmap.com

Tele: (086)0531-82957588

Mobile: (086)18660789051

WeChat: A18660789051

QQ: 29862351

2 Software deployment

2.1 Deployment mode

PyramidMap integrates all the dependencies required for operation internally. You only need to decompress the software to use it (Chinese path is not supported for the moment). Double click the PyramidMapView.exe executable to run it. The deployment mode is shown in Figure 2-1.




Figure 2-1: Schematic Diagram of PyramidMap Deployment Operation Mode

The PyramidMap GeoTools visualization toolset is only supported running in a Windows environment currently , with a minimum resolution requirement of 1920 * 1200.

2.2 Running mode

- Client/Server mode

PyramidMap can complete independent mapping, map editing, symbol definition rendering, Geodatabase geographic database connection, access, map data input and output, GeoServer map server space management, map service publishing, hosting and access and other full process processing. PyramidMap can independently complete all functions from mapping to editing, support multiple spatial geographic databases, including but not limited to Oracle, Postgre, MySQL, and complete the input, output, access and storage of map data. PyramidMap can be seamlessly connected with GeoServer map server, and can be used as a visualization client tool of GeoServer to complete workspace and data storage management of remote server, layer publishing, map symbol production and publishing, server layer and symbol data management, preview and other serialized operations on the client. To sum up, PyramidMap provides map users with a full process function from mapping to Web side use. PyramidMap supports deployment in Internet and intranet environments. It has all the dependencies required for integrated operation. It can be used after decompression without installation (Chinese path is not supported temporarily).The role and operation mode of PyramidMap in WebGIS network architecture are shown in Figure 2-2.




Figure 2-2: The role and operation mode of PyramidMap in WebGIS network architecture

2.3 System function

Functions	Products				Application Scenario
	Free	Basic	Standard	Professional	
Map display	●	●	●	●	Displaying various map such as vector, raster, geodatabase, GeoServer and WMTS.
Map resource management	●	●	●	●	Vector, raster, geodatabase, GeoServer, WMS, WFS/WMTS layers list.
Shp creation and editing	●	●	●	●	Design and create the original Shape file and initialize the data table.
Map feature selection	●	●	●	●	The selecting interface exchange of map points, lines, and surface features.
Map feature drawing	●	●	●	●	Create points, lines, and polygons on the map and perform custom rendering.
Map data editing	●	●	●	●	Add, delete, and modify map features and their attribute data.
Map data query	●	●	●	●	Build visual query analyzer, implement multi condition constructed queries for attribute data, and achieve specific rendering of result sets.
Map data conversion			●	●	The bidirectional exchange between heterogeneous data such as Shp, Geodatabase, GeoServer, and Excel, Csv, Kml, GeoJson.
Map symbol management		●	●	●	Create SLD symbols and manage in pool locally, and achieve bidirectional synchronization with GeoServer.
Coordinate System Conversion			●	●	Coordinate systems conversion for vector and raster, supporting the vast majority of EPSG standardized geographic and projection coordinate systems.
Vector layers tile	Level 10	Level 12	Level 16	Level 24	Build TMS, Google XYZ, MVT (Mapbox Vector Tile), MBTile (Mapbox Tile) tiles.
Raster layers tile	Level 10	Level 12	Level 16	Level 24	Build TMS, Google XYZ, MBTile (Mapbox Tile) tiles.
Raster data processing			●	●	Raster compression, slicing, merging, NoData processing.
GeoDatabase connections pool	●	●	●	●	Supports Oracle, PostGIS, MySQL, and SQL Server connections pools.
Import and export of GeoDatabase			●	●	Import layers into geodatabase and export out such as Shp, Csv, Kml, GeoJson.
GeoServer connections pool	●	●	●	●	Create GeoServer connections and maintain in pool mode.
GeoServer workspace management				●	Creates and obtains workspaces for GeoServer on client side.
GeoServer datastorage management				●	Creates and obtains data storages for GeoServer on client side.
Workspace Sync with GeoServer				●	Sync workspaces between client and GeoServer.
DataStorage Sync with GeoServer				●	Sync datastorages between client and GeoServer.
SLD Sync with GeoServer			●	●	Sync sld's between client and GeoServer.
Layers published to GeoServer				●	Publish vector and raster layers to GeoServer on the client side.

Table 2-1: PyramidMap release functions list

The download list of examples and experiment data in the PyramidMap GeoTools visualized ToolSet is shown in Table 2-2

Chapter	Experiment data	Web example
3.2 Load business layer	shp files	
3.3.2 Symbol rendering	sld files	
6.1.1 Vector Layer preview	shp files	
6.1.2 Vector Data processing	shp files	
6.7.1 Csv to Shp	csv data	
6.7.2 Excel to Shp	excel data	
6.7.3 GeoJSON to Shp	geojson data	
6.7.4 Shp to Csv and GeoJSON	shp files	
6.7.5 Shp to Kml	shp files	
6.8.4 Build Vector TMS tile	Vector tiling source data	web example
6.8.5 Build Vector XYZ tile	Vector tiling source data	web example
6.8.6 Build Vector MVT tile	Vector tiling source data	web example
6.8.7 Build Vector MBTile tile	Vector tiling source data	web example
6.8.8 Build Raster TMS tile	Raster tiling source data	web example
6.8.9 Build Raster XYZ tile	Raster tiling source data	web example
6.8.10 Build Raster MBTiles	Raster tiling source data	web example

Table 2-2: Experimental data and examples list in PyramidMap GeoTools Visualized Toolset

3 Map view

The main map interface is divided into four functional areas, as shown in Figure 3-1. They are the main map view and the display container of all map data. They accept the loading and display of various map resource data from Shp files, image files, Geodatabase, GeoServer, online maps, etc; The online layer node on the left is the layer data source node that has been loaded into the main map view. It is classified according to the path layer, and has the corresponding level menu to complete the operation as instructed; On the upper right is the Geodatabase data source node, which is classified according to the data connection layer table, and has the corresponding level menu. The operation can be completed according to the instructions. The layer table can be dragged to the map view area or displayed by double clicking the mouse, and automatically added to the layer display node on the left; The lower right side is the GeoServer workspace and layer data source node, which are classified according to GeoServer connection - workspace - layer, and have the corresponding level menu. The operation is completed according to the instructions. The layer can be dragged to the map view area or displayed by double clicking the mouse, and automatically added to the layer display node on the left.




Figure 3-1: Main map viewer

3.1 Load basemap

The base map provides a reference map for the system and an environment for the content to be displayed in the map. When creating a new map, you can select an underlay to use. PyramidMap currently supports many base map resource based on Web Mercator coordinate system and others standard coordinate system. You can change the base map of the current map at any time: you can select the base map from the base map library. With the help of the base map, accurate spatial location calibration can be carried out, map data related to location can be processed, dot, line and picture can be plotted on the map, and accurate positioning and track query can be carried out. The main interface loads and switches the base map through the shortcut menu in the toolbar, as shown in Figure 3-2.




Figure 3-2: Main viewer base map menu

PyramidMap supports vector and raster type base map resources. This base map is designed to be used as a general reference map for informational purposes as well as for GIS professionals and other users to creating web maps and web mapping applications.

The world general reference map includes administrative boundaries, cities, protected areas, highways, roads, railways, water features, buildings and landmarks, overlaid on shaded relief and land cover imagery for added context. This reference map display effect is shown in Figure 3-3.




Figure 3-3: The world general reference map display effect

The local details somewhere for the world general reference map are shown in Figure 3-4.




Figure 3-4: The world general reference map somewhere local details

The world land cover imagery and detailed topographic map presents land cover imagery and detailed topographic maps for the world. This map display effect is shown in Figure 3-5.




Figure 3-5: The world land cover imagery and detailed topographic map display effect

The local details somewhere for the world land cover imagery and detailed topographic map are shown in Figure 3-6.




Figure 3-6: The world land cover imagery and detailed topographic map somewhere local details

The world satellite and aerial imagery map provides one meter or better satellite and aerial imagery in many parts of the world and lower resolution satellite imagery worldwide. The map includes 15m TerraColor imagery at small and mid-scales (~1:591M down to ~1:288k) for the world. The map features Maxar imagery at 0.3m resolution for select metropolitan areas around the world, 0.5m resolution across the United States and parts of Western Europe, and 1m resolution imagery across the rest of the world. The world satellite and aerial imagery map features high-resolution aerial photography contributed by the GIS User Community. This imagery ranges from 0.3m to 0.03m resolution (down to ~1:280 in select communities). The world satellite image display effect is shown in Figure 3-7.



Figure 3-7: The world satellite image map display effect

The local details somewhere for the world satellite and aerial imagery map are shown in Figure 3-8.




Figure 3-8: The world satellite image map somewhere local details

The world physical map presents the Natural Earth physical map at 1.24km per pixel for the world and 500m for the coterminous United States. This map display effect is shown in Figure 3-9.




Figure 3-9: The world physical map display effect

The local details somewhere for the world physical map are shown in Figure 3-10.




Figure 3-10: The world physical map somewhere local details

The world shaded relief map portrays surface elevation as shaded relief. This map is used as a basemap layer to add shaded relief to other GIS maps, such as the ArcGIS Online World Street Map. It is especially useful in maps that do not contain orthoimagery. The map resolution (cell size) is as follows: 30 Meters for the U.S. 90 Meters for all land areas between 60 degrees north and 56 degrees south latitude. 1 KM resolution above 60 degrees north and 56 degrees south. The shaded relief imagery was developed by Esri using GTOPO30, Shuttle Radar Topography Mission (SRTM), and National Elevation Data (NED) data from the USGS. The world shaded relief map display effect is shown in Figure 3-11.




Figure 3-11: The world shaded relief map display effect

The local details somewhere for the world shaded relief map are shown in Figure 3-12.




Figure 3-12: The world shaded relief map somewhere local details

The world street map presents highway-level data for the world. Street-level data includes the United States; much of Canada; Mexico; Europe; Japan; Australia and New Zealand; India; South America and Central America; Africa; and most of the Middle East. This comprehensive street map includes highways, major roads, minor roads, one-way arrow indicators, railways, water features, administrative boundaries, cities, parks, and landmarks, overlaid on shaded relief imagery for added context. Display effect is shown in Figure 3-13.




Figure 3-13: The world street map display effect

The local details somewhere for the world street map are shown in Figure 3-14.




Figure 3-14: The world street map somewhere local details

The world terrain base map is designed to be used as a base map by GIS professionals to overlay other thematic layers such as demographics or land cover. The base map features shaded relief imagery, bathymetry, and coastal water features designed to provide a neutral background for other data layers. The base map currently provides coverage for the world down to a scale of ~1:1m. The world terrain base map display effect is shown in Figure 3-15.




Figure 3-15: The world terrain base map display effect

The local details somewhere for the world terrain base map are shown in Figure 3-16.




Figure 3-16: The world terrain base map somewhere local details

The world topographic base map is designed to be used as a basemap by GIS professionals and as a reference map by anyone. The map includes administrative boundaries, cities, water features, physiographic features, parks, landmarks, highways, roads, railways, and airports overlaid on land cover and shaded relief imagery for added context. The world topographic base map display effect is shown in Figure 3-17.




Figure 3-17: The world topographic base map display effect

The local details somewhere for the world topographic base map are shown in Figure 3-18.




Figure 3-18: The world topographic base map somewhere local details

The world geomorphology and road network map presents highway-level data for the world. Street-level data includes the United States; much of Canada; Japan; Europe; Australia and New Zealand; India; South America and Central America; most of the Middle East; Egypt and Morocco; and parts of southern Africa including Botswana, Lesotho, Namibia, South Africa, and Swaziland. This comprehensive street map includes highways, major roads, minor roads, one-way arrow indicators, railways, water features, administrative boundaries, cities, parks, and landmarks, overlaid on shaded relief imagery for added context. This map display effect is shown in Figure 3-19.




Figure 3-19: The world geomorphology and road network display effect

The local details somewhere for the world geomorphology and road network map are shown in Figure 3-20.




Figure 3-20: The world geomorphology and road network map somewhere local details

3.2 Load business layer

The map view supports the following map data: Shp file type, Geodatabase geographic database type, WMS, WFS, WCS, WMTS and other standardized map services from GeoServer, and various online map resources that follow standardized specifications. The layers added to the view are classified according to the data source path and displayed in the layer node on the left. The hierarchical operation is implemented through the right-click shortcut menu.

3.2.1 Load local Shp layer

Select "Load local vector layer" in the toolbar, as shown in Figure 3-21.




Figure 3-21: Load local vector layer

Loading the required layer through file browser. After successful loading, it will be displayed in the map view, and the layers mount node on the left will be formed, as shown in Figure 3-22.




Figure 3-22: Load local shp file broswer

Then the shp selected display in the map viewer, as shown in Figure 3-23.




Figure 3-23: Load local shp file and display in the map viewer

At the same time, PyramidMap provides a more convenient operation, assuming the map initialization view is shown in Figure 3-24.




Figure 3-24: The map viewer initialization

You can drag and drop the shapefiles to the map view displaying directly, as shown in Figure 3-25.




Figure 3-25: Drag and drop the shapefiles to the map view displaying directly

The display effect is shown in Figure 3-26.




Figure 3-26: Drag and drop the shapefiles displaying

3.2.2 Load Geodatabase layer

In the node tree of the database connection pool on the main interface, double-click the database node to dynamically load its internal layer. Drag the layer node to the map view or double-click the mouse to display it. At the same time, the layer mount node on the left is formed, as shown in Figure 3-27.




Figure 3-27: Loading and displaying vector layers in Geodatabase

3.2.3 Geodatabase node catalog and operation

On the upper right side of the main interface, there is a Geodatabase connection pool node, which provides a Geodatabase data source. Double click the database node to dynamically load its internal layers. The layer nodes can be dragged or double clicked to displaying in the map viewer. Different levels of nodes have corresponding shortcut menus. The database node menu

completes database connection test, editing, layer list management, and deletion operations, as shown in Figure 3-28.




Figure 3-28: Geodatabase node popup menu

The layer node menu supports exporting database layers to Shp, Kml, Csv, GeoJson and other formats or being deleted, as shown in Figure 3-29.




Figure 3-29: Geodatabase layer node popup menu

3.2.4 Load GeoServer layer

In the node tree of the GeoServer connection pool in the main interface, double-click the GeoServer node to dynamically load its internal workspace and its layers. The layer nodes can be dragged or double clicked to displaying in the map viewer, at the same time, the layer mount node on the left is formed, as shown in Figure 3-30.




Figure 3-30: Loading and displaying vector layers in GeoServer

3.2.5 GeoServer node catalog and operation

On the lower right side of the main interface, the GeoServer connects to the pool node, providing the GeoServer data source. Double click the GeoServer node, then dynamic loading the internal workspace and layer nodes. Nodes at different levels have corresponding shortcut menus. The GeoServer node menu completes the server connection test, connection editing, obtaining server synchronization data (configuring the GeoServer workspace and data storage and its database connection), workspace management (localizing and modifying the workspace parameters and synchronizing them to the server), refreshing the layer list, connection deletion, and other operations, as shown in Figure 3-31.




Figure 3-31: GeoServer node popup menu

Under the GeoServer node is the workspace node. The workspace node menu completes data storage management, layer node refresh, map import, workspace deletion and other operations, as shown in Figure 3-32.




Figure 3-32: GeoServer workspace node popup menu

In particular, in the data storage list, you can edit and modify the database connection and maintain the layer list for each item in the list, including the details of the layer and the addition and deletion maintenance. The layer nodes can be dragged or double clicked to displaying in the map viewer and can be setted sld symbols, exported and deleted, as shown in Figure 3-33.




Figure 3-33: GeoServer layer node popup menu

Especially in the layer node under the GeoServer workspace, right click to set the binding relationship between the layer and the sld display symbol in the GeoServer, as shown in Figure 3-34.




Figure 3-34: Set the binding relationship between the layer and the sld symbol in the GeoServer

PyramidMap will return the sld symbol selection list of the same geometry type on the server according to the selected layer, as shown in Figure 3-35.

No	style	workArea	GeometryType	Symbol	Size(pixel)	StrokeWidth(pixel)	StrokeColor	StrokeOpacity	FillColor	FillOpacity	LabelField	Check
1	cite_lakes				5.0	1		1		1.0		<input type="radio"/>
2	giant_polygon				5.0	1.0		1.0		1.0		<input type="radio"/>
3	grass				5.0	1		1.0		1.0		<input type="radio"/>
4	green				5.0	1.0		1.0		1.0		<input type="radio"/>
5	polygon				5.0	1		1.0		1.0		<input type="radio"/>
6	provinceregion				5.0	1.0		0.579999983310...	0.579999983310...	1.0		<input checked="" type="radio"/>
7	restricted				5.0	1		1.0		0.7		<input type="radio"/>

Figure 3-35: Return sld symbol list of the same geometry type on the server according to the selected layer

Click "OK", the selected layer and sld symbol are bound successfully. Subsequently, the WMS service of this layer output by the GeoServer server will be rendered according to this symbol, as shown in Figure 3-36.




Figure 3-36: The WMS service of this layer output by the GeoServer server will be rendered according to this symbol

3.3 Visible layer node operations

3.3.1 Layer control

The layers in the main map view are classified and managed in checkbox tree nodes. It supports the popup menu and checked visible controlling on each layer node, and the corresponding operations are implemented according to the layer type. The following is layer checkbox node classification and operation for vector layers, as shown in Figure 3-37.




Figure 3-37: Vector layer checkbox node classification and operation

The following is layer checkbox node classification and operation for raster layer, as shown in Figure 3-38.




Figure 3-38: Raster layer checkbox node classification and operation

You can control the visibility of layers and the data processing of different types of layers with the classification and operation of layer checkbox nodes.

3.3.2 Symbol rendering

Select New sld Symbol from the shortcut menu of the vector layer display node to enter the sld symbol definition interface, as shown in Figure 3-39.




Figure 3-39: Definition and effect of map Sld symbols

With this operation, create a style definition file for point (Point, MultiPoint), line (LineString, MultiLineString), polygon (Polygon, MultiPolygon) type layers, and set the annotation field and font type, size, color, and annotation location. After the effect preview is satisfactory, save it as an sld file and include it in the PyramidMap resource pool for maintenance, The SLD resource pool maintained by PyramidMap client can provide feature symbol selection for layers. Select the SLD symbol on the layer node, as shown in Figure 3-40.




Figure 3-40: Select sld symbol on layer node

PyramidMap will automatically match the Sld data according to the geometry type of the selected layer, and provide a selection list of sld resources of the same geometry type, as shown in Figure 3-41.

No.	SldFileName	SldFilePath	GeometryType	Symbol	Size(pixel)	StrokeWidth(pixel)	StrokeColor	StrokeOpacity	FillColor	FillOpacity	LabelField	Check
1	buildpoint1.sld	D:\SLD\buildpoint1.sld	<input checked="" type="radio"/>	Circle	12.0	1.0	1.0	1.0	1.0	1.0		<input type="radio"/>
2	buildpoint2.sld	D:\SLD\buildpoint2.sld	<input checked="" type="radio"/>	Circle	12.0	1.0	1.0	1.0	1.0	1.0		<input type="radio"/>
3	buildpoint3.sld	D:\SLD\buildpoint3.sld	<input checked="" type="radio"/>	Circle	12.0	1.0	1.0	1.0	1.0	1.0		<input type="radio"/>
4	buildpoint5.sld	D:\SLD\buildpoint5.sld	<input checked="" type="radio"/>	Circle	12.0	1.0	1.0	1.0	1.0	1.0		<input checked="" type="radio"/>
5	burg.sld	D:\SLD\burg.sld	<input checked="" type="radio"/>	Circle	20	1.0	1.0	1.0	1.0	1.0		<input type="radio"/>
6	capitals.sld	D:\SLD\capitals.sld	<input checked="" type="radio"/>	circle	6	2	1.0	1.0	1.0	1.0		<input type="radio"/>
7	generic.sld	D:\SLD\generic.sld	<input checked="" type="radio"/>	square	6	1	1	1	1.0	1.0		<input type="radio"/>
8	point.sld	D:\SLD\point.sld	<input checked="" type="radio"/>	square	6	1.0	1.0	1.0	1.0	1.0		<input type="radio"/>

Figure 3-41: SLD resource list of the same geometry type as the selected layer

The rendering effect of the selected sld is applied to the layer, as shown in Figure 3-42.




Figure 3-42: Rendering effect of layer after applying the selected sld

3.3.3 Feature data table

Select the "Open shp table" option in the layer node on the left, as shown in Figure 3-43.




Figure 3-43: Open shp table

The feature data table and query page of the selected layer are shown in Figure 3-44.

FeatureIdentifier	the_geom	NAME	STCTYFIPS	ELEV_METER	LABEL_FLAG
Buildings.1	POINT (-114.61523004299994 32...)	Yuma Territorial Prison	04027	47.0	0
Buildings.2	POINT (-114.30717396799992 34...)	Colorado River Water Pollution Con...	04012	115.0	0
Buildings.3	POINT (-114.2896733209998 34.1...)	La Paz County Courthouse	04012	128.0	0
Buildings.4	POINT (-114.2943957249998 34.1...)	Parker City Hall	04012	127.0	0
Buildings.5	POINT (-114.62106359199993 32...)	Yuma City Hall	04027	49.0	0
Buildings.6	POINT (-114.62273023299991 32...)	Yuma Courthouse	04027	52.0	0
Buildings.7	POINT (-114.3038406339998 34.1...)	Colorado River Indian Agency Head...	04012	126.0	0
Buildings.8	POINT (-123.10528074899992 38...)	McDonald Mountain House	06045	380.0	0
Buildings.9	POINT (-119.61064262799993 35...)	Breckenridge Lodge	06029	1824.0	0
Buildings.10	POINT (-120.10541561299993 36...)	Eleven P Office	06031	383.0	0
Buildings.11	POINT (-118.1031247169998 34.0...)	Maryvale Orphanage	06037	106.0	0
Buildings.12	POINT (-121.3832662339998 36.4...)	Soledad State Prison	06053	63.0	0
Buildings.13	POINT (-118.44813880299989 34...)	Los Angeles City Fire Station	06037	386.0	0
Buildings.14	POINT (-122.49663861699992 37...)	Anglers Lodge	06075	37.0	0
Buildings.15	POINT (-122.41691563499994 37...)	Anna Bremer Memorial Library	06075	25.0	0
Buildings.16	POINT (-122.41135996599992 37...)	Bohemian Club	06075	34.0	0
Buildings.17	POINT (-122.43302691299994 37...)	Bourn Mansion	06075	80.0	0
Buildings.18	POINT (-122.41747103699993 37...)	Brooks Exhibit Hall	06075	19.0	0
Buildings.19	POINT (-122.41163779499993 37...)	Cable Car Barn and Museum	06075	61.0	0
Buildings.20	POINT (-122.42941565399991 37...)	California Historical Society	06075	88.0	0
Buildings.21	POINT (-122.42969317199993 37...)	Casa Cielo	06075	98.0	0
Buildings.22	POINT (-122.4235822579998 37...)	Century Club of California	06075	59.0	0
Buildings.23	POINT (-122.39163733999993 37...)	China Basin Building	06075	1.0	0
Buildings.24	POINT (-122.40469325399993 37...)	Chinese Cultural and Trade Center	06075	12.0	0
Buildings.25	POINT (-122.41719336599994 37...)	Civic Center Auditorium	06075	18.0	0
Buildings.26	POINT (-122.40469325399994 37...)	Columbus Tower	06075	8.0	0
Buildings.27	POINT (-122.4205897599993 37...)	Davies Symphony Hall	06075	20.0	0
Buildings.28	POINT (-122.40330426499993 37...)	DeYoung Building	06075	13.0	0
Buildings.29	POINT (-122.39830436199992 37...)	Embarcadero Center	06075	3.0	0
Buildings.30	POINT (-122.41497107599992 37...)	Far West Library for Educational Re...	06075	7.0	0
Buildings.31	POINT (-122.39552642399991 37...)	Federal Reserve Bank of San Franc...	06075	3.0	0
Buildings.32	POINT (-122.40469325399994 37...)	Fire Station Number Two	06075	18.0	0

Figure 3-44: Shp table and query interface

In the layer data table interface, you can build a combined query condition based on all fields through the query tool to realize simple and complex queries on layers, as shown in Figure 3-45.




Figure 3-45: Layer table query constructor

In the query constructor, you can verify the validity of the built query statements, as shown in Figure 3-46.




Figure 3-46: Query statement validation

The validation results are shown in Figure 3-47.



Figure 3-47: Query statement validation results

Click "Apply" to execute the query. Based on the above construction conditions, the data table query results are shown in Figure 3-48.

FeatureIdentifier	the_geom	NAME	STCTYFIPS	ELEV_METER	LABEL_FLAG
Buildings_1867	POINT (-120.38602709899993 37.9...)	Morgan Mansion	06109	565.0	0
Buildings_1868	POINT (-120.3849159539999 37.98...)	Sonora City Hall	06109	565.0	0
Buildings_1869	POINT (-120.38158251899993 37.9...)	Sugg House	06109	547.0	0
Buildings_1870	POINT (-120.38408263399992 37.9...)	Tuolumne County Courthouse	06109	557.0	0
Buildings_1871	POINT (-120.38408263399992 37.9...)	Tuolumne County Law Library	06109	557.0	0
Buildings_1872	POINT (-120.38574927399993 37.9...)	Tuolumne County Museum	06109	548.0	0
Buildings_1873	POINT (-120.23796654499998 37.9...)	Memorial Hall	06109	790.0	0
Buildings_1874	POINT (-120.36789313199994 37.9...)	Tuolumne County Free Library	06109	626.0	0
Buildings_1875	POINT (-120.29991375299994 37.9...)	Moccasin Creek Power House	06109	283.0	0
Buildings_2272	POINT (-120.38824984799993 38.0...)	Columbia College Library	06109	698.0	0
Buildings_2273	POINT (-120.40047274799991 38.0...)	Columbia Fire House	06109	651.0	0
Buildings_2274	POINT (-120.40019492399995 38.0...)	Claverie Building	06109	655.0	0
Buildings_2275	POINT (-120.40047274799991 38.0...)	Franklin and Wolfe Building	06109	647.0	0
Buildings_2276	POINT (-120.40102824399992 38.0...)	Hildebrand Building	06109	648.0	0
Buildings_2277	POINT (-120.40047274799991 38.0...)	J Levy Building	06109	645.0	0
Buildings_2278	POINT (-120.40047274799991 38.0...)	Knapp Building	06109	650.0	0
Buildings_2279	POINT (-120.40102824399992 38.0...)	Leavitt and Walker Building	06109	649.0	0
Buildings_2280	POINT (-120.40047274799991 38.0...)	Magedini Building	06109	652.0	0
Buildings_2281	POINT (-120.4015838929999 38.03...)	Masonic Hall	06109	647.0	0
Buildings_2282	POINT (-120.4015838929999 38.03...)	McChesney Building	06109	649.0	0
Buildings_2283	POINT (-120.40102824399992 38.0...)	McCheesney and Mills Building	06109	647.0	0
Buildings_2284	POINT (-120.4021387759999 38.0...)	Mississippi House	06109	641.0	0
Buildings_2285	POINT (-120.3868610319999 38.03...)	Miwok Cultural Center	06109	706.0	0
Buildings_2286	POINT (-120.40047274799991 38.0...)	North Brainard Building	06109	647.0	0
Buildings_2287	POINT (-120.40047274799991 38.0...)	Schwarze Building	06109	651.0	0
Buildings_2288	POINT (-120.40047274799992 38.0...)	Soderer and Marshall Building	06109	646.0	0
Buildings_2289	POINT (-120.40047274799991 38.0...)	South Brainard Building	06109	646.0	0
Buildings_2290	POINT (-120.30606899993 38.0...)	Tuolumne Engine Company Number	06109	649.0	0
Buildings_2291	POINT (-120.2271322699991 38.0...)	Twain Harte Community Center	06109	1124.0	0
Buildings_3134	POINT (-116.96724609699993 33.7...)	Hemet Public Library	06065	488.0	0
Buildings_3321	POINT (-116.88724657999991 32.8...)	Crest Branch San Diego County Libr...	06073	488.0	0

Figure 3-48: The data table query results

The query results are displayed on the map synchronously, as shown in Figure 3-49.




Figure 3-49: The query results are displayed on the map synchronously

In particular, the feature data table interacts with the map. Further, the editing, modification and deletion of feature attribute data can be completed in the data table, and the data can be submitted and saved according to the layer data source type. It supports the Shp vector file type, Geodatabase geographic database type, and GeoServer map server type.

4 Map editing

4.1 Create Shp

In PyramidMap, you can create your own Sh-style vector layer. Users can independently select the feature geometry type, map coordinate system, create layer fields and data types, and create vector layers that fully meet their needs. The design interface is shown in Figure 4-1.




Figure 4-1: Shp layer data structure design

The Shp layer data structure includes three aspects: geometric type, coordinate system, and attribute data. The geometric type indicates the geometric shape of map features, including point (Point/MultiPoint), line (LineString/MultiLineString), and polygon (Polygon/MultiPolygon) types; The coordinate system is responsible for defining and describing the coordinate positions of map features, so as to display them in the correct positions and ranges. At the same time, digital maps not only have spatial data, but also can carry various types of attribute data, which is the unity of spatial and attribute data. PyramidMap covers most commonly used standard coordinate systems at present, including the GCS geographic coordinate system and the PCS projection coordinate system. GCS is responsible for the description of the spatial three-dimensional position, such as WGS84. PCS can understand the projection of the spatial position on the plane, and is responsible for the description of the plane position, such as WGS84 Web Mercator, which is the main coordinate system adopted by the current Web map. PyramidMap realizes the selection of coordinate system through classification list, and provides keyword mode to realize quick query and selection, as shown in Figure 4-2.




Figure 4-2: Fast selection of coordinate system through keywords

For a Shp type layer, it can have field information, including field naming, data type, and so on, like common database tables, to store all common types of data except spatial data, and realize the attribute information description of a map feature. Attribute data types include text, long integer, short integer, floating point type, double precision type and date time type. The creation process is shown in Figure 4-3.




Figure 4-3: Design the field structure of Shp layer table

The created Shp layer is automatically added to the layer resource pool of PyramidMap for unified management, and can be selected from the resource pool list for all-purpose , as shown in Figure 4-4.

No	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCS(SRID)	Counts	State	Check
4	Countries.shp	E:\Maps\gas\countries.shp	From local directory	MultiPolygon	Point	GCS_WGS_1984_EPSG_4326	56	Normal	
5	GoldCoast.shp	E:\Maps\California\GoldCoast.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	537	Normal	
6	Hospitals.shp	E:\Maps\California\Hospitals.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	438	Normal	
7	Lakes.shp	E:\Maps\California\Lakes.shp	From local directory	MultiPolygon	MultiPolygon	GCS_WGS_1984_EPSG_4326	2	Normal	
8	LandmarkAreas.shp	E:\Maps\California\LandmarkAreas.shp	From local directory	MultiPolygon	MultiPolygon	GCS_WGS_1984_EPSG_4326	10467	Normal	
9	MajorRoads.shp	E:\Maps\California\MajorRoads.shp	From local directory	MultiLineString	MultiLineString	GCS_WGS_1984_EPSG_4326	72033	Normal	
10	Rivers.shp	E:\Maps\California\Rivers.shp	From local directory	MultiLineString	MultiLineString	GCS_WGS_1984_EPSG_4326	4	Normal	
11	Schools.shp	E:\Maps\California\Schools.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	11381	Normal	
12	States.shp	E:\Maps\California\States.shp	From local directory	MultiPolygon	MultiPolygon	GCS_WGS_1984_EPSG_4326	1	Normal	
13	UrbanAreas.shp	E:\Maps\California\UrbanAreas.shp	From local directory	MultiPolygon	MultiPolygon	GCS_WGS_1984_EPSG_4326	191	Normal	
14	CAPITAL_POINT.shp	E:\Maps\oraclelayers\CAPITAL_POINT.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	1	missing	
15	CITY.shp	E:\Maps\oraclelayers\CITY.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	208	Normal	
16	CITY_REGION.shp	E:\Maps\oraclelayers\CITY_REGION.shp	From db oracle104	MultiPolygon	MultiPolygon	WGS_84_EPSG_4326	385	missing	
17	COUNTY_POINT.shp	E:\Maps\oraclelayers\COUNTY_POINT.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	2862	missing	
18	COUNTY_REGION.shp	E:\Maps\oraclelayers\COUNTY_REGION.shp	From db oracle104	MultiPolygon	MultiPolygon	WGS_84_EPSG_4326	2918	missing	
19	GAS_CONDENSATE_TANK.shp	E:\Maps\oraclelayers\GAS_CONDENSATE_TANK.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	8	missing	
20	GAS_PIPE.shp	E:\Maps\oraclelayers\GAS_PIPE.shp	From db oracle104	MultiLineString	MultiLineString	WGS_84_EPSG_4326	7946	missing	
21	GAS_PIPE_CAP.shp	E:\Maps\oraclelayers\GAS_PIPE_CAP.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	12290	missing	
22	GAS_PRESSURE_BOX.shp	E:\Maps\oraclelayers\GAS_PRESSURE_BOX.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	30	missing	
23	GAS_PRESSURE_CABINET.shp	E:\Maps\oraclelayers\GAS_PRESSURE_CABINET.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	122	missing	
24	GAS_PRESSURE_STATION.shp	E:\Maps\oraclelayers\GAS_PRESSURE_STATION.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	1	missing	
25	GAS_PROTECTIVE_PIPE.shp	E:\Maps\oraclelayers\GAS_PROTECTIVE_PIPE.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	54	missing	
26	GAS_SERVICING_WELL.shp	E:\Maps\oraclelayers\GAS_SERVICING_WELL.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	2	missing	
27	GAS_VALUE.shp	E:\Maps\oraclelayers\GAS_VALUE.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	1	missing	
28	GAS_VALUE_WELL.shp	E:\Maps\oraclelayers\GAS_VALUE_WELL.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	892	missing	
29	PROVINCE_POINT.shp	E:\Maps\oraclelayers\PROVINCE_POINT.shp	From db oracle104	Point	Point	WGS_84_EPSG_4326	33	missing	
30	PROVINCE_REGION.shp	E:\Maps\oraclelayers\PROVINCE_REGION.shp	From db oracle104	MultiPolygon	MultiPolygon	WGS_84_EPSG_4326	1089	missing	
31	gaspipeline.shp	E:\Maps\gas\gaspipeline.shp	Self-built Shp file	Point	Point	WGS_84_EPSG_4326	0	Normal	
32	capital_point.shp	E:\Maps\OTN\capital_point.shp	From local directory	Point	Point	WGS_84_EPSG_4326	1	Normal	
33	city_point.shp	E:\Maps\OTN\city_point.shp	From local directory	Point	Point	WGS_84_EPSG_4326	310	Normal	
34	city_region.shp	E:\Maps\OTN\city_region.shp	From local directory	MultiPolygon	MultiPolygon	WGS_84_EPSG_4326	373	Normal	
35	county_point.shp	E:\Maps\OTN\county_point.shp	From local directory	Point	Point	WGS_84_EPSG_4326	2862	Normal	
36	country_point.shp	E:\Maps\OTN\country_point.shp	From local directory	MultiPolygon	MultiPolygon	WGS_84_EPSG_4326	2918	Normal	
37	province_point.shp	E:\Maps\OTN\province_point.shp	From local directory	Point	Point	WGS_84_EPSG_4326	53	Normal	
38	province_region.shp	E:\Maps\OTN\province_region.shp	From local directory	MultiPolygon	MultiPolygon	WGS_84_EPSG_4326	1089	Normal	
39	gas_condensate_tank.shp	E:\Maps\gas\gas_condensate_tank.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	8	Normal	
40	gas_pipe.shp	E:\Maps\gas\gas_pipe.shp	From local directory	MultiLineString	MultiLineString	GCS_WGS_1984_EPSG_4326	8062	Normal	
41	gas_pipe_cap.shp	E:\Maps\gas\gas_pipe_cap.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	626	Normal	
42	gas_pressure_box.shp	E:\Maps\gas\gas_pressure_box.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	30	Normal	
43	gas_pressure_cabinet.shp	E:\Maps\gas\gas_pressure_cabinet.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	119	Normal	
44	gas_pressure_station.shp	E:\Maps\gas\gas_pressure_station.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	1	Normal	
45	gas_protective_pipe.shp	E:\Maps\gas\gas_protective_pipe.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	54	Normal	
46	gas_servicing_well.shp	E:\Maps\gas\gas_servicing_well.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	2	Normal	
47	gas_value.shp	E:\Maps\gas\gas_value.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	1	Normal	
48	gas_value_well.shp	E:\Maps\gas\gas_value_well.shp	From local directory	Point	Point	GCS_WGS_1984_EPSG_4326	901	Normal	

Figure 4-4: The created Shp layer is added to the map resource pool

Select a layer in the resource pool list to draw map elements and assign data values, as shown in Figure 4-5.




Figure 4-5: Map feature drawing and data assignment for the created Shp layer

This is the complete workflow of creating a map instance and adding it to the resource management pool, mapping, and adding map data.

4.2 Graphical Editing

Map data consists of geometric shapes representing space vectors and feature attributes data. Therefore, map editing includes two parts, they are graphical editing and attributes data editing.

4.2.1 Main view editor

PyramidMap supports the implementation of mouse dotting, line and polygon drawing, and submitting the saving according to the geometric type of the current layer in the main map view and each independent map view. Support Shp vector file, Geodatabase layer, wfs data in GeoServer and other data types. In the main view interface, activate the editing status of the selected layer through the layer node shortcut menu "Open Editing" option, as shown in Figure 4-6.




Figure 4-6: Layer on editing

Click the "Draw" button in the toolbar, as shown in Figure 4-7.




Figure 4-7: For vector layer editing, the "Draw" button in the toolbar

The selected layer enters the editing state, interacts with the mouse, and implements operations such as dotting, drawing lines, and drawing polygons according to the geometric type of the layer, as shown in Figure 4-8.




Figure 4-8: Drawing feature graphic on map

After drawing, click the "Save" button in the toolbar, as shown in Figure 4-9.



Figure 4-9: For the edited map data, the "Save" button in the toolbar

PyramidMap saves and submits the drawn feature data to the layer data source, and supports Shp vector file, Geodatabase vector layer, and GeoServer WFS layer. After successful saving, the system returns a prompt, as shown in Figure 4-10.




Figure 4-10: Drawing and saving map features

4.2.2 Independent view editor

In the Shp layer resource management and Geodatabase layer resource management modules, the independent display view of each layer can be opened through the "Preview and Edit" button to complete the editing operation function, as shown in Figure 4-11.




Figure 4-11: Layer independent display editing function page

Click the drawing button to realize the interactive drawing of the mouse on the map view. After that, click the "Save" button to update and save the data to the data source corresponding to the layer, Shp to the layer file, and the database layer to the feature table.

4.3 Attribute data editing

PyramidMap implements digital editing of the layer attribute table, which is respectively implemented in the main interface visualization layer node and the preview and editing in the Shp or Geodatabase geographical database layer list.

4.3.1 Editing in main map view

Visualize the "Open shp table" option in the right-click shortcut menu of the layer node on the main interface, as shown in Figure 4-12.




Figure 4-12: Visualize the "Open shp table" in the right-click shortcut menu of the layer node

The opened layer data table is shown in Figure 4-13.

Layer features table

FeatureIdentifier	the_geom	NAME	STCTYFIPS	ELEV_METER	LABEL_FLAG
Schools.1	POINT (-114.29022872399992 34....)	Wallace School	04012	127.0	0
Schools.2	POINT (-114.29578464799994 34....)	Blake School	04012	128.0	1
Schools.3	POINT (-114.2885622529999 34....)	Parker High School	04012	127.0	1
Schools.4	POINT (-114.39106511699993 34....)	Colorado River Day School	04012	106.0	0
Schools.5	POINT (-114.60079793499995 34....)	Mohave Elementary School	04015	148.0	0
Schools.6	POINT (-114.43421162999933 34....)	Poston School	04012	96.0	0
Schools.7	POINT (-120.3860276389999 38....)	Columbia College	06109	699.0	
Schools.8	POINT (-121.7488591999991 39....)	Steinord School	06101	22.0	0
Schools.9	POINT (-123.6202907899995 39....)	Blossom School (historical)	06045	316.0	0
Schools.10	POINT (-123.68418331599992 39....)	Bridgeport School (historical)	06045	90.0	0
Schools.11	POINT (-123.50564383299991 39....)	Hansen School (historical)	06045	340.0	0
Schools.12	POINT (-123.27306528299994 39....)	Hearst School (historical)	06045	530.0	0
Schools.13	POINT (-123.03638923099993 38....)	McDonald School (historical)	06045	268.0	0
Schools.14	POINT (-123.71417699799991 39....)	McKay School (historical)	06045	173.0	0
Schools.15	POINT (-123.7427918489999 39....)	Navarre Ridge School House (histo...	06045	150.0	0
Schools.16	POINT (-123.27889600799995 39....)	Pine Ridge School (historical)	06045	619.0	0
Schools.17	POINT (-123.51973285499992 39....)	Signal School (historical)	06045	403.0	0
Schools.18	POINT (-119.50900786299991 35....)	Semitropic School (historical)	06029	78.0	0
Schools.19	POINT (-121.62356192199991 37....)	Byron Hot Springs School (historical)	06013	13.0	0
Schools.20	POINT (-121.64161851699993 37....)	Excelsior School (historical)	06013	9.0	0
Schools.21	POINT (-121.67773107699992 37....)	Iron House School (historical)	06013	4.0	0
Schools.22	POINT (-121.75050942299993 37....)	Lone Tree School (historical)	06013	41.0	0
Schools.23	POINT (-123.18472672399992 39....)	McTear School (historical)	06045	218.0	0
Schools.24	POINT (-117.43421271499994 33....)	Sherman Indian Institute	06065	245.0	1
Schools.25	POINT (-116.0173680199991 33....)	Star King School	06037	19.0	1
Schools.26	POINT (-119.26733337099989 34....)	Ventura Junior College	06111	37.0	1
Schools.27	POINT (-122.40830432899992 37....)	Academy of Art College	06075	35.0	0
Schools.28	POINT (-122.41385993699993 37....)	Cathedral School for Boys	06075	99.0	1
Schools.29	POINT (-122.40608211699993 37....)	Cogswell College	06075	29.0	0
Schools.30	POINT (-122.4199702299991 37....)	Collegio De La Mission	06075	24.0	0
Schools.31	POINT (-122.40886007899991 37....)	Commodore Stockton School	06075	44.0	1
Schools.32	POINT (-122.43302692899994 37....)	Dental School of the University of th...	06075	66.0	0

Open filter constructor Restore

Save Delete Cancel

Figure 4-13: Edit attribute data in the shp data table

Double click the table Cell (except for the Id and Geometry fields) to switch to the editing and input status, and the selected features are highlighted on the map at the same time, as shown in Figure 4-14.




Figure 4-14: The selected features in the data table are highlighted on the map

Batch modification, submission and saving are supported.

4.3.2 Editing in individual map view

Layers in the Shp resource pool and database resource pool can be previewed and edited in an independent display interface, as shown in Figure 4-15.




Figure 4-15: Open the data table in the independent view of each layer

Click "Open shp table" to open the layer feature data table, as shown in Figure 4-16.

Layer features table

FeatureIdentifier	the_geom	NAME	STATE	FIPS	POPULATION	Shape_Leng	Shape_Area
UrbanAreas_1	MULTIPOLYGON (((124.0...	Arcata	CA	06	16432	0.085162444102	5.09316293137E-4
UrbanAreas_2	MULTIPOLYGON (((124.0...	Crescent City	CA	06	5207	0.11336017569	7.02886583916E-4
UrbanAreas_3	MULTIPOLYGON (((124.1...	Eureka	CA	06	27025	0.237178691593	0.00186189011481
UrbanAreas_4	MULTIPOLYGON (((123.8...	Fort Bragg	CA	06	6078	0.066892726559	2.4830579547E-4
UrbanAreas_5	MULTIPOLYGON (((124.1...	Fortuna	CA	06	10119	0.0921948015015	3.41729353922E-4
UrbanAreas_6	MULTIPOLYGON (((124.1...	McKinleyville	CA	06	11111	0.0941052819447	4.73180787832E-4
UrbanAreas_7	MULTIPOLYGON (((124.0...	Rio Dell	CA	06	3012	0.0718199331669	2.6812860847E-4
UrbanAreas_8	MULTIPOLYGON (((124.1...	Samoan	CA	06	0	0.0457780041008	1.30869858023E-4
UrbanAreas_9	MULTIPOLYGON (((121.0...	Cambria	CA	06	15976	0.0679829958946	3.23808914053E-4
UrbanAreas_10	MULTIPOLYGON (((121.9...	Carmel-by-the-Sea	CA	06	4239	0.0963393277869	4.1441850328E-4
UrbanAreas_11	MULTIPOLYGON (((122.2...	Alameda	CA	06	76459	0.270808674192	0.0020586894133
UrbanAreas_12	MULTIPOLYGON (((121.9...	Concord	CA	06	349025	1.77684091175	0.0222974338136
UrbanAreas_13	MULTIPOLYGON (((121.9...	Dublin	CA	06	23229	0.106006083791	4.61695388742E-4
UrbanAreas_14	MULTIPOLYGON (((121.8...	Komandorski Village	CA	06	50553	0.112939740389	5.07237042344E-4
UrbanAreas_15	MULTIPOLYGON (((122.0...	Oakland	CA	06	920303	1.91205791714	0.0307256708871
UrbanAreas_16	MULTIPOLYGON (((122.4...	San Francisco	CA	06	821112	0.728209282744	0.0110278961393
UrbanAreas_17	MULTIPOLYGON (((122.4...	Sausalito	CA	06	16831	0.131695300207	3.82024802665E-4
UrbanAreas_18	MULTIPOLYGON (((121.9...	Fremont	CA	06	211200	0.595098636365	0.00409017252937
UrbanAreas_19	MULTIPOLYGON (((122.5...	Mill Valley	CA	06	13038	0.138503050577	5.13458202338E-4
UrbanAreas_20	MULTIPOLYGON (((121.9...	Monterey	CA	06	48071	0.206389678759	0.001274777679267
UrbanAreas_24	MULTIPOLYGON (((122.0...	Union City	CA	06	53762	0.128686949979	6.88310104428E-4
UrbanAreas_25	MULTIPOLYGON (((123.0...	Cloverdale	CA	06	16605	0.0346827589552	7.27381994441E-5
UrbanAreas_26	MULTIPOLYGON (((122.0...	Colusa	CA	06	9143	0.0823201962166	3.71281458973E-4
UrbanAreas_27	MULTIPOLYGON (((122.6...	Cotati	CA	06	5714	0.160818989669	9.1063859123E-4
UrbanAreas_28	MULTIPOLYGON (((122.8...	Healdsburg	CA	06	15095	0.0839332264899	4.21364358202E-4
UrbanAreas_29	MULTIPOLYGON (((122.5...	Novato	CA	06	47585	0.224157081923	7.83675058805E-4
UrbanAreas_30	MULTIPOLYGON (((122.6...	Petaluma	CA	06	45797	0.297221561892	0.00194528733243
UrbanAreas_31	MULTIPOLYGON (((122.5...	San Rafael	CA	06	94573	0.72638293613	0.00326767289261
UrbanAreas_21	MULTIPOLYGON (((121.7...	San Jose Metro Area	CA	06	1846132	3.09002064606	0.0684612110638
UrbanAreas_22	MULTIPOLYGON (((121.9...	Sania Cruz	CA	06	67289	0.266640532798	0.00232580809656
UrbanAreas_23	MULTIPOLYGON (((121.8...	Seaside	CA	06	38901	0.140816487534	7.41004929063E-4
UrbanAreas_32	MULTIPOLYGON (((122.6...	Santa Rosa	CA	06	135987	0.27302766776	0.00255214589816

Save Delete Cancel Open filter constructor Restore

Figure 4-16: Edit attribute data in the shp independent view

Double click the table Cell (except for the Id and Geometry fields) to switch to the editing input status, and the selected features will be highlighted on the map view at the same time, as shown in Figure 4-17.




Figure 4-17: Layer feature highlight by being selected in independent view

Batch modification, submission and saving are supported.

5 Geodatabase and GeoServer

5.1 Geodatabase connection pool

PyramidMap supports direct connection access with geographic databases to realize the import, export, storage and conversion of map data, and supports (but is not limited to) Oracle, PostGIS (PostgreSQL+GIS function extension), MySQL, SQLServer and other databases. After PyramidMap creates a database connection, it is managed in the database connection pool mode to import, export, preview, edit and other operations of the map. PyramidMap provides two ways to create a geographic database connection: 1. create a database connection through the map database node on the main map display interface; 2. create a database connection on the database configuration page through "System" - "Geodatabase console" entrance.

5.1.1 Geodatabase data source node

In the geographic database node of the main interface, double-click New Database Connection, as shown in Figure 5-1.




Figure 5-1: Main interface create new Geodatabase connection

Open the geographic database connection configuration interface, select the geographic database type, and enter the correct connection parameters. After the connection test is successful, it can be saved and created as an effective geographic database connection, included in the PyramidMap geographic database resource connection pool, and dynamically added to the geodatabase node and the inside layers node, as shown in Figure 5-2.




Figure 5-2: Geodatabase connection created successfully

Description of interface input parameters:

- GeoDB type: Select a database type (Oracle, PostGIS, MySQL)
- Connection name: Customize the Geodatabase connection name.
- Purpose: Customize the Geodatabase connection purpose describe.
- Host IP: IP address of the server where the Geodatabase is hosted.
- Port: The port number used by the database. (Default port number: Oracle 1521, Postgre 5432, MySQL 3306)
- Database instance: the name of the database's service instance to connect to.

- Schema: The schema to be connected is mainly for PostGIS, and others can be ignored. In Oracle, this parameter is consistent with the user name.
- The connection button: test whether the newly created database connection is valid.
- The save button: save the new database connection.
- The cancel button: Exit the interface without performing any operation.

5.1.2 Geodatabase connection pool

Open the Geodatabase connection pool interface through "System" - "Geodatabase console", or directly click the "GeoDB console" button in the toolbar, as shown in Figure 5-3.



Figure 5-3: Create a Geodatabase connection through the system settings portal

The geodatabase connection configuration page is shown in Figure 5-4.

No	DBConnection	Description	DBType	HostIP	Port	Schema	Instance	Encoding	Status	Test	Editor	Check
1	oracle104		oracle	172.19.126.104	1521	sde	geodata	GBK	Modified unsynced to server	Connect	Do edit	
2	sqlserver166		sql server	172.19.126.166	1433		geodata	GBK	New unsynced to server	Connect	Do edit	
3	sqlserver166A		sql server	172.19.126.166	1433		geodata	GBK	New unsynced to server	Connect	Do edit	
4	postgis104		postgis	127.0.0.1	5432	public	geo_data	GBK	Modified unsynced to server	Connect	Do edit	
5	geoserver1-clite-postgis		postgis	localhost	5432	public	geo_data	GBK	synced from Server	Connect	Do edit	
6	geoserver1-clite-postgis1		postgis	127.0.0.1	5432	public	geo_gas	GBK	synced from Server	Connect	Do edit	
7	geoserver1-clite-postgre1		postgis	127.0.0.1	5432	public	geo_gas	GBK	synced from Server	Connect	Do edit	
8	geoserver1-ohn-ohn_postgis		postgis	127.0.0.1	5432	figer	geo_gas	GBK	synced from Server	Connect	Do edit	
9	geoserver1-ohn-postgis0n		postgis	127.0.0.1	5432	public	geo_data	GBK	synced from Server	Connect	Do edit	
10	sqlserver166b		sql server	172.19.126.166	1433		geodata	GBK	New unsynced to server	Connect	Do edit	
11	sqlserver166c		sql server	172.19.126.166	1433		geodata	GBK	New unsynced to server	Connect	Do edit	
12	mysql104		mysql	127.0.0.1	3306		geodata	GBK	Modified unsynced to server	Connect	Do edit	
13	sqlserver1		sql server	127.0.0.1	1433		geodata	GBK	New unsynced to server	Connect	Do edit	
14	geoserver2-l691-l6911		postgis	172.19.128.104	5432		geo_data	GBK	synced from Server	Connect	Do edit	
15	oracle104A		oracle	172.19.126.104	1521	sde	geodata	GBK	New unsynced to server	Connect	Do edit	

Add database connection:

GeoDB Type: postgis Connection name: postgis-local Purpose: The local postgis map data
Host ip: 127.0.0.1 Host port: 5432 Database instance: geo_data
Database account: postgres Password:
Please confirm with the database administrator:
Connect Save Cancel

Modal dialog box: Tips
Geodatabase connection succeeded 确定

Figure 5-4: Geodatabase Connection Configuration and pool

The connections in the pool can be retested, edited and deleted, as shown in Figure 5-5.




Figure 5-5: The connections in the pool can be retested, edited and deleted

Use the connection pool list to test, edit, modify, and delete the Geodatabase connection. Each connection has two button options : Connect and Do Edit.

.Connect: test whether the database connection is successful.

.Do edit: Re edit the Geodatabase connection to make it available.

5.2 GeoServer connection pool

PyramidMap supports direct connection access with GeoServer, realizes multi type layer publishing function, and provides layer service interface for WebGIS. After the connection parameters are configured and tested successfully, create and maintain the GeoServer resource connection pool. PyramidMap provides two ways to create a GeoServer connection: 1. Through the GeoServer tree node on the main interface; 2. Implement it on the GeoServer connection configuration module through "System" - "GeoServer console".

5.2.1 GeoServer data node

In the GeoServer connection node of the main interface, double-click Add GeoServer Connection, as shown in Figure 5-6.




Figure 5-6: Create GeoServer connection through double-clicking on the GeoServer node in the main interface

Open the GeoServer connection configuration interface, enter the correct connection parameters, after the connection testing successful, you can save and create a valid GeoServer connection and hosting the connection in resource pool, and dynamically add it to the GeoServer connection node. Description of interface input parameters:

- GeoServer name: Customize the GeoServer server connection naming.
- Description: Customize the GeoServer connection purpose describe.
- Host IP: IP address of the server where the GeoServer is hosted.
- Port: GeoServer port number. (The port number of the web server hosting GeoServer, such as Tomcat)
- GeoServer account: GeoServer administrator account, default admin, please contact the web administrator for confirmation.
- Password: GeoServer administrator password, please contact the web administrator for confirmation.
- GeoServer web name: The deployment name of GeoServer in the web service. The default is geoserver. Please contact the web administrator for confirmation.

5.2.2 GeoServer connection pool

Open the GeoServer connection pool management interface through "System" - "GeoServer console", or directly click the "GeoServer console" button in the toolbar, as shown in Figure 5-7.



Figure 5-7: Create GeoServer connection menu

In the GeoServer connection pool management interface, create a new GeoServer connection and incorporate it into the unified resource management pool. The workflow is shown in Figure 5-8.




Figure 5-8: Create GeoServer connection and connections pool

The GeoServer connection created successfully is added to the resource connection pool.

5.2.3 Manage GeoServer connections

PyramidMap maintain the GeoServer connections in resource pool, manage the server internal workspace, data storage and layers in the function

modules, as shown in Figure 5-9.




Figure 5-9: Internal management of GeoServer

GeoServer internal management identify:

- Try connect: test whether the selected map server connection is available.
- Open Connection editor: Edit the selected GeoServer connection properties.

- Sync from GeoServer: obtain the selected GeoServer workspace, data storage and database connection properties data, and synchronizing them to the client.
- Open space console: query, edit and modify, delete the workspace and data storage of the selected GeoServer.
- GeoServer layer preview: get the list of selected GeoServer layers and preview them.
- Delete connection: Delete the selected GeoServer connection.

5.3 GeoServer internal operate

The internal space of GeoServer is divided into three levels: workspaces, data storages and layers. As the client of GeoServer, PyramidMap can visually maintain these modules. PyramidMap provides multiple forms of access management to GeoServer server space.

5.3.1 GeoServer Workspace

Through the GeoServer node tree in the main interface, you can right-click on the GeoServer node layer and the workspace node layer to provide management access to the workspace and data storage. The management entry of the GeoServer node to the workspace is shown in Figure 5-10.




Figure 5-10: GeoServer node entrance to workspace

Enter the workspace management module, as shown in Figure 5-11.

WorkSpace	NameSpace	wms	wfs	wcs	wmts	GeoServerConnection	SynchState	Check	OpenEditor	Delete
cite	http://www.opengeospatial.net/cite	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
tiger	http://www.census.gov	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
nurc	http://www.nurc.nato.int	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
sde	http://geoserver.sf.net	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
it.geosolutions	http://www.geo-solutions.it	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
topp	http://www.openplans.org/topp	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
sf	http://www.openplans.org/spearfish	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
digi_gas	http://www.digi_gas.com	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
oth	http://www.oth.com	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete

Figure 5-11: The GeoServer's workspaces pool manage interface

In the workspace module, you can perform the following operations: create a new workspace, synchronize the server workspace to the client, and submit the client workspace to the server. In particular, in the workspace list management pool, you can provide independent attribute editors and delete each workspace in the list table. The new workspace interface and and data interaction with GeoServer is shown in Figure 5-12.




Figure 5-12: The new workspace interface and and data interaction with GeoServer

The new workspace will be automatically attached to the GeoServer node.

5.3.2 GeoServer data storage

In the workspace node, a data storage entry is provided, as shown in Figure 5-13.




Figure 5-13: Workspace node to data storage management entrance

Then enter the data storage management module, as shown in Figure 5-14.




Figure 5-14: The data storage pool interface from the workspace node

In the data storage module, you can perform the following operations: create a new data storage, synchronize the server side data storage to the client, and submit the client side data storage cache to the server. In particular, in the data storage list management pool, you can provide independent editing and deletion operations for each data storage, as shown in Figure 5-15.




figure5-15: Data storage management pool of GeoServer workspace

In the New Data Storage module. You can select the database type corresponding to the data storage, and select the geodatabase connection that matches the type to automatically bring in the configuration of database connection parameters. The selected database connection can be dynamically edited, as shown in Figure 5-16.




Figure 5-16: Edit the database connection for the datastorage

The predefined geodatabase connection serves as an independent resource management pool to provide data sources for GeoServer data storage.

5.3.3 GeoServer pool console

PyramidMap centrally manages GeoServer connections in the form of resource management pools, as shown in Figure 5-17.



Figure 5-17: GeoServer connections resource management pool entrance

PyramidMap creates and maintains the GeoServer resource connection pool, and manages and maintains its internal service space for each GeoServer connection. The module is shown in Figure 5-18.

A screenshot of the 'GeoServer Space' module in PyramidMap. It displays a table of current connections. The columns are: No, GeoServerName, Description, HostIP, Port, WebName, WebUrl, and Check. There are four entries: 1. geoserver1 (HostIP: 127.0.0.1, Port: 8080, WebName: geoserver, WebUrl: http://127.0.0.1:8080/geoserver, checked). 2. geoserver2 (HostIP: 127.0.0.1, Port: 8080, WebName: dhcgisserver, WebUrl: http://127.0.0.1:8080/dhcgisserver). 3. geoserver3 (HostIP: 172.19.126.233, Port: 8080, WebName: geoserver, WebUrl: http://172.19.126.233:8080/geoserver). 4. geoserver100 (HostIP: 192.168.31.100, Port: 8080, WebName: geoserver, WebUrl: http://192.168.31.100:8080/geoserver). Below the table is a form for adding a new connection. It includes fields for 'GeoServer name', 'Host ip', 'GeoServer account', 'Description', 'Host port', 'Password', and 'GeoServer web name'. Buttons at the bottom include 'Try Connect', 'Open connection editor', 'Sync from GeoServer', 'Open space console' (which is highlighted with a red box), 'GeoServer layer preview', 'Open web console', 'Delete connection', 'Connect', 'Save', and 'Cancel'. A status bar at the bottom right shows '0%'.

图5-18: GeoServer connections pool and operation options

Select the GeoServer and click "open space console" button, as shown in Figure 5-19.

WorkSpace	NameSpace	wms	wfs	wcs	wmts	GeoServerConnection	SynchState	Check	OpenEditor	Delete
cite	http://www.opengeospatial.net/cite	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input checked="" type="radio"/>	Do edit	Delete
tiger	http://www.census.gov	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
nurc	http://www.nurc.nato.int	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
sde	http://geoserver.sfr.net	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
it.geosolutions	http://www.geo-solutions.it	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
topp	http://www.openplans.org/topp	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
sf	http://www.openplans.org/spearfish	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
otn	http://www.otn.com	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced to server	<input type="radio"/>	Do edit	Delete
test	http://www.test.com	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	New unsynced to server	<input type="radio"/>	Do edit	Delete

DataStorage	WorkSpace	DBType	DBConnection	Description	SynchState	Check	Connect	OpenEditor	LayersList	Delete
city_region	cite	shapefile			synced from Server	<input type="checkbox"/>	Connect	Do edit	Layers	Delete
county_point	cite	shapefile			synced from Server	<input type="checkbox"/>	Connect	Do edit	Layers	Delete
county_region	cite	shapefile			synced from Server	<input type="checkbox"/>	Connect	Do edit	Layers	Delete
province_point	cite	shapefile			synced from Server	<input type="checkbox"/>	Connect	Do edit	Layers	Delete
capital_point	cite	shapefile			synced to server	<input type="checkbox"/>	Connect	Do edit	Layers	Delete

Figure 5-19: GeoServer workspace and data storage managing pool

The GeoServer workspace and data storage managing pool module displays the list of all workspaces of the server and the data storages list of each workspace. The client side and the server side maintain two-way synchronization to achieve visual management of the server side data by the client side.

In particular, PyramidMap implements a client cache maintenance mechanism for GeoServer. New and modified workspaces and data stores are temporarily stored on the client. When necessary, they are submitted to the GeoServer server in batches. At the same time, the GeoServer server data can be synchronized to the client at any time. This is the two-way synchronization mechanism between PyramidMap and GeoServer.

6 Map data and conversion

PyramidMap supports five types of map data sources, namely Shp file vector layer, file image layer, Geodatabase vector layer, GeoServer vector layer and raster tile layer.

6.1 Vector layers pool

PyramidMap imports the client's Shp file vector layers into the resource pool through a file browser to form a Shp management list pool and supports various operations with corresponding buttons, as shown in Figure 6-1.

The screenshot shows the PyramidMap interface with a central table listing various Shp files. The columns include: No., LayerFileName, LayerFilePath, Remarks, FeatureType, LayerType, UCS(SRID), Encoding, Status, and Check. Most layers are categorized under 'gas' and are included in program management. The table spans multiple rows and columns, with a watermark 'PyramidMap' diagonally across the center.

No	LayerFileName	LayerFilePath	Remarks	FeatureType	LayerType	UCS(SRID)	Encoding	Status	Check
1	gas_condensate_tank.shp	E:\Maps\gaspipe_shp\3857\gas_condensate_tank.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP_	ISO-8859-1	Local hosting	<input type="checkbox"/>	
2	gas_pipe.shp	E:\Maps\gaspipe_shp\3857\gas_pipe.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP_	ISO-8859-1	Local hosting	<input type="checkbox"/>	
3	gas_pipe_cap.shp	E:\Maps\gaspipe_shp\3857\gas_pipe_cap.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP_	ISO-8859-1	Local hosting	<input type="checkbox"/>	
4	gas_pressure_box.shp	E:\Maps\gaspipe_shp\3857\gas_pressure_box.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP_	ISO-8859-1	Local hosting	<input type="checkbox"/>	
5	gas_pressure_cabinet.shp	E:\Maps\gaspipe_shp\3857\gas_pressure_cabinet.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP_	ISO-8859-1	Local hosting	<input type="checkbox"/>	
6	gas_pressure_station.shp	E:\Maps\gaspipe_shp\3857\gas_pressure_station.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP_	ISO-8859-1	Local hosting	<input type="checkbox"/>	
7	gas_protective_pile.shp	E:\Maps\gaspipe_shp\3857\gas_protective_pile.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP_	ISO-8859-1	Local hosting	<input type="checkbox"/>	
8	gas_servicing_well.shp	E:\Maps\gaspipe_shp\3857\gas_servicing_well.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP_	ISO-8859-1	Local hosting	<input type="checkbox"/>	
9	gas_valve.shp	E:\Maps\gaspipe_shp\3857\gas_valve.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP_	ISO-8859-1	Local hosting	<input type="checkbox"/>	
10	gas_valve_well.shp	E:\Maps\gaspipe_shp\3857\gas_valve_well.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP_	ISO-8859-1	Local hosting	<input type="checkbox"/>	
11	geodetic_point.shp	E:\Maps\OTN\geodetic_point.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
12	city_point.shp	E:\Maps\OTN\city_point.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
13	city_region.shp	E:\Maps\OTN\city_region.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
14	county_point.shp	E:\Maps\OTN\county_point.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
15	county_region.shp	E:\Maps\OTN\county_region.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
16	province_point.shp	E:\Maps\OTN\province_point.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
17	province_region.shp	E:\Maps\OTN\province_region.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
18	gas_condensate_tank.shp	E:\Maps\gaspipe_shp\gas_condensate_tank.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
19	gas_pipe.shp	E:\Maps\gaspipe_shp\gas_pipe.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
20	gas_pipe_cap.shp	E:\Maps\gaspipe_shp\gas_pipe_cap.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
21	gas_pressure_box.shp	E:\Maps\gaspipe_shp\gas_pressure_box.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
22	gas_pressure_cabinet.shp	E:\Maps\gaspipe_shp\gas_pressure_cabinet.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
23	gas_pressure_station.shp	E:\Maps\gaspipe_shp\gas_pressure_station.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
24	gas_protective_pile.shp	E:\Maps\gaspipe_shp\gas_protective_pile.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
25	gas_servicing_well.shp	E:\Maps\gaspipe_shp\gas_servicing_well.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
26	gas_valve.shp	E:\Maps\gaspipe_shp\gas_valve.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
27	gas_valve_well.shp	E:\Maps\gaspipe_shp\gas_valve_well.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
28	Buildings.shp	E:\Maps\California\Buildings.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
29	Cemefries.shp	E:\Maps\California\Cemefries.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
30	Churches.shp	E:\Maps\California\Churches.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
31	Counties.shp	E:\Maps\California\Counties.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
32	GolfCourses.shp	E:\Maps\California\GolfCourses.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
33	Hospitals.shp	E:\Maps\California\Hospitals.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
34	Lakes.shp	E:\Maps\California\Lakes.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
35	MajorRoads.shp	E:\Maps\California\MajorRoads.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
36	MajorRoads.shp	E:\Maps\California\MajorRoads.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
37	Rivers.shp	E:\Maps\California\Rivers.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
38	Schools.shp	E:\Maps\California\Schools.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
39	States.shp	E:\Maps\California\States.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
40	UrbanAreas.shp	E:\Maps\California\UrbanAreas.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	

Figure 6-1: Shp layers resource pool

The vector layers pool displays information of every layer in a list format, including:

- Layer name.
- Layer file path.
- Data source types, including: local files, database layers, and GeoServer layers.
- Geometric indicate: Indicate the geometric type of the feature using an icon.
- Geometric type, include: Point/MultiPoint, LineString/MultiLineString, Polygon/MultiPolygon.
- Coordinate System (SRID): The definition of the coordinate system for a layer, including the coordinate system code.
- Data volume: The number of features in a layer.
- Status: The existence status of the current layer resource.

The experimental data used in the example is available in PyramidMap for [download](#).

6.1.1 Layer preview

Through the map preview and editing options, the selected layer file will be opened in a separate map view to achieve layer preview and editing, as shown in Figure 6-2.




Figure 6-2: Open independent preview and editing view of single shp vector layer

Independent map view provides each layer with separate display, rendering, base map selection and overlay, graphical editing, attribute data editing in table, feature selection and deletion operations. It is a comprehensive map service for a single layer.

6.1.2 Data processing

Pyramidmap manages and operates layers uniformly through resource pooling, including layer resource import, layer preview, coordinate system conversion, spatial processing, layer slicing, layer data export, and other operations. As shown in Figure 6-3.

PyramidMap Geotools Visualized Toolset-Local vector layer resource console

File MapData Geodatabase GeoServer System Help

Main View Styles Console Shp Factory Shp Conversion Map Pool GeoDB Console GeoDB Data GeoServer Pool GeoServer Space Map Publish GeoServer Layers GeoServer View

No.	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCS(SRID)	Counts	State	Check
1	Buildings.shp	D:\maps\California3857\Buildings.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG:3857	4361	Normal	<input checked="" type="checkbox"/>	
2	Cemeteries.shp	D:\maps\California3857\Cemeteries.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG:3857	842	Normal	<input checked="" type="checkbox"/>	
3	Churches.shp	D:\maps\California3857\Churches.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG:3857	183613	Normal	<input checked="" type="checkbox"/>	
4	Cities.shp	D:\maps\California3857\Cities.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	56	Normal	<input checked="" type="checkbox"/>	
5	GolfCourses.shp	D:\maps\California3857\GolfCourses.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG:3857	537	Normal	<input checked="" type="checkbox"/>	
6	Hospitals.shp	D:\maps\California3857\Hospitals.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG:3857	438	Normal	<input checked="" type="checkbox"/>	
7	Lakes.shp	D:\maps\California3857\Lakes.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	2	Normal	<input checked="" type="checkbox"/>	
8	LandmarkAreas.shp	D:\maps\California3857\LandmarkAreas.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	10467	Normal	<input checked="" type="checkbox"/>	
9	MajorRoads.shp	D:\maps\California3857\MajorRoads.shp	From local directory	MultilineString	WGS 84 / Pseudo-Mercator EPSG:3857	72033	Normal	<input checked="" type="checkbox"/>	
10	Rivers.shp	D:\maps\California3857\Rivers.shp	From local directory	MultilineString	WGS 84 / Pseudo-Mercator EPSG:3857	4	Normal	<input checked="" type="checkbox"/>	
11	Schools.shp	D:\maps\California3857\Schools.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG:3857	11381	Normal	<input checked="" type="checkbox"/>	
12	States.shp	D:\maps\California3857\States.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	1	Normal	<input checked="" type="checkbox"/>	
13	UrbanAreas.shp	D:\maps\California3857\UrbanAreas.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	181	Normal	<input checked="" type="checkbox"/>	
14	Buildings.shp	D:\maps\China3857\Buildings.shp	From local directory	Point	GCS_WGS_1984_EPSG:4326	4361	Normal	<input checked="" type="checkbox"/>	
15	Cemeteries.shp	D:\maps\China3857\Cemeteries.shp	From local directory	Point	GCS_WGS_1984_EPSG:4326	842	Normal	<input checked="" type="checkbox"/>	
16	Churches.shp	D:\maps\China3857\Churches.shp	From local directory	Point	GCS_WGS_1984_EPSG:4326	183813	Normal	<input checked="" type="checkbox"/>	
17	Cities.shp	D:\maps\China3857\Cities.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG:4326	58	Normal	<input checked="" type="checkbox"/>	
18	GolfCourses.shp	D:\maps\China3857\GolfCourses.shp	From local directory	Point	GCS_WGS_1984_EPSG:4326	537	Normal	<input checked="" type="checkbox"/>	
19	Hospitals.shp	D:\maps\China3857\Hospitals.shp	From local directory	Point	GCS_WGS_1984_EPSG:4326	438	Normal	<input checked="" type="checkbox"/>	
20	Lakes.shp	D:\maps\China3857\Lakes.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG:4326	2	Normal	<input checked="" type="checkbox"/>	
21	LandmarkAreas.shp	D:\maps\China3857\LandmarkAreas.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG:4326	10467	Normal	<input checked="" type="checkbox"/>	
22	MajorRoads.shp	D:\maps\China3857\MajorRoads.shp	From local directory	MultilineString	GCS_WGS_1984_EPSG:4326	72033	Normal	<input checked="" type="checkbox"/>	
23	Rivers.shp	D:\maps\China3857\Rivers.shp	From local directory	MultilineString	GCS_WGS_1984_EPSG:4326	4	Normal	<input checked="" type="checkbox"/>	
24	Schools.shp	D:\maps\China3857\Schools.shp	From local directory	Point	GCS_WGS_1984_EPSG:4326	11381	Normal	<input checked="" type="checkbox"/>	
25	States.shp	D:\maps\China3857\States.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG:4326	1	Normal	<input checked="" type="checkbox"/>	
26	UrbanAreas.shp	D:\maps\China3857\UrbanAreas.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG:4326	191	Normal	<input checked="" type="checkbox"/>	
27	binzhou.shp	D:\maps\Shandong\Binzhou.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	7	Normal	<input checked="" type="checkbox"/>	
28	deshou.shp	D:\maps\Shandong\Deshou.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	11	Normal	<input checked="" type="checkbox"/>	
29	dongying.shp	D:\maps\Shandong\Nedongying.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	5	Normal	<input checked="" type="checkbox"/>	
30	heze.shp	D:\maps\Shandong\Nheze.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	9	Normal	<input checked="" type="checkbox"/>	
31	jinan.shp	D:\maps\Shandong\Njinan.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	12	Normal	<input checked="" type="checkbox"/>	
32	jining.shp	D:\maps\Shandong\Njining.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	11	Normal	<input checked="" type="checkbox"/>	
33	liaocheng.shp	D:\maps\Shandong\Nliaocheng.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	8	Normal	<input checked="" type="checkbox"/>	
34	linyi.shp	D:\maps\Shandong\Nyinyi.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	12	Normal	<input checked="" type="checkbox"/>	
35	qingdao.shp	D:\maps\Shandong\Nqingdao.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	10	Normal	<input checked="" type="checkbox"/>	
36	rizhao.shp	D:\maps\Shandong\Nrizhao.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	4	Normal	<input checked="" type="checkbox"/>	
37	taian.shp	D:\maps\Shandong\Ntaian.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	6	Normal	<input checked="" type="checkbox"/>	
38	weifang.shp	D:\maps\Shandong\Nweifang.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	12	Normal	<input checked="" type="checkbox"/>	
39	weihsia.shp	D:\maps\Shandong\Nweihsia.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	4	Normal	<input checked="" type="checkbox"/>	
40	yantai.shp	D:\maps\Shandong\Nyantai.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	11	Normal	<input checked="" type="checkbox"/>	
41	zaozhuang.shp	D:\maps\Shandong\Nzaozhuang.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	8	Normal	<input checked="" type="checkbox"/>	
42	zibo.shp	D:\maps\Shandong\Nzibo.shp	From local directory	Multipolygon	WGS 84 EPSG:4326	8	Normal	<input checked="" type="checkbox"/>	

Import vector layers Map preview and editing Layer statistics CRS Conversion Spatial processing Layer tile Export out Kml Export out Csv Export out GeoJson Delete Check all

Keep the same coordinate system and without attribute data
Keep the same coordinate system and select attribute data
Convert coordinate system and without attribute data
Convert coordinate system and select attribute data

Figure 6-3: Data Processing Options for the vector layers pool

Support various operations on vector layers, including:

- Import vectorlayers: import client Shp files and Geojson files into the resource management pool.
- Map preview and editing: preview and edit the Shp layer in independent view of each layer in the list pool.
- Layer data statistics: perform the features data statistics of the shp layer in the list pool.
- Coordinate system conversion: perform coordinate system conversion on the shp layer in the list pool.
- Spatial processing: perform spatial processing on shp layers in the list pool, including merging and intersection.
- Build layer tile: For vector layers, TMS standard tiles, XYZ standard tiles, MVT standard tiles, and MBTiles standard tiles are generated according to the preset tile format scale level.
- Data conversion: Shp to Kml, Shp to Csv, Shp to GeoJson.
- Delete: Delete the shp layer in the list pool.

PyramidMap vector layer data processing covers coordinate system conversion, layer slicing, Shp and other heterogeneous spatial data, including mutual conversion between kml, csv, and Geojson. Technical details and examples will be explained in detail in [6.6 Coordinate System Conversion], [6.7 Data Conversion], and [6.8 Map tile].

6.2 Raster layers pool

PyramidMap imports raster image layers of client file types into the raster resource pool through a file browser to form an raster file management list, which supports various operations with corresponding buttons, as shown in Figure 6-4.

No.	LayerFileName	LayerFilePath	Nodata Value	LayerType	Size(byte)	UCS(SRID)	Bands	PixelDepth	DataSources	State	Check
1	320205.tif	D:\maps\raster\3857\320205.tif	0.0	栅格	6223100	WGS 84 / Pseudo-Mercator EPSG 3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
2	Sentinel-2_L2A_False_col.tif	D:\maps\raster\3857\Sentinel-2_L2A_False_color.tif	0.0	栅格	8979080	WGS 84 / Pseudo-Mercator EPSG 3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
3	Sentinel-2_L2A_NDSI.tif	D:\maps\raster\3857\Sentinel-2_L2A_NDSI.tif	0.0	栅格	9459144	WGS 84 / Pseudo-Mercator EPSG 3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
4	Sentinel-2_L2A_Slope.tif	D:\maps\raster\3857\Sentinel-2_L2A_Slope.tif	0.0	栅格	9459144	WGS 84 / Pseudo-Mercator EPSG 3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
5	Sentinel-2_L2A_Scene_cl.tif	D:\maps\raster\3857\Sentinel-2_L2A_Scene_classification.tif	0.0	栅格	9459144	WGS 84 / Pseudo-Mercator EPSG 3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
6	marfen_suitablehabitab.tif	D:\maps\raster\AmericanPacificMarfen\marfen_suitablehab.tif	255.0	栅格	8535561	NAD83 / California Albers EPSG:33101	3	8-bit	From local directory	normal	<input type="checkbox"/>
7	marfen_suitablehabitab_30.tif	D:\maps\raster\AmericanPacificMarfen\marfen_suitablehab_30.tif	-3.402823060737...	栅格	479265	NAD83 / California Albers EPSG:33101	42-bit	From local directory	normal	<input type="checkbox"/>	
8	marfen_suitablehabitab_30.tif	D:\maps\raster\AmericanPacificMarfen\marfen_suitablehab_30.tif	-3.402823060737...	栅格	516635	NAD83 / California Albers EPSG:33101	42-bit	From local directory	normal	<input type="checkbox"/>	
9	marfen_suitablehabitab_30.tif	D:\maps\raster\AmericanPacificMarfen\marfen_suitablehab_30.tif	无	栅格	35349751	NAD83 / California Albers EPSG:33101	42-bit	From local directory	normal	<input type="checkbox"/>	
10	320205_3857.tif	D:\maps\raster\320205_3857.tif	0.0	栅格	6233075	WGS 84 / Pseudo-Mercator EPSG 3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
11	Sentinel-2_L2A_False_col.tif	D:\maps\raster\Sentinel-2_L2A_False_color.tif	无	栅格	8143417	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
12	Sentinel-2_L2A_NDSI.tif	D:\maps\raster\Sentinel-2_L2A_NDSI.tif	无	栅格	7396193	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
13	Sentinel-2_L2A_SWIR.tif	D:\maps\raster\Sentinel-2_L2A_SWIR.tif	无	栅格	8828267	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
14	Sentinel-2_L2A_Scene_cl.tif	D:\maps\raster\Sentinel-2_L2A_Scene_classification_map.tif	无	栅格	892081	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
15	hengxu.tif	D:\maps\raster\hengxu.tif	无	栅格	177386220	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>

Figure 6-4: Raster layers pool

The grid layer resource pool displays layer information for unified resource management in a list format, including:

- Layer name.

- Layer file path.
- NoData value: NoData indicates whether the pixel position information in the grid is available. If a pixel position information is not available, that position will be designated as NoData. Please note that NoData is different from 0, which is a valid numerical value.
- Layer Type: Display the grid layer type in icon mode.
- Size: The data size of the raster layer.
- Coordinate System (SRID): The definition of the coordinate system for a layer, including the coordinate system code.
- Band number: The number of bands in the raster layer.
- Pixel bit depth: The bit depth (pixel depth) of a pixel determines the range of values that a particular raster file can store, which is based on the formula 2^n (where n is the bit depth). For example, an 8-bit raster can have 256 unique values that range from 0 to 255.
- Data source types, including: local grid layer, database export layer, and GeoServer export layer.
- Status: The existence status of the current layer resource.

6.2.1 Layer preview

Through the map preview and editing options, the selected layer file will be opened in a separate map view to achieve layer preview and editing, as shown in Figure 6-5.




Figure 6-5: Map preview of the raster layer

The independent view provides separate display, rendering, and overlay for each layer, and is a comprehensive map service window for a single layer.

6.2.2 Data processing

Pyramidmap manages and operates layers uniformly through resource pooling, including layer resource import, layer preview, coordinate system conversion, spatial processing, layer tile, layer data export, and other operations. As shown in Figures 6-6.

PyramidMap GeoTools Visualized Toolset-Local raster layer resource console

The screenshot shows a software interface for managing raster layers. At the top, there's a menu bar with File, MapData, Geodatabase, GeoServer, System, Help, and several tool icons. Below the menu is a toolbar with buttons for Main View, Styles Console, Shp Factory, Shp Conversion, Map Pool, GeoDB Console, GeoDB data, GeoServer Pool, GeoServer Space, Map Publish, GeoServer Layers, and GeoServer View. A large central area displays a table of raster layers with columns for No., LayerFileName, LayerFilePath, Nodata Value, LayerType, Size(byte), UTM(SRID), Bands, PixelDepth, DataSources, State, and Check. The table contains 15 entries, mostly Sentinel-2 L2A layers. Below the table is a red-bordered section containing buttons for Import raster layers, Map preview and editing, Raster process, Layer tile, Delete, and a checkbox for Check all. The 'Raster process' button is expanded to show options: Raster Compress, Raster Slice, Raster Merge, noData Handle, and CRS Transform.

No.	LayerFileName	LayerFilePath	Nodata Value	LayerType	Size(byte)	UTM(SRID)	Bands	PixelDepth	DataSources	State	Check
1	320205.tif	D:\maps\raster\3857\320205.tif	0.0	栅格	6223100	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	从本地目录	正常	<input type="checkbox"/>
2	Sentinel-2_L2A_False_color.tif	D:\maps\raster\3857\Sentinel-2_L2A_False_color.tif	0.0	栅格	8979080	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	从本地目录	正常	<input type="checkbox"/>
3	Sentinel-2_L2A_NDSI.tif	D:\maps\raster\3857\Sentinel-2_L2A_NDSI.tif	0.0	栅格	9459144	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	从本地目录	正常	<input type="checkbox"/>
4	Sentinel-2_L2A_SWIR.tif	D:\maps\raster\3857\Sentinel-2_L2A_SWIR.tif	0.0	栅格	9459144	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	从本地目录	正常	<input type="checkbox"/>
5	Sentinel-2_L2A_Scene_cl.tif	D:\maps\raster\3857\Sentinel-2_L2A_Scene_classification.tif	0.0	栅格	9459144	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	从本地目录	正常	<input type="checkbox"/>
6	martern_suitability.tif	D:\maps\raster\AmericanPacificMartern\martern_suitability.tif	255.0	栅格	8535561	NAD83 / California Albers EPSG:3310	1	8-bit	从本地目录	正常	<input type="checkbox"/>
7	martern_suitability.tif	D:\maps\raster\AmericanPacificMartern\martern_suitability.tif	-3.402823060737...	栅格	479286	NAD83 / California Albers EPSG:3310	1	42-bit	从本地目录	正常	<input type="checkbox"/>
8	martern_suitability.tif	D:\maps\raster\AmericanPacificMartern\martern_suitability.tif	-3.402823060737...	栅格	8535561	NAD83 / California Albers EPSG:3310	1	42-bit	从本地目录	正常	<input type="checkbox"/>
9	martern_suitability.tif	D:\maps\raster\AmericanPacificMartern\martern_suitability.tif	无	栅格	35230751	NAD83 / California Albers EPSG:3310	1	42-bit	从本地目录	正常	<input type="checkbox"/>
10	320205_3857.tif	D:\maps\raster\320205_3857.tif	0.0	栅格	6233075	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	从本地目录	正常	<input type="checkbox"/>
11	Sentinel-2_L2A_False_color.tif	D:\maps\raster\Sentinel-2_L2A_False_color.tif	无	栅格	8143417	WGS 84 EPSG:4326	3	8-bit	从本地目录	正常	<input type="checkbox"/>
12	Sentinel-2_L2A_NDSI.tif	D:\maps\raster\Sentinel-2_L2A_NDSI.tif	无	栅格	7396193	WGS 84 EPSG:4326	3	8-bit	从本地目录	正常	<input type="checkbox"/>
13	Sentinel-2_L2A_SWIR.tif	D:\maps\raster\Sentinel-2_L2A_SWIR.tif	无	栅格	8828267	WGS 84 EPSG:4326	3	8-bit	从本地目录	正常	<input type="checkbox"/>
14	Sentinel-2_L2A_Scene_cl.tif	D:\maps\raster\Sentinel-2_L2A_Scene_classification.tif	无	栅格	892081	WGS 84 EPSG:4326	3	8-bit	从本地目录	正常	<input type="checkbox"/>
15	hengxu.tif	D:\maps\raster\hengxu.tif	无	栅格	177386220	WGS 84 EPSG:4326	3	8-bit	从本地目录	正常	<input type="checkbox"/>

Figure 6-6: Grid Layer Resource Pool Data Processing Options

Support various operations on raster layer resources pool, including:

- Import raster Layer: import the client raster layer file into the resource management pool.
- Map preview and editing: preview and edit the raster layers in the list pool.
- Raster compression: Compress the raster layers according to the specified compression scheme.
- Raster slice: This is a process that reverses with the raster Mosaic, divide a whole image into multiple slice images according to rules.
- Raster merge: A mosaic combines multiple raster images to obtain a seamless raster.
- Deal noData: process the invalid value of noData for the raster layer in the list pool, mainly to remove the black background and other invalid pixels of the image.
- Coordinate system conversion: perform coordinate system conversion on raster layers in the list pool.
- Build layer tile:: Generate TMS standard tiles, XYZ standard tiles, and MBTiles standard tiles according to the preset tile format scale level for raster.
- Delete: Delete the raster layer in the list pool.

6.2.3 Raster compress

The main advantage of image compression is that the compressed data requires less storage space, and because less information is transmitted, it accelerates the display of the data. The PyramidMap image compression interface is shown in Figures 6-7.




Figure 6-7: Performing raster Compression

PyramidMap supports configuring the same compression strategy for batch data, achieving one click completion. PyramidMap configures image compression strategies through parameters:

- **Compression depth:** By compressing the pixel depth of the original image to 8 bits, the maximum compression ratio can be achieved, but at the cost of reducing the image color scale, grayscale, and image quality. The original pixel depth can be retained.
- **Compression method:** The data compression method can be lossy compression (JPEG/JPEG 2000, WEBP) or lossless compression (LZW, PackBits, and DEFLATE). Lossless compression means that the pixel values in the raster dataset will not change or be lost. If the pixel values of the raster dataset will be used for analyzing or deriving other data products, lossless compression or no compression should be chosen. The amount of compression depends on the data and compression quality. The more similar data, the higher the compression ratio. The lower the compression quality, the higher the compression ratio. Compared to lossless compression, lossy compression usually produces a higher compression ratio.
- **Imaging quality:** When selecting the **JPEG** compression method, the compression quality must be specified. The effective range of compression quality values is 1 to 100, with 75 being the default value.
- **Imaging Scale:** Specify the width/height ratio of the compressed image to the original image.
- **Build a pyramid:** Option whether to build a pyramid structure on the compressed image. Building a pyramid can perform hierarchical indexing on the image, which will accelerate the image loading speed. This is very effective in improving the loading and display speed of big data images.
- **Pixel noData processing:** Remove unnecessary values created around raster data. The specified value is different from other useful data in the raster dataset. For example, values with zero on the grid boundary are different from zero values within the grid dataset. The specified pixel value will be set to NoData in the output grid dataset. For file based grids, to **ignore the background value**, it must be set to the same value as **NoData**. Invalid values in the image can cause a black background. Choosing the invalid value processing option will automatically filter out invalid pixels during the compression process, thereby improving image quality and simplifying the processing process.

The processing process will save the log, and a message prompt will be given after the processing is completed.

6.2.4 Raster slice

Raster slice is the process of dividing a raster dataset into smaller segment based on the features in blocks or faces. The schematic diagram of image slicing is shown in Figures 6-8.



Figure 6-8: Schematic diagram of raster slice

PyramidMap can perform batch slicing operations on rasters in the resource pool, and the raster slicing dialog is shown in Figure 6-9.




Figure 6-9: Raster Slicing processing

Select the tile file format, which can be consistent with the source file, or select Tiff, png, jpg, webp and other different data formats. You can creating tiles according to the number and size strategies, and finally output to the specified save path.

With the NE2_50M_SR_W.tif in the resource pool as an example, the whole image is shown in Figure 6-10.




Figure 6-10: the whole raster image

Taking the 256 * 256 (pixel) slicing strategy as an example, the generated tiles is shown in Figure 6-11.



Figure 6-11: The effect of tiles generated by the whole raster

6.2.5 Raster merge

In a sense, raster mosaicing is the reverse process of the raster tiling. Mosaicing is to combine multiple raster images through mosaic to obtain a seamless raster image. The image merging diagram is shown in Figure 6-12.



Figure 6-12: Schematic diagram of raster mosaicing

PyramidMap batch mosaicing rasters in the resource pool, as shown in Figure 6-13.




Figure 6-13: PyramidMap mosaicing rasters in the resource pool in batches

The effect of the merged raster is shown in Figure 6-14.




Figure 6-14: The effect of rasters mosaicing

Two common methods for combining adjacent or overlapping raster layers are MERGE and MOSAIC. The following is an explanation of the differences between these two types of work. The MOSAIC and MERGE functions work similarly, but there are also differences between them. When the input grids do not have any overlapping area, there is no difference in the output from either MERGE or MOSAIC. The difference is only in the processing of overlapping areas. In the case of MERGE, the sequence of input grids determines the values assigned to cells, giving priority to those entered first. The merge processing mode is shown in Figure 6-15.




Figure 6-15: The merge processing mode

6.2.6 NoData processing

In general, raster images will have NoData values. These NoData are invalid values that do not have actual value and will interfere with image data analysis. Black image frame is a common NoData error, which is particularly common for UAV images and raster data sets after geographical reference processing. In this example, we remove the black border of raster image through NoData invalid value processing. The processing process is shown in Figure 6-16.




Figure 6-16: Remove the black border of raster image through NoData invalid value processing

PyramidMap perform batch NoData processing on images in the resource pool, as shown in Figure 6-17.




Figure 6-17: Batch NoData processing of images in the resource pool

The image with black background before processing is shown in Figure 6-18.



Figure 6-18: The image with black background before processing

6.2.7 Coordinate System Conversion

PyramidMap supports Shp vector file type and raster file type coordinate system conversion, in the above two types of layer resources list, select "Coordinate System Conversion", as shown in Figure 6-19.




Figure 6-19: Select in coordinate system resource pool for conversion

In the coordinate system conversion interface, select the type of target coordinate system, which is divided into two types: spatial coordinate system and plane coordinate system, as well as many standardized coordinate systems to which it belongs. It supports global search by name and EPSG code. Taking WGS84 as an example, we can perform global keyword search according to coordinate system code 4326 to accurately obtain the target coordinate system we want.

6.3 Geodatabase layers pool

PyramidMap imports client shp vector layers into Geodatabase through database connection pool, obtains layer list through database connection pool, and supports various operations with corresponding buttons.

6.3.1 Importing Shp into Geodatabase

PyramidMap maintains the Geodatabase connection pool and the Shp vector layer resource pool to import the Shp vector layer into the Geodatabase in batches. It supports but is not limited to Oracle, PostGIS and MySQL. The import interface and process are shown in Figure 6-20.

The screenshot shows the 'Shp vector layers' import process. It displays a table of Shp files with columns for LayerFileName, LayerType, Remarks, FeatureType, LayerType, UCC(SRID), Encoding, Status, and Check. A progress bar at the bottom indicates 'Importing progress'. A red box highlights the 'Do Import' button.

No	LayerFileName	LayerType	Remarks	FeatureType	LayerType	UCC(SRID)	Encoding	Status	Check
17	province_region.shp	E:\Maps\Gaspipe\shp\gas_province_region.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	
18	gas_condensate_tank.shp	E:\Maps\Gaspipe\shp\gas_condensate_tank.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	
19	gas_pipe_shp	E:\Maps\Gaspipe\shp\gas_pipe.shp	included in program management	MultiLineString	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	
20	gas_pipe_cap.shp	E:\Maps\Gaspipe\shp\gas_pipe_cap.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	
21	gas_pressure_box.shp	E:\Maps\Gaspipe\shp\gas_pressure_box.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	
22	gas_pressure_cabinet.shp	E:\Maps\Gaspipe\shp\gas_pressure_cabinet.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	
23	gas_pressure_station.shp	E:\Maps\Gaspipe\shp\gas_pressure_station.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	
24	gas_protective_pipe.shp	E:\Maps\Gaspipe\shp\gas_protective_pipe.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	
25	gas_servicing_well.shp	E:\Maps\Gaspipe\shp\gas_servicing_well.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	
26	gas_water_well.shp	E:\Maps\Gaspipe\shp\gas_water_well.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	Local hosting	
27	Buildings.shp	E:\Maps\California\Buildings.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
28	Cemeteries.shp	E:\Maps\California\Cemeteries.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
29	Churches.shp	E:\Maps\California\Churches.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
30	Coulties.shp	E:\Maps\California\Counties.shp	included in program management	MultiPolygon	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
31	GolfCourses.shp	E:\Maps\California\GolfCourses.shp	included in program management	Point	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
32	Hospitals.shp	E:\Maps\California\Hospitals.shp	included in program management	MultiPolygon	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
33	Landmark4reas.shp	E:\Maps\California\LandmarkAreas.shp	included in program management	MultiPolygon	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
34	Lakes.shp	E:\Maps\California\Lakes.shp	included in program management	MultiPolygon	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
35	MajorRoads.shp	E:\Maps\California\MajorRoads.shp	included in program management	MultiPolygon	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
36	MajorRoads.shp	E:\Maps\California\MajorRoads.shp	included in program management	MultiLineString	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
37	Rivers.shp	E:\Maps\California\Rivers.shp	included in program management	MultiLineString	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
38	Schools.shp	E:\Maps\California\Schools.shp	included in program management	MultiLineString	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
39	States.shp	E:\Maps\California\States.shp	included in program management	MultiPolygon	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	
40	UrbanAreas.shp	E:\Maps\California\UrbanAreas.shp	included in program management	MultiPolygon	Point	GCS_WGS_1984_EPSG_4326	ISO-8859-1	succesed	

Figure 6-20: Shp vector layers imported to Geodatabase workflow

In this module, users can selectively import Shp vector layers into Geodatabase in batches. After importing, each Shp layer generates a layer feature table with the same name. As a reciprocal process, the layer feature table in Geodatabase can also be exported to different geographic feature data such as Shp, Csv, Kml, GeoJson, etc.

6.3.2 Geodatabase exporting out shp

As a reciprocal process, the features table in Geodatabase can also be exported to different geographical element data such as Shp, Csv, Kml, GeoJson, etc. The operation interface and flow are shown in Figure 6-21.

The screenshot shows the 'Geodatabase layer table export' interface. It displays a table of layer features with columns for No, LayerName, FeatureType, GeometryType, FeatureNumber, CoordinateName, EpsgCode, Status, and Check. A red box highlights the 'Export Shp' button. To the right, there is a file dialog box titled 'Postgis104shps' showing a list of files including 'Amberg.tif', 'Amberg.tif_84', 'GeoServerLayers', 'mosaic', 'NE2_50M_SR', 'NE2_50M_SR_W', 'nodata', 'rasters', 'rasterwgs84', 'tiles1', 'tiles2', and 'vectors'. The status bar at the bottom shows 'File name(D:\maps\postgis104\)' and 'File type(all files)'.

No	LayerName	FeatureType	GeometryType	FeatureNumber	CoordinateName	EpsgCode	Status	Check
1	Buildings	Point	Point	4381	EPSG_4326	4326	pending	
2	Coulties	Point	Point	4382	EPSG_4326	4326	pending	
3	Churches	Point	Point	183613	EPSG_4326	4326	pending	
4	GolfCourses	MultiPolygon	MultiPolygon	58	EPSG_4326	4326	pending	
5	Hospitals	Point	Point	537	EPSG_4326	4326	pending	
6	Lakes	Point	Point	438	EPSG_4326	4326	pending	
7	Landmark4reas	MultiPolygon	MultiPolygon	1047	EPSG_4326	4326	pending	
8	MajorRoads	MultiPolygon	MultiLineString	72033	EPSG_4326	4326	pending	
9	Rivers	MultiLineString	MultiLineString	4	EPSG_4326	4326	pending	
10	Schools	Point	Point	11381	EPSG_4326	4326	pending	
11	States	MultiPolygon	MultiPolygon	17057	EPSG_4326	4326	pending	
12	UrbanAreas	MultiPolygon	MultiPolygon	191	EPSG_4326	4326	pending	
13	capital_point	Point	Point	1	EPSG_4326	4326	pending	
14	city_point	Point	Point	311	EPSG_4326	4326	pending	
15	city_region	MultiPolygon	MultiPolygon	373	EPSG_4326	4326	pending	
16	county_point	Point	Point	2029	EPSG_4326	4326	pending	
17	country_region	MultiPolygon	MultiPolygon	2918	EPSG_4326	4326	pending	
18	gas_condensate_tank	Point	Point	8	EPSG_4326	4326	pending	
19	gas_pipe	MultiLineString	MultiLineString	8047	EPSG_4326	4326	pending	
20	gas_pipe_cap	Point	Point	629	EPSG_4326	4326	pending	
21	gas_pipe_cap	Point	Point	30	EPSG_4326	4326	pending	
22	gas_pressure_box	Point	Point	119	EPSG_4326	4326	pending	
23	gas_pressure_cabinet	Point	Point	1	EPSG_4326	4326	pending	
24	gas_pressure_station	Point	Point	1	EPSG_4326	4326	pending	

Figure 6-21: Geodatabase layer table export interface and workflow chart

In this module, users can selectively export the layer tables in Geodatabase as Shp, Csv, Kml and GeoJson under the specified path. Taking the exported Shp file as an example, the export process, export status and export file are shown in Figure 6-22.

No	DBConnection	description	DBType	HostIP	Port	Schema	Instance	Encoding	Status	Test	Editor	Check
1	oracle104	oracle	oracle	127.0.0.1	1521	ade	geodata	GBK	Modified unsyncd to server	Connect	Do edit	<input type="radio"/>
2	postgres104	postgres	postgres	127.0.0.1	5432	public	geo_data	GBK	Modified unsyncd to server	Connect	Do edit	<input checked="" type="radio"/>
3	postgislocal	The local postgis map...	postgis	127.0.0.1	5432	public	geo_data	GBK	New unsyncd to server	Connect	Do edit	<input type="radio"/>
4	geoserver100-cte-ctepostgis		postgis	localhost	5432	public	geo_gas	GBK	syncd from Server	Connect	Do edit	<input type="radio"/>
5	geoserver100-cte-postgis1		postgis	127.0.0.1	5432	public	geo_gas	GBK	syncd from Server	Connect	Do edit	<input type="radio"/>
6	geoserver100-cte-postgis1		postgis	127.0.0.1	5432	public	geo_data	GBK	syncd from Server	Connect	Do edit	<input type="radio"/>
7	geoserver100-ctn-postgis0		postgis	127.0.0.1	5432	public	geo_data	GBK	Modified unsyncd to server	Connect	Do edit	<input type="radio"/>

No	LayerName	FeatureType	GeometryType	FeatureNumbered	CoordinateName	EpsgCode	Status	Check
1	Buildings	Point	Point	4381	EPSG 4326	4326	succes	<input checked="" type="checkbox"/>
2	Cemeteries	Point	Point	842	EPSG 4326	4326	succes	<input checked="" type="checkbox"/>
3	Churches	Point	Point	183613	EPSG 4326	4326	succes	<input checked="" type="checkbox"/>
4	Coast	MultiPolygon	Polygon	59	EPSG 4326	4326	succes	<input checked="" type="checkbox"/>
5	GolfCourses	Point	Point	537	EPSG 4326	4326	succes	<input checked="" type="checkbox"/>
6	Hospitals	Point	Point	438	EPSG 4326	4326	succes	<input checked="" type="checkbox"/>
7	Lakes	MultiPolygon	Polygon	2	EPSG 4326	4326	succes	<input checked="" type="checkbox"/>
8	LandmarkAreas	MultiPolygon	Polygon	1084	EPSG 4326	4326	succes	<input checked="" type="checkbox"/>
9	MapRoads	MultiLineString	LineString	4420	EPSG 4326	4326	pending	<input type="checkbox"/>
10	Rivers	MultiLineString	LineString	4	EPSG 4326	4326	pending	<input type="checkbox"/>
11	Schools	Point	Point	11381	EPSG 4326	4326	pending	<input type="checkbox"/>
12	States	MultiPolygon	Polygon	1	EPSG 4326	4326	pending	<input type="checkbox"/>
13	UrbanAreas	MultiPolygon	Polygon	191	EPSG 4326	4326	pending	<input type="checkbox"/>
14	water_point	Point	Point	192	EPSG 4326	4326	pending	<input type="checkbox"/>
15	city_point	Point	Point	311	EPSG 4326	4326	pending	<input type="checkbox"/>
16	city_region	MultiPolygon	Polygon	373	EPSG 4326	4326	pending	<input type="checkbox"/>
17	country_point	Point	Point	2862	EPSG 4326	4326	pending	<input type="checkbox"/>
18	country_region	MultiPolygon	Polygon	2910	EPSG 4326	4326	pending	<input type="checkbox"/>
19	gas_condensate_tank	Point	Point	8	EPSG 4326	4326	pending	<input type="checkbox"/>
20	gas_pipe	MultiLineString	LineString	8047	EPSG 4326	4326	pending	<input type="checkbox"/>
21	gas_pipe_cap	Point	Point	628	EPSG 4326	4326	pending	<input type="checkbox"/>
22	gas_pressure_box	Point	Point	30	EPSG 4326	4326	pending	<input type="checkbox"/>
23	gas_pressure_cabinet	Point	Point	1	EPSG 4326	4326	pending	<input type="checkbox"/>
24	gas_measure_station	Point	Point	4	EPSG 4326	4326	pending	<input type="checkbox"/>

layers exporting

Figure 6-22: Geodatabase layer table export process, export status and export file flow chart

Select the database connection, dynamically obtain its internal layer resources, perform corresponding processing, and support various operations on layer resources with corresponding buttons, including:

- Export Shp: Export Geodatabase layers to shp files.
- Export Kml: Export Geodatabase layers to kml files.
- Export Csv: Export Geodatabase layers to csv files.
- Export GeoJson: Export Geodatabase layers to geojson files.
- Delete layers: Bulk delete the selected Geodatabase layers.

Reload and display the exported Shp layer in the map view, as shown in Figure 6-23.




Figure 6-23: Display of Shp layer exported from Geodatabase

6.3.3 Geodatabase layers preview and edit

The layer table in Geodatabase can be queried and previewed directly. The operation interface and flow diagram are shown in Figure 6-24.

No	DBconnection	description	DBType	HostIP	Port	Schema	Instance	Encoding	Status	Test	Editor	Check
1	oracle104		oracle	127.0.0.1	1521	sde	geodata	GBK	Modified unsynced to server	Connect	Do edit	<input checked="" type="radio"/>
2	postgis104	postgis	postgis	127.0.0.1	5432	public	geo_data	GBK	Modified unsynced to server	Connect	Do edit	<input type="radio"/>
3	postgislocal	The local postgis map d...	postgis	127.0.0.1	5432	public	geo_data	GBK	New unsynced to server	Connect	Do edit	<input type="radio"/>
4	geoserver100-cte-postgis	postgis	localhost	5432	public	geo_data	GBK	synced from Server	Connect	Do edit	<input type="radio"/>	
5	geoserver100-cte-postgis1	postgis	127.0.0.1	5432	public	geo_gas	GBK	synced from Server	Connect	Do edit	<input type="radio"/>	
6	geoserver100-cte-postgre1	postgis	127.0.0.1	5432	public	geo_gas	GBK	synced from Server	Connect	Do edit	<input type="radio"/>	
7	geoserver100-cte-postgisn	postgis	127.0.0.1	5432	public	geo_data	GBK	Modified unsynced to server	Connect	Do edit	<input type="radio"/>	

No	LayerName	FeatureType	GeometryType	FeaturesNumber	CoordinateName	EpsgCode	Check
1	BUILDINGS	Point	○	4381	EPSG:4326	4326	<input checked="" type="radio"/>
2	CAPITAL_POINT	Point	○	11	EPSG:4326	4326	<input type="radio"/>
3	CEMETRIES	Point	○	842	EPSG:4326	4326	<input type="radio"/>
4	CHURCHES	Point	○	183613	EPSG:4326	4326	<input type="radio"/>
5	CITY_POINT	Point	○	310	EPSG:4326	4326	<input type="radio"/>
6	CITY_REGION	MultiPolygon	☒	373	EPSG:4326	4326	<input type="radio"/>
7	COUNTIES	MultiPolygon	☒	58	EPSG:4326	4326	<input type="radio"/>
8	COUNTY_POINT	Point	○	2862	EPSG:4326	4326	<input type="radio"/>
9	COUNTY_REGION	MultiPolygon	☒	2918	EPSG:4326	4326	<input type="radio"/>
10	GAS_CONDENSATE_TANK	Point	○	8	EPSG:4326	4326	<input type="radio"/>
11	GAS_PIPE	MultiLineString	☒	8055	EPSG:4326	4326	<input type="radio"/>
12	GAS_PIPE_CAP	Point	○	626	EPSG:4326	4326	<input type="radio"/>
13	GAS_PRESSURE_BOX	Point	○	30	EPSG:4326	4326	<input type="radio"/>
14	GAS_PRESSURE_CABINET	Point	○	119	EPSG:4326	4326	<input type="radio"/>
15	GAS_PRESSURE_STATION	Point	○	1	EPSG:4326	4326	<input type="radio"/>
16	GAS_PROTECTIVE_PILE	Point	○	54	EPSG:4326	4326	<input type="radio"/>
17	GAS_SERVICING_WELL	Point	○	2	EPSG:4326	4326	<input type="radio"/>
18	GAS_VALVE	Point	○	1	EPSG:4326	4326	<input type="radio"/>
19	GAS_VALVE_WELL	Point	○	901	EPSG:4326	4326	<input type="radio"/>

Figure 6-24: Geodatabase layer table query and preview

Select the database connection, dynamically obtain its internal layer resources, perform corresponding processing, and support various operations on layer resources with corresponding buttons, including:

- Feature List: forms the feature list of the selected layer.
- Coordinate data: form a list of geographical coordinates of the selected layer.
- Records number: perform data statistics on the features in the layer.
- Layer's center: calculates the center point location of the layer.
- Map preview and edit: preview and edit the layers in the management pool.

In particular, through the map preview and editing options, the selected layer file will be opened in an independent map view to preview and edit the layer, as shown in Figure 6-25.




Figure 6-25: Open the independent preview and editing view of the single geodatabase layer

Independent map view provides each layer with separate display, rendering, base map selection and overlay, image-based editing, data table editing, feature selection and deletion operations. It is a comprehensive map service for a single layer.

6.4 GeoServer vector layers pool

PyramidMap publishes vector layers of client Shp file to GeoServer through GeoServer connection, and obtains the Internal layers through GeoServer connection in the pool, supporting various operations with corresponding buttons.

6.4.1 GeoServer layers preview

Select the GeoServer connection to dynamically acquire its internal layers and perform corresponding processing., as shown in Figure 6-26.

The screenshot shows the 'GeoServer layer preview' tab selected in the top navigation bar. Below it, a table lists four GeoServer connections:

No	GeoServerName	Description	HostIP	Port	WebName	Check
1	geoserver1		127.0.0.1	8080	geoserver	<input checked="" type="radio"/>
2	geoserver2		127.0.0.1	8080	dhcisserver	<input type="radio"/>
3	geoserver3		172.19.126.233	8080	geoserver	<input type="radio"/>
4	geoserver100	GeoServer in 192.168.31.100	192.168.31.100	8080	geoserver	<input type="radio"/>

Below this, another table lists the internal layers for the selected 'geoserver1' connection:

No	LayerTitle	LayerName	WorkSpace	GeoServerUrl	DataStorage	Style	UCS	Geometr...	LayerType	Min X	Max X	Min Y	Max Y	Check
1	Buildings	Buildings	otn	http://127.0.0.1:8080/geoserver	Buildings	point	EPSG:4326	<input checked="" type="radio"/>	point	-124.26561068...	-114.28967332...	32.5547790440...	42.0004030190...	<input type="radio"/>
2	Cemeteries	Cemeteries	otn	http://127.0.0.1:8080/geoserver	Cemeteries	point	EPSG:4326	<input checked="" type="radio"/>	point	-124.2619944...	-114.49633767...	32.5686672600...	42.1209942250...	<input type="radio"/>
3	Churches	Churches	otn	http://127.0.0.1:8080/geoserver	Churches	point	EPSG:4326	<input checked="" type="radio"/>	point	-170.3222219...	-163.028333300...	-14.335555599...	64.9540207530...	<input type="radio"/>
4	Counties	Counties	otn	http://127.0.0.1:8080/geoserver	Counties	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	-120.40972100...	-114.13121199...	32.5341569920...	42.0095189850...	<input type="radio"/>
5	GolfCourses	GolfCourses	otn	http://127.0.0.1:8080/geoserver	GolfCourses	point	EPSG:4326	<input checked="" type="radio"/>	point	-124.16867133...	-114.60079785...	32.6403330870...	41.8354129110...	<input type="radio"/>
6	Hospitals	Hospitals	otn	http://127.0.0.1:8080/geoserver	Hospitals	point	EPSG:4326	<input checked="" type="radio"/>	point	-124.19111769...	-114.30398999...	32.6167757460...	41.7727103900...	<input type="radio"/>
7	Lakes	Lakes	otn	http://127.0.0.1:8080/geoserver	Lakes	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	-120.15212727...	-115.59582327...	33.1103213640...	39.2493473640...	<input type="radio"/>
8	LandmarkAreas	LandmarkAreas	otn	http://127.0.0.1:8080/geoserver	LandmarkAreas	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	-124.19303702...	-114.18072800...	32.5425189980...	41.9960510040...	<input type="radio"/>
9	MajorRoads	MajorRoads	otn	http://127.0.0.1:8080/geoserver	MajorRoads	line	EPSG:4326	<input checked="" type="radio"/>	linestring	-124.40275454...	-114.12942727...	32.5421545450...	42.0132272730...	<input type="radio"/>
10	Rivers	Rivers	otn	http://127.0.0.1:8080/geoserver	Rivers	line	EPSG:4326	<input checked="" type="radio"/>	linestring	-124.05229327...	-119.33676227...	36.3913315450...	42.0067957370...	<input type="radio"/>
11	Schools	Schools	otn	http://127.0.0.1:8080/geoserver	Schools	point	EPSG:4326	<input checked="" type="radio"/>	point	-124.32227960...	-70.687523662...	32.5433900720...	41.9879431430...	<input type="radio"/>
12	States	States	otn	http://127.0.0.1:8080/geoserver	States	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	-124.40972100...	-114.13121199...	32.5341569920...	42.0095189850...	<input type="radio"/>
13	UrbanAreas	UrbanAreas	otn	http://127.0.0.1:8080/geoserver	UrbanAreas	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	-124.21915192...	-114.27694190...	32.5559449040...	41.9810329080...	<input type="radio"/>
14	capital_point	capital_point	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:4326	<input checked="" type="radio"/>	point	116.5055080...	116.505708800...	40.324461100...	40.1328461100...	<input type="radio"/>
15	city_point	city_point	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:4326	<input checked="" type="radio"/>	point	79.843047485...	131.406188984...	15.9976377487...	52.6016998291...	<input type="radio"/>
16	city_region	city_region	otn	http://127.0.0.1:8080/geoserver	postgis104	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	73.1794815063...	135.405303955...	11.0382738113...	53.7730674743...	<input type="radio"/>
17	county_point	county_point	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:4326	<input checked="" type="radio"/>	point	80.9004548950...	134.551940917...	18.3353710174...	53.1429176330...	<input type="radio"/>
18	county_region	county_region	otn	http://127.0.0.1:8080/geoserver	postgis104	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	77.7176132202...	135.382736206...	17.9404830932...	53.7387313842...	<input type="radio"/>
19	gas_condensate_tank	gas_condensate_tank	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34517860254...	1.34695368513...	350.96069833...	36251046.929...	<input type="radio"/>
20	gas_pipe	gas_pipe	otn	http://127.0.0.1:8080/geoserver	postgis104	line	EPSG:3857	<input checked="" type="radio"/>	linestring	1.34461039767...	1.34696250271...	240.9643.771...	3629163.2984...	<input type="radio"/>
21	gas_pipe_cap	gas_pipe_cap	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34465345507...	1.34695345953...	360.3878.7072...	362860914.1040...	<input type="radio"/>
22	gas_pressure_box	gas_pressure_box	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.344653455725...	1.34695465325E7...	360.4467.1919...	3628894.2044...	<input type="radio"/>
23	gas_pressure_cabinet	gas_pressure_cabinet	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34462921718...	1.346949492785...	360.3721.5800...	3629004.25959...	<input type="radio"/>
24	gas_pressure_station	gas_pressure_station	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34633706468...	360.8912.0386...	3608914.0386...		<input type="radio"/>
25	gas_protective_pile	gas_protective_pile	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.345191011767...	1.34662476464E7...	360.7336.8577...	3623375.6472...	<input type="radio"/>
26	gas_servicing_well	gas_servicing_well	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34593063535...	1.3464039198...	361.0205.9532...	3617492.7543...	<input type="radio"/>
27	gas_valve	gas_valve	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34593050139...	1.34593070139...	3617491.6183...	3617493.6183...	<input type="radio"/>

At the bottom of the interface, there are two buttons: 'Preview' and 'Set style'.

Figure 6-26: GeoServer connections pool and its internal layers pool

Various operations on layer resources are supported, including:

- Preview: preview the selected layer through WMS service mode.
- Set Style: set the sld display symbol matching its geometric type for the selected layer, as shown in Figure 6-27.

No	style	workArea	GeometryType	Symbol	Size(pixel)	StrokeWidth(pixel)	StrokeColor	StrokeOpacity	FillColor	FillOpacity	LabelField	Check
1	burg			circle	6	2	1.0	1.0		1.0		<input checked="" type="radio"/>
2	capitals			square	6	1	1	1.0		1.0		<input type="radio"/>
3	generic			Cross	30.0	5.0	0.379999995231...	1.0		0.37999999523...		<input type="radio"/>
4	I8101			Circle	5.0	1.0	1.0	1.0		1.0		<input type="radio"/>
5	I81701			X	35.0	5.0	0.310000002384...	1.0		0.31000000238...		<input type="radio"/>
6	I821			Square	35.0	5.0	1.0	1.0		1.0		<input type="radio"/>
7	I8501			Star	30.0	4.0	1.0	1.0		1.0		<input type="radio"/>
8	I8801			square	6	1.0	1.0	1.0		1.0		<input type="radio"/>
9	point											

Figure 6-27: Get the internal styles in the GeoServer selected and form styles list pool

Select style in the list and assign it to the selected layer.

In particular, through the map preview and editing options, the selected layer file will be opened in the independent GeoServer map view to preview the layer. The editing function is not supported temporarily, as shown in Figure 6-28.




Figure 6-28: The GeoServer vector layer is previewed according to the preset sld style

6.4.2 GeoServer layers exporting

As a reciprocal process with layers publishing, the layers hosted in GeoServer can be exported to different geographic feature data such as Shp, Csv, Kml, GeoJson, etc. The operation interface and flow are shown in Figure 6-29.




Figure 6-29: GeoServer layer export selection and specified export path

In the GeoServer layer resource list, select a layer and export it to the specified path in batch. The export process is displayed with a progress bar, and the flow diagram is shown in Figure 6-30.




Figure 6-30: GeoServer layer export process diagram

The selected layer is exported to the specified target path, and the export progress is displayed through the progress bar. The exported map is reloaded into the map view in the form of Shp vector file, as shown in Figure 6-31.




Figure 6-31: The exported Shp vector layer of GeoServer is reloaded to the map view for display

6.5 GeoServer raster layer pool

Select the raster layer in the Figure 6-8 GeoServer map server connection pool and its list, and the selected layer file will be opened in the independent GeoServer map view to preview the layer. The editing function is not supported temporarily, as shown in Figure 6-32.




Figure 6-32: The GeoServer raster layer is previewed

6.6 Coordinate System Conversion

PyramidMap supports coordinate system conversion of Shp vector file and raster file layers. Select a layer from the above two types in the resource pool, and select "Coordinate System Conversion" button, as shown in Figure 6-33.

The screenshot shows the GeoServer interface with a list of layers. The top navigation bar includes File, MapData, Geodatabase, GeoServer, System, Help, Main Mapview, Styles Console, Shp Factory, Map Resource, GeoDB Console, GeoDB data, GeoServer Console, GeoServer Space, Map Publish, GeoServer Layers, and GeoServer View. Below the navigation bar is a table listing various layers with their file names, paths, remarks, feature types, layer types, UTM(SRID), encodings, status, and checkmarks.

No	LayerFileName.shp	LayerFilePath	Remarks	FeatureType	LayerType	UCS(SRID)	Encoding	Status	Check
1	gas_condensate_tank.shp	E:\Maps\gaspipe_shp385\gas_condensate_tank.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting	<input checked="" type="checkbox"/>	
2	gas_pipe.shp	E:\Maps\gaspipe_shp385\gas_pipe.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting	<input checked="" type="checkbox"/>	
3	gas_pipe_cap.shp	E:\Maps\gaspipe_shp385\gas_pipe_cap.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting	<input checked="" type="checkbox"/>	
4	gas_pressure_box.shp	E:\Maps\gaspipe_shp385\gas_pressure_box.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting	<input checked="" type="checkbox"/>	
5	gas_pressure_cabinet.shp	E:\Maps\gaspipe_shp385\gas_pressure_cabinet.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting	<input checked="" type="checkbox"/>	
6	gas_pressure_stations.shp	E:\Maps\gaspipe_shp385\gas_pressure_stations.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting	<input checked="" type="checkbox"/>	
7	gas_protective_pile.shp	E:\Maps\gaspipe_shp385\gas_protective_pile.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting	<input checked="" type="checkbox"/>	
8	gas_servicing_well.shp	E:\Maps\gaspipe_shp385\gas_servicing_well.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting	<input checked="" type="checkbox"/>	
9	gas_valve.shp	E:\Maps\gaspipe_shp385\gas_valve.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting	<input checked="" type="checkbox"/>	
10	gas_well.shp	E:\Maps\gaspipe_shp385\gas_well.shp	included in program management	vector	WGS_1984_World_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting	<input checked="" type="checkbox"/>	
11	capital_point.shp	E:\Maps\OTNS\capital_point.shp	included in program management	vector	WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
12	city_point.shp	E:\Maps\OTNS\city_point.shp	included in program management	vector	WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
13	city_region.shp	E:\Maps\OTNS\city_region.shp	included in program management	vector	WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
14	county_point.shp	E:\Maps\OTNS\county_point.shp	included in program management	vector	WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
15	county_region.shp	E:\Maps\OTNS\county_region.shp	included in program management	vector	WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
16	province_point.shp	E:\Maps\OTNS\province_point.shp	included in program management	vector	WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
17	province_region.shp	E:\Maps\OTNS\province_region.shp	included in program management	vector	WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
18	gas_condensate_tank.shp	E:\Maps\gaspipe_shp\gas_condensate_tank.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
19	gas_pipe.shp	E:\Maps\gaspipe_shp\gas_pipe.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
20	gas_pipe_cap.shp	E:\Maps\gaspipe_shp\gas_pipe_cap.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
21	gas_pressure_box.shp	E:\Maps\gaspipe_shp\gas_pressure_box.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
22	gas_pressure_cabinet.shp	E:\Maps\gaspipe_shp\gas_pressure_cabinet.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
23	gas_pressure_stations.shp	E:\Maps\gaspipe_shp\gas_pressure_stations.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
24	gas_protective_pile.shp	E:\Maps\gaspipe_shp\gas_protective_pile.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
25	gas_servicing_well.shp	E:\Maps\gaspipe_shp\gas_servicing_well.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
26	gas_valve.shp	E:\Maps\gaspipe_shp\gas_valve.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
27	gas_well.shp	E:\Maps\gaspipe_shp\gas_well.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
28	Buildings.shp	E:\Maps\California\Buildings.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
29	Cemeteries.shp	E:\Maps\California\Cemeteries.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
30	Churches.shp	E:\Maps\California\Churches.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
31	Counties.shp	E:\Maps\California\Counties.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
32	Crossroads.shp	E:\Maps\California\crossroads.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
33	Hospitals.shp	E:\Maps\California\hospitals.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
34	Lakes.shp	E:\Maps\California\lakes.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
35	LandmarkAreas.shp	E:\Maps\California\landmarkAreas.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
36	MajorRoads.shp	E:\Maps\California\majorRoads.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
37	Rivers.shp	E:\Maps\California\rivers.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
38	Schools.shp	E:\Maps\California\schools.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
39	States.shp	E:\Maps\California\states.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	
40	UrbanAreas.shp	E:\Maps\California\urbanAreas.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting	<input type="checkbox"/>	

Below the table are several buttons: Import vector layers, Map preview and editing, Layer data statistics, Coordinate System Conversion (highlighted with a red box), Spatial processing, Export Kml, Export Csv, Export GeoJson, Delete, and All.

Figure 6-33: Select a layer for coordinate system conversion

The coordinate system conversion interface pops up, as shown in Figure 6-34.




Figure 6-34: Select in coordinate system resource pool for conversion

In the coordinate system conversion interface, select the type of target coordinate system, which is divided into two types: spatial coordinate system and plane coordinate system, as well as many standardized coordinate systems to which it belongs. It supports global search by name and EPSG code. Taking WGS84 as an example, we can perform global keyword search according to coordinate system code 4326 to accurately obtain the target coordinate system we want, as shown in Figure 6-35.




Figure 6-35: Select in coordinate system with global keyword searching according to coordinate system code

Select the target storage path and click "OK" to perform coordinate system conversion. The selected layers will be converted and saved to the target path according to the specified coordinate system. The progress bar displays the conversion progress, as shown in Figure 6-36.




Figure 6-36: Converts the selected layer to the specified coordinate system under the target path

The experimental data used in the example is available in PyramidMap for [download](#).

6.8 Map Tile

Map tiling is a method of dividing an entire map into grids with row and column numbers according to certain rules. Map tiling is the most effective and primary technical means to improve the loading speed of layers, especially for large-scale remote sensing images. Major GIS manufacturers have done so.

For vector maps, tiling can only draw the corresponding elements within the grid according to the required display range, thereby reducing rendering pressure. For raster maps, it can reduce the

amount of data requested (or read) at once, thus displaying the map within the area more efficiently.

How to effectively tiling maps according to standard specifications and make the map tiles dataset suitable for different map engines to display correctly on the web is a technical challenge. In this chapter, we will demonstrate the implementation solutions of mainstream slicing technologies such as TMS, XYZ, MVT, MBTiles, etc. through specific examples.

6.8.1 Tile pyramid model

The concept of map tiling was first proposed and applied by Google Maps, which uses a specific cutting method to slice the world map grid image using Web Mercator projection coordinates. Web Mercator projection is also a scheme created by Google, which simulates the real elliptical Earth as an isosphere for plane projection, making it convenient for computers to calculate. Subsequently, major mainstream WebGIS and internet map applications adopted a method based on this projection coordinate system for tiling.

The map is tiled according to the pyramid model, and the tile map pyramid model is a multi-resolution hierarchical model that stores and displays at different resolutions according to user needs under a unified spatial reference, forming a pyramid structure with resolution ranging from coarse to fine and data volume ranging from small to large. The geographical range represented remains unchanged. The lower the pyramid, the more detailed the map information it represents, and the larger of the scale. The schematic diagram of the principle is shown in Figure 6-65.

Lowest resolution, lowest scale



Highest resolution, Highest scale

Figure 6-65: Map tile pyramid model

The main principle of a tiling pyramid is to project the Earth of a curved surface onto a two-dimensional plane based on a specific map projection coordinate system, and then divide the two-dimensional plane into multiple scales, which is equivalent to creating multiple digital maps with different resolution levels. Each level corresponds to corresponding codes, and the higher the level, the higher the resolution corresponding to the map; Then, the global spatial range map at each level is gridded using a certain spatial partitioning method, dividing it into fixed size square grid images of several rows and columns. These segmented regular individual grid units are called tiles, and the partitioning method for each level is in the same way.

According to this model, map tiles of corresponding levels can be scheduled based on the displayed range, and corresponding grids can be displayed based on the region, thereby further reducing the amount of data requested (read). Compared to traditional maps, tiling maps reduce the amount of data requested (read) and accelerate rendering efficiency, but it takes up more storage space. It is a typical space for time solution, and the drawbacks of this solution can be almost ignored in today's increasingly low storage costs.

6.8.2 Tile coordinate system

The encoding of all tiles is based on the tile coordinate system, and the origin of the tile coordinate system can be represented in two forms:

①TMS standard: TMS (Tile Map Service) is a tile map service defined by the Open Source Geospatial Foundation (OSGeo). In the TMS specification (GeoServer follows this specification), the YX order is used, where latitude at the first and longitude at the last, with the bottom left corner of the map as the origin and the Y coordinate increasing from south to north. The principle is shown in Figure 6-66.




Figure 6-66: Schematic diagram of TMS tile specification

The numbering method for tiles is to start from the bottom left corner and increase the sequence number in ascending/descending order.

②XYZ standard: It is a tiling specification developed by Google/OSM(Open Street Map), using the XY order, where longitude at the first, latitude at the last, and the origin is in the upper left corner of the map. The Y coordinate increases from north to south, as shown in Figure 6-66.




Figure 6-67: Schematic diagram of XYZ tile specification

The numbering method for TILES is to start from the top left corner and increase the sequence number in descending/rightward order. Tiled layer related attributes, including the coordinate system used, EPSG: numerical code; The width and height of the tiles are 256x256 pixels, and the Origin coordinates are (-180, 90). Each pixel represents a unit of longitude and latitude (units per pixel) of $0.703125/2^n$ (n is the number of layers of tiles). From this, it can be calculated that when the tile level is level 0, the longitude and latitude across a tile is 180 degrees, indicating that the level 0 is composed of two tiles of 256x256 size side by side.

6.8.3 Tile representation

Example as TMS standard, the representation of map tiles is shown in Figures 6-68.




Figure 6-68: Schematic diagram of XYZ tile specification

The attributes related to the tiled layer, including the coordinate system used, (EPSG: numerical code is a coordinate system parameter published and maintained by the European Petroleum Survey Group, and different numerical codes represent different coordinate systems, such as the commonly used WGS84 the EPSG code is 4326); The size of tiles (width&height), such as 256x256 or 512x512 pixels; The origin coordinates in TMS format are (-180, -90), and the origin coordinates in XYZ format are (-180, 90); The number of units per pixel represented by each pixel is $0.703125/2^n$ (n is the number of layers of tiles). From this, it can be calculated that when the tile level is level 0, the span of a tile is 180 degrees, indicating that level 0 is composed of two tiles of 256x256 size side by side.

The level is represented by z , where the longitude direction of the tiles (refers to the method of changing the longitude of the tiles, that is, east-west direction, east direction is positive) is numbered as x , and the latitude direction (refers to the direction of changing the dimension of the tiles, TMS refers to north-south direction, north direction is positive; XYZ refers to north-south direction, south direction is positive) is numbered as y , and z is the pyramid hierarchy of the current tile, which is the scaling ratio of the current layer. Therefore, each tile can be uniquely described by a three-dimensional tuple (x, y, z) . The tile representation of the map at zoom=1 is shown in Figures 6-69.



Figure 6-69: Tile representation of the map at zoom=1

The tile representation of the map at zoom=2 is shown in Figures 6-70.



Figure 6-70: Tile representation of the map at zoom=2

In the traditional sense, map tile is oriented towards raster on the server side. After the layers are rendered according to the preset style, they are graded and tiled according to the set coordinate system, extend, and zoom level. Map tiles are stored in the form of static bitmaps in the server path, and the tiled images of the corresponding regions are returned based on the client's request extend and scale.

PyramidMap supports all the standard vector and raster map tile processing mentioned above, including: 1: TMS standard vector tile, 2: XYZ standard vector tile, 3: MVT standard vector tile, 4: MBTiles standard vector tile, 5: TMS standard raster tile, 6: XYZ standard raster tile, and 7: MBTiles standard raster tile. The tile operation entry is shown in Figure 6-71.




Figure 6-71: PyramidMap Layer Tile Entry

PyramidMap tiling operations are implemented in the vector map resource pool and the raster map resource pool, respectively.

6.8.4 Build Vector TMS tile

TMS (Tile Map Service) is a tile standard defined by the Open Source Geospatial Foundation (OSGeo). TMS defines tile starting from the bottom left corner of the map, with the bottom left corner of the map as the origin of the tile and coding system, and the vertical coordinate (Y value) increasing from south to north. PyramidMap supports TMS tile of vector layers, providing dynamic tile data loading at different resolutions for web GIS applications. In the PyramidMap vector resource pool, select the vector layer in batch mode, as shown in Figure 6-72.

No.	Layer/fileName	Layer/filePath	DataSources	GeomGraphic	GeomType	UCS(SRID)	Counts	State	Check
1	Buildings.shp	D:\maps\California\Buildings.shp	From local directory	Point	GCS_WGS_1984 EPSG:4326	4361	Normal	<input type="checkbox"/>	
2	Cemeteries.shp	D:\maps\California\Cemeteries.shp	From local directory	Point	GCS_WGS_1984 EPSG:4326	842	Normal	<input checked="" type="checkbox"/>	
3	Churches.shp	D:\maps\California\Churches.shp	From local directory	Point	GCS_WGS_1984 EPSG:4326	183613	Normal	<input type="checkbox"/>	
4	Coulters.shp	D:\maps\California\Coulters.shp	From local directory	Multipolygon	GCS_WGS_1984 EPSG:4326	56	Normal	<input type="checkbox"/>	
5	GolfCourses.shp	D:\maps\California\GolfCourses.shp	From local directory	Point	GCS_WGS_1984 EPSG:4326	537	Normal	<input checked="" type="checkbox"/>	
6	Hospitals.shp	D:\maps\California\Hospitals.shp	From local directory	Point	GCS_WGS_1984 EPSG:4326	433	Normal	<input type="checkbox"/>	
7	Lakes.shp	D:\maps\California\Lakes.shp	From local directory	Multipolygon	GCS_WGS_1984 EPSG:4326	2	Normal	<input checked="" type="checkbox"/>	
8	LandmarkAreas.shp	D:\maps\California\LandmarkAreas.shp	From local directory	Multipolygon	GCS_WGS_1984 EPSG:4326	10467	Normal	<input type="checkbox"/>	
9	MajorRoads.shp	D:\maps\California\MajorRoads.shp	From local directory	MultilineString	GCS_WGS_1984 EPSG:4326	72033	Normal	<input type="checkbox"/>	
10	Rivers.shp	D:\maps\California\Rivers.shp	From local directory	MultilineString	GCS_WGS_1984 EPSG:4326	4	Normal	<input checked="" type="checkbox"/>	
11	Schools.shp	D:\maps\California\Schools.shp	From local directory	Point	GCS_WGS_1984 EPSG:4326	11381	Normal	<input type="checkbox"/>	
12	States.shp	D:\maps\California\States.shp	From local directory	Multipolygon	GCS_WGS_1984 EPSG:4326	1	Normal	<input checked="" type="checkbox"/>	
13	UrbanAreas.shp	D:\maps\California\UrbanAreas.shp	From local directory	Multipolygon	GCS_WGS_1984 EPSG:4326	191	Normal	<input checked="" type="checkbox"/>	
14	binzhou.shp	D:\maps\Shandong\EN3857\binzhou.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	7	Normal	<input type="checkbox"/>	
15	dezhou.shp	D:\maps\Shandong\EN3857\dezhou.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	11	Normal	<input type="checkbox"/>	
16	dongning.shp	D:\maps\Shandong\EN3857\dongning.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	5	Normal	<input type="checkbox"/>	
17	heze.shp	D:\maps\Shandong\EN3857\heze.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	9	Normal	<input type="checkbox"/>	
18	jinan.shp	D:\maps\Shandong\EN3857\jinan.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	2	Normal	<input type="checkbox"/>	
19	jining.shp	D:\maps\Shandong\EN3857\jining.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	11	Normal	<input type="checkbox"/>	
20	laicheng.shp	D:\maps\Shandong\EN3857\laicheng.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	8	Normal	<input type="checkbox"/>	
21	linyi.shp	D:\maps\Shandong\EN3857\linyi.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	12	Normal	<input type="checkbox"/>	
22	qingdao.shp	D:\maps\Shandong\EN3857\qingdao.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	10	Normal	<input type="checkbox"/>	
23	rizhao.shp	D:\maps\Shandong\EN3857\rizhao.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	4	Normal	<input type="checkbox"/>	
24	taian.shp	D:\maps\Shandong\EN3857\taian.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	6	Normal	<input type="checkbox"/>	
25	wEIFANG.shp	D:\maps\Shandong\EN3857\wEIFANG.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	12	Normal	<input type="checkbox"/>	
26	weihai.shp	D:\maps\Shandong\EN3857\weihai.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	4	Normal	<input type="checkbox"/>	
27	yantai.shp	D:\maps\Shandong\EN3857\yantai.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	11	Normal	<input type="checkbox"/>	
28	zaoyang.shp	D:\maps\Shandong\EN3857\zaoyang.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	6	Normal	<input type="checkbox"/>	
29	zibo.shp	D:\maps\Shandong\EN3857\zibo.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	8	Normal	<input type="checkbox"/>	
30	binzhou.shp	D:\maps\Shandong\EN3857\binzhou.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	7	Normal	<input type="checkbox"/>	
31	dezhou.shp	D:\maps\Shandong\EN3857\dezhou.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	11	Normal	<input type="checkbox"/>	
32	dongning.shp	D:\maps\Shandong\EN3857\dongning.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	5	Normal	<input type="checkbox"/>	
33	heze.shp	D:\maps\Shandong\EN3857\heze.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	9	Normal	<input type="checkbox"/>	
34	jinan.shp	D:\maps\Shandong\EN3857\jinan.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	12	Normal	<input type="checkbox"/>	
35	jining.shp	D:\maps\Shandong\EN3857\jining.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	11	Normal	<input type="checkbox"/>	
36	laicheng.shp	D:\maps\Shandong\EN3857\laicheng.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	8	Normal	<input type="checkbox"/>	
37	linyi.shp	D:\maps\Shandong\EN3857\linyi.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	12	Normal	<input type="checkbox"/>	
38	qingdao.shp	D:\maps\Shandong\EN3857\qingdao.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	10	Normal	<input type="checkbox"/>	
39	rizhao.shp	D:\maps\Shandong\EN3857\rizhao.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	4	Normal	<input type="checkbox"/>	
40	taian.shp	D:\maps\Shandong\EN3857\taian.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	6	Normal	<input type="checkbox"/>	
41	wEIFANG.shp	D:\maps\Shandong\EN3857\wEIFANG.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	12	Normal	<input type="checkbox"/>	
42	weihai.shp	D:\maps\Shandong\EN3857\weihai.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	4	Normal	<input type="checkbox"/>	
43	yantai.shp	D:\maps\Shandong\EN3857\yantai.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	11	Normal	<input type="checkbox"/>	
44	zaozhuang.shp	D:\maps\Shandong\EN3857\zaozhuang.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	6	Normal	<input type="checkbox"/>	
45	zibo.shp	D:\maps\Shandong\EN3857\zibo.shp	From local directory	Multipolygon	WGS 84 / EPSG:4326	8	Normal	<input type="checkbox"/>	

Figure 6-72: Select Vector layers for TMS tile

Select the TMS tile option and then open the tile scheme interface, as shown in Figure 6-73.




Figure 6-73: TMS tile scheme for vector layer

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

The rendering scheme defines the rendering mode of the layer and supports rendering configurations for all collection types such as Point/MultiPoint, Linestring/MultiLinestring, Polygon/MultiPolygon, including point type symbols, size, stroke width, stroke and fill colors, and the opacity.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The tiling process is shown in Figures 6-74.




Figure 6-74: TMS tiling process of vector layers

The progress bar indicate the tiling process and status of each selected layer. The completion prompt is shown in Figure 6-75.




Figure 6-75: TMS tiling completed prompt

The final generated tiles will be classified according to the original layer name, grouped according to the Z value (zoom level) and X value, named according to the Y value, and saved to the corresponding hierarchical directory. At the same level, the tiles will be grouped based on the X value. The tiles with the same X value will be saved to the same path which named with the X value, and the tiles will be named with the Y value. The directory structure is shown as Figure 6-76.

1	2023/9/7 9:51
2	2023/9/7 9:51
3	2023/9/7 9:51
4	2023/9/7 9:51
5	2023/9/7 9:51
6	2023/9/7 9:51
7	2023/9/7 9:51
8	2023/9/7 9:51
9	2023/9/7 9:51
10	2023/9/7 9:51
11	2023/9/7 9:51

Figure 6-76: The target TMS tiles folder which corresponding to the zoomlevel

View the tile file at a certain level, as shown in Figures 6-77.




Figure 6-77: Vector layer TMS tiles file

When storing tiles, the code uses a folder structure that follows the TMS (Tile Map Service) standard, namely Z/X/Y.png, where Z represents the zoom level and X and Y represent the coordinates of the tiles. During this process, the code also checks and creates necessary folders. After completing the tiling, deploy the tiles to a web server, such as Apache Tomcat, nothing with the professional mapserver such as GeoServer, that will greatly reduce the difficulty and cost of map deployment and maintenance. You can deploy independently, access tiles data through HTTP URLs, or integrate deployment with projects, and access tiles data through relative paths. As an example, we demonstrate the web gis application through Leaflet, the complete code is as follows:

```

1 <!DOCTYPE html>
2 <html lang="en">
3   <head>
4     <meta charset="UTF-8">
5     <meta name="viewport" content="width=device-width, initial-scale=1.0">
6     <title>Leaflet vector TMS tiles Example</title>
7     <link rel="stylesheet"
8       href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9   </head>
10  <style type="text/css">
11    body {
12      margin: 0;
13      padding: 0;

```

```

13     }
14     html, body, #map{
15         width: 100%;
16         height: 100%;
17     }
18 </style>
19 <body>
20
21 <div id="map" ></div>
22
23 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
24 <script>
25     var map = L.map('map').setView([31.562710059362658,120.29751401540051],
26     8);
27         // loading the ArcGIS basemap resource
28     L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/world_Topo_
29 _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
30         // loading the local TMS tiles,Please modify according to the real path
31         // of yourself.
32         L.tileLayer('.data/tiles/jinan/{z}/{x}/{y}.png', {
33             tms: true, // Indicates this is a TMS tile
34             opacity: 0.7 // The opacity of the polygon tile can be adjusted as
35             needed
36         }).addTo(map);
37 </script>
38
39 </body>
40 </html>

```

Then display on the map as shown in Figures 6-78.




Figure 6-78: The TMS tiles loading in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The original shp of the vector tiles is also provided in PyramidMap [download](#). You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

6.8.5 Build Vector XYZ tile

XYZ tile is a standard adopted by Google/OSM (Open Street Map). TMS defines tile as starting from the bottom left corner of the map, with the bottom left corner of the map as the origin of the tile and coding system, and the vertical coordinate (Y value) increasing from south to north. On the contrary, Google uses the top left corner of the map as the origin of the tile and coding system, with the y-axis (Y value) increasing from north to south. In the PyramidMap vector map resource pool, select the vector layer and support batch selection, as shown in Figure 6-79.

The screenshot shows the PyramidMap interface with a list of vector layers in a central table. The table columns include No., LayerFileName, LayerFilePath, DataSources, GeomGraphic, GeomType, UCR(SRID), Counts, State, and Check. The layers listed are: Buildings.shp, Cemeteries.shp, Churches.shp, Counties.shp, GolfCourses.shp, Hospitals.shp, Lakes.shp, LandmarkAreas.shp, MajorRoads.shp, Rivers.shp, Schools.shp, States.shp, and UrbanAreas.shp. Most layers are categorized as MultiPolygon, while some like Cemeteries, Churches, and Counties are Point types. SRIDs range from 3857 to 4326. A watermark 'Pyramidmap.com' is diagonally across the interface.

No.	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCR(SRID)	Counts	State	Check
1	Buildings.shp	D:\maps\California3857\Buildings.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	4361	Normal	
2	Cemeteries.shp	D:\maps\California3857\Cemeteries.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	842	Normal	
3	Churches.shp	D:\maps\California3857\Churches.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	183613	Normal	
4	Counties.shp	D:\maps\California3857\Counties.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	58	Normal	
5	GolfCourses.shp	D:\maps\California3857\GolfCourses.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	537	Normal	
6	Hospitals.shp	D:\maps\California3857\Hospitals.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	438	Normal	
7	Lakes.shp	D:\maps\California3857\Lakes.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	2	Normal	
8	LandmarkAreas.shp	D:\maps\California3857\LandmarkAreas.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	10467	Normal	
9	MajorRoads.shp	D:\maps\California3857\MajorRoads.shp	From local directory	MultilineString	MultilineString	WGS 84 / Pseudo-Mercator EPSG:3857	72033	Normal	
10	Rivers.shp	D:\maps\California3857\Rivers.shp	From local directory	MultilineString	MultilineString	WGS 84 / Pseudo-Mercator EPSG:3857	4	Normal	
11	Schools.shp	D:\maps\California3857\Schools.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	11381	Normal	
12	States.shp	D:\maps\California3857\States.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	1	Normal	
13	UrbanAreas.shp	D:\maps\California3857\UrbanAreas.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	191	Normal	
14	Buildings.shp	D:\maps\CaliforniaBuildings.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	4361	Normal	
15	Cemeteries.shp	D:\maps\CaliforniaCemeteries.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	842	Normal	
16	Churches.shp	D:\maps\CaliforniaChurches.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	183613	Normal	
17	Counties.shp	D:\maps\CaliforniaCounties.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG:4326	58	Normal	
18	GolfCourses.shp	D:\maps\CaliforniaGolfCourses.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	537	Normal	
19	Hospitals.shp	D:\maps\CaliforniaHospitals.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	438	Normal	
20	Lakes.shp	D:\maps\CaliforniaLakes.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG:4326	2	Normal	
21	LandmarkAreas.shp	D:\maps\CaliforniaLandmarkAreas.shp	From local directory	MultilineString	MultilineString	GCS_WGS_1984 EPSG:4326	10467	Normal	
22	MajorRoads.shp	D:\maps\CaliforniaMajorRoads.shp	From local directory	MultilineString	MultilineString	GCS_WGS_1984 EPSG:4326	72033	Normal	
23	Rivers.shp	D:\maps\CaliforniaRivers.shp	From local directory	MultilineString	MultilineString	GCS_WGS_1984 EPSG:4326	4	Normal	
24	Schools.shp	D:\maps\CaliforniaSchools.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	11381	Normal	
25	States.shp	D:\maps\CaliforniaStates.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG:4326	1	Normal	
26	UrbanAreas.shp	D:\maps\CaliforniaUrbanAreas.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG:4326	191	Normal	

At the bottom, there is a toolbar with buttons for Import vector layers, Map preview and editing, Layer statistics, CRS Conversion, Spatial processing, and a dropdown menu for tile formats: TMS tile, XYZ tile (which is selected and highlighted with a red box), MVT tile, and Mapbox tile. There are also buttons for Export out Kml, Export out Csv, Export out GeoJson, Delete, and Check all.

Figure 6-79: Select vector layers for XYZ tile

Select the XYZ format tile and then open the tile scheme interface, as shown in Figure 6-80.




Figure 6-80: XYZ tile scheme for vector layer

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

The rendering scheme defines the rendering mode of the layer and supports rendering configurations for all collection types such as Point/MultiPoint, LineString/MultiLineString, Polygon/MultiPolygon, including point type symbols, size, stroke width, stroke and fill colors, and the opacity.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The tiling process is shown in Figures 6-81.




Figure 6-81: XYZ tiling process of vector layers

The progress bar indicate the tiling process and status of each selected layer. The completion prompt is shown in Figure 6-82.




Figure 6-82: XYZ tiling completed prompt

The final generated tiles will be classified according to the original layer name, grouped according to the Z value (zoom level) and X value, named according to the Y value, and saved to the corresponding hierarchical directory. At the same level, the tiles will be grouped based on the X value. The tiles with the same X value will be saved to the same path which named with the X

value, and the tiles will be named with the Y value. The directory structure is shown as Figure 6-83.

1	2023/9/7 11:19
2	2023/9/7 11:19
3	2023/9/7 11:19
4	2023/9/7 11:19
5	2023/9/7 11:19
6	2023/9/7 11:19
7	2023/9/7 11:19
8	2023/9/7 11:19
9	2023/9/7 11:19
10	2023/9/7 11:19
11	2023/9/7 11:19

Figure 6-83: The target XYZ tiles folder which corresponding to the zoomlevel

View the tile file at a certain level, as shown in Figures 6-84.




Figure 6-84: Vector layer XYZ tiles file

When storing tiles, the code uses a folder structure that follows the TMS (Tile Map Service) standard, namely Z/X/Y.png, where Z represents the zoom level and X and Y represent the coordinates of the tiles. During this process, the code also checks and creates necessary folders. After completing the tiling, deploy the tiles to a web server, such as Apache Tomcat, nothing with the professional mapserver such as GeoServer, that will greatly reduce the difficulty and cost of map deployment and maintenance. You can deploy independently, access tiles data through HTTP URLs, or integrate deployment with projects, and access tiles data through relative paths. As an example, we demonstrate the web gis application through Leaflet, the complete code is as follows:

```

1 <!DOCTYPE html>
2 <html lang="en">
3 <head>
4   <meta charset="UTF-8">
5   <meta name="viewport" content="width=device-width, initial-scale=1.0">
6   <title>Leaflet vector XYZ Tiles Example</title>
7   <link rel="stylesheet"
8     href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9   <style type="text/css">
```

```

10    body {
11        margin: 0;
12        padding: 0;
13    }
14    html, body, #map{
15        width: 100%;
16        height: 100%;
17    }
18 </style>
19 <body>
20
21 <div id="map" ></div>
22
23 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
24 <script>
25     //Initialize the map and set the center and zoom levels
26     var map = L.map('map').setView([33.923710059362658,-118.23851401540051], 8);
27     // Loading ArcGIS online basemap resource
28
29     L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/world_Topo_
30 _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
31     // Load local XYZ TILES, please modify according to your file path.
32     L.tileLayer('./data/tiles/xyz3857/UrbanAreas/{z}/{x}/{y}.png', {
33         tms: false, // Indicates this is an XYZ standard tiles
34         opacity: 0.7 // The transparency of the tile can be adjusted as
35         needed
36     }).addTo(map);
37 </script>
38 </body>
39 </html>

```

The loading effect on the map is shown in Figures 6-85.




Figure 6-85: The XYZ format tiles loading in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The original shp of the vector tiles is also provided in PyramidMap [download](#). You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

6.8.6 Build Vector MVT tile

MVT (Mapbox Vector Tiles), as the name suggests, this is a vector tile standard created by Mapbox. At present, there are three main formats for vector tiles: mvt (pbf), geojson, and topojson, all of these which with the best compression rate and transmission speed being the mvt format. MVT divides the traditional tile mode into two processes which including vector tiles data and style rendering separately, it represents a more novel map service mode. Its characteristic is that the server only stores vector tile data, and the rendering is completed on the client side. MVT vector tile technology inherits the dual advantages of vector data and traditional tile, reflected in the following aspects:

- 1. Lossless storage: Tiles are stored in mvt format, based on each tile number. All sizes are 256 * 256; Smaller granularity and nearly lossless information;
- 2. Smaller volume: MVT has higher compression rate and smaller volume;
- 3. Fast response speed: This is an inherent characteristic of tiled data, and the server returns data according to the client's request level;
- 4. Fast transmission speed: The data and rendering are separated, and the server only returns mvt vector data, which reduces the network load and improves the transmission and loading speed;
- 5. Implement client-side rendering: In the web client, achieve custom style rendering, giving a more flexible and rich display effect;
- 6. Implement more UI interaction: MVT enables client side vectorization operations on maps, such as interactive operations, attribute and spatial queries, independent value rendering, thematic statistics, and other feature based functions, thereby enriching map functionality.
- 7. Make full use of hardware resources: mvt utilizes OpenGL/WebGL drivers, adjusts graphics card and memory performance, adapts to client screens, and performs high-precision vector rendering based on screen resolution. It can be said that for the same tile data, different hardware performance and rendering effects are different, which completely depends on the client's display system.

Based on the above advantages, MVT technology has quickly gained recognition and support from a wide range of map manufacturers. ArcGIS, Leaflet, MapTiler, and OpenLayers have all added support for the MVT specification.

Of course, when viewed dialectically, advantages and disadvantages come with each other, and there is no such thing as having only advantages and no disadvantages. The disadvantage of MVT is its by-product of pursuing advantages, which is its high technical cost. Currently, the using range of MVT is limited by the following points:

- 1. High technical difficulty: The usual approach is to upload the map to Mapbox studio and perform slicing hosting on the Mapbox platform. This requires registering a Mapbox account and customizing the tile mode, which is a complex process;
- 2. High usage cost: The usage cost of online MVT generation and hosting is very high. Taking Mapbox Studio as an example, its service space and traffic are limited, and if it exceeds the limit, fees will be charged. For ordinary users and small and medium-sized enterprises, this is not an ideal option;

PyramidMap provides the ability for users to independently produce, host, and use MVTs. PyramidMap can perform MVT tiles in localization, and deploy the tiles data freely. You can publish data within the programs together, and access tiles data through URL relative paths without any special configuration in the web application, greatly simplifying the map data processing, improving system deployment flexibility, and reducing project implementation costs.

Before tiling, let's first take a look at the original layer in shp format, using Building.shp as an example, which represents the iconic buildings, locations, and elevations of California, as shown in Figures 6-86.




Figure 6-86: The Original Shp for MVT tiles

Its specific location is shown in Figures 6-87.




Figure 6-87: The specific location of the original Shp

Open data table of the shp file, as shown in Figure 6-88.

FeatureIdentifier	the_geom	NAME	STCTYFIPS	ELEV_METER	LABEL_FLAG
Buildings.1549	POINT (-118.21813073899995 34....)	Quartz Hill Branch County of Los An...	06037	760.0	0
Buildings.1550	POINT (-118.6106419429999 34....)	Woodland Hills Branch Los Angeles ...	06037	274.0	0
Buildings.1551	POINT (-119.77934336899995 38....)	Alpine County Courthouse	06003	1684.0	0
Buildings.1552	POINT (-119.7804546656899995 38....)	Alpine County Free Library	06003	1686.0	0
Buildings.1553	POINT (-119.77934336899995 38....)	Alpine County Law Library	06003	1684.0	0
Buildings.1554	POINT (-119.7807323389994 34....)	Historical Society of Alpine County ...	06003	1688.0	0
Buildings.1555	POINT (-118.11618354099994 34....)	Palmdale City Library	06037	810.0	0
Buildings.1556	POINT (-117.89950894199993 34....)	Pearblossom Arts Center	06037	929.0	0
Buildings.1557	POINT (-117.75839058899994 34....)	Beth Israel Community Center	06037	272.0	0
Buildings.1558	POINT (-117.76033505399995 34....)	Eagles Hall	06037	255.0	0
Buildings.1559	POINT (-117.75172357599995 34....)	Pomona City Hall	06037	260.0	0
Buildings.1560	POINT (-117.75283487399992 34....)	Pomona County Building	06037	259.0	0
Buildings.1561	POINT (-120.11352076799994 39....)	Childrens House	06017	1902.0	0
Buildings.1562	POINT (-120.11370959299999 39....)	Ehrman Mansion	06017	1903.0	0
Buildings.1563	POINT (-119.97164788099992 38....)	El Dorado Government Center	06017	1912.0	0
Buildings.1564	POINT (-120.11324294399992 39....)	General Phipps Cabin	06017	1900.0	0
Buildings.1565	POINT (-120.83826827499995 38....)	Georgetown Branch El Dorado Cou...	06017	814.0	0
Buildings.1566	POINT (-120.11463191299993 39....)	Ice House	06017	1902.0	0
Buildings.1567	POINT (-120.11324294399992 39....)	North Boat House	06017	1900.0	0
Buildings.1568	POINT (-120.58464788499992 38....)	Pilot Creek House (historical)	06017	1300.0	0
Buildings.1569	POINT (-120.11213164599991 39....)	South Boat House	06017	1901.0	0
Buildings.1570	POINT (-120.10046316899991 38....)	Tea House	06017	1902.0	0
Buildings.1571	POINT (-120.89132708999995 38....)	Kane House	06017	232.0	0
Buildings.1572	POINT (-120.89216056299995 38....)	Marshall Gold Discovery State Histo...	06017	231.0	0
Buildings.1573	POINT (-120.89299373099993 38....)	Marshalls Cabin	06017	281.0	0
Buildings.1574	POINT (-119.97629245999991 38....)	Meyer Visitors Center	06017	1905.0	0
Buildings.1575	POINT (-120.89077144099991 38....)	Old Coloma Theatre	06017	265.0	0
Buildings.1576	POINT (-120.88993827399992 38....)	Papini House	06017	236.0	0
Buildings.1577	POINT (-119.97323684999992 38....)	South Lake Tahoe Branch El Dorad...	06017	1907.0	0
Buildings.1578	POINT (-120.89160491739991 38....)	Thomas House	06017	243.0	0
Buildings.1579	POINT (-120.89021594499991 38....)	Vineyard House	06017	278.0	0
Buildings.1580	POINT (-121.07049985389993 38....)	Oakridge-Finfrared Hills Branch Fl...	06017	237.0	0

Figure 6-88: Open data table of Buildings.shp

Next, we will tile the vector layers including Buildings.shp in the vector resource pool under batch mode, as shown in Figure 6-89.

The screenshot shows the PyramidMap GeoTools Visualized Toolset interface. At the top, there is a menu bar with File, MapData, Geodatabase, GeoServer, System, and Help. Below the menu is a toolbar with icons for Main View, Styles Console, Ship Factory, Ship Conversion, Map Pool, GeoDB Console, GeoDB data, Geo Server Pool, Geo Server Space, Map Publish, Geo Server Layers, and Geo Server View. A large table below the toolbar lists 26 vector layers with columns for No., LayerFileName, LayerFilePath, DataSources, GeomGraphic, GeomType, UCS(SRID), Counts, State, and Check. The table includes layers such as Buildings.shp, Cemeteries.shp, Churches.shp, Counties.shp, GolfCourses.shp, Hospitals.shp, Lakes.shp, LandmarkAreas.shp, MajorRoads.shp, Rivers.shp, Schools.shp, States.shp, and UrbanAreas.shp. The 'UrbanAreas.shp' layer is highlighted in blue. At the bottom of the table, there are buttons for Import vector layers, Map preview and editing, Layer statistics, CRS Conversion, Spatial processing, and a dropdown menu labeled 'Layer tile' which is expanded to show options: TMS tile, XYZ tile, MVT tile (selected), and Mapbox tile. There are also buttons for Export out Kml, Export out Csv, Export out GeoJson, Delete, and a 'Check all' checkbox.

Figure 6-89: Choose Vector layers to MVT tiling

Select the MVT tile and then open the tile scheme interface, as shown in Figure 6-90.

The screenshot shows the 'Scheme for the MVT (Mapbox Vector Tiles)' dialog box. At the top, it says 'Select target CRS' with 'GCS' selected, a 'Keywords' search bar, a 'Search' button, a 'Restore' button, and a checked 'Keep origin crs of each layer' checkbox. Below this is a table with columns for No., EPSG Code, and CRS. The table lists various datums, many of which are marked as 'Unknown'. The 'Check' column contains radio buttons. At the bottom of the table is a 'Check all' checkbox. Below the table, there is a 'Scheme for tile:' section with a 'Max zoomlevel' slider set to 11, and a range from 1 to 23. There is also a 'Save Path:' field containing 'D:\maps\vectortiles\mvt3857' and a 'Select' button. At the very bottom are 'Yes', 'Help', and 'Cancel' buttons.

Figure 6-90: Vector layer MVT tiling scheme

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

Unlike TMS and XYZ tiling, MVT does not require pre set map rendering. In fact, the results of TMS and XYZ format tiling are still png tiles. The tile data is stored in the server as a static image and not rendered on the client. Although the data source is vector, the tiles are non vector. The MVT are only vector data, and map rendering is achieved through user-defined style files on the client, so there is no need to preset tile rendering strategies.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The tiling process is shown in Figures 6-91.




Figure 6-91: MVT tiling process of vector layers

The progress bar indicate the tiling process and status of each selected layer.

The final generated tiles will be classified according to the original layer name, grouped according to the Z value (zoom level) and X value, named according to the Y value, and saved to the corresponding hierarchical directory. At the same level, the tiles will be grouped based on the X value. The tiles with the same X value will be saved to the same path which named with the X value, and the tiles will be named with the Y value.

View the mvt tile files at a certain level. As shown in Figures 6-92.

190.mvt	2023/8/30 19:40	MVT	1 KB
191.mvt	2023/8/30 19:40	MVT	1 KB
192.mvt	2023/8/30 19:40	MVT	1 KB
193.mvt	2023/8/30 19:40	MVT	1 KB
194.mvt	2023/8/30 19:40	MVT	1 KB
195.mvt	2023/8/30 19:40	MVT	1 KB
196.mvt	2023/8/30 19:40	MVT	1 KB
197.mvt	2023/8/30 19:40	MVT	4 KB
198.mvt	2023/8/30 19:40	MVT	4 KB
199.mvt	2023/8/30 19:40	MVT	2 KB
200.mvt	2023/8/30 19:40	MVT	1 KB
201.mvt	2023/8/30 19:40	MVT	1 KB
202.mvt	2023/8/30 19:40	MVT	1 KB
203.mvt	2023/8/30 19:40	MVT	1 KB
204.mvt	2023/8/30 19:40	MVT	1 KB
205.mvt	2023/8/30 19:40	MVT	1 KB
206.mvt	2023/8/30 19:40	MVT	1 KB

Figure 6-92: View the mvt tile files at a certain level

At this point, the MVT vector tiling process is completed.

When storing tiles, the code uses a folder structure that follows the TMS (Tile Map Service) standard, namely Z/X/Y.png, where Z represents the zoom level and X and Y represent the coordinates of the tiles. During this process, the code also checks and creates necessary folders. After completing the tiling, deploy the tiles to a web server, such as Apache Tomcat, nothing with the professional mapserver such as GeoServer, that will greatly reduce the difficulty and cost of map deployment and maintenance. You can deploy independently, access tiles data through HTTP URLs, or integrate deployment with projects, and access tiles data through relative paths. As an example, we demonstrate the web gis application through Leaflet.

Taking the Buildings.shp as an example, open its data table in PyramidMap, as shown in Figure 6-93.

要素数据列表	FeatureIdentifier	the_geom	NAME	STCTYFIPS	ELEV_METER	LABEL_FLAG	-	□	X
Buildings.2147	POINT (-118.41594433949994 37.362151761000064)	Paiute-Shoshone Indian Cultural Center	06027	1282.0	0				
Buildings.2148	POINT (-118.1784339969999 37.385484732000066)	Schulman Grove Visitor Center	06027	3068.0	0				
Buildings.2149	POINT (-118.19026164599993 36.80215464900045)	Eastern California Museum	06027	1203.0	0				
Buildings.2150	POINT (-118.19926164599991 36.80215464900045)	Inyo County Courthouse	06027	1199.0	0				
Buildings.2151	POINT (-118.19898397499992 36.80215464900045)	Inyo County Free Library	06027	1198.0	0				
Buildings.2152	POINT (-116.86671957099992 36.46169267800008)	Death Valley National Park Visitor Center	06027	-54.0	0				
Buildings.2153	POINT (-120.34241937199994 38.25259448000046)	Independence Hall	06009	1193.0	0				
Buildings.2154	POINT (-120.07602104409995 38.4397095200007)	Tamarack Lodge	06009	2107.0	0				
Buildings.2155	POINT (-120.52984923099994 38.40074509000004)	West Point Branch Calaveras County Library	06009	830.0	0				
Buildings.2156	POINT (-120.5271481659999 38.39546764900007)	West Point Community Hall	06009	829.0	0				
Buildings.2157	POINT (-120.35464196499993 38.254917240000054)	Arnold Branch Calaveras County Library	06009	1204.0	0				
Buildings.2158	POINT (-120.46242164099993 38.13408701100008)	Black Bart Playhouse	06009	659.0	0				
Buildings.2159	POINT (-120.46853301399995 38.138253459000055)	Black Sheep Vinters	06009	658.0	0				
Buildings.2160	POINT (-120.4565824499992 38.14519784700008)	Bret Harte Center	06009	683.0	0				
Buildings.2161	POINT (-120.46519957999993 38.137420139000085)	Mitchler Hotel	06009	660.0	0				
Buildings.2162	POINT (-120.4640884349998 38.13797578800006)	Murphys Branch Calaveras County Library	06009	662.0	0				
Buildings.2163	POINT (-120.45964370199994 38.13769794000004)	Native Daughters Hall	06009	663.0	0				
Buildings.2164	POINT (-120.4663421072499991 38.13797563500009)	Old Timers Museum	06009	663.0	0				
Buildings.2165	POINT (-120.4674218699998 38.13797563500009)	Traver Building	06009	662.0	0				
Buildings.2166	POINT (-120.541867953399988 38.07131024000045)	Angels Camp Branch Calaveras County Library	06009	437.0	0				
Buildings.2167	POINT (-120.54936845999993 38.07658867100008)	Angels Camp City Hall	06009	472.0	0				
Buildings.2168	POINT (-120.5474239499992 38.07603302200005)	Angels Camp Museum	06009	467.0	0				
Buildings.2169	POINT (-120.68132055299992 38.19602977700035)	Calaveras County Courthouse	06009	307.0	0				
Buildings.2170	POINT (-120.66604204299995 38.191298550007)	Calaveras County Government Center	06009	336.0	0				
Buildings.2171	POINT (-120.6804872329998 38.196830980005)	Calaveras County Historical Museum	06009	302.0	0				
Buildings.2172	POINT (-120.66604204299995 38.191298550007)	Calaveras County Law Library	06009	336.0	0				
Buildings.2173	POINT (-120.6804872329998 38.197140922000074)	Calaveras County Library	06009	297.0	0				
Buildings.2174	POINT (-120.68076505699992 38.1971418747000086)	Metropolitan Cultural Center	06009	296.0	0				
Buildings.2175	POINT (-120.55381319299994 38.079084790006)	Prince Garibaldi Building	06009	472.0	0				
Buildings.2176	POINT (-120.68132055299992 38.19575195300007)	San Andreas Town Hall	06009	309.0	0				
Buildings.2177	POINT (-119.75014407399993 36.81078298300008)	Aspen Hall	06019	102.0	0				
Buildings.2178	POINT (-119.751810714099992 36.81078298300008)	Baker Hall	06019	102.0	0				

Figure 6-93: MVT raw layer Buildings.shp data table

We will render the features with the ELEV_METER field value by query and highlighting way in Leaflet. This field represents the elevation of the building's location in meters, and the code is as follows:

```

1  <!DOCTYPE html>
2  <html lang="ja">
3  <head>
4      <meta charset="UTF-8">
5      <meta name="viewport" content="width=device-width, initial-scale=1.0">
6      <meta http-equiv="X-UA-Compatible" content="ie=edge">
7      <link rel="stylesheet"
8          href="//cdnjs.cloudflare.com/ajax/libs/leaflet/0.7.7/leaflet.css"/>
9      <style>
10         .map {
11             width: 100%;
12             height: 1100px;
13         }
14         .info {
15             padding: 6px 8px;
16             font: 14px/16px Arial, Helvetica, sans-serif;
17             background: white;
18             background: rgba(255,255,255,0.8);
19             box-shadow: 0 0 15px rgba(0,0,0,0.2);
20             border-radius: 5px;
21         }
22         .info h4 {
23             margin: 0 0 5px;
24             color: #777;
25         }
26     </style>
27     <script src="//cdnjs.cloudflare.com/ajax/libs/leaflet/0.7.7/leaflet-
src.js"></script>
28     <script src=".//js/Leaflet.MapboxVectorTile.min.js"></script>
29     <title>Leaflet MVT Tiles Example</title>
30 </head>
31 <body>
32     <div class="map" id="map"></div>
33     <script>
34         const map = L.map("map", {
35             maxZoom: 17
36         }).setView([37.627254,-122.365161], 11);
37         // Loading ArcGIS online basemap
38         const base =
39             L.tileLayer("https://server.arcgisonline.com/ArcGIS/rest/services/world_Topo
40             _Map/MapServer/tile/{z}/{y}/{x}").addTo(map);
41         // Load MVT layers and construct feature data query criteria for
42         // grouping rendering
43         const buildings = new L.TileLayer.MVTSource({
44             url: ".//data/tiles/mvt3857/Buildings/{z}/{x}/{y}.mvt",
45             maxzoom: 18,
46             //maxNativeZoom: 15,
47             mutexToggle: false,
48             onClick: hoveronFeature,
49             style: function(feature){
50                 let color = ((feature.properties.ELEV_METER >= 100) &&
51                 (feature.properties.ELEV_METER <= 300)) ? "#FFFF00" :
52                     ((feature.properties.ELEV_METER > 300) &&
53                     (feature.properties.ELEV_METER <= 500)) ? "#FFD700" :

```

```

48             ((feature.properties.ELEV_METER > 500) &&
49             (feature.properties.ELEV_METER <= 700)) ? "#6495ED" :
50                 ((feature.properties.ELEV_METER > 700) &&
51                 (feature.properties.ELEV_METER <= 900)) ? "#FF00FF" :
52                     ((feature.properties.ELEV_METER > 900) &&
53                     (feature.properties.ELEV_METER <= 1100)) ? "#C71585" :
54                         ((feature.properties.ELEV_METER > 1100) &&
55                         (feature.properties.ELEV_METER <= 1300)) ? "#8A2BE2" :
56                             ((feature.properties.ELEV_METER > 1300) &&
57                             (feature.properties.ELEV_METER <= 1500)) ? "#7A67EE" :
58                                 ((feature.properties.ELEV_METER > 1500) &&
59                                 (feature.properties.ELEV_METER <= 1700)) ? "#0000FF" :
60                                     ((feature.properties.ELEV_METER > 1700) &&
61                                     (feature.properties.ELEV_METER <= 2000)) ? "#00EE76" :
62                                         "#0000FF";
63
64         return {color: color, radius: 5, selected: {color: "red", radius:
65           10}};
66     }
67   );
68   buildings.addTo(map);
69   // Building information display components
70   const info = L.control();
71   info.onAdd = function (map) {
72     this._div = L.DomUtil.create('div', 'info'); // create a div with
73     // a class "info"
74     this.update();
75     return this._div;
76   };
77   // Display selected feature attributes
78   info.update = function (props) {
79     this._div.innerHTML = '<h4>Building Info</h4>' + (props ?
80       '<b>' + props.NAME + '</b>' :
81       'click circles');
82   };
83   info.addTo(map);
84   function hoveronFeature(e) {
85     if(!e.feature) return;
86     info.update(e.feature.properties);
87   }
88   </script>
89 </body>
90 </html>

```

The rendering effect of grouping the values of the ELEV_METER field is shown as Figure 6-94.




Figure 6-94: Value range grouping rendering and query highlighting for MVT tiles

Select the features, highlight it, the effect is shown as Figure 6-95.




Figure 6-95: highlighting the features selected

Select the feature, display the information, as shown in Figure 6-96.




Figure 6-96: Display the information of the feature selected

All the above queries are based on the feature data in the vector tiles. In a sense, vector tile is equivalent to achieving desktop version vector layer visualization on the web, as well as data thematic statistics and rendering based on this.

The above process implements the complete process of MVT vector tile and its application on the web side. From the map, we can see that even when zoomed in to the maximum level (depending on the tile level), the map remains undistorted because the tile data is vector.

So how to determine the application plan of MVT in actual projects? First of all, imagine a scenario where users need to place a map of a certain country on the internet and require it to be accurate to village level administrative areas, roads, and buildings. You have many options to choose from, of course, the best one is definitely vector tile. Firstly, we exclude WMS and WFS, which are relatively inefficient. Which should be choosed between WMTS and vector tile? Although both are tile, the basic data of WMTS is images and does not support operations on layer's feature. Therefore, the vector tile is the optimal and almost the only choice in the large-scale map applications involving map feature data, and the MVT in Mapbox specification is almost the first choice.

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The original shp of the vector tiles is also provided in PyramidMap [download](#). You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

6.8.7 Build Vector MBTile tile

MBTiles (Mapbox tiles), as the name suggests, this is an open source tile standard created by Mapbox, with the goal of promoting standardization and efficiency of the tiling. MBTiles supports both vector and raster tiles as well as interactive grid tiles, MBTiles using Web Mercator projection to describe tile coordinate data through metadata, including boundaries, longitude and latitude coordinates, etc. MBTiles internally grades tiles, essentially a map tile dataset based on SQLite, which improves the efficiency of tile retrieval through database indexing, much higher than folder mode tiles. You can build yourself vector MbTiles in PyramidMap, as shown in Figures 6-97.

The screenshot shows the PyramidMap software interface. At the top, there is a menu bar with options: File, MapData, Geodatabase, GeoServer, System, Help. Below the menu is a toolbar with various icons for different functions. The main area displays a table of vector layers:

No.	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCS(SRID)	Counts	State	Check
1	Buildings.shp	D:\maps\California3857\Buildings.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	436	Normal	<input checked="" type="checkbox"/>	
2	Cemeteries.shp	D:\maps\California3857\Cemeteries.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	842	Normal	<input checked="" type="checkbox"/>	
3	Churches.shp	D:\maps\California3857\Churches.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	183613	Normal	<input type="checkbox"/>	
4	Counties.shp	D:\maps\California3857\Counties.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	58	Normal	<input checked="" type="checkbox"/>	
5	GolfCourses.shp	D:\maps\California3857\GolfCourses.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	537	Normal	<input checked="" type="checkbox"/>	
6	Hospitals.shp	D:\maps\California3857\Hospitals.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	438	Normal	<input checked="" type="checkbox"/>	
7	Lakes.shp	D:\maps\California3857\Lakes.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	2	Normal	<input checked="" type="checkbox"/>	
8	LandmarkAreas.shp	D:\maps\California3857\LandmarkAreas.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	10467	Normal	<input type="checkbox"/>	
9	MajorRoads.shp	D:\maps\California3857\MajorRoads.shp	From local directory	MultilineString	WGS 84 / Pseudo-Mercator EPSG 3857	72033	Normal	<input type="checkbox"/>	
10	Rivers.shp	D:\maps\California3857\Rivers.shp	From local directory	MultilineString	WGS 84 / Pseudo-Mercator EPSG 3857	4	Normal	<input checked="" type="checkbox"/>	
11	Schools.shp	D:\maps\California3857\Schools.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	11381	Normal	<input type="checkbox"/>	
12	States.shp	D:\maps\California3857\States.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	1	Normal	<input checked="" type="checkbox"/>	
13	UrbanAreas.shp	D:\maps\California3857\UrbanAreas.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	191	Normal	<input checked="" type="checkbox"/>	
14	Buildings.shp	D:\maps\California\Buildings.shp	From local directory	Point	GCS_WGS_1984 EPSG 4326	4361	Normal	<input type="checkbox"/>	
15	Cemeteries.shp	D:\maps\California\Cemeteries.shp	From local directory	Point	GCS_WGS_1984 EPSG 4326	842	Normal	<input type="checkbox"/>	
16	Churches.shp	D:\maps\California\Churches.shp	From local directory	Point	GCS_WGS_1984 EPSG 4326	183613	Normal	<input type="checkbox"/>	
17	Counties.shp	D:\maps\California\Counties.shp	From local directory	Multipolygon	GCS_WGS_1984 EPSG 4326	58	Normal	<input type="checkbox"/>	
18	GolfCourses.shp	D:\maps\California\GolfCourses.shp	From local directory	Point	GCS_WGS_1984 EPSG 4326	537	Normal	<input type="checkbox"/>	
19	Hospitals.shp	D:\maps\California\Hospitals.shp	From local directory	Point	GCS_WGS_1984 EPSG 4326	438	Normal	<input type="checkbox"/>	
20	Lakes.shp	D:\maps\California\Lakes.shp	From local directory	Multipolygon	GCS_WGS_1984 EPSG 4326	2	Normal	<input type="checkbox"/>	
21	LandmarkAreas.shp	D:\maps\California\LandmarkAreas.shp	From local directory	Multipolygon	GCS_WGS_1984 EPSG 4326	10467	Normal	<input type="checkbox"/>	
22	MajorRoads.shp	D:\maps\California\MajorRoads.shp	From local directory	MultilineString	GCS_WGS_1984 EPSG 4326	72033	Normal	<input type="checkbox"/>	
23	Rivers.shp	D:\maps\California\Rivers.shp	From local directory	MultilineString	GCS_WGS_1984 EPSG 4326	4	Normal	<input type="checkbox"/>	
24	Schools.shp	D:\maps\California\Schools.shp	From local directory	Point	GCS_WGS_1984 EPSG 4326	11381	Normal	<input type="checkbox"/>	
25	States.shp	D:\maps\California\States.shp	From local directory	Multipolygon	GCS_WGS_1984 EPSG 4326	1	Normal	<input type="checkbox"/>	
26	UrbanAreas.shp	D:\maps\California\UrbanAreas.shp	From local directory	Multipolygon	GCS_WGS_1984 EPSG 4326	191	Normal	<input type="checkbox"/>	

At the bottom of the interface, there is a toolbar with various buttons: Import vector layers, Map preview and editing, Layer statistics, CRS Conversion, Spatial processing, Layer tile, Export out Kml, Export out Csv, Export out GeoJson, Delete, and a checkbox labeled "Check all". A dropdown menu under the "Layer tile" button shows options: Build TMS tile, Build XYZ tile, Build MVT tile, and Build MBTiles tile. The "Build MBTiles tile" option is highlighted.

Figure 6-97: Build vector MbTiles in PyramidMap

Select the MBTiles tiles option and then open the tile scheme interface, as shown in Figure 6-98.




Figure 6-98: Vector MbTiles tile scheme

In the tiling scheme, select the target CRS(coordinate system) for the target tile dataset. The default option is to keep the original CRS of each layer indicated by the checkbox. If you want to transform to another CRS for the target tiles, you should uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your chosen. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

The rendering scheme defines the rendering mode of the layer and supports rendering configurations for all collection types such as Point/MultiPoint, Linestring/MultiLinestring, Polygon/MultiPolygon, including point type symbols, size, stroke width, stroke and fill colors, and the opacity.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

The MbTiles scheme supports both TMS and XYZ standards, you can choose as needing.

Select the tile level and target save path, the tile scale can be supported up to 24 zoomlevel.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The tiling process is shown in Figures 6-99.




Figure 6-99: Vector MbTiles tile process

The tiling process has a progress bar and the tiled status displayed for each layer and the tiling completion prompt is shown in Figure 6-100.




Figure 6-100: Vector MbTiles tiling completed

The generated target tile files is shown as Figure 6-101.

 Buildings.mbtiles	2023/9/8 15:28	MBTILES	3,452 KB
 Cemetrics.mbtiles	2023/9/8 15:28	MBTILES	3,027 KB
 Counties.mbtiles	2023/9/8 15:29	MBTILES	4,994 KB
 GolfCourses.mbtiles	2023/9/8 15:29	MBTILES	2,860 KB
 Hospitals.mbtiles	2023/9/8 15:29	MBTILES	2,852 KB
 Lakes.mbtiles	2023/9/8 15:29	MBTILES	897 KB
 Rivers.mbtiles	2023/9/8 15:29	MBTILES	1,079 KB
 States.mbtiles	2023/9/8 15:31	MBTILES	4,485 KB

Figure 6-101: Vector MbTiles files

The tile file corresponds to the original layer name, and each vector layer corresponds to its MBtiles file. MBtiles can be freely deployed to web servers, such as Tomcat, without needing professional map servers such as GeoServer, therefore greatly reducing the difficulty of map deployment and maintenance as well as project costs. You can deploy independently, access data through HTTP URLs, or integrate deployment with projects, and access data through relative paths. Taking Leaflet as an example to implement web side MBtiles loading, the complete code is as follows:

```

1  <!DOCTYPE html>
2  <html lang="en">
3  <head>
4      <meta charset="UTF-8">
5      <meta name="viewport" content="width=device-width, initial-scale=1.0">
6      <title>Leaflet vector MBTiles Example</title>
7      <link rel="stylesheet"
8          href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9  </head>
10 <style type="text/css">
11     body {
12         margin: 0;
13         padding: 0;
14     }
15     html, body, #map{
16         width: 100%;
17         height: 100%;
18     }
19 </style>
20 <body>
21 <div id="map" ></div>
22
23 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
24 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
25 <script src="https://unpkg.com/sql.js@0.3.2/js/sql.js"></script>
26 <script
27     src="https://unpkg.com/Leaflet.TileLayer.MBTiles@1.0.0/Leaflet.TileLayer.MBT
28     tiles.js"></script>
29 <script>
30     var map = L.map('map').fitWorld();
31     // Loading ArcGIS online basemap

```

```

30      L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/World_Topo
31      _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
32      // Load local MBTiles, please modify according to your file path.
33      // Create Counties mbtiles layer
34      var mb_Counties =
35          L.tileLayer.mbtiles('./data/tiles/mbtiles3857xyz/Counties.mbtiles');
36      // Create Hospitals mbtiles layer
37      var mb_Hospitals =
38          L.tileLayer.mbtiles('./data/tiles/mbtiles3857xyz/Hospitals.mbtiles');
39      // Add Counties mbtiles layer to map
40      mb_Counties.addTo(map);
41      // Add Hospitals mbtiles layer to map
42      mb_Hospitals.addTo(map);
43  </script>
44
45  </body>
46  </html>

```

The Counties mbtiles and Hospitals mbtiles were added to the map in the Leaflet engine as shown in Figures 6-102.




Figure 6-102: loading MbTiles in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The original shp of the vector tiles is also provided in PyramidMap [download](#). You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

6.8.8 Build Raster TMS tile

PyramidMap supports TMS, XYZ, and MbTiles standard tile of raster layers, as shown in Figure 6-103.

The screenshot shows the PyramidMap software interface. At the top, there is a menu bar with options: File, MapData, Geodatabase, GeoServer, System, Help. Below the menu is a toolbar with various icons. A large table lists raster layers with columns: No., LayerFileName, LayerFilePath, Nodata Value, LayerType, Size(byte), UCRS(SRID), Bands, PixelDepth, DataSources, State, and Check. The table contains 15 entries, mostly from the 'Sentinel-2_L2A' dataset. At the bottom of the interface is a toolbar with buttons: Import raster layers, Map preview and editing, CRS Conversion, Deal noData, Layer tile (highlighted with a red box), Raster merge, Layer's center, Delete, and Check all. Below the toolbar is a button labeled 'Build TMS tile' with three sub-options: Build TMS tile (highlighted with a red box), Build XYZ tile, and Build MBTiles tile.

Figure 6-103: PyramidMap raster layer TMS tile

The TMS tile standard has been identified in the section [6.8.4 Vector TMS tile].

Select the TMS tile and then open the scheme interface, as shown in Figure 6-104.

The screenshot shows the 'Scheme for creating TMS tiles' dialog box. At the top, it says 'Select target CRS' with a dropdown set to 'PCS', 'Keywords' set to '3857', 'Search' and 'Restore' buttons, and a checked checkbox 'Keep origin crs of each layer'. Below this is a table with columns: No., EPSG Code, CRS, and Check. The table lists various CRS options, with 'WGS 84 / Pseudo-Mercator' selected (indicated by a checked checkbox). Below the table is a section titled 'Define layer rendering styles:' with two radio buttons: 'Rendering mode:' (set to 'Rendering by raster RGB') and 'Rendering by band grayscale'. Further down are sections for 'Scheme for tile:' (set to 'Tile size (pixels)' 256) and 'Max zoomle...' (set to 23, with a slider and a list of zoom levels: 1, 3, 5, 7, 9, 11, 13, 15, 17, 19, 21, 23). There is also a 'Save Path:' field containing 'D:\maps\rastertiles\tms3857' and a 'Select' button. At the bottom are 'Yes', 'Help', and 'Cancel' buttons.

Figure 6-104: Raster TMS tile scheme

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

Please choose the rendering mode based on the band of the raster layer. For single band layers, please choose to render according to grayscale, and for multi band layers, please choose to render according to RGB raster.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

Select the tile level and target save path, the tile scale can be supported up to 24 zoomlevel.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The execution process is shown in Figures 6-105.




Figure 6-105: Raster TMS tiling process

The progress bar indicate the tiling process and status of each selected layer. The tiling completion prompt is shown in Figure 6-106.




Figure 6-106: Raster TMS tiling completed

The final generated tiles will be classified according to the original layer name, grouped according to the Z value (zoom level) and X value, named according to the Y value, and saved to the corresponding hierarchical directory. At the same level, the tiles will be grouped based on the X value. The tiles with the same X value will be saved to the same path which named with the X value, and the tiles will be named with the Y value. The directory structure is shown as Figure 6-107.




Figure 6-107: TMS tiles Folder

View the slicing file at a certain level, as shown in Figure 6-108.



Figure 6-108: Raster TMS tile files

When storing tiles, the code uses a folder structure that follows the TMS (Tile Map Service) standard, namely Z/X/Y.png, where Z represents the zoom level and X and Y represent the coordinates of the tiles. During this process, the code also checks and creates necessary folders. After completing the tiling, deploy the tiles to a web server, such as Apache Tomcat, nothing with the professional mapserver such as GeoServer, that will greatly reduce the difficulty and cost of map deployment and maintenance. You can deploy independently, access tiles data through HTTP URLs, or integrate deployment with projects, and access tiles data through relative paths. As an example, we demonstrate the web gis application through Leaflet, the complete code is as follows:

```

1 <!DOCTYPE html>
2 <html lang="en">
3 <head>
4     <meta charset="UTF-8">
5     <meta name="viewport" content="width=device-width, initial-scale=1.0">
6     <title>Leaflet raster TMS tiles Example</title>
7     <link rel="stylesheet"
8         href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9 </head>
10 <style type="text/css">
11     body {
12         margin: 0;
13         padding: 0;
14     }
15     html, body, #map{
16         width: 100%;
17         height: 100%;
18     }
19 </style>
20 <body>
21 <div id="map" ></div>
22
23 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
24 <script>
25     var map = L.map('map').setView([31.562710059362658,120.29751401540051],
26     8); // 初始化地图并设置中心和缩放级别
27     // Loading ArcGIS online basemap
28 
```

```

27     L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/World_Topo
28     _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
29     // Load local TMS tiles, please modify according to your file path.
30     L.tileLayer('.data/tiles/tms3857/{z}/{x}/{y}.png', {
31       tms: true, // Indicates this is an TMS tile
32       opacity: 0.7 // The transparency of the tile can be adjusted as
33       needed
34     }).addTo(map);
35   </script>
36
37 </body>
38 </html>

```

The loading effect on the map is shown in Figures 6-109.




Figure 6-109: Loading raster TMS tiles in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The original image(such as Tiff) of the raster tiles is also provided in PyramidMap [download](#). You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

6.8.9 Build Raster XYZ Tile

PyramidMap supports TMS, XYZ, and MbTiles standard tile of raster layers, as shown in Figure 6-110.




Figure 6-110: PyramidMap raster layer XYZ tile

The XYZ tile standard has been identified in the section [6.8.5 Vector XYZ tile].

Select the XYZ tile and then open the scheme interface, as shown in Figure 6-111.




Figure 6-111: Raster TMS tile scheme

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

Please choose the rendering mode based on the band of the raster layer. For single band layers, please choose to render according to grayscale, and for multi band layers, please choose to render according to RGB raster.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

Select the tile level and target save path, the tile scale can be supported up to 24 zoomlevel.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The execution process is shown in Figures 6-112.




Figure 6-112: Raster TMS tiling process

The progress bar indicate the tiling process and status of each selected layer. The tiling completion prompt is shown in Figure 6-113.




Figure 6-113: Raster XYZ tiling completed

The final generated tiles will be classified according to the original layer name, grouped according to the Z value (zoom level) and X value, named according to the Y value, and saved to the corresponding hierarchical directory. At the same level, the tiles will be grouped based on the X value. The tiles with the same X value will be saved to the same path which named with the X value, and the tiles will be named with the Y value. The directory structure is shown as Figure 6-114.

	1	2023/9/8 12:17
	2	2023/9/8 12:17
	3	2023/9/8 12:17
	4	2023/9/8 12:17
	5	2023/9/8 12:17
	6	2023/9/8 12:17
	7	2023/9/8 12:17
	8	2023/9/8 12:17
	9	2023/9/8 12:17
	10	2023/9/8 12:17
	11	2023/9/8 12:17
	12	2023/9/8 12:17
	13	2023/9/8 12:17

Figure 6-114: XYZ TILE Folder

View the slicing file at a certain level, as shown in Figure 6-115.



Figure 6-108: Raster XYZ tile files

When storing tiles, the code uses a folder structure that follows the TMS (Tile Map Service) standard, namely Z/X/Y.png, where Z represents the zoom level and X and Y represent the coordinates of the tiles. During this process, the code also checks and creates necessary folders. After completing the tiling, deploy the tiles to a web server, such as Apache Tomcat, nothing with the professional mapserver such as GeoServer, that will greatly reduce the difficulty and cost of map deployment and maintenance. You can deploy independently, access tiles data through HTTP URLs, or integrate deployment with projects, and access tiles data through relative paths. As an example, we demonstrate the web gis application through Leaflet, the complete code is as follows:

```

1  <!DOCTYPE html>
2  <html lang="en">
3  <head>
4      <meta charset="UTF-8">
5      <meta name="viewport" content="width=device-width, initial-scale=1.0">
6      <title>Leaflet raster XYZ tiles Example</title>
7      <link rel="stylesheet"
8          href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9  </head>
10 <style type="text/css">
11     body {
12         margin: 0;
13         padding: 0;
14     }
15     html, body, #map{
16         width: 100%;
17         height: 100%;
18     }
19 </style>
20 <body>
21 <div id="map" ></div>
22
23 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
24 <script>
25     var map = L.map('map').setView([31.562710059362658,120.29751401540051],
8); // 初始化地图并设置中心和缩放级别

```

```

26     // Loading ArcGIS online basemap
27
28     L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/world_Topo
29 _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
30
31     // Load local XYZ tiles, please modify according to your file path.
32     L.tileLayer('.data/tiles/xyz3857/{z}/{x}/{y}.png', {
33         tms: false, // Indicates this is an XYZ tile
34         opacity: 0.7 // The transparency of the tile can be adjusted as
35         needed
36     }).addTo(map);
37
38 </script>
39
40 </body>
41
42 </html>

```

The loading effect on the map is shown in Figures 6-116.




Figure 6-116: Loading raster TMS tiles in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The original image(such as Tiff) of the raster tiles is also provided in PyramidMap [download](#). You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

6.8.10 Build Raster MBTiles

MBTiles (Mapbox tiles), as the name suggests, this is an open source tile standard created by Mapbox, with the goal of promoting standardization and efficiency of the tiling. MBTiles supports both vector and raster tiles as well as interactive grid tiles, MBTiles using Web Mercator projection to describe tile coordinate data through metadata, including boundaries, longitude and latitude

coordinates, etc. MBTiles internally grades tiles, essentially a map tile dataset based on SQLite, which improves the efficiency of tile retrieval through database indexing, much higher than folder mode tiles. You can build yourself raster MbTiles in PyramidMap, as shown in Figures 6-117.

The screenshot shows the PyramidMap software interface. At the top, there is a menu bar with options like File, MapData, Geodatabase, GeoServer, System, Help, Main View, Styles Console, Shp Factory, Shp Conversion, Map Pool, GeoDB Console, GeoDB data, GeoServer Pool, GeoServer Space, Map Publish, GeoServer Layers, and GeoServer View. Below the menu is a table listing various raster layers with columns for No., LayerFileName, LayerFilePath, Nodata Value, LayerType, Size(byte), UCS(SRID), Bands, PixelDepth, DataSources, State, and Check. Some rows are highlighted in blue. At the bottom of the table, there is a toolbar with buttons for Import raster layers, Map preview and editing, CRS Conversion, Deal noData, Layer tile, Raster merge, Layer's center, Delete, and a checkbox for Check all. A context menu is open over one of the rows, with options Build TMS tile, Build XYZ tile, and Build MBTiles tile, the latter being highlighted with a red box.

Figure 6-97: Build raster MbTiles in PyramidMap

Select the MBTiles tile and then open the tile scheme interface, as shown in Figure 6-118.

The screenshot shows the 'Scheme for the creating MBTiles tiles' dialog box. At the top, it says 'Select target CRS' with 'PCS' selected, 'Keywords' set to '3857', and a 'Search' button. There is also a checked checkbox 'Keep origin crs of each layer'. Below this is a table with columns 'No.', 'EPSG Code', 'CRS', and 'Check'. The table lists several CRS options, with '1825 3857 "WGS 84 / Pseudo-Mercator"' selected and checked. Below the table is a section titled 'Define layer rendering styles:' with 'Rendering mode:' radio buttons for 'Rendering by band grayscale' and 'Rendering by raster RGB' (which is selected). Under 'Scheme for tile:', there is a 'Tile size (pixels)' dropdown set to '256', a 'Max zoomle...' slider with values from 1 to 23, and radio buttons for 'TMS standard' and 'XYZ standard' (which is selected). Under 'Save Path:', there is a text input field 'D:\maps\rastertiles\mbtiles3857xyz' and a 'Select' button. At the bottom are 'Yes', 'Help', and 'Cancel' buttons.

Figure 6-118: Raster MBTile tile scheme

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

Please choose the rendering mode based on the band of the raster layer. For single band layers, please choose to render according to grayscale, and for multi band layers, please choose to render according to RGB raster.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

The MbTiles scheme supports both TMS and XYZ standards, you can choose as needing.

Select the tile level and target save path, the tile scale can be supported up to 24 zoomlevel.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The execution process is shown in Figures 6-119.




Figure 6-119: Raster MBtiles tiling process

The progress bar indicate the tiling process and status of each selected layer. The tiling completion prompt is shown in Figure 6-120.




Figure 6-120: Raster MBtiles tiling completed

The generated target MBTtiles files is shown as Figure 6-121.

<input type="checkbox"/> 320205.mbtiles	2023/9/8 12:33	MBTILES	5,506 KB
<input type="checkbox"/> hengxuhe.mbtiles	2023/8/25 20:09	MBTILES	897 KB
<input type="checkbox"/> Sentinel-2_L2A_False_color.mbtiles	2023/9/8 12:33	MBTILES	27,888 KB
<input type="checkbox"/> Sentinel-2_L2A_NDSI.mbtiles	2023/9/8 12:33	MBTILES	26,081 KB
<input type="checkbox"/> Sentinel-2_L2A_SWIR.mbtiles	2023/9/8 12:34	MBTILES	30,217 KB

Figure 6-121: The target raster MbTiles files

The tile file corresponds to the original layer name, and each raster layer corresponds to its MBtiles file. MBtiles can be freely deployed to web servers, such as Tomcat, without needing professional map servers such as GeoServer, therefore greatly reducing the difficulty of map deployment and maintenance as well as project costs. You can deploy independently, access data through HTTP URLs, or integrate deployment with projects, and access data through relative paths. Taking Leaflet as an example to implement web side MBtiles loading, the complete code is as follows:

```

1  <!DOCTYPE html>
2  <html lang="en">
3  <head>
4      <meta charset="UTF-8">
5      <meta name="viewport" content="width=device-width, initial-scale=1.0">
6      <title>Leaflet raster xyz tiles Example</title>
7      <link rel="stylesheet"
8          href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9      <style type="text/css">
10         body {
11             margin: 0;

```

```

12         padding: 0;
13     }
14     html, body, #map{
15         width: 100%;
16         height: 100%;
17     }
18 </style>
19 <body>
20
21 <div id="map" ></div>
22
23 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
24 <script>
25     var map = L.map('map').setView([31.562710059362658,120.29751401540051],
26     8); // 初始化地图并设置中心和缩放级别
27     // Loading ArcGIS online basemap
28
29     L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/world_Topo_
30 _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
31     // Load local MBTiles, please modify according to your file path.
32     L.tileLayer('.data/tiles/mbtiles3857/Sentinel-
33 2_L2A_NDSI.mbtiles').addTo(map);
34 </script>
35
36 </body>
37 </html>

```

The loading effect on the map is shown in Figures 6-122.




Figure 6-122: Loading raster MBTiles in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The original image(such as Tiff) of the raster tiles is also provided in PyramidMap [download](#). You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

7 Map rendering and sld symbol

Before starting this chapter, we must understand that geospatial data does not have inherent visual components and must be styled in order to view the data. Style specifies the color, thickness, and other visible attributes used to present data on the map. For example, in ArcGIS, the display styles of point, line, and area map features are defined in mxd map documents. For the same layer, different rendering styles can be defined in different map documents to present different display effects. In GeoServer, styling is done using a markup language called Styled Layer Descriptor (SLD). SLD is an XML based markup language that is very powerful, and although it is somewhat complex, we can visually define it through the PyramidMap tool. This chapter focuses on the functions of SLD, its definition method in PyramidMap, management modes, and how it works in GeoServer.

SLD defines the symbolic features of map elements, which include: ① geometric types of points, lines, and surfaces; ② Edge width, color, and transparency; ③ Fill color and transparency; ④ Image size and icon; ⑤ Annotation fields, fonts, font colors, sizes, normal or bold, annotation positions, and fine tuning offsets describe the display of map features. On this basis, more advanced styles can be used. Especially for Point types, with well-known shapes such as circles, squares, stars, and even custom graphics or text can be used to specify points. You can use the dash style and hash value to set the line style. You can use custom tile shapes to fill polygons. Styles can be based on attributes in the data to style certain features in different ways. You can also annotate features with text. Styles can also be determined by the zoom level to fit their apparent size. In short, the possibility of using SLD to describe the display mode of spatial geometric shapes is enormous.

Clearly, defining and modifying SLD files is a complex process. PyramidMap provides a visualization approach that enables the creation, editing, and maintenance of SLD, and maintains bidirectional synchronization with the GeoServer server. It uploads data to the designated service space of GeoServer, forming a complete SLD production, management, and service process.

7.1 Define sld symbols at client

7.1.1 Create sld on visualizing layer nodes

At the visualization layer node on the left of the main map interface, create the sld symbol through the right-click shortcut menu, as shown in Figure 7-1.




Figure 7-1: Creating sld symbols on visualization layer node

PyramidMap will implement the sld symbol definition method through the visual palette according to the geometric type (point, line, polygon) of the selected layer, as shown in Figure 7-2.




Figure 7-2: Create sld symbol definition on layer node through palette

In the sld definition module, create map symbols for different geometric types of points, lines, and surfaces through the color palette. The symbol features include: stroke color, stroke width, fill color, transparency, size, icon, annotation field, font, font color, size, normal or bold, annotation position, fine adjustment offset, etc. The display effect can be previewed in real time on the layer, saved as an sld file, and maintained in the sld resource pool at the same time, As shown in Figure 7-3.




Figure 7-3: Create and save sld symbol definition on layer node through palette

The following is a simple SLD example we created that can be applied to layers containing points.

```

1 1 <?xml version="1.0" encoding="ISO-8859-1"?>
2 2 <StyledLayerDescriptor version="1.0.0"
3 3   xsi:schemaLocation="http://www.opengis.net/sld
4 4     StyledLayerDescriptor.xsd"
5 5   xmlns="http://www.opengis.net/sld"
6 6   xmlns:ogc="http://www.opengis.net/ogc"
7 7   xmlns:xlink="http://www.w3.org/1999/xlink"
8 8   xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
9 9     <NamedLayer>
10 10       <Name>Simple point</Name>
11 11       <UserStyle>
12 12         <Title>simple point sld</Title>
13 13         <FeatureTypestyle>
14 14           <Rule>
15 15             <PointSymbolizer>
16 16               <Graphic>
17 17                 <Mark>
18 18                   <wellKnownName>circle</wellKnownName>
19 19                   <Fill>
20 20                     <CssParameter name="fill">#FF0000</CssParameter>
21 21                   </Fill>
22 22                 <Mark>
23 23                   <size>10</size>
24 24               </Graphic>
25 25             </PointSymbolizer>
26 26           </Rule>
27 27         </FeatureTypestyle>
28 28       </UserStyle>
29 29     </NamedLayer>

```

Although the example looks long, only a few lines are really important to understand. **Line 14** states that a “PointSymbolizer” is to be used to style data as points. **Lines 15-17** state that points are to be styled using a graphic shape specified by a “well known name”, in this case a circle. SLD provides names for many shapes such as “square”, “star”, “triangle”, etc. **Lines 18-20** specify the shape should be filled with a color of #FF0000 (red). This is an RGB color code, written in hexadecimal, in the form of #RRGGBB. Finally, **line 22** specifies that the size of the shape is 10 pixels in width. The rest of the structure contains metadata about the style, such as a name identifying the style and a title for use in legends.

7.1.2 Create map symbols in the sld resource pool

PyramidMap performs centralized and unified management of client SLDs in the way of resource management pool. Enter through the "Styles console" entry of the main interface menu to open the SLD resource management pool module, as shown in Figure 7-4.




Figure 7-4: Sld symbol resource pool and creation module

PyramidMap maintains a local SLD resource pool itself, and uniformly and centrally manages the SLD files created by the client and obtained from the GeoServer. There are two ways to obtain the SLD data source, one is from the GeoServer, the other is created at the PyramidMap client. All work flows are completed in the SLD unified resource management pool module, as shown in Figure 7-5.




Figure 7-5: Complete the sld symbol creation and management workflow in the sld unified resource management pool

The defined sld file is included in the resource management list to realize resource sharing. You can select symbols in the sld resource pool to preview the effect, as shown in Figure 7-6.




Figure 7-6: Select the map symbol in the sld resource pool for effect preview

PyramidMap will match in the layer resource pool according to the geometry type of the selected sld symbol, and return the list of layers of the same type, as shown in Figure 7-7.

Preview the selected style

No	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCS(GRID)	Counts	State	Chs
1	Buildings.shp	E:\Maps\California\Buildings.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	4381	Normal	Normal	
2	Cemeteries.shp	E:\Maps\California\Cemeteries.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	842	Normal	Normal	
3	Churches.shp	E:\Maps\California\Churches.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	183613	Normal	Normal	
4	GolfCourses.shp	E:\Maps\California\GolfCourses.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	537	Normal	Normal	
5	Hospitals.shp	E:\Maps\California\Hospitals.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	438	Normal	Normal	
6	Schools.shp	E:\Maps\California\Schools.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	11381	Normal	Normal	
7	CAPITAL_POINT.shp	E:\Maps\oraclelayers\CAPITAL_POINT.shp	From db oracle104	Point	WGS 84 EPSG4326	1	missing	Normal	
8	CITY_POINT.shp	E:\Maps\oraclelayers\CITY_POINT.shp	From db oracle104	Point	WGS 84 EPSG4326	308	missing	Normal	
9	COUNTY_POINT.shp	E:\Maps\oraclelayers\COUNTY_POINT.shp	From db oracle104	Point	WGS 84 EPSG4326	2862	missing	Normal	
10	GAS_CONDENSATE_TANK.shp	E:\Maps\oraclelayers\GAS_CONDENSATE_TANK.shp	From db oracle104	Point	WGS 84 EPSG4326	8	missing	Normal	
11	GAS_PUMP.shp	E:\Maps\oraclelayers\GAS_PUMP.shp	From db oracle104	Point	WGS 84 EPSG4326	12290	missing	Normal	
12	GAS_PRESSURE_BOX.shp	E:\Maps\oraclelayers\GAS_PRESSURE_BOX.shp	From db oracle104	Point	WGS 84 EPSG4326	30	missing	Normal	
13	GAS_PRESSURE_CABINETS.shp	E:\Maps\oraclelayers\GAS_PRESSURE_CABINETS.shp	From db oracle104	Point	WGS 84 EPSG4326	122	missing	Normal	
14	GAS_PRESSURE_STATIONS.shp	E:\Maps\oraclelayers\GAS_PRESSURE_STATIONS.shp	From db oracle104	Point	WGS 84 EPSG4326	1	missing	Normal	
15	GAS_PROTECTIVEPILE.shp	E:\Maps\oraclelayers\GAS_PROTECTIVEPILE.shp	From db oracle104	Point	WGS 84 EPSG4326	54	missing	Normal	
16	GAS_SERVICING_WELL.shp	E:\Maps\oraclelayers\GAS_SERVICING_WELL.shp	From db oracle104	Point	WGS 84 EPSG4326	2	missing	Normal	
17	GAS_VALVE.shp	E:\Maps\oraclelayers\GAS_VALVE.shp	From db oracle104	Point	WGS 84 EPSG4326	1	missing	Normal	
18	GAS_VALVE_WELL.shp	E:\Maps\oraclelayers\GAS_VALVE_WELL.shp	From db oracle104	Point	WGS 84 EPSG4326	892	missing	Normal	
19	PROVINCE_POINT.shp	E:\Maps\oraclelayers\PROVINCE_POINT.shp	From db oracle104	Point	WGS 84 EPSG4326	33	missing	Normal	
20	gaspipeline.shp	E:\Maps\gas\gaspipeline.shp	Self-built Sld file	Point	EPSG4326	0	missing	Normal	
21	capital_point.shp	E:\Maps\OTNS\capital_point.shp	From local directory	Point	WGS 84 EPSG4326	1	Normal	Normal	
22	city_point.shp	E:\Maps\OTNS\city_point.shp	From local directory	Point	WGS 84 EPSG4326	310	Normal	Normal	
23	county_point.shp	E:\Maps\OTNS\county_point.shp	From local directory	Point	WGS 84 EPSG4326	2862	Normal	Normal	
24	province_point.shp	E:\Maps\OTNS\province_point.shp	From local directory	Point	WGS 84 EPSG4326	33	Normal	Normal	
25	gas_condensate_tank.shp	E:\Maps\gas\gas_condensate_tank.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	8	Normal	Normal	
26	gas_pipe_cap.shp	E:\Maps\gas\gas_pipe_cap.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	12290	Normal	Normal	
27	gas_pressure_box.shp	E:\Maps\gas\gas_gas_pressure_box.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	30	Normal	Normal	
28	gas_pressure_cabinet.shp	E:\Maps\gas\gas_gas_pressure_cabinet.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	122	Normal	Normal	
29	gas_pressure_station.shp	E:\Maps\gas\gas_gas_pressure_station.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	1	Normal	Normal	
30	gas_protective_pile.shp	E:\Maps\gas\gas_gas_protective_pile.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	54	Normal	Normal	
31	gas_servicing_well.shp	E:\Maps\gas\gas_gas_servicing_well.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	2	Normal	Normal	
32	gas_valve.shp	E:\Maps\gas\gas_gas_valve.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	1	Normal	Normal	
33	gas_valve_well.shp	E:\Maps\gas\gas_gas_valve_well.shp	From local directory	Point	IGCS_WGS_1984_EPSG4326	892	Normal	Normal	

Apply Help Cancel

Figure 7-7: Returns the list of layers with the same geometry type as the selected sld

Click "Apply" to preview the effect, as shown in Figure 7-8.




Figure 7-8: Sld symbol map effect preview

7.1.3 Get GeoServer sld symbols

Obtain sld symbols from the GeoServer through connection pool and add to the local SLD resource pool, as shown in Figure 7-9.




Figure 7-9: Obtain sld symbols from the GeoServer through connection pool

Select the GeoServer connection, click "Get server styles", PyramidMap gets the global SLDs in GeoServer and the SLDs in each workspace, and downloads them to the client resource pool for sharing.

7.2 Map rendering effect with sld

At the visualization layer node on the left side of the main interface, right-click the shortcut menu to Open the sld selection list. In this module, the sld resource files of the same type will be automatically filtered from the sld symbol resource pool maintained by the system according to the geometric type (point, line, and face) of the selected layer to form a selectable list. You can select the corresponding sld symbol definition to achieve the desired map rendering effect ,all of the workflow as shown in Figure 7-10.




Figure 7-10: Select sld for visualization layer node to achieve map rendering effect

7.3 Client sld symbols submitted to GeoServer

PyramidMap submits the client sld symbols to the GeoServer through the connection pool, as shown in Figure 7-11.




Figure 7-11: Client sld resources submitted to the GeoServer

Select all or part of the sld files and click “Sync to Server” to synchronously submit the selected sld symbols to the global space inside the GeoServer.

8 Publishing map service

WebGIS is the trend of map application development and the most extensive map application mode at present, including browser end, mobile end and embedded terminal application. Vector layer, raster layer and Geodatabase layer must be published as map service url to be applied in WebGIS terminal which hosted in map server such as GeoServer that provides web map service. GeoServer is based on the OpenGIS Web server specification, follows the OGC open standard, and can run in any J2EE/servlet based container, such as tomcat, webLogic, and webSphere, etc. GeoServer has complete functions and supports multiple map service functions, such as WMS/WFS/WCS/WMTS/KML. In the traditional way, using the GeoServer console to publish map services is very complicated and requires highly professional staff.

The significance of PyramidMap is to provide a visual guidance process to publish the layers in the local resource pool to the GeoServer server, which is simpler and easier to use than the traditional web console mode of GeoServer. The human-computer interaction is more friendly and intuitive, and the operation is convenient, which greatly reduces the professional skill requirements for operators. Even companies and individuals without GIS capabilities can easily use it, which is the biggest feature of the software. PyramidMap supports three types of layer publishing: Shp file type layer, image file type layer, and geographic database type layer. The main interface provides shortcut menu entries, as shown in Figure 8-1.




Figure 8-1: Main interface map service publishing shortcut menu entry

GeoServer supports the following three data storage modes of layer services: Geodatabase layer type, Shp vector file type, and raster image file type.

8.1 Publish Shp vector layers

Publish the local Shp vector layer to the shapefile directory on the GeoServer and use it as a data storage. GeoServer allows to store shp in file mode and output map services to web client. This is a complex process to package and submit client Shp files to the data cache path preset by GeoServer, and output them as rest map services for WebGIS access. PyramidMap simplifies this process through high integration, and makes it easier through visual guidance, the operation flows is shown in Figure 8-2.




Figure 8-2: Workflow of publishing Shp vector layer to shapefile directory on GeoServer

The Shp file is uploaded to the shapefile directory preset by GeoServer, stored as a file, and exported to the map rest service.

8.2 Publish raster layers

Like the Shp vector layer publishing process, GeoServer allows raster layers being stored in file directory mode and output services to web client. Select the layers to publish in the local raster files resource pool, and then select the target GeoServer and workspace to publish. As shown in Figure 8-3.




Figure 8-3: Workflow of publishing raster layer to raster file directory on GeoServer

8.3 Publish Geodatabase layers

The more powerful service function of GeoServer is that it can adapt to most DBMS geographic database systems, publish the map data as a service, and provide flexible web map services in a more extensive way to meet large-scale industrial map applications. Based on this, PyramidMap integrates the adaptation interface to the geographic database supported by GeoServer, supports but is not limited to publishing the layers in Oracle, PostGIS, MySQL and other geographic databases to GeoServer, and outputs WMS/WFS and other types of map services, as shown in Figure 8-4.

The screenshot displays the PyramidMap interface for publishing geodatabase layers to a GeoServer. It includes several tabs at the top: Main Mapview, Styles Console, Shp Factory, Map Resource, GeoDB Console, GeoDB data, Geo Server Console, Geo Server Space, Map Publish, GeoServer Layers, and GeoServer View.

Select vector layers:

No	LayerFileName	LayerFilePath	Remarks	FeatureType	LayerType	UCS(SRID)	Encoding	Status	Check
30	Churches.shp	E:\Maps\California\Churches.shp	included in program management	Point	GCS_WGS_1984 EPSG:4326	ISO-8859-1	succeed	<input checked="" type="checkbox"/>	
31	Counties.shp	E:\Maps\California\Counties.shp	included in program management	MultiPolygon	GCS_WGS_1984 EPSG:4326	ISO-8859-1	succeed	<input checked="" type="checkbox"/>	
32	GolfCourses.shp	E:\Maps\California\GolfCourses.shp	included in program management	Point	GCS_WGS_1984 EPSG:4326	ISO-8859-1	succeed	<input checked="" type="checkbox"/>	
33	Hospitals.shp	E:\Maps\California\Hospitals.shp	included in program management	MultiPolygon	GCS_WGS_1984 EPSG:4326	ISO-8859-1	succeed	<input checked="" type="checkbox"/>	
34	Lakes.shp	E:\Maps\California\Lakes.shp	included in program management	MultiPolygon	GCS_WGS_1984 EPSG:4326	ISO-8859-1	succeed	<input checked="" type="checkbox"/>	
35	LandmarkAreas.shp	E:\Maps\California\LandmarkAreas.shp	included in program management	MultiPolygon	GCS_WGS_1984 EPSG:4326	ISO-8859-1	succeed	<input checked="" type="checkbox"/>	
36	MajorRoads.shp	E:\Maps\California\MajorRoads.shp	included in program management	MultiLineString	GCS_WGS_1984 EPSG:4326	ISO-8859-1	pending	<input type="checkbox"/>	
37	Metro.shp	E:\Maps\California\Metro.shp	included in program management	MultiPolygon	GCS_WGS_1984 EPSG:4326	ISO-8859-1	pending	<input type="checkbox"/>	
38	Schools.shp	E:\Maps\California\Schools.shp	included in program management	Point	GCS_WGS_1984 EPSG:4326	ISO-8859-1	pending	<input type="checkbox"/>	
39	States.shp	E:\Maps\California\States.shp	included in program management	MultiPolygon	GCS_WGS_1984 EPSG:4326	ISO-8859-1	pending	<input type="checkbox"/>	
40	UrbanAreas.shp	E:\Maps\California\UrbanAreas.shp	included in program management	MultiPolygon	GCS_WGS_1984 EPSG:4326	ISO-8859-1	pending	<input type="checkbox"/>	

Select GeoServer:

No	GeoServerName	Description	HostIP	Port	WebName	WebUrl	Check
1	geoserver1		127.0.0.1	8080	geoserver	http://127.0.0.1:8080/geoserver	<input checked="" type="radio"/>
2	geoserver2		127.0.0.1	8080	dhcgiserver	http://127.0.0.1:8080/dhcgiserver	<input type="radio"/>
3	geoserver3		172.19.126.233	8080	geoserver	http://172.19.126.233:8080/geoserver	<input type="radio"/>
4	geoserver100	GeoServer in 192.168.31.100	192.168.31.100	8080	geoserver	http://192.168.31.100:8080/geoserver	<input type="radio"/>

Select workspace:

WorkSpace	NameSpace	wms	wfs	wcs	wmts	GeoServerConnection	SynchState	Check
otn	http://www.oten.com	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input checked="" type="radio"/>
cite	http://www.opengeospatial.net/cite	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>
tiger	http://www.census.gov	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>
nurc	http://www.nurc.nato.int	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>
sde	http://geoserver.sf.net	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>
itgeosolutions	http://www.geo-solutions.it	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>
topp	http://www.openplans.org/topp	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>
sf	http://www.openplans.org/spearfish	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>

Select datastorage:

DataStorage	WorkSpace	DBType	DBConnection	Description	Connect	OpenEditor	LayersList	Check
postgis104	otn	postgis	postgis104		<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="radio"/>

Importing vector layers into the database
Start publishing

Figure 8-4: Workflow of publishing geodatabase layer to GeoServer

Select the vector layer to publish in the local vector layer resource pool, and then select the GeoServer target server to publish, the workspace in the server, and the data store. The map will first be imported into the geographic database corresponding to the data store, and then published as a map service in zaiGeoServer. PyramidMap realizes the traditional complicated publishing process through an integrated visual process, greatly reducing the difficulty of work and improving the efficiency.

8.4 Manage GeoServer layers

As the visualization client of GeoServer map server, PyramidMap implements unified management of layers in GeoServer, including layer preview and query. PyramidMap's management of GeoServer layers includes three main functions: GeoServer data source node in the main interface, as shown in Figure 8-5.




Figure 8-5: GeoServer data source node in the main interface

Through the GeoServer data source node, you can complete various hierarchical operations on the GeoServer workspace, data storage, and layers. PyramidMap provides access to GeoServer layer preview list and GeoServer layer management list through toolbar menu items, as shown in Figure 8-6.




Figure 8-6: Main interface GeoServer layers operation entrance

Through the above menu items, the layer preview and management of GeoServer can be realized.

8.4.1 GeoServer layers preview

PyramidMap previews the layers published by the server through the GeoServer resource connection pool. The list of layers is shown in Figure 8-7.

PyramidMap Visualization Desktop-GeoServer layers preview console

File MapData Geodatabase GeoServer System Help

Main Mapview Styles Console Shp Factory Map Resource GeoDB Console GeoDB data Geo Server Console Geo Server Space Map Publish GeoServer Layers Geo Server View

No	GeoServerName	Description	HostIP	Port	WebName	WebUrl	Check
1	geoserver1		127.0.0.1	8080	geoserver	http://127.0.0.1:8080/geoserver	<input checked="" type="checkbox"/>
2	geoserver2		127.0.0.1	8080	dhcgiserver	http://127.0.0.1:8080/dhcgiserver	<input type="checkbox"/>
3	geoserver3		172.19.126.233	8080	geoserver	http://172.19.126.233:8080/geoserver	<input type="checkbox"/>
4	geoserver100	GeoServer in 192.168.31.100	192.168.31.100	8080	geoserver	http://192.168.31.100:8080/geoserver	<input type="checkbox"/>

layersList:

No	LayerTitle	LayerName	WorkSpace	GeoServerUrl	DataStorage	Style	UCS	Geometr	LayerType	Min X	Max X	Min Y	Max Y	Check
1	Buildings	Buildings	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 4326	<input checked="" type="checkbox"/>	point	-124.31549895...	-114.23979187...	32.5075454711...	42.0476341247...	<input checked="" type="checkbox"/>
2	capital_point	capital_point	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 4326	<input checked="" type="checkbox"/>	point	116.50550988...	116.505509880	40.1324461100...	40.1324461100...	<input type="checkbox"/>
3	city_point	city_point	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 4326	<input checked="" type="checkbox"/>	point	79.9483047485...	131.406188964...	15.9976377487...	52.6016998291...	<input type="checkbox"/>
4	city_region	city_region	oth	http://127.0.0.1:8080/geoserver	postgis104	polygon	EPSG 4326	<input checked="" type="checkbox"/>	polygon	73.1794815063...	135.40530395...	11.0382738113...	53.7730674743...	<input type="checkbox"/>
5	county_point	county_point	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 4326	<input checked="" type="checkbox"/>	point	80.9084548950...	134.551940917...	18.3353710174...	53.1429176330...	<input type="checkbox"/>
6	county_region	county_region	oth	http://127.0.0.1:8080/geoserver	postgis104	polygon	EPSG 4326	<input checked="" type="checkbox"/>	polygon	77.176132202...	135.382736202...	17.9404830932...	53.7387313842...	<input type="checkbox"/>
7	gas_condensate_tank	gas_condensate_tank	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 3857	<input checked="" type="checkbox"/>	point	1.34517860254...	1.34659368513...	3608506.9833...	3625104.6929...	<input type="checkbox"/>
8	gas_pipe	gas_pipe	oth	http://127.0.0.1:8080/geoserver	postgis104	line	EPSG 3857	<input checked="" type="checkbox"/>	linestring	1.34461039577...	1.34699250277...	3603643.771...	3629163.2984...	<input type="checkbox"/>
9	gas_pipe_cap	gas_pipe_cap	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 3857	<input checked="" type="checkbox"/>	point	1.34485345507...	1.34695345353...	3603678.7072...	3628609.1408...	<input type="checkbox"/>
10	gas_pressure_box	gas_pressure_box	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 3857	<input checked="" type="checkbox"/>	point	1.34484357525...	1.34656453257...	3604467.1919...	3628894.2044...	<input type="checkbox"/>
11	gas_pressure_cabinet	gas_pressure_cabinet	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 3857	<input checked="" type="checkbox"/>	point	1.34462821718...	1.34689492788...	3603721.5806...	3629004.25859...	<input type="checkbox"/>
12	gas_pressure_station	gas_pressure_station	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 3857	<input checked="" type="checkbox"/>	point	1.34633686468...	1.34633706488...	3608912.0386...	3608914.0386...	<input type="checkbox"/>
13	gas_protective_pile	gas_protective_pile	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 3857	<input checked="" type="checkbox"/>	point	1.34519101177...	1.34662476487...	3607338.8577...	3623375.6472...	<input type="checkbox"/>
14	gas_servicing_well	gas_servicing_well	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 3857	<input checked="" type="checkbox"/>	point	1.34593063535...	1.34644303191...	3610205.9532...	3617492.7543...	<input type="checkbox"/>
15	gas_valve	gas_valve	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 3857	<input checked="" type="checkbox"/>	point	1.34593050139...	1.34593070139...	3617491.6183...	3617493.6183...	<input type="checkbox"/>
16	gas_valve_well	gas_valve_well	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 3857	<input checked="" type="checkbox"/>	point	1.34461051047...	1.34696228317...	3603643.8278...	3629154.9864...	<input type="checkbox"/>
17	province_point	province_point	oth	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG 4326	<input checked="" type="checkbox"/>	point	85.544189249...	128.174219194...	19.212895629...	46.949332827...	<input type="checkbox"/>
18	province_region	province_region	oth	http://127.0.0.1:8080/geoserver	postgis104	polygon	EPSG 4326	<input checked="" type="checkbox"/>	polygon	73.441277000...	135.08693...	18.159829000...	53.5617710000...	<input type="checkbox"/>
19	capital_point	capital_point	cite	http://127.0.0.1:8080/geoserver	capital_point	point	EPSG 4326	<input checked="" type="checkbox"/>	point	116.505608800...	116.505608800...	40.1325461100...	40.1325461100...	<input type="checkbox"/>
20	city_point	city_point	cite	http://127.0.0.1:8080/geoserver	city_point	point	EPSG 4326	<input checked="" type="checkbox"/>	point	75.221319900...	134.288735000...	18.5075849900...	52.9706019900...	<input type="checkbox"/>
21	city_region	city_region	cite	http://127.0.0.1:8080/geoserver	city_region	polygon	EPSG 4326	<input checked="" type="checkbox"/>	polygon	73.487537000...	135.097257...	0.25315392723...	53.5615080000...	<input type="checkbox"/>
22	county_point	county_point	cite	http://127.0.0.1:8080/geoserver	county_point	point	EPSG 4326	<input checked="" type="checkbox"/>	point	75.221319900...	134.288735000...	18.5075849900...	52.9706019900...	<input type="checkbox"/>
23	county_region	county_region	cite	http://127.0.0.1:8080/geoserver	county_region	polygon	EPSG 4326	<input checked="" type="checkbox"/>	polygon	73.487537000...	135.097256000...	18.1177040000...	53.5615090000...	<input type="checkbox"/>
24	gas_condensate_tank	gas_condensate_tank	cite	http://127.0.0.1:8080/geoserver	gas_condensate...	point	EPSG 3857	<input checked="" type="checkbox"/>	point	120.838449853...	120.966568885...	30.8131513005...	30.9411190741...	<input type="checkbox"/>
25	gas_pipe	gas_pipe	cite	http://127.0.0.1:8080/geoserver	gas_pipe	line	EPSG 3857	<input checked="" type="checkbox"/>	linestring	120.7845406964...	120.999240659...	30.7756237473...	30.9723847841...	<input type="checkbox"/>
26	gas_pipe_cap	gas_pipe_cap	cite	http://127.0.0.1:8080/geoserver	gas_pipe_cap	point	EPSG 3857	<input checked="" type="checkbox"/>	point	120.7845407408...	121.287217605...	30.6272956456...	30.9919681943...	<input type="checkbox"/>
27	gas_pressure_box	gas_pressure_box	cite	http://127.0.0.1:8080/geoserver	gas_pressure...	point	EPSG 3857	<input checked="" type="checkbox"/>	point	120.7917385917...	120.963950059...	30.7919788022...	30.9703121005...	<input type="checkbox"/>

Preview Set style

Figure 8-7: GeoServer layer list

The GeoServer layer list includes two types: vector and image. The vector layer is divided into point, line and face types. Select the vector layer and click Preview. PyramidMap will load and display the selected vector layer through WMS, as shown in Figure 8-8.




Figure 8-8: GeoServer vector layer preview

Select an raster layer and click Preview. PyramidMap will load and display the selected raster layer in WMS mode, as shown in Figure 8-9.




Figure 8-9: GeoServer raster layer preview

8.4.2 GeoServer layers export and conversion

PyramidMap provides some column export and data conversion operations for the layers in GeoServer, which is not available in regular GeoServer, giving more flexibility and operable space to map data. As shown in Figure 8-10.

The screenshot displays the PyramidMap interface for managing GeoServer layers. At the top, there is a menu bar with options like File, MapData, Geodatabase, GeoServer, System, and Help. Below the menu is a toolbar with various icons for managing layers. The main area is divided into two sections: 'Select GeoServer' and 'layersList'.

Select GeoServer:

No	GeoServerName	Description	HostIP	Port	WebName	WebUrl	Check
1	geoserver1		127.0.0.1	8080	geoserver	http://127.0.0.1:8080/geoserver	<input checked="" type="checkbox"/>
2	geoserver2		127.0.0.1	8080	dhcplisserver	http://127.0.0.1:8080/dhcplisserver	<input type="checkbox"/>
3	geoserver3		172.19.126.233	8080	geoserver	http://172.19.126.233:8080/geoserver	<input type="checkbox"/>
4	geoserver100	GeoServer in 192.168.31.100	192.168.31.100	8080	geoserver	http://192.168.31.100:8080/geoserver	<input type="checkbox"/>

layersList:

No	LayerTitle	LayerName	WorkSpace	GeoServerUrl	DataStorage	Style	UCS	Geometr.	LayerType	Min X	Max X	Min Y	Max Y	Check
1	Buildings	Buildings	otn	http://127.0.0.1:8080/geoserver	postgis104	buildingpoint	EPSG:4326	<input checked="" type="radio"/>	point	-124,318	-114,24	32,508	42,048	<input checked="" type="checkbox"/>
2	capital_point	capital_point	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:4326	<input checked="" type="radio"/>	point	116,506	116,506	40,132	40,133	<input checked="" type="checkbox"/>
3	city_point	city_point	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:4326	<input checked="" type="radio"/>	point	79,848	131,406	15,998	52,602	<input checked="" type="checkbox"/>
4	city_region	city_region	otn	http://127.0.0.1:8080/geoserver	postgis104	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	73,179	135,405	11,038	53,773	<input checked="" type="checkbox"/>
5	county_point	county_point	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:4326	<input checked="" type="radio"/>	point	80,908	134,552	18,335	53,143	<input checked="" type="checkbox"/>
6	county_region	county_region	otn	http://127.0.0.1:8080/geoserver	postgis104	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	77,718	135,383	17,94	53,739	<input checked="" type="checkbox"/>
7	gas_condensate_tank	gas_condensate_tank	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	13,451,786,025	13,465,936,851	3,608,506,983	3,625,104,693	<input checked="" type="checkbox"/>
8	gas_pipe	gas_pipe	otn	http://127.0.0.1:8080/geoserver	postgis104	line	EPSG:3857	<input checked="" type="radio"/>	linestring	13,446,103,957	13,469,625,028	3,603,643,771	3,629,163,298	<input checked="" type="checkbox"/>
9	gas_pipe_cap	gas_pipe_cap	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	13,446,534,551	13,469,534,535	3,603,878,707	3,628,809,141	<input checked="" type="checkbox"/>
10	gas_pressure_box	gas_pressure_box	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	13,446,435,572	13,465,645,325	3,604,467,192	3,628,894,204	<input checked="" type="checkbox"/>
11	gas_pressure_cabinet	gas_pressure_cabinet	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	13,446,282,172	13,468,949,279	3,603,721,581	3,629,004,256	<input checked="" type="checkbox"/>
12	gas_pressure_station	gas_pressure_station	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	13,463,368,847	13,463,370,647	3,608,912,039	3,608,914,039	<input checked="" type="checkbox"/>
13	gas_protective_pile	gas_protective_pile	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	13,451,910,117	13,466,247,646	3,607,338,858	3,623,375,647	<input checked="" type="checkbox"/>
14	gas_servicing_well	gas_servicing_well	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	13,459,206,353	13,464,403,92	3,610,205,953	3,617,492,754	<input checked="" type="checkbox"/>
15	gas_valve	gas_valve	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	13,459,305,014	13,459,307,014	3,617,491,618	3,617,493,618	<input checked="" type="checkbox"/>
16	gas_valve_well	gas_valve_well	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	13,446,105,105	13,469,622,832	3,603,643,828	3,629,154,986	<input checked="" type="checkbox"/>
17	province_point	province_point	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:4326	<input checked="" type="radio"/>	point	85,544	128,174	19,213	46,943	<input checked="" type="checkbox"/>
18	province_region	province_region	otn	http://127.0.0.1:8080/geoserver	postgis104	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	73,441	135,087	18,16	53,562	<input checked="" type="checkbox"/>
19	capital_point	capital_point	cite	http://127.0.0.1:8080/geoserver	capital_point	point	EPSG:4326	<input checked="" type="radio"/>	point	116,506	116,506	40,133	40,133	<input checked="" type="checkbox"/>
20	city_point	city_point	cite	http://127.0.0.1:8080/geoserver	city_point	point	EPSG:4326	<input checked="" type="radio"/>	point	75,987	131,151	16,179	52,42	<input checked="" type="checkbox"/>
21	city_region	city_region	cite	http://127.0.0.1:8080/geoserver	city_region	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	73,488	135,097	0,253	53,562	<input checked="" type="checkbox"/>
22	county_point	county_point	cite	http://127.0.0.1:8080/geoserver	county_point	point	EPSG:4326	<input checked="" type="radio"/>	point	75,221	134,286	18,508	52,971	<input checked="" type="checkbox"/>
23	county_region	county_region	cite	http://127.0.0.1:8080/geoserver	county_region	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	73,488	135,097	18,118	53,562	<input checked="" type="checkbox"/>
24	gas_condensate_tank	gas_condensate_tank	cite	http://127.0.0.1:8080/geoserver	gas_condensate_tank	point	EPSG:3857	<input checked="" type="radio"/>	point	120,839	120,967	30,813	30,941	<input checked="" type="checkbox"/>
25	gas_pipe	gas_pipe	cite	http://127.0.0.1:8080/geoserver	gas_pipe	line	EPSG:3857	<input checked="" type="radio"/>	linestring	120,788	120,999	30,776	30,972	<input checked="" type="checkbox"/>
26	gas_pipe_cap	gas_pipe_cap	cite	http://127.0.0.1:8080/geoserver	gas_pipe_cap	point	EPSG:3857	<input checked="" type="radio"/>	point	120,745	121,287	30,627	30,992	<input checked="" type="checkbox"/>
27	gas_pressure_box	gas_pressure_box	cite	http://127.0.0.1:8080/geoserver	gas_pressure_box	point	EPSG:3857	<input checked="" type="radio"/>	point	120,791	120,964	30,782	30,97	<input checked="" type="checkbox"/>

At the bottom of the interface, there are buttons for 'Export Shp', 'Export Kml', 'Export Csv', 'Export GeJson', and 'Delete layers'.

Figure 8-10: GeoServer layers export and conversion

PyramidMap can export the layers in GeoServer to Shp, Kml, Csv, Geojson and other formats, realizing the visual transformation of map data and expanding the utilization space of map data.