

# PyramidMap Geotools Visualized Toolset Instructions

## PyramidMap Geotools Visualized Toolset Instructions

### 1 Introduction

- 1.1: Function overview
- 1.2 Contact us

### 2 Software deployment

- 2.1 Deployment mode
- 2.2 Running mode
- 2.3 System function
  - 2.3.1 Edition classify
  - 2.3.2 Obtain authorization
- 2.4 Examples and tutorial data
- 2.5 Shortcut Key

### 3 Map view

- 3.1 Load basemap
- 3.2 Load business layer
  - 3.2.1 Load local layers
  - 3.2.2 Load Geodatabase layer
  - 3.2.3 Load GeoServer layer
- 3.3 Visible layer node
  - 3.3.1 Layer control
  - 3.3.2 SLD symbol
  - 3.3.3 Features table
  - 3.3.4 Layer data export
  - 3.3.5 Restore to the layer extend

### 4 Map query and editing

- 4.1 Map query
  - 4.1.1 Feature Selection query
  - 4.1.2 Feature table query
  - 4.1.3 Building query analyzer
- 4.2 Map editing

- 4.2.1 Create Shp
- 4.2.2 Shp editing
  - 4.2.2.1 Main view editor
  - 4.2.2.2 Standalone view editor
- 4.2.3 Database layer editing
- 4.2.4 GeoServer Layer Editing

## 5 Geodatabase and GeoServer

- 5.1 Geodatabase connection pool
  - 5.1.1 Geodatabase data source node
  - 5.1.2 Geodatabase connection pool
- 5.2 GeoServer connection pool
  - 5.2.1 GeoServer data node
  - 5.2.2 GeoServer connection pool
  - 5.2.3 Manage GeoServer connections
- 5.3 GeoServer internal operate
  - 5.3.1 GeoServer Workspace
  - 5.3.2 GeoServer data storage
  - 5.3.3 GeoServer pool console

## 6 Map data and conversion

- 6.1 Vector layers pool
  - 6.1.1 Vector layer preview
  - 6.1.2 Vector data processing
- 6.2 Raster layers pool
  - 6.2.1 Raster layer preview
  - 6.2.2 Raster data processing
  - 6.2.3 Raster compress
  - 6.2.4 Raster slice
  - 6.2.5 Raster merge
  - 6.2.6 NoData processing
  - 6.2.7 Coordinate System Conversion
- 6.3 Geodatabase layers pool
  - 6.3.1 Importing shp to Geodatabase
  - 6.3.2 Geodatabase exporting out shp
  - 6.3.3 Geodatabase layers preview and edit
- 6.4 GeoServer vector layers pool
  - 6.4.1 GeoServer layers preview
  - 6.4.2 GeoServer layers exporting
- 6.5 GeoServer raster layer pool
- 6.6 Coordinate System Conversion
- 6.7 Data conversion
  - 6.7.1 Csv to Shp
  - 6.7.2 Excel to Shp
  - 6.7.3 GeoJSON to Shp
  - 6.7.4 Shp to Csv and GeoJSON
  - 6.7.5 Shp to Kml
- 6.8 Map Tile
  - 6.8.1 Tile pyramid model
  - 6.8.2 Tile coordinate system
  - 6.8.3 Tile representation
  - 6.8.4 Build Vector TMS tile
  - 6.8.5 Build Vector XYZ tile
  - 6.8.6 Build Vector MVT tile
  - 6.8.7 Build Vector MBTile tile
  - 6.8.8 Build Raster TMS tile
  - 6.8.9 Build Raster XYZ Tile

## 6.8.10 Build Raster MBTiles

### 7 Map rendering and sld symbol

#### 7.1 Define sld symbols at client

##### 7.1.1 Create sld on visualizing layer nodes

##### 7.1.2 Create map symbols in the sld resource pool

##### 7.1.3 Get GeoServer sld symbols

#### 7.2 Map rendering effect with sld

#### 7.3 Client sld symbols submitted to GeoServer

### 8 Publishing map service

#### 8.1 Publish vector cache layers

#### 8.2 Publish raster cache layers

#### 8.3 Publish Geodatabase layers

#### 8.4 Manage GeoServer layers

##### 8.4.1 GeoServer layers preview

##### 8.4.2 GeoServer layers export and conversion


# 1 Introduction

## 1.1: Function overview

As the world enters the information and digital era, the development of communication and Internet technology has completely changed the way people communicate and perceive the world. GIS (Geographic Information System) has developed from original paper map to holographic digital electronic map. GIS is synchronized with the software and hardware support of operating system, communication interconnection and mobile terminal, and has penetrated into all aspects of social production and people's life. From space launch, satellite remote sensing, express delivery and bus service, almost every link is shining with the glory of GIS. GIS can integrate spatial and dynamic information into holographic digital visual effects, and provide timely and accurate visual services for geographical research, geographical decision-making and residents' lives. The rich and colorful services of GIS come from its massive data support and powerful analysis and processing capabilities. However, the production, storage, analysis, processing and service provision of map data is an extremely professional, arduous and complex work, which has professional requirements for workflow and operators, and the technical cost is very high. Therefore, many enterprises with this demand but weak technology are discouraged. PyramidMap is a simple and practical GIS data processing workflow platform for small and medium-sized enterprises to solve this problem.

PyramidMap GeoTools visual map tool set is launched by PyramidMap ([www.Pyramidmap.com](http://www.Pyramidmap.com)). It is based on GeoTools component technology, which can be used as an independent map processing tool, as well as oriented to GeoServer and used as its client. It constitutes a simple and easy-to-use map service system covering mapping, editing and assignment, rendering, database storage, service release and management. It is simple and easy to use, covering mapping, editing and assignment, rendering, database storage, service publishing, and management. The purpose of PyramidMap is to transform the professional and even daunting GIS data processing into an approachable, easy to use, relaxed and pleasant workflow. On this basis, the original complex process of GeoServer and Geodatabase connection and map service publishing is transformed into a fully guided visualization process, reducing the user threshold and improving the efficiency of map operation. Thus, GIS users are given the ability to independently complete the whole process from map mapping to web map services. Its ultimate goal is to provide efficient data processing process for WebGIS applications. That is to say, PyramidMap tool provides you with

the most basic data assurance processing process for WebGIS applications. It belongs to the core layer of map data processing and is also the most complex process. PyramidMap is fully qualified for this work. The process is shown in Figure 1-1.



PyramidMap workflow

Figure 1-1: Diagram of PyramidMap Total Energy

PyramidMap is positioned at the key link of the whole WebGIS implementation process, and completes the processing and storage of key map data before the feasibility of WebGIS. Traditionally, it is highly dependent on the skills of professional GIS personnel. Now it can be easily completed by PyramidMap, which greatly reduces the access threshold for GIS users and improves the efficiency of map data processing.

## 1.2 Contact us

PyramidMap focuses on GIS application services and is committed to building a complete ecosystem of efficient GIS data processing, enterprise level geographic data storage, distributed map services, web and mobile map applications. It can help you achieve map data processing more easily and quickly, until the terminal displays the entire process of the application as a streamlined service. Welcome visiting to: <http://www.pyramidmap.com> obtaining beta software and technical information. For more technical support, please contact PyramidMap studio.

Email: [service@pyramidmap.com](mailto:service@pyramidmap.com)

Tele: (086)0531-82957588

Mobile: (086)18660789051

WeChat: A18660789051

QQ: 29862351

## 2 Software deployment

### 2.1 Deployment mode

PyramidMap integrates all the dependencies required for operation internally. You only need to decompress the software to use it (Chinese path is not supported for the moment). Double click the PyramidMapView.exe executable to run it. The deployment mode is shown in Figure 2-1.




Figure 2-1: Schematic Diagram of PyramidMap Deployment Operation Mode

The PyramidMap GeoTools visualization toolset is only supported running in a Windows environment currently , with a minimum resolution requirement of 1920 \* 1200.

## 2.2 Running mode

- Client/Server mode

PyramidMap can complete independent mapping, map editing, symbol definition rendering, Geodatabase geographic database connection, access, map data input and output, GeoServer map server space management, map service publishing, hosting and access and other full process processing. PyramidMap can independently complete all functions from mapping to editing, support multiple spatial geographic databases, including but not limited to Oracle, Postgre, MySQL, and complete the input, output, access and storage of map data. PyramidMap can be seamlessly connected with GeoServer map server, and can be used as a visualization client tool of GeoServer to complete workspace and data storage management of remote server, layer publishing, map symbol production and publishing, server layer and symbol data management, preview and other serialized operations on the client. To sum up, PyramidMap provides map users with a full process function from mapping to Web side use. PyramidMap supports deployment in Internet and intranet environments. It has all the dependencies required for integrated operation. It can be used after decompression without installation (Chinese path is not supported temporarily).The role and operation mode of PyramidMap in WebGIS network architecture are shown in Figure 2-2.




Figure 2-2: The role and operation mode of PyramidMap in WebGIS network architecture

## 2.3 System function

### 2.3.1 Edition classify

The edition and functions distribute of PyramidMap are shown in Table 2-1.

Functions	Products				Application Scenario
	Free	Basic	Standard	Professional	
Map display	●	●	●	●	Displaying various map such as vector, raster, geodatabase, GeoServer and WMTS.
Map resource management	●	●	●	●	Vector, raster, geodatabase, GeoServer, WMS, WFS/WMTS layers list.
Shp creation and editing	●	●	●	●	Design and create the original Shape file and initialize the data table.
Map feature selection	●	●	●	●	The selecting interface exchange of map points, lines, and surface features.
Map feature drawing	●	●	●	●	Create points, lines, and polygons on the map and perform custom rendering.
Map data editing		●	●	●	Add, delete, and modify map features and their attribute data.
Map data query	●	●	●	●	Build visual query analyzer, implement multi condition constructed queries for attribute data, and achieve specific rendering of result sets.
Map data conversion			●	●	The bidirectional exchange between heterogeneous data such as Shp, Geodatabase, GeoServer, and Excel, Csv, Kml, GeoJson.
Map symbol management		●	●	●	Create SLD symbol and manage in pool locally, and achieve bidirectional synchronization with GeoServer.
Coordinate System Conversion			●	●	Coordinate system conversion for vector and raster, supporting the vast majority of EPSG standardized geographic and projection coordinate systems.
Vector layers tile	Level 10	Level 12	Level 16	Level 24	Build TMS, Google XYZ, MVT (Mapbox Vector Tile), MBTile (Mapbox Tile) tiles.
Raster layers tile	Level 10	Level 12	Level 16	Level 24	Build TMS, Google XYZ, MBTile (Mapbox Tile) tiles.
Raster data processing			●	●	Raster compression, slicing, merging, NoData processing.
GeoDatabase connections pool	●	●	●	●	Supports Oracle, PostGIS, MySQL, and SQL Server connections pools.
Import and export of GeoDatabase			●	●	Import layers into geodatabase and export out such as Shp, Csv, Kml, GeoJson.
GeoServer connections pool	●	●	●	●	Create GeoServer connections and maintain in pool mode.
GeoServer workspace management				●	Creates and obtains workspaces for GeoServer on client side.
GeoServer datastorage management				●	Creates and obtains data storages for GeoServer on client side.
Workspace Sync with GeoServer				●	Sync workspaces between client and GeoServer.
DataStorage Sync with GeoServer				●	Sync datastorages between client and GeoServer.
SLD Sync with GeoServer			●	●	Sync slds between client and GeoServer.
Layers published to GeoServer				●	Publish vector and raster layers to GeoServer on the client side.

Table 2-2: The edition and functions distribute

### 2.3.2 Obtain authorization

Enter the software register page through the system menu 'Software register', please send your user ID to: [service@pyramidmap.com](mailto:service@pyramidmap.com) Or contact PyramidMap through WeChat or other means to obtain authorization.

## 2.4 Examples and tutorial data

PyramidMap provides supporting experimental data for each chapter as tutoring teaching data for learning PyramidMap. The supporting experimental data and sample downloads are shown in Table 2-2:

Chapter	Experiment data	Web example
3.2.1 Load local layers	<a href="#">vector files</a>	
3.2.1 Load local layers	<a href="#">raster files</a>	
3.3.2 SLD symbol	<a href="#">sld files</a>	
4.1 Map query	<a href="#">shp files</a>	
4.2 Map editting	<a href="#">shp files</a>	
6.1.1 Vector layer preview	<a href="#">vector files</a>	
6.1.2 Vector data process	<a href="#">vector files</a>	
6.2.1 Raster layer preview	<a href="#">raster files</a>	
6.2.2 Raster layer process	<a href="#">raster files</a>	
6.3.1 Imported shp to Geodatabase	<a href="#">shp files</a>	
6.7.1 Csv to Shp	<a href="#">csv data</a>	
6.7.2 Excel to Shp	<a href="#">excel data</a>	

Chapter	Experiment data	Web example
6.7.3 GeoJSON to Shp	<a href="#">geojson data</a>	
6.7.4 Shp to Csv and GeoJSON	<a href="#">shp files</a>	
6.7.5 Shp to Kml	<a href="#">shp files</a>	
6.8.4 Build Vector TMS tile	<a href="#">vector tiling source data</a>	<a href="#">web example</a>
6.8.5 Build Vector XYZ tile	<a href="#">vector tiling source data</a>	<a href="#">web example</a>
6.8.6 Build Vector MVT tile	<a href="#">vector tiling source data</a>	<a href="#">web example</a>
6.8.7 Build Vector MBTile tile	<a href="#">vector tiling source data</a>	<a href="#">web example</a>
6.8.8 Build Raster TMS tile	<a href="#">raster tiling source data</a>	<a href="#">web example</a>
6.8.9 Build Raster XYZ tile	<a href="#">raster tiling source data</a>	<a href="#">web example</a>
6.8.10 Build Raster MBTiles	<a href="#">raster tiling source data</a>	<a href="#">web example</a>
8.1 Publish vector cache layers	<a href="#">vector files</a>	
8.2 Publish raster cache layers	<a href="#">raster files</a>	

Table 2-2: Experimental data and examples list in PyramidMap GeoTools Visualized Toolset

You can download and experiment with the corresponding functions of PyramidMap in chapter order.

## 2.5 Shortcut Key

---

The Shortcut Keys in PyramidMap are shown in Table 2-3:

Shortcut Key	Description
F1	Open help
F2	<a href="#">PyramidMap home</a>
F3	<a href="#">PyramidMap examples and tutorial data</a>
F4	<a href="#">PyramidMap updates</a>
F5	<a href="#">PyramidMap technical white paper</a>
F6	<a href="#">PyramidMap download</a>
F7	<a href="#">Related technical</a>
F8	PyramidMap register
F9	Vector layers pool management
F10	Raster layers pool management
F11	Create geodatabase connection
F12	Create geoserver connection

Table 2-3: Shortcut Key list

## 3 Map view

---

The main map interface is divided into four functional areas, as shown in Figure 3-1. They are the main map view and the display container of all map data. They accept the loading and display of various map resource data from Shp files, image files, Geodatabase, GeoServer, online maps, etc; The online layer node on the left is the layer data source node that has been loaded into the main map view. It is classified according to the path layer, and has the corresponding level menu to complete the operation as instructed; On the upper right is the Geodatabase data source node, which is classified according to the data connection layer table, and has the corresponding level

menu. The operation can be completed according to the instructions. The layer table can be dragged to the map view area or displayed by double clicking the mouse, and automatically added to the layer display node on the left; The lower right side is the GeoServer workspace and layer data source node, which are classified according to GeoServer connection - workspace - layer, and have the corresponding level menu. The operation is completed according to the instructions. The layer can be dragged to the map view area or displayed by double clicking the mouse, and automatically added to the layer display node on the left.




Figure 3-1: Main map viewer

### 3.1 Load basemap

The base map provides a reference map for the system and an environment for the content to be displayed in the map. When creating a new map, you can select an underlay to use. PyramidMap currently supports many base map resource based on Web Mercator coordinate system and others standard coordinate system. You can change the base map of the current map at any time: you can select the base map from the base map library. With the help of the base map, accurate spatial location calibration can be carried out, map data related to location can be processed, dot, line and picture can be plotted on the map, and accurate positioning and track query can be carried out. The main interface loads and switches the base map through the shortcut menu in the toolbar, as shown in Figure 3-2.




Figure 3-2: Main viewer base map menu

PyramidMap supports vector and raster type base map resources. This base map is designed to be used as a general reference map for informational purposes as well as for GIS professionals and other users to creating web maps and web mapping applications.

The world general reference map includes administrative boundaries, cities, protected areas, highways, roads, railways, water features, buildings and landmarks, overlaid on shaded relief and land cover imagery for added context. This reference map display effect is shown in Figure 3-3.




Figure 3-3: The world general reference map display effect

The local details somewhere for the world general reference map are shown in Figure 3-4.




Figure 3-4: The world general reference map somewhere local details

The world land cover imagery and detailed topographic map presents land cover imagery and detailed topographic maps for the world. This map display effect is shown in Figure 3-5.




Figure 3-5: The world land cover imagery and detailed topographic map display effect

The local details somewhere for the world land cover imagery and detailed topographic map are shown in Figure 3-6.




Figure 3-6: The world land cover imagery and detailed topographic map somewhere local details

The world satellite and aerial imagery map provides one meter or better satellite and aerial imagery in many parts of the world and lower resolution satellite imagery worldwide. The map includes 15m TerraColor imagery at small and mid-scales (~1:591M down to ~1:288k) for the world. The map features Maxar imagery at 0.3m resolution for select metropolitan areas around the world, 0.5m resolution across the United States and parts of Western Europe, and 1m resolution imagery across the rest of the world. The world satellite and aerial imagery map features high-resolution aerial photography contributed by the GIS User Community. This imagery ranges from 0.3m to 0.03m resolution (down to ~1:280 in select communities). The world satellite image display effect is shown in Figure 3-7.




Figure 3-7: The world satellite image map display effect

The local details somewhere for the world satellite and aerial imagery map are shown in Figure 3-8.




Figure 3-8: The world satellite image map somewhere local details

The world physical map presents the Natural Earth physical map at 1.24km per pixel for the world and 500m for the coterminous United States. This map display effect is shown in Figure 3-9.




Figure 3-9: The world physical map display effect

The local details somewhere for the world physical map are shown in Figure 3-10.




Figure 3-10: The world physical map somewhere local details

The world shaded relief map portrays surface elevation as shaded relief. This map is used as a basemap layer to add shaded relief to other GIS maps, such as the ArcGIS Online World Street Map. It is especially useful in maps that do not contain orthoimagery. The map resolution (cell size) is as follows: 30 Meters for the U.S. 90 Meters for all land areas between 60 degrees north and 56 degrees south latitude. 1 KM resolution above 60 degrees north and 56 degrees south. The shaded relief imagery was developed by Esri using GTOPO30, Shuttle Radar Topography Mission (SRTM), and National Elevation Data (NED) data from the USGS. The world shaded relief map display effect is shown in Figure 3-11.




Figure 3-11: The world shaded relief map display effect

The local details somewhere for the world shaded relief map are shown in Figure 3-12.




Figure 3-12: The world shaded relief map somewhere local details

The world street map presents highway-level data for the world. Street-level data includes the United States; much of Canada; Mexico; Europe; Japan; Australia and New Zealand; India; South America and Central America; Africa; and most of the Middle East. This comprehensive street map includes highways, major roads, minor roads, one-way arrow indicators, railways, water features, administrative boundaries, cities, parks, and landmarks, overlaid on shaded relief imagery for added context. Display effect is shown in Figure 3-13.




Figure 3-13: The world street map display effect

The local details somewhere for the world street map are shown in Figure 3-14.




Figure 3-14: The world street map somewhere local details

The world terrain base map is designed to be used as a base map by GIS professionals to overlay other thematic layers such as demographics or land cover. The base map features shaded relief imagery, bathymetry, and coastal water features designed to provide a neutral background for other data layers. The base map currently provides coverage for the world down to a scale of ~1:1m. The world terrain base map display effect is shown in Figure 3-15.




Figure 3-15: The world terrain base map display effect

The local details somewhere for the world terrain base map are shown in Figure 3-16.




Figure 3-16: The world terrain base map somewhere local details

The world topographic base map is designed to be used as a basemap by GIS professionals and as a reference map by anyone. The map includes administrative boundaries, cities, water features, physiographic features, parks, landmarks, highways, roads, railways, and airports overlaid on land cover and shaded relief imagery for added context. The world topographic base map display effect is shown in Figure 3-17.




Figure 3-17: The world topographic base map display effect

The local details somewhere for the world topographic base map are shown in Figure 3-18.




Figure 3-18: The world topographic base map somewhere local details

The world geomorphology and road network map presents highway-level data for the world. Street-level data includes the United States; much of Canada; Japan; Europe; Australia and New Zealand; India; South America and Central America; most of the Middle East; Egypt and Morocco; and parts of southern Africa including Botswana, Lesotho, Namibia, South Africa, and Swaziland. This comprehensive street map includes highways, major roads, minor roads, one-way arrow indicators, railways, water features, administrative boundaries, cities, parks, and landmarks, overlaid on shaded relief imagery for added context. This map display effect is shown in Figure 3-19.




Figure 3-19: The world geomorphology and road network display effect

The local details somewhere for the world geomorphology and road network map are shown in Figure 3-20.




Figure 3-20: The world geomorphology and road network map somewhere local details

## 3.2 Load business layer

The map view supports the following map data: Shp file type, Geodatabase geographic database type, WMS, WFS, WCS, WMTS and other standardized map services from GeoServer, and various online map resources that follow standardized specifications. The layers added to the view are classified according to the data source path and displayed in the layer node on the left. The hierarchical operation is implemented through the right-click shortcut menu.

### 3.2.1 Load local layers

PyramidMap supports vector and ratsre type layers. Select "Load local vector layer" in the toolbar, as shown in Figure 3-21.




Figure 3-21: Load local vector layer

Loading the required layer through file browser. After successful loading, it will be displayed in the map view, and the layers mount node on the left will be formed, as shown in Figure 3-22.




Figure 3-22: Load local shp file browser

Then the shp selected display in the map viewer, as shown in Figure 3-23.




Figure 3-23: Load local shp file and display in the map viewer

At the same time, PyramidMap provides a more convenient operation, assuming the map initialization view is shown in Figure 3-24.




Figure 3-24: The map viewer initialization

You can drag and drop the shapefiles to the map view displaying directly, as shown in Figure 3-25.




Figure 3-25: Drag and drop the shapefiles to the map view displaying directly

The display effect is shown in Figure 3-26.




Figure 3-26: Drag and drop the shapefiles displaying

The tutorial data used in the example is provided in PyramidMap [download](#).

PyramidMap supports batch file drag and drop operations, allowing multiple GeoTiff raster image files to be dragged and displayed in the map view, as shown in Figure 3-27.




Figure 3-27: Dragging and dropping GeoTiff directly to the map view

The display effect is shown in Figure 3-28.




Figure 3-28: Geotiff shown on the map view

The tutorial data used in the example is provided in PyramidMap [download](#).

### 3.2.2 Load Geodatabase layer

On the upper right side of the main interface, there are Geodatabase connections node that provides geodatabase layers. Double click the database node to dynamically load its internal layers. The layer node supports two loading methods: drag and double click. Different levels of nodes have corresponding shortcut menus.

The db node dynamically loads its internal layers and operates on the geodatabase, as shown in Figure 3-29.




Figure 3-29: Geodatabase node shortcut menu

The database node menu completes db connection testing, editing, layers management, and deletion operations.

The layer node menu supports exporting database tables to layer formats such as shp, kml, csv, geojson, and deleting them as shown in Figure 3-30.




Figure 3-30: Geodatabase layer node shortcut menu

Drag the layer node to the map view or double-click to display it, while forming a layer mount node on the left. The display process is shown in Figure 3-31.




Figure 3-31: Loading and displaying vector layers in Geodatabase

### 3.2.3 Load GeoServer layer

On the lower right side of the main interface, there is a GeoServer connection pool node, which provides GeoServer data source. Double click on the server node to dynamically load the internal workspace and layer nodes, as shown in Figure 3-32.




Figure 3-32: GeoServer node shortcut menu

The GeoServer node completes server connection testing, connection editing, obtaining server synchronization data (workspace, data storage and connection configuration), workspace management (client local management and syncing with remote server), importing layers and list managing, connection management, and other operations, as shown in Figure 3-33.




Figure 3-33: GeoServer workspace node shortcut menu

Specifically, in the data storage list, it is possible to edit and modify database connections for each item in the list, as well as maintain a layer list, including detailed information on layers and maintenance of additions and deletions. Layer nodes support dragging to the map view and double clicking to display, set style symbols, export, and delete operations, as shown in Figure 3-34.




Figure 3-34: GeoServer layer node shortcut menu

Especially in the layer node to set the binding relationship between the layer and the sld symbol inside the server, as shown in Figure 3-35.




Figure 3-35: Setting the binding relationship between layer and sld inside the GeoServer

PyramidMap will return a list of sld symbol of the same type on the server based on the geometry type of the selected layer, as shown in Figure 3-36.

No.	Sld bind	Workspace	Geometry	SymbolKind	Size(pixels)	Stroke(pixels)	StrokeColor	StrokeOpacity	FillColor	FillOpacity	AnnotationFilled	Select
1	cite_lakes		<input checked="" type="checkbox"/>		5.0	1	<input type="color"/>	1	<input type="color"/>	1.0		<input type="radio"/>
2	grass		<input checked="" type="checkbox"/>		5.0	1	<input type="color"/>	1.0	<input type="color"/>	1.0		<input type="radio"/>
3	green		<input checked="" type="checkbox"/>		5.0	1.0	<input type="color"/>	1.0	<input type="color"/>	1.0		<input type="radio"/>
4	polygon		<input checked="" type="checkbox"/>		5.0	1	<input type="color"/>	1.0	<input type="color"/>	1.0		<input type="radio"/>
5	provinceregion		<input checked="" type="checkbox"/>		5.0	1.0	<input type="color"/>	0.579999983310...	<input type="color"/>	0.57999998331...		<input checked="" type="radio"/>
6	restricted		<input checked="" type="checkbox"/>		5.0	1	<input type="color"/>	1.0	<input type="color"/>	0.7		<input type="radio"/>

Figure 3-36: Get the list of sld with the same type in the server based on the geometry type of the selected layer

Click "Yes" and the layer is successfully bound to the SLD symbol. As a result, the style setting of the vector layer in GeoServer has been implemented in the Pyramidmap client. GeoServer outputs the layer to the WMS service and will render according to this symbol.

Double click on the GeoServer node to dynamically load its internal workspace and its layers. Drag or double-click the layer node to display on the map view , while forming a layer mount node on the left. For example, the layer shown as in Figure 3-37.




Figure 3-37: Loading and displaying the selected Layer in GeoServer on map view

For the raster layer in GeoServer, the same operation process applies, taking one image layer in the top space as an example, as shown in Figure 3-38.




Figure 3-38: Loading and displaying the image layer of GeoServer on map view

### 3.3 Visible layer node

### 3.3.1 Layer control

The layers in the main map view are classified and managed in checkbox tree nodes. It supports the popup menu and checked visible controlling on each layer node, and the corresponding operations are implemented according to the layer type. The following is layer checkbox node classification and operation for vector layers, as shown in Figure 3-39.




Figure 3-39: Vector layer checkbox node classification and operation

The following is layer checkbox node classification and operation for raster layer, as shown in Figure 3-40.




Figure 3-40: Raster layer checkbox node classification and operation

You can control the visibility of layers and the data processing of different types of layers with the classification and operation of layer checkbox nodes.

### 3.3.2 SLD symbol

Select New sld Symbol from the shortcut menu of the vector layer display node to enter the sld symbol definition interface, as shown in Figure 3-41.




Figure 3-41: Definition and effect of map Sld symbols

With this operation, create a style definition file for point (Point, MultiPoint), line (LineString, MultiLineString), polygon (Polygon, MultiPolygon) type layers, and set the annotation field and font type, size, color, and annotation location. After the effect preview is satisfactory, save it as an sld file and include it in the PyramidMap resource pool for maintenance, The SLD resource pool maintained by PyramidMap client can provide feature symbol selection for layers. Select the SLD symbol on the layer node, as shown in Figure 3-42.




Figure 3-42: Select sld symbol on layer node

PyramidMap will automatically match the Sld data according to the geometry type of the selected layer, and provide a selection list of sld resources of the same geometry type, as shown in Figure 3-43.

Local styles selection console													
No	StdFileName	StdFilePath	GeometryTy...	Symbol	Size(pixel)	StrokeWidth(pixel)	StrokeColor	StrokeOpacity	FillColor	FillOpacity	LabelField	Check	
1	buildpoint1.sld	D:\\SLD\\buildpoint1.sld	<input checked="" type="radio"/>	Circle	12.0	1.0		1.0		1.0		<input type="radio"/>	
2	buildpoint2.sld	D:\\SLD\\buildpoint2.sld	<input checked="" type="radio"/>	Circle	12.0	1.0		1.0		1.0		<input type="radio"/>	
3	buildpoint3.sld	D:\\SLD\\buildpoint3.sld	<input checked="" type="radio"/>	Circle	12.0	1.0		1.0		1.0		<input type="radio"/>	
4	buildpoint5.sld	D:\\SLD\\buildpoint5.sld	<input checked="" type="radio"/>	Circle	12.0	1.0		1.0		1.0		<input checked="" type="checkbox"/>	
5	burg.sld	D:\\SLD\\burg.sld	<input checked="" type="radio"/>		20	1.0		1.0		1.0		<input type="radio"/>	
6	capitals.sld	D:\\SLD\\capitals.sld	<input checked="" type="radio"/>	circle	6	2		1.0		1.0		<input type="radio"/>	
7	generic.sld	D:\\SLD\\generic.sld	<input checked="" type="radio"/>	square	6	1		1		1.0		<input type="radio"/>	
8	point.sld	D:\\SLD\\point.sld	<input checked="" type="radio"/>	square	6	1.0		1.0		1.0		<input type="radio"/>	

Figure 3-43: SLD resource list of the same geometry type as the selected layer

The rendering effect of the selected sld is applied to the layer, as shown in Figure 3-44.




Figure 3-44: Rendering effect of layer after applying the selected sld

The tutorial data used in the example is provided in PyramidMap [download](#).

PyramidMap supports RGB raster rendering of image layers and grayscale rendering by band. Taking a certain image layer in GeoServer as an example, it is displayed in on the map view, as shown in Figure 3-45.




图3-45：在独立视图中对影像图层进行数字化编辑

Choose to perform grayscale rendering based on a single band, as shown in Figure 3-46.




Figure 3-46: Grayscale rendering of image layers by a single band

The rendering effect is shown in Figures 3-47.




Figure 3-47: Grayscale rendering of image layers by a single band

Select an RGB raster for rendering, and the rendering effect is shown in Figure 3-48.




Figure 3-48: Raster rendering of image layers in RGB

### 3.3.3 Features table

We take the UrbanAreas.shp layer as an example, which represents the population distribution of various counties in California. Select the "Open features table" option in the layer node on the left, as shown in Figure 3-49.




Figure 3-49: Open features table

The features table of the selected layer are shown in Figure 3-50.

Open features table

FeatureIdentifier	the_geom	NAME	STATE	FIPS	POPULATION	Shape_Leng	Shape_Area
UrbanAreas_1	MULTIPOLYGON (((124.0... Arcata	CA	06	16432	0.085162444102	5.09316293137E-4	
UrbanAreas_2	MULTIPOLYGON (((124.0... Crescent City	CA	06	5207	0.11336017569	7.02886583916E-4	
UrbanAreas_3	MULTIPOLYGON (((124.1... Eureka	CA	06	27025	0.237178691593	0.00185189011481	
UrbanAreas_4	MULTIPOLYGON (((123.8... Fort Bragg	CA	06	6078	0.066892726559	2.4830579547E-4	
UrbanAreas_5	MULTIPOLYGON (((124.1... Fortuna	CA	06	10119	0.0921948015015	3.41729353922E-4	
UrbanAreas_6	MULTIPOLYGON (((124.1... McKinleyville	CA	06	11111	0.0941052819447	4.73180787832E-4	
UrbanAreas_7	MULTIPOLYGON (((124.0... Rio Dell	CA	06	3012	0.071899331669	2.6812960847E-4	
UrbanAreas_8	MULTIPOLYGON (((124.1... Samoa	CA	06	0	0.0457780041008	1.30889868023E-4	
UrbanAreas_9	MULTIPOLYGON (((121.0... Cambria	CA	06	15976	0.0879829956946	3.23808914053E-4	
UrbanAreas_10	MULTIPOLYGON (((121.9... Carmel-by-the-Sea	CA	06	4239	0.0963393277869	4.1441850328E-4	
UrbanAreas_11	MULTIPOLYGON (((122.2... Alameda	CA	06	76459	0.270808674192	0.00206886941333	
UrbanAreas_12	MULTIPOLYGON (((121.9... Concord	CA	06	349025	1.77684091175	0.0222974338136	
UrbanAreas_13	MULTIPOLYGON (((121.9... Dublin	CA	06	23229	0.106006083791	4.61695388742E-4	
UrbanAreas_14	MULTIPOLYGON (((121.8... Komandorski Village	CA	06	50553	0.112939740389	5.07237042344E-4	
UrbanAreas_15	MULTIPOLYGON (((122.0... Oakland	CA	06	920303	1.91205791714	0.0307256708871	
UrbanAreas_16	MULTIPOLYGON (((122.4... San Francisco	CA	06	821112	0.728209282744	0.0110278961393	
UrbanAreas_17	MULTIPOLYGON (((122.4... Sausalito	CA	06	16831	0.131695300207	3.82024802665E-4	
UrbanAreas_18	MULTIPOLYGON (((121.9... Fremont	CA	06	211200	0.595098636365	0.00409017252937	
UrbanAreas_19	MULTIPOLYGON (((122.5... Mill Valley	CA	06	13038	0.138503050577	5.13458202338E-4	
UrbanAreas_20	MULTIPOLYGON (((121.9... Monterey	CA	06	48071	0.206289678759	0.001274777678267	
UrbanAreas_21	MULTIPOLYGON (((121.7... San Jose Metro Area	CA	06	1846132	3.00002064608	0.0684612110638	
UrbanAreas_22	MULTIPOLYGON (((121.9... Santa Cruz	CA	06	67289	0.256640532798	0.0023520809656	
UrbanAreas_23	MULTIPOLYGON (((121.8... Seaside	CA	06	38901	0.140816487534	7.410049290563E-4	
UrbanAreas_24	MULTIPOLYGON (((122.0... Union City	CA	06	53762	0.128686949979	6.68310104428E-4	
UrbanAreas_25	MULTIPOLYGON (((123.0... Cloverdale	CA	06	16605	0.0346827589552	7.27381994441E-4	
UrbanAreas_26	MULTIPOLYGON (((122.0... Colusa	CA	06	9143	0.0823201962166	3.71281458973E-4	
UrbanAreas_27	MULTIPOLYGON (((122.6... Cotati	CA	06	5714	0.160818989669	9.1083859123E-4	
UrbanAreas_28	MULTIPOLYGON (((122.8... Healdsburg	CA	06	15095	0.0839332264899	4.21364358202E-4	
UrbanAreas_29	MULTIPOLYGON (((122.5... Novato	CA	06	47585	0.224157081923	7.83675058805E-4	
UrbanAreas_30	MULTIPOLYGON (((122.6... Petaluma	CA	06	45797	0.297221561892	0.00194528733243	
UrbanAreas_31	MULTIPOLYGON (((122.5... San Rafael	CA	06	94573	0.726382938613	0.00326767289261	
UrbanAreas_32	MULTIPOLYGON (((122.6... Santa Rosa	CA	06	135987	0.273902766776	0.00255214589816	

Open query builder | Revert

Save | Delete | Help | Cancel

Figure 3-50: open features table of selected layer

The selected feature is highlighted on the map synchronously, as shown in Figure 3-51.




Figure 3-51: Selected features synchronized and highlighted on the map

Further query functions will be detailed in the section [4.1.3 Building a query analyzer].

### 3.3.4 Layer data export

It is easy to export data to the target format on the visible layer node in the main view, as shown in Figure 3-52.




Figure 3-52: Export the selected layer as the target data format

The target data format include: shp, kml, csv, GeoJSON, all of these are commonly used data in GIS and can be converted to each other as needed. We will provide a detailed explanation on data conversion in the **[6 Map data and conversion]** section.

### 3.3.5 Restore to the layer extend

At any time, if you need to restore the map to the original visible range of a layer, you can select that layer and choose the right-click shortcut menu "Restore to the layer extend" to adapt the map view to the extend of this layer as shown in Figure 3-53.




Figure 3-53: select that layer and choose the right-click shortcut menu "Restore to the layer extend" to adapt the map view

The map view is restored to the visible extend of the selected layer, as shown in Figure 3-54.




Figure 3-54: The map view is restored to the visible extend of the selected layer

## 4 Map query and editing

PyramidMap aims to provide users with a simple, easy-to-use, accurate, and fast map query and editing system. Its most distinctive features include visual interface interaction, bidirectional linkage of charts, flexible map editing, efficient data updates, and comprehensive service coverage. Specifically, in terms of service coverage, it supports shp/kml/csv/excel/geojson multi type data conversion, DBMS geodatabase, and WFS standardized service interfaces, thus meeting the application requirements of multiple types of GIS projects.

### 4.1 Map query

PyramidMap provides graphical and tabular data queries, allowing you to select features in the map view or layer data table for real-time interactive queries with the map view. Furthermore, you can use the query tool provided by the system to independently build SQL query analysis statements, achieving more accurate and powerful layer query functions. The Shp data used in this example is provided in PyramidMap [Download shp tutorial data](#).

#### 4.1.1 Feature Selection query

PyramidMap supports clicking on map features for selection, with supported feature types including Point/MultiPoint, LineString/MultiLineString/, Polygon/MultiPolygon. The selected feature will be highlighted on the map, and the data table will be opened to locate the record location of the feature. You can modify it except for FID, the\_Geometry and Blob binary field. The feature selection operation is shown in Figure 4-1.




Figure 4-1: Select feature on map

Click on the "Select features" tool in the map toolbar, then select and highlight the selected feature on map, and open the data table as shown in Figure 4-2.

Layer features table													
FeatureIdentifier	the_geom	NAME	STATE_NAME	STATE_FIPS	CNTY_FIPS	FIPS	POP2000	POP...	...	...	...	...	...
Counties_55	MULTIPOL...	Tuolumne	California	06	102	06109	54501	59730	...	...	...	...	...

Save   Delete   Cancel

Figure 4-2: Open data table of the selected feature

At the same time, the selected feature is highlighted on the map, as shown in Figure 4-3.




Figure 4-3: the selected feature is highlighted on the map

Double click on the data table to make all fields editable except for FID, geometry and blob binary type. Enter new data and click save to commit and update the map data. Click 'Delete' and confirm to delete the selected feature. PyramidMap supports editing on shp vector, geodatabase vector and WFS services layer such as of GeoServer.

## 4.1.2 Feature table query

Select the "Open Data Table" option in the left layer node of the main view, as shown in Figure 4-4.




Figure 4-4: Opening the layer features table

The feature data table and query module of the selected layer are shown in Figure 4-5.

FeatureIdentifier	the_geom	NAME	STATE	FIPS	POPULATION	Shape_Leng	Shape_Area
UrbanAreas.1	MULTIPOLYGON (((-124.0... Arcata	CA	06	16432	0.085162444102	5.09316293137E-4	
UrbanAreas.2	MULTIPOLYGON (((-124.1... Crescent City	CA	06	5207	0.11336017569	7.02886583916E-4	
UrbanAreas.3	MULTIPOLYGON (((-124.1... Eureka	CA	06	27025	0.237178691593	0.00186189011481	
UrbanAreas.4	MULTIPOLYGON (((-123.8... Fort Bragg	CA	06	6078	0.066892726559	2.4830579547E-4	
UrbanAreas.5	MULTIPOLYGON (((-124.1... Fortuna	CA	06	10119	0.0921948015015	3.41729353922E-4	
UrbanAreas.6	MULTIPOLYGON (((-124.1... McKinleyville	CA	06	11111	0.0941052819447	4.73180787832E-4	
UrbanAreas.7	MULTIPOLYGON (((-124.0... Rio Dell	CA	06	3012	0.0718199331669	2.6812960847E-4	
UrbanAreas.8	MULTIPOLYGON (((-124.1... Samoa	CA	06	0	0.0457780041006	1.30889868023E-4	
UrbanAreas.9	MULTIPOLYGON (((-121.0... Cambria	CA	06	15976	0.0878829958946	3.23808914053E-4	
UrbanAreas.10	MULTIPOLYGON (((-121.9... Carmel-by-the-Sea	CA	06	4239	0.0693392377869	4.1441850328E-4	
UrbanAreas.11	MULTIPOLYGON (((-122.2... Alameda	CA	06	76459	0.270808674192	0.00206886941333	
UrbanAreas.12	MULTIPOLYGON (((-121.9... Concord	CA	06	349025	1.77684091175	0.0222974338136	
UrbanAreas.13	MULTIPOLYGON (((-121.9... Dublin	CA	06	23229	0.106006083791	4.61695388742E-4	
UrbanAreas.14	MULTIPOLYGON (((-121.8... Komandorski Village	CA	06	50553	0.1128939740389	5.07237042344E-4	
UrbanAreas.15	MULTIPOLYGON (((-122.0... Oakland	CA	06	920303	1.91205791714	0.0307256708871	
UrbanAreas.16	MULTIPOLYGON (((-122.4... San Francisco	CA	06	821112	0.728209282744	0.0110278961393	
UrbanAreas.17	MULTIPOLYGON (((-122.4... Sausalito	CA	06	16831	0.131695300207	3.82024802665E-4	
UrbanAreas.18	MULTIPOLYGON (((-121.9... Fremont	CA	06	211200	0.595098636365	0.00409017252937	
UrbanAreas.19	MULTIPOLYGON (((-122.5... Mill Valley	CA	06	13038	0.138503050577	5.13458202338E-4	
UrbanAreas.20	MULTIPOLYGON (((-121.9... Monterey	CA	06	48071	0.2062896787759	0.00127477678267	
UrbanAreas.21	MULTIPOLYGON (((-121.7... San Jose Metro Area	CA	06	1846132	3.09002064606	0.0684612110638	
UrbanAreas.22	MULTIPOLYGON (((-121.9... Santa Cruz	CA	06	67289	0.266640532798	0.0023528080956	
UrbanAreas.23	MULTIPOLYGON (((-121.8... Seaside	CA	06	38901	0.140816487534	7.41004929063E-4	
UrbanAreas.24	MULTIPOLYGON (((-122.0... Union City	CA	06	53762	0.128686949979	6.88310104428E-4	
UrbanAreas.25	MULTIPOLYGON (((-123.0... Colverdale	CA	06	16605	0.0346827589552	7.27381994441E-5	
UrbanAreas.26	MULTIPOLYGON (((-122.0... Colusa	CA	06	9143	0.0823201962166	3.71281458973E-4	
UrbanAreas.27	MULTIPOLYGON (((-122.6... Cotati	CA	06	5714	0.160818989669	9.1083859123E-4	
UrbanAreas.28	MULTIPOLYGON (((-122.8... Healdsburg	CA	06	15095	0.0839332264899	4.21364358202E-4	
UrbanAreas.29	MULTIPOLYGON (((-122.5... Novato	CA	06	47585	0.224157081923	7.83675058085E-4	
UrbanAreas.30	MULTIPOLYGON (((-122.6... Petaluma	CA	06	45797	0.297221581992	0.00194528732343	
UrbanAreas.31	MULTIPOLYGON (((-122.5... San Rafael	CA	06	94573	0.72638293613	0.00326767289261	
UrbanAreas.32	MULTIPOLYGON (((-122.6... Santa Rosa	CA	06	1135987	0.273802766776	0.00256214588916	

Figure 4-5: Opening the layer features table

The selected feature is highlighted on the map synchronously, as shown in Figure 4-6.




Figure 4-6: The selected feature is highlighted on the map synchronously

### 4.1.3 Building query analyzer

In the layer data table interface, you can build a combined query condition based on all fields through the query tool to realize simple and complex queries on layers, as shown in Figure 4-7.




Figure 4-7: Layer table query constructor

In the query constructor, you can verify the validity of the built query statements, as shown in Figure 4-8.




Figure 4-8: Query statement validation

The validation results are shown in Figure 4-9.



Figure 4-9: Query statement validation results

Click "Apply" to execute the query. Based on the above construction conditions, the data table query results are shown in Figure 4-10.

FeatureIdentifier	the_geom	NAME	STCTYFIPS	ELEV_METER	LABEL_FLAG
Buildings_1867	POINT (-120.38602709899993 37.9...)	Morgan Mansion	06109	565.0	0
Buildings_1868	POINT (-120.3849159539999 37.9...)	Sonora City Hall	06109	565.0	0
Buildings_1869	POINT (-120.38158251899993 37.9...)	Sugg House	06109	547.0	0
Buildings_1870	POINT (-120.38408263399992 37.9...)	Tuolumne County Courthouse	06109	557.0	0
Buildings_1871	POINT (-120.38408263399992 37.9...)	Tuolumne County Law Library	06109	557.0	0
Buildings_1872	POINT (-120.38574927399992 37.9...)	Tuolumne County Museum	06109	548.0	0
Buildings_1873	POINT (-120.23798654499998 37.9...)	Memorial Hall	06109	790.0	0
Buildings_1874	POINT (-120.38789313199994 37.9...)	Tuolumne County Free Library	06109	626.0	0
Buildings_1875	POINT (-120.29991375299994 37.9...)	Moccasin Creek Power House	06109	283.0	0
Buildings_2272	POINT (-120.38824984799993 38.0...)	Columbia College Library	06109	698.0	0
Buildings_2273	POINT (-120.40047274799991 38.0...)	Columbia Fire House	06109	651.0	0
Buildings_2274	POINT (-120.40019492399995 38.0...)	Claverie Building	06109	655.0	0
Buildings_2275	POINT (-120.40047274799991 38.0...)	Franklin and Wolfe Building	06109	647.0	0
Buildings_2276	POINT (-120.40102824399992 38.0...)	Hildebrand Building	06109	648.0	0
Buildings_2277	POINT (-120.40047274799991 38.0...)	J Levy Building	06109	645.0	0
Buildings_2278	POINT (-120.40047274799991 38.0...)	Knapp Building	06109	650.0	0
Buildings_2279	POINT (-120.40102824399992 38.0...)	Leavitt and Walker Building	06109	649.0	0
Buildings_2280	POINT (-120.40047274799991 38.0...)	Magedini Building	06109	652.0	0
Buildings_2281	POINT (-120.4015838929999 38.0...)	Masonic Hall	06109	647.0	0
Buildings_2282	POINT (-120.4015838929999 38.0...)	McChesney Building	06109	649.0	0
Buildings_2283	POINT (-120.40102824399992 38.0...)	McCheesney and Mills Building	06109	647.0	0
Buildings_2284	POINT (-120.4021387759999 38.0...)	Mississippi House	06109	641.0	0
Buildings_2285	POINT (-120.3868610319999 38.0...)	Miwok Cultural Center	06109	706.0	0
Buildings_2286	POINT (-120.40047274799991 38.0...)	North Brainard Building	06109	647.0	0
Buildings_2287	POINT (-120.40047274799991 38.0...)	Schwarze Building	06109	651.0	0
Buildings_2288	POINT (-120.40102824399992 38.0...)	Soderer and Marshall Building	06109	646.0	0
Buildings_2289	POINT (-120.40047274799991 38.0...)	South Brainard Building	06109	646.0	0
Buildings_2290	POINT (-120.40130606899993 38.0...)	Tuolumne Engine Company Number	06109	649.0	0
Buildings_2291	POINT (-120.22713226999991 38.0...)	Twain Harte Community Center	06109	1124.0	0
Buildings_3134	POINT (-116.96724609699993 33.7...)	Hemet Public Library	06065	488.0	0
Buildings_3321	POINT (-116.86724657999991 32.8...)	Crest Branch San Diego County Libr...	06073	488.0	0

Figure 4-10: The data table query results

The query results are displayed on the map synchronously, as shown in Figure 4-11.




Figure 4-11: The query results are displayed on the map synchronously

In particular, the feature data table interacts with the map. Further, the editing, modification and deletion of feature attribute data can be completed in the data table, and the data can be submitted and saved according to the layer data source type. It supports the Shp vector file type, Geodatabase geographic database type, and GeoServer map server type.

## 4.2 Map editing

Map data editing includes the creation, modification, and deletion of point, line, and surface type map features. This process not only includes attribute data, but also involves editing spatial geometric vectors. This is the biggest difference from ordinary data and also the characteristic and difficulty of GIS data processing. Therefore, map editing is not an easy process to achieve in any GIS system. Based on this, PyramidMap is committed to providing users with a simple and user-friendly map editing tool that conforms to their habits, helping them complete graphic drawing and digital editing, and achieving easy connection and smooth switching between the

two processes. All designs are designed to maximize user convenience, and the ultimate goal is also achieved according to this principle. PyramidMap map editing mainly focuses on vector layers, including Shp file types, GeoDatabase enterprise level geographic database types (supporting Oracle, Postgre, MySQL), and Map Server (supporting GeoServer) WFS layer service types. The Shp data used in this example is provided in PyramidMap [Download shp experimental data] (<https://www.pyramidmap.com/download/4.2-shp.zip>) .

## 4.2.1 Create Shp

In PyramidMap, you can create your own Sh-style vector layer. Users can independently select the feature geometry type, map coordinate system, create layer fields and data types, and create vector layers that fully meet their needs. The design interface is shown in Figure 4-12.




Figure 4-12: Shp layer data structure design

The Shp layer data structure includes three aspects: geometric type, coordinate system, and attribute data. The geometric type indicates the geometric shape of map features, including point (Point/MultiPoint), line (LineString/MultiLineString), and polygon (Polygon/MultiPolygon) types; The coordinate system is responsible for defining and describing the coordinate positions of map features, so as to display them in the correct positions and ranges. At the same time, digital maps not only have spatial data, but also can carry various types of attribute data, which is the unity of spatial and attribute data. PyramidMap covers most commonly used standard coordinate systems at present, including the GCS geographic coordinate system and the PCS projection coordinate system. GCS is responsible for the description of the spatial three-dimensional position, such as WGS84. PCS can understand the projection of the spatial position on the plane, and is responsible for the description of the plane position, such as WGS84 Web Mercator, which

is the main coordinate system adopted by the current Web map. PyramidMap realizes the selection of coordinate system through classification list, and provides keyword mode to realize quick query and selection, as shown in Figure 4-13.




Figure 4-13: Fast selection of coordinate system through keywords

For a Shp type layer, it can have field information, including field naming, data type, and so on, like common database tables, to store all common types of data except spatial data, and realize the attribute information description of a map feature. Attribute data types include text, long integer, short integer, floating point type, double precision type and date time type. The creation process is shown in Figure 4-14.




Figure 4-14: Design the field structure of Shp layer table

The created Shp layer is automatically added to the layer resource pool of PyramidMap for unified management, and can be selected from the resource pool list for all-purpose , as shown in Figure 4-15.

No	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCS(SRID)	Counts	State	Check
4	Countries.shp	E:\Maps\gas\countries.shp	From local directory	MultiPolygon	Geometry	GCS_WGS_1984 EPSG:4326	56	Normal	
5	GoldCoast.shp	E:\Maps\California\goldcoast.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	537	Normal	
6	Hospitals.shp	E:\Maps\California\hospitals.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	438	Normal	
7	Lakes.shp	E:\Maps\California\lakes.shp	From local directory	MultiPolygon	MultiPolygon	GCS_WGS_1984 EPSG:4326	2	Normal	
8	Landmark\Areas.shp	E:\Maps\California\Landmark\areas.shp	From local directory	MultiPolygon	MultiPolygon	GCS_WGS_1984 EPSG:4326	10467	Normal	
9	MajorRoads.shp	E:\Maps\California\majorroads.shp	From local directory	MultiLineString	MultiLineString	GCS_WGS_1984 EPSG:4326	72033	Normal	
10	Rivers.shp	E:\Maps\California\rivers.shp	From local directory	MultiLineString	MultiLineString	GCS_WGS_1984 EPSG:4326	4	Normal	
11	Schools.shp	E:\Maps\California\schools.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	11381	Normal	
12	States.shp	E:\Maps\California\states.shp	From local directory	MultiPolygon	MultiPolygon	GCS_WGS_1984 EPSG:4326	1	Normal	
13	UrbanAreas.shp	E:\Maps\California\urbanareas.shp	From local directory	MultiPolygon	MultiPolygon	GCS_WGS_1984 EPSG:4326	191	Normal	
14	CAPITAL_POINT.shp	E:\Maps\layers\california\capital_point.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	1	missing	
15	CITY.shp	E:\Maps\layers\california\city.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	308	Normal	
16	CITY_REGION.shp	E:\Maps\layers\california\city_region.shp	From db oracle104	MultiPolygon	MultiPolygon	WGS_84 EPSG:4326	385	missing	
17	COUNTY_POINT.shp	E:\Maps\layers\california\county_point.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	2862	missing	
18	COUNTY_REGION.shp	E:\Maps\layers\california\county_region.shp	From db oracle104	MultiPolygon	MultiPolygon	WGS_84 EPSG:4326	2918	missing	
19	GAS_CONDENSATE_TANK.shp	E:\Maps\layers\california\gas_condensate_tank.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	8	missing	
20	GAS_PIPE.shp	E:\Maps\layers\california\gas_pipe.shp	From db oracle104	MultiLineString	MultiLineString	WGS_84 EPSG:4326	7946	missing	
21	GAS_PIPE_CAP.shp	E:\Maps\layers\california\gas_pipe_cap.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	12290	missing	
22	GAS_PRESSURE_BOX.shp	E:\Maps\layers\california\gas_pressure_box.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	30	missing	
23	GAS_PRESSURE_CABINET.shp	E:\Maps\layers\california\gas_pressure_cabinet.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	122	missing	
24	GAS_PRESSURE_STATION.shp	E:\Maps\layers\california\gas_pressure_station.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	1	missing	
25	GAS_PROTECTIVE_PIPE.shp	E:\Maps\layers\california\gas_protective_pipe.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	54	missing	
26	GAS_SERVICING_WELL.shp	E:\Maps\layers\california\gas_servicing_well.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	2	missing	
27	GAS_VALUE.shp	E:\Maps\layers\california\gas_value.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	1	missing	
28	GAS_VALUE_WELL.shp	E:\Maps\layers\california\gas_value_well.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	892	missing	
29	PROVINCE_POINT.shp	E:\Maps\layers\california\province_point.shp	From db oracle104	Point	Point	WGS_84 EPSG:4326	33	missing	
30	PROVINCE_REGION.shp	E:\Maps\layers\california\province_region.shp	From db oracle104	MultiPolygon	MultiPolygon	WGS_84 EPSG:4326	1089	missing	
31	gaspipeline.shp	E:\Maps\gas\gaspipeline.shp	Self-built Shp file	Point	Point	WGS_84 EPSG:4326	0	Normal	
32	capital_point.shp	E:\Maps\OTN\capital_point.shp	From local directory	Point	Point	WGS_84 EPSG:4326	1	Normal	
33	city_point.shp	E:\Maps\OTN\city_point.shp	From local directory	Point	Point	WGS_84 EPSG:4326	310	Normal	
34	city_region.shp	E:\Maps\OTN\city_region.shp	From local directory	MultiPolygon	MultiPolygon	WGS_84 EPSG:4326	373	Normal	
35	county_point.shp	E:\Maps\OTN\county_point.shp	From local directory	Point	Point	WGS_84 EPSG:4326	2862	Normal	
36	country_region.shp	E:\Maps\OTN\country_region.shp	From local directory	MultiPolygon	MultiPolygon	WGS_84 EPSG:4326	2918	Normal	
37	provinces_point.shp	E:\Maps\OTN\provinces_point.shp	From local directory	Point	Point	WGS_84 EPSG:4326	53	Normal	
38	province_region.shp	E:\Maps\OTN\provinces_region.shp	From local directory	MultiPolygon	MultiPolygon	WGS_84 EPSG:4326	1089	Normal	
39	gas_condensate_tank.shp	E:\Maps\gas\gas_condensate_tank.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	8	Normal	
40	gas_pipe.shp	E:\Maps\gas\gas_pipe.shp	From local directory	MultiLineString	MultiLineString	GCS_WGS_1984 EPSG:4326	8062	Normal	
41	gas_pipe_cap.shp	E:\Maps\gas\gas_pipe_cap.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	626	Normal	
42	gas_pressure_box.shp	E:\Maps\gas\gas_pressure_box.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	30	Normal	
43	gas_pressure_cabinet.shp	E:\Maps\gas\gas_pressure_cabinet.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	119	Normal	
44	gas_pressure_station.shp	E:\Maps\gas\gas_pressure_station.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	1	Normal	
45	gas_protective_pipe.shp	E:\Maps\gas\gas_protective_pipe.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	54	Normal	
46	gas_servicing_well.shp	E:\Maps\gas\gas_servicing_well.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	2	Normal	
47	gas_value.shp	E:\Maps\gas\gas_value.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	1	Normal	
48	gas_value_well.shp	E:\Maps\gas\gas_value_well.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	901	Normal	

Figure 4-15: The created Shp layer is added to the map resource pool

Select a layer in the resource pool list to draw map elements and assign data values, as shown in Figure 4-16.




Figure 4-16: Map feature drawing and data assignment for the created Shp layer

This is the complete workflow of creating a map instance and adding it to the resource management pool, mapping, and adding map data.

## 4.2.2 Shp editing

Map data consists of feature data that represents the geometric shape of spatial vectors and describes attributes. Therefore, map editing involves two parts, namely graphical editing and digital editing. PyramidMap implements the process of drawing multiple types of primitives such as points, lines, and faces based on the geometric type of the current layer, as well as inputting, submitting, and saving attribute data. The layer data sources supported by PyramidMap include: Shp file, geodatabase, and wfs type.

### 4.2.2.1 Main view editor

This section takes the Rivers.shp layer as an example, and the original layer is shown in Figure 4-17.




Figure 4-17: Creating new feature on Rivers.shp layer as an example

In the main view interface, activate the editing status of the selected layer through the "Enable selected and editing" option on the layer node shortcut menu, as shown in Figure 4-18.




Figure 4-18: Enable layer editing/center>

Click the "Draw" button in the toolbar, as shown in Figure 4-19.




Figure 4-19: The "Draw" button in the toolbar for vector layer editing

The map enters the editing state, and through mouse interaction, operations such as dotting, drawing lines, and drawing polygons can be achieved based on the geometric type of the layer. The Rivers layer represents rivers, belonging to the Linestring type. Create new features as shown in Figure 4-20.




Figure 4-20: Creating a new feature on Rivers.shp layer as an example

The green boxes in the figure show the three newly created river elements. The creation process includes two parts: drawing lineString type entities and inputting attribute data. PyramidMap combines the two organically and can switch smoothly. The attribute data input part is shown in Figure 4-21.

List of newly created features						
FeatureIdentifier	the_geom	NAME	SYSTEM	MILES	Shape_Leng	
fid-15744cd1_18b52e96396_-7fe0	MULTILINESTRING ((-118.9277118... river1	Natural rivers	112.5	220		
fid-15744cd1_18b52e96396_-7fe0	MULTILINESTRING ((-119.9240038... river2	Natural rivers	106.6	196		
fid-15744cd1_18b52e96396_-7ff7	MULTILINESTRING ((-119.4409531... river3	Natural rivers	90.7	155		

Figure 4-21: New Feature attribute data entry interface for rivers.shp

As shown in the figure, create a new element, click Start, draw with the mouse, double-click End, and the drawing is complete. Add a new entry for the attribute data of the element in the data table. Double click on the table Cell (all fields except FID, Geometry, and Blob can be edited) to switch to the editing input state, and at the same time, the corresponding map entities are highlighted to ensure accurate data correspondence and binding. Attribute data supports batch

input, submission and saving, and data updates to Shp layer files. It should be specifically pointed out that there are differences in the drawing methods for different geometric types of primitives, such as Point (point), lineString (line), and Polygon (face). We will compare and explain them in table form, as shown in Table 4-1.

Geometry	Drawing Example	Data schematic diagram	Description of drawing and data entry methods																																				
Point		<table border="1"> <tr><td>States....</td><td>MULTI...</td><td>North ...</td><td>37</td><td>S Atl</td><td>NC</td></tr> <tr><td>States....</td><td>MULTI...</td><td>Tenne...</td><td>47</td><td>E S Cen</td><td>TN</td></tr> <tr><td>states....</td><td>MULTI...</td><td>Texas</td><td>48</td><td>W S Cen</td><td>TX</td></tr> <tr><td>States....</td><td>MULTI...</td><td>New M...</td><td>35</td><td>Mtn</td><td>NM</td></tr> <tr><td>States....</td><td>MULTI...</td><td>Alabama</td><td>01</td><td>E S Cen</td><td>AL</td></tr> <tr><td>States....</td><td>MULTI...</td><td>Mississ...</td><td>28</td><td>E S Cen</td><td>MS</td></tr> </table>	States....	MULTI...	North ...	37	S Atl	NC	States....	MULTI...	Tenne...	47	E S Cen	TN	states....	MULTI...	Texas	48	W S Cen	TX	States....	MULTI...	New M...	35	Mtn	NM	States....	MULTI...	Alabama	01	E S Cen	AL	States....	MULTI...	Mississ...	28	E S Cen	MS	Open map editing, click on Draw with the mouse, add Point to the map, add attribute data for the new feature to the table, double-click cells, enter data, click Save commit to the layer data source.
States....	MULTI...	North ...	37	S Atl	NC																																		
States....	MULTI...	Tenne...	47	E S Cen	TN																																		
states....	MULTI...	Texas	48	W S Cen	TX																																		
States....	MULTI...	New M...	35	Mtn	NM																																		
States....	MULTI...	Alabama	01	E S Cen	AL																																		
States....	MULTI...	Mississ...	28	E S Cen	MS																																		
LineString		<table border="1"> <tr><td>States....</td><td>MULTI...</td><td>North ...</td><td>37</td><td>S Atl</td><td>NC</td></tr> <tr><td>States....</td><td>MULTI...</td><td>Tenne...</td><td>47</td><td>E S Cen</td><td>TN</td></tr> <tr><td>states....</td><td>MULTI...</td><td>Texas</td><td>48</td><td>W S Cen</td><td>TX</td></tr> <tr><td>States....</td><td>MULTI...</td><td>New M...</td><td>35</td><td>Mtn</td><td>NM</td></tr> <tr><td>States....</td><td>MULTI...</td><td>Alabama</td><td>01</td><td>E S Cen</td><td>AL</td></tr> <tr><td>States....</td><td>MULTI...</td><td>Mississ...</td><td>28</td><td>E S Cen</td><td>MS</td></tr> </table>	States....	MULTI...	North ...	37	S Atl	NC	States....	MULTI...	Tenne...	47	E S Cen	TN	states....	MULTI...	Texas	48	W S Cen	TX	States....	MULTI...	New M...	35	Mtn	NM	States....	MULTI...	Alabama	01	E S Cen	AL	States....	MULTI...	Mississ...	28	E S Cen	MS	Open map editing, click to start drawing with the mouse, continuously click on the drawing node, and connect the lines at the same time. Double click to end, and the formed lineString entity is added to the map. Add new data to the table, double-click the cell, enter the data, click Save submit to the layer data source. Please note that drawing a linestring requires at least two points.
States....	MULTI...	North ...	37	S Atl	NC																																		
States....	MULTI...	Tenne...	47	E S Cen	TN																																		
states....	MULTI...	Texas	48	W S Cen	TX																																		
States....	MULTI...	New M...	35	Mtn	NM																																		
States....	MULTI...	Alabama	01	E S Cen	AL																																		
States....	MULTI...	Mississ...	28	E S Cen	MS																																		
Polygon		<table border="1"> <tr><td>States....</td><td>MULTI...</td><td>North ...</td><td>37</td><td>S Atl</td><td>NC</td></tr> <tr><td>States....</td><td>MULTI...</td><td>Tenne...</td><td>47</td><td>E S Cen</td><td>TN</td></tr> <tr><td>states....</td><td>MULTI...</td><td>Texas</td><td>48</td><td>W S Cen</td><td>TX</td></tr> <tr><td>States....</td><td>MULTI...</td><td>New M...</td><td>35</td><td>Mtn</td><td>NM</td></tr> <tr><td>States....</td><td>MULTI...</td><td>Alabama</td><td>01</td><td>E S Cen</td><td>AL</td></tr> <tr><td>States....</td><td>MULTI...</td><td>Mississ...</td><td>28</td><td>E S Cen</td><td>MS</td></tr> </table>	States....	MULTI...	North ...	37	S Atl	NC	States....	MULTI...	Tenne...	47	E S Cen	TN	states....	MULTI...	Texas	48	W S Cen	TX	States....	MULTI...	New M...	35	Mtn	NM	States....	MULTI...	Alabama	01	E S Cen	AL	States....	MULTI...	Mississ...	28	E S Cen	MS	Open map editing, click to start drawing with the mouse, continuously click on the drawing node, and form an polygon. Double click to end, and the formed Polygon is added to the map with a new data item added to the table, double click on the cell, enter the data, click Save submit to the layer data source. Please note that drawing a polygon requires at least three points.
States....	MULTI...	North ...	37	S Atl	NC																																		
States....	MULTI...	Tenne...	47	E S Cen	TN																																		
states....	MULTI...	Texas	48	W S Cen	TX																																		
States....	MULTI...	New M...	35	Mtn	NM																																		
States....	MULTI...	Alabama	01	E S Cen	AL																																		
States....	MULTI...	Mississ...	28	E S Cen	MS																																		

Table 4-1: Drawing and input attribute data for different geometry feature

#### 4.2.2.2 Standalone view editor

Every vector layers such as shp, database layer and wfs layer can be previewed and edited in standalone view editor, as shown in Figure 4-22.




Figure 4-22: Open the data table in the independent view of each layer

Click "Open shp table" to open the layer feature data table, as shown in Figure 4-23.

Layer features table

FeatureIdentifier	the_geom	NAME	STATE	FIPS	POPULATION	Shape_Leng	Shape_Area
UrbanAreas_1	MULTIPOLYGON (((124.0...	Arcata	CA	06	16432	0.085162444102	5.09316293137E-4
UrbanAreas_2	MULTIPOLYGON (((124.1...	Crescent City	CA	06	5207	0.11336017569	7.02886583916E-4
UrbanAreas_3	MULTIPOLYGON (((124.1...	Eureka	CA	06	27025	0.237178691593	0.00185189011481
UrbanAreas_4	MULTIPOLYGON (((123.8...	Fort Bragg	CA	06	6078	0.066892726559	2.4830579547E-4
UrbanAreas_5	MULTIPOLYGON (((124.1...	Fortuna	CA	06	10119	0.0921948015015	3.41729353922E-4
UrbanAreas_6	MULTIPOLYGON (((124.1...	McKinleyville	CA	06	11111	0.0941052819447	4.73180787832E-4
UrbanAreas_7	MULTIPOLYGON (((124.0...	Rio Dell	CA	06	3012	0.0719189331669	2.6812660847E-4
UrbanAreas_8	MULTIPOLYGON (((124.1...	Samoa	CA	06	0	0.0457780041008	1.30886868023E-4
UrbanAreas_9	MULTIPOLYGON (((121.0...	Carbula	CA	06	15976	0.0879829956946	3.23808914053E-4
UrbanAreas_10	MULTIPOLYGON (((121.9...	Carmel-by-the-Sea	CA	06	4239	0.0963393277869	4.1441850328E-4
UrbanAreas_11	MULTIPOLYGON (((122.2...	Alameda	CA	06	76459	0.270808674192	0.00206886941333
UrbanAreas_12	MULTIPOLYGON (((121.9...	Concord	CA	06	349025	1.77684091175	0.0222974338136
UrbanAreas_13	MULTIPOLYGON (((121.9...	Dublin	CA	06	23229	0.106006083791	4.61695388742E-4
UrbanAreas_14	MULTIPOLYGON (((121.8...	Komandorski Village	CA	06	50553	0.112939740389	5.07237042344E-4
UrbanAreas_15	MULTIPOLYGON (((122.0...	Oakland	CA	06	920303	1.91205791714	0.0307256708871
UrbanAreas_16	MULTIPOLYGON (((122.4...	San Francisco	CA	06	821112	0.728209282744	0.0110278961393
UrbanAreas_17	MULTIPOLYGON (((122.4...	Sausalito	CA	06	16831	0.131695300207	3.82024802665E-4
UrbanAreas_18	MULTIPOLYGON (((121.9...	Fremont	CA	06	211200	0.595098636365	0.00409017252937
UrbanAreas_19	MULTIPOLYGON (((122.5...	Mill Valley	CA	06	13038	0.138503050577	5.13458202338E-4
UrbanAreas_20	MULTIPOLYGON (((121.9...	Monterey	CA	06	48071	0.2062896787759	0.001274777678267
UrbanAreas_24	MULTIPOLYGON (((122.0...	Union City	CA	06	53762	0.128688949979	6.88310104428E-4
UrbanAreas_25	MULTIPOLYGON (((123.0...	Cloverdale	CA	06	16605	0.0346827589552	7.27381994441E-5
UrbanAreas_26	MULTIPOLYGON (((122.0...	Colusa	CA	06	9143	0.0823201982166	3.71281458973E-4
UrbanAreas_27	MULTIPOLYGON (((122.6...	Cotati	CA	06	5714	0.160818989669	9.1063859123E-4
UrbanAreas_28	MULTIPOLYGON (((122.8...	Healdsburg	CA	06	15095	0.0839332264899	4.21364358202E-4
UrbanAreas_29	MULTIPOLYGON (((122.5...	Novato	CA	06	47585	0.224157081923	7.83675058805E-4
UrbanAreas_30	MULTIPOLYGON (((122.6...	Petaluma	CA	06	45795	0.297221561892	0.00194528733243
UrbanAreas_31	MULTIPOLYGON (((122.5...	San Rafael	CA	06	94573	0.72638293613	0.00326767289261
UrbanAreas_21	MULTIPOLYGON (((121.7...	San Jose Metro Area	CA	06	1846132	3.09002064606	0.0684612110638
UrbanAreas_22	MULTIPOLYGON (((121.9...	Santa Cruz	CA	06	67289	0.266640532798	0.00235280809656
UrbanAreas_23	MULTIPOLYGON (((121.8...	Seaside	CA	06	38901	0.140815487534	7.41004929063E-4
UrbanAreas_32	MULTIPOLYGON (((122.6...	Santa Rosa	CA	06	135987	0.273802766776	0.00255214588916

Open filter constructor    Restore

Save    Delete    Cancel

Figure 4-23: Edit attribute data in the shp independent view

Double click the table Cell (except for the Id and Geometry fields) to switch to the editing input status, and the selected features will be highlighted on the map view at the same time, as shown in Figure 4-24.




Figure 4-24: Layer feature highlight by being selected in independent view

Specifically, the feature table interacts with the map, and further, editing, modifying, and deleting feature attribute data can be completed in the data table, and saved according to the layer type. PyramidMap supports creating new feature and data editing on shp, geodatabase and WFS layers.

### 4.2.3 Database layer editing

PyramidMap performs graphical and digital editing of vector layers in geodatabases. Taking the LandmarkAreas layer in Postgis as an example, In the main view interface, activate the editing status of the selected layer through the layer node shortcut menu "Enable selected and editing" option, as shown in Figure 4-25.




Figure 4-25: Edit Geodatabase layer

Click the "Draw" button in the toolbar, as shown in Figure 4-26.




Figure 4-26: The "Draw" button in the toolbar for vector layer editing

The selected layer enters the editing state, interacts with the mouse, and implements operations such as dotting, drawing lines, and drawing polygons according to the geometric type of the layer, as shown in Figure 4-27.




Figure 4-27: Drawing feature graphic on map

After drawing, click the "Save" button in the toolbar, as shown in Figure 4-28.



Figure 4-28: The "Save" button in the toolbar for the edited map data

PyramidMap saves and submits the drawn feature data to the Geodatabase layer. After successful saving, the system returns a prompt, as shown in Figure 4-29.




Figure 4-29: Drawing and saving features to the Geodatabase layer

#### 4.2.4 GeoServer Layer Editing

PyramidMap supports graphic and digital editing of vector layers in GeoServer through WFS services.

In the main interface, open the GeoServer layer node. Taking the states layer in the top workspace as an example, it represents the contours of various states in the United States. Double click the layer node or drag it to display on the map view, as shown in Figure 4-30.




Figure 4-30: Double click on the GeoServer layer or drag it to display on the map view

Select the "Open features table" option from the right-click shortcut menu, the opened layer table is shown in Figure 4-31.

Feature ID	the_ge	STATE_ID	STATE	SUB_R_ID	STATE	LAND_ID	WATER_ID	PERS_ID	FAMILI_ID	HOUS_ID	MALE	FEMALE	WORK_ID	DRVAL_ID	CARP_ID	PUBTR_ID	EMPL_ID	UNEM_ID	SERV_ID	MANUAL	P_MALE	P_FEM	SAMP_ID
states_1	MULTI..._Illinois	17	E N Cen IL	14398...	1993.3...	1.1430...	29248...	42022...	55522...	58783...	41992...	37417...	65260...	53807...	54179...	38504...	13601...	82890...	0.486...	0.514...	17477...		
states_2	MULTI..._District_11	11	S Alt DC	159.055...	17.991...	60590...	12208...	24963...	28297...	32393...	22997...	10669...	36621.0...	11142...	30399...	23442...	65498.0...	22407...	0.466...	0.534...	72696.0...		
states_3	MULTI..._Delaw...	10	S Alt DE	5062.4...	1385.0...	66618...	17586...	24749...	32296...	34320...	24756...	25808...	42968.0...	8069.0...	33514...	13945.0...	87973.0...	44140.0...	0.485...	0.515...	10277...		
states_4	MULTI..._West_V...	54	S Alt WV	62384.2...	375.199...	17934...	50025...	68855...	86153...	93194...	66170...	49316...	10691...	7237.0...	67108...	71420...	20595...	12417...	0.48...	0.52...	31756...		
states_5	MULTI..._Maryland_24	24	S Alt MD	25318...	6189.7...	47814...	12458...	17489...	23196...	24627...	17830...	17238...	37644...	20216...	24813...	11163...	56869...	26030...	0.485...	0.515...	68477...		
states_6	MULTI..._Colora...	08	Mtn CO	28865...	960.364...	32943...	85421...	12824...	16312...	16630...	12330...	12168...	21027...	46893.0...	16332...	99438.0...	42107...	18176...	0.495...	0.505...	51267...		
states_7	MULTI..._Kentucky_21	21	E S Cen KY	10396...	1772.5...	45515...	12373...	17186...	21951...	23563...	16565...	15029...	27309...	48158.0...	19709...	14812...	55674...	36162...	0.482...	0.518...	64651...		
states_8	MULTI..._Kansas_20	20	WN Cen KS	21192...	1188.8...	24775...	65860...	94472...	12146...	12629...	90738...	92657...	13559...	7585.0...	11722...	57772...	34639...	16642...	0.49...	0.51...	45341...		
states_9	MULTI..._Virginia_51	51	S Alt VA	10253...	4263.82...	61608...	16276...	22890...	30309...	31497...	23432...	22786...	49925...	12579.0...	30251...	14192...	77718...	42007...	0.49...	0.51...	89808...		
states_10	MULTI..._Missouri_29	29	WN Cen MO	17844...	2100.1...	51170...	13683...	19612...	24643...	26527...	18611...	18160...	31204...	47129.0...	23673...	15538...	65978...	38674...	0.482...	0.518...	86499...		
states_11	MULTI..._Arizona_04	04	Mtn AZ	29433...	942.772...	36652...	94060...	13688...	18106...	18545...	13582...	11783...	23908...	32650.0...	16038...	12390...	45589...	18510...	0.494...	0.506...	46817...		
states_12	MULTI..._Idaho_40	40	WS Cen OR	17787...	3170.9...	31455...	85532...	12061...	15308...	16147...	11464...	10788...	19090...	71817...	13691...	10093...	40580...	20560...	0.487...	0.513...	52872...		
states_13	MULTI..._North_...	37	S Alt NC	12817...	10309...	66288...	18120...	25170...	32142...	34143...	24840...	25279...	52982...	33902.0...	32384...	16308...	88356...	70114...	0.485...	0.515...	10135...		
states_14	MULTI..._Tenne...	47	E S Cen TN	10582...	23115...	48299...	13340...	18352...	23261...	25037...	17773...	17470...	32117...	29542.0...	22306...	15212...	59640...	45618...	0.482...	0.518...	73665...		
states_15	MULTI..._Texas_48	48	WS Cen TX	68821...	17337...	1.7122...	43771...	51159...	84333...	86886...	61925...	58504...	11429...	16881...	76873...	59026...	21392...	10423...	0.493...	0.507...	24876...		
states_16	MULTI..._New_M...	35	Mtn NV	30447...	586.054...	13795...	35825...	49768...	67787...	70168...	49184...	47035...	87085.0...	60119.0...	57621...	49368.0...	16991...	68673.0...	0.491...	0.509...	23762...		
states_17	MULTI..._Alabama_01	01	E S Cen AL	13144...	43322...	40405...	11038...	15067...	19361...	21044...	14556...	13743...	26719...	13279.0...	17417...	12858...	47479...	36049...	0.479...	0.521...	63003...		
states_18	MULTI..._Mississ...	28	E S Cen MS	12150...	3598.3...	25732...	67437...	91137...	12306...	13425...	89074...	7742...	18401...	8020.0...	10287...	94712.0...	29407...	22264...	0.478...	0.522...	39962...		
states_19	MULTI..._Georgia_13	13	S Alt GA	14957...	3934.9...	64573...	17074...	23593...	31345...	32227...	23464...	23725...	46573...	86587.0...	30815...	18739...	80241...	53659...	0.485...	0.515...	93508...		
states_20	MULTI..._South_...	45	S Alt SC	77987...	4910.6...	34867...	92820...	12590...	16865...	17981...	12669...	12347...	27720...	18092.0...	16034...	94573.0...	45569...	33782...	0.484...	0.516...	50646...		
states_21	MULTI..._Arkans...	05	WS Cen AR	13487...	2867.3...	23507...	65155...	89117...	11330...	12176...	84972...	76463...	15302...	5096.0...	99428...	72079...	29879...	21065...	0.482...	0.518...	41422...		
states_22	MULTI..._Loui...	22	WS Cen LA	11283...	19978...	42199...	10984...	14992...	20313...	21885...	14688...	12393...	24734...	49252.0...	16416...	17530...	48002...	24375...	0.481...	0.519...	62881...		
states_23	MULTI..._Florida_12	12	S Alt FL	13985...	30456...	1.2937...	35118...	51348...	62617...	66762...	49435...	44680...	81854...	11635...	58104...	35676...	16839...	67505...	0.484...	0.516...	16038...		
states_24	MULTI..._Michigan_26	26	E N Cen MI	14713...	12547...	92952...	24391...	34193...	45127...	47825...	33887...	43315...	87085.0...	60119.0...	57621...	49368.0...	16991...	68673.0...	0.491...	0.509...	17358...		
states_25	MULTI..._Montana_30	30	Mtn MT	37699...	3858.5...	79908...	21166...	30616...	39576...	40329...	29324...	25037...	41442.0...	20502...	35072...	26217.0...	12309...	43619.0...	0.495...	0.505...	15009...		
states_26	MULTI..._Maine_23	23	N Eng ME	79939...	10236...	12279...	32868...	46531...	59785...	63007...	45629...	42410...	79763...	5084.0...	57184...	10278...	17283...	94926.0...	0.487...	0.513...	27432...		
states_27	MULTI..._North_...	38	WN Cen ND	17869...	4427.7...	63880...	16627...	24087...	31820...	32059...	23704...	20954...	31320...	1638.0...	28755...	16083...	10493...	33936.0...	0.494...	0.502...	15520...		
states_28	MULTI..._South_...	46	WN Cen SD	19657...	31894.9...	69600...	18030...	25903...	34249...	35350...	25082...	23347...	32610.0...	9711.0...	32189...	13983.0...	11959...	41921.0...	0.492...	0.508...	16274...		
states_29	MULTI..._Wyomi...	56	Mtn WY	25150...	1848.1...	45358...	11982...	16883...	22700...	22658...	16456...	15367...	28109.0...	2963.0...	20786...	13112.0...	71419.0...	29157.0...	0.5...	0.5...	83202.0...		
states_30	MULTI..._Wiscon...	55	E N Cen WI	13955...	8223.2...	47964...	12492...	17891...	23454...	24509...	17631...	17106...	26465...	57559.0...	23359...	12919...	68816...	42574...	0.489...	0.511...	11805...		
states_31	MULTI..._Idaho_16	16	Mtn ID	21432...	2131.1...	10067...	26319...	36072...	50095...	50579...	35913...	32988...	52958.0...	8572.0...	44370...	29070.0...	14480...	68391.0...	0.498...	0.502...	20159...		
states_32	MULTI..._Vermont_50	50	N Eng VT	23955...	947.04...	56275...	14489...	21085...	27549...	28726...	20980...	19880...	35711.0...	2033.0...	23814...	17600...	84759.0...	36048.0...	0.49...	0.51...	14637...		

Figure 4-41: Open GeoServer layer table

The selected features are highlighted on the map at the same time, as shown in Figure 4-42.




Figure 4-42: Highlighting the selected features in the layer table on the map

Double click on the table Cell (all fields except FID, Geometry, and Blob can be edited) to switch to the editing and entry status, supporting batch modification and submission and saving of attribute data through the wfs way.

## 5 Geodatabase and GeoServer

### 5.1 Geodatabase connection pool

PyramidMap supports direct connection access with geographic databases to realize the import, export, storage and conversion of map data, and supports (but is not limited to) Oracle, PostGIS (PostgreSQL+GIS function extension), MySQL, SQLServer and other databases. After PyramidMap creates a database connection, it is managed in the database connection pool mode to import, export, preview, edit and other operations of the map. PyramidMap provides two ways to create a geographic database connection: 1. create a database connection through the map database node on the main map display interface; 2. create a database connection on the database configuration page through "System" - "Geodatabase console" entrance.

#### 5.1.1 Geodatabase data source node

In the geographic database node of the main interface, double-click New Database Connection, as shown in Figure 5-1.




Figure 5-1: Main interface create new Geodatabase connection

Open the geographic database connection configuration interface, select the geographic database type, and enter the correct connection parameters. After the connection test is successful, it can be saved and created as an effective geographic database connection, included in the PyramidMap geographic database resource connection pool, and dynamically added to the geodatabase node and the inside layers node, as shown in Figure 5-2.




Figure 5-2: Geodatabase connection created successfully

Description of interface input parameters:

- GeoDB type: Select a database type (Oracle, PostGIS, MySQL)
- Connection name: Customize the Geodatabase connection name.
- Purpose: Customize the Geodatabase connection purpose describe.
- Host IP: IP address of the server where the Geodatabase is hosted.
- Port: The port number used by the database. (Default port number: Oracle 1521, Postgre 5432, MySQL 3306)
- Database instance: the name of the database's service instance to connect to.

- Schema: The schema to be connected is mainly for PostGIS, and others can be ignored. In Oracle, this parameter is consistent with the user name.
- The connection button: test whether the newly created database connection is valid.
- The save button: save the new database connection.
- The cancel button: Exit the interface without performing any operation.

## 5.1.2 Geodatabase connection pool

Open the Geodatabase connection pool interface through "System" - "Geodatabase console", or directly click the "GeoDB console" button in the toolbar, as shown in Figure 5-3.



Figure 5-3: Create a Geodatabase connection through the system settings portal

The geodatabase connection configuration page is shown in Figure 5-4.

No	DBConnection	Description	DBType	HostIP	Port	Schema	Instance	Encoding	Status	Test	Editor	Check
1	oracle104		oracle	172.19.126.104	1521	sde	geodata	GBK	Modified unsynced to server	Connect	Do edit	
2	sqlserver166		sql server	172.19.126.166	1433		geodata	GBK	New unsynced to server	Connect	Do edit	
3	sqlserver166A		sql server	172.19.126.166	1433		geodata	GBK	New unsynced to server	Connect	Do edit	
4	postgis104		postgis	127.0.0.1	5432	public	geo_data	GBK	Modified unsynced to server	Connect	Do edit	
5	geoserver1-clite-postgis		postgis	localhost	5432	public	geo_data	GBK	synced from Server	Connect	Do edit	
6	geoserver1-clite-postgis1		postgis	127.0.0.1	5432	public	geo_gas	GBK	synced from Server	Connect	Do edit	
7	geoserver1-clite-postgre1		postgis	127.0.0.1	5432	public	geo_gas	GBK	synced from Server	Connect	Do edit	
8	geoserver1-ohn-ohn_postgis		postgis	127.0.0.1	5432	figer	geo_gas	GBK	synced from Server	Connect	Do edit	
9	geoserver1-ohn-postgis0		postgis	127.0.0.1	5432	public	geo_data	GBK	synced from Server	Connect	Do edit	
10	sqlserver166b		sql server	172.19.126.166	1433		geodata	GBK	New unsynced to server	Connect	Do edit	
11	sqlserver166c		sql server	172.19.126.166	1433		geodata	GBK	New unsynced to server	Connect	Do edit	
12	mysql104		mysql	127.0.0.1	3306		geodata	GBK	Modified unsynced to server	Connect	Do edit	
13	sqlserver1		sql server	127.0.0.1	1433		geodata	GBK	New unsynced to server	Connect	Do edit	
14	geoserver2-l691-l6911		postgis	172.19.128.104	5432		geo_data	GBK	synced from Server	Connect	Do edit	
15	oracle104A		oracle	172.19.126.104	1521	sde	geodata	GBK	New unsynced to server	Connect	Do edit	

Add database connection:

GeoDB Type: postgis Connection name: postgis-local  
Host ip: 127.0.0.1 Host port: 5432 Purpose: The local postgis map data  
Database account: postgres Password:  
Please confirm with the database administrator:

Connect Save Cancel

Tips: Geodatabase connection succeeded 确定

Figure 5-4: Geodatabase Connection Configuration and pool

The connections in the pool can be retested, edited and deleted, as shown in Figure 5-5.




Figure 5-5: The connections in the pool can be retested, edited and deleted

Use the connection pool list to test, edit, modify, and delete the Geodatabase connection. Each connection has two button options : Connect and Do Edit.

.Connect: test whether the database connection is successful.

.Do edit: Re edit the Geodatabase connection to make it available.

## 5.2 GeoServer connection pool

PyramidMap supports direct connection access with GeoServer, realizes multi type layer publishing function, and provides layer service interface for WebGIS. After the connection parameters are configured and tested successfully, create and maintain the GeoServer resource connection pool. PyramidMap provides two ways to create a GeoServer connection: 1. Through the GeoServer tree node on the main interface; 2. Implement it on the GeoServer connection configuration module through "System" - "GeoServer console".

### 5.2.1 GeoServer data node

In the GeoServer connection node of the main interface, double-click Add GeoServer Connection, as shown in Figure 5-6.




Figure 5-6: Create GeoServer connection through double-clicking on the GeoServer node in the main interface

Open the GeoServer connection configuration interface, enter the correct connection parameters, after the connection testing successful, you can save and create a valid GeoServer connection and hosting the connection in resource pool, and dynamically add it to the GeoServer connection node. Description of interface input parameters:

- GeoServer name: Customize the GeoServer server connection naming.
- Description: Customize the GeoServer connection purpose describe.
- Host IP: IP address of the server where the GeoServer is hosted.
- Port: GeoServer port number. (The port number of the web server hosting GeoServer, such as Tomcat)
- GeoServer account: GeoServer administrator account, default admin, please contact the web administrator for confirmation.
- Password: GeoServer administrator password, please contact the web administrator for confirmation.
- GeoServer web name: The deployment name of GeoServer in the web service. The default is geoserver. Please contact the web administrator for confirmation.

## 5.2.2 GeoServer connection pool

Open the GeoServer connection pool management interface through "System" - "GeoServer console", or directly click the "GeoServer console" button in the toolbar, as shown in Figure 5-7.



Figure 5-7: Create GeoServer connection menu

In the GeoServer connection pool management interface, create a new GeoServer connection and incorporate it into the unified resource management pool. The workflow is shown in Figure 5-8.




Figure 5-8: Create GeoServer connection and connections pool

The GeoServer connection created successfully is added to the resource connection pool.

### 5.2.3 Manage GeoServer connections

PyramidMap maintain the GeoServer connections in resource pool, manage the server internal workspace, data storage and layers in the function

modules, as shown in Figure 5-9.




Figure 5-9: Internal management of GeoServer

GeoServer internal management identify:

- Try connect: test whether the selected map server connection is available.
- Open Connection editor: Edit the selected GeoServer connection properties.

- Sync from GeoServer: obtain the selected GeoServer workspace, data storage and database connection properties data, and synchronizing them to the client.
- Open space console: query, edit and modify, delete the workspace and data storage of the selected GeoServer.
- GeoServer layer preview: get the list of selected GeoServer layers and preview them.
- Delete connection: Delete the selected GeoServer connection.

## 5.3 GeoServer internal operate

The internal space of GeoServer is divided into three levels: workspaces, data storages and layers. As the client of GeoServer, PyramidMap can visually maintain these modules. PyramidMap provides multiple forms of access management to GeoServer server space.

### 5.3.1 GeoServer Workspace

Through the GeoServer node tree in the main interface, you can right-click on the GeoServer node layer and the workspace node layer to provide management access to the workspace and data storage. The management entry of the GeoServer node to the workspace is shown in Figure 5-10.




Figure 5-10: GeoServer node entrance to workspace

Enter the workspace management module, as shown in Figure 5-11.

GeoServer GeoServer workspace console												
workArea:		WorkSpace	NameSpace	wms	wfs	wcs	wmts	GeoServerConnection	SynchState	Check	OpenEditor	Delete
cite	http://www.opengeospatial.net/cite	<input checked="" type="checkbox"/>		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
tiger	http://www.census.gov	<input type="checkbox"/>		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
nurc	http://www.nurc.nato.int	<input type="checkbox"/>		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
sde	http://geoserver.sf.net	<input type="checkbox"/>		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
it.geosolutions	http://www.geo-solutions.it	<input type="checkbox"/>		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
topp	http://www.openplans.org/topp	<input type="checkbox"/>		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
sf	http://www.openplans.org/spearfish	<input type="checkbox"/>		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
digi_gas	http://www.digi_gas.com	<input type="checkbox"/>		<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete
oth	http://www.oth.com	<input type="checkbox"/>		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver100	synced from Server	<input type="checkbox"/>	Do edit	Delete

New workspace Sync from GeoServer Sync to GeoServer 0% All Cancel

Figure 5-11: The GeoServer's workspaces pool manage interface

In the workspace module, you can perform the following operations: create a new workspace, synchronize the server workspace to the client, and submit the client workspace to the server. In particular, in the workspace list management pool, you can provide independent attribute editors and delete each workspace in the list table. The new workspace interface and and data interaction with GeoServer is shown in Figure 5-12.




Figure 5-12: The new workspace interface and and data interaction with GeoServer

The new workspace will be automatically attached to the GeoServer node.

### 5.3.2 GeoServer data storage

In the workspace node, a data storage entry is provided, as shown in Figure 5-13.




Figure 5-13: Workspace node to data storage management entrance

Then enter the data storage management module, as shown in Figure 5-14.




Figure 5-14: The data storage pool interface from the workspace node

In the data storage module, you can perform the following operations: create a new data storage, synchronize the server side data storage to the client, and submit the client side data storage cache to the server. In particular, in the data storage list management pool, you can provide independent editing and deletion operations for each data storage, as shown in Figure 5-15.




figure5-15: Data storage management pool of GeoServer workspace

In the New Data Storage module. You can select the database type corresponding to the data storage, and select the geodatabase connection that matches the type to automatically bring in the configuration of database connection parameters. The selected database connection can be dynamically edited, as shown in Figure 5-16.




Figure 5-16: Edit the database connection for the datastorage

The predefined geodatabase connection serves as an independent resource management pool to provide data sources for GeoServer data storage.

### 5.3.3 GeoServer pool console

PyramidMap centrally manages GeoServer connections in the form of resource management pools, as shown in Figure 5-17.



Figure 5-17: GeoServer connections resource management pool entrance

PyramidMap creates and maintains the GeoServer resource connection pool, and manages and maintains its internal service space for each GeoServer connection. The module is shown in Figure 5-18.

A screenshot of the PyramidMap interface showing the GeoServer connections pool and operation options. The top menu bar and toolbar are visible. The main area displays a table of GeoServer connections with columns: No, GeoServerName, Description, HostIP, Port, WebName, WebUrl, and Check. Four entries are listed: geoserver1, geoserver2, geoserver3, and geoserver100. Below the table is a form for adding a new connection. Fields include 'GeoServer name' (with a placeholder 'geoserver'), 'Description' (empty), 'Host ip' (empty), 'Host port' (empty), 'GeoServer account' (with placeholder 'admin'), 'Password' (empty), 'GeoServer web name' (with placeholder 'geoserver'), and a note: 'It's the GeoServer hosted name in web server, default is geoserver. Please determine according to the actual deployment.' At the bottom of the form are 'Connect', 'Save', and 'Cancel' buttons. A red box highlights the 'Open space console' button in the toolbar above the form.

图5-18: GeoServer connections pool and operation options

Select the GeoServer and click “open space console” button, as shown in Figure 5-19.

WorkSpace	NameSpace	wms	wfs	wcs	wmts	GeoServerConnection	SynchState	Check	OpenEditor	Delete
cite	http://www.opengeospatial.net/cite	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input checked="" type="radio"/>	Do edit	Delete
tiger	http://www.census.gov	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
nurc	http://www.nurc.nato.int	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
sde	http://geoserver.sfr.net	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
it.geosolutions	http://www.geo-solutions.it	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
topp	http://www.openplans.org/topp	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
sf	http://www.openplans.org/spearfish	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced from Server	<input type="radio"/>	Do edit	Delete
otn	http://www.otn.com	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	geoserver1	synced to server	<input type="radio"/>	Do edit	Delete
test	http://www.test.com	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	geoserver1	New unsynced to server	<input type="radio"/>	Do edit	Delete

DataStorage	WorkSpace	DBType	DBConnection	Description	SynchState	Check	Connect	OpenEditor	LayersList	Delete
city_region	cite	shapefile			synced from Server	<input type="checkbox"/>	Connect	Do edit	Layers	Delete
county_point	cite	shapefile			synced from Server	<input type="checkbox"/>	Connect	Do edit	Layers	Delete
county_region	cite	shapefile			synced from Server	<input type="checkbox"/>	Connect	Do edit	Layers	Delete
province_point	cite	shapefile			synced from Server	<input type="checkbox"/>	Connect	Do edit	Layers	Delete
capital_point	cite	shapefile			synced to server	<input type="checkbox"/>	Connect	Do edit	Layers	Delete

Figure 5-19: GeoServer workspace and data storage managing pool

The GeoServer workspace and data storage managing pool module displays the list of all workspaces of the server and the data storages list of each workspace. The client side and the server side maintain two-way synchronization to achieve visual management of the server side data by the client side.

In particular, PyramidMap implements a client cache maintenance mechanism for GeoServer. New and modified workspaces and data stores are temporarily stored on the client. When necessary, they are submitted to the GeoServer server in batches. At the same time, the GeoServer server data can be synchronized to the client at any time. This is the two-way synchronization mechanism between PyramidMap and GeoServer.

## 6 Map data and conversion

PyramidMap supports five types of map data sources, namely Shp file vector layer, file image layer, Geodatabase vector layer, GeoServer vector layer and raster tile layer.

### 6.1 Vector layers pool

PyramidMap imports the client's Shp file vector layers into the resource pool through a file browser to form a Shp management list pool and supports various operations with corresponding buttons, as shown in Figure 6-1.

No	LayerFileName	LayerFilePath	Remarks	FeatureType	LayerType	UCS(SRID)	Encoding	Status	Check
1	gas_condensate_tank.shp	E:\Maps\gaspipe_shp\3857\gas_condensate_tank.shp	included in program management	vector	WGS_1984.Web_Mercator_Auxiliary_Sphere EP.	ISO-8859-1	Local hosting	<input type="checkbox"/>	
2	gas_pipe.shp	E:\Maps\gaspipe_shp\3857\gas_pipe.shp	included in program management	vector	WGS_1984.Web_Mercator_Auxiliary_Sphere EP.	ISO-8859-1	Local hosting	<input type="checkbox"/>	
3	gas_pipe_cap.shp	E:\Maps\gaspipe_shp\3857\gas_pipe_cap.shp	included in program management	vector	WGS_1984.Web_Mercator_Auxiliary_Sphere EP.	ISO-8859-1	Local hosting	<input type="checkbox"/>	
4	gas_pressure_box.shp	E:\Maps\gaspipe_shp\3857\gas_pressure_box.shp	included in program management	vector	WGS_1984.Web_Mercator_Auxiliary_Sphere EP.	ISO-8859-1	Local hosting	<input type="checkbox"/>	
5	gas_pressure_cabinet.shp	E:\Maps\gaspipe_shp\3857\gas_pressure_cabinet.shp	included in program management	vector	WGS_1984.Web_Mercator_Auxiliary_Sphere EP.	ISO-8859-1	Local hosting	<input type="checkbox"/>	
6	gas_pressure_station.shp	E:\Maps\gaspipe_shp\3857\gas_pressure_station.shp	included in program management	vector	WGS_1984.Web_Mercator_Auxiliary_Sphere EP.	ISO-8859-1	Local hosting	<input type="checkbox"/>	
7	gas_protective_pile.shp	E:\Maps\gaspipe_shp\3857\gas_protective_pile.shp	included in program management	vector	WGS_1984.Web_Mercator_Auxiliary_Sphere EP.	ISO-8859-1	Local hosting	<input type="checkbox"/>	
8	gas_servicing_well.shp	E:\Maps\gaspipe_shp\3857\gas_servicing_well.shp	included in program management	vector	WGS_1984.Web_Mercator_Auxiliary_Sphere EP.	ISO-8859-1	Local hosting	<input type="checkbox"/>	
9	gas_valve.shp	E:\Maps\gaspipe_shp\3857\gas_valve.shp	included in program management	vector	WGS_1984.Web_Mercator_Auxiliary_Sphere EP.	ISO-8859-1	Local hosting	<input type="checkbox"/>	
10	gas_valve_well.shp	E:\Maps\gaspipe_shp\3857\gas_valve_well.shp	included in program management	vector	WGS_1984.Web_Mercator_Auxiliary_Sphere EP.	ISO-8859-1	Local hosting	<input type="checkbox"/>	
11	geofield_point.shp	E:\Maps\OTN\geofield_point.shp	included in program management	vector	WGS_84 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
12	city_point.shp	E:\Maps\OTN\city_point.shp	included in program management	vector	WGS_84 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
13	city_region.shp	E:\Maps\OTN\city_region.shp	included in program management	vector	WGS_84 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
14	county_point.shp	E:\Maps\OTN\county_point.shp	included in program management	vector	WGS_84 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
15	county_region.shp	E:\Maps\OTN\county_region.shp	included in program management	vector	WGS_84 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
16	province_point.shp	E:\Maps\OTN\province_point.shp	included in program management	vector	WGS_84 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
17	province_region.shp	E:\Maps\OTN\province_region.shp	included in program management	vector	WGS_84 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
18	gas_condensate_tank.shp	E:\Maps\gaspipe_shp\gas_condensate_tank.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
19	gas_pipe.shp	E:\Maps\gaspipe_shp\gas_pipe.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
20	gas_pipe_cap.shp	E:\Maps\gaspipe_shp\gas_pipe_cap.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
21	gas_pressure_box.shp	E:\Maps\gaspipe_shp\gas_pressure_box.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
22	gas_pressure_cabinet.shp	E:\Maps\gaspipe_shp\gas_pressure_cabinet.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
23	gas_pressure_station.shp	E:\Maps\gaspipe_shp\gas_pressure_station.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
24	gas_protective_pile.shp	E:\Maps\gaspipe_shp\gas_protective_pile.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
25	gas_servicing_well.shp	E:\Maps\gaspipe_shp\gas_servicing_well.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
26	gas_valve.shp	E:\Maps\gaspipe_shp\gas_valve.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
27	gas_valve_well.shp	E:\Maps\gaspipe_shp\gas_valve_well.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
28	Buildings.shp	E:\Maps\California\Buildings.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
29	Cemefries.shp	E:\Maps\California\Cemefries.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
30	Churches.shp	E:\Maps\California\Churches.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
31	Counties.shp	E:\Maps\California\Counties.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
32	GolfCourses.shp	E:\Maps\California\GolfCourses.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
33	Hospitals.shp	E:\Maps\California\Hospitals.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
34	Lakes.shp	E:\Maps\California\Lakes.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
35	MajorRoads.shp	E:\Maps\California\MajorRoads.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
36	MajorRoads.shp	E:\Maps\California\majorRoads.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
37	Rivers.shp	E:\Maps\California\Rivers.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
38	Schools.shp	E:\Maps\California\Schools.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
39	States.shp	E:\Maps\California\States.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	
40	UrbanAreas.shp	E:\Maps\California\UrbanAreas.shp	included in program management	vector	GCS_WGS_1984 EPSG_4326	ISO-8859-1	Local hosting	<input type="checkbox"/>	

Figure 6-1: Shp layers resource pool

The vector layers pool displays information of every layer in a list format, including:

- Layer name.
- Layer file path.
- Data source types, including: local files, database layers, and GeoServer layers.
- Geometric indicate: Indicate the geometric type of the feature using an icon.
- Geometric type, include: Point/MultiPoint, LineString/MultiLineString, Polygon/MultiPolygon.
- Coordinate System (SRID): The definition of the coordinate system for a layer, including the coordinate system code.
- Data volume: The number of features in a layer.
- Status: The existence status of the current layer resource.

### 6.1.1 Vector layer preview

Through the map preview and editing options, the selected layer file will be opened in a separate map view to achieve layer preview and editing, as shown in Figure 6-2.




Figure 6-2: Open independent preview and editing view of single shp vector layer

Independent map view provides each layer with separate display, rendering, base map selection and overlay, graphical editing, attribute data editing in table, feature selection and deletion operations. It is a comprehensive map service for a single layer. The tutorial data used in this chapter is provided in PyramidMap [Download vector tutorial data](#).

## 6.1.2 Vector data processing

Pyramidmap manages and operates layers uniformly through resource pooling, including layer resource import, layer preview, coordinate system conversion, spatial processing, layer slicing, layer data export, and other operations. As shown in Figure 6-3.

PyramidMap Geotools Visualized Toolset-Local vector layer resource console

File MapData Geodatabase GeoServer System Help

No.	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCS(SRID)	Counts	State	Check
1	Buildings.shp	D:\maps\California\357\Buildings.shp	From local directory	● Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	4381	Normal	✓
2	Cemeteries.shp	D:\maps\California\357\Cemeteries.shp	From local directory	● Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	842	Normal	✓
3	Churches.shp	D:\maps\California\357\Churches.shp	From local directory	● Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	1836313	Normal	✓
4	Counries.shp	D:\maps\California\357\Countries.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	58	Normal	✓
5	GolfCourses.shp	D:\maps\California\357\GolfCourses.shp	From local directory	● Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	537	Normal	✓
6	Hospitals.shp	D:\maps\California\357\Hospitals.shp	From local directory	● Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	438	Normal	✓
7	Lakes.shp	D:\maps\California\357\Lakes.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	2	Normal	✓
8	LandmarkAreas.shp	D:\maps\California\357\LandmarkAreas.shp	From local directory	■ MultiLineString	MultilineString	WGS 84 / Pseudo-Mercator EPSG:3857	10467	Normal	✓
9	MajorRoads.shp	D:\maps\California\357\MajorRoads.shp	From local directory	■ MultiLineString	MultilineString	WGS 84 / Pseudo-Mercator EPSG:3857	72033	Normal	✓
10	Rivers.shp	D:\maps\California\357\Rivers.shp	From local directory	● Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	4	Normal	✓
11	Schools.shp	D:\maps\California\357\Schools.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	11381	Normal	✓
12	States.shp	D:\maps\California\357\States.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	1	Normal	✓
13	UrbanArea.shp	D:\maps\California\357\UrbanArea.shp	From local directory	● Point	Point	GCS_WGS_1984_EPSG:4326	181	Normal	✓
14	Buildings1.shp	D:\maps\California\Buildings.shp	From local directory	● Point	Point	GCS_WGS_1984_EPSG:4326	4381	Normal	✓
15	Cemeteries1.shp	D:\maps\California\Cemeteries.shp	From local directory	● Point	Point	GCS_WGS_1984_EPSG:4326	842	Normal	✓
16	Churches1.shp	D:\maps\California\Churches.shp	From local directory	● Point	Point	GCS_WGS_1984_EPSG:4326	1836313	Normal	✓
17	Counries1.shp	D:\maps\California\Countries.shp	From local directory	■ MultiPolygon	Multipolygon	GCS_WGS_1984_EPSG:4326	58	Normal	✓
18	GolfCourses1.shp	D:\maps\California\GolfCourses.shp	From local directory	● Point	Point	GCS_WGS_1984_EPSG:4326	537	Normal	✓
19	Hospitals1.shp	D:\maps\California\Hospitals.shp	From local directory	● Point	Point	GCS_WGS_1984_EPSG:4326	438	Normal	✓
20	Lakes1.shp	D:\maps\California\Lakes.shp	From local directory	■ MultiPolygon	Multipolygon	GCS_WGS_1984_EPSG:4326	2	Normal	✓
21	LandmarkAreas1.shp	D:\maps\California\LandmarkAreas.shp	From local directory	■ MultiLineString	MultilineString	GCS_WGS_1984_EPSG:4326	10467	Normal	✓
22	MajorRoads1.shp	D:\maps\California\MajorRoads.shp	From local directory	■ MultiLineString	MultilineString	GCS_WGS_1984_EPSG:4326	72033	Normal	✓
23	Rivers1.shp	D:\maps\California\Rivers.shp	From local directory	■ MultiLineString	MultilineString	GCS_WGS_1984_EPSG:4326	4	Normal	✓
24	Schools1.shp	D:\maps\California\Schools.shp	From local directory	● Point	Point	GCS_WGS_1984_EPSG:4326	11381	Normal	✓
25	States1.shp	D:\maps\California\States.shp	From local directory	■ MultiPolygon	Multipolygon	GCS_WGS_1984_EPSG:4326	1	Normal	✓
26	UrbanArea1.shp	D:\maps\California\UrbanArea.shp	From local directory	■ MultiPolygon	Multipolygon	GCS_WGS_1984_EPSG:4326	191	Normal	✓
27	binhzhou.shp	D:\maps\Shandong\Binhzhou.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	7	Normal	✓
28	dezhou.shp	D:\maps\Shandong\Dezhou.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	11	Normal	✓
29	dongying.shp	D:\maps\Shandong\Dongying.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	5	Normal	✓
30	heze.shp	D:\maps\Shandong\Heze.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	9	Normal	✓
31	jinan.shp	D:\maps\Shandong\Jinan.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	12	Normal	✓
32	jining.shp	D:\maps\Shandong\Jining.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	11	Normal	✓
33	liaocheng.shp	D:\maps\Shandong\Liacheng.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	8	Normal	✓
34	linyi.shp	D:\maps\Shandong\Linxi.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	12	Normal	✓
35	qingdao.shp	D:\maps\Shandong\Qingdao.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	10	Normal	✓
36	taian.shp	D:\maps\Shandong\Taian.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	4	Normal	✓
37	tai'an.shp	D:\maps\Shandong\Tainan.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	8	Normal	✓
38	weifang.shp	D:\maps\Shandong\Weifang.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	12	Normal	✓
39	weihaishp	D:\maps\Shandong\Weihaishp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	4	Normal	✓
40	yantai.shp	D:\maps\Shandong\Yantai.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	11	Normal	✓
41	zaozhuang.shp	D:\maps\Shandong\Zaozhuang.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	6	Normal	✓
42	zibo.shp	D:\maps\Shandong\Zibo.shp	From local directory	■ MultiPolygon	Multipolygon	WGS 84 EPSG:4326	8	Normal	✓

Import vector layers Map preview and editing Layer statistics CRS Conversion Spatial processing Layer tile Export out Kml Export out Csv Export out GeoJson Delete Check all

Keep the same coordinate system and without attribute data  
Keep the same coordinate system and select attribute data  
Convert coordinate system and without attribute data  
Convert coordinate system and select attribute data

Figure 6-3: Data Processing Options for the vector layers pool

Support various operations on vector layers, including:

- Import vectorlayers: import client Shp files and Geojson files into the resource management pool.
- Map preview and editing: preview and edit the Shp layer in independent view of each layer in the list pool.
- Layer data statistics: perform the features data statistics of the shp layer in the list pool.
- Coordinate system conversion: perform coordinate system conversion on the shp layer in the list pool.
- Spatial processing: perform spatial processing on shp layers in the list pool, including merging and intersection.
- Build layer tile: For vector layers, TMS standard tiles, XYZ standard tiles, MVT standard tiles, and MBTiles standard tiles are generated according to the preset tile format scale level.
- Data conversion: Shp to Kml, Shp to Csv, Shp to GeoJson.
- Delete: Delete the shp layer in the list pool.

PyramidMap vector layer data processing covers coordinate system conversion, layer slicing, Shp and other heterogeneous spatial data, including mutual conversion between kml, csv, and Geojson. Technical details and examples will be explained in detail in **[6.6 Coordinate System Conversion]**, **[6.7 Data Conversion]** and **[6.8 Map tile]**. The tutorial data used in this chapter is provided in PyramidMap [Download shp tutorial data](#).

## 6.2 Raster layers pool

PyramidMap imports raster image layers of client file types into the raster resource pool through a file browser to form an raster file management list, which supports various operations with corresponding buttons, as shown in Figure 6-4.

No.	LayerFileName	LayerFilePath	Nodata Value	LayerType	Size(byte)	UCS(SRID)	Bands	PixelDepth	DataSources	State	Check
1	320205.tif	D:\maps\raster\3857\320205.tif	0.0		6223100	WGS 84 / Pseudo-Mercator EPSG:3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
2	Sentinel-2_L2A_False_color.tif	D:\maps\raster\3857\Sentinel-2_L2A_False_color.tif	0.0		8979080	WGS 84 / Pseudo-Mercator EPSG:3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
3	Sentinel-2_L2A_NDSI.tif	D:\maps\raster\3857\Sentinel-2_L2A_NDSI.tif	0.0		9459144	WGS 84 / Pseudo-Mercator EPSG:3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
4	Sentinel-2_L2A_SWIR.tif	D:\maps\raster\3857\Sentinel-2_L2A_SWIR.tif	0.0		9459144	WGS 84 / Pseudo-Mercator EPSG:3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
5	Sentinel-2_L2A_Scene_classification.tif	D:\maps\raster\3857\Sentinel-2_L2A_Scene_classification.tif	0.0		9459144	WGS 84 / Pseudo-Mercator EPSG:3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
6	marten_suitablehabit.tif	D:\maps\raster\AmericanPacificMarten\marten_suitablehabit.tif	255.0		8535561	NAD83 / California Albers EPSG:33101	3	8-bit	From local directory	normal	<input type="checkbox"/>
7	marten_suitablehabit.tif_20	D:\maps\raster\AmericanPacificMarten\marten_suitablehabit_20.tif	-3.402823060737...		479265	NAD83 / California Albers EPSG:33101	42-bit	From local directory	normal	<input type="checkbox"/>	
8	marten_suitablehabit.tif_30	D:\maps\raster\AmericanPacificMarten\marten_suitablehabit_30.tif	-3.402823060737...		516635	NAD83 / California Albers EPSG:33101	42-bit	From local directory	normal	<input type="checkbox"/>	
9	marten_suitablehabit.tif_30_	D:\maps\raster\AmericanPacificMarten\marten_suitablehabit_30.tif	无		35349751	NAD83 / California Albers EPSG:33101	42-bit	From local directory	normal	<input type="checkbox"/>	
10	320205_3857.tif	D:\maps\raster\320205_3857.tif	0.0		6233075	WGS 84 / Pseudo-Mercator EPSG:3...	3	8-bit	From local directory	normal	<input type="checkbox"/>
11	Sentinel-2_L2A_False_color.tif	D:\maps\raster\Sentinel-2_L2A_False_color.tif	无		8143417	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
12	Sentinel-2_L2A_NDSI.tif	D:\maps\raster\Sentinel-2_L2A_NDSI.tif	无		7396193	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
13	Sentinel-2_L2A_SWIR.tif	D:\maps\raster\Sentinel-2_L2A_SWIR.tif	无		8828267	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
14	Sentinel-2_L2A_Scene_classification.tif	D:\maps\raster\Sentinel-2_L2A_Scene_classification.tif	无		892081	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
15	hengxuhu.tif	D:\maps\raster\hengxuhu.tif	无		177386220	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>

Figure 6-4: Raster layers pool

The grid layer resource pool displays layer information for unified resource management in a list format, including:

- Layer name.
- Layer file path.
- NoData value: NoData indicates whether the pixel position information in the grid is available. If a pixel position information is not available, that position will be designated as NoData. Please note that NoData is different from 0, which is a valid numerical value.
- Layer Type: Display the grid layer type in icon mode.
- Size: The data size of the raster layer.
- Coordinate System (SRID): The definition of the coordinate system for a layer, including the coordinate system code.
- Band number: The number of bands in the raster layer.
- Pixel bit depth: The bit depth (pixel depth) of a pixel determines the range of values that a particular raster file can store, which is based on the formula  $2^n$  (where n is the bit depth). For example, an 8-bit raster can have 256 unique values that range from 0 to 255.
- Data source types, including: local grid layer, database export layer, and GeoServer export layer.
- Status: The existence status of the current layer resource.

### 6.2.1 Raster layer preview

Through the map preview and editing options, the selected layer file will be opened in a separate map view to achieve layer preview and editing, as shown in Figure 6-5.




Figure 6-5: Map preview of the raster layer

The independent view provides separate display, rendering, and overlay for each layer, and is a comprehensive map service window for a single layer. The tutorial data used in this chapter is provided in PyramidMap [Download raster tutorial data](#).

### 6.2.2 Raster data processing

Pyramidmap manages and operates layers uniformly through resource pooling, including layer resource import, layer preview, coordinate system conversion, spatial processing, layer tile, layer data export, and other operations. As shown in Figures 6-6.

The screenshot shows the PyramidMap interface with a toolbar at the top and a main content area below. The main content area displays a table of raster layers with columns for No., LayerFileName, LayerFilePath, Nodata Value, LayerType, Size(byte), UTM(SRID), Bands, PixelDepth, DataSources, State, and Check. Below the table is a red-bordered section containing buttons for Import raster layers, Map preview and editing, Raster process, Layer tile, Delete, and Check all. A vertical menu for Raster process includes options like Raster Compress, Raster Slice, Raster Merge, noData Handle, and CRS Transform.

No.	LayerFileName	LayerFilePath	Nodata Value	LayerType	Size(byte)	UTM(SRID)	Bands	PixelDepth	DataSources	State	Check
1	320205.tif	D:\maps\raster\3857320205.tif	0.0	栅格	6223100	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	From local directory	normal	<input type="checkbox"/>
2	Sentinel-2_L2A_False_color.tif	D:\maps\raster\3857\Sentinel-2_L2A_False_color.tif	0.0	栅格	8979080	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	From local directory	normal	<input type="checkbox"/>
3	Sentinel-2_L2A_NDSI.tif	D:\maps\raster\3857\Sentinel-2_L2A_NDSI.tif	0.0	栅格	9459144	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	From local directory	normal	<input type="checkbox"/>
4	Sentinel-2_L2A_SWIR.tif	D:\maps\raster\3857\Sentinel-2_L2A_SWIR.tif	0.0	栅格	9459144	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	From local directory	normal	<input type="checkbox"/>
5	Sentinel-2_L2A_Scene_cl.tif	D:\maps\raster\3857\Sentinel-2_L2A_Scene_classification.tif	0.0	栅格	9459144	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	From local directory	normal	<input type="checkbox"/>
6	martern_suitability.tif	D:\maps\raster\AmericanPacificMartern\martern_suitability.tif	255.0	栅格	8535561	NAD83 / California Albers EPSG:3310	1	8-bit	From local directory	normal	<input type="checkbox"/>
7	martern_suitability.tif	D:\maps\raster\AmericanPacificMartern\martern_suitability.tif	-3.402823060737...	栅格	479286	NAD83 / California Albers EPSG:3310	1	42-bit	From local directory	normal	<input type="checkbox"/>
8	martern_suitability.tif	D:\maps\raster\AmericanPacificMartern\martern_suitability.tif	-3.402823060737...	栅格	8535561	NAD83 / California Albers EPSG:3310	1	42-bit	From local directory	normal	<input type="checkbox"/>
9	martern_suitability.tif	D:\maps\raster\AmericanPacificMartern\martern_suitability.tif	无	栅格	35230751	NAD83 / California Albers EPSG:3310	1	42-bit	From local directory	normal	<input type="checkbox"/>
10	320205_3857.tif	D:\maps\raster\320205_3857.tif	0.0	栅格	62330751	WGS 84 / Pseudo-Mercator EPSG 3..3	3	8-bit	From local directory	normal	<input type="checkbox"/>
11	Sentinel-2_L2A_False_color.tif	D:\maps\raster\Sentinel-2_L2A_False_color.tif	无	栅格	8143417	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
12	Sentinel-2_L2A_NDSI.tif	D:\maps\raster\Sentinel-2_L2A_NDSI.tif	无	栅格	7396193	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
13	Sentinel-2_L2A_SWIR.tif	D:\maps\raster\Sentinel-2_L2A_SWIR.tif	无	栅格	8828267	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
14	Sentinel-2_L2A_Scene_cl.tif	D:\maps\raster\Sentinel-2_L2A_Scene_classification.tif	无	栅格	892081	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>
15	hengxu.tif	D:\maps\raster\hengxu.tif	无	栅格	177386220	WGS 84 EPSG:4326	3	8-bit	From local directory	normal	<input type="checkbox"/>

Figure 6-6: Grid Layer Resource Pool Data Processing Options

Support various operations on raster layer resources pool, including:

- Import raster Layer: import the client raster layer file into the resource management pool.
- Map preview and editing: preview and edit the raster layers in the list pool.
- Raster compression: Compress the raster layers according to the specified compression scheme.
- Raster slice: This is a process that reverses with the raster Mosaic, divide a whole image into multiple slice images according to rules.
- Raster merge: A mosaic combines multiple raster images to obtain a seamless raster.
- Deal noData: process the invalid value of noData for the raster layer in the list pool, mainly to remove the black background and other invalid pixels of the image.
- Coordinate system conversion: perform coordinate system conversion on raster layers in the list pool.
- Build layer tile:: Generate TMS standard tiles, XYZ standard tiles, and MBTiles standard tiles according to the preset tile format scale level for raster.
- Delete: Delete the raster layer in the list pool.

The tutorial data used in this chapter is provided in PyramidMap [Download raster tutorial data](#).

### 6.2.3 Raster compress

The main advantage of image compression is that the compressed data requires less storage space, and because less information is transmitted, it accelerates the display of the data. The PyramidMap image compression interface is shown in Figures 6-7.




Figure 6-7: Performing raster Compression

PyramidMap supports configuring the same compression strategy for batch data, achieving one click completion. PyramidMap configures image compression strategies through parameters:

- **Compression depth:** By compressing the pixel depth of the original image to 8 bits, the maximum compression ratio can be achieved, but at the cost of reducing the image color scale, grayscale, and image quality. The original pixel depth can be retained.
- **Compression method:** The data compression method can be lossy compression (JPEG/JPEG 2000, WEBP) or lossless compression (LZW, PackBits, and DEFLATE). Lossless compression means that the pixel values in the raster dataset will not change or be lost. If the pixel values of the raster dataset will be used for analyzing or deriving other data products, lossless compression or no compression should be chosen. The amount of compression depends on the data and compression quality. The more similar data, the higher the compression ratio. The lower the compression quality, the higher the compression ratio. Compared to lossless compression, lossy compression usually produces a higher compression ratio.
- **Imaging quality:** When selecting the **JPEG** compression method, the compression quality must be specified. The effective range of compression quality values is 1 to 100, with 75 being the default value.
- **Imaging Scale:** Specify the width/height ratio of the compressed image to the original image.
- **Build a pyramid:** Option whether to build a pyramid structure on the compressed image. Building a pyramid can perform hierarchical indexing on the image, which will accelerate the image loading speed. This is very effective in improving the loading and display speed of big data images.
- **Pixel noData processing:** Remove unnecessary values created around raster data. The specified value is different from other useful data in the raster dataset. For example, values with zero on the grid boundary are different from zero values within the grid dataset. The specified pixel value will be set to NoData in the output grid dataset. For file based grids, to **ignore the background value**, it must be set to the same value as **NoData**. Invalid values in the image can cause a black background. Choosing the invalid value processing option will automatically filter out invalid pixels during the compression process, thereby improving image quality and simplifying the processing process.

The processing process will save the log, and a message prompt will be given after the processing is completed.

## 6.2.4 Raster slice

Raster slice is the process of dividing a raster dataset into smaller segment based on the features in blocks or faces. The schematic diagram of image slicing is shown in Figures 6-8.



Figure 6-8: Schematic diagram of raster slice

PyramidMap can perform batch slicing operations on rasters in the resource pool, and the raster slicing dialog is shown in Figure 6-9.




Figure 6-9: Raster Slicing processing

Select the tile file format, which can be consistent with the source file, or select Tiff, png, jpg, webp and other different data formats. You can creating tiles according to the number and size strategies, and finally output to the specified save path.

With the NE2\_50M\_SR\_W.tif in the resource pool as an example, the whole image is shown in Figure 6-10.




Figure 6-10: the whole raster image

Taking the 256 \* 256 (pixel) slicing strategy as an example, the generated tiles is shown in Figure 6-11.



Figure 6-11: The effect of tiles generated by the whole raster

## 6.2.5 Raster merge

In a sense, raster mosaicing is the reverse process of the raster tiling. Mosaicing is to combine multiple raster images through mosaic to obtain a seamless raster image. The image merging diagram is shown in Figure 6-12.



Figure 6-12: Schematic diagram of raster mosaicing

PyramidMap batch mosaicing rasters in the resource pool, as shown in Figure 6-13.




Figure 6-13: PyramidMap mosaicing rasters in the resource pool in batches

The effect of the merged raster is shown in Figure 6-14.




Figure 6-14: The effect of rasters mosaicing

Two common methods for combining adjacent or overlapping raster layers are MERGE and MOSAIC. The following is an explanation of the differences between these two types of work. The MOSAIC and MERGE functions work similarly, but there are also differences between them. When the input grids do not have any overlapping area, there is no difference in the output from either MERGE or MOSAIC. The difference is only in the processing of overlapping areas. In the case of MERGE, the sequence of input grids determines the values assigned to cells, giving priority to those entered first. The merge processing mode is shown in Figure 6-15.




Figure 6-15: The merge processing mode

## 6.2.6 NoData processing

In general, raster images will have NoData values. These NoData are invalid values that do not have actual value and will interfere with image data analysis. Black image frame is a common NoData error, which is particularly common for UAV images and raster data sets after geographical reference processing. In this example, we remove the black border of raster image through NoData invalid value processing. The processing process is shown in Figure 6-16.




Figure 6-16: Remove the black border of raster image through NoData invalid value processing

PyramidMap perform batch NoData processing on images in the resource pool, as shown in Figure 6-17.




Figure 6-17: Batch NoData processing of images in the resource pool

The image with black background before processing is shown in Figure 6-18.




Figure 6-18: The image with black background before processing

## 6.2.7 Coordinate System Conversion

PyramidMap supports Shp vector file type and raster file type coordinate system conversion, in the above two types of layer resources list, select "coordinate system conversion", as shown in Figure 6-19.




Figure 6-19: Select in coordinate system resource pool for conversion

In the coordinate system conversion interface, select the type of target coordinate system, which is divided into two types: spatial coordinate system and plane coordinate system, as well as many standardized coordinate systems to which it belongs. It supports global search by name and EPSG code. Taking WGS84 as an example, we can perform global keyword search according to coordinate system code 4326 to accurately obtain the target coordinate system we want.

## 6.3 Geodatabase layers pool

PyramidMap imports client shp vector layers into Geodatabase through database connection pool, obtains layer list through database connection pool, and supports various operations with corresponding buttons.

### 6.3.1 Importing shp to Geodatabase

PyramidMap maintains the Geodatabase connection pool and the Shp vector layer resource pool to import the Shp vector layer into the Geodatabase in batches. It supports but is not limited to Oracle, PostGIS and MySQL. The import interface and process are shown in Figure 6-20.

The screenshot shows the 'Shp vector layers' import interface. At the top, there's a navigation bar with tabs like 'Main Mapview', 'Styles Console', etc. Below it is a table titled 'Select Geodatabase:' showing various database connections (No, DBconnection, description, DBType, HostIP, Port, Schema, Instance, Encoding, Status, Test, Editor, Check). A red box highlights the 'Check' column for the first few rows. At the bottom of the table is a large red box containing the 'Do Import' button.

Figure 6-20: Shp vector layers imported to Geodatabase workflow

In this module, users can selectively import Shp vector layers into Geodatabase in batches. After importing, each Shp layer generates a layer feature table with the same name. As a reciprocal process, the layer feature table in Geodatabase can also be exported to different geographic feature data such as Shp, Csv, Kml, Geojson, etc. The tutorial data used in this chapter is provided in PyramidMap [Download shp tutorial data](#).

### 6.3.2 Geodatabase exporting out shp

As a reciprocal process, the features table in Geodatabase can also be exported to different geographical element data such as Shp, Csv, Kml, Geojson, etc. The operation interface and flow are shown in Figure 6-21.

The screenshot shows the 'Geodatabase layer table export interface'. At the top, there's a navigation bar with tabs like 'Main Mapview', 'Styles Console', etc. Below it is a table titled 'Layer features table:' showing various layers (No, LayerName, FeatureType, GeometryType, FeaturesNumber, CoordinateName, EpsgCode, Status, Check). A red box highlights the 'Check' column for the first few rows. To the right, there's a file dialog window titled '打开' (Open) showing a list of files and folders. At the bottom, there are several export buttons: 'Export Shp' (highlighted with a red box), 'Export Kml', 'Export Csv', 'Export GeoJson', and 'Delete layers'.

Figure 6-21: Geodatabase layer table export interface and workflow chart

In this module, users can selectively export the layer tables in Geodatabase as Shp, Csv, Kml and GeoJson under the specified path. Taking the exported Shp file as an example, the export process, export status and export file are shown in Figure 6-22.

No	DBConnection	description	DBType	HostIP	Port	Schema	Instance	Encoding	Status	Test	Editor	Check
1	oracle104		oracle	127.0.0.1	1521	ade	geodata	GBK	Modified unsyncd to server	Connect	Do edit	<input type="radio"/>
2	postgres104	The local postgres map...	postgis	127.0.0.1	5432	public	geo_data	GBK	Modified unsyncd to server	Connect	Do edit	<input checked="" type="radio"/>
3	postgislocal		postgis	127.0.0.1	5432	public	geo_data	GBK	New unsyncd to server	Connect	Do edit	<input type="radio"/>
4	geoserver100-cite-ctepostgis		postgis	localhost	5432	public	geo_gas	GBK	synced from Server	Connect	Do edit	<input type="radio"/>
5	geoserver100-cite-postgis1		postgis	127.0.0.1	5432	public	geo_gas	GBK	synced from Server	Connect	Do edit	<input type="radio"/>
6	geoserver100-cte-postgis1		postgis	127.0.0.1	5432	public	geo_data	GBK	synced from Server	Connect	Do edit	<input type="radio"/>
7	geoserver100-ctn-postgis0		postgis	127.0.0.1	5432	public	geo_data	GBK	Modified unsyncd to server	Connect	Do edit	<input type="radio"/>

No	LayerName	FeatureType	GeometryType	FeatureNumbered	CoordinateName	EpsgCode	Status	Check
1	Buildings	Point	Point	4381	EPSG 4326	4326	succes	<input checked="" type="checkbox"/>
2	Cemeteries	Point	Point	842	EPSG 4326	4326	succes	<input type="checkbox"/>
3	Churches	Point	Point	183613	EPSG 4326	4326	succes	<input type="checkbox"/>
4	Colleges	MultiPolygon	Polygon	95005454	EPSG 4326	4326	succes	<input type="checkbox"/>
5	GolfCourses	Point	Point	537	EPSG 4326	4326	succes	<input type="checkbox"/>
6	Hospitals	Point	Point	438	EPSG 4326	4326	succes	<input type="checkbox"/>
7	Lakes	MultiPolygon	Polygon	2	EPSG 4326	4326	succes	<input type="checkbox"/>
8	LandmarkAreas	MultiPolygon	Polygon	1041	EPSG 4326	4326	succes	<input type="checkbox"/>
9	MajorRoads	MultiLineString	LineString	72033	EPSG 4326	4326	pending	<input type="checkbox"/>
10	Rivers	MultiLineString	LineString	4	EPSG 4326	4326	pending	<input type="checkbox"/>
11	Schools	Point	Point	11381	EPSG 4326	4326	pending	<input type="checkbox"/>
12	States	MultiPolygon	Polygon	1	EPSG 4326	4326	pending	<input type="checkbox"/>
13	UrbanAreas	MultiPolygon	Polygon	191	EPSG 4326	4326	pending	<input type="checkbox"/>
14	water_point	Point	Point	1	EPSG 4326	4326	pending	<input type="checkbox"/>
15	city_point	Point	Point	311	EPSG 4326	4326	pending	<input type="checkbox"/>
16	city_region	MultiPolygon	Polygon	373	EPSG 4326	4326	pending	<input type="checkbox"/>
17	country_point	Point	Point	28629	EPSG 4326	4326	pending	<input type="checkbox"/>
18	country_region	MultiPolygon	Polygon	2910	EPSG 4326	4326	pending	<input type="checkbox"/>
19	gas_condensate_tank	Point	Point	8	EPSG 4326	4326	pending	<input type="checkbox"/>
20	gas_pipe	MultiLineString	LineString	8047	EPSG 4326	4326	pending	<input type="checkbox"/>
21	gas_pipe_cap	Point	Point	628	EPSG 4326	4326	pending	<input type="checkbox"/>
22	gas_pressure_box	Point	Point	30	EPSG 4326	4326	pending	<input type="checkbox"/>
23	gas_pressure_cabinet	Point	Point	1	EPSG 4326	4326	pending	<input type="checkbox"/>
24	gas_measure_station	Point	Point	4	EPSG 4326	4326	pending	<input type="checkbox"/>

layers exporting

All

Buildings.dbf  
Buildings.frx  
Buildings.prj  
Buildings.shp  
Buildings.shx  
Cemeteries.dbf  
Cemeteries.frx  
Cemeteries.prj  
Cemeteries.shp  
Cemeteries.shx  
Churches.dbf  
Churches.frx  
Churches.prj  
Churches.shp  
Churches.shx  
Counties.dbf  
Counties.frx  
Counties.prj  
Counties.shp  
Counties.shx  
GolfCourses.dbf  
GolfCourses.frx  
GolfCourses.prj  
GolfCourses.shp  
Hospitals.dbf  
Hospitals.frx  
Hospitals.prj  
Hospitals.shp  
Hospitals.shx  
Lakes.dbf  
Lakes.frx

Figure 6-22: Geodatabase layer table export process, export status and export file flow chart

Select the database connection, dynamically obtain its internal layer resources, perform corresponding processing, and support various operations on layer resources with corresponding buttons, including:

- Export Shp: Export Geodatabase layers to shp files.
- Export Kml: Export Geodatabase layers to kml files.
- Export Csv: Export Geodatabase layers to csv files.
- Export GeoJson: Export Geodatabase layers to geojson files.
- Delete layers: Bulk delete the selected Geodatabase layers.

Reload and display the exported Shp layer in the map view, as shown in Figure 6-23.




Figure 6-23: Display of Shp layer exported from Geodatabase

### 6.3.3 Geodatabase layers preview and edit

The layer table in Geodatabase can be queried and previewed directly. The operation interface and flow diagram are shown in Figure 6-24.

No	DBconnection	description	DBType	HostIP	Port	Schema	Instance	Encoding	Status	Test	Editor	Check
1	oracle104		oracle	127.0.0.1	1521	sde	geodata	GBK	Modified unsynced to server	Connect	Do edit	<input checked="" type="radio"/>
2	postgis104	postgis	postgis	127.0.0.1	5432	public	geo_data	GBK	Modified unsynced to server	Connect	Do edit	<input type="radio"/>
3	postgislocal	The local postgis map ...	postgis	127.0.0.1	5432	public	geo_data	GBK	New unsynced to server	Connect	Do edit	<input type="radio"/>
4	geoserver100-cte-postgis	postgis	localhost	5432	public	geo_data	GBK	synced from Server	Connect	Do edit	<input type="radio"/>	
5	geoserver100-cte-postgis1	postgis	127.0.0.1	5432	public	geo_gas	GBK	synced from Server	Connect	Do edit	<input type="radio"/>	
6	geoserver100-cte-postgre1	postgis	127.0.0.1	5432	public	geo_gas	GBK	synced from Server	Connect	Do edit	<input type="radio"/>	
7	geoserver100-cte-postgis0	postgis	127.0.0.1	5432	public	geo_data	GBK	Modified unsynced to server	Connect	Do edit	<input type="radio"/>	

No	LayerName	FeatureType	GeometryType	FeaturesNumber	CoordinateName	EpsgCode	Check
1	BUILDINGS	Point	○	4361	EPSG:4326	4326	<input checked="" type="radio"/>
2	CAPITAL_POINT	Point	○	11	EPSG:4326	4326	<input type="radio"/>
3	CEMETRIES	Point	○	842	EPSG:4326	4326	<input type="radio"/>
4	CHURCHES	Point	○	183613	EPSG:4326	4326	<input type="radio"/>
5	CITY_POINT	Point	○	310	EPSG:4326	4326	<input type="radio"/>
6	CITY_REGION	MultiPolygon	☒	373	EPSG:4326	4326	<input type="radio"/>
7	COUNTIES	MultiPolygon	☒	58	EPSG:4326	4326	<input type="radio"/>
8	COUNTY_POINT	Point	○	2862	EPSG:4326	4326	<input type="radio"/>
9	COUNTY_REGION	MultiPolygon	☒	2918	EPSG:4326	4326	<input type="radio"/>
10	GAS_CONDENSATE_TANK	Point	○	8	EPSG:4326	4326	<input type="radio"/>
11	GAS_PIPE	MultiLineString	☒	8055	EPSG:4326	4326	<input type="radio"/>
12	GAS_PIPE_CAP	Point	○	626	EPSG:4326	4326	<input type="radio"/>
13	GAS_PRESSURE_BOX	Point	○	30	EPSG:4326	4326	<input type="radio"/>
14	GAS_PRESSURE_CABINET	Point	○	119	EPSG:4326	4326	<input type="radio"/>
15	GAS_PRESSURE_STATION	Point	○	1	EPSG:4326	4326	<input type="radio"/>
16	GAS_PROTECTIVE_PIPE	Point	○	54	EPSG:4326	4326	<input type="radio"/>
17	GAS_SERVICING_WELL	Point	○	2	EPSG:4326	4326	<input type="radio"/>
18	GAS_VALVE	Point	○	1	EPSG:4326	4326	<input type="radio"/>
19	GAS_VALVE_WELL	Point	○	901	EPSG:4326	4326	<input type="radio"/>

Figure 6-24: Geodatabase layer table query and preview

Select the database connection, dynamically obtain its internal layer resources, perform corresponding processing, and support various operations on layer resources with corresponding buttons, including:

- Feature List: forms the feature list of the selected layer.
- Coordinate data: form a list of geographical coordinates of the selected layer.
- Records number: perform data statistics on the features in the layer.
- Layer's center: calculates the center point location of the layer.
- Map preview and edit: preview and edit the layers in the management pool.

In particular, through the map preview and editing options, the selected layer file will be opened in an independent map view to preview and edit the layer, as shown in Figure 6-25.




Figure 6-25: Open the independent preview and editing view of the single geodatabase layer

Independent map view provides each layer with separate display, rendering, base map selection and overlay, image-based editing, data table editing, feature selection and deletion operations. It is a comprehensive map service for a single layer.

## 6.4 GeoServer vector layers pool

PyramidMap publishes vector layers of client Shp file to GeoServer through GeoServer connection, and obtains the Internal layers through GeoServer connection in the pool, supporting various operations with corresponding buttons.

### 6.4.1 GeoServer layers preview

Select the GeoServer connection to dynamically acquire its internal layers and perform corresponding processing., as shown in Figure 6-26.

The screenshot shows the 'GeoServer layer preview' tab selected in the top navigation bar. Below it, a table lists 'GeoServer layers console' with columns for No, GeoServerName, Description, HostIP, Port, WebName, and Check. The 'Check' column contains radio buttons. A larger table below, titled 'layersList:', lists internal layers with columns for No, LayerTitle, LayerName, WorkSpace, GeoServerUrl, DataStorage, Style, UCS, Geometr..., LayerType, Min X, Max X, Min Y, Max Y, and Check. Each row represents a different layer type (e.g., Buildings, Cemeteries, Churches, Counties, GolfCourses, Hospitals, Lakes, LandmarkAreas, MajorRoads, Rivers, Schools, States, UrbanAreas, capital\_point, city\_point, city\_region, county\_point, county\_region, gas\_condensate\_tank, gas\_pipe, gas\_pipe\_cap, gas\_pressure\_box, gas\_pressure\_cabinet, gas\_pressure\_station, gas\_protective\_pile, gas\_servicing\_well, gas\_valve) with its specific details. At the bottom, there are 'Preview' and 'Set style' buttons.

No	GeoServerName	Description	HostIP	Port	WebName	Check
1	geoserver1		127.0.0.1	8080	geoserver	<input checked="" type="radio"/>
2	geoserver2		127.0.0.1	8080	dhcisserver	<input type="radio"/>
3	geoserver3		172.19.126.233	8080	geoserver	<input type="radio"/>
4	geoserver100	GeoServer in 192.168.31.100	192.168.31.100	8080	geoserver	<input type="radio"/>

No	LayerTitle	LayerName	WorkSpace	GeoServerUrl	DataStorage	Style	UCS	Geometr...	LayerType	Min X	Max X	Min Y	Max Y	Check
1	Buildings	Buildings	otn	http://127.0.0.1:8080/geoserver	Buildings	point	EPSG:4326	<input checked="" type="radio"/>	point	-124.26561068...	-114.28967332...	32.5547790440...	42.0004030190...	<input checked="" type="radio"/>
2	Cemeteries	Cemeteries	otn	http://127.0.0.1:8080/geoserver	Cemeteries	point	EPSG:4326	<input checked="" type="radio"/>	point	-124.2619944...	-114.49633767...	32.5686672600...	42.120942250...	<input type="radio"/>
3	Churches	Churches	otn	http://127.0.0.1:8080/geoserver	Churches	point	EPSG:4326	<input checked="" type="radio"/>	point	-170.73222219...	163.02833300...	-14.335555599...	64.9540207530...	<input type="radio"/>
4	Counties	Counties	otn	http://127.0.0.1:8080/geoserver	Counties	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	-124.40972100...	-114.13121199...	32.5341569920...	42.0095189850...	<input type="radio"/>
5	GolfCourses	GolfCourses	otn	http://127.0.0.1:8080/geoserver	GolfCourses	point	EPSG:4326	<input checked="" type="radio"/>	point	-124.16867133...	-114.60079785...	32.6403330870...	41.8354129110...	<input type="radio"/>
6	Hospitals	Hospitals	otn	http://127.0.0.1:8080/geoserver	Hospitals	point	EPSG:4326	<input checked="" type="radio"/>	point	-124.19111769...	-114.30398999...	32.6167757460...	41.7727103900...	<input type="radio"/>
7	Lakes	Lakes	otn	http://127.0.0.1:8080/geoserver	Lakes	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	-120.15212727...	-115.59582327...	33.1103213600...	39.2493473640...	<input type="radio"/>
8	LandmarkAreas	LandmarkAreas	otn	http://127.0.0.1:8080/geoserver	LandmarkAreas	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	-124.19303702...	-114.18072800...	32.5425189980...	41.9960510040...	<input type="radio"/>
9	MajorRoads	MajorRoads	otn	http://127.0.0.1:8080/geoserver	MajorRoads	line	EPSG:4326	<input checked="" type="radio"/>	linestring	-124.40275454...	-114.12942727...	32.5421545450...	42.0132272730...	<input type="radio"/>
10	Rivers	Rivers	otn	http://127.0.0.1:8080/geoserver	Rivers	line	EPSG:4326	<input checked="" type="radio"/>	linestring	-124.05229327...	-119.33676227...	36.3913315450...	42.0067957370...	<input type="radio"/>
11	Schools	Schools	otn	http://127.0.0.1:8080/geoserver	Schools	point	EPSG:4326	<input checked="" type="radio"/>	point	-124.32227960...	-70.687523662...	32.5433900720...	41.9879431430...	<input type="radio"/>
12	States	States	otn	http://127.0.0.1:8080/geoserver	States	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	-124.40972100...	-114.13121199...	32.5341569920...	42.0095189850...	<input type="radio"/>
13	UrbanAreas	UrbanAreas	otn	http://127.0.0.1:8080/geoserver	UrbanAreas	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	-124.21915192...	-114.27694190...	32.5559449040...	41.9810329080...	<input type="radio"/>
14	capital_point	capital_point	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:4326	<input checked="" type="radio"/>	point	116.5055080...	116.505708800...	40.324461100...	40.1328461100...	<input type="radio"/>
15	city_point	city_point	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:4326	<input checked="" type="radio"/>	point	79.843047485...	131.406188984...	15.9976377487...	52.6016998291...	<input type="radio"/>
16	city_region	city_region	otn	http://127.0.0.1:8080/geoserver	postgis104	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	73.1794815063...	[...]	11.0382738113...	53.7730674743...	<input type="radio"/>
17	county_point	county_point	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:4326	<input checked="" type="radio"/>	point	80.9004548950...	134.551940917...	18.3353710174...	53.1429176330...	<input type="radio"/>
18	county_region	county_region	otn	http://127.0.0.1:8080/geoserver	postgis104	polygon	EPSG:4326	<input checked="" type="radio"/>	polygon	77.717613202...	135.382736206...	17.9404830932...	53.7387313842...	<input type="radio"/>
19	gas_condensate_tank	gas_condensate_tank	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34517860254...	1.34695368513...	3608506.9833...	3625104.6929...	<input type="radio"/>
20	gas_pipe	gas_pipe	otn	http://127.0.0.1:8080/geoserver	postgis104	line	EPSG:3857	<input checked="" type="radio"/>	linestring	1.34461039767...	1.34696250277...	3603643.771...	3629163.2984...	<input type="radio"/>
21	gas_pipe_cap	gas_pipe_cap	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34465345507...	1.34695345503...	3603878.7072...	3628609.1408...	<input type="radio"/>
22	gas_pressure_box	gas_pressure_box	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34465355725...	1.3469545325E7...	3604467.1919...	3628894.2044...	<input type="radio"/>
23	gas_pressure_cabinet	gas_pressure_cabinet	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34462621718...	1.34694942785...	3603721.5800...	3629004.25959...	<input type="radio"/>
24	gas_pressure_station	gas_pressure_station	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34633706468...	3608912.0386...	3608914.0386...	<input type="radio"/>	
25	gas_protective_pile	gas_protective_pile	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.345191011767...	1.3466247646E7...	3607336.8577...	3623375.6472...	<input type="radio"/>
26	gas_servicing_well	gas_servicing_well	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34593063535...	1.3464039198...	3612025.9532...	3617492.7543...	<input type="radio"/>
27	gas_valve	gas_valve	otn	http://127.0.0.1:8080/geoserver	postgis104	point	EPSG:3857	<input checked="" type="radio"/>	point	1.34593050139...	1.34593070139...	3617491.6183...	3617493.6183...	<input type="radio"/>

Figure 6-26: GeoServer connections pool and its internal layers pool

Various operations on layer resources are supported, including:

- Preview: preview the selected layer through WMS service mode.
- Set Style: set the sld display symbol matching its geometric type for the selected layer, as shown in Figure 6-27.




Figure 6-27: Get the internal styles in the GeoServer selected and form styles list pool

Select style in the list and assign it to the selected layer.

In particular, through the map preview and editing options, the selected layer file will be opened in the independent GeoServer map view to preview the layer. The editing function is not supported temporarily, as shown in Figure 6-28.




Figure 6-28: The GeoServer vector layer is previewed according to the preset sld style

## 6.4.2 GeoServer layers exporting

As a reciprocal process with layers publishing, the layers hosted in GeoServer can be exported to different geographic feature data such as Shp, Csv, Kml, GeoJson, etc. The operation interface and flow are shown in Figure 6-29.




Figure 6-29: GeoServer layer export selection and specified export path

In the GeoServer layer resource list, select a layer and export it to the specified path in batch. The export process is displayed with a progress bar, and the flow diagram is shown in Figure 6-30.




Figure 6-30: GeoServer layer export process diagram

The selected layer is exported to the specified target path, and the export progress is displayed through the progress bar. The exported map is reloaded into the map view in the form of Shp vector file, as shown in Figure 6-31.




Figure 6-31: The exported Shp vector layer of GeoServer is reloaded to the map view for display

## 6.5 GeoServer raster layer pool

Select the raster layer in the Figure 6-8 GeoServer map server connection pool and its list, and the selected layer file will be opened in the independent GeoServer map view to preview the layer. The editing function is not supported temporarily, as shown in Figure 6-32.




Figure 6-32: The GeoServer raster layer is previewed

## 6.6 Coordinate System Conversion

PyramidMap supports coordinate system conversion of Shp vector file and raster file layers. Select a layer from the above two types in the resource pool, and select "Coordinate System Conversion" button, as shown in Figure 6-33.

The screenshot shows the GeoServer interface with a table of layers. The columns include: No, LayerName, LayerFilePath, Remarks, FeatureType, LayerType, UGS(SRID), Encoding, Status, and Check. Most layers are in EPSG:4326 (WGS\_1984) and ISO-8659-1 encoding, with some in GCS\_WGS\_1984. The 'Check' column contains checked boxes for many rows.

No	LayerName	LayerFilePath	Remarks	FeatureType	LayerType	UGS(SRID)	Encoding	Status	Check
1	gas_condensate_tank.shp	E:\Maps\gaspipe_shp385\gas_condensate_tank.shp	included in program management	vector	WGS_1984_Web_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting		
2	gas_pipe.shp	E:\Maps\gaspipe_shp385\gas_pipe.shp	included in program management	vector	WGS_1984_Web_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting		
3	gas_pipe_cap.shp	E:\Maps\gaspipe_shp385\gas_pipe_cap.shp	included in program management	vector	WGS_1984_Web_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting		
4	gas_pressure_box.shp	E:\Maps\gaspipe_shp385\gas_pressure_box.shp	included in program management	vector	WGS_1984_Web_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting		
5	gas_pressure_cabinet.shp	E:\Maps\gaspipe_shp385\gas_pressure_cabinet.shp	included in program management	vector	WGS_1984_Web_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting		
6	gas_pressure_stations.shp	E:\Maps\gaspipe_shp385\gas_pressure_stations.shp	included in program management	vector	WGS_1984_Web_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting		
7	gas_protective_pile.shp	E:\Maps\gaspipe_shp385\gas_protective_pile.shp	included in program management	vector	WGS_1984_Web_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting		
8	gas_servicing_well.shp	E:\Maps\gaspipe_shp385\gas_servicing_well.shp	included in program management	vector	WGS_1984_Web_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting		
9	gas_valve.shp	E:\Maps\gaspipe_shp385\gas_valve.shp	included in program management	vector	WGS_1984_Web_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting		
10	gas_well.shp	E:\Maps\gaspipe_shp385\gas_well.shp	included in program management	vector	WGS_1984_Web_Mercator_Auxiliary_Sphere_EP.	ISO-8659-1	Local hosting		
11	capital_point.shp	E:\Maps\OTN\Capital_point.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8659-1	Local hosting		
12	city_point.shp	E:\Maps\OTN\City_point.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8659-1	Local hosting		
13	city_region.shp	E:\Maps\OTN\City_region.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8659-1	Local hosting		
14	county_point.shp	E:\Maps\OTN\County_point.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8659-1	Local hosting		
15	county_region.shp	E:\Maps\OTN\County_region.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8659-1	Local hosting		
16	province_point.shp	E:\Maps\OTN\Province_point.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8659-1	Local hosting		
17	province_region.shp	E:\Maps\OTN\Province_region.shp	included in program management	vector	WGS_84_EPSG_4326	ISO-8659-1	Local hosting		
18	gas_condensate_tank.shp	E:\Maps\gaspipe_shp\gas_condensate_tank.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
19	gas_pipe.shp	E:\Maps\gaspipe_shp\gas_pipe.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
20	gas_pipe_cap.shp	E:\Maps\gaspipe_shp\gas_pipe_cap.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
21	gas_pressure_box.shp	E:\Maps\gaspipe_shp\gas_pressure_box.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
22	gas_pressure_cabinet.shp	E:\Maps\gaspipe_shp\gas_pressure_cabinet.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
23	gas_pressure_stations.shp	E:\Maps\gaspipe_shp\gas_pressure_stations.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
24	gas_protective_pile.shp	E:\Maps\gaspipe_shp\gas_protective_pile.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
25	gas_servicing_well.shp	E:\Maps\gaspipe_shp\gas_servicing_well.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
26	gas_valve.shp	E:\Maps\gaspipe_shp\gas_valve.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
27	gas_well.shp	E:\Maps\gaspipe_shp\gas_well.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
28	Buildings.shp	E:\Maps\California\Buildings.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
29	Cemeteries.shp	E:\Maps\California\Cemeteries.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
30	Churches.shp	E:\Maps\California\Churches.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
31	Counties.shp	E:\Maps\California\Counties.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
32	Crossroads.shp	E:\Maps\California\crossroads.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
33	Hospitals.shp	E:\Maps\California\hospitals.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
34	Lakes.shp	E:\Maps\California\lakes.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
35	LandmarkAreas.shp	E:\Maps\California\landmarkAreas.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
36	MajorRoads.shp	E:\Maps\California\majorRoads.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
37	Rivers.shp	E:\Maps\California\rivers.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
38	Schools.shp	E:\Maps\California\schools.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
39	States.shp	E:\Maps\California\states.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		
40	UrbanAreas.shp	E:\Maps\California\urbanAreas.shp	included in program management	vector	GCS_WGS_1984_EPSG_4326	ISO-8659-1	Local hosting		

Figure 6-33: Select a layer for coordinate system conversion

The coordinate system conversion interface pops up, as shown in Figure 6-34.




Figure 6-34: Select in coordinate system resource pool for conversion

In the coordinate system conversion interface, select the type of target coordinate system, which is divided into two types: spatial coordinate system and plane coordinate system, as well as many standardized coordinate systems to which it belongs. It supports global search by name and EPSG code. Taking WGS84 as an example, we can perform global keyword search according to coordinate system code 4326 to accurately obtain the target coordinate system we want, as shown in Figure 6-35.




Figure 6-35: Select in coordinate system with global keyword searching according to coordinate system code

Select the target storage path and click "OK" to perform coordinate system conversion. The selected layers will be converted and saved to the target path according to the specified coordinate system. The progress bar displays the conversion progress, as shown in Figure 6-36.




Figure 6-36: Converts the selected layer to the specified coordinate system under the target path

The experimental data used in the example is available in PyramidMap for [download](#).

## 6.7 Data conversion

PyramidMap supports the mutual conversion between multi-source heterogeneous data and Shp layers, giving map application systems the ability to diversify data sources and convert maps into diversified production data. PyramidMap supports bidirectional conversion between Shp and Csv, Excel, GeoJson, as well as unidirectional conversion from Shp to Km1/Kmz. The functional entrances for converting Csv, Excel, and GeoJson to Shp are shown in Figure 6-37.




Figure 6-37: Csv, Excel, GeoJson to Shp Function Entry

## 6.7.1 Csv to Shp

PyramidMap supports the conversion of CSV which meets contractual specifications into Shp graphics, and the data source supports feature types such as Point/MultiPoint, LineString/MultiLineString, Polygon/MultiPolygon, etc. PyramidMap parses CSV according to the agreed specifications and converts it into SHP. The PyramidMap converter reads from CSV format and uses a column named WKT as geometric data. The WKT column contains geometry as well known text. If you are writing data to CSV format, make sure to create geometry and write it to the WKT column. The WKT data format that meets the specifications is shown in Figures 6-38.

R	S	T	U	V	W	X	Y	Z
WKT								
MULTIPOLYGON (((120.41966 36.090991, 120.410955 36.092223, 120.405539 36.088717,								
MULTIPOLYGON (((120.41966 36.090991, 120.420219 36.094797, 120.434309 36.097592,								
MULTIPOLYGON (((119.717048 36.04185, 119.713138 36.040507, 119.708576 36.034802,								
MULTIPOLYGON (((120.484492 36.215752, 120.497775 36.211479, 120.511275 36.208688,								
MULTIPOLYGON (((120.343439 36.208341, 120.351539 36.20287, 120.358739 36.200331,								
MULTIPOLYGON (((120.57066 36.327374, 120.566191 36.327846, 120.559705 36.331624,								
MULTIPOLYGON (((120.656037 36.322163, 120.663004 36.331782, 120.666899 36.332726,								
MULTIPOLYGON (((119.717048 36.04185, 119.720353 36.040649, 119.721315 36.036462,								
MULTIPOLYGON (((120.008077 36.498223, 120.031974 36.481695, 120.038025 36.485246,								
MULTIPOLYGON (((120.634452 36.588998, 120.635631 36.596796, 120.638921 36.599337,								

Figure 6-38: WKT data format that meets specifications

Other columns will be written to Shp as attribute data. Specifically, for Point type files, PyramidMap also supports replacing wkt with longitude/latitude fields to represent coordinate values. In other words, for Point type CSV files that represent coordinate data in longitude/latitude (case insensitive) fields instead of WKT format, PyramidMap also supports conversion to Shp. The data format example is shown as below.

```

1 LATITUDE, LONGITUDE, CITY, NUMBER
2 46.066667,11.116667,Trento,140
3 44.9441,-93.0852,st Paul,125
4 13.752222,100.493889,Bangkok,150
5 45.420833,-75.69,ottawa,200

```

```

6 44.9801,-93.251867,Minneapolis,350
7 46.519833,6.6335,Lausanne,560
8 48.428611,-123.365556,Victoria,721
9 -33.925278,18.423889,Cape Town,550
10 -33.859972,151.211111,Sydney,436
11 41.383333,2.183333,Barcelona,914
12 39.739167,-104.984722,Denver,869
13 52.95,-1.133333,Nottingham,800
14 45.52,-122.681944,Portland,840
15 37.5667,129.681944,Seoul,473
16 50.733992,7.099814,Bonn,700

```

The Csv to Shp conversion view is shown in Figure 6-39.




Figure 6-39: Csv to Shp Conversion Interface

PyramidMap supports two methods of selecting CSV data: file selector and drag and drop. Taking the drag and drop mode as an example, it is shown in Figure 6-40.




Figure 6-40: Selecting and dragging CSV files to the conversion interface

Form a list of files to be converted, as shown in Figure 6-41.




Figure 6-41: Dragging and Dropping CSV Files to Form a Conversion List

Specifically, in general, the wkt data in CSV does not explicitly indicate coordinate system information, so the output file should be specified with a \*\* Spatial Reference System \*\* (SRS). PyramidMap supports a wide range of SRSs (approximately 5000), and we are constantly updating them. Specify the \*\* Spatial Reference System \*\* (SRS) for the output file, as shown in Figures 6-42.




Figure 6-42: Specifying a Spatial Reference System (SRS) for Output Files

The spatial reference system (SRS) is divided into the Geographic coordinate system (GCS) representing three-dimensional space and the projection coordinate system (PCS) representing right angles to the plane. We classify them in these two ways, and conduct Full-text search through keywords. Perform the conversion process, as shown in Figure 6-43.




Figure 6-43: Performing conversion on CSV file list

The conversion is complete, as shown in Figure 6-44.




Figure 6-44: CSV file list conversion completed

Form a shp and overlay it onto the map view. The preview effect is shown in Figure 6-45.




Figure 6-45: Superimposing the formed shp onto the map view, preview effect

The tutorial data for this chapter is available in PyramidMap to [download](#).

## 6.7.2 Excel to Shp

PyramidMap supports Excel conversion to Shp graphics that meet contractual specifications, and the data source supports feature types such as Point/MultiPoint, LineString/MultiLineString, Polygon/MultiPolygon. PyramidMap parses Excel according to the agreed specifications and converts it into shp. The PyramidMap converter reads from Excel format and uses a column named WKT as geometric data. The WKT column contains geometry as well known text. If you are writing data in Excel format, please ensure that the geometry is created and written into the WKT column. The WKT data format that meets the specifications is shown in Figures 6-46.

R	S	T	U	V	W	X	Y	Z
WKT								
MULTIPOLYGON (((120.41966 36.090991, 120.410955 36.092223, 120.405539 36.088717,								
MULTIPOLYGON (((120.41966 36.090991, 120.420219 36.094797, 120.434309 36.097592,								
MULTIPOLYGON (((119.717048 36.04185, 119.713138 36.040507, 119.708576 36.034802,								
MULTIPOLYGON (((120.484492 36.215752, 120.497775 36.211479, 120.511275 36.208688,								
MULTIPOLYGON (((120.343439 36.208341, 120.351539 36.20287, 120.358739 36.200331,								
MULTIPOLYGON (((120.57066 36.327374, 120.566191 36.327846, 120.559705 36.331624,								
MULTIPOLYGON (((120.656037 36.322163, 120.663004 36.331782, 120.666899 36.332726,								
MULTIPOLYGON (((119.717048 36.04185, 119.720353 36.040649, 119.721315 36.036462,								
MULTIPOLYGON (((120.008077 36.498223, 120.031974 36.481695, 120.038025 36.485246,								
MULTIPOLYGON (((120.634452 36.588998, 120.635631 36.596796, 120.638921 36.599337,								

Figure 6-46: WKT data format that meets specifications

Other columns will be written to Shp as attribute data. Specifically, similar to the section on converting Csv to Shp in 6.7.1, PyramidMap also supports replacing wkt with longitude/latitude fields to indicate the coordinate values for Point type files. In other words, PyramidMap also supports conversion to Shp for Point type Excel files that represent coordinate data in longitude/latitude (case insensitive) fields instead of WKT format. The Excel to SHP conversion interface is shown in Figure 6-47.




Figure 6-47: Excel to SHP Conversion Interface

PyramidMap supports two methods of selecting Excel data: file selector and drag and drop. Taking the drag and drop mode as an example, it is shown in Figure 6-48.




Figure 6-48: Select and drag an Excel file to the conversion interface

Form a list of files to be converted, as shown in Figures 6-49.




Figure 6-49: Dragging and Dropping Excel Files to Form a Conversion List

Specifically, in general, the wkt data in Excel does not explicitly indicate coordinate system information, so a \* \* Spatial Reference System \* \* (SRS) should be specified for the output file. PyramidMap supports a wide range of SRSs (approximately 5000), and we are constantly updating them. Specify the \* \* Spatial Reference System \* \* (SRS) for the output file, as shown in Figures 6-50.




Figure 6-50: Specifying a Spatial Reference System (SRS) for Output Files

The spatial reference system (SRS) is divided into the Geographic coordinate system (GCS) representing three-dimensional space and the projection coordinate system (PCS) representing right angles to the plane. We classify them in these two ways, and conduct Full-text search through keywords. Perform the conversion process, as shown in Figure 6-51.




Figure 6-51: Performing Conversion on Excel File List

The conversion is complete, as shown in Figure 6-52.




Figure 6-52: Excel file list conversion completed

Form a shp and overlay it onto the map view. The preview effect is shown in Figure 6-53.




Figure 6-53: Superimposing the formed shp onto the map view, preview effect

The tutorial data for this chapter is available in PyramidMap to [download](#).

## 6.7.3 GeoJSON to Shp

GeoJSON is an open standard geospatial data exchange format that can represent simple geographic features and their non-spatial attributes. It has become a de facto data standard and is increasingly widely used in data exchange between GIS systems and platforms. GeoJSON is based on JavaScript Object Representation (JSON) and is a format used for encoding various geographic data structures. GeoJSON uses geographical coordinate Frame of reference to define six basic types of geometry: Point, LineString, Polygon, MultiPoint, MultiLineString, and MultiPolygon. GeoJSON geometry can be combined with attribute data to define the features of features and provide data support for conversion to Shp format. The following is an example of a valid GeoJSON file:

```

22                     [119.717048, 36.041844],
23                     [119.72035, 36.040649],
24                     [119.721314, 36.036459],
25                     [119.724365, 36.037674],
26                     [119.729332, 36.037267],
27                     [119.730267, 36.035008],
28                     [119.731875, 36.035606],
29                     [119.733143, 36.034548],
30                     [119.734037, 36.032421],
31                     [119.734633, 36.028226],
32                     [119.717048, 36.041844]
33                 ]
34             ]
35         }
36     }]
37 }
38 }
```

PyramidMap will parse and convert GeoJSON into shp according to standard specifications, verify the validity of the file, and display error messages when the file is invalid. To treat a GeoJSON file as a valid file in PyramidMap, it must start with named "type" as key and with the value of 'FeatureCollection'. You can convert GeoJSON into Shp for loading in project or layer form in the map. Specifically, if the coordinate system CRS parameter is not specified in the data, the coordinate data will be processed as WGS84:4326 by default.

The GeoJSON to shp conversion interface is shown in Figure 6-54.




Figure 6-54: GeoJSON to shp conversion interface

PyramidMap supports two methods of selecting GeoJSON data: file selector and drag and drop. Taking the drag and drop mode as an example, it is shown in Figure 6-55.




Figure 6-55: Selecting and dragging GeoJSON files to the conversion interface

Form a list of files to be converted, as shown in Figure 6-56.




Figure 6-56: Dragging and Dropping GeoJSON Files to Form a Conversion List

GeoJSON uses geographical coordinate Frame of reference to define six basic types of geometry: Point, LineString, Polygon, MultiPoint, MultiLineString, and MultiPolygon. GeoJSON geometry can be combined with attribute data to define the features of features and provide data support for conversion to Shp format. Perform the conversion process, as shown in Figures 6-57.




Figure 6-57: Performing conversion on GeoJSON file list

The conversion is complete, as shown in Figure 6-58.




Figure 6-58: GeoJSON file list conversion completed

Form a shp and overlay it onto the map view. The preview effect is shown in Figure 6-59.




Figure 6-59: Superimposing the formed shp onto the map view, preview effect

The tutorial data for this chapter is available in PyramidMap to [download](#).

## 6.7.4 Shp to Csv and GeoJSON

PyramidMap supports the conversion of Shp vector layers to structured data types such as Kml, Csv, GeoJson, etc. On the vector layer node of PyramidMap Home screen, the data conversion operation is realized through the right-click menu, as shown in Figure 6-60.




Figure 6-60: PyramidMap vector layer node right-click to converting operation

By using the loaded vector layer nodes, it is easy to export maps to multiple types of structured data such as Shp, Csv, Kml, GeoJSON, etc. The operation of the same industry can also be completed in the vector map resource pool, as shown in Figure 6-61.

No	LayerFileName	LayerFilePath	DataSources	GeomGraph	GeomType	UCSR(GRID)	Counts	State	Check
1	binzhou.shp	D:\images\Shp\binzhou.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	7	Normal	
2	zhaozhou.shp	D:\images\Shp\zhaozhou.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	11	Normal	
3	dongying.shp	D:\images\Shp\dongying.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	5	Normal	
4	heze.shp	D:\images\Shp\heze.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	9	Normal	
5	linyi.shp	D:\images\Shp\linyi.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	12	Normal	
6	jining.shp	D:\images\Shp\jining.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	11	Normal	
7	liaocheng.shp	D:\images\Shp\liaocheng.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	8	Normal	
8	linyi.shp	D:\images\Shp\linyi.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	12	Normal	
9	zhaozhou.shp	D:\images\Shp\zhaozhou.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	10	Normal	
10	rizhao.shp	D:\images\Shp\rizhao.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	4	Normal	
11	tai'an.shp	D:\images\Shp\tai'an.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	6	Normal	
12	weihai.shp	D:\images\Shp\weihai.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	12	Normal	
13	wei'an.shp	D:\images\Shp\wei'an.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	4	Normal	
14	yanhai.shp	D:\images\Shp\yanhai.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	11	Normal	
15	zaizhuang.shp	D:\images\Shp\zaizhuang.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	5	Normal	
16	zibo.shp	D:\images\Shp\zibo.shp	From local directory		Multipolygon	WGS 84 EPSG:4326	9	Normal	

Figure 6-61: Vector layer resource pool and data conversion

Taking Csv data as an example, the transformed data fragments are shown below.

```

1 LATITUDE, LONGITUDE, CITY, NUMBER
2 46.066667, 11.116667, Trento, 140
3 44.9441, -93.0852, St Paul, 125
4 13.752222, 100.493889, Bangkok, 150
5 45.420833, -75.69, Ottawa, 200
6 44.9801, -93.251867, Minneapolis, 350
7 46.519833, 6.6335, Lausanne, 560
8 48.428611, -123.365556, Victoria, 721
9 -33.925278, 18.423889, Cape Town, 550
10 -33.859972, 151.211111, Sydney, 436

```

```

11 41.383333, 2.183333, Barcelona, 914
12 39.739167, -104.984722, Denver, 869
13 52.95, -1.133333, Nottingham, 800
14 45.52, -122.681944, Portland, 840
15 37.5667,129.681944,Seoul,473
16 50.733992,7.099814,Bonn,700,2016

```

The tutorial data for this chapter is available in PyramidMap to [download](#).

## 6.7.5 Shp to Kml

Keyhole Markup Language (KML) is an XML based format used to store geographic data and related content, and is an official Open Geospatial Consortium (OGC) standard. The KML format is easy to publish on the Internet and can be viewed through many free applications such as Google Earth and ArcGIS Explorer, making it commonly used for sharing geographic data with non GIS users. KML files have an extension of \*.kml \*\* or \*.kmz \*\* (representing compressed KML files).

Same as the method of exporting Csv and GeoJSON, PyramidMap implements data conversion from vector layer to Kml through layer nodes and map resource pool selection list in the Home screen. The layer node conversion of the Home screen is shown in Figure 6-62.




Figure 6-62: PyramidMap vector layer node right-click kml conversion operation

The same conversion operation can also be completed in the vector map resource pool, as shown in Figure 6-63.




Figure 6-63: Vector layer resource pool and kml data conversion

Select the Shp layer in the list, select the target data format and options, and take the "Convert Coordinate System to Select Attribute Data" option as an example. The execution interface is shown in Figure 6-64.




Figure 6-64: Shp to Kml Setting Coordinate System and Attribute Data Options

Select the target coordinate system and the fields to be exported, click "OK", and the selected shp layer will be selected according to the specified coordinate system and fields, and exported as a kml file under the target path. The exported kml data fragment is as follows:

```

1  <?xml version="1.0" encoding="UTF-8"?>
2  <kml
3      xmlns:xs="http://www.w3.org/2001/XMLSchema"
4      xmlns:kml="http://earth.google.com/kml/2.1">
5      <Document id="featureCollection">
6          <Placemark id="fid-79657dd2_189aaf861b2_-7ffd">

```

```

7      <name>**city</name>
8      <MultiGeometry>
9          <Polygon>
10         <outerBoundaryIs>
11            <LinearRing>
12              <coordinates>121.737819,37.128871
13              121.740542,37.12828 121.743526,37.12536 121.737819,37.128871</coordinates>
14            </LinearRing>
15        </outerBoundaryIs>
16    </Polygon>
17    <Polygon>
18        <outerBoundaryIs>
19          <LinearRing>
20            <coordinates>121.484626,36.732883
21            121.490872,36.738411 121.491364,36.742102 121.484626,36.732883</coordinates>
22          </LinearRing>
23        </outerBoundaryIs>
24    </Polygon>
25  </MultiGeometry>
26 </Placemark>
27 </Document>
28 </kml>

```

The tutorial data for this chapter is available in PyramidMap to [download](#).

## 6.8 Map Tile

Map tiling is a method of dividing an entire map into grids with row and column numbers according to certain rules. Map tiling is the most effective and primary technical means to improve the loading speed of layers, especially for large-scale remote sensing images. Major GIS manufacturers have done so.

For vector maps, tiling can only draw the corresponding elements within the grid according to the required display range, thereby reducing rendering pressure. For raster maps, it can reduce the amount of data requested (or read) at once, thus displaying the map within the area more efficiently.

How to effectively tiling maps according to standard specifications and make the map tiles dataset suitable for different map engines to display correctly on the web is a technical challenge. In this chapter, we will demonstrate the implementation solutions of mainstream slicing technologies such as TMS, XYZ, MVT, MBTiles, etc. through specific examples.


### 6.8.1 Tile pyramid model

The concept of map tiling was first proposed and applied by Google Maps, which uses a specific cutting method to slice the world map grid image using Web Mercator projection coordinates. Web Mercator projection is also a scheme created by Google, which simulates the real elliptical Earth as an isosphere for plane projection, making it convenient for computers to calculate. Subsequently, major mainstream WebGIS and internet map applications adopted a method based on this projection coordinate system for tiling.

The map is tiled according to the pyramid model, and the tile map pyramid model is a multi-resolution hierarchical model that stores and displays at different resolutions according to user needs under a unified spatial reference, forming a pyramid structure with resolution ranging from coarse to fine and data volume ranging from small to large. The geographical range represented

remains unchanged. The lower the pyramid, the more detailed the map information it represents, and the larger of the scale. The schematic diagram of the principle is shown in Figure 6-65.

## Lowest resolution, lowest scale



## Highest resolution, Highest scale

Figure 6-65: Map tile pyramid model

The main principle of a tiling pyramid is to project the Earth of a curved surface onto a two-dimensional plane based on a specific map projection coordinate system, and then divide the two-dimensional plane into multiple scales, which is equivalent to creating multiple digital maps with different resolution levels. Each level corresponds to corresponding codes, and the higher the level, the higher the resolution corresponding to the map; Then, the global spatial range map at each level is gridded using a certain spatial partitioning method, dividing it into fixed size square grid images of several rows and columns. These segmented regular individual grid units are called tiles, and the partitioning method for each level is in the same way.

According to this model, map tiles of corresponding levels can be scheduled based on the displayed range, and corresponding grids can be displayed based on the region, thereby further reducing the amount of data requested (read). Compared to traditional maps, tiling maps reduce the amount of data requested (read) and accelerate rendering efficiency, but it takes up more storage space. It is a typical space for time solution, and the drawbacks of this solution can be almost ignored in today's increasingly low storage costs.

## 6.8.2 Tile coordinate system

The encoding of all tiles is based on the tile coordinate system, and the origin of the tile coordinate system can be represented in two forms:

①TMS standard: TMS (Tile Map Service) is a tile map service defined by the Open Source Geospatial Foundation (OSGeo). In the TMS specification (GeoServer follows this specification), the YX order is used, where latitude at the first and longitude at the last, with the bottom left corner of the map as the origin and the Y coordinate increasing from south to north. The principle is shown in Figure 6-66.




Figure 6-66: Schematic diagram of TMS tile specification

The numbering method for tiles is to start from the bottom left corner and increase the sequence number in ascending/descending order.

②XYZ standard: It is a tiling specification developed by Google/OSM(Open Street Map), using the XY order, where longitude at the first, latitude at the last, and the origin is in the upper left corner of the map. The Y coordinate increases from north to south, as shown in Figure 6-66.




Figure 6-67: Schematic diagram of XYZ tile specification

The numbering method for TILES is to start from the top left corner and increase the sequence number in descending/rightward order. Tiled layer related attributes, including the coordinate system used, EPSG: numerical code; The width and height of the tiles are 256x256 pixels, and the Origin coordinates are (-180, 90). Each pixel represents a unit of longitude and latitude (units per pixel) of  $0.703125/2^n$  ( $n$  is the number of layers of tiles). From this, it can be calculated that when the tile level is level 0, the longitude and latitude across a tile is 180 degrees, indicating that the level 0 is composed of two tiles of 256x256 size side by side.

### 6.8.3 Tile representation

Example as TMS standard, the representation of map tiles is shown in Figures 6-68.




Figure 6-68: Schematic diagram of XYZ tile specification

The attributes related to the tiled layer, including the coordinate system used, (EPSG: numerical code is a coordinate system parameter published and maintained by the European Petroleum Survey Group, and different numerical codes represent different coordinate systems, such as the commonly used WGS84 the EPSG code is 4326); The size of tiles (width&height), such as 256x256 or 512x512 pixels; The origin coordinates in TMS format are (-180, -90), and the origin coordinates in XYZ format are (-180, 90); The number of units per pixel represented by each pixel is  $0.703125/2^n$  ( $n$  is the number of layers of tiles). From this, it can be calculated that when the tile level is level 0, the span of a tile is 180 degrees, indicating that level 0 is composed of two tiles of 256x256 size side by side.

The level is represented by z, where the longitude direction of the tiles (refers to the method of changing the longitude of the tiles, that is, east-west direction, east direction is positive) is numbered as x, and the latitude direction (refers to the direction of changing the dimension of the tiles, TMS refers to north-south direction, north direction is positive; XYZ refers to north-south direction, south direction is positive) is numbered as y, and z is the pyramid hierarchy of the current tile, which is the scaling ratio of the current layer. Therefore, each tile can be uniquely described by a three-dimensional tuple (x, y, z). The tile representation of the map at zoom=1 is shown in Figures 6-69.



Figure 6-69: Tile representation of the map at zoom=1

The tile representation of the map at zoom=2 is shown in Figures 6-70.




Figure 6-70: Tile representation of the map at zoom=2

In the traditional sense, map tile is oriented towards raster on the server side. After the layers are rendered according to the preset style, they are graded and tiled according to the set coordinate system, extend, and zoom level. Map tiles are stored in the form of static bitmaps in the server path, and the tiled images of the corresponding regions are returned based on the client's request extend and scale.

PyramidMap supports all the standard vector and raster map tile processing mentioned above, including: 1: TMS standard vector tile, 2: XYZ standard vector tile, 3: MVT standard vector tile, 4: MBTiles standard vector tile, 5: TMS standard raster tile, 6: XYZ standard raster tile, and 7: MBTiles standard raster tile. The tile operation entry is shown in Figure 6-71.




Figure 6-71: PyramidMap Layer Tile Entry

PyramidMap tiling operations are implemented in the vector map resource pool and the raster map resource pool, respectively.

## 6.8.4 Build Vector TMS tile

TMS (Tile Map Service) is a tile standard defined by the Open Source Geospatial Foundation (OSGeo). TMS defines tile starting from the bottom left corner of the map, with the bottom left corner of the map as the origin of the tile and coding system, and the vertical coordinate (Y value) increasing from south to north. PyramidMap supports TMS tile of vector layers, providing dynamic tile data loading at different resolutions for web GIS applications. In the PyramidMap vector resource pool, select the vector layer in batch mode, as shown in Figure 6-72.

No.	Layer/fileName	Layer/filePath	DataSources	GeomGraphic	GeoType	UCS(SRID)	Counts	State	Check
1	Buildings.shp	D:\maps\California\Buildings.shp	From local directory	Point	GCS_WGS_1984_EPSG_4326	4361	Normal	<input type="checkbox"/>	
2	Cemeteries.shp	D:\maps\California\Cemeteries.shp	From local directory	Point	GCS_WGS_1984_EPSG_4326	842	Normal	<input checked="" type="checkbox"/>	
3	Churches.shp	D:\maps\California\Churches.shp	From local directory	Point	GCS_WGS_1984_EPSG_4326	183613	Normal	<input type="checkbox"/>	
4	Coulters.shp	D:\maps\California\Coulters.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG_4326	56	Normal	<input type="checkbox"/>	
5	GolfCourses.shp	D:\maps\California\GolfCourses.shp	From local directory	Point	GCS_WGS_1984_EPSG_4326	537	Normal	<input checked="" type="checkbox"/>	
6	Hospitals.shp	D:\maps\California\Hospitals.shp	From local directory	Point	GCS_WGS_1984_EPSG_4326	433	Normal	<input type="checkbox"/>	
7	Lakes.shp	D:\maps\California\Lakes.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG_4326	2	Normal	<input checked="" type="checkbox"/>	
8	LandmarkAreas.shp	D:\maps\California\LandmarkAreas.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG_4326	10467	Normal	<input type="checkbox"/>	
9	MajorRoads.shp	D:\maps\California\MajorRoads.shp	From local directory	MultilineString	GCS_WGS_1984_EPSG_4326	72033	Normal	<input type="checkbox"/>	
10	Rivers.shp	D:\maps\California\Rivers.shp	From local directory	MultilineString	GCS_WGS_1984_EPSG_4326	4	Normal	<input checked="" type="checkbox"/>	
11	Schools.shp	D:\maps\California\Schools.shp	From local directory	Point	GCS_WGS_1984_EPSG_4326	11381	Normal	<input type="checkbox"/>	
12	States.shp	D:\maps\California\States.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG_4326	1	Normal	<input checked="" type="checkbox"/>	
13	UrbanAreas.shp	D:\maps\China\UrbanAreas.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG_4326	131	Normal	<input checked="" type="checkbox"/>	
14	binzhou.shp	D:\maps\Shandong\binzhou.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	7	Normal	<input type="checkbox"/>	
15	dezhou.shp	D:\maps\Shandong\dezhou.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	11	Normal	<input type="checkbox"/>	
16	dongning.shp	D:\maps\Shandong\EN3857\dongning.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	5	Normal	<input type="checkbox"/>	
17	heze.shp	D:\maps\Shandong\EN3857\heze.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	9	Normal	<input type="checkbox"/>	
18	jinan.shp	D:\maps\Shandong\EN3857\jinan.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	12	Normal	<input type="checkbox"/>	
19	jining.shp	D:\maps\Shandong\EN3857\jining.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	11	Normal	<input type="checkbox"/>	
20	laicheng.shp	D:\maps\Shandong\EN3857\laicheng.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	8	Normal	<input type="checkbox"/>	
21	linyi.shp	D:\maps\Shandong\EN3857\linyi.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	12	Normal	<input type="checkbox"/>	
22	qingdao.shp	D:\maps\Shandong\EN3857\qingdao.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	10	Normal	<input type="checkbox"/>	
23	rizhao.shp	D:\maps\Shandong\EN3857\rizhao.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	4	Normal	<input type="checkbox"/>	
24	taian.shp	D:\maps\Shandong\EN3857\taian.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	6	Normal	<input type="checkbox"/>	
25	wefang.shp	D:\maps\Shandong\EN3857\wefang.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	12	Normal	<input type="checkbox"/>	
26	weihai.shp	D:\maps\Shandong\EN3857\weihai.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	4	Normal	<input type="checkbox"/>	
27	yantai.shp	D:\maps\Shandong\EN3857\yantai.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	11	Normal	<input type="checkbox"/>	
28	zaoyang.shp	D:\maps\Shandong\EN3857\zaoyang.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	6	Normal	<input type="checkbox"/>	
29	zibo.shp	D:\maps\Shandong\EN3857\zibo.shp	From local directory	Multipolygon	WGS_84_Pseudo-Mercator_EPSG_3857	8	Normal	<input type="checkbox"/>	
30	binzhou.shp	D:\maps\Shandong\EN3857\binzhou.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	7	Normal	<input type="checkbox"/>	
31	dezhou.shp	D:\maps\Shandong\EN3857\dezhou.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	11	Normal	<input type="checkbox"/>	
32	dongning.shp	D:\maps\Shandong\EN3857\east.dongning.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	5	Normal	<input type="checkbox"/>	
33	heze.shp	D:\maps\Shandong\EN3857\heze.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	9	Normal	<input type="checkbox"/>	
34	jinan.shp	D:\maps\Shandong\EN3857\jinan.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	12	Normal	<input type="checkbox"/>	
35	jining.shp	D:\maps\Shandong\EN3857\jining.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	11	Normal	<input type="checkbox"/>	
36	laicheng.shp	D:\maps\Shandong\EN3857\laicheng.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	8	Normal	<input type="checkbox"/>	
37	linyi.shp	D:\maps\Shandong\EN3857\linyi.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	12	Normal	<input type="checkbox"/>	
38	qingdao.shp	D:\maps\Shandong\EN3857\qingdao.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	10	Normal	<input type="checkbox"/>	
39	rizhao.shp	D:\maps\Shandong\EN3857\rizhao.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	4	Normal	<input type="checkbox"/>	
40	taian.shp	D:\maps\Shandong\EN3857\taian.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	6	Normal	<input type="checkbox"/>	
41	wefang.shp	D:\maps\Shandong\EN3857\wefang.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	12	Normal	<input type="checkbox"/>	
42	weihai.shp	D:\maps\Shandong\EN3857\weihai.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	11	Normal	<input type="checkbox"/>	
43	yantai.shp	D:\maps\Shandong\EN3857\yantai.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	11	Normal	<input type="checkbox"/>	
44	zaozhuang.shp	D:\maps\Shandong\EN3857\zaozhuang.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	6	Normal	<input type="checkbox"/>	
45	zibo.shp	D:\maps\Shandong\EN3857\zibo.shp	From local directory	Multipolygon	WGS_84_EPSG_4326	8	Normal	<input type="checkbox"/>	

Figure 6-72: Select Vector layers for TMS tile

Select the TMS tile option and then open the tile scheme interface, as shown in Figure 6-73.




Figure 6-73: TMS tile scheme for vector layer

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

The rendering scheme defines the rendering mode of the layer and supports rendering configurations for all collection types such as Point/MultiPoint, Linestring/MultiLinestring, Polygon/MultiPolygon, including point type symbols, size, stroke width, stroke and fill colors, and the opacity.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The tiling process is shown in Figures 6-74.




Figure 6-74: TMS tiling process of vector layers

The progress bar indicate the tiling process and status of each selected layer. The completion prompt is shown in Figure 6-75.




Figure 6-75: TMS tiling completed prompt

The final generated tiles will be classified according to the original layer name, grouped according to the Z value (zoom level) and X value, named according to the Y value, and saved to the corresponding hierarchical directory. At the same level, the tiles will be grouped based on the X value. The tiles with the same X value will be saved to the same path which named with the X value, and the tiles will be named with the Y value. The directory structure is shown as Figure 6-76.

1	2023/9/7 9:51
2	2023/9/7 9:51
3	2023/9/7 9:51
4	2023/9/7 9:51
5	2023/9/7 9:51
6	2023/9/7 9:51
7	2023/9/7 9:51
8	2023/9/7 9:51
9	2023/9/7 9:51
10	2023/9/7 9:51
11	2023/9/7 9:51

Figure 6-76: The target TMS tiles folder which corresponding to the zoomlevel

View the tile file at a certain level, as shown in Figures 6-77.




Figure 6-77: Vector layer TMS tiles file

When storing tiles, the code uses a folder structure that follows the TMS (Tile Map Service) standard, namely Z/X/Y.png, where Z represents the zoom level and X and Y represent the coordinates of the tiles. During this process, the code also checks and creates necessary folders. After completing the tiling, deploy the tiles to a web server, such as Apache Tomcat, nothing with the professional mapserver such as GeoServer, that will greatly reduce the difficulty and cost of map deployment and maintenance. You can deploy independently, access tiles data through HTTP URLs, or integrate deployment with projects, and access tiles data through relative paths. As an example, we demonstrate the web gis application through Leaflet, the complete code is as follows:

```

1 <!DOCTYPE html>
2 <html lang="en">
3   <head>
4     <meta charset="UTF-8">
5     <meta name="viewport" content="width=device-width, initial-scale=1.0">
6     <title>Leaflet vector TMS tiles Example</title>
7     <link rel="stylesheet"
8       href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9   </head>
10  <style type="text/css">
11    body {
12      margin: 0;
13      padding: 0;

```

```
13     }
14     html, body, #map{
15         width: 100%;
16         height: 100%;
17     }
18 </style>
19 <body>
20 <div id="map" ></div>
21 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
22 <script>
23     var map = L.map('map').setView([31.562710059362658,120.29751401540051], 8);
24     // loading the ArcGIS basemap resource
25 L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/World_Topo
26 _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
27     // loading the local TMS tiles,Please modify according to the real path
28     // of yourself.
29     L.tileLayer('.data/tiles/jinan/{z}/{x}/{y}.png', {
30         tms: true, // Indicates this is a TMS tile
31         opacity: 0.7 // The opacity of the polygon tile can be adjusted as
32         needed
33     }).addTo(map);
34 </script>
35 </body>
36 </html>
```

Then display on the map as shown in Figures 6-78.




Figure 6-78: The TMS tiles loading in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The tutorial shp files to build tiles can be [download](#) also in PyramidMap. You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

## 6.8.5 Build Vector XYZ tile

XYZ tile is a standard adopted by Google/OSM (Open Street Map). TMS defines tile as starting from the bottom left corner of the map, with the bottom left corner of the map as the origin of the tile and coding system, and the vertical coordinate (Y value) increasing from south to north. On the contrary, Google uses the top left corner of the map as the origin of the tile and coding system, with the y-axis (Y value) increasing from north to south. In the PyramidMap vector map resource pool, select the vector layer and support batch selection, as shown in Figure 6-79.

The screenshot shows the PyramidMap interface with a toolbar at the top and a main content area below. The content area displays a table of vector layers:

No.	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCS(SRID)	Counts	State	Check
1	Buildings.shp	D:\maps\California3857\Buildings.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	4361	Normal	<input checked="" type="checkbox"/>
2	Cemeteries.shp	D:\maps\California3857\Cemeteries.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	842	Normal	<input checked="" type="checkbox"/>
3	Churches.shp	D:\maps\California3857\Churches.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	183613	Normal	<input type="checkbox"/>
4	Counties.shp	D:\maps\California3857\Counties.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	58	Normal	<input checked="" type="checkbox"/>
5	GolfCourses.shp	D:\maps\California3857\GolfCourses.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	537	Normal	<input checked="" type="checkbox"/>
6	Hospitals.shp	D:\maps\California3857\Hospitals.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	438	Normal	<input checked="" type="checkbox"/>
7	Lakes.shp	D:\maps\California3857\Lakes.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	2	Normal	<input checked="" type="checkbox"/>
8	LandmarkAreas.shp	D:\maps\California3857\LandmarkAreas.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	10467	Normal	<input type="checkbox"/>
9	MajorRoads.shp	D:\maps\California3857\MajorRoads.shp	From local directory	MultilineString	MultilineString	WGS 84 / Pseudo-Mercator EPSG:3857	72033	Normal	<input type="checkbox"/>
10	Rivers.shp	D:\maps\California3857\Rivers.shp	From local directory	MultilineString	MultilineString	WGS 84 / Pseudo-Mercator EPSG:3857	4	Normal	<input checked="" type="checkbox"/>
11	Schools.shp	D:\maps\California3857\Schools.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG:3857	11381	Normal	<input checked="" type="checkbox"/>
12	States.shp	D:\maps\California3857\States.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	1	Normal	<input checked="" type="checkbox"/>
13	UrbanAreas.shp	D:\maps\California3857\UrbanAreas.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG:3857	191	Normal	<input checked="" type="checkbox"/>
14	Buildings.shp	D:\maps\CaliforniaBuildings.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	4361	Normal	<input type="checkbox"/>
15	Cemeteries.shp	D:\maps\CaliforniaCemeteries.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	842	Normal	<input type="checkbox"/>
16	Churches.shp	D:\maps\CaliforniaChurches.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	183613	Normal	<input type="checkbox"/>
17	Counties.shp	D:\maps\CaliforniaCounties.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG:4326	58	Normal	<input type="checkbox"/>
18	GolfCourses.shp	D:\maps\CaliforniaGolfCourses.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	537	Normal	<input type="checkbox"/>
19	Hospitals.shp	D:\maps\CaliforniaHospitals.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	438	Normal	<input type="checkbox"/>
20	Lakes.shp	D:\maps\CaliforniaLakes.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG:4326	2	Normal	<input type="checkbox"/>
21	LandmarkAreas.shp	D:\maps\CaliforniaLandmarkAreas.shp	From local directory	MultilineString	MultilineString	GCS_WGS_1984 EPSG:4326	10467	Normal	<input type="checkbox"/>
22	MajorRoads.shp	D:\maps\CaliforniaMajorRoads.shp	From local directory	MultilineString	MultilineString	GCS_WGS_1984 EPSG:4326	72033	Normal	<input type="checkbox"/>
23	Rivers.shp	D:\maps\CaliforniaRivers.shp	From local directory	MultilineString	MultilineString	GCS_WGS_1984 EPSG:4326	4	Normal	<input type="checkbox"/>
24	Schools.shp	D:\maps\CaliforniaSchools.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG:4326	11381	Normal	<input type="checkbox"/>
25	States.shp	D:\maps\CaliforniaStates.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG:4326	1	Normal	<input type="checkbox"/>
26	UrbanAreas.shp	D:\maps\CaliforniaUrbanAreas.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG:4326	191	Normal	<input type="checkbox"/>

Below the table, there is a toolbar with various buttons, and a dropdown menu labeled "Layer tile" which is highlighted with a red box. The dropdown menu contains four options: "TMS tile", "XYZ tile" (which is selected), "MVT tile", and "Mapbox tile".

Figure 6-79: Select vector layers for XYZ tile

Select the XYZ format tile and then open the tile scheme interface, as shown in Figure 6-80.




Figure 6-80: XYZ tile scheme for vector layer

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

The rendering scheme defines the rendering mode of the layer and supports rendering configurations for all collection types such as Point/MultiPoint, LineString/MultiLineString, Polygon/MultiPolygon, including point type symbols, size, stroke width, stroke and fill colors, and the opacity.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The tiling process is shown in Figures 6-81.




Figure 6-81: XYZ tiling process of vector layers

The progress bar indicate the tiling process and status of each selected layer. The completion prompt is shown in Figure 6-82.




Figure 6-82: XYZ tiling completed prompt

The final generated tiles will be classified according to the original layer name, grouped according to the Z value (zoom level) and X value, named according to the Y value, and saved to the corresponding hierarchical directory. At the same level, the tiles will be grouped based on the X value. The tiles with the same X value will be saved to the same path which named with the X

value, and the tiles will be named with the Y value. The directory structure is shown as Figure 6-83.

 1	2023/9/7 11:19
 2	2023/9/7 11:19
 3	2023/9/7 11:19
 4	2023/9/7 11:19
 5	2023/9/7 11:19
 6	2023/9/7 11:19
 7	2023/9/7 11:19
 8	2023/9/7 11:19
 9	2023/9/7 11:19
 10	2023/9/7 11:19
 11	2023/9/7 11:19

Figure 6-83: The target XYZ tiles folder which corresponding to the zoomlevel

View the tile file at a certain level, as shown in Figures 6-84.




Figure 6-84: Vector layer XYZ tiles file

When storing tiles, the code uses a folder structure that follows the TMS (Tile Map Service) standard, namely Z/X/Y.png, where Z represents the zoom level and X and Y represent the coordinates of the tiles. During this process, the code also checks and creates necessary folders. After completing the tiling, deploy the tiles to a web server, such as Apache Tomcat, nothing with the professional mapserver such as GeoServer, that will greatly reduce the difficulty and cost of map deployment and maintenance. You can deploy independently, access tiles data through HTTP URLs, or integrate deployment with projects, and access tiles data through relative paths. As an example, we demonstrate the web gis application through Leaflet, the complete code is as follows:

```

1 <!DOCTYPE html>
2 <html lang="en">
3 <head>
4   <meta charset="UTF-8">
5   <meta name="viewport" content="width=device-width, initial-scale=1.0">
6   <title>Leaflet vector XYZ Tiles Example</title>
7   <link rel="stylesheet"
8     href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9   <style type="text/css">
```

```

10    body {
11        margin: 0;
12        padding: 0;
13    }
14    html, body, #map{
15        width: 100%;
16        height: 100%;
17    }
18 </style>
19 <body>
20 <div id="map" ></div>
21 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
22 <script>
23     //Initialize the map and set the center and zoom levels
24     var map = L.map('map').setView([33.923710059362658,-118.23851401540051],
25     8);
26     // Loading ArcGIS online basemap resource
27
28     L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/world_Topo
29     _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
30     // Load local XYZ TILES, please modify according to your file path.
31     L.tileLayer('./data/tiles/xyz3857/UrbanAreas/{z}/{x}/{y}.png', {
32         tms: false, // Indicates this is an XYZ standard tiles
33         opacity: 0.7 // The transparency of the tile can be adjusted as
34         needed
35     }).addTo(map);
36 </script>
37 </body>
38 </html>

```

The loading effect on the map is shown in Figures 6-85.




Figure 6-85: The XYZ format tiles loading in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The tutorial shp files to build tiles can be [download](#) also in PyramidMap. You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

## 6.8.6 Build Vector MVT tile

MVT (Mapbox Vector Tiles), as the name suggests, this is a vector tile standard created by Mapbox. At present, there are three main formats for vector tiles: mvt (pbf), geojson, and topojson, all of these which with the best compression rate and transmission speed being the mvt format. MVT divides the traditional tile mode into two processes which including vector tiles data and style rendering separately, it represents a more novel map service mode. Its characteristic is that the server only stores vector tile data, and the rendering is completed on the client side. MVT vector tile technology inherits the dual advantages of vector data and traditional tile, reflected in the following aspects:

- 1. Lossless storage: Tiles are stored in mvt format, based on each tile number. All sizes are 256 \* 256; Smaller granularity and nearly lossless information;
- 2. Smaller volume: MVT has higher compression rate and smaller volume;
- 3. Fast response speed: This is an inherent characteristic of tiled data, and the server returns data according to the client's request level;
- 4. Fast transmission speed: The data and rendering are separated, and the server only returns mvt vector data, which reduces the network load and improves the transmission and loading speed;
- 5. Implement client-side rendering: In the web client, achieve custom style rendering, giving a more flexible and rich display effect;
- 6. Implement more UI interaction: MVT enables client side vectorization operations on maps, such as interactive operations, attribute and spatial queries, independent value rendering, thematic statistics, and other feature based functions, thereby enriching map functionality.
- 7. Make full use of hardware resources: mvt utilizes OpenGL/WebGL drivers, adjusts graphics card and memory performance, adapts to client screens, and performs high-precision vector rendering based on screen resolution. It can be said that for the same tile data, different hardware performance and rendering effects are different, which completely depends on the client's display system.

Based on the above advantages, MVT technology has quickly gained recognition and support from a wide range of map manufacturers. ArcGIS, Leaflet, MapTiler, and OpenLayers have all added support for the MVT specification.

Of course, when viewed dialectically, advantages and disadvantages come with each other, and there is no such thing as having only advantages and no disadvantages. The disadvantage of MVT is its by-product of pursuing advantages, which is its high technical cost. Currently, the using range of MVT is limited by the following points:

- 1. High technical difficulty: The usual approach is to upload the map to Mapbox studio and perform slicing hosting on the Mapbox platform. This requires registering a Mapbox account and customizing the tile mode, which is a complex process;
- 2. High usage cost: The usage cost of online MVT generation and hosting is very high. Taking Mapbox Studio as an example, its service space and traffic are limited, and if it exceeds the limit, fees will be charged. For ordinary users and small and medium-sized enterprises, this is not an ideal option;

PyramidMap provides the ability for users to independently produce, host, and use MVTs. PyramidMap can perform MVT tiles in localization, and deploy the tiles data freely. You can publish data within the programs together, and access tiles data through URL relative paths without any special configuration in the web application, greatly simplifying the map data processing, improving system deployment flexibility, and reducing project implementation costs.

Before tiling, let's first take a look at the original layer in shp format, using Building.shp as an example, which represents the iconic buildings, locations, and elevations of California, as shown in Figures 6-86.




Figure 6-86: The Original Shp for MVT tiles

Its specific location is shown in Figures 6-87.




Figure 6-87: The specific location of the original Shp

Open data table of the shp file, as shown in Figure 6-88.

FeatureIdentifier	the_geom	NAME	STCTYFIPS	ELEV_METER	LABEL_FLAG
Buildings.1549	POINT (-118.21813073899995 34....)	Quartz Hill Branch County of Los An...	06037	760.0	0
Buildings.1550	POINT (-118.6106419429999 34....)	Woodland Hills Branch Los Angeles ...	06037	274.0	0
Buildings.1551	POINT (-119.77934336899995 38....)	Alpine County Courthouse	06003	1684.0	0
Buildings.1552	POINT (-119.78045466899995 38....)	Alpine County Free Library	06003	1686.0	0
Buildings.1553	POINT (-119.77934336899995 38....)	Alpine County Law Library	06003	1684.0	0
Buildings.1554	POINT (-119.78073233899994 34....)	Historical Society of Alpine County ...	06003	1688.0	0
Buildings.1555	POINT (-118.11618354099994 34....)	Palmdale City Library	06037	810.0	0
Buildings.1556	POINT (-117.89950598199993 34....)	Pearblossom Arts Center	06037	929.0	0
Buildings.1557	POINT (-117.75839058899994 34....)	Beth Israel Community Center	06037	272.0	0
Buildings.1558	POINT (-117.76033505399995 34....)	Eagles Hall	06037	255.0	0
Buildings.1559	POINT (-117.751235759995 34....)	Pomona City Hall	06037	260.0	0
Buildings.1560	POINT (-117.75283487399992 38....)	Pomona County Building	06037	259.0	0
Buildings.1561	POINT (-120.11352076799994 39....)	Childrens House	06017	1902.0	0
Buildings.1562	POINT (-120.11370959299995 39....)	Ehrman Mansion	06017	1903.0	0
Buildings.1563	POINT (-119.97164788099992 38....)	El Dorado Government Center	06017	1912.0	0
Buildings.1564	POINT (-120.11324294399992 39....)	General Phipps Cabin	06017	1900.0	0
Buildings.1565	POINT (-120.83826827499995 38....)	Georgetown Branch El Dorado Cou...	06017	814.0	0
Buildings.1566	POINT (-120.11463191299993 39....)	Ice House	06017	1902.0	0
Buildings.1567	POINT (-120.11324294399992 39....)	North Boat House	06017	1900.0	0
Buildings.1568	POINT (-120.58464788499992 38....)	Pilot Creek House (historical)	06017	1300.0	0
Buildings.1569	POINT (-120.11213164599991 39....)	South Boat House	06017	1901.0	0
Buildings.1570	POINT (-120.10046316899991 38....)	Tea House	06017	1902.0	0
Buildings.1571	POINT (-120.89132708999995 38....)	Kane House	06017	232.0	0
Buildings.1572	POINT (-120.89216056299995 38....)	Marshall Gold Discovery State Histo...	06017	231.0	0
Buildings.1573	POINT (-120.89299373099993 38....)	Marshalls Cabin	06017	281.0	0
Buildings.1574	POINT (-119.97629245999991 38....)	Meyer Visitors Center	06017	1905.0	0
Buildings.1575	POINT (-120.89077144099991 38....)	Old Coloma Theatre	06017	265.0	0
Buildings.1576	POINT (-120.88993827399992 38....)	Papini House	06017	236.0	0
Buildings.1577	POINT (-119.97323684999992 38....)	South Lake Tahoe Branch El Dorad...	06017	1907.0	0
Buildings.1578	POINT (-120.89160481399991 38....)	Thomas House	06017	243.0	0
Buildings.1579	POINT (-120.89021594499991 38....)	Vineyard House	06017	278.0	0
Buildings.1580	POINT (-121.07049853899993 38....)	Oakridge-Finfrared Hills Branch Fl...	06017	237.0	0

Figure 6-88: Open data table of Buildings.shp

Next, we will tile the vector layers including Buildings.shp in the vector resource pool under batch mode, as shown in Figure 6-89.

The screenshot shows the PyramidMap interface with the 'GeoServer Layers' tab selected. A large table lists various vector layers from a local directory, including Buildings.shp, Cemeteries.shp, Churches.shp, Counties.shp, GolfCourses.shp, Hospitals.shp, Lakes.shp, LandmarkAreas.shp, MajorRoads.shp, Rivers.shp, Schools.shp, States.shp, and UrbanAreas.shp. The 'Spatial processing' dropdown menu at the bottom is open, and the 'Layer tile' option is highlighted with a red box.

No.	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCS(SRID)	Counts	State	Check
1	Buildings.shp	D:\maps\California\3857\Buildings.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	4361	Normal	<input checked="" type="checkbox"/>	
2	Cemeteries.shp	D:\maps\California\3857\Cemeteries.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	842	Normal	<input checked="" type="checkbox"/>	
3	Churches.shp	D:\maps\California\3857\Churches.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	183613	Normal	<input type="checkbox"/>	
4	Counties.shp	D:\maps\California\3857\Counties.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	58	Normal	<input checked="" type="checkbox"/>	
5	GolfCourses.shp	D:\maps\California\3857\GolfCourses.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	537	Normal	<input checked="" type="checkbox"/>	
6	Hospitals.shp	D:\maps\California\3857\Hospitals.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	438	Normal	<input checked="" type="checkbox"/>	
7	Lakes.shp	D:\maps\California\3857\Lakes.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	2	Normal	<input checked="" type="checkbox"/>	
8	LandmarkAreas.shp	D:\maps\California\3857\LandmarkAreas.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	10467	Normal	<input type="checkbox"/>	
9	MajorRoads.shp	D:\maps\California\3857\MajorRoads.shp	From local directory	MultilineString	WGS 84 / Pseudo-Mercator EPSG 3857	72033	Normal	<input type="checkbox"/>	
10	Rivers.shp	D:\maps\California\3857\Rivers.shp	From local directory	MultilineString	WGS 84 / Pseudo-Mercator EPSG 3857	4	Normal	<input checked="" type="checkbox"/>	
11	Schools.shp	D:\maps\California\3857\Schools.shp	From local directory	Point	WGS 84 / Pseudo-Mercator EPSG 3857	11381	Normal	<input type="checkbox"/>	
12	States.shp	D:\maps\California\3857\States.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	11	Normal	<input checked="" type="checkbox"/>	
13	UrbanAreas.shp	D:\maps\California\3857\UrbanAreas.shp	From local directory	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	191	Normal	<input checked="" type="checkbox"/>	
14	Buildings.shp	D:\maps\California\Buildings.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	4361	Normal	<input type="checkbox"/>	
15	Cemeteries.shp	D:\maps\California\Cemeteries.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	842	Normal	<input type="checkbox"/>	
16	Churches.shp	D:\maps\California\Churches.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG4326	183613	Normal	<input type="checkbox"/>	
17	Counties.shp	D:\maps\California\Counties.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG4326	58	Normal	<input type="checkbox"/>	
18	GolfCourses.shp	D:\maps\California\GolfCourses.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	537	Normal	<input type="checkbox"/>	
19	Hospitals.shp	D:\maps\California\Hospitals.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG4326	438	Normal	<input type="checkbox"/>	
20	Lakes.shp	D:\maps\California\Lakes.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG4326	2	Normal	<input type="checkbox"/>	
21	LandmarkAreas.shp	D:\maps\California\LandmarkAreas.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG4326	10467	Normal	<input type="checkbox"/>	
22	MajorRoads.shp	D:\maps\California\MajorRoads.shp	From local directory	MultilineString	GCS_WGS_1984_EPSG4326	72033	Normal	<input type="checkbox"/>	
23	Rivers.shp	D:\maps\California\Rivers.shp	From local directory	MultilineString	GCS_WGS_1984_EPSG4326	4	Normal	<input type="checkbox"/>	
24	Schools.shp	D:\maps\California\Schools.shp	From local directory	Point	GCS_WGS_1984_EPSG4326	11381	Normal	<input type="checkbox"/>	
25	States.shp	D:\maps\California\States.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG4326	1	Normal	<input type="checkbox"/>	
26	UrbanAreas.shp	D:\maps\California\UrbanAreas.shp	From local directory	Multipolygon	GCS_WGS_1984_EPSG4326	191	Normal	<input type="checkbox"/>	

Figure 6-89: Choose Vector layers to MVT tiling

Select the MVT tile and then open the tile scheme interface, as shown in Figure 6-90.

The screenshot shows the 'Scheme for the MVT (Mapbox Vector Tiles)' dialog. At the top, it says 'Select target CRS' set to 'GCS'. Below is a table of datum definitions. In the center, there's a 'Max zoomlevel' slider with values from 1 to 23, currently set to 11. At the bottom, there's a 'Save Path' field containing 'D:\maps\vectortiles\mvt3857' and a 'Select' button.

No.	EPSG Code	CRS	Check
1	3819	HD1909	<input checked="" type="radio"/>
2	3821	TWD67	<input type="radio"/>
3	3824	TWD97	<input type="radio"/>
4	3889	IGRS	<input type="radio"/>
5	3906	MGI 1901	<input type="radio"/>
6	4001	Unknown datum based upon the Airy 1830 ellipsoid	<input type="radio"/>
7	4002	Unknown datum based upon the Airy Modified 1849 ellipsoid	<input type="radio"/>
8	4003	Unknown datum based upon the Australian National Spheroid	<input type="radio"/>
9	4004	Unknown datum based upon the Bessel 1841 ellipsoid	<input type="radio"/>
10	4005	Unknown datum based upon the Bessel Modified ellipsoid	<input type="radio"/>
11	4006	Unknown datum based upon the Bessel Namibia ellipsoid	<input type="radio"/>
12	4007	Unknown datum based upon the Clarke 1858 ellipsoid	<input type="radio"/>
13	4008	Unknown datum based upon the Clarke 1866 ellipsoid	<input type="radio"/>
14	4009	Unknown datum based upon the Clarke 1866 Michigan ellipsoid	<input type="radio"/>
15	4010	"Unknown datum based upon the Clarke 1880 (Benoit) ellipsoid"	<input type="radio"/>
16	4011	"Unknown datum based upon the Clarke 1880 (IGN) ellipsoid"	<input type="radio"/>
17	4012	"Unknown datum based upon the Clarke 1880 (RGS) ellipsoid"	<input type="radio"/>
18	4013	"Unknown datum based upon the Clarke 1880 (Arc) ellipsoid"	<input type="radio"/>
19	4014	"Unknown datum based upon the Clarke 1880 (SGA 1922) ellipsoid"	<input type="radio"/>
20	4015	"Unknown datum based upon the Everest 1830 (1937 Adjustment) ellipsoid"	<input type="radio"/>

Figure 6-90: Vector layer MVT tiling scheme

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

Unlike TMS and XYZ tiling, MVT does not require pre set map rendering. In fact, the results of TMS and XYZ format tiling are still png tiles. The tile data is stored in the server as a static image and not rendered on the client. Although the data source is vector, the tiles are non vector. The MVT are only vector data, and map rendering is achieved through user-defined style files on the client, so there is no need to preset tile rendering strategies.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The tiling process is shown in Figures 6-91.




Figure 6-91: MVT tiling process of vector layers

The progress bar indicate the tiling process and status of each selected layer.

The final generated tiles will be classified according to the original layer name, grouped according to the Z value (zoom level) and X value, named according to the Y value, and saved to the corresponding hierarchical directory. At the same level, the tiles will be grouped based on the X value. The tiles with the same X value will be saved to the same path which named with the X value, and the tiles will be named with the Y value.

View the mvt tile files at a certain level. As shown in Figures 6-92.

190.mvt	2023/8/30 19:40	MVT	1 KB
191.mvt	2023/8/30 19:40	MVT	1 KB
192.mvt	2023/8/30 19:40	MVT	1 KB
193.mvt	2023/8/30 19:40	MVT	1 KB
194.mvt	2023/8/30 19:40	MVT	1 KB
195.mvt	2023/8/30 19:40	MVT	1 KB
196.mvt	2023/8/30 19:40	MVT	1 KB
197.mvt	2023/8/30 19:40	MVT	4 KB
198.mvt	2023/8/30 19:40	MVT	4 KB
199.mvt	2023/8/30 19:40	MVT	2 KB
200.mvt	2023/8/30 19:40	MVT	1 KB
201.mvt	2023/8/30 19:40	MVT	1 KB
202.mvt	2023/8/30 19:40	MVT	1 KB
203.mvt	2023/8/30 19:40	MVT	1 KB
204.mvt	2023/8/30 19:40	MVT	1 KB
205.mvt	2023/8/30 19:40	MVT	1 KB
206.mvt	2023/8/30 19:40	MVT	1 KB

Figure 6-92: View the mvt tile files at a certain level

At this point, the MVT vector tiling process is completed.

When storing tiles, the code uses a folder structure that follows the TMS (Tile Map Service) standard, namely Z/X/Y.png, where Z represents the zoom level and X and Y represent the coordinates of the tiles. During this process, the code also checks and creates necessary folders. After completing the tiling, deploy the tiles to a web server, such as Apache Tomcat, nothing with the professional mapserver such as GeoServer, that will greatly reduce the difficulty and cost of map deployment and maintenance. You can deploy independently, access tiles data through HTTP URLs, or integrate deployment with projects, and access tiles data through relative paths. As an example, we demonstrate the web gis application through Leaflet.

Taking the Buildings.shp as an example, open its data table in PyramidMap, as shown in Figure 6-93.

要素数据列表	FeatureIdentifier	the_geom	NAME	STCTYFIPS	ELEV_METER	LABEL_FLAG	-	□	X
Buildings.2147	POINT (-118.41594433949994 37.362151761000064)	Paiute-Shoshone Indian Cultural Center	06027	1282.0	0				
Buildings.2148	POINT (-118.1784339969999 37.385484732000066)	Schulman Grove Visitor Center	06027	3068.0	0				
Buildings.2149	POINT (-118.20148393599993 36.801321328000085)	Eastern California Museum	06027	1203.0	0				
Buildings.2150	POINT (-118.19926164599991 36.80215464900045)	Inyo County Courthouse	06027	1199.0	0				
Buildings.2151	POINT (-118.19898397499992 36.80215464900045)	Inyo County Free Library	06027	1198.0	0				
Buildings.2152	POINT (-116.86671957099992 36.46189267800008)	Death Valley National Park Visitor Center	06027	-54.0	0				
Buildings.2153	POINT (-120.342441937199994 38.282539448000046)	Independence Hall	06009	1193.0	0				
Buildings.2154	POINT (-120.07602104499995 38.4397095200007)	Tamarack Lodge	06009	2107.0	0				
Buildings.2155	POINT (-120.52964328099994 38.40074509000004)	West Point Branch Calaveras County Library	06009	630.0	0				
Buildings.2156	POINT (-120.5271481659999 38.39546764900007)	West Point Community Hall	06009	829.0	0				
Buildings.2157	POINT (-120.35464196499993 38.254917240000054)	Arnold Branch Calaveras County Library	06009	1204.0	0				
Buildings.2158	POINT (-120.46242164099993 38.13408701100008)	Black Bart Playhouse	06009	659.0	0				
Buildings.2159	POINT (-120.46853301399995 38.13825345900005)	Black Sheep Vinters	06009	658.0	0				
Buildings.2160	POINT (-120.4565824499992 38.14519784700008)	Bret Harte Center	06009	683.0	0				
Buildings.2161	POINT (-120.46519957999993 38.137420139000085)	Mitchler Hotel	06009	660.0	0				
Buildings.2162	POINT (-120.46408843499998 38.13797578800006)	Murphys Branch Calaveras County Library	06009	662.0	0				
Buildings.2163	POINT (-120.45964370199994 38.13769796400004)	Native Daughters Hall	06009	663.0	0				
Buildings.2164	POINT (-120.46631072499991 38.13797563500009)	Old Timers Museum	06009	663.0	0				
Buildings.2165	POINT (-120.4674218659999 38.13797563500009)	Traver Building	06009	662.0	0				
Buildings.2166	POINT (-120.51486793399989 38.07131024000045)	Angels Camp Branch Calaveras County Library	06009	437.0	0				
Buildings.2167	POINT (-120.54936845999993 38.07658867100008)	Angels Camp City Hall	06009	472.0	0				
Buildings.2168	POINT (-120.5474239499992 38.07603302200005)	Angels Camp Museum	06009	467.0	0				
Buildings.2169	POINT (-120.68132055299992 38.19602977700035)	Calaveras County Courthouse	06009	307.0	0				
Buildings.2170	POINT (-120.66604204299995 38.191298550007)	Calaveras County Government Center	06009	336.0	0				
Buildings.2171	POINT (-120.6804872329999 38.196830980005)	Calaveras County Historical Museum	06009	302.0	0				
Buildings.2172	POINT (-120.66604204299995 38.191298550007)	Calaveras County Law Library	06009	336.0	0				
Buildings.2173	POINT (-120.6804872329999 38.197140922000074)	Calaveras County Library	06009	297.0	0				
Buildings.2174	POINT (-120.68076505699992 38.1971418747000086)	Metropolitan Cultural Center	06009	296.0	0				
Buildings.2175	POINT (-120.55381319299994 38.079084790006)	Prince Garibaldi Building	06009	472.0	0				
Buildings.2176	POINT (-120.68132055299992 38.19575195300007)	San Andreas Town Hall	06009	309.0	0				
Buildings.2177	POINT (-119.75014407399993 38.81078298300008)	Aspen Hall	06019	102.0	0				
Buildings.2178	POINT (-119.751810714099992 38.81078298300008)	Baker Hall	06019	102.0	0				

Figure 6-93: MVT raw layer Buildings.shp data table

We will render the features with the ELEV\_METER field value by query and highlighting way in Leaflet. This field represents the elevation of the building's location in meters, and the code is as follows:

```

1  <!DOCTYPE html>
2  <html lang="ja">
3  <head>
4      <meta charset="UTF-8">
5      <meta name="viewport" content="width=device-width, initial-scale=1.0">
6      <meta http-equiv="X-UA-Compatible" content="ie=edge">
7      <link rel="stylesheet"
8          href="//cdnjs.cloudflare.com/ajax/libs/leaflet/0.7.7/leaflet.css"/>
9      <style>
10         .map {
11             width: 100%;
12             height: 1100px;
13         }
14         .info {
15             padding: 6px 8px;
16             font: 14px/16px Arial, Helvetica, sans-serif;
17             background: white;
18             background: rgba(255,255,255,0.8);
19             box-shadow: 0 0 15px rgba(0,0,0,0.2);
20             border-radius: 5px;
21         }
22         .info h4 {
23             margin: 0 0 5px;
24             color: #777;
25         }
26     </style>
27     <script src="//cdnjs.cloudflare.com/ajax/libs/leaflet/0.7.7/leaflet-
src.js"></script>
28     <script src=".//js/Leaflet.MapboxVectorTile.min.js"></script>
29     <title>Leaflet MVT Tiles Example</title>
30 </head>
31 <body>
32     <div class="map" id="map"></div>
33     <script>
34         const map = L.map("map", {
35             maxZoom: 17
36         }).setView([37.627254,-122.365161], 11);
37         // Loading ArcGIS online basemap
38         const base =
39             L.tileLayer("https://server.arcgisonline.com/ArcGIS/rest/services/world_Topo
40             _Map/MapServer/tile/{z}/{y}/{x}").addTo(map);
41         // Load MVT layers and construct feature data query criteria for
42         // grouping rendering
43         const buildings = new L.TileLayer.MVTSource({
44             url: ".//data/tiles/mvt3857/Buildings/{z}/{x}/{y}.mvt",
45             maxzoom: 18,
46             //maxNativeZoom: 15,
47             mutexToggle: false,
48             onClick: hoveronFeature,
49             style: function(feature){
50                 let color = ((feature.properties.ELEV_METER >= 100) &&
51                 (feature.properties.ELEV_METER <= 300)) ? "#FFFF00" :
52                     ((feature.properties.ELEV_METER > 300) &&
53                     (feature.properties.ELEV_METER <= 500)) ? "#FFD700" :

```

```

48             ((feature.properties.ELEV_METER > 500) &&
49             (feature.properties.ELEV_METER <= 700)) ? "#6495ED" :
50                 ((feature.properties.ELEV_METER > 700) &&
51                 (feature.properties.ELEV_METER <= 900)) ? "#FF00FF" :
52                     ((feature.properties.ELEV_METER > 900) &&
53                     (feature.properties.ELEV_METER <= 1100)) ? "#C71585" :
54                         ((feature.properties.ELEV_METER > 1100) &&
55                         (feature.properties.ELEV_METER <= 1300)) ? "#8A2BE2" :
56                             ((feature.properties.ELEV_METER > 1300) &&
57                             (feature.properties.ELEV_METER <= 1500)) ? "#7A67EE" :
58                                 ((feature.properties.ELEV_METER > 1500) &&
59                                 (feature.properties.ELEV_METER <= 1700)) ? "#0000FF" :
60                                     ((feature.properties.ELEV_METER > 1700) &&
61                                     (feature.properties.ELEV_METER <= 2000)) ? "#00EE76" :
62                                         "#0000FF";
63             return {color: color, radius: 5, selected: {color: "red", radius:
64               10}};
65         }
66     });
67     buildings.addTo(map);
68     // Building information display components
69     const info = L.control();
70     info.onAdd = function (map) {
71       this._div = L.DomUtil.create('div', 'info'); // create a div with
72       a class "info"
73       this.update();
74       return this._div;
75     };
76     // Display selected feature attributes
77     info.update = function (props) {
78       this._div.innerHTML = '<h4>Building Info</h4>' + (props ?
79           '<b>' + props.NAME + '</b>' :
80           'Click circles');
81     };
82     info.addTo(map);
83     function hoveronFeature(e) {
84       if(!e.feature) return;
85       info.update(e.feature.properties);
86     }
87   
```

The rendering effect of grouping the values of the ELEV\_METER field is shown as Figure 6-94.




Figure 6-94: Value range grouping rendering and query highlighting for MVT tiles

Select the features, highlight it, the effect is shown as Figure 6-95.




Figure 6-95: highlighting the features selected

Select the feature, display the information, as shown in Figure 6-96.




Figure 6-96: Display the information of the feature selected

All the above queries are based on the feature data in the vector tiles. In a sense, vector tile is equivalent to achieving desktop version vector layer visualization on the web, as well as data thematic statistics and rendering based on this.

The above process implements the complete process of MVT vector tile and its application on the web side. From the map, we can see that even when zoomed in to the maximum level (depending on the tile level), the map remains undistorted because the tile data is vector.

So how to determine the application plan of MVT in actual projects? First of all, imagine a scenario where users need to place a map of a certain country on the internet and require it to be accurate to village level administrative areas, roads, and buildings. You have many options to choose from, of course, the best one is definitely vector tile. Firstly, we exclude WMS and WFS, which are relatively inefficient. Which should be choosed between WMTS and vector tile? Although both are tile, the basic data of WMTS is images and does not support operations on layer's feature. Therefore, the vector tile is the optimal and almost the only choice in the large-scale map applications involving map feature data, and the MVT in Mapbox specification is almost the first choice.

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The tutorial shp files to build tiles can be [download](#) also in PyramidMap. You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

## 6.8.7 Build Vector MBTile tile

MBTiles (Mapbox tiles), as the name suggests, this is an open source tile standard created by Mapbox, with the goal of promoting standardization and efficiency of the tiling. MBTiles supports both vector and raster tiles as well as interactive grid tiles, MBTiles using Web Mercator projection to describe tile coordinate data through metadata, including boundaries, longitude and latitude coordinates, etc. MBTiles internally grades tiles, essentially a map tile dataset based on SQLite, which improves the efficiency of tile retrieval through database indexing, much higher than folder mode tiles. You can build yourself vector MbTiles in PyramidMap, as shown in Figures 6-97.

The screenshot shows the PyramidMap software interface. At the top, there is a menu bar with options: File, MapData, Geodatabase, GeoServer, System, Help. Below the menu is a toolbar with various icons for different functions like Main View, Styles Console, Shp Factory, Shp Conversion, Map Pool, GeoDB Console, GeoDB data, GeoServer Pool, GeoServer Space, Map Publish, GeoServer Layers, and GeoServer View. The main area displays a table of vector layers:

No.	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCS(SRID)	Counts	State	Check
1	Buildings.shp	D:\maps\California3857\Buildings.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG 3857	436	Normal	<input checked="" type="checkbox"/>
2	Cemeteries.shp	D:\maps\California3857\Cemeteries.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG 3857	842	Normal	<input checked="" type="checkbox"/>
3	Churches.shp	D:\maps\California3857\Churches.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG 3857	183613	Normal	<input type="checkbox"/>
4	Counties.shp	D:\maps\California3857\Counties.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	58	Normal	<input checked="" type="checkbox"/>
5	GolfCourses.shp	D:\maps\California3857\GolfCourses.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG 3857	537	Normal	<input checked="" type="checkbox"/>
6	Hospitals.shp	D:\maps\California3857\Hospitals.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG 3857	438	Normal	<input checked="" type="checkbox"/>
7	Lakes.shp	D:\maps\California3857\Lakes.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	2	Normal	<input checked="" type="checkbox"/>
8	LandmarkAreas.shp	D:\maps\California3857\LandmarkAreas.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	10467	Normal	<input type="checkbox"/>
9	MajorRoads.shp	D:\maps\California3857\MajorRoads.shp	From local directory	MultilineString	MultilineString	WGS 84 / Pseudo-Mercator EPSG 3857	72033	Normal	<input type="checkbox"/>
10	Rivers.shp	D:\maps\California3857\Rivers.shp	From local directory	MultilineString	MultilineString	WGS 84 / Pseudo-Mercator EPSG 3857	4	Normal	<input checked="" type="checkbox"/>
11	Schools.shp	D:\maps\California3857\Schools.shp	From local directory	Point	Point	WGS 84 / Pseudo-Mercator EPSG 3857	11381	Normal	<input type="checkbox"/>
12	States.shp	D:\maps\California3857\States.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	11	Normal	<input checked="" type="checkbox"/>
13	UrbanAreas.shp	D:\maps\California3857\UrbanAreas.shp	From local directory	Multipolygon	Multipolygon	WGS 84 / Pseudo-Mercator EPSG 3857	101	Normal	<input checked="" type="checkbox"/>
14	Buildings.shp	D:\maps\California\Buildings.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG 4326	4361	Normal	<input type="checkbox"/>
15	Cemeteries.shp	D:\maps\California\Cemeteries.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG 4326	842	Normal	<input type="checkbox"/>
16	Churches.shp	D:\maps\California\Churches.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG 4326	183613	Normal	<input type="checkbox"/>
17	Counties.shp	D:\maps\California\Counties.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG 4326	58	Normal	<input type="checkbox"/>
18	GolfCourses.shp	D:\maps\California\GolfCourses.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG 4326	537	Normal	<input type="checkbox"/>
19	Hospitals.shp	D:\maps\California\Hospitals.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG 4326	438	Normal	<input type="checkbox"/>
20	Lakes.shp	D:\maps\California\Lakes.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG 4326	2	Normal	<input type="checkbox"/>
21	LandmarkAreas.shp	D:\maps\California\LandmarkAreas.shp	From local directory	MultilineString	MultilineString	GCS_WGS_1984 EPSG 4326	10467	Normal	<input type="checkbox"/>
22	MajorRoads.shp	D:\maps\California\MajorRoads.shp	From local directory	MultilineString	MultilineString	GCS_WGS_1984 EPSG 4326	72033	Normal	<input type="checkbox"/>
23	Rivers.shp	D:\maps\California\Rivers.shp	From local directory	MultilineString	MultilineString	GCS_WGS_1984 EPSG 4326	4	Normal	<input type="checkbox"/>
24	Schools.shp	D:\maps\California\Schools.shp	From local directory	Point	Point	GCS_WGS_1984 EPSG 4326	11381	Normal	<input type="checkbox"/>
25	States.shp	D:\maps\California\States.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG 4326	1	Normal	<input type="checkbox"/>
26	UrbanAreas.shp	D:\maps\California\UrbanAreas.shp	From local directory	Multipolygon	Multipolygon	GCS_WGS_1984 EPSG 4326	191	Normal	<input type="checkbox"/>

At the bottom of the interface, there is a toolbar with buttons for Import vector layers, Map preview and editing, Layer statistics, CRS Conversion, Spatial processing, Layer tile, Export out Kml, Export out Csv, Export out GeoJson, Delete, and a checkbox labeled Check all. The Layer tile button is currently selected, and a dropdown menu is open, showing options: Build TMS tile, Build XYZ tile, Build MVT tile, and Build MBTiles tile.

Figure 6-97: Build vector MbTiles in PyramidMap

Select the MBTiles tiles option and then open the tile scheme interface, as shown in Figure 6-98.




Figure 6-98: Vector MbTiles tile scheme

In the tiling scheme, select the target CRS(coordinate system) for the target tile dataset. The default option is to keep the original CRS of each layer indicated by the checkbox. If you want to transform to another CRS for the target tiles, you should uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your chosen. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

The rendering scheme defines the rendering mode of the layer and supports rendering configurations for all collection types such as Point/MultiPoint, Linestring/MultiLinestring, Polygon/MultiPolygon, including point type symbols, size, stroke width, stroke and fill colors, and the opacity.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

The MbTiles scheme supports both TMS and XYZ standards, you can choose as needing.

Select the tile level and target save path, the tile scale can be supported up to 24 zoomlevel.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The tiling process is shown in Figures 6-99.




Figure 6-99: Vector MbTiles tile process

The tiling process has a progress bar and the tiled status displayed for each layer and the tiling completion prompt is shown in Figure 6-100.




Figure 6-100: Vector MbTiles tiling completed

The generated target tile files is shown as Figure 6-101.

 Buildings.mbtiles	2023/9/8 15:28	MBTILES	3,452 KB
 Cemetrics.mbtiles	2023/9/8 15:28	MBTILES	3,027 KB
 Counties.mbtiles	2023/9/8 15:29	MBTILES	4,994 KB
 GolfCourses.mbtiles	2023/9/8 15:29	MBTILES	2,860 KB
 Hospitals.mbtiles	2023/9/8 15:29	MBTILES	2,852 KB
 Lakes.mbtiles	2023/9/8 15:29	MBTILES	897 KB
 Rivers.mbtiles	2023/9/8 15:29	MBTILES	1,079 KB
 States.mbtiles	2023/9/8 15:31	MBTILES	4,485 KB

Figure 6-101: Vector MbTiles files

The tile file corresponds to the original layer name, and each vector layer corresponds to its MBtiles file. MBtiles can be freely deployed to web servers, such as Tomcat, without needing professional map servers such as GeoServer, therefore greatly reducing the difficulty of map deployment and maintenance as well as project costs. You can deploy independently, access data through HTTP URLs, or integrate deployment with projects, and access data through relative paths. Taking Leaflet as an example to implement web side MBtiles loading, the complete code is as follows:

```

1  <!DOCTYPE html>
2  <html lang="en">
3  <head>
4      <meta charset="UTF-8">
5      <meta name="viewport" content="width=device-width, initial-scale=1.0">
6      <title>Leaflet vector MBTiles Example</title>
7      <link rel="stylesheet"
8          href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9  </head>
10 <style type="text/css">
11     body {
12         margin: 0;
13         padding: 0;
14     }
15     html, body, #map{
16         width: 100%;
17         height: 100%;
18     }
19 </style>
20 <body>
21 <div id="map" ></div>
22 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
23 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
24 <script src="https://unpkg.com/sql.js@0.3.2/js/sql.js"></script>
25 <script src="https://unpkg.com/Leaflet.TileLayer.MBTiles@1.0.0/Leaflet.TileLayer.MBTiles.js"></script>
26 <script>
27     var map = L.map('map').fitWorld();
28     // Loading ArcGIS online basemap
29
30     L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/world_Topo
31 _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);

```

```

29 // Load local MBTiles, please modify according to your file path.
30 // Create Counties mbtiles layer
31 var mb_Counties =
  L.tileLayer.mbtiles('./data/tiles/mbtiles3857xyz/Counties.mbtiles');
32 // Create Hospitals mbtiles layer
33 var mb_Hospitals =
  L.tileLayer.mbtiles('./data/tiles/mbtiles3857xyz/Hospitals.mbtiles');
34 // Add Counties mbtiles layer to map
35 mb_Counties.addTo(map);
36 // Add Hospitals mbtiles layer to map
37 mb_Hospitals.addTo(map);
38 </script>
39 </body>
40 </html>

```

The Counties mbtiles and Hospitals mbtiles were added to the map in the Leaflet engine as shown in Figures 6-102.




Figure 6-102: loading MbTiles in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The tutorial shp files to build tiles can be [download](#) also in PyramidMap. You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

## 6.8.8 Build Raster TMS tile

PyramidMap supports TMS, XYZ, and MbTiles standard tile of raster layers, as shown in Figure 6-103.




Figure 6-103: PyramidMap raster layer TMS tile

The TMS tile standard has been identified in the section [6.8.4 Vector TMS tile].

Select the TMS tile and then open the scheme interface, as shown in Figure 6-104.




Figure 6-104: Raster TMS tile scheme

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

Please choose the rendering mode based on the band of the raster layer. For single band layers, please choose to render according to grayscale, and for multi band layers, please choose to render according to RGB raster.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

Select the tile level and target save path, the tile scale can be supported up to 24 zoomlevel.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The execution process is shown in Figures 6-105.




Figure 6-105: Raster TMS tiling process

The progress bar indicate the tiling process and status of each selected layer. The tiling completion prompt is shown in Figure 6-106.




Figure 6-106: Raster TMS tiling completed

The final generated tiles will be classified according to the original layer name, grouped according to the Z value (zoom level) and X value, named according to the Y value, and saved to the corresponding hierarchical directory. At the same level, the tiles will be grouped based on the X value. The tiles with the same X value will be saved to the same path which named with the X value, and the tiles will be named with the Y value. The directory structure is shown as Figure 6-107.




Figure 6-107: TMS tiles Folder

View the slicing file at a certain level, as shown in Figure 6-108.



Figure 6-108: Raster TMS tile files

When storing tiles, the code uses a folder structure that follows the TMS (Tile Map Service) standard, namely Z/X/Y.png, where Z represents the zoom level and X and Y represent the coordinates of the tiles. During this process, the code also checks and creates necessary folders. After completing the tiling, deploy the tiles to a web server, such as Apache Tomcat, nothing with the professional mapserver such as GeoServer, that will greatly reduce the difficulty and cost of map deployment and maintenance. You can deploy independently, access tiles data through HTTP URLs, or integrate deployment with projects, and access tiles data through relative paths. As

an example, we demonstrate the web gis application through Leaflet, the complete code is as follows:

```
1  <!DOCTYPE html>
2  <html lang="en">
3  <head>
4      <meta charset="UTF-8">
5      <meta name="viewport" content="width=device-width, initial-scale=1.0">
6      <title>Leaflet raster TMS tiles Example</title>
7      <link rel="stylesheet"
8          href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9  </head>
10 <style type="text/css">
11     body {
12         margin: 0;
13         padding: 0;
14     }
15     html, body, #map{
16         width: 100%;
17         height: 100%;
18     }
19 </style>
20 <body>
21 <div id="map" ></div>
22 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
23 <script>
24     // Initialize map and set the center and zoom levels
25     var map = L.map('map').setView([42.562710059362658,10.29751401540051],
26 );
27     // Loading ArcGIS online basemap
28
29     L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/world_Topo
30 _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
31     // Load local TMS tiles, please modify according to your file path.
32     L.tileLayer('.data/tiles/tms3857/{z}/{x}/{y}.png', {
33         tms: true, // Indicates this is an TMS tile
34         opacity: 0.7 // The transparency of the tile can be adjusted as
needed
35     }).addTo(map);
36 </script>
37 </body>
38 </html>
```

The loading effect on the map is shown in Figures 6-109.



Figure 6-109: Loading raster TMS tiles in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The tutorial raster files to build tiles can be [download](#) also in PyramidMap. You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

## 6.8.9 Build Raster XYZ Tile

PyramidMap supports TMS, XYZ, and MbTiles standard tile of raster layers, as shown in Figure 6-110.




Figure 6-110: PyramidMap raster layer XYZ tile

The XYZ tile standard has been indentified in the section [6.8.5 Vector XYZ tile].

Select the XYZ tile and then open the scheme interface, as shown in Figure 6-111.




Figure 6-111: Raster TMS tile scheme

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated.

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

Please choose the rendering mode based on the band of the raster layer. For single band layers, please choose to render according to grayscale, and for multi band layers, please choose to render according to RGB raster.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

Select the tile level and target save path, the tile scale can be supported up to 24 zoomlevel.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The execution process is shown in Figures 6-112.




Figure 6-112: Raster TMS tiling process

The progress bar indicate the tiling process and status of each selected layer. The tiling completion prompt is shown in Figure 6-113.




Figure 6-113: Raster XYZ tiling completed

The final generated tiles will be classified according to the original layer name, grouped according to the Z value (zoom level) and X value, named according to the Y value, and saved to the corresponding hierarchical directory. At the same level, the tiles will be grouped based on the X value. The tiles with the same X value will be saved to the same path which is named with the X value, and the tiles will be named with the Y value. The directory structure is shown as Figure 6-114.




Figure 6-114: XYZ TILE Folder

View the slicing file at a certain level, as shown in Figure 6-115.




Figure 6-108: Raster XYZ tile files

When storing tiles, the code uses a folder structure that follows the TMS (Tile Map Service) standard, namely Z/X/Y.png, where Z represents the zoom level and X and Y represent the coordinates of the tiles. During this process, the code also checks and creates necessary folders. After completing the tiling, deploy the tiles to a web server, such as Apache Tomcat, nothing with the professional mapserver such as GeoServer, that will greatly reduce the difficulty and cost of map deployment and maintenance. You can deploy independently, access tiles data through HTTP URLs, or integrate deployment with projects, and access tiles data through relative paths. As an example, we demonstrate the web gis application through Leaflet, the complete code is as follows:

```

1 <!DOCTYPE html>
2 <html lang="en">
3 <head>
4   <meta charset="UTF-8">
5   <meta name="viewport" content="width=device-width, initial-scale=1.0">
6   <title>Leaflet raster XYZ tiles Example</title>
```

```

7   <link rel="stylesheet"
8     href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9   </head>
10  <style type="text/css">
11    body {
12      margin: 0;
13      padding: 0;
14    }
15    html, body, #map{
16      width: 100%;
17      height: 100%;
18    }
19  </style>
20  <body>
21  <div id="map" ></div>
22  <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
23  <script>
24    // Initialize map and set the center and zoom levels
25    var map = L.map('map').setView([51.362710059362658,7.99751401540051],
26    7);
27    // Loading ArcGIS online basemap
28
29    L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/World_Topo
30 _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
31    // Load local XYZ tiles, please modify according to your file path.
32    L.tileLayer('.data/tiles/xyz3857/{z}/{x}/{y}.png', {
33      tms: false, // Indicates this is an XYZ tile
34      opacity: 0.7 // The transparency of the tile can be adjusted as
needed
35    }).addTo(map);
36  </script>
37  </body>
38  </html>

```

The loading effect on the map is shown in Figures 6-116.




Figure 6-116: Loading raster TMS tiles in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The tutorial raster files to build tiles can be [download](#) also in PyramidMap. You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

## 6.8.10 Build Raster MBTiles

MBTiles (Mapbox tiles), as the name suggests, this is an open source tile standard created by Mapbox, with the goal of promoting standardization and efficiency of the tiling. MBTiles supports both vector and raster tiles as well as interactive grid tiles, MBTiles using Web Mercator projection to describe tile coordinate data through metadata, including boundaries, longitude and latitude coordinates, etc. MBTiles internally grades tiles, essentially a map tile dataset based on SQLite, which improves the efficiency of tile retrieval through database indexing, much higher than folder mode tiles. You can build yourself raster MbTiles in PyramidMap, as shown in Figures 6-117.




Figure 6-97: Build raster MbTiles in PyramidMap

Select the MBTiles tile and then open the tile scheme interface, as shown in Figure 6-118.




Figure 6-118: Raster MBTile tile scheme

In the tiling scheme, select the target coordinate system, which is the coordinate system of the target tile dataset. The default option is to keep the original coordinate system of each layer. If need to change it, you can uncheck it and select the desired target coordinate system. The tile operation will automatically convert the coordinate system based on your selection. PyramidMap provides the vast majority of standard coordinate system and is still being continuously updated. It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the Web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system is chosen for tile operations.

Please choose the rendering mode based on the band of the raster layer. For single band layers, please choose to render according to grayscale, and for multi band layers, please choose to render according to RGB raster.

The scheme defines the tile size and the maximum scaling level. The tile size is measured in pixels, representing the size of each target tile.

The MbTiles scheme supports both TMS and XYZ standards, you can choose as needing.

Select the tile level and target save path, the tile scale can be supported up to 24 zoomlevel.

It should be noted that tile process is a work that consumes system resources and requires high system performance. The tiling speed depends on system performance. Therefore, it is strongly recommended to run the tile process on the workstation level computers.

The execution process is shown in Figures 6-119.




Figure 6-119: Raster MBtiles tiling process

The progress bar indicate the tiling process and status of each selected layer. The tiling completion prompt is shown in Figure 6-120.




Figure 6-120: Raster MBtiles tiling completed

The generated target MBTtiles files is shown as Figure 6-121.

	320205.mbtiles	2023/9/8 12:33	MBTILES	5,506 KB
	hengxuhe.mbtiles	2023/8/25 20:09	MBTILES	897 KB
	Sentinel-2_L2A_False_color.mbtiles	2023/9/8 12:33	MBTILES	27,888 KB
	Sentinel-2_L2A_NDSI.mbtiles	2023/9/8 12:33	MBTILES	26,081 KB
	Sentinel-2_L2A_SWIR.mbtiles	2023/9/8 12:34	MBTILES	30,217 KB

Figure 6-121: The target raster MbTiles files

The tile file corresponds to the original layer name, and each raster layer corresponds to its MBtiles file. MBtiles can be freely deployed to web servers, such as Tomcat, without needing professional map servers such as GeoServer, therefore greatly reducing the difficulty of map deployment and maintenance as well as project costs. You can deploy independently, access data through HTTP URLs, or integrate deployment with projects, and access data through relative paths. Taking Leaflet as an example to implement web side MBtiles loading, the complete code is as follows:

```

1  <!DOCTYPE html>
2  <html lang="en">
3  <head>
4      <meta charset="UTF-8">
5      <meta name="viewport" content="width=device-width, initial-scale=1.0">
6      <title>Leaflet raster XYZ tiles Example</title>
7      <link rel="stylesheet"
8          href="https://unpkg.com/leaflet@1.7.1/dist/leaflet.css" />
9  </head>
10 <style type="text/css">
11     body {
12         margin: 0;
13         padding: 0;
14     }
15     html, body, #map{
16         width: 100%;
17         height: 100%;
18     }
19 </style>
20 <body>
21 <div id="map" ></div>
22 <script src="https://unpkg.com/leaflet@1.7.1/dist/leaflet.js"></script>
23 <script>
24     // Initialize map and set the center and zoom levels
25     var map = L.map('map').setView([50.492710059362658,4.09751401540051],
26     9);
27     // Loading ArcGIS online basemap
28     L.tileLayer('https://server.arcgisonline.com/ArcGIS/rest/services/World_Topo
29     _Map/MapServer/tile/{z}/{y}/{x}').addTo(map);
30     // Load local MBTiles, please modify according to your file path.
31     L.tileLayer('.data/tiles/mbtiles3857/Sentinel-
32     2_L2A_NDSI.mbtiles').addTo(map);
33 </script>
34 </body>
35 </html>
```

The loading effect on the map is shown in Figures 6-122.




Figure 6-122: Loading raster MBTiles in Leaflet

It should be noted that although PyramidMap supports tiling operations in all standard coordinate systems, most WebGIS platforms currently use the web Mercator 3857 coordinate system. Therefore, in general, the Web Mercator 3857 coordinate system should be chosen for tile.

The example code and the tile data of this web app are provided in PyramidMap [download](#). The tutorial raster files to build tiles can be [download](#) also in PyramidMap. You can download it themselves. The web app has a complete running environment and is deployed to Tomcat or other web servers for plug and play. At the same time, you can use the experimental data in PyramidMap and follow the operating instructions to perform tile validation by yourself. PyramidMap looks forward to your valuable feedback.

## 7 Map rendering and sld symbol

Before starting this chapter, we must understand that geospatial data does not have inherent visual components and must be styled in order to view the data. Style specifies the color, thickness, and other visible attributes used to present data on the map. For example, in ArcGIS, the display styles of point, line, and area map features are defined in mxd map documents. For the same layer, different rendering styles can be defined in different map documents to present different display effects. In GeoServer, styling is done using a markup language called Styled Layer Descriptor (SLD). SLD is an XML based markup language that is very powerful, and although it is somewhat complex, we can visually define it through the PyramidMap tool. This chapter focuses on the functions of SLD, its definition method in PyramidMap, management modes, and how it works in GeoServer.

SLD defines the symbolic features of map elements, which include: ① geometric types of points, lines, and surfaces; ② Edge width, color, and transparency; ③ Fill color and transparency; ④ Image size and icon; ⑤ Annotation fields, fonts, font colors, sizes, normal or bold, annotation positions, and fine tuning offsets describe the display of map features. On this basis, more

advanced styles can be used. Especially for Point types, with well-known shapes such as circles, squares, stars, and even custom graphics or text can be used to specify points. You can use the dash style and hash value to set the line style. You can use custom tile shapes to fill polygons. Styles can be based on attributes in the data to style certain features in different ways. You can also annotate features with text. Styles can also be determined by the zoom level to fit their apparent size. In short, the possibility of using SLD to describe the display mode of spatial geometric shapes is enormous.

Clearly, defining and modifying SLD files is a complex process. PyramidMap provides a visualization approach that enables the creation, editing, and maintenance of SLD, and maintains bidirectional synchronization with the GeoServer server. It uploads data to the designated service space of GeoServer, forming a complete SLD production, management, and service process.

## 7.1 Define sld symbols at client

### 7.1.1 Create sld on visualizing layer nodes

At the visualization layer node on the left of the main map interface, create the sld symbol through the right-click shortcut menu, as shown in Figure 7-1.




Figure 7-1: Creating sld symbols on visualization layer node

PyramidMap will implement the sld symbol definition method through the visual palette according to the geometric type (point, line, polygon) of the selected layer, as shown in Figure 7-2.




Figure 7-2: Create sld symbol definition on layer node through palette

In the sld definition module, create map symbols for different geometric types of points, lines, and surfaces through the color palette. The symbol features include: stroke color, stroke width, fill color, transparency, size, icon, annotation field, font, font color, size, normal or bold, annotation position, fine adjustment offset, etc. The display effect can be previewed in real time on the layer, saved as an sld file, and maintained in the sld resource pool at the same time. As shown in Figure 7-3.




Figure 7-3: Create and save sld symbol definition on layer node through palette

The following is a simple SLD example we created that can be applied to layers containing points.

```

1 <?xml version="1.0" encoding="ISO-8859-1"?>
2 <StyledLayerDescriptor version="1.0.0"
3   xsi:schemaLocation="http://www.opengis.net/sld
4     StyledLayerDescriptor.xsd"
5   xmlns="http://www.opengis.net/sld"
6   xmlns:ogc="http://www.opengis.net/ogc"
```

```

6   6      xmlns:xlink="http://www.w3.org/1999/xlink"
7   7      xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
8   8      <NamedLayer>
9   9          <Name>simple point</Name>
10 10          <UserStyle>
11 11              <Title>Simple point sld</Title>
12 12              <FeatureTypeStyle>
13 13                  <Rule>
14 14                      <PointSymbolizer>
15 15                          <Graphic>
16 16                              <Mark>
17 17                                  <wellKnownName>circle</wellKnownName>
18 18                                  <Fill>
19 19                                      <CssParameter name="fill">#FF0000</CssParameter>
20 20                                  </Fill>
21 21                              </Mark>
22 22                      <size>10</size>
23 23                  </Graphic>
24 24          </PointSymbolizer>
25 25      </Rule>
26 26      </FeatureTypeStyle>
27 27      </UserStyle>
28 28  </NamedLayer>
29 29 </StyledLayerDescriptor>

```

Although the example looks long, only a few lines are really important to understand. **Line 14** states that a “PointSymbolizer” is to be used to style data as points. **Lines 15-17** state that points are to be styled using a graphic shape specified by a “well known name”, in this case a circle. SLD provides names for many shapes such as “square”, “star”, “triangle”, etc. **Lines 18-20** specify the shape should be filled with a color of `#FF0000` (red). This is an RGB color code, written in hexadecimal, in the form of `#RRGGBB`. Finally, **line 22** specifies that the size of the shape is 10 pixels in width. The rest of the structure contains metadata about the style, such as a name identifying the style and a title for use in legends.

## 7.1.2 Create map symbols in the sld resource pool

PyramidMap performs centralized and unified management of client SLDs in the way of resource management pool. Enter through the "Styles console" entry of the main interface menu to open the SLD resource management pool module, as shown in Figure 7-4.




Figure 7-4: Sld symbol resource pool and creation module

PyramidMap maintains a local SLD resource pool itself, and uniformly and centrally manages the SLD files created by the client and obtained from the GeoServer. There are two ways to obtain the SLD data source, one is from the GeoServer, the other is created at the PyramidMap client. All work flows are completed in the SLD unified resource management pool module, as shown in Figure 7-5.




Figure 7-5: Complete the sld symbol creation and management workflow in the sld unified resource management pool

The defined sld file is included in the resource management list to realize resource sharing. You can select symbols in the sld resource pool to preview the effect, as shown in Figure 7-6.

No	StdFileName	StdFilePath	Geometry...	Symbol	Size(pixel)	StrokeWidth(pixel)	StrokeColor	StrokeOpacity	FillColor	FillOpacity	LabelField	Check
25	IB101.sld	D:\SLD\IB101.sld	<input checked="" type="radio"/>	Cross	30.0	5.0	#000000	0.3799999952316284	#000000	0.3799999952316284		<input checked="" type="checkbox"/>
26	IB1701.sld	D:\SLD\IB1701.sld	<input checked="" type="radio"/>	Circle	5.0	1.0	#000000	1.0	#000000	1.0		<input type="checkbox"/>
27	IB21.sld	D:\SLD\IB21.sld	<input checked="" type="radio"/>	X	35.0	5.0	#000000	0.3100000023841858	#000000	0.3100000023841858		<input type="checkbox"/>
28	IB50.sld	D:\SLD\IB50.sld	<input checked="" type="radio"/>	Square	35.0	5.0	#000000	0.3100000023841858	#000000	0.3100000023841858		<input type="checkbox"/>
29	IB901.sld	D:\SLD\IB901.sld	<input checked="" type="radio"/>	Star	30.0	4.0	#000000	1.0	#000000	1.0		<input type="checkbox"/>
30	line.sld	D:\SLD\line.sld	<input checked="" type="radio"/>	~	1.0	1.0	#000000	1.0	#000000	1.0		<input type="checkbox"/>
31	otn_citypoint.sld	D:\SLD\otn_citypoint.sld	<input checked="" type="radio"/>	circle	16	1.0	#000000	1.0	#000000	1.0	NAME	<input type="checkbox"/>
32	otn_countypoint.sld	D:\SLD\otn_countypoint.sld	<input checked="" type="radio"/>	circle	14	1.0	#000000	1.0	#000000	1.0	NAME	<input type="checkbox"/>
33	otn_provincepoint.sld	D:\SLD\otn_provincepoint.sld	<input checked="" type="radio"/>	circle	18	1.0	#000000	1.0	#000000	1.0	NAME	<input type="checkbox"/>
34	poi.sld	D:\SLD\poi.sld	<input checked="" type="radio"/>	circle	7	1.0	#000000	1.0	#FFFF00	1.0	NAME	<input type="checkbox"/>
35	point.sld	D:\SLD\point.sld	<input checked="" type="radio"/>	square	6	1.0	#000000	1.0	#000000	1.0		<input type="checkbox"/>
36	point_circle_1101.sld	D:\SLD\point_circle_1101.sld	<input checked="" type="radio"/>	Circle	20.0	1.0	#000000	1.0	#000000	1.0		<input type="checkbox"/>
37	pointbuild.sld	D:\SLD\pointbuild.sld	<input checked="" type="radio"/>	Circle	16.0	1.0	#000000	1.0	#000000	1.0	NAME	<input checked="" type="checkbox"/>
38	poly_landmarks.sld	D:\SLD\poly_landmarks.sld	<input checked="" type="radio"/>	~	5.0	1.0	#000000	1.0	#000000	1.0	NAME	<input type="checkbox"/>
39	polygon.sld	D:\SLD\polygon.sld	<input checked="" type="radio"/>	~	1	1.0	#000000	1.0	#000000	1.0		<input type="checkbox"/>
40	pophatch.sld	D:\SLD\pophatch.sld	<input checked="" type="radio"/>	~	5.0	1.0	#000000	1.0	#000000	1.0	STATE_ABBR	<input type="checkbox"/>

New sld style: point Style effect preview Import local sld style Sync to Server editor Delete  Check all

Figure 7-6: Select the map symbol in the sld resource pool for effect preview

PyramidMap will match in the layer resource pool according to the geometry type of the selected sld symbol, and return the list of layers of the same type, as shown in Figure 7-7.

No	LayerFileName	LayerFilePath	DataSources	GeomGraphic	GeomType	UCS(SRID)	Counts	State	Check
1	Buildings.shp	E:\Maps\California\Buildings.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	4361	Normal	<input checked="" type="checkbox"/>
2	Cemeteries.shp	E:\Maps\California\Cemeteries.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	842	Normal	<input type="checkbox"/>
3	Churches.shp	E:\Maps\California\Churches.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	183613	Normal	<input type="checkbox"/>
4	GolfCourses.shp	E:\Maps\California\GolfCourses.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	537	Normal	<input type="checkbox"/>
5	Hospitals.shp	E:\Maps\California\Hospitals.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	438	Normal	<input type="checkbox"/>
6	Schools.shp	E:\Maps\California\Schools.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	11381	Normal	<input type="checkbox"/>
7	CAPITAL_POINT.shp	E:\Maps\oraclelayers\CAPITAL_POINT.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	1	missing	<input type="checkbox"/>
8	CITY_POINT.shp	E:\Maps\oraclelayers\CITY_POINT.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	308	missing	<input type="checkbox"/>
9	COUNTY_POINT.shp	E:\Maps\oraclelayers\COUNTY_POINT.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	2862	missing	<input type="checkbox"/>
10	GAS_CONDENSATE_TANK.shp	E:\Maps\oraclelayers\GAS_CONDENSATE_TANK.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	8	missing	<input type="checkbox"/>
11	GAS_CAB.shp	E:\Maps\oraclelayers\GAS_CAB.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	12290	missing	<input type="checkbox"/>
12	GAS_PRESSURE_BOX.shp	E:\Maps\oraclelayers\GAS_PRESSURE_BOX.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	30	missing	<input type="checkbox"/>
13	GAS_PRESSURE CABINET.s	E:\Maps\oraclelayers\GAS_PRESSURE CABINET.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	122	missing	<input type="checkbox"/>
14	GAS_PRESSURE_STATION.s	E:\Maps\oraclelayers\GAS_PRESSURE_STATION.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	1	missing	<input type="checkbox"/>
15	GAS_PROTECTIVE_PILE.shp	E:\Maps\oraclelayers\GAS_PROTECTIVE_PILE.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	54	missing	<input type="checkbox"/>
16	GAS_SERVICING_WELL.shp	E:\Maps\oraclelayers\GAS_SERVICING_WELL.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	2	missing	<input type="checkbox"/>
17	GAS_VALVE.shp	E:\Maps\oraclelayers\GAS_VALVE.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	1	missing	<input type="checkbox"/>
18	GAS_VALVE_WELL.shp	E:\Maps\oraclelayers\GAS_VALVE_WELL.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	892	missing	<input type="checkbox"/>
19	PROVINCE_POINT.shp	E:\Maps\oraclelayers\PROVINCE_POINT.shp	From db oracle104	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	33	missing	<input type="checkbox"/>
20	gaspipeline.shp	E:\Maps\gas\gaspipeline.shp	Self-built Shp file	<input checked="" type="radio"/>	Point	EPSG4326	0	missing	<input type="checkbox"/>
21	capital_point.shp	E:\Maps\OTNS\capital_point.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	1	Normal	<input type="checkbox"/>
22	city_point.shp	E:\Maps\OTNS\city_point.shp	From local directory	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	310	Normal	<input type="checkbox"/>
23	county_point.shp	E:\Maps\OTNS\county_point.shp	From local directory	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	2062	Normal	<input type="checkbox"/>
24	province_point.shp	E:\Maps\OTNS\province_point.shp	From local directory	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	33	Normal	<input type="checkbox"/>
25	gas_condensate_tank.shp	E:\Maps\gas\gas\gas_condensate_tank.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	8	Normal	<input type="checkbox"/>
26	gas_pipe_cap.shp	E:\Maps\gas\gas\gas_pipe_cap.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	12290	Normal	<input type="checkbox"/>
27	gas_pressure_box.shp	E:\Maps\gas\gas\gas\gas_pressure_box.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	30	Normal	<input type="checkbox"/>
28	gas_pressure_cabinet.shp	E:\Maps\gas\gas\gas\gas_pressure_cabinet.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	122	Normal	<input type="checkbox"/>
29	gas_pressure_station.shp	E:\Maps\gas\gas\gas\gas_pressure_station.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	1	Normal	<input type="checkbox"/>
30	gas_protective_pile.shp	E:\Maps\gas\gas\gas\gas_protective_pile.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	54	Normal	<input type="checkbox"/>
31	gas_servicing_well.shp	E:\Maps\gas\gas\gas\gas_servicing_well.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	2	Normal	<input type="checkbox"/>
32	gas_valve.shp	E:\Maps\gas\gas\gas\gas_valve.shp	From local directory	<input checked="" type="radio"/>	Point	GCS_WGS_1984 EPSG4326	1	Normal	<input type="checkbox"/>
33	gas_valve_well.shp	E:\Maps\gas\gas\gas\gas_valve_well.shp	From local directory	<input checked="" type="radio"/>	Point	WGS 84 EPSG4326	862	Normal	<input type="checkbox"/>

Apply Help Cancel

Figure 7-7: Returns the list of layers with the same geometry type as the selected sld

Click "Apply" to preview the effect, as shown in Figure 7-8.




Figure 7-8: Sld symbol map effect preview

### 7.1.3 Get GeoServer sld symbols

Obtain sld symbols from the GeoServer through connection pool and add to the local SLD resource pool, as shown in Figure 7-9.




Figure 7-9: Obtain sld symbols from the GeoServer through connection pool

Select the GeoServer connection, click "Get server styles", PyramidMap gets the global SLDs in GeoServer and the SLDs in each workspace, and downloads them to the client resource pool for sharing.

## 7.2 Map rendering effect with sld

At the visualization layer node on the left side of the main interface, right-click the shortcut menu to Open the sld selection list. In this module, the sld resource files of the same type will be automatically filtered from the sld symbol resource pool maintained by the system according to the geometric type (point, line, and face) of the selected layer to form a selectable list. You can select the corresponding sld symbol definition to achieve the desired map rendering effect ,all of the workflow as shown in Figure 7-10.




Figure 7-10: Select sld for visualization layer node to achieve map rendering effect

## 7.3 Client sld symbols submitted to GeoServer

PyramidMap submits the client sld symbols to the GeoServer through the connection pool, as shown in Figure 7-11.




Figure 7-11: Client sld resources submitted to the GeoServer

Select all or part of the sld files and click “Sync to Server” to synchronously submit the selected sld symbols to the global space inside the GeoServer.

# 8 Publishing map service

WebGIS is the trend of map application development and the most extensive map application mode at present, including browser end, mobile end and embedded terminal application. Vector layer, raster layer and Geodatabase layer must be published as map service url to be applied in WebGIS terminal which hosted in map server such as GeoServer that provides web map service. GeoServer is based on the OpenGIS Web server specification, follows the OGC open standard, and can run in any J2EE/servlet based container, such as tomcat, webLogic, and webSphere, etc. GeoServer has complete functions and supports multiple map service functions, such as WMS/WFS/WCS/WMTS/KML. In the traditional way, using the GeoServer console to publish map services is very complicated and requires highly professional staff.

The significance of PyramidMap is to provide a visual guidance process to publish the layers in the local resource pool to the GeoServer server, which is simpler and easier to use than the traditional web console mode of GeoServer. The human-computer interaction is more friendly and intuitive, and the operation is convenient, which greatly reduces the professional skill requirements for operators. Even companies and individuals without GIS capabilities can easily use it, which is the biggest feature of the software. PyramidMap supports three types of layer publishing: Shp file type layer, image file type layer, and geographic database type layer. The main interface provides shortcut menu entries, as shown in Figure 8-1.




Figure 8-1: Main interface map service publishing shortcut menu entry

GeoServer supports the following three data storage modes of layer services: Geodatabase layer type, Shp vector file type, and raster image file type.

## 8.1 Publish vector cache layers

---

Publish the local Shp vector layer to the shapefile directory on the GeoServer and use it as a data storage. GeoServer allows to store shp in file mode and output map services to web client. This is a complex process to package and submit client Shp files to the data cache path preset by GeoServer, and output them as rest map services for WebGIS access. PyramidMap simplifies this process through high integration, and makes it easier through visual guidance, the operation flows is shown in Figure 8-2.




Figure 8-2: Workflow of publishing Shp vector layer to shapefile directory on GeoServer

The Shp file is uploaded to the shapefile directory preset by GeoServer, stored as a file, and exported to the map rest service.

The tutorial data used in this example is provided in PyramidMap [Download tutorial vector layers](#), readers can download it themselves.

## 8.2 Publish raster cache layers

Like the Shp vector layer publishing process, GeoServer allows raster layers being stored in file directory mode and output services to web client. Select the layers to publish in the local raster files resource pool, and then select the target GeoServer and workspace to publish. As shown in Figure 8-3.




Figure 8-3: Workflow of publishing raster layer to raster file directory on GeoServer

The tutorial data used in this example is provided in PyramidMap [Download tutorial raster layers](#), readers can download it themselves.

## 8.3 Publish Geodatabase layers

The more powerful service function of GeoServer is that it can adapt to most DBMS geographic database systems, publish the map data as a service, and provide flexible web map services in a more extensive way to meet large-scale industrial map applications. Based on this, PyramidMap integrates the adaptation interface to the geographic database supported by GeoServer, supports but is not limited to publishing the layers in Oracle, PostGIS, MySQL and other geographic databases to GeoServer, and outputs WMS/WFS and other types of map services, as shown in Figure 8-4.




Figure 8-4: Workflow of publishing geodatabase layer to GeoServer

Select the vector layer to publish in the local vector layer resource pool, and then select the GeoServer target server to publish, the workspace in the server, and the data store. The map will first be imported into the geographic database corresponding to the data store, and then published as a map service in zaiGeoServer. PyramidMap realizes the traditional complicated publishing process through an integrated visual process, greatly reducing the difficulty of work and improving the efficiency.

## 8.4 Manage GeoServer layers

As the visualization client of GeoServer map server, PyramidMap implements unified management of layers in GeoServer, including layer preview and query. PyramidMap's management of GeoServer layers includes three main functions: GeoServer data source node in the main interface, as shown in Figure 8-5.




Figure 8-5: GeoServer data source node in the main interface

Through the GeoServer data source node, you can complete various hierarchical operations on the GeoServer workspace, data storage, and layers. PyramidMap provides access to GeoServer layer preview list and GeoServer layer management list through toolbar menu items, as shown in Figure 8-6.




Figure 8-6: Main interface GeoServer layers operation entrance

Through the above menu items, the layer preview and management of GeoServer can be realized.

### 8.4.1 GeoServer layers preview

PyramidMap previews the layers published by the server through the GeoServer resource connection pool. The list of layers is shown in Figure 8-7.

No.	ConnName	Description	HostIP	Port	Web name	Web URL	Select
1	geoserver1		127.0.1	8080	geoserver	http://127.0.1.8080/geoserver	<input type="radio"/>
2	geoserver2		127.0.1	8080	dhcgiserver	http://127.0.1.8080/dhcgiserver	<input type="radio"/>
3	geoserver3		172.19.126.233	8080	geoserver	http://172.19.126.233:8080/geoserver	<input type="radio"/>
4	geoserver100	GeoServer in 192.168.31.100	192.168.31.100	8080	geoserver	http://192.168.31.100:8080/geoserver	<input type="radio"/>

No.	LayerTitle	LayerName	Workspace	ServiceSpace	DataStorage	Sld bind	CRS	Geometry	LayerType	MinX	MaxX	MinY	MaxY	Select	
14	Manhattan (NY) landmarks	poly_landmarks	tiger				EPSG:4326		Polygon	-74.047185	-73.90782	40.679848	40.882078	<input type="radio"/>	
15	Manhattan (NY) roads	tiger_roads	tiger				EPSG:4326		LineString	-74.02722	-73.907005	40.684221	40.878178	<input type="radio"/>	
16	A sample ArcGrid file	Arc_Sample	nurc				EPSG:4326		rasterType	-180.0	180.0	-90.0	90.0	<input type="radio"/>	
17	North America sample ...	Img_Sample	nurc				EPSG:4326		rasterType	-130.0516	-62.0054	20.7052	54.1141	<input type="radio"/>	
18	Pk50095	nurc					EPSG:32633		rasterType	347649.930868	370725.976428	5176214.08253...	5199891.35285...	<input type="radio"/>	
19	mosaic	nurc					EPSG:4326		raster	EPSG:4326	6.346	20.83	36.492	46.591	<input type="radio"/>
20.	hunansheng	topp					EPSG:3857		rasterType	121100735012	1.27188179945	2831509.38772...	3520154.13851...	<input type="radio"/>	
21	USA Population	states	topp				EPSG:4326		Polygon	124.73142200	-66.969849	24.955987	49.371735	<input checked="" type="radio"/>	
22	Tasmania cities	tasmania_cities	topp				EPSG:4326		Point	145.19754	148.27298000...	-43.423512	-40.852802	<input type="radio"/>	
23	Tasmania roads	tasmania_roads	topp				EPSG:4326		LineString	145.19754	148.27298000...	-43.423512	-40.852802	<input type="radio"/>	
24	Tasmania state boundar...	tasmania_state_bound...	topp				EPSG:4326		rasterType	143.834824000	148.479141000...	-43.648056	-39.573891	<input type="radio"/>	
25	Tasmania water bodies	tasmania_water_bodies	topp				EPSG:4326		rasterType	145.971618999	147.21969	-43.031944	-41.775558	<input type="radio"/>	
26	Spearfish archeological ...	archsites	sf				EPSG:26713		point	589851.43766	608348.490310	4914490.88293...	4926501.89803...	<input type="radio"/>	
27	Spearfish bug locations	bugsites	sf				EPSG:26713		Point	590223.438272	608462.460462	4914107.88251...	4920523.89081...	<input type="radio"/>	
28	Spearfish restricted areas	restricted	sf				EPSG:26713		rasterType	591579.195809	599648.925168	4916236.65222...	4925872.14621...	<input type="radio"/>	
29	Spearfish roads	roads	sf				EPSG:26713		rasterType	599434.856468	609527.210215...	4914006.33783...	4928063.39801...	<input type="radio"/>	
30	Spearfish elevation	stdem	sf				EPSG:26713		rasterType	589980.0	609000.0	4913700.0	4928010.0	<input type="radio"/>	
31	Spearfish streams	streams	sf				EPSG:26713		LineString	589434.497123	609518.211742...	4913947.34229...	4928071.04996...	<input type="radio"/>	
32	Buildings	Buildings	test				EPSG:4326		Point	-124.3154983...	-114.2397189...	32.507545471...	-42.0476341247...	<input type="radio"/>	
33	Cemeteries	Cemeteries	test				EPSG:4326		Point	-124.31082916...	-114.44750213...	32.5209045410...	-42.1687545776	<input type="radio"/>	
34	Counties	Counties	test				EPSG:4326		rasterType	-124.46111297...	-114.07981872	32.4807782592	42.0569000244	<input type="radio"/>	
35	GolfCourses	GolfCourses	test				EPSG:4326		Point	-124.21651458...	-114.55295562...	32.5943565388...	41.8813896179...	<input type="radio"/>	
36	Hospitals	Hospitals	test				EPSG:4326		Point	-124.42056243...	-114.25454711...	32.570953308...	41.8164932894...	<input type="radio"/>	
37	Lakes	Lakes	test				EPSG:4326		rasterType	-120.152127273	-115.59582373	33.1103213640...	39.2493473640...	<input type="radio"/>	
38	MajorRoads	MajorRoads	test				EPSG:4326		LineString	124.39470153...	-112.12548065...	32.4949607849...	42.0605850219...	<input type="radio"/>	
39	Rivers	Rivers	test				EPSG:4326		LineString	124.052293273	-118.336762273	36.391315450...	42.067957370...	<input type="radio"/>	
40	UrbanAreas	UrbanAreas	test				EPSG:4326		rasterType	124.26885749...	-114.22722625	32.5088157653...	42.0281600952...	<input type="radio"/>	

Figure 8-7: GeoServer layer list

The GeoServer layer includes vector and image types, while the vector layer includes point, linestring and polygon types. PyramidMap performs corresponding WMS/WFS service request operations based on the GeoServer layer type. WMS/WFS are both OGC standard services, with the difference being that the former provides read-only access while the latter supports editing operations. Taking the states vector layer in the top workspace as an example, it supports WMS/WFS operations, as shown in Figure 8-8.




Figure 8-8: GeoServer vector layer preview

Taking the hunansheng image layer in the top space as an example, WMS preview is supported, as shown in Figure 8-9.




Figure 8-9: GeoServer raster layer preview

## 8.4.2 GeoServer layers export and conversion

PyramidMap provides some column export and data conversion operations for the layers in GeoServer, which is not available in regular GeoServer, giving more flexibility and operable space to map data. As shown in Figure 8-10.

No.	LayerTitle	LayerName	Workspace	ServiceSpace	DataStorage	Std bind	CRS	Geometry	LayerType	MinX	MaxX	MinY	MaxY	Select
1	Buildings	Buildings	cite	http://127.0.1.8080/geoserver	postgre1014	provinceregion	EPSG:4326	Point	Polygon	-124.315	-114.24	32.508	42.048	<input checked="" type="checkbox"/>
2	World rectangle	giant_polygon	tiger	http://127.0.1.8080/geoserver	nyc	provinceregion	EPSG:4326	Polygon	Polygon	-180	180	-90	90	<input checked="" type="checkbox"/>
3	Manhattan (NY) points of ...	poi	tiger	http://127.0.1.8080/geoserver	nyc	generic	EPSG:4326	Point	Polygon	-74.012	-74.002	40.708	40.72	<input checked="" type="checkbox"/>
4	Manhattan (NY) landmarks	poly_landmarks	tiger	http://127.0.1.8080/geoserver	nyc	poly_landmarks	EPSG:4326	Polygon	Polygon	-74.047	-73.908	40.68	40.882	<input checked="" type="checkbox"/>
5	Manhattan (NY) roads	tiger_roads	tiger	http://127.0.1.8080/geoserver	nyc	tiger_roads	EPSG:4326	LineString	Polygon	-74.027	-73.907	40.684	40.878	<input checked="" type="checkbox"/>
6	USA Population	states	topp	http://127.0.1.8080/geoserver	states_shapefile	population	EPSG:4326	Polygon	Polygon	-124.731	-66.97	24.956	49.372	<input checked="" type="checkbox"/>
7	Tasmania cities	tasmania_cities	topp	http://127.0.1.8080/geoserver	taz_shapes	capitals	EPSG:4326	Point	Polygon	145.198	146.273	-43.424	-40.853	<input checked="" type="checkbox"/>
8	Tasmania roads	tasmania_roads	topp	http://127.0.1.8080/geoserver	taz_shapes	simple_roads	EPSG:4326	LineString	Polygon	145.198	148.273	-43.424	-40.853	<input checked="" type="checkbox"/>
9	Tasmania state boundary	tasmania_state_bound...	topp	http://127.0.1.8080/geoserver	taz_shapes	green	EPSG:4326	Polygon	Polygon	143.835	148.479	-43.646	-39.574	<input checked="" type="checkbox"/>
10	Tasmania water bodies	tasmania_water_bodies	topp	http://127.0.1.8080/geoserver	taz_shapes	restricted	EPSG:4326	Polygon	Polygon	145.972	147.22	-43.032	-41.776	<input checked="" type="checkbox"/>
11	Spearfish archeological ...	archsites	sf	http://127.0.1.8080/geoserver	sf	point	EPSG:267113	Point	Polygon	589.851438	608.34646	4,914,490.883	4,926,501.898	<input checked="" type="checkbox"/>
12	Spearfish bug locations	bugsites	sf	http://127.0.1.8080/geoserver	sf	capital	EPSG:267113	Point	Polygon	590.223438	608.46246	4,914,107.883	4,920,523.891	<input checked="" type="checkbox"/>
13	Spearfish restricted areas	restricted	sf	http://127.0.1.8080/geoserver	sf	restricted	EPSG:267113	Polygon	Polygon	591.579186	599.648925	4,916,236.662	4,925,872.148	<input checked="" type="checkbox"/>
14	Spearfish roads	roads	sf	http://127.0.1.8080/geoserver	sf	simple_roads	EPSG:267113	LineString	Polygon	589.434856	609.52721	4,914,006.338	4,928,063.398	<input checked="" type="checkbox"/>
15	Spearfish streams	streams	sf	http://127.0.1.8080/geoserver	sf	simple_streams	EPSG:267113	LineString	Polygon	589.434497	609.518212	4,913,947.342	4,928,071.05	<input checked="" type="checkbox"/>
16	Buildings	Buildings	test	http://127.0.1.8080/geoserver	postgre231104	point	EPSG:4326	Point	Polygon	-124.315	-114.24	32.508	42.048	<input checked="" type="checkbox"/>
17	Cemeteries	Cemeteries	test	http://127.0.1.8080/geoserver	postgre231104	point	EPSG:4326	Point	Polygon	-124.311	-114.448	32.521	42.169	<input checked="" type="checkbox"/>
18	Counties	Counties	test	http://127.0.1.8080/geoserver	postgre231104	polygon	EPSG:4326	Polygon	Polygon	-124.461	-114.08	32.487	42.057	<input checked="" type="checkbox"/>
19	Golf Courses	GolfCourses	test	http://127.0.1.8080/geoserver	postgre231104	point	EPSG:4326	Point	Polygon	-124.217	-114.553	32.594	41.881	<input checked="" type="checkbox"/>
20	Hospitals	Hospitals	test	http://127.0.1.8080/geoserver	postgre231104	point	EPSG:4326	Point	Polygon	-124.241	-114.255	32.571	41.818	<input checked="" type="checkbox"/>
21	Lakes	Lakes	test	http://127.0.1.8080/geoserver	postgre231104	polygon	EPSG:4326	Polygon	Polygon	-120.152	-115.596	33.11	39.249	<input checked="" type="checkbox"/>
22	Major Roads	MajorRoads	test	http://127.0.1.8080/geoserver	postgre231104	line	EPSG:4326	LineString	Polygon	-124.335	-114.125	32.495	42.051	<input checked="" type="checkbox"/>
23	Rivers	Rivers	test	http://127.0.1.8080/geoserver	postgre231104	line	EPSG:4326	LineString	Polygon	-124.052	-118.337	36.391	42.007	<input checked="" type="checkbox"/>
24	Urban Areas	UrbanAreas	test	http://127.0.1.8080/geoserver	postgre231104	polygon	EPSG:4326	Polygon	Polygon	124.269	-114.227	32.509	42.028	<input checked="" type="checkbox"/>

Figure 8-10: GeoServer layers export and conversion

PyramidMap can export the layers in GeoServer to Shp, Kml, Csv, GeoJson and other formats, realizing the visual transformation of map data and expanding the utilization space of map data.