DirectXTutorial.com

The Ultimate DirectX Tutorial

Navigation

Home
DirectX for Windows 8
DirectX 11.2
DirectX 11.1
DirectX for Desktop
DirectX 11
DirectX 9
Useful Resources
About DirectXTutorial
DirectXTutorial Premium
Testimonials

Contact

Contact me here: Twitter: @dastopher Email: chris@directxtutorial.com

Or leave me feedback:

Lesson 3: Rendering Frames

<u>Previous</u> <u>Next</u>

Lesson Overview

Once Direct3D is initialized, it's time to start doing some actual rendering. Rendering itself is very easy, but there is a little bit of preparatory work involved. In this lesson we're going to get everything set up to render a blank frame, over and over again.

The setup involved is simple. There are two things that need to be done. First, we need to tell the GPU where in memory to create the final image (for us, this is the back buffer). Second, we need to tell the GPU where on the backbuffer it should draw.

Once that's done, we can render, and man is it easy.

Setting the Render Target

Let's start with where to render to. Now logically you would say, "the backbuffer, duh!" and be done. However, Direct3D doesn't actually know that at this point. It is possible that you do not want to render to the back buffer right away. For example many games render to the surface of a model, then render that model to the back buffer. This technique can produce a variety of effects. If you have played the game *Portal* you will have seen an example of this. In *Portal*, the game engine first renders to the portal, then renders a full scene with the portal image included.



Rendering to a Portal, and Rendering to the Back Buffer

When rendering in Direct3D, you must establish the render target. This is a simple COM object that maintains a location in video memory for you to render into. In most cases (including our case) this is the back buffer.

Here's how we do it:

ID3D11RenderTargetView *backbuffer; // global declaration

// this function initializes and prepares Direct3D for use
void InitD3D(HWND hWnd)
{
 // Direct3D initialization

```
// ...
// get the address of the back buffer
ID3D11Texture2D *pBackBuffer;
swapchain->GetBuffer(0, __uuidof(ID3D11Texture2D), (LPVOID*)&pBackBuffer);

// use the back buffer address to create the render target
dev->CreateRenderTargetView(pBackBuffer, NULL, &backbuffer);
pBackBuffer->Release();

// set the render target as the back buffer
devcon->OMSetRenderTargets(1, &backbuffer, NULL);
}
```

Whoa. It looks complex, but it's pretty simple.

There are three things being done here. First, we determine the address of the back buffer. Second, we create a COM object using that address to represent the render target. Third, we set that object as the active render target.

There's some new code here, so let's find out what it all means.

ID3D11RenderTargetView *backbuffer;

This variable is a pointer to an object that holds all the information about the render target. We'll be rendering to the back buffer, so we'll call this variable 'backbuffer'.

ID3D11Texture2D *pBackBuffer;

In 3D rendering, a *texture* is another name for an image. An ID3D11Texture2D is an object that stores a flat image. Like any COM object, we first define the pointer, and later a function creates the object for us.

swapchain->GetBuffer(0, __uuidof(ID3D11Texture2D), (LPVOID*)&pBackBuffer);

You may not believe me, but this command is actually simple. What this GetBuffer() function does is find the back buffer on the swap chain and use it to create the pBackBuffer texture object.

The first parameter is the number of the back buffer to get. We are only using one back buffer on this chain, and it is back buffer #0. Therefore, the first parameter will be 0.

The second parameter is a number identifying the ID3D11Texture2D COM object. Each type of COM object has its own unique ID that is used to get information about it. To get this ID, we must use the __uuidof operator. The exact details of how this works are unimportant, but the reason we do it is so that the GetBuffer() function knows what type of object it is supposed to be creating.

The third parameter may not make sense to you unless you are at least intermediate with C++. Basically a void* is a pointer that points to no particular type of variable. For example, a double* points to a double, whereas an int* points to an int. A void* is used to point to anything, and it can be converted to any other type of pointer.

In this third parameter, we have a pointer to a void*. This void* gets filled with the location of the ID3D11Texture2D object. It needs to be a void* because there are other types of objects we could be asking for.

This particular function is one that you won't be messing around with too much, so don't worry if it's a little bit shrowded in mystery right now. You'll have an easier time getting it as you learn more about Direct3D.

dev->CreateRenderTargetView(pBackBuffer, NULL, &backbuffer);

This function creates the render target object. We created the pointer for this object at the top of the program.

The first parameter is a pointer to the texture. It should be 'pBackBuffer' for our program.

The second parameter is a struct that describes the render target. We won't need to fill this out for the back buffer. We'll just set it to NULL.

The third parameter is the address of the object pointer. The pointer name was 'backbuffer', so we'll use '&backbuffer'.

pBackBuffer->Release();

The Release() function frees all memory and closes all threads used by a COM object. We are done with the pBackBuffer object, so we will Release() it. Note that this doesn't destroy the back buffer, it only closes the texture object we used to access it.

devcon->OMSetRenderTargets(1, &backbuffer, NULL);

This last function actually sets the render target. More exactly, it sets multiple render targets.

The first parameter is the number of render targets to set. This will usually be 1, but there are cases where it will be more.

The second parameter is a pointer to a list of render target view objects. We only have one, so it's just the address of our render target object (&backbuffer).


The third parameter is advanced, and we'll get into it in a later lesson. For now it can be NULL.

This section of code is a bit complex. Make sure you go over it until you get what is happening, because it will be used and modified many times in your Direct3D programming.

Setting the Viewport

This section of code will be a piece of cake compared to the last one.

A *viewport* is a way of translating pixel coordinates to normalized coordinates. The following diagram shows the difference between the two.



Pixel Coordinates and Normalized Coordinates

On the left, pixel coordinates start at 0, 0 in the upper-left corner, and increase one pixel at a time. On the right, normalized coordinates start at -1, -1 and increase to 1, 1, no matter the size of the back buffer. The word *normalized* means that a value is adjusted until it equals 1.

What -1, -1 and 1, 1 actually equate to is determined by the viewport. The viewport is a struct that lets us set where -1, -1 and 1, 1 will be in pixel coordinates.

Here's what the code to set the viewport looks like:

```
// this function initializes and prepares Direct3D for use
void InitD3D(HWND hWnd)
{
    // Direct3D initialization
    // ...

    // Set the render target
    // ...

    // Set the viewport
    D3D11_VIEWPORT viewport;
    ZeroMemory(&viewport, sizeof(D3D11_VIEWPORT));

    viewport.TopLeftX = 0;
    viewport.TopLeftY = 0;
    viewport.Width = 800;
    viewport.Height = 600;

    devcon->RSSetViewports(1, &viewport);
}
```

Probably the only line here that needs explanation is the last one.

RSSetViewports() is a function that activates viewport structs. The first parameter is the number of viewports being used, and the second parameter is the address of a list of pointers to the viewport structs.

Using multiple viewports is handy in certain advanced situations, but we won't get into them here. For now, 1 and '&viewport' will suit the parameters fine.

Rendering Frames

Next we'll create a function that renders a single frame. The frame will be rather simple for now, and will consist only of a blue background. Of course, you can change the color if you want. Here is the code for this function.

```
// this is the function used to render a single frame
void RenderFrame(void)
{
    // clear the back buffer to a deep blue
    devcon->ClearRenderTargetView(backbuffer, D3DXCOLOR(0.0f, 0.2f, 0.4f, 1.0f));

    // do 3D rendering on the back buffer here

    // switch the back buffer and the front buffer
    swapchain->Present(0, 0);
}
```

Nice! A whopping two lines of code! Let's talk about what they do.

devcon->ClearRenderTargetView()

This fills a render target buffer with a specific color. In our case, we are going to fill our back buffer. It's pretty simple. There are two parameters.

The first one is the address of the render target object. We just put 'backbuffer' here.

The second parameter is the color you want to fill the back buffer with. To do this, we use a simple struct called D3DXCOLOR. The four constructor parameters are used to build the color. The first three are the red, green and blue values, and the fourth is the alpha value (which is meaningless on a backbuffer, but necessary as we'll see later on).

swapchain->Present()

Next we call the Present() function. This function is where everything that has been drawn on the back buffer actually appears. It's job is basically to perform the "swap" in the swap chain, so that the back buffer becomes the front buffer.

The two parameters, both set to 0, are not going to be used much in this tutorial.

Obligatory Cleanup

In the last lesson we closed down Direct3D by releasing each COM object we created. Most COM objects have this Release() function, and if they do, we must call it when we're done. The render target object is no exception.

```
// this is the function that cleans up Direct3D and COM
void CleanD3D()
{
    // close and release all existing COM objects
    swapchain->Release();
    backbuffer->Release();
    dev->Release();
    devcon->Release();
}
```

Get into the habit of ensuring that all COM objects are released. The more we add, the easier it can be to forget one.


The Finished Program

Excellent! We've got Direct3D running and we've got a simple, blank frame rendering into a window. We're making good progress.

Below, I've added in the new code. Take a look over it, and go ahead and run the new program.

[Main.cpp]

Now that we've got a frame rendering, we should get a blue window!



Our Direct3D Program, Now in Color

Ready...Set...

Once again, let's look at what we've learned and find out if we're ready to move on.

Questions

- 1. What is a render target? What function creates the render target?
- 2. What two functions render the blank, blue frame? What do these functions do exactly?3. What are normalized coordinates?

Exercises

- See if you can get your program to change colors while running. Make it fade from blue to black.
 Change the viewport and see what "happens". We'll discuss why this is in a few lessons.

Next Lesson: Going Fullscreen

GO! GO! GO!

© 2006-2020 DirectXTutorial.com. All Rights Reserved. Expand