### The Hardware/Software Interface

CSE351 Spring 2013

x86 Programming I

#### Roadmap

#### C:

```
car *c = malloc(sizeof(car));
c->miles = 100;
c->gals = 17;
float mpg = get_mpg(c);
free(c);
```

#### Java:

# Assembly language:

```
get_mpg:
    pushq %rbp
    movq %rsp, %rbp
    ...
    popq %rbp
    ret
```

OS:

Data & addressing **Integers & floats** Machine code & C x86 assembly programming **Procedures &** stacks **Arrays & structs** Memory & caches **Processes** Virtual memory **Memory allocation** Java vs. C

# Machine code:



# Computer system:








### **Today**

- Move instructions, registers, and operands
- Memory addressing modes
- swap example: 32-bit vs. 64-bit
- Arithmetic operations

## Why learn assembly language?

- Not to be able to write programs directly in assembly
  - Compilers do that for you
- But to be able to understand the code generated by compilers, so that you can then:
  - Optimize performance of critical sections of code
  - Investigate unexpected or even buggy behavior
  - Understand how security vulnerabilities arise, and how to protect against them

## **Integer Registers (IA32)**



stack pointer base pointer

#### Three Basic Kinds of Instructions

- Transfer data between memory and register
  - Load data from memory into register
    - %reg = Mem[address]
  - Store register data into memory
    - Mem[address] = %reg

Remember: memory is indexed just like an array[]!

- Perform arithmetic function on register or memory data
  - c = a + b;
- Transfer control
  - Unconditional jumps to/from procedures
  - Conditional branches

#### **Moving Data: IA32**

- Moving Data
  - movx Source, Dest
  - **x** is one of {**b**, **w**, **1**}
  - mov1 Source, Dest:
    Move 4-byte "long word"
  - movw Source, Dest: Move 2-byte "word"
  - movb Source, Dest:
    Move 1-byte "byte"

Lots of these in typical code

%eax
%ecx
%edx
%ebx
%esi
%edi
%esp
%ebp

#### **Moving Data: IA32**

Moving Data

mov1 *Source*, *Dest*:

- Operand Types
  - Immediate: Constant integer data
    - Example: \$0x400, \$-533
    - Like C constant, but prefixed with \\$'
    - Encoded with 1, 2, or 4 bytes
  - Register: One of 8 integer registers
    - Example: %eax, %edx
    - But %esp and %ebp reserved for special use
    - Others have special uses for particular instructions
  - Memory: 4 consecutive bytes of memory at address given by register
    - Simplest example: (%eax)
    - Various other "address modes"

%eax
%ecx
%edx
%ebx
%esi
%edi
%esp
%ebp

#### movl Operand Combinations

Cannot do memory-memory transfer with a single instruction.

### Memory vs. registers

Why both?

#### **Memory Addressing Modes: Basic**

- Indirect (R) Mem[Reg[R]]
  - Register R specifies the memory address

```
movl (%ecx),%eax
```

- Displacement D(R) Mem[Reg[R]+D]
  - Register R specifies a memory address
    - (e.g. the start of some memory region)
  - Constant displacement D specifies the offset from that address

```
movl 8 (%ebp), %edx
```

### **Using Basic Addressing Modes**


```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

#### swap:

```
pushl %ebp
movl %esp,%ebp
pushl %ebx
movl 12(%ebp),%ecx
mov1 8 (%ebp), %edx
movl (%ecx), %eax
                       Body
movl (%edx),%ebx
movl %eax,(%edx)
movl %ebx,(%ecx)
movl -4(%ebp), %ebx
movl %ebp,%esp
                       Finish
popl %ebp
ret
```

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

Register	Value	
%ecx	ур	
%edx	хр	
%eax	t1	
%ebx	t0	



```
movl 12(%ebp),%ecx # ecx = yp
movl 8(%ebp),%edx # edx = xp
movl (%ecx),%eax # eax = *yp (t1)
movl (%edx),%ebx # ebx = *xp (t0)
movl %eax,(%edx) # *xp = eax
movl %ebx,(%ecx) # *yp = ebx
```

### **Understanding Swap**



%edx

%ecx


%ebx

%esi

%edi


%esp

%ebp 0x104



**Address** 

## **Understanding Swap**



%edx

%ecx 0x120


%ebx

%esi

%edi

%esp

%ebp 0x104



```
movl 12(%ebp),%ecx  # ecx = yp
movl 8(%ebp),%edx  # edx = xp
movl (%ecx),%eax  # eax = *yp (t1)
movl (%edx),%ebx  # ebx = *xp (t0)
movl %eax,(%edx)  # *xp = eax
movl %ebx,(%ecx)  # *yp = ebx
```

**Address** 

#### **Understanding Swap**

%eax

%edx 0x124

%ecx 0x120


%ebx

%esi

%edi

%esp

%ebp 0x104




```
movl 12(%ebp),%ecx  # ecx = yp
movl 8(%ebp),%edx  # edx = xp
movl (%ecx),%eax  # eax = *yp (t1)
movl (%edx),%ebx  # ebx = *xp (t0)
movl %eax,(%edx)  # *xp = eax
movl %ebx,(%ecx)  # *yp = ebx
```



```
Address
              123
                        0x124
              456
                        0x120
                        0x11c
                        0x118
      Offset
                        0x114
         12
              0x120
yp
                        0x110
          8
              0x124
хp
                        0x10c
          4
              Rtn adr
                        0x108
%ebp
                        0x104
         -4
                        0x100
```

```
movl 12(%ebp),%ecx # ecx = yp
movl 8(%ebp),%edx # edx = xp
movl (%ecx),%eax # eax = *yp (t1)
movl (%edx),%ebx # ebx = *xp (t0)
movl %eax,(%edx) # *xp = eax
movl %ebx,(%ecx) # *yp = ebx
```



```
Address
              123
                        0x124
              456
                        0x120
                        0x11c
                        0x118
      Offset
                        0x114
         12
              0x120
yp
                        0x110
          8
              0x124
хp
                        0x10c
          4
              Rtn adr
                        0x108
%ebp
                        0x104
         -4
                        0x100
```

```
movl 12(%ebp),%ecx # ecx = yp
movl 8(%ebp),%edx # edx = xp
movl (%ecx),%eax # eax = *yp (t1)
movl (%edx),%ebx # ebx = *xp (t0)
movl %eax,(%edx) # *xp = eax
movl %ebx,(%ecx) # *yp = ebx
```

**Address** 



```
456
                         0x124
              456
                         0x120
                         0x11c
                         0x118
      Offset
                         0x114
         12
              0 \times 120
yp
                         0x110
           8
              0x124
хp
                         0x10c
           4
              Rtn adr
                         0x108
%ebp
                         0x104
          -4
                         0x100
```

```
movl 12(%ebp),%ecx  # ecx = yp
movl 8(%ebp),%edx  # edx = xp
movl (%ecx),%eax  # eax = *yp (t1)
movl (%edx),%ebx  # ebx = *xp (t0)
movl %eax,(%edx)  # *xp = eax
movl %ebx,(%ecx)  # *yp = ebx
```



```
Address
              456
                        0x124
              123
                        0x120
                        0x11c
                        0x118
      Offset
                        0x114
         12
              0x120
yp
                        0x110
          8
              0x124
хp
                        0x10c
          4
              Rtn adr
                        0x108
%ebp
                        0x104
         -4
                        0x100
```

```
movl 12(%ebp),%ecx  # ecx = yp
movl 8(%ebp),%edx  # edx = xp
movl (%ecx),%eax  # eax = *yp (t1)
movl (%edx),%ebx  # ebx = *xp (t0)
movl %eax,(%edx)  # *xp = eax
movl %ebx,(%ecx)  # *yp = ebx
```

64-bits wide x86-64 Integer Registers %r8 %rax %eax %r8d %rbx %r9 %r9d %ebx %r10 %rcx %r10d %ecx %rdx %r11 %edx %r11d %r12 %rsi %r12d %esi %r13 %rdi %edi %r13d %r14 %rsp %r14d %esp %rbp %r15 %r15d %ebp

Extend existing registers, and add 8 new ones; all accessible as 8, 16, 32, 64 bits.

#### 32-bit vs. 64-bit operands


■ Long word 1 (4 Bytes)  $\leftrightarrow$  Quad word q (8 Bytes)

#### New instruction forms:

- mov1 → movq
- addl → addq
- sall → salq
- etc.
- x86-64 can still use 32-bit instructions that generate 32-bit results
  - Higher-order bits of destination register are just set to 0
  - Example: addl

#### **Swap Ints in 32-bit Mode**

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```



```
swap:
   pushl %ebp
   movl %esp,%ebp
                             Setup
   pushl %ebx
   movl 12(%ebp),%ecx
   mov1 8(%ebp), %edx
   movl (%ecx),%eax
                             Body
   movl (%edx),%ebx
   movl %eax, (%edx)
   movl %ebx,(%ecx)
   movl -4(%ebp),%ebx
   movl %ebp,%esp
                             Finish
   popl %ebp
   ret
```

#### Swap Ints in 64-bit Mode

```
void swap(int *xp, int *yp)
{
  int t0 = *xp;
  int t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

```
swap:
  movl (%rdi), %edx
  movl (%rsi), %eax
  movl %eax, (%rdi)
  movl %edx, (%rsi)
  retq
```

- Arguments passed in registers (why useful?)
  - First (xp) in %rdi, second (yp) in %rsi
  - 64-bit pointers
- No stack operations required
- 32-bit data
  - Data held in registers %eax and %edx
  - mov1 operation (the 1 refers to data width, not address width)

#### **Swap Long Ints in 64-bit Mode**

```
void swap_l
   (long int *xp, long int *yp)
{
   long int t0 = *xp;
   long int t1 = *yp;
   *xp = t1;
   *yp = t0;
}
```

#### ■ 64-bit data

- Data held in registers %rax and %rdx
- movq operation
- "q" stands for quad-word

#### **Complete Memory Addressing Modes**

- Remember, the addresses used for accessing memory in mov (and other) instructions can be computed in several different ways
- Most General Form:

```
D(Rb,Ri,S) Mem[Reg[Rb] + S*Reg[Ri] + D]
```

- D: Constant "displacement" 1, 2, or 4 bytes
- Rb: Base register: Any of the 8/16 integer registers
- Ri: Index register: Any, except for %esp or %rsp
  - Unlikely you'd use %ebp, either
- Scale: 1, 2, 4, or 8 (why these numbers?)
- Special Cases: can use any combination of D, Rb, Ri and S

```
(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]]
```

D(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]+D]

(Rb,Ri,S) Mem[Reg[Rb]+S\*Reg[Ri]]

#### **Address Computation Examples**

%edx	0xf000	
%ecx	0x100	

(Rb,Ri)	Mem[Reg[Rb]+Reg[Ri]]
D(,Ri,S)	Mem[S*Reg[Ri]+D]
(Rb,Ri,S)	Mem[Reg[Rb]+S*Reg[Ri]
D(Rb)	Mem[Reg[Rb] +D]

Expression	Address Computation	Address
0x8 (%edx)	0xf000 + 0x8	0xf008
(%edx,%ecx)	0xf000 + 0x100	0xf100
(%edx,%ecx,4)	0xf000 + 4*0x100	0xf400
0x80(,%edx,2)	2*0xf000 + 0x80	0x1e080

#### **Address Computation Instruction**

#### leal Src,Dest

- Src is address mode expression
- Set Dest to address computed by expression
  - (lea stands for load effective address)
- Example: leal (%edx,%ecx,4), %eax

#### Uses

- Computing addresses without a memory reference
  - E.g., translation of p = &x[i];
- Computing arithmetic expressions of the form x + k\*i
  - k = 1, 2, 4, or 8

#### **Some Arithmetic Operations**

**■ Two Operand (Binary) Instructions:** 

```
Format
                      Computation
                      Dest = Dest + Src
addl Src,Dest
subl Src,Dest
                      Dest = Dest - Src
imull Src,Dest
                      Dest = Dest * Src
                                              Also called shill
sall Src,Dest
                      Dest = Dest << Src
sarl Src, Dest
                      Dest = Dest >> Src
                                              Arithmetic
                      Dest = Dest >> Src
                                              Logical
shrl Src,Dest
xorl Src,Dest
                      Dest = Dest ^ Src
andl Src,Dest
                      Dest = Dest & Src.
orl Src,Dest
                      Dest = Dest | Src
```

- Watch out for argument order! (especially sub1)
- No distinction between signed and unsigned int (why?)

#### **Some Arithmetic Operations**

■ One Operand (Unary) Instructions


■ See textbook section 3.5.5 for more instructions: mull, cltd, idivl, divl

#### Using leal for Arithmetic Expressions

```
int arith
  (int x, int y, int z)
{
  int t1 = x+y;
  int t2 = z+t1;
  int t3 = x+4;
  int t4 = y * 48;
  int t5 = t3 + t4;
  int rval = t2 * t5;
  return rval;
}
```


```
arith:
   pushl %ebp
                                   Set
   movl %esp, %ebp
                                   Up
   movl 8(%ebp), %eax
   movl 12 (%ebp), %edx
   leal (%edx, %eax), %ecx
   leal (%edx, %edx, 2), %edx
                                   Body
   sall $4,%edx
   addl 16(%ebp),%ecx
   leal 4(%edx,%eax),%eax
   imull %ecx, %eax
   movl %ebp,%esp
                                  Finish
   popl %ebp
   ret
```

```
int arith
  (int x, int y, int z)
{
  int t1 = x+y;
  int t2 = z+t1;
  int t3 = x+4;
  int t4 = y * 48;
  int t5 = t3 + t4;
  int rval = t2 * t5;
  return rval;
}
```




```
movl 8(%ebp),%eax # eax = x
movl 12(%ebp),%edx # edx = y
leal (%edx,%eax),%ecx # ecx = x+y (t1)
leal (%edx,%edx,2),%edx # edx = y + 2*y = 3*y
sall $4,%edx # edx = 48*y (t4)
addl 16(%ebp),%ecx # ecx = z+t1 (t2)
leal 4(%edx,%eax),%eax # eax = 4+t4+x (t5)
imull %ecx,%eax # eax = t5*t2 (rval)
```

```
int arith
  (int x, int y, int z)
{
  int t1 = x+y;
  int t2 = z+t1;
  int t3 = x+4;
  int t4 = y * 48;
  int t5 = t3 + t4;
  int rval = t2 * t5;
  return rval;
}
```




```
movl 8(%ebp),%eax # eax = x
movl 12(%ebp),%edx # edx = y
leal (%edx,%eax),%ecx # ecx = x+y (t1)
leal (%edx,%edx,2),%edx # edx = y + 2*y = 3*y
sall $4,%edx # edx = 48*y (t4)
addl 16(%ebp),%ecx # ecx = z+t1 (t2)
leal 4(%edx,%eax),%eax # eax = 4+t4+x (t5)
imull %ecx,%eax # eax = t5*t2 (rval)
```

```
int arith
  (int x, int y, int z)
{
  int t1 = x+y;
  int t2 = z+t1;
  int t3 = x+4;
  int t4 = y * 48;
  int t5 = t3 + t4;
  int rval = t2 * t5;
  return rval;
}
```



```
movl 8(%ebp),%eax # eax = x
movl 12(%ebp),%edx # edx = y
leal (%edx,%eax),%ecx # ecx = x+y (t1)
leal (%edx,%edx,2),%edx # edx = y + 2*y = 3*y
sall $4,%edx # edx = 48*y (t4)
addl 16(%ebp),%ecx # ecx = z+t1 (t2)
leal 4(%edx,%eax),%eax # eax = 4+t4+x (t5)
imull %ecx,%eax # eax = t5*t2 (rval)
```

```
int arith
  (int x, int y, int z)
{
  int t1 = x+y;
  int t2 = z+t1;
  int t3 = x+4;
  int t4 = y * 48;
  int t5 = t3 + t4;
  int rval = t2 * t5;
  return rval;
}
```



```
movl 8(%ebp),%eax # eax = x
movl 12(%ebp),%edx # edx = y
leal (%edx,%eax),%ecx # ecx = x+y (t1)
leal (%edx,%edx,2),%edx # edx = y + 2*y = 3*y
sall $4,%edx # edx = 48*y (t4)
addl 16(%ebp),%ecx # ecx = z+t1 (t2)
leal 4(%edx,%eax),%eax # eax = 4+t4+x (t5)
imull %ecx,%eax # eax = t5*t2 (rval)
```

#### Observations about arith

```
int arith
  (int x, int y, int z)
{
  int t1 = x+y;
  int t2 = z+t1;
  int t3 = x+4;
  int t4 = y * 48;
  int t5 = t3 + t4;
  int rval = t2 * t5;
  return rval;
}
```

- Instructions in different order from C code
- Some expressions require multiple instructions
- Some instructions cover multiple expressions
- Get exact same code when compile:
- (x+y+z)\*(x+4+48\*y)

```
movl 8(%ebp),%eax # eax = x
movl 12(%ebp),%edx # edx = y
leal (%edx,%eax),%ecx # ecx = x+y (t1)
leal (%edx,%edx,2),%edx # edx = y + 2*y = 3*y
sall $4,%edx # edx = 48*y (t4)
addl 16(%ebp),%ecx # ecx = z+t1 (t2)
leal 4(%edx,%eax),%eax # eax = 4+t4+x (t5)
imull %ecx,%eax # eax = t5*t2 (rval)
```

```
int logical(int x, int y)
{
  int t1 = x^y;
  int t2 = t1 >> 17;
  int mask = (1<<13) - 7;
  int rval = t2 & mask;
  return rval;
}</pre>
```

```
logical:
   pushl %ebp
   movl %esp,%ebp

movl 8(%ebp),%eax
   xorl 12(%ebp),%eax
   sarl $17,%eax
   andl $8185,%eax

Body

movl %ebp,%esp
   popl %ebp
   ret
Finish
```

```
movl 8(%ebp),%eax # eax = x
xorl 12(%ebp),%eax # eax = x^y
sarl $17,%eax # eax = t1>>17
andl $8185,%eax # eax = t2 & 8185

**

**Rtn adr Old %ebp **ebp
```

```
int logical(int x, int y)
{
   int t1 = x^y;
   int t2 = t1 >> 17;
   int mask = (1<<13) - 7;
   int rval = t2 & mask;
   return rval;
}</pre>
```

```
logical:
   pushl %ebp
   movl %esp,%ebp

movl 8(%ebp),%eax
   xorl 12(%ebp),%eax
   sarl $17,%eax
   andl $8185,%eax

Body

movl %ebp,%esp
   popl %ebp
   ret
Finish
```

```
movl 8(%ebp),%eax eax = x

xorl 12(%ebp),%eax eax = x^y (t1)

sarl $17,%eax eax = t1>>17 (t2)

andl $8185,%eax eax = t2 & 8185
```

```
int logical(int x, int y)
{
  int t1 = x^y;
  int t2 = t1 >> 17;
  int mask = (1<<13) - 7;
  int rval = t2 & mask;
  return rval;
}</pre>
```

```
logical:
   pushl %ebp
   movl %esp,%ebp

movl 8(%ebp),%eax
   xorl 12(%ebp),%eax
   sarl $17,%eax
   andl $8185,%eax

Body

movl %ebp,%esp
   popl %ebp
   ret
Finish
```

```
movl 8(%ebp),%eax eax = x

xorl 12(%ebp),%eax eax = x^y (t1)

sarl $17,%eax eax = t1>>17 (t2)

andl $8185,%eax eax = t2 & 8185
```

```
int logical(int x, int y)
{
  int t1 = x^y;
  int t2 = t1 >> 17;
  int mask = (1<<13) - 7;
  int rval = t2 & mask;
  return rval;
}</pre>
```

```
2^{13} = 8192, 2^{13} - 7 = 8185 ...001000000000000, ...0001111111111001
```

```
logical:
   pushl %ebp
   movl %esp,%ebp

movl 8(%ebp),%eax
   xorl 12(%ebp),%eax
   sarl $17,%eax
   andl $8185,%eax

Body

movl %ebp,%esp
   popl %ebp
   ret
Finish
```

```
movl 8(%ebp),%eax eax = x

xorl 12(%ebp),%eax eax = x^y (t1)

sarl $17,%eax eax = t1>>17 (t2)

andl $8185,%eax eax = t2 & 8185
```