User Guide for Developing a Virtual Object Layer Plugin

Mohamad Chaarawi 1 1 The HDF Group, hdfgroup.org 1 1th January 2018



CONTENTS

Contents

1	Introduction		
2		5 8 10 14 18 21 24 28	
3	New VOL API Routines 2		
4 5	4.1 Implementing an Internal Plugin	32 33	
	5.1 Creating an External Plugin		
6	Interchanging and Stacking VOL Plugins 6.1 Stacking Plugins on Top of Each Other	35	
$\mathbf{A}_{]}$	ppendix A VOL Plugin Example	37	
_	ppendix B Listing of Direct Mapping to VOL Callback APIs	44	

1 Introduction

The Virtual Object Layer (VOL) is an abstraction layer in the HDF5 library that intercepts all API calls that could potentially access objects in an HDF5 container and forwards those calls to the plugin "object drivers". The plugins could store the objects in a variety of ways. A plugin could, for example, have objects be distributed remotely over different platforms, provide a raw mapping of the model to the file system, or even store the data in other file formats (like native netCDF or HDF4 format). The user still gets the same data model where access is done to a single HDF5 "container"; however, the plugin object driver translates from what the user sees to how the data is actually stored. Having this abstraction layer maintains the object model of HDF5 and would allow HDF5 developers or users to write their own plugins for accessing HDF5 data.

This user guide is for developers interested in developing a VOL plugin for the HDF5 library. The document is meant to be used in conjunction with the HDF5 reference manual. It is assumed that the reader has good knowledge of the VOL architecture obtained by reading the VOL architectural design document [1]. The document will cover the steps needed to create external and internal VOL plugins. Both ways have a lot of common steps and rules that will be covered first.

2 Creating a VOL Plugin

Each VOL plugin should be of type H5VL_class_t, Listing 1.

```
/* Class information for each VOL driver */
   typedef struct H5VL_class_t {
2
       unsigned int version;
3
       H5VL_class_value_t value;
4
       const char *name;
5
       herr_t (*initialize)(hid_t vipl_id);
6
       herr_t (*terminate)(hid_t vtpl_id);
       size_t fapl_size;
       void * (*fapl_copy)(const void *info);
       herr_t (*fapl_free)(void *info);
       /* Data Model */
12
       H5VL_attr_class_t
13
                                 attr_cls;
       H5VL_dataset_class_t
                                 dataset_cls;
14
       H5VL_datatype_class_t
                                 datatype_cls;
15
       H5VL_file_class_t
                                 file_cls;
16
17
       H5VL_group_class_t
                                 group_cls;
       H5VL_link_class_t
18
                                 link_cls;
       H5VL_object_class_t
                                 object_cls;
19
       /* Services */
21
       H5VL_async_class_t
                                 async_cls;
22
       herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);
23
   } H5VL_class_t;
24
```

Listing 1: VOL plugin class, H5VLpublic.h

The version field is the HDF5 VOL driver version.

The value field is a unique integer enum identifier that should be greater than 128 for external plugins and smaller than 128 for internal plugins. Setting it in the VOL structure is required.

The name field is a string that uniquely identifies the VOL plugin name. Setting it in the VOL structure is required. No two plugins with the same name can be registered with the library at the same time.

The initialize field is a function pointer to a routine that a plugin implements to set up or initialize access to the plugin. Implementing this function by the plugin is not required since some plugins do not require any set up to start accessing the plugin. In that case, the value of the function pointer should be set to NULL. Plugin specific variables that are required to be passed from users should be passed through the VOL initialize property list. Generic properties can be added to this property class for user-defined plugins that cannot modify the HDF5 library to add internal properties. For more information consult the property list reference manual pages.

The terminate field is a function pointer to a routine that a plugin implements to terminate or finalize access to the plugin. Implementing this function by the plugin is not required since some plugins do not require any termination phase to the plugin. In that case, the value of the function pointer should be set to NULL. Plugin specific variables that are required to be passed from users should be passed through the VOL terminate property list. Generic properties can be added to this property class for user-defined plugins that cannot modify the HDF5 library to add internal properties. For more information consult the property list reference manual pages.

The fapl_size field indicates the size required to store the info data that the plugin needs. That info data is passed when the plugin is selected for usage with the file access property list (fapl) function. It might be that the plugin defined does not require any information from the user, which means the size in this field will be zero. More information about the info data and the fapl selection routines follow later.

The fapl_copy field is a function pointer that is called when the plugin is selected with the fapl function. It allows the plugin to make a copy of the info data since the user might free it when closing the fapl. It is required if there is info data needed by the plugin.

The fapl_free field is a function pointer that is called to free the info data when the fapl close routine is called. It is required if there is info data needed by the plugin.

The rest of the fields in the H5VL_class_t struct are "subclasses" that define all the VOL function callbacks that are mapped to from the HDF5 API layer. Those subclasses are categorized into two categories, Data Model and Services. Data Model classes are those that provide functionality for accessing an HDF5 container and objects in that container as defined by the HDF5 data model. Service classes are those that provide services for users that are not related to the data model specifically. Asynchronous operations, for example, are a service that most plugins can implement, so we add a class for it in the VOL structure. If a service becomes generic enough and common among many plugins, a class for it should be added to the VOL structure. However, many plugins can/will provide services that are not shared by other plugins. A good way to support these services is through an optional callback in the VOL structure which can be a hook from the API to the plugin that provides those services, passing any necessary arguments needed without the HDF5 library having to worry about supporting that service. A similar API operation to allow users to use that service will be added. This API call would be similar to an "ioctl" call where any kind of operation can be supported and passed down to the plugin that has enough knowledge from the user to interpret the type of the operation. All classes and their defined callbacks will be detailed in the following sub-sections.

2.1 Mapping the API to the Callbacks

The callback interface defined for the VOL has to be general enough to handle all the HDF5 API operations that would access the file. Furthermore, it has to capture future additions to the HDF5 library with little to no changes to the callback interface. Changing the interface often whenever new features are added would be discouraging to plugin developers since that would mean reworking their VOL plugin structure. To remedy this issue, every callback will contain two parameters:

- A data transfer property list (DXPL) which allows that API to put some properties on for the plugins to retrieve if they have to for particular operations, without having to add arguments to the VOL callback function.
- A pointer to a request (void **req) to handle asynchronous operations if the HDF5 library adds support for them in future releases (beyond the 1.8 series). That pointer is set by the VOL plugin to a request object it creates to manage progress on that asynchronous operation. If the req is NULL, that means that the API operation is blocking and so the plugin would not execute the operation asynchronously. If the plugin does not support asynchronous operations, it needs not to worry about this field and leaves it unset.

In order to keep the number of the VOL object classes and callbacks concise and readable, it was decided not to have a one-to-one mapping between API operation and callbacks. Furthermore, to keep the callbacks themselves short and not cluttered with a lot of parameters, some of the parameters are passed in as properties in property lists included with the callback. The value of those properties can be retrieved by calling the public routine (or its private version if this is an internal plugin):

```
herr_t H5Pget(hid_t plist_id, const char *property_name, void *value);
```

The property names and value types will be detailed when describing each callback in their respective sections.

The HDF5 library provides several routines to access an object in the container. For example, to open an attribute on a group object, the user could use H5Aopen() and pass the group identifier directly where the attribute needs to be opened. Alternatively, the user could use H5Aopen_by_name() or H5Aopen_by_idx() to open the attribute, which provides a more flexible way of locating the attribute, whether by a starting object location and a path or an index type and traversal order. All those types of accesses usually map to one VOL callback with a parameter that indicates the access type. In the example of opening an attribute, the three API open routine will map to the same VOL open callback but with a different location parameter. The same applies to all types of routines that have multiple types of accesses. The location parameter is a structure defined in Listing 2.

```
/*
    * Structure to hold parameters for object locations.
2
    * either: BY_SELF, BY_NAME, BY_IDX, BY_ADDR, BY_REF
3
   typedef struct H5VL_loc_params_t {
6
       H5I_type_t obj_type; /* The object type of the location object */
       H5VL_loc_type_t type; /* The location type */
       union { /* parameters of the location */
           struct H5VL_loc_by_name loc_by_name;
10
           struct H5VL_loc_by_idx loc_by_idx;
11
12
           struct H5VL_loc_by_addr loc_by_addr;
           struct H5VL_loc_by_ref loc_by_ref;
13
       }loc_data;
14
   } H5VL_loc_params_t
15
16
17
    * Types for different ways that objects are located in an
18
    * HDF5 container.
19
20
21
   typedef enum H5VL_loc_type_t {
       /* starting location is the target object*/
22
       H5VL_OBJECT_BY_SELF,
23
24
       /* location defined by object and path in H5VL_loc_by_name */
25
       H5VL_OBJECT_BY_NAME,
26
27
       /* location defined by object, path, and index in H5VL_loc_by_idx */
28
       H5VL_OBJECT_BY_IDX,
29
30
       /* location defined by physical address in H5VL_loc_by_addr */
31
       H5VL_OBJECT_BY_ADDR,
32
33
       /* NOT USED */
34
       H5VL_OBJECT_BY_REF
35
   } H5VL_loc_type_t;
36
37
   struct H5VL_loc_by_name {
38
       const char *name; /* The path relative to the starting location */
39
       hid_t lapl_id; /* The link access property list */
40
   };
41
42
   struct H5VL_loc_by_idx {
43
       const char *name; /* The path relative to the starting location */
44
       H5_index_t idx_type; /* Type of index */
45
       H5_iter_order_t order; /* Index traversal order */
46
       hsize_t n; /* position in index */
47
       hid_t lapl_id; /* The link access property list */
48
   };
49
50
   struct H5VL_loc_by_addr {
51
       haddr_t addr; /* physical address of location */
52
53
54
   /* Not used for now */
55
   struct H5VL_loc_by_ref {
56
       H5R_type_t ref_type;
57
       const void *_ref;
58
       hid_t lapl_id;
59
   };
60
```

Listing 2: Structure to hold parameters for object locations, H5VLpublic.h

Other API routines that would make a one-to-one mapping difficult are:

- the Get operations that retrieve something from an object; for example a property list or a datatype of a dataset, etc.
- API routines are specific to each class of callbacks (attributes, files, etc...). Having a callback for each
 one would clutter the VOL callback structure and reduce user-friendliness.
- API routines that make sense to only implement in the native HDF5 file format and would not be
 possible to implement in other plugins. Adding a callback for those routines would be confusing to
 plugin developers.

To handle that large set of API routines, each class in the Data Model category has three generic callbacks, get, specific, and optional to handle the three set of API operations outline above respectively. The callbacks will have a valist argument to handle the different set of parameters that could be passed in. The get and specific callbacks also have an op_type that contain an enum of the type of operation that is requested to be performed. Using that type, the valist argument can be parsed. The optional callback is a free for all callback where anything from the API layer is passed in directly. This callback is used to support plugin specific operations in the API that other plugins should or would not know about. More information about types and the arguments for each type will be detailed in the corresponding class arguments.

2.2 The File Function Callbacks

The file API routines (H5F) allow HDF5 users to create and manage HDF5 containers. All the H5F API routines that modify the HDF5 container map to one of the file callback routines in this class that the plugin needs to implement, Listing 3.

Listing 3: File class for file API routines, H5VLpublic.h

The create callback in the file class should create a container and returns a pointer to the file structure created by the plugin containing information to access the container in future calls.

```
Signature:
```

```
void *(*create)(const char *name, unsigned flags, hid_t fcpl_id, hid_t fapl_id, hid_t dxpl_id, void **req);

Arguments:

name (IN): The name of the container to be created.

flags (IN): The creation flags of the container.

fcpl_id (IN): The file creation property list.

fapl_id (IN): The file access property list.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

The open callback in the file class should open a container and returns a pointer to the file structure created by the plugin containing information to access the container in future calls.

```
Signature:

void *(*open)(const char *name, unsigned flags, hid_t fapl_id, hid_t dxpl_id, void **req);
```

```
Arguments:

name (IN): The name of the container to open.

flags (IN): The open flags of the container.

fapl_id (IN): The file access property list.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

The get callback in the file class should retrieve information about the container as specified in the get_type parameter. It returns an herr_t indicating success or failure.

```
Signature:
       herr_t (*get)(void *obj, H5VL_file_get_t get_type, hid_t dxpl_id,
           void **req, va_list arguments);
   The get_type argument is an enum:
   /* types for all file get API routines */
   typedef enum H5VL_file_get_t {
2
       H5VL_FILE_GET_FAPL,
                             /* file access property list */
3
                              /* file creation property list */
       H5VL_FILE_GET_FCPL,
       H5VL_FILE_GET_INTENT, /* file intent
                                                            */
                              /* file name
                                                            */
       H5VL_FILE_GET_NAME,
       H5VL_FILE_GET_OBJ_COUNT, /* object count in file
                                                            */
       H5VL_FILE_GET_OBJ_IDS, /* object ids in file
                                                            */
       H5VL_OBJECT_GET_FILE /* retrieve or resurrect file of object */
   } H5VL_file_get_t;
10
   Arguments:
                  (IN): The container or object where information needs to be retrieved from.
    obj
    get_type
                  (IN): The type of the information to retrieve.
                  (IN): The data transfer property list.
    dxpl_id
                  (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
    req
    arguments
                  (IN/OUT): argument list containing parameters and output pointers for the get opera-
   The arguments argument contains a variable list of arguments depending on the get_type parameter.
   The following list shows the argument list, in order, for each type:
      • H5VL_FILE_GET_FCPL, to retrieve the file creation property list:
           1. hid_t *ret_id (OUT): buffer for the identifier of the file creation property list.
      • H5VL_FILE_GET_FAPL, to retrieve the file access property list:
           1. hid_t *ret_id (OUT): buffer for the identifier of the file access property list.
      • H5VL_FILE_GET_OBJ_COUNT:, to retrieve the object count in the container:
           1. unsigned types (IN): type of objects to look for.
           2. ssize_t *ret (OUT): buffer for the object count.
      • H5VL_FILE_GET_OBJ_IDS:, to retrieve object identifiers in the container:
           1. unsigned types (IN): type of objects to look for.
           2. size_t max_objs (IN): maximum number of objects to open.
           hid_t *oid_list (OUT): buffer for the object identifiers.
           4. ssize_t *ret (OUT): buffer for the object count.
      • H5VL_FILE_GET_INTENT, get access intent of the container:
           1. unsigned *ret (OUT): buffer for the intent value.
      • H5VL_FILE_GET_NAME, get container name an object belongs to:
```

```
1. H5I_type_t type (IN): the object type in obj.
    2. size_t size (IN): size of the buffer for the file name.
    3. char *name (OUT): buffer for the file name.
    4. ssize_t *ret (OUT): buffer for the entire size of the file name.
• H5VL_OBJECT_GET_FILE, get the container that the object belongs to:
    1. H5I_type_t type (IN): the object type in obj.
    2. void **ret (OUT): pointer to the file structure returned by the plugin.
```

The specific callback in the file class implements specific operations on HDF5 files as specified in the

```
specific_type parameter. It returns an herr_t indicating success or failure.
Signature:
    herr_t (*specific)(void *obj, H5VL_file_specific_t specific_type, hid_t dxpl_id, void **req,
        va_list arguments);
The specific_type argument is an enum:
/* types for file SPECIFIC callback */
typedef enum H5VL_file_specific_t {
    H5VL_FILE_FLUSH,
                                    /* Flush file */
    H5VL_FILE_IS_ACCESSIBLE,
                                    /* Check if a file is accessible */
    H5VL_FILE_MOUNT,
                                    /* Mount a file */
    H5VL_FILE_UNMOUNT
                                    /* Un-Mount a file */
} H5VL_file_specific_t;
Arguments:
                   (IN): The container or object where the operation needs to happen.
 obj
 specific_type
                   (IN): The type of the operation.
 dxpl_id
                   (IN): The data transfer property list.
                   (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
 arguments
                   (IN/OUT): argument list containing parameters and output pointers for the get opera-
                   tion.
The arguments argument contains a variable list of arguments depending on the specific_type param-
eter. The following list shows the argument list, in order, for each type:
   • H5VL_FILE_FLUSH, flushes all buffers associated with the container to disk:
        1. H5I_type_t obj_type (IN): The object type of obj on which the flush operation was called.
        2. H5F_scope_t scope (IN): The scope of the flushing action.
   • H5VL_FILE_IS_ACCESSIBLE, checks if a container is accessible using a specific file access property
      list:
        1. hid_t *fapl_id (IN): file access property list.
        2. char *name (IN): name of the container to check.
        3. htri_t *result (OUT): buffer for the result; 0 if no, 1 if yes.
```

- 1. H5I_type_t type (IN): the object type in obj.
- 2. char *name (IN): name of the group onto which the file specified by file is to be mounted.
- 3. void *file (IN): child file to be mounted.
- 4. hid_t *fmpl_id (IN): file mount property list.
- H5VL_FILE_UNMOUNT, un-mounts a file from the location object:
 - 1. H5I_type_t type (IN): the object type in obj.

```
2. char *name (IN): name of the mount point.
```

The optional callback in the file class implements plugin specific operations on an HDF5 container. It returns an herr_t indicating success or failure.

```
Arguments:

obj (IN): The container or object where the operation needs to happen.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.

arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each plugin should be able to parse the va_list arguments if it has plugin specific operations to implement and determine the type of the operation and the parameters through a predefined schema. For example, in the native plugin, the first argument in the va_list is the optional argument type enum defined as follows:

```
/* types for all file optional operations */
   typedef enum H5VL_file_optional_t {
       H5VL_FILE_CLEAR_ELINK_CACHE, /* Clear external link cache
       H5VL_FILE_GET_FILE_IMAGE, /* file image
                                                                     */
       H5VL_FILE_GET_FREE_SECTIONS, /* file free selections
                                                                     */
       H5VL_FILE_GET_FREE_SPACE, /* file freespace
                                                                     */
                                   /* file info
                                                                     */
       H5VL_FILE_GET_INFO,
       H5VL_FILE_GET_MDC_CONF,
                                   /* file metadata cache configuration */
       H5VL FILE GET MDC HR.
                                   /* file metadata cache hit rate
                                                                     */
       H5VL_FILE_GET_MDC_SIZE,
                                   /* file metadata cache size
                                                                     */
10
       H5VL_FILE_GET_SIZE,
                                   /* file size
                                                                     */
11
                                   /* file VFD handle
12
       H5VL_FILE_GET_VFD_HANDLE,
                                                                     */
       H5VL_FILE_REOPEN,
                                   /* reopen the file
                                                                     */
13
       H5VL_FILE_RESET_MDC_HIT_RATE, /* get metadata cache hit rate */
15
       H5VL_FILE_SET_MDC_CONFIG
                                  /* set metadata cache configuration */
   } H5VL_file_optional_t;
```

The remaining arguments are parsed depending on the optional operation type.

The close callback in the file class should terminate access to the file object and free all resources it was consuming, and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*close)(void *file, hid_t dxpl_id, void **req);

Arguments:
file (IN): Pointer to the file.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

2.3 The Group Function Callbacks

The group API routines (H5G) allow HDF5 users to create and manage HDF5 groups. All the H5G API routines that modify the HDF5 container map to one of the group callback routines in this class that the plugin needs to implement, Listing 4.

Listing 4: Structure for group callback routines, H5VLpublic.h

The create callback in the group class creates a group object in the container of the location object and returns a pointer to the group structure containing information to access the group in future calls.

```
Signature:
    void *(*create)(void *obj, H5VL_loc_params_t loc_params, const char *name, hid_t gcpl_id,
        hid_t gapl_id, hid_t dxpl_id, void **req);
Arguments:
               (IN): Pointer to an object where the group needs to be created or where the look-up of
 obj
               the target object needs to start.
               (IN): The location parameters as explained in Section 2.1. The type can be only
 loc_params
               H5VL_OBJECT_BY_SELF in this callback.
               (IN): The name of the group to be created.
 name
               (IN): The group creation property list. It contains all the group creation properties in
 dcpl_id
               addition to the link creation property list of the create operation (an hid_t) that can be
               retrieved with the property H5VL_GRP_LCPL_ID.
               (IN): The group access property list.
 gapl_id
               (IN): The data transfer property list.
 dxpl_id
 req
               (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

The open callback in the group class opens a group object in the container of the location object and returns a pointer to the group structure containing information to access the group in future calls.

```
Signature:
   void *(*open)(void *obj, H5VL_loc_params_t loc_params,
       const char*name, hid_t gapl_id, hid_t dxpl_id, void **req);
Arguments:
               (IN): Pointer to an object where the group needs to be opened or where the look-up of
 obj
               the target object needs to start.
               (IN): The location parameters as explained in Section 2.1. The type can be only
 loc_params
               H5VL_OBJECT_BY_SELF in this callback.
               (IN): The name of the group to be opened.
 name
               (IN): The group access property list.
 dapl_id
               (IN): The data transfer property list.
 dxpl_id
               (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

The get callback in the group class retrieves information about the group as specified in the get_type parameter. It returns an herr_t indicating success or failure.

```
Signature:

herr_t (*get)(void *obj, H5VL_group_get_t get_type, hid_t dxpl_id, void **req, va_list arguments);

The get_type argument is an enum:
```

```
/* types for all group get API routines */
typedef enum H5VL_group_get_t {
   H5VL_GROUP_GET_GCPL,
                            /*group creation property list */
   H5VL_GROUP_GET_INFO
                            /*group info
} H5VL_group_get_t;
Arguments:
              (IN): The group object where information needs to be retrieved from.
 obj
 get_type
              (IN): The type of the information to retrieve.
 dxpl_id
              (IN): The data transfer property list.
              (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
              (IN/OUT): argument list containing parameters and output pointers for the get opera-
 arguments
              tion.
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_GROUP_GET_GCPL, to retrieve the group creation property list of the group specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the group creation property list.
- H5VL_GROUP_GET_INFO, to retrieve the attribute info:
 - 1. H5VL_loc_params_t loc_params (IN): The location parameters explained in Section 2.1.
 - 2. H5G_info_t *ginfo (OUT): info structure to fill the group info in.

The specific callback in the group class currently does not require any functionality to be implemented and should be left as NULL.

The optional callback in the group class implements plugin specific operations on an HDF5 group. It returns an herr_t indicating success or failure.

```
herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
obj (IN): The container or object where the operation needs to happen.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each plugin should be able to parse the valist arguments if it has plugin specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

The close callback in the group class terminates access to the group object and frees all resources it was consuming, and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*close)(void *group, hid_t dxpl_id, void **req);

Arguments:
group (IN): Pointer to the group object.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

2.4 The Dataset Function Callbacks

The dataset API routines (H5D) allow HDF5 users to create and manage HDF5 datasets. All the H5D API routines that modify the HDF5 container map to one of the dataset callback routines in this class that the plugin needs to implement, Listing 5.

```
typedef struct H5VL_dataset_class_t {
       void *(*create)(void *obj, H5VL_loc_params_t loc_params, const char *name, hid_t dcpl_id,
           hid_t dapl_id, hid_t dxpl_id, void **req);
       void *(*open)(void *obj, H5VL_loc_params_t loc_params, const char *name, hid_t dapl_id, hid_t
           dxpl_id, void **req);
       herr_t (*read)(void *dset, hid_t mem_type_id, hid_t mem_space_id, hid_t file_space_id, hid_t
           xfer_plist_id, void * buf, void **req);
       herr_t (*write)(void *dset, hid_t mem_type_id, hid_t mem_space_id, hid_t file_space_id, hid_t
           xfer_plist_id, const void * buf, void **req);
       herr_t (*get)(void *obj, H5VL_dataset_get_t get_type, hid_t dxpl_id, void **req, va_list
           arguments);
       herr_t (*specific)(void *obj, H5VL_dataset_specific_t specific_type, hid_t dxpl_id, void
           **req, va_list arguments);
       herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);
       herr_t (*close) (void *dset, hid_t dxpl_id, void **req);
   } H5VL_dataset_class_t;
10
```

Listing 5: Structure for dataset callback routines, H5VLpublic.h

The create callback in the dataset class creates a dataset object in the container of the location object and returns a pointer to the dataset structure containing information to access the dataset in future calls.

```
Signature:
   void *(*create)(void *obj, H5VL_loc_params_t loc_params, const char *name, hid_t dcpl_id,
        hid_t dapl_id, hid_t dxpl_id, void **req);
Arguments:
               (IN): Pointer to an object where the dataset needs to be created or where the look-up of
 obj
               the target object needs to start.
               (IN): The location parameters as explained in Section 2.1. The type can be only
 loc_params
               H5VL_OBJECT_BY_SELF in this callback.
               (IN): The name of the dataset to be created.
 name
 dcpl_id
               (IN): The dataset creation property list. It contains all the dataset creation properties in
               addition to the dataset datatype (an hid_t), dataspace (an hid_t), and the link creation
               property list of the create operation (an hid_t) that can be retrieved with the properties,
               H5VL_DSET_TYPE_ID, H5VL_DSET_SPACE_ID, and H5VL_DSET_LCPL_ID respectively.
               (IN): The dataset access property list.
 dapl_id
               (IN): The data transfer property list.
 dxpl_id
               (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
```

The open callback in the dataset class opens a dataset object in the container of the location object and returns a pointer to the dataset structure containing information to access the dataset in future calls.

```
Signature:
   void *(*open)(void *obj, H5VL_loc_params_t loc_params, const char *name, hid_t dapl_id,
        hid_t dxpl_id, void **req);
Arguments:
               (IN): Pointer to an object where the dataset needs to be opened or where the look-up of
 obj
               the target object needs to start.
               (IN): The location parameters as explained in Section 2.1. The type can be only
 loc_params
               H5VL_OBJECT_BY_SELF in this callback.
               (IN): The name of the dataset to be opened.
 name
               (IN): The dataset access property list.
 dapl_id
               (IN): The data transfer property list.
 dxpl_id
 req
               (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

The read callback in the dataset class reads data from the dataset object and returns an herr_t indicating success or failure.

```
Signature:
   herr_t (*read)(void *dset, hid_t mem_type_id, hid_t mem_space_id,
       hid_t file_space_id, hid_t dxpl_id, void *buf, void **req);
Arguments:
 dset
                  (IN): Pointer to the dataset object.
                  (IN): The memory datatype of the data.
 mem_type_id
                  (IN): The memory dataspace selection.
 mem_space_id
                  (IN): The file dataspace selection.
 file_space_id
                  (IN): The data transfer property list.
 dxpl_id
 buf
                  (OUT): Data buffer to be read into.
                  (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
```

The write callback in the dataset class writes data to the dataset object and returns an herr_t indicating success or failure.

```
Signature:
   herr_t (*write)(void *dset, hid_t mem_type_id, hid_t mem_space_id,
       hid_t file_space_id, hid_t dxpl_id, const void * buf, void **req);
Arguments:
 dset
                  (IN): Pointer to the dataset object.
 mem_type_id
                  (IN): The memory datatype of the data.
                  (IN): The memory dataspace selection.
 mem_space_id
 file_space_id
                  (IN): The file dataspace selection.
                  (IN): The data transfer property list.
 dxpl_id
 buf
                  (IN): Data buffer to be written from.
                  (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
```

The get callback in the dataset class retrieves information about the dataset as specified in the get_type parameter.It returns an herr_t indicating success or failure.

```
Signature:
    herr_t (*get)(void *dset, H5VL_dataset_get_t get_type,
       hid_t dxpl_id, void **req, va_list arguments);
The get_type argument is an enum:
/* types for dataset GET callback */
typedef enum H5VL_dataset_get_t {
    H5VL_DATASET_GET_DAPL,
                                         /* access property list */
    H5VL_DATASET_GET_DCPL,
                                         /* creation property list */
    H5VL_DATASET_GET_OFFSET,
                                         /* offset */
    H5VL_DATASET_GET_SPACE,
                                         /* dataspace */
    H5VL_DATASET_GET_SPACE_STATUS,
                                         /* space status */
    H5VL_DATASET_GET_STORAGE_SIZE,
                                         /* storage size */
    H5VL_DATASET_GET_TYPE
                                         /* datatype */
} H5VL_dataset_get_t;
Arguments:
               (IN): The dataset object where information needs to be retrieved from.
 dset
               (IN): The type of the information to retrieve.
 get_type
 dxpl_id
               (IN): The data transfer property list.
               (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
               (IN/OUT): argument list containing parameters and output pointers for the get opera-
 arguments
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_DATASET_GET_DAPL, to retrieve the dataset access property list of the dataset specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the dataset access property list.
- H5VL_DATASET_GET_DCPL, to retrieve the dataset creation property list of the dataset specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the dataset creation property list.
- H5VL_DATASET_GET_OFFSET, to retrieve the offset of the dataset specified in obj in the container:
 - 1. haddr_t *ret (OUT): buffer for the offset of the dataset in the container.
- H5VL_DATASET_GET_SPACE, to retrieve the dataspace of the dataset specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the dataset dataspace.
- H5VL_DATASET_GET_SPACE_STATUS, to retrieve the information whether space has been allocated for the dataset:
 - 1. H5D_space_status_t *allocation (OUT): buffer for the space status.
- H5VL_DATASET_GET_STORAGE_SIZE, to retrieve the storage size of the dataset specified in obj:
 - 1. hsize_t *ret (OUT): buffer for the storage size of the dataset in the container.
- H5VL_DATASET_GET_TYPE, to retrieve the datatype of the dataset specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the dataset datatype.

The specific callback in the dataset class implements specific operations on HDF5 datasets as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

```
Signature:
   herr_t (*specific)(void *obj, H5VL_file_specific_t specific_type, hid_t dxpl_id, void **req,
        va_list arguments);
The specific_type argument is an enum:
/* types for dataset SPECFIC callback */
typedef enum H5VL_dataset_specific_t {
   H5VL_DATASET_SET_EXTENT
                                   /* H5Dset_extent */
} H5VL_dataset_specific_t;
Arguments:
                  (IN): The dset where the operation needs to happen.
 obj
                  (IN): The type of the operation.
 specific_type
                  (IN): The data transfer property list.
 dxpl_id
                  (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
                  (IN/OUT): argument list containing parameters and output pointers for the get opera-
 arguments
                  tion.
```

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_DATASET_SET_EXTENT, changes the extent of the dataset dimensions:
 - 1. hsize_t size (IN): Array containing the new magnitude of each dimension of the dataset.

The optional callback in the dataset class implements plugin specific operations on an HDF5 dataset. It returns an herr_t indicating success or failure.

```
Signature:

herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
```

```
obj (IN): The container or object where the operation needs to happen.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.

arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each plugin should be able to parse the va_list arguments if it has plugin specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

The close callback in the dataset class terminates access to the dataset object and free all resources it was consuming and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*close)(void *dset, hid_t dxpl_id, void **req);

Arguments:
dset (IN): Pointer to the dataset object.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

2.5 The Attribute Function Callbacks

The attribute API routines (H5A) allow HDF5 users to create and manage HDF5 attributes. All the H5A API routines that modify the HDF5 container map to one of the attribute callback routines in this class that the plugin needs to implement, Listing 6.

Listing 6: Structure for attribute callback routines, H5VLpublic.h

The create callback in the attribute class creates an attribute object in the container of the location object and returns a pointer to the attribute structure containing information to access the attribute in future calls.

```
Signature:

void *(*create)(void *obj, H5VL_loc_params_t loc_params,

const char *attr_name, hid_t acpl_id, hid_t aapl_id,

hid_t dxpl_id, void **req);

Arguments:
```

obj	(IN): Pointer to an object where the attribute needs to be created or where the look-up
	of the target object needs to start.
loc_params	(IN): The location parameters as explained in Section 2.1.
$attr_name$	(IN): The name of the attribute to be created.
$\mathtt{acpl_id}$	(IN): The attribute creation property list. It contains all the attribute creation properties
	in addition to the attribute datatype (an hid_t) and dataspace (an hid_t) that can be
	retrieved with the properties, <code>H5VL_ATTR_TYPE_ID</code> and <code>H5VL_ATTR_SPACE_ID</code> .
$\mathtt{aapl}_{\mathtt{-}}\mathtt{id}$	(IN): The attribute access property list.
$\mathtt{dxpl}_{\mathtt{-}}\mathtt{id}$	(IN): The data transfer property list.
req	(IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.

The open callback in the attribute class opens an attribute object in the container of the location object and returns a pointer to the attribute structure containing information to access the attribute in future calls.

```
Signature:
   void *(*open)(void *obj, H5VL_loc_params_t loc_params,
       const char *attr_name, hid_t aapl_id, hid_t dxpl_id, void **req);
Arguments:
 obj
               (IN): Pointer to an object where the attribute needs to be opened or where the look-up
               of the target object needs to start.
               (IN): The location parameters as explained in Section 2.1.
 loc_params
               (IN): The name of the attribute to be opened.
 attr\_name
               (IN): The attribute access property list.
 aapl_id
 dxpl_id
               (IN): The data transfer property list.
               (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
```

The read callback in the attribute class reads data from the attribute object and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*read)(void *attr, hid_t mem_type_id, void *buf,
    hid_t dxpl_id, void **req);

Arguments:
attr (IN): Pointer to the attribute object.
mem_type_id (IN): The memory datatype of the attribute.
buf (OUT): Data buffer to be read into.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

The write callback in the attribute class writes data to the attribute object and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*write)(void *attr, hid_t mem_type_id, const void *buf,
hid_t dxpl_id, void **req);

Arguments:
attr (IN): Pointer to the attribute object.
mem_type_id (IN): The memory datatype of the attribute.
buf (IN): Data buffer to be written.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

The get callback in the attribute class retrieves information about the attribute as specified in the get_type parameter.It returns an herr_t indicating success or failure.

```
Signature:
      herr_t (*get)(void *obj, H5VL_attr_get_t get_type, hid_t dxpl_id,
          void **req, va_list arguments);
  The get_type argument is an enum:
  /* types for attribute GET callback */
  typedef enum H5VL_attr_get_t {
2
      H5VL_ATTR_GET_ACPL,
                                      /* creation property list */
      H5VL_ATTR_GET_INFO,
                                      /* info */
      H5VL_ATTR_GET_NAME,
                                      /* access property list */
5
      H5VL_ATTR_GET_SPACE,
                                     /* dataspace */
6
      H5VL_ATTR_GET_STORAGE_SIZE,
                                     /* storage size */
      H5VL_ATTR_GET_TYPE
                                       /* datatype */
  } H5VL_attr_get_t;
  Arguments:
                 (IN): An attribute or location object where information needs to be retrieved from.
    attr
    get_type
                 (IN): The type of the information to retrieve.
                 (IN): The data transfer property list.
   dxpl_id
                 (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
   req
                 (IN/OUT): argument list containing parameters and output pointers for the get opera-
    arguments
                 tion.
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_ATTR_GET_ACPL, to retrieve the attribute creation property list of the attribute specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the attribute creation property list.
- H5VL_ATTR_GET_INFO, to retrieve the attribute info:
 - 1. H5VL_loc_params_t loc_params (IN): The location parameters explained in Section 2.1.
 - 2. H5A_info_t *ainfo (OUT): info structure to fill the attribute info in.
- H5VL_ATTR_GET_NAME, to retrieve an attribute name on a particular object specified in obj:
 - 1. H5VL_loc_params_t loc_params (IN): The location parameters explained in Section 2.1. The type could be either H5VL_OBJECT_BY_SELF meaning obj is the attribute, or H5VL_OBJECT_BY_IDX meaning the attribute to retrieve the name for should be looked up using the index information on the object in obj and the index information in loc_params.
 - 2. size_t buf_size (IN): the size of the buffer to store the name in.
 - 3. void *buf (OUT): Buffer to store the name in.
 - 4. ssize_t *ret_val (OUT): return the actual size needed to store the fill attribute name.
- H5VL_ATTR_GET_SPACE, to retrieve the dataspace of the attribute specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the attribute dataspace.
- H5VL_ATTR_GET_STORAGE_SIZE, to retrieve the storage size of the attribute specified in obj:
 - 1. hsize_t *ret (OUT): buffer for the storage size of the attribute in the container.
- H5VL_ATTR_GET_TYPE, to retrieve the datatype of the attribute specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the attribute datatype.

The specific callback in the attribute class implements specific operations on HDF5 attributes as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

```
Signature:

herr_t (*specific)(void *obj, H5VL_loc_params_t loc_params, H5VL_attr_specific_t
```

```
specific_type, hid_t dxpl_id, void **req, va_list arguments);
  The specific_type argument is an enum:
  /* types for attribute SPECFIC callback */
  typedef enum H5VL_attr_specific_t {
                                      /* H5Adelete(_by_name/idx) */
      H5VL_ATTR_DELETE,
      H5VL_ATTR_EXISTS,
                                      /* H5Aexists(_by_name) */
                                      /* H5Aiterate(_by_name) */
      H5VL_ATTR_ITER,
5
      H5VL_ATTR_RENAME
                                      /* H5Arename(_by_name) */
6
  } H5VL_attr_specific_t;
  Arguments:
                     (IN): The location object where the operation needs to happen.
    obj
                     (IN): The location parameters as explained in Section 2.1.
    loc_params
                     (IN): The type of the operation.
    specific_type
                     (IN): The data transfer property list.
    dxpl_id
                     (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
    req
    arguments
                     (IN/OUT): argument list containing parameters and output pointers for the get opera-
```

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_ATTR_DELETE, to delete an attribute on an object:
 - 1. char *attr_name (IN): the name of the attribute to delete.
- H5VL_ATTR_EXISTS, to check if an attribute exists on a particular object specified in obj:
 - 1. H5VL_loc_params_t loc_params (IN): The location parameters explained in Section 2.1.
 - 2. char *attr_name (IN): the attribute name to check.
 - 3. htri_t *ret (OUT): existence result, 0 if false, 1 if true.
- H5VL_ATTR_ITER, to iterate over all attributes of an object and call a user-specified callback on each one:
 - 1. H5_index_t idx_type (IN): Type of index.
 - 2. H5_iter_order_t order (IN): Order in which to iterate over index.
 - 3. hsize_t *idx (IN/OUT): Initial and return offset within index.
 - 4. H5A_operator2_t op (IN): User-defined function to pass each attribute to.
 - 5. void *op_data (IN/OUT): User data to pass through to and to be returned by iterator operator function.
- H5VL_ATTR_RENAME, to rename an attribute on an object:
 - 1. char *old_name (IN): the original name of the attribute.
 - 2. char *new_name (IN): the new name to assign for the attribute.

The optional callback in the attribute class implements plugin specific operations on an HDF5 attribute. It returns an herr_t indicating success or failure.

```
Signature:

herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);
```

```
Arguments:
obj (IN): The container or object where the operation needs to happen.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each plugin should be able to parse the va_list arguments if it has plugin specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

The close callback in the attribute class terminates access to the attribute object and free all resources it was consuming, and returns an herr_t indicating success or failure.

```
Arguments:

attr (IN): Pointer to the attribute object.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

2.6 The Named Datatype Function Callbacks

The HDF5 datatype routines (H5T) allow users to create and manage HDF5 datatypes. Those routines are divided into two categories. One that operates on all types of datatypes but do not modify the contents of the container (all in memory), and others that operate on named datatypes by accessing the container. When a user creates an HDF5 datatype, it is still an object in memory space (transient datatype) that has not been added to the HDF5 containers. Only when a user commits the HDF5 datatype, it becomes persistent in the container. Those are called named/committed datatypes. The transient H5T routines should work on named datatypes nevertheless.

All the H5T API routines that modify the HDF5 container map to one of the named datatype callback routines in this class that the plugin needs to implement, Listing 7.

```
typedef struct H5VL_datatype_class_t {
    void *(*commit)(void *obj, H5VL_loc_params_t loc_params, const char *name, hid_t type_id,
        hid_t lcpl_id, hid_t tcpl_id, hid_t tapl_id, hid_t dxpl_id, void **req);

void *(*open)(void *obj, H5VL_loc_params_t loc_params, const char * name, hid_t tapl_id, hid_t
        dxpl_id, void **req);

herr_t (*get) (void *obj, H5VL_datatype_get_t get_type, hid_t dxpl_id, void **req, va_list
        arguments);

herr_t (*specific)(void *obj, H5VL_datatype_specific_t specific_type, hid_t dxpl_id, void
        **req, va_list arguments);

herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

herr_t (*close) (void *dt, hid_t dxpl_id, void **req);

} H5VL_datatype_class_t;
```

Listing 7: Structure for datatype callback routines, H5VLpublic.h

The commit callback in the named datatype class creates a datatype object in the container of the location object and returns a pointer to the datatype structure containing information to access the datatype in future calls.

```
Signature:

void *(*commit)(void *obj, H5VL_loc_params_t loc_params,

const char *name, hid_t type_id, hid_t lcpl_id, hid_t tcpl_id,

hid_t tapl_id, hid_t dxpl_id, void **req);

Arguments:
```

```
obj
              (IN): Pointer to an object where the datatype needs to be committed or where the look-up
              of the target object needs to start.
              (IN): The location parameters as explained in Section 2.1. In this call, the location type
loc_params
              is always H5VL_OBJECT_BY_SELF.
              (IN): The name of the datatype to be created.
name
              (IN): The transient datatype identifier to be committed.
type_id
lcpl_id
              (IN): The link creation property list.
tcpl_id
              (IN): The datatype creation property list.
tapl_id
              (IN): The datatype access property list.
dxpl_id
              (IN): The data transfer property list.
              (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
req
```

The open callback in the named datatype class opens a previously committed datatype object in the container of the location object and returns a pointer to the datatype structure containing information to access the datatype in future calls.

```
Signature:
   void *(*open) (void *obj, H5VL_loc_params_t loc_params,
       const char * name, hid_t tapl_id, hid_t dxpl_id, void **req);
Arguments:
 obj
               (IN): Pointer to an object where the datatype needs to be opened or where the look-up
               of the target object needs to start.
               (IN): The location parameters as explained in Section 2.1. In this call, the location type
 loc_params
               is always H5VL_OBJECT_BY_SELF.
               (IN): The name of the datatype to be opened.
 name
               (IN): The datatype access property list.
 tapl_id
 dxpl_id
               (IN): The data transfer property list.
               (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
```

The get_binary callback in the named datatype class serializes the original transient HDF5 datatype that was committed, or returns the size that is required for it be serialized if the passed in buffer is NULL. The HDF5 library provides two functions to encode and decode datatypes in their transient form, H5Tencode() and H5Tdecode(). When a datatype is committed, the plugin is required to keep the serialized form of the transient datatype stored somewhere in the container (which is usually the case anyway when committing a named datatype), so it can be retrieved with this call. This is needed to generate the higher level HDF5 datatype identifier that allows all the H5T "transient" routines to work properly on the named datatype.

```
ssize_t (*get_binary)(void *obj, unsigned char *buf, size_t size,
hid_t dxpl_id, void **req);

Arguments:
obj (IN): Pointer to the named datatype object.
buf (OUT): Buffer to out the binary form of the datatype in.
size (IN): The size of the buffer passed in (0 if NULL).
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

The get callback in the named datatype class retrieves information about the named datatype as specified in the get_type parameter.It returns an herr_t indicating success or failure.

```
Signature:

herr_t (*get) (void *obj, H5VL_datatype_get_t get_type,

hid_t dxpl_id, void **req, va_list arguments);
```

```
The get_type argument is an enum:
   /* types for datatype GET callback */
1
   typedef enum H5VL_datatype_get_t {
2
      H5VL_DATATYPE_GET_BINARY,
                                            /* get serialized form of transient type */
3
      H5VL_DATATYPE_GET_TCPL
                                            /* datatype creation property list */
   } H5VL_datatype_get_t;
   Arguments:
                 (IN): The named datatype to retrieve information from.
    obj
                 (IN): The type of the information to retrieve.
    get_type
    dxpl_id
                 (IN): The data transfer property list.
                 (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
    req
    arguments
                 (IN/OUT): argument list containing parameters and output pointers for the get opera-
                 tion.
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_DATATYPE_GET_BINARY, to retrieve the serialized original transient HDF5 datatype that was committed, or return the size that is required for it be serialized if the passed in buffer is NULL. The HDF5 library provides two functions to encode and decode datatypes in their transient form, H5Tencode() and H5Tdecode(). When a datatype is committed, the plugin is required to keep the serialized form of the transient datatype stored somewhere in the container (which is usually the case anyway when committing a named datatype), so it can be retrieved with this call. This is needed to generate the higher level HDF5 datatype identifier that allows all the H5T "transient" routines to work properly on the named datatype.
 - 1. ssize_t *nalloc (OUT): buffer to store the total size of the serialized datatype.
 - 2. void *buf (OUT): buffer to store the serialized datatype.
 - 3. size_t size (IN): size of the passed in buffer.
- H5VL_DATATYPE_GET_TCPL, to retrieve the datatype creation property list:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the type creation property list.

The specific callback in the datatype class currently does not require any functionality to be implemented and should be left as NULL.

The optional callback in the datatype class implements plugin specific operations on an HDF5 datatype. It returns an herr_t indicating success or failure.

```
Arguments:

obj (IN): The container or object where the operation needs to happen.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.

arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each plugin should be able to parse the valist arguments if it has plugin specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

The close callback in the named datatype class terminates access to the datatype object and free all resources it was consuming and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*close) (void *dt, hid_t dxpl_id, void **req);
```

```
Arguments:
dt (IN): Pointer to the datatype object.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
```

2.7 The Object Function Callbacks

The object API routines (H5O) allow HDF5 users to manage HDF5 group, dataset, and named datatype objects. All the H5O API routines that modify the HDF5 container map to one of the object callback routines in this class that the plugin needs to implement, Listing 8.

Listing 8: Structure for object callback routines, H5VLpublic.h

The open callback in the object class opens the object in the container of the location object and returns a pointer to the object structure containing information to access the object in future calls.

```
Signature:
   void *(*open)(void *obj, H5VL_loc_params_t loc_params,
       H5I_type_t *opened_type, hid_t dxpl_id, void **req);
Arguments:
 obj
                (IN): Pointer to a file or group where the object needs to be opened or where the look-up
                of the target object needs to start.
 loc_params
                (IN): The location parameters as explained in Section 2.1.
 opened_type
                (OUT): buffer to return the type of the object opened (H5I_GROUP or H5I_DATASET or
                H5I_DATATYPE).
                (IN): The data transfer property list.
 dxpl_id
                (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
```

The copy callback in the object class copies the object from the source object to the destination object. It returns an herr_t indicating success or failure.

```
src_obi
               (IN): Pointer to location of the source object to be copied.
               (IN): The location parameters as explained in Section 2.1. The type should only be
loc_params1
               H5VL_OBJECT_BY_SELF for this callback.
               (IN): Name of the source object to be copied.
src_name
dst_obj
               (IN): Pointer to location of the destination object.
               (IN): The location parameters as explained in Section 2.1. The type should only be
loc_params2
               H5VL_OBJECT_BY_SELF for this callback.
dst_name
               (IN): Name to be assigned to the new copy.
ocpypl_id
               (IN): The object copy property list.
               (IN): The link creation property list.
lcpl_id
               (IN): The data transfer property list.
dxpl_id
               (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
req
```

The get callback in the object class retrieves information about the object as specified in the get_type parameter.It returns an herr_t indicating success or failure.

```
Signature:
   herr_t (*get)(void *obj, H5VL_loc_params_t loc_params,
       H5VL_object_get_t get_type, hid_t dxpl_id,
       void **req, va_list arguments);
The get_type argument is an enum:
/* type for object GET callback */
typedef enum H5VL_object_get_t {
   H5VL_REF_GET_NAME,
                                    /* object name
   H5VL_REF_GET_REGION,
                                    /* dataspace of region
   H5VL_REF_GET_TYPE
                                    /* type of object
} H5VL_object_get_t;
Arguments:
               (IN): A location object where information needs to be retrieved from.
 obj
               (IN): The location parameters as explained in Section 2.1.
 loc_params
               (IN): The type of the information to retrieve.
 get_type
 dxpl_id
               (IN): The data transfer property list.
               (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
               (IN/OUT): argument list containing parameters and output pointers for the get opera-
 arguments
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_REF_GET_NAME, to retrieve a name for a referenced object:
 - 1. ssize_t *ret (OUT): buffer to return the length of the name.
 - 2. char* name (OUT): buffer to copy the name into.
 - 3. size_t size (IN): size of the buffer name, if 0, return only the buffer size needed.
 - 4. H5R_type_t ret_type (IN): type of region reference to query.
 - 5. void *ref (IN): the region reference to query.
- H5VL_REF_GET_REGION, to retrieve a region reference contained in obj:
 - 1. hid_t *ret_id (OUT): buffer for the dataspace created from the region reference.
 - 2. H5R_type_t ret_type (IN): type of region reference (should be H5R_DATASET_REGION).
 - 3. void *ref (IN): the region reference to open.
- H5VL_REF_GET_TYPE, to retrieve object type a reference points to:
 - 1. ${\tt H50_type_t}$ *type (OUT): buffer to return the object type.
 - 2. H5R_type_t ret_type (IN): type of region reference to query.

3. void *ref (IN): the region reference to query.

The specific callback in the object class implements specific operations on HDF5 objects as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

```
Signature:
       herr_t (*specific)(void *obj, H5VL_loc_params_t loc_params, H5VL_object_specific_t
            specific_type, hid_t dxpl_id, void **req, va_list arguments);
The specific_type argument is an enum:
/* types for object SPECIFIC callback */
typedef enum H5VL_object_specific_t {
   H5VL_OBJECT_CHANGE_REF_COUNT, /* H5Oincr/decr_refcount
   H5VL_OBJECT_EXISTS,
                                    /* H50exists_by_name
                                    /* H5Ovisit(_by_name)
   H5VL_OBJECT_VISIT,
                                    /* H5Rcreate
   H5VL_REF_CREATE
} H5VL_object_specific_t;
Arguments:
                   (IN): The location object where the operation needs to happen.
 obj
                   (IN): The location parameters as explained in Section 2.1.
 loc_params
 specific_type
                  (IN): The type of the operation.
                  (IN): The data transfer property list.
 dxpl_id
                   (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
 arguments
                   (IN/OUT): argument list containing parameters and output pointers for the get opera-
                  tion.
```

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_OBJECT_CHANGE_REF_COUNT, to update the reference count for the object in obj:
 - 1. int ref_count (IN): reference count to set on the object.
- H5VL_OBJECT_EXISTS, to check if an object with name specified in loc_params (type H5VL_OBJECT_BY_NAME) exists:
 - 1. htri_t *ret (OUT): existence result, 0 if false, 1 if true.
- H5VL_OBJECT_VISIT, to iterate over all objects starting at the location provided and call a user-specified callback on each one:
 - 1. H5_index_t idx_type (IN): Type of index.
 - 2. H5_iter_order_t order (IN): Order in which to iterate over index.
 - 3. H50_iterate_t op (IN): User-defined function to pass each object to.
 - 4. void *op_data (IN/OUT): User data to pass through to and to be returned by iterator operator function.
- H5VL_REF_CREATE, to create a reference of an object under the location object obj:
 - 1. void *ref (OUT): the region reference created.
 - 2. char* name (IN): Name of the object at the location obj.
 - 3. H5R_type_t ret_type (IN): type of region reference to create.
 - 4. hid_t* space_id (IN): Dataspace identifier with selection. Used only for dataset region references; passed as -1 if reference is an object reference, i.e., of type H5R_OBJECT.

The optional callback in the object class implements plugin specific operations on an HDF5 object. It returns an herr_t indicating success or failure.

```
herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
obj (IN): The container or object where the operation needs to happen.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each plugin should be able to parse the va_list arguments if it has plugin specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

2.8 The Link Function Callbacks

The link API routines (H5L) allow HDF5 users to create and manage HDF5 links. All the H5L API routines that modify the HDF5 container map to one of the link callback routines in this class that the plugin needs to implement, Listing 9.

Listing 9: Structure for link callback routines, H5VLpublic.h

The create callback in the group class creates a hard, soft, external, or user-defined links in the container. It returns an herr_t indicating success or failure.

<pre>create_type obj loc_params lcpl_id</pre>	 (IN): type of the link to be created. (IN): Pointer to an object where the link needs to be created from. (IN): The location parameters as explained in Section 2.1 for the source object. (IN): The link creation property list. It contains all the link creation properties in addition to other API parameters depending on the creation type, which will be detailed
	next.
$lapl_id$	(IN): The link access property list.
$\mathtt{dxpl_id}$	(IN): The data transfer property list.
req	(IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.

As mentioned in the argument list, the lcpl_id contains the parameters for the link creation operation depending on the creation type:

- H5VL_LINK_CREATE_HARD contains two properties:
 - 1. H5VL_LINK_TARGET (with type void*): The target object where the hard link needs to be created to.
 - 2. H5VL_LINK_TARGET_LOC_PARAMS (with type H5VL_loc_params_t): The location parameters as explained in Section 2.1 for the target object.
- H5VL_LINK_CREATE_SOFT contains one property:
 - 1. H5VL_LINK_TARGET_NAME (with type char*): The target link where the soft link should point to.
- H5VL_LINK_CREATE_UD contains two properties:
 - 1. H5VL_LINK_TYPE (with type H5L_type_t): The user defined link class. H5L_TYPE_EXTERNAL suggests an external link is to be created.
 - 2. H5VL_LINK_UDATA (with type void*): User supplied link information (contains the external link buffer for external links).
 - 3. H5VL_LINK_UDATA_SIZE (with type size_t): size of the udata buffer.

The move callback in the link class moves a link within the HDF5 container. It returns an herr_t indicating success or failure.

```
Signature:
   herr_t (*move)(void *src_obj, H5VL_loc_params_t loc_params1, void *dst_obj,
        H5VL_loc_params_t loc_params2, hid_t lcpl, hid_t lapl, hid_t dxpl_id, void **req);
Arguments:
                 (IN): original/source object or file.
 src_obj
                (IN): The location parameters for the source object as explained in Section 2.1. The type
 loc_params1
                 can be only H5VL_OBJECT_BY_NAME in this callback.
 dst_obj
                 (IN): destination object or file.
 loc\_params1
                (IN): The location parameters for the destination object as explained in Section 2.1. The
                 type can be only H5VL_OBJECT_BY_NAME in this callback.
 lcpl_id
                 (IN): The link creation property list.
 lapl_id
                 (IN): The link access property list.
 dxpl_id
                 (IN): The data transfer property list.
                 (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
 req
```

The copy callback in the link class copies a link within the HDF5 container. It returns an herr_t indicating success or failure.

```
(IN): original/source object or file.
src_obi
                (IN): The location parameters for the source object as explained in Section 2.1. The type
loc_params1
                can be only H5VL_OBJECT_BY_NAME in this callback.
dst_obj
                (IN): destination object or file.
                (IN): The location parameters for the destination object as explained in Section 2.1. The
loc_params1
                type can be only H5VL_OBJECT_BY_NAME in this callback.
lcpl_id
                (IN): The link creation property list.
lapl_id
                (IN): The link access property list.
dxpl_id
                (IN): The data transfer property list.
                (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
req
```

The get callback in the link class retrieves information about links as specified in the get_type parameter. It returns an herr_t indicating success or failure.

```
Signature:
      herr_t (*get)(void *obj, H5VL_loc_params_t loc_params,
          H5VL_link_get_t get_type, hid_t dxpl_id, void **req,
          va_list arguments);
  The get_type argument is an enum:
  /* types for all link get API routines */
  typedef enum H5VL_link_get_t {
      H5VL_LINK_GET_INFO,
                                                   */
                                /* link info
      H5VL_LINK_GET_NAME,
                                /* link name
                                                   */
      H5VL_LINK_GET_VAL
                                 /* link value
                                                   */
5
  } H5VL_link_get_t;
   Arguments:
                  (IN): The file or group object where information needs to be retrieved from.
    obj
                  (IN): The location parameters for the source object as explained in Section 2.1. The type
    loc_params
                  can be only <code>H5VL_OBJECT_BY_NAME</code> or <code>H5VL_OBJECT_BY_IDX</code> in this callback.
                  (IN): The type of the information to retrieve.
    get_type
                  (IN): The data transfer property list.
    dxpl_id
                  (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.
    req
                  (IN/OUT): argument list containing parameters and output pointers for the get opera-
    arguments
                  tion.
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_LINK_GET_INFO, to retrieve the link info from the link specified in the loc_params:
 - 1. H5L_info_t linfo (OUT): pointer to info structure to fill.
- H5VL_LINK_GET_NAME, to retrieve the name of the link specified by the index information in loc_params (loc_params is of type H5VL_OBJECT_BY_IDX only with this type):
 - 1. char* name (OUT): buffer to copy the name into.
 - 2. size_t size (IN): size of the buffer name, if 0, return only the buffer size needed.
 - 3. ssize_t *ret (OUT): buffer to return the length of the link name.
- H5VL_LINK_GET_VAL, to retrieve the link value from the link specified in the loc_params:
 - 1. void *buf (OUT): buffer to put the value into.
 - 2. size_t size (IN): size of the passed in buffer.

The specific callback in the link class implements specific operations on HDF5 links as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

Signature: herr_t (*specific)(void *obj, H5VL_loc_params_t loc_params, H5VL_link_specific_t specific_type, hid_t dxpl_id, void **req, va_list arguments); The specific_type argument is an enum: /* types for link SPECIFIC callback */ typedef enum H5VL_link_specific_t { /* H5Ldelete(_by_idx) H5VL_LINK_DELETE, */ H5VL_LINK_EXISTS, /* link existence H5VL_LINK_ITER /* H5Literate/visit(_by_name) */ } H5VL_link_specific_t; **Arguments:** (IN): The location object where the operation needs to happen. obj loc_params (IN): The location parameters as explained in Section 2.1. specific_type (IN): The type of the operation. (IN): The data transfer property list. dxpl_id (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin. req arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_LINK_DELETE, to remove a link specified in the location parameter from an HDF5 container.
- H5VL_LINK_EXITS, to determine whether the link specified in the loc_params exits (loc_params is of type H5VL_OBJECT_BY_NAME only with this type):
 - 1. htri_t *ret (OUT): buffer for the existence of the link (0 for no, 1 for yes).
- H5VL_LINK_ITER, to iterate over all links starting at the location provided and call a user-specified callback on each one:
 - 1. hbool_t recursive (IN): whether to recursively follow links into subgroups of the specified group.
 - 2. H5_index_t idx_type (IN): Type of index.
 - 3. H5_iter_order_t order (IN): Order in which to iterate over index.
 - 4. hsize_t *idx (IN/OUT): iteration position where to start and return position where an interrupted iteration may restart.
 - 5. H5L_iterate_t op (IN): User-defined function to pass each link to.
 - 6. void *op_data (IN/OUT): User data to pass through to and to be returned by iterator operator function.

The optional callback in the link class implements plugin specific operations on an HDF5 link. It returns an herr_t indicating success or failure.

```
Signature:

herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
```

```
obj (IN): The container or object where the operation needs to happen.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.

arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each plugin should be able to parse the valist arguments if it has plugin specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

2.9 The Asynchronous Function Callbacks

The Asynchronous Function Callbacks

As of now, the HDF5 library does not provide asynchronous API operations. An asynchronous class to manage asynchronous operations was added nevertheless to handle an asynchronous API that might be added in the future, Listing 10.

```
typedef struct H5VL_async_class_t {
    herr_t (*cancel)(void **, H5ES_status_t *);
    herr_t (*test) (void **, H5ES_status_t *);
    herr_t (*wait) (void **, H5ES_status_t *);
} H5VL_async_class_t;
```

Listing 10: Structure for async callback routines, H5VLpublic.h

The H5ES_status_t argument is an enum:

```
/* Asynchronous operation status */

typedef enum H5ES_status_t {

H5ES_STATUS_IN_PROGRESS, /* Operation has not yet completed */

H5ES_STATUS_SUCCEED, /* Operation has completed, successfully */

H5ES_STATUS_FAIL, /* Operation has completed, but failed */

H5ES_STATUS_CANCEL /* Operation has not completed and has been cancelled */

H5ES_status_t;
```

The cancel callback attempts to cancel an asynchronous operation and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*cancel)(void **req, H5ES_status_t *status);

Arguments:
req (IN): A pointer to the asynchronous request.
status (OUT): result of the cancel operation.
```

The test callback tests an asynchronous operation completion and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*test)(void **req, H5ES_status_t *status);

Arguments:
req (IN): A pointer to the asynchronous request.
status (OUT): result of the test operation.
```

The wait callback waits for an asynchronous operation completion and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*wait)(void **req, H5ES_status_t *status);
```

```
Arguments:
req (IN): A pointer to the asynchronous request.
status (OUT): result of the wait operation.
```

2.10 The Optional Generic Callback

A generic optional callback is provided for services that are specific to a plugin. Asynchronous operations/services could have been implemented through this optional callback, however since we anticipate asynchronous operations to be common across many plugins, they have been promoted to a subclass by themselves as shown in the previous section. Other services that are not shared across different plugins might include transactional semantics for managing operations like in /reffastforward, MSC - add more use cases here.

The optional callback has the following definition. It returns an herr_t indicating success or failure.

```
herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:

obj (IN): The container or object where the operation needs to happen.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the plugin.

arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

3 New VOL API Routines

New API routines have been added to the HDF5 library to manage VOL plugins. This section details each new API call and explains their intended usage.

```
Signature:
```

```
hid_t H5VLregister(const H5VL_class_t *cls);

Arguments:
```

cls (IN): A pointer to the plugin structure to register.

Registers a user defined VOL plugin with the HDF5 library and returns an identifier for that plugin to be used if successful, otherwise returns a negative value. This function is used when the application has direct access to the plugin it wants to use and is able to obtain a pointer for the plugin structure to pass to the HDF5 library. The plugin must be unregistered before the application exists with H5VLunregister().

```
Signature:

hid_t H5VLregister_by_name(const char *plugin_name);

Arguments:
name (IN): The plugin name to search for an register.
```

Registers a VOL plugin with the HDF5 library given the name of the plugin and returns an identifier for that plugin to be used if successful, otherwise returns a negative value. If the plugin is already registered the library will create an identifier for it and returns it to the user; otherwise the library will look for available third party plugins and dynamically load them and registers them for use, then returns an identifier for the plugin. Third party plugins must be installed on the system as a shared library or DLL. The plugin must be unregistered before the application exists with H5VLunregister().

Signature:

herr_t H5VLunregister(hid_t plugin_id);

Arguments:

plugin_id (IN): A valid identifier of the plugin to unregister.

Unregisters a plugin from the library and return a positive value on success otherwise return a negative value.

Signature:

htri_t H5VLis_registered(const char *name);

Arguments:

name (IN): The plugin name to check for.

Checks if a VOL plugin is registered with the library given the plugin name and returns TRUE/FALSE on success, otherwise it returns a negative value.

Signature:

ssize_t H5VLget_plugin_name(hid_t obj_id, char *name/*out*/, size_t size);

Arguments:

obj_id (IN): The object identifier to check.

name (OUT): Buffer pointer to put the plugin name. If NULL, the library just returns the size

required to store the plugin name.

size (IN): the size of the passed in buffer.

Retrieves the name of a VOL plugin given and object identifier that was created/opened with it. On success, the name length is returned.

Signature:

hid_t H5VLget_plugin_id(const char *name);

Arguments:

name (IN): The plugin name to check for.

Given a plugin name that is registered with the library, this function returns an identifier for the plugin. If the plugin is not registered with the library, a negative value is returned. The identifier must be released with a call to H5VLclose().

Signature:

herr_t H5VLclose(hid_t plugin_id);

Arguments:

plugin_id (IN): A valid identifier of the plugin to close.

Shuts down access to the plugin that the identifier points to and release resources associated with it.

Signature:

hid_t H5VLobject_register(void *obj, H5I_type_t obj_type, hid_t plugin_id);

Arguments:

```
obj (IN): pointer to the object to register.
obj_type (IN): The type of the object (H5I_FILE, H5I_DATASET, H5I_GROUP, H5I_ATTRIBUTE,
H5I_DATATYPE).
plugin_id (IN): identifier of the vol plugin the object is associated with.
```

Creates an HDF5 identifier for an object given its type and an identifier of the plugin that was used in creating it. This function is typically used by external plugins wanting to wrap an hid_t around a plugin specific object to return to a user callback for functions like H5Literate, H5Lvisit, H5Ovisit, H5Aiterate etc... A Negative value is returned on failure.

```
Signature:

herr_t H5VLget_object(hid_t obj_id, void **obj);

Arguments:
obj_id (IN): identifier of the object to dereference.
obj (OUT): buffer to store the pointer of the VOL object associated with the object identifier.
```

Retrieves a pointer to the VOL object from an HDF5 file or object identifier.

```
Signature:

herr_t H5VLinitialize(hid_t plugin_id, hid_t vipl_id);

Arguments:
plugin_id (IN): identifier of VOL plugin to initialize.
vipl_id (IN): VOL initialize property list containing properties required for plugin initialization.
```

Initializes access to the VOL plugin represented by plugin_id with initialization parameters set as properties in the the property list vipl_id. Some plugins may not require initialization. For more information about plugin initialization and what properties are required to be set in the property list refer to the actual plugin documentation.

```
Signature:

herr_t H5VLterminate(hid_t plugin_id, hid_t vtpl_id);

Arguments:
plugin_id (IN): identifier of VOL plugin to terminate.
vtpl_id (IN): VOL terminate property list containing properties required for plugin termination.
```

Terminates access to the VOL plugin represented by plugin_id with termination parameters set as properties in the the property list vtpl_id. Some plugins may not require termination. For more information about plugin termination and what properties are required to be set in the property list refer to the actual plugin documentation.

A set of API calls that map directly to the VOL callbacks themselves have been added to aid in the development of stacked or mirrored plugins. For more information on usage refer to Section 6. The routines are listed in Appendix B.

4 Creating and Using an Internal Plugin

Internal plugins are developed internally with the HDF5 library and are required to ship with the entire library to be used. Typically those plugins need to use internal features and functions of the HDF5 library that are not available publicly from the user application.

4.1 Implementing an Internal Plugin

The first step to implement an internal plugin is to implement all the callbacks defined in the VOL class as described in Section 2. After implementing the VOL class, the next step would be to allow users to select this

plugin to be used. This is done by creating a new API routine to set the plugin on the file access property list. For example, if we create an internal plugin called "dummy" that needs an MPI communicator and info object as information from the user, that routine signature should look like:

```
herr_t H5Pset_fapl_dummy(hid_t fapl_id, MPI_Comm comm, MPI_Info info);
```

The implementation for the above routine should use the internal function:

```
herr_t H5P_set_vol(H5P_genplist_t *plist, H5VL_class_t *vol_cls, const
void *vol_info);
```

that will set the file access using that fapl_id to go through the "dummy" plugin. It will also call the copy callback of the "dummy" plugin on the info object (comm and info).

A sample implementation for the H5Pset_fapl_dummy() would look like this:

```
/* DUMMY-specific file access properties */
   typedef struct H5VL_dummy_fapl_t {
       MPI_Comm
                                   /* communicator
                          comm:
       MPI_Info
                          info;
                                   /* MPI information */
   } H5VL_dummy_fapl_t;
   herr t
   H5Pset_fapl_dummy(hid_t fapl_id, MPI_Comm comm, MPI_Info info)
9
       H5VL_dummy_fapl_t fa;
10
       H5P_genplist_t *plist;
                                  /* Property list pointer */
11
       herr_t
                      ret_value;
12
       FUNC_ENTER_API(FAIL)
14
       if(fapl_id == H5P_DEFAULT)
          HGOTO_ERROR(H5E_PLIST, H5E_BADVALUE, FAIL, "can't set values in default property list")
       if(NULL == (plist = H5P_object_verify(fapl_id, H5P_FILE_ACCESS)))
19
           HGOTO_ERROR(H5E_ARGS, H5E_BADTYPE, FAIL, "not a file access property list")
20
21
       if(MPI_COMM_NULL == comm)
22
           HGOTO_ERROR(H5E_PLIST, H5E_BADTYPE, FAIL, "not a valid communicator")
23
24
       /* Initialize driver specific properties */
25
       fa.comm = comm;
26
       fa.info = info;
27
28
       ret_value = H5P_set_vol(plist, &H5VL_dummy_g, &fa);
29
30
31
   done:
       FUNC_LEAVE_API(ret_value)
32
   } /* end H5Pset_fapl_dummy() */
33
```

At this point, the internal plugin is ready to be used. For more information on how to implement an internal plugin, the native plugin for the HDF5 library is a comprehensive plugin that implements all features of the library and can be used as a guide.

4.2 Using an Internal Plugin

An internal plugin is registered automatically with the HDF5 library when the library gets initialized. Users should not attempt to register an internal plugin. The internal registration operation creates a global identifier for each internal plugin. Applications can query the library for that identifier using the plugin name with H5VLget_plugin_id(). This identifier is used to initialize the plugin if it requires an initialization phase. A third party library could use that ID to create a plugin that stacks or mirrors on top of an internal plugin using that identifier (refer to Section 6 for more details on stacking and mirroring).

Some plugins could require an initialization phase before using the plugin with some input parameters from users. For example, a remote plugin would need to setup a connection to a remote machine with a specific hostname that the user knows and the HDF5 library does not know about. This process is done by creating a VOL initialization property list and setting a public property that should be defined by the internal plugin to the hostname of the remote machine. The user then calls the initialize routine (H5VLintialize()) with the plugin id and the property list to initialize the plugin. Some plugins could create a public API routine that wraps the property list creation, property settings, and plugin initialization into one routine that the user calls to simplify this process for the users. The native HDF5 plugin does not require an initialization phase.

Now that the plugin is initialized, the application can create or open an HDF5 container using the internal plugin by creating a file access property list and calling the corresponding API routine that the internal plugin should define for setting the VOL plugin property and container parameters on the file access property list. That FAPL can be passed to the H5Fcreate() or H5Fopen calls to access the container through the VOL plugin. Subsequently, all other HDF5 calls on the container and objects created or opened in that container will automatically go to the selected VOL plugin.

After closing all objects and containers on that plugin, the application should terminate access to the selected plugin if it requires a termination phase by calling H5VLterminate() with the required termination properties (similar to the initialization phase). The native HDF5 plugin does not require a termination phase.

The internal plugin is unregistered automatically by the HDF5 library on library termination, and users should not attempt to unregister it themselves.

5 Creating and Using an External Plugin

External plugins are developed outside of the HDF5 library and do not use any internal HDF5 private functions. They do not require to be shipped with the HDF5 library, but can just link to it from userspace just like an HDF5 application. If an external VOL plugin is installed on the system as a shared library or a DLL, the library can search for it and load it dynamically to be used by an application.

5.1 Creating an External Plugin

Developing an external plugin is similar to developing an internal plugin. Refer to Section 2 for details on plugin creation. The important thing to keep in mind is that external plugins cannot use internal HDF5 features. The "value" field for an external plugin should be a positive integer greater than 128. The name should be unique across all plugins registered with the library.

For the HDF5 library to be able to load an external plugin dynamically, the plugin developer has to define two public routines with the following name and signature:

```
H5PL_type_t H5PLget_plugin_type(void)
const void *H5PLget_plugin_info(void)
```

H5PLget_plugin_type should return the library type which should always be H5PL_TYPE_V0L. H5PLget_plugin_info should return a pointer to the plugin structure defining the VOL plugin with all the callbacks. For example, consider an external plugin defined as:

```
static const H5VL_class_t H5VL_log_g = {
    1, /* version */
    502, /* value */
    "log", /* name */
    ...
}
```

The plugin would implement the two routines as:

```
H5PL_type_t H5PLget_plugin_type(void) {return H5PL_TYPE_VOL;}
const void *H5PLget_plugin_info(void) {return &H5VL_log_g;}
```

Implementing iteration and visit callbacks in external plugins requires the plugin invoking the user defined callback function with an HDF5 identifier (hid_t) on the location object. The current HDF5 H5I API does not allow creating and dereferencing identifiers that point to HDF5 object types. Therefore, two new API routines have been added (see Section 3 for more details) to get around that. H5VLobject_register() is used to create an HDF5 identifier for a VOL object handle (file, group, dataset, named datatype, or attribute). H5VLget_object() is used to dereference the HDF5 identifier back to the VOL object handle.

5.2 Using an External Plugin

Unlike internal plugins, external plugins cannot create an API routine for applications to use to set the VOL plugin in the file access property list. External plugin developers can, however, provide a wrapper routine that registers the plugin with H5VLregister() instead of having the application call that directly with the pointer to the plugin class structure. Both ways are possible if the external plugin used is in the application's userspace. External plugins provided by third party vendors that are not in the application's userspace but are installed on the system with a shared library or DLL can be registered by the application using H5VLregister_name() provided that the application knows the plugin's name in advance.

The registration operation will return a global identifier for the registered plugin. Applications can query the library for that identifier using the plugin name with <code>H5VLget_plugin_id()</code>. This identifier is used to initialize the plugin if it requires an initialization phase. A third party library could use that ID to create a plugin that stacks or mirrors on top of an internal plugin using that identifier (refer to Section 6 for more details on stacking and mirroring).

Some plugins could require an initialization phase before using the plugin with some input parameters from users. This process is done by creating a VOL initialization property list and setting a public property that should be defined by the internal plugin to the hostname of the remote machine. The user then calls the initialize routine (H5VLintialize()) with the plugin_id and the property list to initialize the plugin. An external plugin could abstract those operations into a wrapper routine that wraps the property list creation, property settings, and plugin initialization into one call that the user makes to simplify this process.

The application then sets the plugin access property in the file access property list to the external plugin using the plugin identifier with this API routine:

```
herr_t H5Pset_vol(hid_t fapl_id, hid_t plugin_id, const void *new_vol_info);
```

where new_vol_info is the plugin information needed from the application. Typically it is a plugin defined structure with some fields to setup the plugin access. The external plugin could also provide a wrapper function around this to make it easier for the application to use.

Now that the plugin is initialized, the application can create or open an HDF5 container using the external plugin. After closing all objects and containers on that plugin, the application should terminate access to the selected plugin if it requires a termination phase by calling H5VLterminate() with the required termination properties (similar to the initialization phase).

Finally, the application is required to un-register the plugin from the library when access to the container(s) is terminated using H5VLunregister.

6 Interchanging and Stacking VOL Plugins

Accessing an HDF5 container with a VOL plugin different than the one it was created with would be a valid approach as long as the underlying file format is the same. This would be the user's responsibility to ensure that the different plugins are interchangeable.

6.1 Stacking Plugins on Top of Each Other

It would also be possible to stack VOL plugins on top of each other. This notion is similar to the idea of the split VFD, where underneath the split VFD itself, two file drivers would be used, one for the file storing the metadata and another for raw data. Some stackings make sense and others would be erroneous. For example, stacking the native HDF5 plugin on top of a non-HDF5 backend plugin does not make sense and

is erroneous. Figure 1 shows a stacking of a remote plugin, where data is distributed remotely, on top of the native h5 plugin, where servers that store the data at remote locations use the h5 file format.




Figure 1: Stacked VOL plugins.

6.2 Mirroring Plugins

Another useful design option is to allow a mirroring plugin, where the HDF5 API calls are forwarded through a mirror plugin to two or more VOL plugins. This is an extension to the stacking feature. Figure 2 shows an example of a VOL mirror that maps HDF5 API calls to an h5 backend plugin and an XML backend plugin.

Another possible VOL plugin could be a statistic plugin that just gathers information on HDF5 API calls and records statistics associated with the number of calls to specific API functions and corresponding parameters. This plugin would be very useful for profiling purposes. The statistics plugin would be stacked on top of another VOL plugin that actually performs the required access to the file.

6.3 Implementing Stacked & Mirrored Plugins

A new set of API calls that map directly to the VOL callbacks have been added to the HDF5 library to make stacking and mirroring easy for plugin developers. Those APIs are listed at then end of Section 3. They are similar to the public VFD (H5FD) routines that call the VFD callbacks directly.

A mirror VOL plugin could, for example, implement the create callback in the file class by creating two HDF5 containers each with a different underlying plugin with 2 calls to:

where each call uses a different file access property list, each with the VOL plugin property set to the underlying plugin. Then the mirror plugin creates a structure containing the pointers for the containers returned from both underlying plugins and returns a pointer to that structure as the output of the file create callback. Subsequent access to the container created would receive as input the structure with the two files




Figure 2: Mirrored VOL plugins.

and would again call the public VOL routines twice for each plugin with its corresponding file object and combine the output as needed.

Appendix A demonstrates how to stack a simple plugin that does a printf of the VOL operation on top of the native HDF5 plugin.

Appendix A

VOL Plugin Example

This appendix shows a simple implementation of a **printf** plugin that stacks on top of the native HDF5 plugin. Note that not all callbacks have been implemented since this is just an example for explaining the general framework of the VOL plugin.

```
#include <stdio.h>
   #include <stdlib.h>
   #include <assert.h>
   #include "hdf5.h"
   #define LOG 502
   static herr_t H5VL_log_init(hid_t vipl_id);
9
   static herr_t H5VL_log_term(hid_t vtpl_id);
10
11
   /* Datatype callbacks */
12
   static void *H5VL_log_datatype_commit(void *obj, H5VL_loc_params_t loc_params, const char *name,
        hid_t type_id, hid_t lcpl_id, hid_t tcpl_id, hid_t tapl_id, hid_t dxpl_id, void **req);
   static void *H5VL_log_datatype_open(void *obj, H5VL_loc_params_t loc_params, const char *name,
        hid_t tapl_id, hid_t dxpl_id, void **req);
   static herr_t H5VL_log_datatype_get(void *dt, H5VL_datatype_get_t get_type, hid_t dxpl_id, void
        **req, va_list arguments);
   static herr_t H5VL_log_datatype_close(void *dt, hid_t dxpl_id, void **req);
17
   /* Dataset callbacks */
18
   static void *H5VL_log_dataset_create(void *obj, H5VL_loc_params_t loc_params, const char *name,
19
       hid_t dcpl_id, hid_t dapl_id, hid_t dxpl_id, void **req);
   static void *H5VL_log_dataset_open(void *obj, H5VL_loc_params_t loc_params, const char *name,
       hid_t dapl_id, hid_t dxpl_id, void **req);
   static herr_t H5VL_log_dataset_read(void *dset, hid_t mem_type_id, hid_t mem_space_id,
21
                                    hid_t file_space_id, hid_t plist_id, void *buf, void **req);
22
   static herr_t H5VL_log_dataset_write(void *dset, hid_t mem_type_id, hid_t mem_space_id,
23
                                     hid_t file_space_id, hid_t plist_id, const void *buf, void **req);
24
   static herr_t H5VL_log_dataset_close(void *dset, hid_t dxpl_id, void **req);
25
26
   /* File callbacks */
27
   static void *H5VL_log_file_create(const char *name, unsigned flags, hid_t fcpl_id, hid_t fapl_id,
28
       hid_t dxpl_id, void **req);
   static void *H5VL_log_file_open(const char *name, unsigned flags, hid_t fapl_id, hid_t dxpl_id,
        void **req);
   static herr_t H5VL_log_file_get(void *file, H5VL_file_get_t get_type, hid_t dxpl_id, void **req,
        va_list arguments);
   static herr_t H5VL_log_file_close(void *file, hid_t dxpl_id, void **req);
31
32
   /* Group callbacks */
33
   static void *H5VL_log_group_create(void *obj, H5VL_loc_params_t loc_params, const char *name,
34
        hid_t gcpl_id, hid_t gapl_id, hid_t dxpl_id, void **req);
   static herr_t H5VL_log_group_close(void *grp, hid_t dxpl_id, void **req);
35
36
   /* Link callbacks */
37
38
39
   /* Object callbacks */
   static void *H5VL_log_object_open(void *obj, H5VL_loc_params_t loc_params, H5I_type_t
40
        *opened_type, hid_t dxpl_id, void **req);
   static herr_t H5VL_log_object_specific(void *obj, H5VL_loc_params_t loc_params,
41
        H5VL_object_specific_t specific_type, hid_t dxpl_id, void **req, va_list arguments);
42
   hid_t native_plugin_id = -1;
43
44
   static const H5VL_class_t H5VL_log_g = {
45
       Ο,
       LOG,
47
```

```
"log",
                                                  /* name */
48
        H5VL_log_init,
                                                  /* initialize */
49
        H5VL_log_term,
                                                  /* terminate */
50
        sizeof(hid_t),
51
        NULL,
52
        NULL,
53
                                                   /* attribute_cls */
        {
54
            NULL, //H5VL_log_attr_create,
                                                       /* create */
55
            NULL, //H5VL_log_attr_open,
                                                       /* open */
56
            NULL, //H5VL_log_attr_read,
                                                       /* read */
57
           NULL, //H5VL_log_attr_write,
                                                       /* write */
58
            NULL, //H5VL_log_attr_get,
                                                       /* get */
59
            NULL, //H5VL_log_attr_specific,
                                                       /* specific */
60
            NULL, //H5VL_log_attr_optional,
                                                       /* optional */
61
           NULL //H5VL_log_attr_close
                                                       /* close */
62
63
                                                   /* dataset_cls */
64
                                                      /* create */
            H5VL_log_dataset_create,
65
            H5VL_log_dataset_open,
                                                      /* open */
66
            H5VL_log_dataset_read,
                                                      /* read */
67
            H5VL_log_dataset_write,
                                                      /* write */
            NULL, //H5VL_log_dataset_get,
                                                      /* get */
69
            NULL, //H5VL_log_dataset_specific,
                                                      /* specific */
70
            NULL, //H5VL_log_dataset_optional,
                                                      /* optional */
71
                                                      /* close */
            H5VL_log_dataset_close
72
        },
73
                                                      /* datatype_cls */
        {
74
            H5VL_log_datatype_commit,
                                                      /* commit */
75
            H5VL_log_datatype_open,
                                                      /* open */
76
77
            H5VL_log_datatype_get,
                                                      /* get_size */
78
            NULL, //H5VL_log_datatype_specific,
                                                      /* specific */
79
            NULL, //H5VL_log_datatype_optional,
                                                      /* optional */
                                                      /* close */
80
            H5VL_log_datatype_close
        },
81
                                                  /* file_cls */
82
                                                     /* create */
            H5VL_log_file_create,
83
            H5VL_log_file_open,
                                                     /* open */
84
            H5VL_log_file_get,
                                                     /* get */
85
            NULL, //H5VL_log_file_specific,
                                                     /* specific */
86
            NULL, //H5VL_log_file_optional,
                                                     /* optional */
87
            H5VL_log_file_close
                                                     /* close */
88
        },
89
90
                                                  /* group_cls */
                                                      /* create */
            H5VL_log_group_create,
91
                                                     /* open */
92
            NULL, //H5VL_log_group_open,
                                                     /* get */
            NULL, //H5VL_log_group_get,
93
            NULL, //H5VL_log_group_specific,
                                                     /* specific */
94
            NULL, //H5VL_log_group_optional,
                                                     /* optional */
95
            H5VL_log_group_close
                                                     /* close */
96
        },
97
                                                   /* link_cls */
98
            NULL, //H5VL_log_link_create,
                                                       /* create */
99
            NULL, //H5VL_log_link_copy,
                                                       /* copy */
100
            NULL, //H5VL_log_link_move,
                                                       /* move */
101
            NULL, //H5VL_log_link_get,
                                                       /* get */
102
            NULL, //H5VL_log_link_specific,
                                                       /* specific */
103
                                                       /* optional */
            NULL, //H5VL_log_link_optional,
104
        },
105
                                                   /* object_cls */
106
            H5VL_log_object_open,
                                                       /* open */
107
            NULL, //H5VL_log_object_copy,
                                                       /* copy */
108
            NULL, //H5VL_log_object_get,
                                                       /* get */
109
            H5VL_log_object_specific,
                                                       /* specific */
110
            NULL, //H5VL_log_object_optional,
                                                       /* optional */
        },
112
        {
113
```

```
NULL,
114
            NULL,
115
            NULL
116
117
        NULL
118
    };
119
120
    typedef struct H5VL_log_t {
121
        void *under_object;
122
    } H5VL_log_t;
123
124
    static herr_t
125
    visit_cb(hid_t oid, const char *name,
126
             const H50_info_t *oinfo, void *udata)
127
128
        ssize_t len;
129
        char n[25];
130
131
        if(H5Iget_type(oid) == H5I_GROUP) {
132
            len = H5VLget_plugin_name(oid, n, 50);
            printf ("Visiting GROUP VOL name = s \dn, n, len);
134
135
        if(H5Iget_type(oid) == H5I_DATASET)
136
            printf("visiting dataset\n");
137
        if(H5Iget_type(oid) == H5I_DATATYPE)
138
            printf("visiting datatype\n");
139
140
        return 1;
141
142
    }
143
144
    int main(int argc, char **argv) {
            const char file_name[]="large_dataset.h5";
145
            const char group_name[]="/Group";
146
            const char dataset_name[]="Data";
147
            char fullpath[500];
148
            hid_t file_id;
149
            hid_t group_id;
150
            hid_t dataspaceId;
151
            hid_t datasetId;
            hid_t acc_tpl;
153
            hid_t under_fapl;
154
155
            hid_t vol_id, vol_id2;
156
            hid_t int_id;
157
            hid_t attr;
158
            hid_t space;
            const unsigned int nelem=60;
159
            int *data;
160
            unsigned int i;
161
            hsize_t dims[1];
162
            ssize_t len;
163
            char name[25];
164
            static hsize_t
                                ds_size[2] = \{10, 20\};
            under_fapl = H5Pcreate (H5P_FILE_ACCESS);
167
            H5Pset_fapl_native(under_fapl);
168
            assert(H5VLis_registered("native") == 1);
169
170
            vol_id = H5VLregister (&H5VL_log_g);
171
            assert(vol_id > 0);
172
            assert(H5VLis_registered("log") == 1);
173
174
            vol_id2 = H5VLget_plugin_id("log");
175
176
            H5VLinitialize(vol_id2, H5P_DEFAULT);
            H5VLclose(vol_id2);
177
178
            native_plugin_id = H5VLget_plugin_id("native");
179
```

```
assert(native_plugin_id > 0);
180
181
            acc_tpl = H5Pcreate (H5P_FILE_ACCESS);
182
           H5Pset_vol(acc_tpl, vol_id, &under_fapl);
183
184
            file_id = H5Fcreate(file_name, H5F_ACC_TRUNC, H5P_DEFAULT, acc_tpl);
185
           len = H5VLget_plugin_name(file_id, name, 25);
186
            printf ("FILE VOL name = %s %d\n", name, len);
187
            group_id = H5Gcreate2(file_id, group_name, H5P_DEFAULT, H5P_DEFAULT, H5P_DEFAULT);
            len = H5VLget_plugin_name(group_id, name, 50);
           printf ("GROUP VOL name = %s %d\n", name, len);
191
192
            int_id = H5Tcopy(H5T_NATIVE_INT);
193
           H5Tcommit2(file_id, "int", int_id, H5P_DEFAULT, H5P_DEFAULT);
194
            len = H5VLget_plugin_name(int_id, name, 50);
195
            printf ("DT COMMIT name = %s %d\n", name, len);
196
            H5Tclose(int_id);
197
198
            int_id = H5Topen2(file_id, "int", H5P_DEFAULT);
199
            len = H5VLget_plugin_name(int_id, name, 50);
200
            printf ("DT OPEN name = %s %d\n", name, len);
201
           H5Tclose(int_id);
202
203
            int_id = H5Oopen(file_id,"int",H5P_DEFAULT);
204
            len = H5VLget_plugin_name(int_id, name, 50);
205
           printf ("DT OOPEN name = %s %d\n", name, len);
206
207
            len = H5Fget_name(file_id, name, 50);
208
            printf("name = %d %s\n", len, name);
            data = malloc (sizeof(int)*nelem);
            for(i=0;i<nelem;++i)</pre>
212
             data[i]=i;
213
214
            dims [0] = 60;
215
            dataspaceId = H5Screate_simple(1, dims, NULL);
216
            space = H5Screate_simple (2, ds_size, ds_size);
217
218
            sprintf(fullpath,"%s/%s",group_name,dataset_name);
219
            datasetId = H5Dcreate2(file_id, fullpath, H5T_NATIVE_INT, dataspaceId, H5P_DEFAULT,
220
                H5P_DEFAULT, H5P_DEFAULT);
           H5Sclose(dataspaceId);
221
222
223
           len = H5VLget_plugin_name(datasetId, name, 50);
           printf ("DSET name = %s %d\n", name, len);
224
225
            H5Dwrite(datasetId, H5T_NATIVE_INT, H5S_ALL, H5S_ALL, H5P_DEFAULT, data);
226
            H5Dclose(datasetId);
227
228
            H5Ovisit(file_id, H5_INDEX_NAME, H5_ITER_NATIVE, visit_cb, NULL);
            free (data);
           H5Oclose(int_id);
232
           H5Sclose (space);
233
           H5Gclose(group_id);
234
235
           H5Fclose(file_id);
236
            H5Pclose(acc_tpl);
237
           H5Pclose(under_fapl);
238
239
            H5VLclose(native_plugin_id);
240
            H5VLterminate(vol_id, H5P_DEFAULT);
241
           H5VLunregister (vol_id);
242
            assert(H5VLis_registered("log") == 0);
243
            return 0;
244
```

```
}
245
246
    static herr_t H5VL_log_init(hid_t vipl_id)
247
248
        printf("----- LOG INIT\n");
249
        return 0;
250
251
252
    static herr_t H5VL_log_term(hid_t vtpl_id)
253
254
        printf("----- LOG TERM\n");
255
        return 0;
256
    }
257
258
    static void *
259
    H5VL_log_file_create(const char *name, unsigned flags, hid_t fcpl_id, hid_t fapl_id, hid_t
260
         dxpl_id, void **req)
261
        hid_t under_fapl;
262
        H5VL_log_t *file;
263
264
        file = (H5VL_log_t *)calloc(1, sizeof(H5VL_log_t));
265
266
        under_fapl = *((hid_t *)H5Pget_vol_info(fapl_id));
267
        file->under_object = H5VLfile_create(name, flags, fcpl_id, under_fapl, dxpl_id, req);
268
269
        printf("----- LOG H5Fcreate\n");
270
        return (void *)file;
271
272
    }
273
274
    static void *
    H5VL_log_file_open(const char *name, unsigned flags, hid_t fapl_id, hid_t dxpl_id, void **req)
275
276
        hid_t under_fapl;
277
        H5VL_log_t *file;
278
279
        file = (H5VL_log_t *)calloc(1, sizeof(H5VL_log_t));
280
281
        under_fapl = *((hid_t *)H5Pget_vol_info(fapl_id));
282
        file->under_object = H5VLfile_open(name, flags, under_fapl, dxpl_id, req);
283
284
        printf("----- LOG H5Fopen\n");
285
286
        return (void *)file;
287
    }
288
    static herr t
289
    H5VL_log_file_get(void *file, H5VL_file_get_t get_type, hid_t dxpl_id, void **req, va_list
290
         arguments)
291
        H5VL_log_t *f = (H5VL_log_t *)file;
292
293
        H5VLfile_get(f->under_object, native_plugin_id, get_type, dxpl_id, req, arguments);
294
        printf("----- LOG H5Fget %d\n", get_type);
296
        return 1:
297
    }
298
    static herr_t
299
    H5VL_log_file_close(void *file, hid_t dxpl_id, void **req)
300
301
        H5VL_log_t *f = (H5VL_log_t *)file;
302
303
        H5VLfile_close(f->under_object, native_plugin_id, dxpl_id, req);
304
        free(f);
305
306
        printf("----- LOG H5Fclose\n");
307
        return 1;
308
```

```
}
309
310
    static void *
311
    H5VL_log_group_create(void *obj, H5VL_loc_params_t loc_params, const char *name,
312
                         hid_t gcpl_id, hid_t gapl_id, hid_t dxpl_id, void **req)
313
314
        H5VL_log_t *group;
315
        H5VL_log_t *o = (H5VL_log_t *)obj;
316
        group = (H5VL_log_t *)calloc(1, sizeof(H5VL_log_t));
318
319
        group->under_object = H5VLgroup_create(o->under_object, loc_params, native_plugin_id, name,
320
            gcpl_id, gapl_id, dxpl_id, req);
321
        printf("----- LOG H5Gcreate\n");
322
        return (void *)group;
323
324
325
    static herr_t
326
    H5VL_log_group_close(void *grp, hid_t dxpl_id, void **req)
327
328
        H5VL_log_t *g = (H5VL_log_t *)grp;
329
330
        H5VLgroup_close(g->under_object, native_plugin_id, dxpl_id, req);
331
        free(g);
332
333
        printf("----- LOG H5Gclose\n");
334
        return 1;
335
336
337
    static void *
338
    H5VL_log_datatype_commit(void *obj, H5VL_loc_params_t loc_params, const char *name,
                            hid_t type_id, hid_t lcpl_id, hid_t tcpl_id, hid_t tapl_id, hid_t dxpl_id,
340
                                void **req)
    {
341
        H5VL_log_t *dt;
342
        H5VL_log_t *o = (H5VL_log_t *)obj;
343
344
        dt = (H5VL_log_t *)calloc(1, sizeof(H5VL_log_t));
345
346
        dt->under_object = H5VLdatatype_commit(o->under_object, loc_params, native_plugin_id, name,
347
                                             type_id, lcpl_id, tcpl_id, tapl_id, dxpl_id, req);
348
349
350
        printf("----- LOG H5Tcommit\n");
        return dt;
351
    }
352
    static void *
353
    H5VL_log_datatype_open(void *obj, H5VL_loc_params_t loc_params, const char *name, hid_t tapl_id,
354
        hid_t dxpl_id, void **req)
355
        H5VL_log_t *dt;
356
        H5VL_log_t *o = (H5VL_log_t *)obj;
357
        dt = (H5VL_log_t *)calloc(1, sizeof(H5VL_log_t));
359
360
        dt->under_object = H5VLdatatype_open(o->under_object, loc_params, native_plugin_id, name,
361
            tapl_id, dxpl_id, req);
362
        printf("----- LOG H5Topen\n");
363
        return (void *)dt;
364
    }
365
    static herr_t
367
    H5VL_log_datatype_get(void *dt, H5VL_datatype_get_t get_type, hid_t dxpl_id, void **req, va_list
         arguments)
369
    {
```

```
370
        H5VL_log_t *o = (H5VL_log_t *)dt;
        herr_t ret_value;
371
372
        ret_value = H5VLdatatype_get(o->under_object, native_plugin_id, get_type, dxpl_id, req,
373
            arguments);
374
        printf("----- LOG datatype get\n");
375
        return ret_value;
376
    }
    static herr t
379
    H5VL_log_datatype_close(void *dt, hid_t dxpl_id, void **req)
380
381
        H5VL_log_t *type = (H5VL_log_t *)dt;
382
383
        assert(type->under_object);
384
385
        H5VLdatatype_close(type->under_object, native_plugin_id, dxpl_id, req);
386
387
        free(type);
        printf("----- LOG H5Tclose\n");
389
390
        return 1;
    }
391
392
    static void *
393
    H5VL_log_object_open(void *obj, H5VL_loc_params_t loc_params, H5I_type_t *opened_type, hid_t
394
        dxpl_id, void **req)
395
        H5VL_log_t *new_obj;
396
        H5VL_log_t *o = (H5VL_log_t *)obj;
        new_obj = (H5VL_log_t *)calloc(1, sizeof(H5VL_log_t));
400
        new_obj->under_object = H5VLobject_open(o->under_object, loc_params, native_plugin_id,
401
            opened_type, dxpl_id, req);
402
        printf("----- LOG H5Oopen\n");
403
        return (void *)new_obj;
404
405
406
    static herr_t
407
    H5VL_log_object_specific(void *obj, H5VL_loc_params_t loc_params, H5VL_object_specific_t
         specific_type,
409
                           hid_t dxpl_id, void **req, va_list arguments)
410
        H5VL_log_t *o = (H5VL_log_t *)obj;
411
412
        H5VLobject_specific(o->under_object, loc_params, native_plugin_id, specific_type, dxpl_id,
413
            req, arguments);
414
        printf("----- LOG Object specific\n");
415
        return 1;
416
    }
417
418
    static void *
419
    H5VL_log_dataset_create(void *obj, H5VL_loc_params_t loc_params, const char *name, hid_t dcpl_id,
420
        hid_t dapl_id, hid_t dxpl_id, void **req)
421
        H5VL_log_t *dset;
422
423
        H5VL_log_t *o = (H5VL_log_t *)obj;
424
        dset = (H5VL_log_t *)calloc(1, sizeof(H5VL_log_t));
425
426
        dset->under_object = H5VLdataset_create(o->under_object, loc_params, native_plugin_id, name,
427
            dcpl_id, dapl_id, dxpl_id, req);
```

428

```
printf("----- LOG H5Dcreate\n");
429
        return (void *)dset;
430
431
432
    static void *
433
    H5VL_log_dataset_open(void *obj, H5VL_loc_params_t loc_params, const char *name, hid_t dapl_id,
434
         hid_t dxpl_id, void **req)
435
        H5VL_log_t *dset;
        H5VL_log_t *o = (H5VL_log_t *)obj;
        dset = (H5VL_log_t *)calloc(1, sizeof(H5VL_log_t));
439
440
        dset->under_object = H5VLdataset_open(o->under_object, loc_params, native_plugin_id, name,
441
            dapl_id, dxpl_id, req);
442
        printf("----- LOG H5Dopen\n");
443
        return (void *)dset;
444
    }
445
    static herr t
447
    H5VL_log_dataset_read(void *dset, hid_t mem_type_id, hid_t mem_space_id,
                         hid_t file_space_id, hid_t plist_id, void *buf, void **req)
449
450
        H5VL_log_t *d = (H5VL_log_t *)dset;
451
452
        H5VLdataset_read(d->under_object, native_plugin_id, mem_type_id, mem_space_id, file_space_id,
453
                        plist_id, buf, req);
454
        printf("----- LOG H5Dread\n");
        return 1;
    }
    static herr_t
    H5VL_log_dataset_write(void *dset, hid_t mem_type_id, hid_t mem_space_id,
460
                          hid_t file_space_id, hid_t plist_id, const void *buf, void **req)
461
462
        H5VL_log_t *d = (H5VL_log_t *)dset;
463
464
        H5VLdataset_write(d->under_object, native_plugin_id, mem_type_id, mem_space_id, file_space_id,
465
                        plist_id, buf, req);
466
467
        printf("----- LOG H5Dwrite\n");
468
469
        return 1;
470
    }
471
    static herr t
    H5VL_log_dataset_close(void *dset, hid_t dxpl_id, void **req)
472
473
        H5VL_log_t *d = (H5VL_log_t *)dset;
474
475
        H5VLdataset_close(d->under_object, native_plugin_id, dxpl_id, req);
476
        free(d);
        printf("----- LOG H5Dclose\n");
479
480
        return 1;
    }
481
```

Appendix B

Listing of Direct Mapping to VOL Callback APIs

```
/* ATTRIBUTE OBJECT ROUTINES */
void *H5VLattr_create(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, const char
*attr_name, hid_t acpl_id, hid_t aapl_id, hid_t dxpl_id, void **req);
```

```
void *H5VLattr_open(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, const char *name,
       hid_t aapl_id, hid_t dxpl_id, void **req);
   herr_t H5VLattr_read(void *attr, hid_t plugin_id, hid_t dtype_id, void *buf, hid_t dxpl_id, void
        **rea):
   herr_t H5VLattr_write(void *attr, hid_t plugin_id, hid_t dtype_id, const void *buf, hid_t dxpl_id,
        void **req);
   herr_t H5VLattr_get(void *obj, hid_t plugin_id, H5VL_attr_get_t get_type, hid_t dxpl_id, void
        **req, va_list arguments);
   herr_t H5VLattr_specific(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id,
       H5VL_attr_specific_t specific_type, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLattr_optional(void *obj, hid_t plugin_id, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLattr_close(void *attr, hid_t plugin_id, hid_t dxpl_id, void **req);
10
11
   /* DATASET OBJECT ROUTINES */
12
   void *H5VLdataset_create(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, const char
13
        *name, hid_t dcpl_id, hid_t dapl_id, hid_t dxpl_id, void **req);
   void *H5VLdataset_open(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, const char *name,
14
       hid_t dapl_id, hid_t dxpl_id, void **req);
   herr_t H5VLdataset_read(void *dset, hid_t plugin_id, hid_t mem_type_id, hid_t mem_space_id, hid_t
       file_space_id, hid_t plist_id, void *buf, void **req);
   herr_t H5VLdataset_write(void *dset, hid_t plugin_id, hid_t mem_type_id, hid_t mem_space_id, hid_t
       file_space_id, hid_t plist_id, const void *buf, void **req);
   herr_t H5VLdataset_get(void *dset, hid_t plugin_id, H5VL_dataset_get_t get_type, hid_t dxpl_id,
       void **req, va_list arguments);
   herr_t H5VLdataset_specific(void *obj, hid_t plugin_id, H5VL_dataset_specific_t specific_type,
18
       hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLdataset_optional(void *obj, hid_t plugin_id, hid_t dxpl_id, void **req, va_list
19
       arguments):
   herr_t H5VLdataset_close(void *dset, hid_t plugin_id, hid_t dxpl_id, void **req);
20
   /* DATATYPE OBJECT ROUTINES */
   void *H5VLdatatype_commit(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, const char
        *name, hid_t type_id, hid_t lcpl_id, hid_t tcpl_id, hid_t tapl_id, hid_t dxpl_id, void **req);
   void *H5VLdatatype_open(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, const char
        *name, hid_t tapl_id, hid_t dxpl_id, void **req);
   herr_t H5VLdatatype_get(void *dt, hid_t plugin_id, H5VL_datatype_get_t get_type, hid_t dxpl_id,
       void **req, va_list arguments);
   herr_t H5VLdatatype_specific(void *obj, hid_t plugin_id, H5VL_datatype_specific_t specific_type,
       hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLdatatype_optional(void *obj, hid_t plugin_id, hid_t dxpl_id, void **req, va_list
   herr_t H5VLdatatype_close(void *dt, hid_t plugin_id, hid_t dxpl_id, void **req);
30
31
   /* FILE OBJECT ROUTINES */
32
   void *H5VLfile_create(const char *name, unsigned flags, hid_t fcpl_id, hid_t fapl_id, hid_t
33
        dxpl_id, void **req);
   void *H5VLfile_open(const char *name, unsigned flags, hid_t fapl_id, hid_t dxpl_id, void **req);
   herr_t H5VLfile_get(void *file, hid_t plugin_id, H5VL_file_get_t get_type, hid_t dxpl_id, void
        **req, va_list arguments);
   herr_t H5VLfile_specific(void *obj, hid_t plugin_id, H5VL_file_specific_t specific_type, hid_t
        dxpl_id, void **req, va_list arguments);
   herr_t H5VLfile_optional(void *obj, hid_t plugin_id, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLfile_close(void *file, hid_t plugin_id, hid_t dxpl_id, void **req);
39
40
   /* GROUP OBJECT ROUTINES */
41
   void *H5VLgroup_create(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, const char *name,
       hid_t gcpl_id, hid_t gapl_id, hid_t dxpl_id, void **req);
   void *H5VLgroup_open(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, const char *name,
       hid_t gapl_id, hid_t dxpl_id, void **req);
   herr_t H5VLgroup_get(void *obj, hid_t plugin_id, H5VL_group_get_t get_type, hid_t dxpl_id, void
       **req, va_list arguments);
```

REFERENCES REFERENCES

```
herr_t H5VLgroup_specific(void *obj, hid_t plugin_id, H5VL_group_specific_t specific_type, hid_t
       dxpl_id, void **req, va_list arguments);
   herr_t H5VLgroup_optional(void *obj, hid_t plugin_id, hid_t dxpl_id, void **req, va_list
        arguments):
   herr_t H5VLgroup_close(void *grp, hid_t plugin_id, hid_t dxpl_id, void **req);
47
48
49
   /* LINK OBJECT ROUTINES */
50
   herr_t H5VLlink_create(H5VL_link_create_type_t create_type, void *obj, H5VL_loc_params_t
        loc_params, hid_t plugin_id, hid_t lcpl_id, hid_t lapl_id, hid_t dxpl_id, void **req);
   herr_t H5VLlink_copy(void *src_obj, H5VL_loc_params_t loc_params1, void *dst_obj,
       H5VL_loc_params_t loc_params2, hid_t plugin_id, hid_t lcpl_id, hid_t lapl_id, hid_t dxpl_id,
       void **rea):
   herr_t H5VLlink_move(void *src_obj, H5VL_loc_params_t loc_params1, void *dst_obj,
       H5VL_loc_params_t loc_params2, hid_t plugin_id, hid_t lcpl_id, hid_t lapl_id, hid_t dxpl_id,
       void **req);
   herr_t H5VLlink_get(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, H5VL_link_get_t
       get_type, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLlink_specific(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id,
       H5VL_link_specific_t specific_type, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLlink_optional(void *obj, hid_t plugin_id, hid_t dxpl_id, void **req, va_list arguments);
57
58
   /* OBJECT ROUTINES */
59
   void *H5VLobject_open(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, H5I_type_t
60
        *opened_type, hid_t dxpl_id, void **req);
   herr_t H5VLobject_copy(void *src_obj, H5VL_loc_params_t loc_params1, hid_t plugin_id1, const char
61
                           void *dst_obj, H5VL_loc_params_t loc_params2, hid_t plugin_id2, const char
        *dst_name, hid_t ocpypl_id, hid_t lcpl_id, hid_t dxpl_id, void **req);
   herr_t H5VLobject_get(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id, H5VL_object_get_t
       get_type, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLobject_specific(void *obj, H5VL_loc_params_t loc_params, hid_t plugin_id,
       H5VL_object_specific_t specific_type, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLobject_optional(void *obj, hid_t plugin_id, hid_t dxpl_id, void **req, va_list
       arguments);
65
   /* ASYNCHRONOUS ROUTINES */
66
   herr_t H5VLrequest_cancel(void **req, hid_t plugin_id, H5ES_status_t *status);
67
   herr_t H5VLrequest_test(void **req, hid_t plugin_id, H5ES_status_t *status);
   herr_t H5VLrequest_wait(void **req, hid_t plugin_id, H5ES_status_t *status);
```

References

[1] M. Chaarawi and Q. Koziol, "RFC: Virtual Object Layer," 2014, available at https://bitbucket.hdfgroup.org/projects/HDFFV/repos/hdf5doc/browse/RFCs/HDF5/VOL/RFC.