CAPI Reference Manual

Version 6.1



Copyright and Trademarks

CAPI Reference Manual

Version 6.1

December 2011

Copyright © 2011 by LispWorks Ltd.

All Rights Reserved. No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise, without the prior written permission of LispWorks Ltd.

The information in this publication is provided for information only, is subject to change without notice, and should not be construed as a commitment by LispWorks Ltd. LispWorks Ltd assumes no responsibility or liability for any errors or inaccuracies that may appear in this publication. The software described in this book is furnished under license and may only be used or copied in accordance with the terms of that license.

LispWorks and KnowledgeWorks are registered trademarks of LispWorks Ltd.

Adobe and PostScript are registered trademarks of Adobe Systems Incorporated. Other brand or product names are the registered trademarks or trademarks of their respective holders.

The code for walker.lisp and compute-combination-points is excerpted with permission from PCL, Copyright © 1985, 1986, 1987, 1988 Xerox Corporation.

The XP Pretty Printer bears the following copyright notice, which applies to the parts of LispWorks derived therefrom:

Copyright © 1989 by the Massachusetts Institute of Technology, Cambridge, Massachusetts.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that this copyright and permission notice appear in all copies and supporting documentation, and that the name of M.I.T. not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission. M.I.T. makes no representation about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty. M.I.T. disclaims all warranties with regard to this software, including all implied warranties of merchantability and fitness. In no event shall M.I.T. be liable for any special, indirect or consequential damages or any damages whatsoever resulting from loss of use, data or profits, whether in an action of contract, negligence or other tortious action, arising out of or in connection with the use or performance of this software.

LispWorks contains part of ICU software obtained from http://source.icu-project.org and which bears the following copyright and permission notice:

ICU License - ICU 1.8.1 and later

COPYRIGHT AND PERMISSION NOTICE

Copyright © 1995-2006 International Business Machines Corporation and others. All rights reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder. All trademarks and registered trademarks mentioned herein are the property of their respective owners.

US Government Restricted Rights

The LispWorks Software is a commercial computer software program developed at private expense and is provided with restricted rights. The LispWorks Software may not be used, reproduced, or disclosed by the Government except as set forth in the accompanying End User License Agreement and as provided in DFARS 227.7202-1(a), 227.7202-3(a) (1995), FAR 12.212(a)(1995), FAR 52.227-19, and/or FAR 52.227-14 Alt III, as applicable. Rights reserved under the copyright laws of the United States.

Address

LispWorks Ltd St. John's Innovation Centre Cowley Road Cambridge CB4 0WS England

Telephone

From North America: 877 759 8839 (toll-free)

From elsewhere: +44 1223 421860

Fax

From North America: 617 812 8283 From elsewhere: +44 870 2206189

www.lispworks.com

Contents

Preface xxiii

1 CAPI Reference Entries 1

abort-callback 1 abort-dialog 2 abort-exit-confirmer 3 accepts-focus-p 4 activate-pane 5 active-pane-copy 6 active-pane-copy-p 6 active-pane-cut 6 active-pane-cut-p 6 active-pane-deselect-all 6 active-pane-deselect-all-p 6 active-pane-paste 6 active-pane-paste-p 6 active-pane-select-all 6 active-pane-select-all-p 6 active-pane-undo 6 active-pane-undo-p 6

append-items 7 apply-in-pane-process 8 apply-in-pane-process-if-alive 9 arrow-pinboard-object 10 attach-interface-for-callback 11 attach-simple-sink 12 attach-sink 13 beep-pane 14 browser-pane 15 browser-pane-navigate 23 browser-pane-busy 23 browser-pane-go-forward 23 browser-pane-go-back 23 browser-pane-stop 23 browser-pane-refresh 23 browser-pane-property-get 25 browser-pane-property-put 25 button 25 button-panel 31 calculate-constraints 36 calculate-layout 37 callbacks 38 call-editor 41 can-use-metafile-p 42 capi-object 42 capi-object-property 43 check-button 44 check-button-panel 45 choice 46 choice-selected-item 50 choice-selected-item-p 52 choice-selected-items 52 choice-update-item 54 clipboard 55 clipboard-empty 57 clone 57 cocoa-default-application-interface 58 cocoa-view-pane 62 cocoa-view-pane-view 63 collect-interfaces 64

collection 65

collection-find-next-string 69

collection-find-string 70

collection-last-search 70

collection-search 71

collector-pane 71

color-screen 73

column-layout 73

component-name 76

confirm-quit 76

confirm-yes-or-no 78

confirmer-pane 78

contain 79

convert-relative-position 80

convert-to-screen 81

count-collection-items 85

current-dialog-handle 85

current-document 87

current-pointer-position 87

current-popup 88

current-printer 89

default-editor-pane-line-wrap-marker 89

default-library 90

define-command 90

define-interface 92

define-layout 98

define-menu 99

define-ole-control-component 100

destroy 102

detach-simple-sink 103

detach-sink 104

display 104

display-dialog 107

display-errors 110

display-message 110

display-message-for-pane 111

display-pane 111

display-pane-selected-text 113

display-pane-selection 113

display-pane-selection-p 114

display-popup-menu 115 display-replacable-dialog 116 display-tooltip 117 docking-layout 118 docking-layout-pane-docked-p 122 docking-layout-pane-visible-p 122 document-container 123 document-frame 124 double-headed-arrow-pinboard-object 128 double-list-panel 129 drag-pane-object 131 draw-metafile 133 draw-metafile-to-image 134 drawn-pinboard-object 136 draw-pinboard-object 137 draw-pinboard-object-highlighted 138 draw-pinboard-object-unhighlighted 138 drop-object-allows-drop-effect-p 139 drop-object-collection-index 139 drop-object-collection-item 141 drop-object-drop-effect 142 drop-object-get-object 143 drop-object-pane-x 144 drop-object-pane-y 144 drop-object-provides-format 145 *echo-area-cursor-inactive-style* 145 echo-area-pane 146 *editor-cursor-color* 146 *editor-cursor-active-style* 147 *editor-cursor-drag-style* 147 *editor-cursor-inactive-style* 148 editor-pane 148 editor-pane-blink-rate 158 editor-pane-buffer 159 *editor-pane-composition-selected-range-face-plist* 160 editor-pane-default-composition-callback 160 *editor-pane-default-composition-face* 162 editor-pane-native-blink-rate 163 editor-pane-selected-text 163 editor-pane-selected-text-p 164

editor-pane-stream 164

editor-window 165

element 165

element-container 172

element-interface-for-callback 173

element-screen 174

ellipse 174

ensure-area-visible 174

ensure-interface-screen 175

execute-with-interface 176

execute-with-interface-if-alive 177

exit-confirmer 178

exit-dialog 179

expandable-item-pinboard-object 180

extended-selection-tree-view 180

filtering-layout 181

filtering-layout-match-object-and-exclude-p 185

find-graph-edge 185

find-graph-node 186

find-interface 187

find-string-in-collection 188

force-screen-update 188

force-update-all-screens 189

foreign-owned-interface 189

form-layout 190

free-metafile 191

free-sound 192

get-collection-item 192

get-constraints 193

get-horizontal-scroll-parameters 193

get-page-area 194

get-printer-metrics 195

get-scroll-position 196

get-vertical-scroll-parameters 197

graph-edge 198

graph-node 199

graph-node-children 199

graph-object 200

graph-pane 200

graph-pane-add-graph-node 204

graph-pane-delete-object 205

graph-pane-delete-objects 205

graph-pane-delete-selected-objects 206

graph-pane-direction 207

graph-pane-edges 208

graph-pane-nodes 208

graph-pane-object-at-position 209

graph-pane-select-graph-nodes 209

graph-pane-update-moved-objects 210

grid-layout 211

hide-interface 216

hide-pane 216

highlight-pinboard-object 217

image-list 217

image-pinboard-object 219

image-set 220

install-postscript-printer 221

installed-libraries 223

interactive-pane 224

interactive-pane-execute-command 226

interface 227

interface-customize-toolbar 244

interface-display 245

interface-display-title 246

interface-document-modified-p 247

interface-editor-pane 248

interface-extend-title 248

interface-geometry 249

interface-iconified-p 250

interface-keys-style 250

interface-match-p 253

interface-menu-groups 254

interface-preserve-state 255

interface-preserving-state-p 255

interface-reuse-p 256

interface-toolbar-state 257

interface-visible-p 259

interpret-description 260

invalidate-pane-constraints 261

invoke-command 261

invoke-untranslated-command 262

item 262

itemp 264

item-pane-interface-copy-object 264

item-pinboard-object 266

labelled-arrow-pinboard-object 267

labelled-line-pinboard-object 267

layout 268

line-pinboard-object 270

line-pinboard-object-coordinates 271

list-panel 272

list-panel-enabled 283

list-panel-filter-state 284

list-panel-items-and-filter 285

list-panel-search-with-function 286

list-panel-unfiltered-items 288

list-view 288

listener-pane 294

listener-pane-insert-value 295

load-cursor 295

load-sound 299

locate-interface 300

lower-interface 301

make-container 302

make-docking-layout-controller 303

make-foreign-owned-interface 303

make-general-image-set 305

make-icon-resource-image-set 306

make-image-locator 307

make-menu-for-pane 307

make-pane-popup-menu 309

make-resource-image-set 311

make-scaled-general-image-set 312

make-scaled-image-set 313

make-sorting-description 314

manipulate-pinboard 315

map-collection-items 318

map-pane-children 319

map-pane-descendant-children 322

map-typeout 323

maximum-moving-objects-to-track-edges 323 menu 324 menu-component 328 menu-item 331 menu-object 337 merge-menu-bars 340 message-pane 342 modify-editor-pane-buffer 342 mono-screen 343 move-line 343 multi-column-list-panel 344 multi-line-text-input-pane 349 non-focus-list-interface 350 non-focus-list-toggle-enable-filter 350 non-focus-list-toggle-filter 351 non-focus-list-add-filter 351 non-focus-list-remove-filter 351 non-focus-maybe-capture-gesture 351 non-focus-terminate 353 non-focus-update 354 ole-control-add-verbs 354 ole-control-close-object 355 ole-control-component 356 ole-control-doc 358 ole-control-frame 359 ole-control-i-dispatch 360 ole-control-insert-object 361 ole-control-ole-object 361 ole-control-pane 362 ole-control-pane-frame 365 ole-control-pane-simple-sink 365 ole-control-user-component 366 option-pane 367 output-pane 371 over-pinboard-object-p 384 page-setup-dialog 385 pane-adjusted-offset 386 pane-adjusted-position 387 pane-close-display 388 pane-descendant-child-with-focus 389

pane-got-focus 390 pane-has-focus-p 390 pane-initial-focus 391 pane-interface-copy-object 392 pane-interface-copy-p 392 pane-interface-cut-object 392 pane-interface-cut-p 392 pane-interface-deselect-all 392 pane-interface-deselect-all-p 392 pane-interface-paste-object 392 pane-interface-paste-p 392 pane-interface-select-all 392 pane-interface-select-all-p 392 pane-interface-undo 392 pane-interface-undo-p 392 pane-popup-menu-items 393 pane-screen-internal-geometry 396 pane-string 397 pane-supports-menus-with-images 398 parse-layout-descriptor 398 password-pane 399 play-sound 400 pinboard-layout 401 pinboard-object 404 pinboard-object-at-position 408 pinboard-object-graphics-arg 409 pinboard-object-overlap-p 410 pinboard-pane-position 411 pinboard-pane-size 412 popup-confirmer 413 popup-menu-button 424 *ppd-directory* 424 print-capi-button 425 print-collection-item 425 print-dialog 427 print-editor-buffer 428 print-file 429 print-rich-text-pane 430 print-text 431 printer-configuration-dialog 431

printer-metrics 432 printer-port-handle 434 printer-port-supports-p 434 *printer-search-path* 435 process-pending-messages 436 progress-bar 437 prompt-for-color 437 prompt-for-confirmation 438 prompt-for-directory 440 prompt-for-file 442 prompt-for-files 445 prompt-for-font 446 prompt-for-form 447 prompt-for-forms 449 prompt-for-integer 450 prompt-for-items-from-list 451 prompt-for-number 452 prompt-for-string 453 prompt-for-symbol 455 prompt-for-value 457 prompt-with-list 458 prompt-with-list-non-focus 461 prompt-with-message 466 push-button 467 push-button-panel 469 quit-interface 470 radio-button 472 radio-button-panel 473 raise-interface 474 range-pane 475 range-set-sizes 476 read-sound-file 477 rectangle 478 redisplay-collection-item 478 redisplay-interface 479 redisplay-menu-bar 479 redraw-pinboard-layout 480 redraw-pinboard-object 481 reinitialize-interface 481 remove-capi-object-property 482

remove-items 483 replace-dialog 484 replace-items 484 report-active-component-failure 485 reuse-interfaces-p 487 rich-text-pane 487 rich-text-pane-character-format 490 rich-text-pane-operation 491 rich-text-pane-paragraph-format 495 rich-text-version 496 right-angle-line-pinboard-object 496 row-layout 497 screen 499 screen-active-interface 501 screen-active-p 501 screen-logical-resolution 502 screen-internal-geometries 503 screen-monitor-geometries 504 screen-internal-geometry 505 screens 506 scroll 507 scroll-bar 509 scroll-if-not-visible-p 511 search-for-item 512 selection 512 selection-empty 514 set-application-interface 514 set-button-panel-enabled-items 516 set-clipboard 516 set-composition-placement 518 set-confirm-quit-flag 519 set-default-editor-pane-blink-rate 519 set-default-interface-prefix-suffix 520 set-default-use-native-input-method 522 set-display-pane-selection 522 set-drop-object-supported-formats 523 set-editor-parenthesis-colors 525 set-geometric-hint 526 set-hint-table 526 set-horizontal-scroll-parameters 527

set-interactive-break-gestures 528

set-list-panel-keyboard-search-reset-time 529

set-object-automatic-resize 530

set-pane-focus 535

set-rich-text-pane-character-format 535

set-rich-text-pane-paragraph-format 538

set-selection 540

set-printer-metrics 541

set-printer-options 542

set-text-input-pane-selection 544

set-top-level-interface-geometry 544

set-vertical-scroll-parameters 546

shell-pane 547

show-interface 548

show-pane 549

simple-layout 549

simple-network-pane 550

simple-pane 550

simple-pane-handle 561

simple-pane-visible-height 562

simple-pane-visible-size 562

simple-pane-visible-width 563

simple-pinboard-layout 564

simple-print-port 565

slider 566

sort-object-items-by 569

sorted-object 570

sorted-object-sort-by 570

sorted-object-sorted-by 571

start-gc-monitor 572

static-layout 573

stop-gc-monitor 574

stop-sound 575

switchable-layout 575

switchable-layout-switchable-children 577

tab-layout 577

tab-layout-panes 582

tab-layout-visible-child 582

text-input-choice 583

text-input-pane 584

text-input-pane-append-recent-items 599

text-input-pane-delete-recent-items 599

text-input-pane-prepend-recent-items 600

text-input-pane-recent-items 601

text-input-pane-replace-recent-items 602

text-input-pane-set-recent-items 602

text-input-pane-complete-text 604

text-input-pane-copy 605

text-input-pane-cut 605

text-input-pane-delete 606

text-input-pane-in-place-complete 606

text-input-pane-paste 607

text-input-pane-selected-text 608

text-input-pane-selection 608

text-input-pane-selection-p 609

text-input-range 610

title-pane 612

titled-menu-object 613

titled-object 614

titled-pinboard-object 618

toolbar 620

toolbar-button 622

toolbar-component 628

toolbar-object 630

top-level-interface 631

top-level-interface-display-state 632

top-level-interface-geometry 633

top-level-interface-geometry-key 634

top-level-interface-p 636

top-level-interface-save-geometry-p 636

tracking-pinboard-layout 637

tree-view 639

tree-view-ensure-visible 649

tree-view-expanded-p 650

tree-view-item-checkbox-status 650

tree-view-item-children-checkbox-status 651

tree-view-update-an-item 652

tree-view-update-item 652

undefine-menu 653

unhighlight-pinboard-object 653

uninstall-postscript-printer 654 unmap-typeout 655 update-all-interface-titles 655 update-interface-title 656 update-pinboard-object 656 update-screen-interface-titles 657 *update-screen-interfaces-hooks* 657 update-toolbar 658 virtual-screen-geometry 658 with-atomic-redisplay 659 with-busy-interface 660 with-dialog-results 661 with-document-pages 663 with-external-metafile 664 with-geometry 667 with-internal-metafile 669 with-output-to-printer 671 with-page 672 with-page-transform 673 with-print-job 673 with-random-typeout 674 wrap-text 675 wrap-text-for-pane 676 x-y-adjustable-layout 677

2 GP Reference Entries 679

2pi 679
analyze-external-image 680
apply-rotation 680
apply-rotation-around-point 681
apply-scale 682
apply-translation 683
augment-font-description 683
clear-external-image-conversions 684
clear-graphics-port 685
clear-graphics-port-state 685
clear-rectangle 686
compress-external-image 687
compute-char-extents 687

convert-external-image 688

convert-to-font-description 689

copy-area 690

copy-external-image 691

copy-pixels 692

copy-transform 693

create-pixmap-port 693

default-image-translation-table 695

define-font-alias 695

destroy-pixmap-port 696

dither-color-spec 696

draw-arc 697

draw-arcs 698

draw-character 699

draw-circle 700

draw-ellipse 701

draw-image 702

draw-line 704

draw-lines 705

draw-path 705

draw-point 709

draw-points 710

draw-polygon 710

draw-polygons 711

draw-rectangle 712

draw-rectangles 713

draw-string 714

ensure-gdiplus 716

external-image 717

external-image-color-table 718

external-image-color-table 718

externalize-and-write-image 719

externalize-image 721

f2pi 722

find-best-font 723

find-matching-fonts 724

font 724

font-description 725

font-description 726

font-description-attributes 727

font-description-attribute-value 727

font-dual-width-p 728

font-fixed-width-p 728

font-single-width-p 729

fpi 730

fpi-by-2 730

free-image 730

free-image-access 731

get-bounds 731

get-character-extent 732

get-char-ascent 733

get-char-descent 733

get-char-width 734

get-enclosing-rectangle 734

get-font-ascent 735

get-font-average-width 736

get-font-descent 736

get-font-height 737

get-font-width 737

get-graphics-state 738

get-origin 738

get-string-extent 739

get-transform-scale 740

graphics-port-background 740

graphics-port-font 740

graphics-port-foreground 740

graphics-port-transform 740

graphics-state 741

image 750

image-access-height 750

image-access-width 750

image-access-pixel 751

image-access-pixels-from-bgra 752

image-access-pixels-to-bgra 753

image-access-transfer-from-image 754

image-access-transfer-to-image 755

image-freed-p 756

image-loader 756

image-translation 757

initialize-dithers 758

inset-rectangle 758 inside-rectangle 759 invalidate-rectangle 760 invert-transform 761 list-all-font-names 761 list-known-image-formats 762 load-icon-image 763 load-image 765 make-dither 767 make-font-description 768 make-graphics-state 769 make-image 769 make-image-access 770 make-image-from-port 771 make-sub-image 772 make-transform 773 merge-font-descriptions 774 offset-rectangle 775 ordered-rectangle-union 775 pi-by-2 776 pixblt 777 pixmap-port 778 port-drawing-mode-quality-p 778 port-graphics-state 779 port-height 780 port-string-height 780 port-string-width 781 port-width 781 postmultiply-transforms 782 premultiply-transforms 782 read-and-convert-external-image 783 read-external-image 784 rectangle-bind 785 rectangle-bottom 786 rectangle-height 786 rectangle-left 787 rectangle-right 787 rectangle-top 788 rectangle-union 788

rectangle-width 789

rect-bind 790 register-image-load-function 790 register-image-translation 791 reset-image-translation-table 792 separation 793 set-default-image-load-function 793 set-graphics-port-coordinates 794 set-graphics-state 795 transform 795 transform-area 796 transform-distance 796 transform-distances 797 transform-is-rotated 797 transform-point 798 transform-points 798 transform-rect 799 undefine-font-alias 800 union-rectangle 800 *unit-transform* 801 unit-transform-p 801 unless-empty-rect-bind 802 untransform-distance 802 untransform-distances 803 untransform-point 803 untransform-points 804 validate-rectangle 805 with-dither 806 with-graphics-mask 806 with-graphics-post-translation 808 with-graphics-rotation 809 with-graphics-scale 810 with-graphics-state 810 with-graphics-transform 812 with-graphics-transform-reset 813 with-graphics-translation 814 with-inverse-graphics 815 without-relative-drawing 815 with-pixmap-graphics-port 816 with-transformed-area 817 with-transformed-point 818

with-transformed-points 819 with-transformed-rect 819 write-external-image 820

3 COLOR Reference Entries 823

apropos-color-alias-names 823 apropos-color-names 824 apropos-color-spec-names 825 color-alpha 826 color-<component>826 *color-database* 827 color-level 828 color-model 829 color-with-alpha 829 colors=830 convert-color 831 define-color-alias 832 define-color-models 833 delete-color-translation 834 ensure-<command>835 get-all-color-names 836 get-color-alias-translation 837 get-color-spec 838 load-color-database 839 make-gray 839 make-hsv 840 make-rgb 841 read-color-db 842 unconvert-color 843

Index 845

Preface

This manual contains reference entries for the functions, classes, macros and accessors in the capi package, and the graphics-ports and color packages. Entries are listed alphabetically, and the typographical conventions used are similar to those used in *Common Lisp: the Language* (2nd Edition). Further details on the conventions used are given below. For a more tutorial approach to the CAPI with further examples see the *CAPI User Guide*.

Note: Although the graphics-ports and color packages are not strictly part of the CAPI, they are included in this manual because the functionality is usually called from CAPI elements such as output panes. Please also see the relevant chapters in the *CAPI User Guide* for further information on Graphics Ports and the LispWorks Color System.

Conventions used for reference entries

Each entry is headed by the symbol name and type, followed by a number of fields providing further details. These fields consist of a subset of the following: "Package", "Summary", "Signature", "Arguments", "Values", "Method Signature", "Initial Value", "Superclasses", "Subclasses", "Initargs", "Accessors", "Readers", "Compatibility Note", "Description", "Notes", "Examples", and "See also".

The default package containing each symbol is the capi package in the CAPI reference chapter, and so on, unless stated otherwise in the "Package" section of an entry.

Throughout, variable arguments, slots and return values are italicised. They look *like this* in the Description.

Throughout, exported symbols are printed like-this. The package qualifier is usually omitted, as if the current package is capi (or graphics-ports or color.)

Entries with a long "Description" section usually have as their first field a short "Summary" providing a quick overview of the purpose of the symbol being described.

The "Signature" section provides details of the arguments taken by the functions and macros.

The "Subclasses" section of each CAPI class entry lists the external subclasses, though not subclasses of those.

The "Superclasses" sections of each CAPI class entry lists the external superclasses, though not superclasses of those.

The "Initargs" section describes the initialization arguments of the class. Initargs of superclasses are also valid.

Note: in LispWorks4.2 and previous versions, the "Initargs" section was headed "Slots".

Examples of the use of commands are given under the "Examples" heading. The code is written with explicit package qualifiers such as capi:interface, so that it can be run as-is, regardless of the current package. Some example files can also be found in your installation directory under examples/capi/.

Finally, the "See also" section provides a reference to other related symbols.

The LispWorks manuals

The LispWorks manual set comprises the following books:

- The LispWorks User Guide and Reference Manual describes the main language-level features and tools available in LispWorks, along with reference pages.
- The *LispWorks IDE User Guide* describes the LispWorks IDE, the user interface for LispWorks. This is a set of windowing tools that help you to develop and test Common Lisp programs.

- The *LispWorks Editor User Guide* describes the keyboard commands and programming interface to the LispWorks IDE editor tool.
- The CAPI User Guide and the CAPI Reference Manual describe the CAPI.
 This is a library of classes, functions, and macros for developing graphical user interfaces for your applications. The CAPI User Guide is a tutorial guide to the CAPI, and the CAPI Reference Manual is an in-depth reference text.
- The LispWorks Foreign Language Interface User Guide and Reference Manual explains how you can use C source code in applications developed using LispWorks.
- The LispWorks Delivery User Guide describes how you can deliver working, standalone versions of your LispWorks applications for distribution to your customers.
- The KnowledgeWorks and Prolog User Guide describes the LispWorks toolkit for building knowledge-based systems. Prolog is a logic programming system within Common Lisp.
- The *Common Lisp Interface Manager 2.0 User's Guide* describes the portable Lisp-based GUI toolkit.

These books are all available in online form, in both HTML format and PDF format. Also in PDF and plain text format is:

The LispWorks Release Notes and Installation Guide which contains notes
explaining how to install LispWorks and get it running. It also contains
a set of release notes which lists new features and any last minute issues
that could not be included in the main manual set.

Commands in the **Help** menu of any of the Common LispWorks tools give you direct access to the online documentation in HTML format, using the HTML browser that is supplied with LispWorks. Details of how to use these commands can be found in the *LispWorks IDE User Guide*.

Documentation is also provided in PDF form. You can use Adobe[®] Reader[®] to browse the PDF documentation online or to print it. Adobe Reader is available from Adobe's web site, http://www.adobe.com/.

Please let us know at lisp-support@lispworks.com if you find any mistakes in the LispWorks documentation, or if you have any suggestions for improvements.

1

CAPI Reference Entries

The following chapter documents symbols exported from the capi package.

abort-callback Function

Summary Aborts out of the context of the current callback.

Package capi

Signature abort-callback &optional always-abort

Arguments always-abort A generalized boolean.

Description The function abort-callback aborts out of the context of the

current callback, returning mil when it is relevant (for exam-

ple in an interface confirm-destroy-callback).

If called outside the context of a callback, if *always-abort* is t then abort-callback calls (abort), otherwise it just returns.

The default value of always-abort is t.

See also callbacks interface

abort-dialog Function

Summary The abort-dialog function aborts the current dialog.

Package capi

Signature abort-dialog &rest ignored-args

Description This function is used to abort the current dialog. For example,

it can be made a selection callback from a **Cancel** button so that pressing the button aborts the dialog. In a similar manner the complementary function <code>exit-dialog</code> can be

used as a callback for an **OK** button.

If there is no current dialog then abort-dialog does nothing and returns nil. If there is a current dialog then abort-dialog either returns non-nil or does a non-local exit.

abort-dialog either returns non-nil or does a non-local exit. Therefore code that depends on abort-dialog returning must be written carefully. Constructs like this can be useful:

```
(unless (capi:abort-dialog)
  (foo))
```

Above, foo will be called only if there is no current dialog.

It is not useful to do either:

```
(when (capi:abort-dialog)
  (foo))
Or
(progn
  (capi:abort-dialog)
  (foo))
```

as in both cases it is not well-defined whether *foo* will be called if there is a current dialog.

Example (capi:display-dialog

(capi:make-container

(make-instance 'capi:push-button

:text "Cancel"

:callback 'capi:abort-dialog)

:title "Test Dialog"))

Also see the examples in the directory

examples/capi/dialogs/.

See also exit-dialog

display-dialog
popup-confirmer

interface

abort-exit-confirmer

Function

Summary Aborts the exiting of a dialog.

Package capi

Signature abort-exit-confirmer

Description The function abort-exit-confirmer can be used to abort

the exiting of a confirmer. It can be used in the ok-function of a

confirmer, to abort the exit and return to the dialog.

If abort-exit-confirmer is called outside the exiting of a

confirmer, it does nothing.

Example This example asks the user for a string. If the string is longer

than 20 characters, it confirms with the user that they really want such a long string, and if they do not it returns to the

dialog.

See also popup-confirmer

accepts-focus-p

Generic Function

Summary Determines if an element accepts the focus.

Package capi

Signature accepts-focus-p element => result

Arguments *element* A CAPI element.

Values result A boolean.

Description Determines if the element *element* accepts the focus for user

input, and controls tabstops.

The method on element uses the value of the *accepts-focus-p* slot, but methods on some subclasses override this.

accepts-focus-p also influences whether a pane is a tabstop. On Microsoft Windows a pane acts as a tabstop if and only if the function accepts-focus-p returns true and the element accepts-focus-p initarg value is :force. On Motif and Cocoa, a pane acts as a tabstop if and only if the function accepts-focus-p returns true.

See also element

pane-has-focus-p

set-object-automatic-resize

activate-pane Function

Summary The activate-pane function gives the focus to a pane and

brings the window containing it to the front.

Package capi

Signature activate-pane pane

Description This brings the window containing *pane* to the front, and

gives the focus to the pane (or a sensible alternative inside the same interface if that pane cannot accept the focus).

Example This example demonstrates how to swap the focus from one

window to another.

'capi:text-input-pane)))

(setq button

(capi:activate-pane text-input-pane)

(capi:activate-pane button)

See also hide-interface

raise-interface

set-object-automatic-resize

show-interface
quit-interface
simple-pane

1 CAPI Reference Entries

active-pane-copy
active-pane-cut
active-pane-cut-p
active-pane-deselect-all
active-pane-deselect-all-p
active-pane-paste
active-pane-paste-p
active-pane-select-all
active-pane-select-all
active-pane-select-all-p
active-pane-undo

Functions

Summary Perform, or check applicability of, an "edit/select operation"

on the active pane.

Signature active-pane-copy &optional pane

active-pane-copy-p &optional pane

active-pane-cut &optional pane

active-pane-cut-p &optional pane

active-pane-deselect-all &optional pane

active-pane-deselect-all-p &optional pane

active-pane-paste &optional pane

active-pane-paste-p &optional pane

active-pane-select-all &optional pane

active-pane-select-all-p &optional pane

active-pane-undo &optional pane

active-pane-undo-p &optional pane

Description

These functions perform an "edit/select operation" on the active pane, or check if this operation is currently applicable.

The active pane will be the one on the same screen as *pane* if *pane* is non-nil, or otherwise the same screen as the default interface.

These functions find the active pane, that is the pane where keyboard input currently goes. Note that this is not necessarily a pane that is recognized by CAPI. The predicates (those with names ending -p) return true if the operation is currently applicable. The other functions tell the active pane to do the operation.

The edit/select operations are implemented by the pane-interface-* generic functions such as pane-interface-copy-object.

It is not an error to do the operation even if the predicate returns false. It will just do nothing useful.

Examples

See examples/capi/applications/rich-text-edi-

tor.lisp

See also pane-interface-copy-object

append-items

Generic Function

Summary Adds to the items in a collection.

Signature append-items collection new-items

Arguments *collection* A collection.

new-items A sequence.

Description The generic function append-items adds the items in new-

items to the collection collection.

1 CAPI Reference Entries

This is logically equivalent to recalculating the collection items and calling (setf collection-items). However, append-items is more efficient and causes less flickering on screen.

append-items can only be used when the collection has the default items-get-function svref.

See also

collection
remove-items
replace-items

apply-in-pane-process

Function

Summary Applies a function in the process associated with a pane.

Package

capi

Signature

apply-in-pane-process pane function &rest args => nil

Description

The function apply-in-pane-process applies function to args in the process that is associated with pane. This is required when function modifies pane or changes how it is displayed. If pane has not been displayed yet, then function is called immediately.

Notes

- All accesses (reads as well as writes) on a pane should be performed in the pane's process. Within a callback on the pane's interface this happens automatically, but applyin-pane-process is a useful utility in other circumstances.
- **2.** apply-in-pane-process calls *function* on the current process if the pane's interface does not have a process.
- If the pane's process is no longer active then apply-inpane-process applies function directly.

4. apply-in-pane-process-if-alive is another way to call *function* in the CAPI process appropriate for *pane*. However it only does this if *pane* is alive so in particular, if *pane* does not have a process, it does not call *function*.

Example

Editor commands must be called in the correct process:

apply-in-pane-process-if-alive

Function

Summary Applies a function in the process associated with a pane.

Package capi

Signature apply-in-pane-process-if-alive pane function &rest args =>

nil

Description The function apply-in-pane-process-if-alive applies

function to args in the process that is associated with pane, if

pane is alive.

This is like apply-in-pane-process except that function is called only if the pane is alive in the sense defined for the interface in execute-with-interface-if-alive. If pane does not have a process, then function is not called.

See also apply-in-pane-process

execute-with-interface-if-alive

arrow-pinboard-object

Class

Summary A pinboard-object that draws itself as an arrow.

Package capi

Superclasses line-pinboard-object

Subclasses double-headed-arrow-pinboard-object

labelled-arrow-pinboard-object

Initargs : head A keyword specifying the position of the

arrowhead on the line.

:head-direction

A keyword specifying the direction of the

arrowhead.

:head-length The length of the arrowhead.

:head-breadth The breadth of the arrowhead, or nil.

:head-graphics-args

A graphics args plist.

Description An instance of the class arrow-pinboard-object is a

pinboard-object that draws itself as an arrow.

head must be :end, :middle or:start. The default is :end.

head-direction must be :forwards, :backwards or :both. The

default is : forwards.

head-length is the length of the arrowhead in pixels. It defaults

to 12.

head-breadth is the breadth of the arrowhead in pixels, or mil

which means that the breadth is half of *head-length*. The

default is nil.

head-graphics-args is a plist of graphics state parameters and values used when drawing the arrow head. For information

about the graphics state, see graphics-state.

```
Example
              (capi:contain
               (make-instance
                'capi:pinboard-layout
                :description
                (list
                 (make-instance 'capi:arrow-pinboard-object
                                :start-x 5 :start-y 10
                                :end-x 105 :end-y 60 )
                 (make-instance 'capi:arrow-pinboard-object
                                :start-x 5 :start-y 110
                                :end-x 105 :end-y 160
                                :head :middle)
                 (make-instance 'capi:arrow-pinboard-object
                                :start-x 5 :start-y 210
                                :end-x 105 :end-y 260
                                :head-direction :both )
                 (make-instance 'capi:arrow-pinboard-object
                                :start-x 5 :start-y 310
                                :end-x 105 :end-y 360
                                :head-graphics-args
                                '(:foreground :pink)
                                :head-length 30)
                 (make-instance 'capi:arrow-pinboard-object
                                :start-x 5 :start-y 410
                                :end-x 105 :end-y 460
                                :head-length 30 :head-breadth 5)
                 (make-instance 'capi:arrow-pinboard-object
                                :start-x 5 :start-y 510
                                :end-x 105 :end-y 560
                                :head-breadth 10
                                :head-direction :backwards))
                :visible-min-width 120
                :visible-min-height 620))
```

attach-interface-for-callback

Function

Summary Changes the interface that is passed when a callback is made.

Package capi

Signature attach-interface-for-callback element interface

CAPI Reference Entries

Description The function attach-interface-for-callback changes

> the interface that is passed when a callback is made. Callbacks for *element* get passed *interface* instead of *element*'s

parent interface.

See also callbacks

element

element-interface-for-callback

interface

attach-simple-sink

Function

Summary Attaches a sink to the active component in an ole-control-

pane.

Package capi

Signature attach-simple-sink invoke-callback pane interface-name &key

sink-class => sink

Arguments invoke-callback A function designator.

> pane An ole-control-pane.

interface-name A refguid or the symbol :default.

sink-class A symbol naming a class.

Values sink The sink object.

Description The function attach-simple-sink make a sink object and

attaches it to the active component in pane.

When an event callback is triggered for the source interface named by *interface-name*, the sink object will call the *invoke*callback with four arguments: the pane (see sink-class below), the source method name as a string, the source method type (either:method,:get or:put) and a vector of the remaining

callback arguments.

interface-name is either a string naming a source interface that
the component in pane supports or :default to connect to
the default source interface.

sink-class can be used to control the class of the sink object. This defaults to ole-control-pane-simple-sink, but can be a subclass of this class to allow the first argument of the invoke-callback to be chosen by a method on the generic function com:simple-i-dispatch-callback-object.

Attached sinks are automatically disconnected when the object is closed or can be manually disconnected by calling detach-simple-sink.

Notes This function is implemented only in LispWorks for Win-

dows. Load the functionality by (require "embed").

See also detach-simple-sink

ole-control-pane

ole-control-pane-simple-sink

attach-sink Function

Summary Attaches a sink to the active component in an ole-control-

pane.

Package capi

Signature attach-sink sink pane interface-name

Arguments *sink* A class instance.

pane An ole-control-pane.

interface-name A refguid or the symbol :default.

Description The function attach-sink attaches a sink to the active

component in the the ole-control-pane pane.

1 CAPI Reference Entries

sink is an instance of a class that implements the source interface *interface-name*.

pane is an ole-control-pane which is the pane where the component is.

interface-name is either a string naming a source interface that
the component in pane supports or :default to connect to
the default source interface.

Attached sinks are automatically disconnected when the object is closed or can be manually disconnected by calling detach-sink.

Notes This function is implemented only in LispWorks for Win-

dows. Load the functionality by (require "embed").

See also detach-sink

ole-control-pane

beep-pane Function

Summary Sounds a beep.

Package capi

Signature beep-pane &optional pane

Description The function beep-pane sounds a beep on the screen associ-

ated with pane or on the current screen if pane is nil.

Example (capi:beep-pane)

See also simple-pane

screen

browser-pane Class

Summary Embeds a pane that can display HTML. Implemented only

on Microsoft Windows and Cocoa.

Superclasses simple-pane

Subclasses None

InitargS :before-navigate-callback

A function that is called before navigating,

or nil.

:navigate-complete-callback

A function that is called when navigation

completes, or nil.

:new-window-callback

A function that is called before opening a

new window, or mil.

:status-text-change-callback

A function that is called when there is a new

status text or mil.

:document-complete-callback

A function that is called when a document is

complete, or mil.

:title-change-callback

A function that is called when the title

changes, or mil.

:update-commands-callback

A function that is called when the enabled

status of commands related to the pane may

need to change, or mil.

:internet-explorer-callback

Microsoft Windows specific: A function that is whenever there is an event from the underlying IWebBrowser2, or nil.

:navigate-error-callback

A function that is called when the pane fails to navigate, or mil.

:debug A boolean specifying whether debugging

mode is on or not.

:url A string specifying the initial URL.

Accessors browser-pane-navigate-complete-callback

browser-pane-new-window-callback

browser-pane-status-text-change-callback browser-pane-document-complete-callback browser-pane-title-change-callback browser-pane-update-commands-callback browser-pane-internet-explorer-callback browser-pane-before-navigate-callback browser-pane-navigate-error-callback

browser-pane-debug

Readers browser-pane-url

browser-pane-successful-p

browser-pane-title

Description

A browser-pane is a pane that embeds a pane that can display HTML. Navigation in the pane happens either by the user clicking on hyperlinks, or by the application using browser-pane-navigate. The various callbacks gives the program information on what happens in the window and can be used to control (for example, to block or redirect pages).

browser-pane is implemented only on Microsoft Windows (where it embeds an IWebBrowser2) and Cocoa (where it uses WebKit).

The initarg :url specifies the initial URL. After being created, the pane automatically navigates to this URL.

When *before-navigate-callback* is non-nil, it is called before any navigation (whether programmatic or by the user), and gives the application control over whether to perform the navigation. The callback must have this signature:

before-navigate-callback pane url &key hyper-link-p subframe-p frame-name post-data headers &allow-other-keys => doit-p

before-navigate-callback pane url &key sub-frame-p frame-name &allow-other-keys => do-it

pane is the pane that navigates, and *url* is a string to which it wants to navigate. *sub-frame-p* is true when the navigation is for a sub-frame inside the current URL, otherwise *sub-frame-p* is nil. *frame-name* is either nil or the name of a sub-frame when the navigation is to a sub-frame.

If *before-navigate-callback* returns nil, the navigation is cancelled.

Note: To perform a redirection, just call browser-pane-navigate to the required URL, and return nil from before-navigate-callback.

If *new-window-callback* is non-nil, it is called before the pane tries to open a new window. It must have this signature:

new-window-callback pane url &key context flags &allowother-keys => do-it-p

pane is the pane that wants to open a new window, and *url* is a string containing the URL that the new window will navigate to. *context* is a string containing the URL of the page from which the request comes.

flags is implementation specific flags. On Cocoa *flags* is always 0. On Microsoft Windows *flags* contains bits from the NWMF enumeration.

If new-window-callback returns mil, the opening of the new window is cancelled. If new-window-callback returns t or is not supplied, it launches a browser using the OS settings.

On Microsoft Windows, *new-window-callback* is invoked from the "NewWindow3" event (or "NewWindow2" for old versions) of the sink of the underlying IWebBrowser2. If not cancelled, the pane opens a new normal Internet Explorer window.

If *document-complete-callback* is non-nil, it is called when the new document in the pane is complete. It must be a function with signature:

document-complete-callback => pane url title

url is the loaded URL, and may be nil in the case of failure. title is a string that is associated with the URL url (or the previous URL if the latest call failed).

document-complete-callback is called when, as far as the system is concerned, all the data for the URL has been loaded and is displayed in the pane. There is only one call to document-complete-callback for each navigation of the pane.

If *navigate-complete-callback* is non-nil, it is called whenever a navigation completes. *navigate-complete-callback* can be called several times for each navigation of the pane. It must be a function with the signature:

navigate-complete-callback pane url sub-frame-p =>

pane is the pane that is navigated. *url* is a string to which it navigated, unless the navigation failed, in which case *url* is nil. *sub-frame-p* is true when the navigation was in a subframe.

Notes: For most puposes the *document-complete-callback* is more useful than *navigate-complete-callback*. When *navigate-complete-callback* gets a nil *url*, the value of the URL in the

pane (that is, what the accessor browser-pane-url returns) is still set to the actual URL. The success flag (which you can read with browser-pane-successful-p) is set to nil.

url can be non-nil even if there was an error in the navigation, if the server supplied another URL. In this case, on Microsoft Windows only, the success flag is set to :redirected. You can read it with browser-pane-successful-p.

If *navigate-error-callback* is non-nil, it is called when navigation fails for some reason. It should have this signature:

navigate-error-callback pane url &key http-code error-symbol implementation-error-code message frame-name sub-frame-p fatal &allow-other-keys => cancel

pane is the navigating pane, and *url* is the URL that got the error.

If the failure is server-side failure, then *http-code* contains the http-code in the response of the server, otherwise (that is, when it failed to connect to a server) it is nil.

error-symbol is a keyword uniquely identifying the error. For an http error it is of the form :http_status*, and for requests with bad syntax error-symbol is :bad-request.

On Microsoft Windows *implementation-error-code* is the code in the "NavigateError" event. If *http-code* is non-nil then *implementation-error-code* and *http-code* will be the same. On Cocoa *implementation-error-code* will be the same as *http-code* in the case of server-side failure, otherwise it is one of the NSURLEr-ror* constants.

fatal is a boolean. A non-nil value means that nothing is going to be displayed in the pane to tell the user about the error.

message is a message saying what the error is. sub-frame-p is t when the navigation is for a sub-frame, otherwise nil. frame-name is the name of the frame.

The return value *cancel* of *navigate-error-callback* should be one of nil, t, or :stop, with these interpretations:

1 CAPI Reference Entries

On Microsoft Windows this means displaying either the substitution page from the server if there is one, or displaying automatically generated (by the underlying IWebBrowser2) error page.

t Cancel. On Microsoft Windows this means not displaying the automatically generated error page, but displaying server substitution if there is any.

stop Stop the navigation immediately.

Note that the effect of the returned value *cancel* is only on the specific navigation, so it possible for a sub-frame to be stopped, while the main page and maybe other sub-frames complete.

On Cocoa there is no automatically generated error page, so the return value of *cancel* mil means the same as t, and both display whatever the server returned.

Note: To redirect on error, *navigate-error-callback* should just call browser-pane-navigate with the new page and return :stop.

If *title-change-callback* is non-nil, it is called when the title of the pane should change. It should have this signature:

title-change-callback pane new-title

new-title is a string, which the application should use as the title of the pane.

Note: In most cases, using the *title* argument of the *document-complete-callback* is more useful.

If *status-text-change-callback* is non-nil, it is called when the status text of the pane should change. It has this signature:

status-text-change-callback pane new-status-text

new-status-text is a string, which the application should use as the status text for the pane.

If *update-commands-callback* is non-nil, it is called when other panes (typically buttons or menu items) that are used to perform commands on the pane need to update. The callback has this signature:

update-commands-callback pane what enabled-p

Currently what can be one of:

:forward Other panes that are used to go forward in

the pane should be enabled or disabled.

:backward Other panes that are used to go backward in

the pane should be enabled or disabled.

Additionally on Microsoft Windows only, what can be:

t Other panes that may try to anything with

the pane may need updating. Note that this callback is called quite often with what = t, so make sure it usually does not do much

work in this case.

enabled-p specifies whether the other panes should be enabled or disabled.

On Windows only, if *internet-explorer-callback* is non-nil, it is called for each event for the pane. It has the signature

internet-explorer-callback pane event-name args

event-name is a string specifying the event. args is a vector containing the arguments in order. The callback is called before any code that is used to implement the callbacks, which is called afterwards withe same argument vector. That means that the callback should not set anything in the vector, except when debugging.

internet-explorer-callback is intended to add functionality that is not given by the callbacks, and for debugging (but see also :debug). If you need more control, you probably wants to define your pane directly: for the basics see examples/com/ole/html-pane.lisp.

debug specifies that the pane should be in debugging mode. Currently, on Microsoft Windows this means that it prints each event and the arguments that it receives. Whenever an event is sent to the sink associated with the embedded browser, the method name (which is the same as the event name in this case) and the argument are printed to mp:*background-standard-output*. On Cocoa it prints some diagnostics to mp:*background-standard-output*.

browse-pane-url returns the current *url* of the pane. Initially the value is the keyword :url, but once the browser completed navigation to some URL it is changed to this. Note that the *url* changes even if the navigation was not successful, as long as it was not stopped or cancelled and there was no substitution page.

browse-pane-title returns the title of the current document. Note that during navigation browse-pane-title and browse-pane-url may not be synchronised. They are synchronised when *document-complete-callback* is called, until the next *before-navigate-callback* call.

browser-pane-successful-p tests whether the navigation to the current URL completed successfully, returning nil for failure and t for success. On Microsoft Windows only it can also return: substituted, which means that the server returned an error but also supplied a substitution page. On Cocoa, browser-pane-successful-p returns only t or nil.

Notes

browser-pane and related APIs are implemented on Microsoft Windows and Cocoa only.

See also

browser-pane-navigate
browser-pane-busy
browser-pane-refresh

browser-pane-navigate browser-pane-busy browser-pane-go-forward browser-pane-go-back browser-pane-stop browser-pane-refresh

Generic Functions

Summary Controls a browser-pane.

Signature browser-pane-navigate pane url => result

browser-pane-busy pane => result

browser-pane-go-back pane

browser-pane-go-forward pane

browser-pane-stop pane

browser-pane-refresh pane &optional level

Arguments pane A browser-pane.

url A string.

level One of the keywords :normal and

:refresh completely.

Values result A boolean.

name A string.

Description These generic functions are used to control an instance of

browser-pane.

browser-pane-navigate navigates to the supplied URL, that is it gets and displays the contents of the URL. Note that if there is any redirection, it is the redirected URL that is dis-

played.

browser-pane-navigate does the navigation asynchronously, so when the function returns the navigation has just started. If *result* is then the navigation started, and if *result* is nil then some error in the url has already been detected. If the pane has an error callback, it already has been called in this case.

Note: browser-pane-navigate can be used to effect a redirection from inside the error before navigation and newwindow callbacks.

browser-pane-busy tests whether the browser is currently navigating, returning true if it is.

browser-pane-go-forward and browser-pane-go-back navigate forward and back in the history, like the buttons on most web browsers.

browser-pane-stop stops the current navigation.

browser-pane-refresh refreshes the pane, which means rereading the URL. *level* can be one of:

:normal Asks the server for the contents again. This is the default value of *level*.

:refresh completely

Asks the server for the contents again without looking at any cache (it uses header Pragma:no-cache).

Notes browser-pane and related APIs are implemented on Microsoft Windows and Cocoa only.

See also browser-pane

browser-pane-property-get browser-pane-property-put

Generic Functions

Summary	Get or set value of a specified Windows property of the underlying browser.	
Signature	browser-pane-property-get pane property-name browser-pane-property-put pane property-name value	
Description	<i>property-name</i> has to be one of the properties listed in the Properties section of the documentation of IWebBrowser2 in the MSDN.	
Notes	 browser-pane-property-get and browser-pane- property-put are implemented on Microsoft Windows only. 	
	2. browser-pane-property-get and browser-pane- property-put do not correspond to the methods "Get- Property" and "PutProperty" of IWebBrowser2.	
See also	browser-pane	

button	Class
Summary	A button is a pane that displays either a piece of text or an image, and that performs an action when pressed. Certain types of buttons can also be selected and deselected.
Package	capi
Superclasses	simple-pane item
Subclasses	<pre>push-button radio-button check-button</pre>

Initargs :interaction The interaction style for the button.

:selected For radio button and check button styles, if

selected is set to t, the button is initially

selected.

:callback Specifies the callback to use when the button

is selected.

:image An image for the button (or nil).

:selected-image

The image used when the button is selected.

:enabled If nil the button cannot be selected.

:cancel-p If true the button is the "Cancel" button, that

is, the button selected by the Escape key.

:default-p If true the button is the default button, that

is, the button selected by the Return key.

The following two initargs controlling alternate images apply only on Motif and Microsoft Windows:

:disabled-image

The image for the button when disabled (or nil).

:selected-disabled-image

The image used when the button is selected and disabled.

The following initary controlling another alternate image applies only on GTK+ and Motif and Microsoft Windows:

:armed-image The image used when the button is pressed and interaction is :no-selection.

The following initargs controlling mnemonics apply only on Microsoft Windows:

:mnemonic A character, integer or symbol specifying a

mnemonic for the button.

:mnemonic-text

A string specifying the text and a mnemonic.

:mnemonic-escape

A character specifying the mnemonic escape. The default value is #\&.

Accessors

button-selected
button-image
button-armed-image
button-selected-image
button-disabled-image
button-selected-disabled-image
button-enabled
button-cancel-p
button-default-p

Description

The class button is the class that push-button, radio-button, and check-button are built on. It can be displayed either with text or an image, and a callback is called when the button is clicked. It inherits all of its textual behavior from item, including the slot *text* which is the text that appears in the button.

Rather than creating direct instances of button, you usually create instances of its subclasses, each of which has a specific interaction style. Occasionally it may be easier to instantiate button directly with the appropriate value of *interaction* (for instance, when the interaction style is only known at runtime) but you may not use such a button as an item in a button-panel.

The values allowed for *interaction* are as follows:

:no-selection A push button.

:single-selection

A radio button.

:multiple-selection

A check button.

Both radio buttons and check buttons can have a selection which can be set using the initarg :selected and the accessor button-selected.

The button's callback gets called when the user clicks on the button, and by default gets passed the data in the button and the interface. This can be changed by specifying a callback type as described in the description of callbacks. The following callbacks are accepted by buttons:

:selection-callback

Called when the button is selected.

:callback For buttons this is a synonym of :selection-callback.

:retract-callback

Called when the button is deselected.

By default, image and disabled-image are nil, meaning that the button is a text button, but if image is provided then the button displays an image instead of the text. The image can be an external-image or any object accepted by load-image, including a .ico file on Microsoft Windows. The disabled image is the image that is shown when the button is disabled (or nil, meaning that it is left for the window system to decide how to display the image as disabled). On some platforms the system computes the disabled image and so disabled-image is ignored.

The button's actions can be enabled and disabled with the *enabled* slot, and its associated accessor button-enabled. This means that when the button is disabled, pressing on it does not call any callbacks or change its selection.

Note that the class button-panel provides functionality to group buttons together, and should normally be used in preference to creating individual buttons yourself. For instance, a radio-button-panel makes a number of radio buttons and also controls them such that only one button is ever selected at a time

A mnemonic is an underlined character within the button *text* or the printed representation of the button *data* which can be entered to select the button. The value *mnemonic* is interpreted as described for menu.

An alternative way to specify a mnemonic is to pass *mnemonic-text*. This is a string which provides the text for the button and also specifies the mnemonic character. *mnemonic-text* and *mnemonic-escape* are interpreted in just the same way as the *mnemonic-title* and *mnemonic-escape* of menu.

Notes

- 1. The simple-pane initary foreground is not supported for buttons on Windows and Cocoa.
- 2. The *disabled-image*, *armed-image* and *selected-disabled-image* will work on Microsoft Windows provided you are running with the themed look-and-feel (which is the default). See "Using Windows themes" in the *CAPI User Guide*.

Example

In the following example a button is created. Using the button-enabled accessor the button is then enabled and disabled.

In the next example a button with an image instead of text is created.

```
(setq button
      (capi:contain
       (make-instance
        'capi:push-button
        :image
        (merge-pathnames
         "capi/applications/images/info.bmp"
         (sys:lispworks-dir "examples")))))
The following examples illustrate mnemonics:
(defun egg (&rest ignore)
  (declare (ignore ignore))
  (capi:display-message "Egg"))
(capi:contain
 (make-instance 'capi:push-button
                :selection-callback 'egg
                :mnemonic-text "Chicken && Rice"))
(capi:contain
 (make-instance 'capi:push-button
                :data "Chicken"
                :selection-callback 'egg
                :mnemonic #\k))
Compare this with the previous example: the #\k does not
appear and the #\e becomes the mnemonic:
(capi:contain
 (make-instance 'capi:push-button
                :selection-callback 'egg
                 :mnemonic-escape #\k
                :mnemonic-text "Chicken"))
Also see the example in the directory
examples/capi/buttons/.
button-panel
```

See also

callbacks

button-panel Class

Summary The class button-panel is a pane containing a number of

buttons that are laid out in a particular style, and that have

group behavior.

Package capi

Superclasses choice

titled-object
simple-pane

Subclasses push-button-panel

radio-button-panel
check-button-panel

Initargs :layout-class The type of layout for the buttons.

:layout-args Initialization arguments for the layout.

:callbacks The selection callbacks for each button.

:button-class The class of the buttons.

:images A list.

:disabled-images

A list.

:armed-images A list.

:selected-images

A list.

:selected-disabled-images

A list.

:help-keys A list.

:default-button

Specifies the default button.

:cancel-button

Specifies the cancel button.

The following initargs controlling mnemonics apply only on Microsoft Windows:

:mnemonics A list specifying mnemonics for the buttons.

:mnemonic-items

A list of strings, each specifying the text and a mnemonic.

:mnemonic-escape

A character specifying the mnemonic escape. The default value is #\&.

:mnemonic-title

A string specifying the title and a mnemonic.

Accessors pane-layout

Description

The class button-panel inherits most of its behavior from choice, which is an abstract class providing support for handling items and selections. By default, a button panel has single selection interaction style (meaning that only one of the buttons can be selected at any one time), but this can be changed by specifying an *interaction*.

The subclasses push-button-panel, radio-button-panel and check-button-panel are provided as convenience classes, but they are just button panels with different interactions (:no-selection, :single-selection and :multiple-selection respectively).

The layout of the buttons is controlled by a layout of class layout-class (which defaults to row-layout) but this can be changed to be any other CAPI layout. When the layout is created, the list of initargs layout-args is passed to make-instance.

Each button uses the callbacks specified for the button panel itself, unless the argument *callbacks* is specified. *callbacks* should be a list (one element per button). Each element of *callbacks*, if non-nil, will be used as the selection callback of the corresponding button.

button-class, if supplied, determines the class used for each of the buttons. This should be the class appropriate for the *interaction*, or a subclass of it. The default behavior is to create buttons of the class appropriate for the *interaction*.

Each of images, disabled-images, armed-images, selected-images, selected-disabled-images and help-keys, if supplied, should be a list of the same length as items. The values are passed to the corresponding item, and interpreted as described for button. The button-panel images values map to button image arguments, and so on.

For button-panel and its subclasses, the *items* supplied to the :items initarg and (setf collection-items) function can contain button objects. In this case, the button is used directly in the button panel rather than a button being created by the CAPI.

This allows button size and spacing to be controlled explicitly. Note that the button must be of the appropriate type for the subclass of button-panel being used, as shown in the following table:

Button panel class	Button class
push-button-panel	push-button
radio-button-panel	radio-button
check-button-panel	check-button

Table 1.1 Button and panel classes

For example,

default-button specifies which button is the default (selected by pressing Return). It should be equal to a member of items when compared by test-function. If the items are non-immediate objects such as strings or button objects, you must ensure either that the same (eq) object is passed in items as in default-button, or that a suitable test-function is supplied.

cancel-button specifies which button is selected by pressing Escape. The comparison with members of items is as for default-button.

mnemonics is a list of the same length as *items*. Each element is a character, integer or symbol specifying the mnemonic for the corresponding button in the same way as described for menu.

mnemonic-items is an alternate way to specify the mnemonics in a button panel. It is a list of the same length as *items*. Each element is a string which is interpreted for the corresponding button as its *mnemonic-text* initarg.

mnemonic-title and mnemonic-escape are interpreted as for menu. mnemonic-escape specifies the escape character for mnemonics both in the buttons and in the pane's title.

Compatibility note

Button panels now default to having a maximum size constrained to their minimum size as this is useful when attempting to layout button panels into arbitrary spaces without them changing size. To get the old behavior, specify :visible-max-width nil in the make-instance.

Example

```
(capi:contain (make-instance
               'capi:button-panel
               :items '(:red :green :blue)
               :print-function 'string-capitalize))
(setq buttons
      (capi:contain
       (make-instance
        'capi:button-panel
        :items '(:red :green :blue)
        :print-function 'string-capitalize
        :interaction :multiple-selection)))
(capi:apply-in-pane-process
buttons #'(setf capi:choice-selected-items)
'(:red :green) buttons)
(capi:contain (make-instance
               'capi:button-panel
               :items '(1 2 3 4 5 6 7 8 9)
               :layout-class 'capi:grid-layout
               :layout-args '(:columns 3)))
```

This example illustrates use of *default-button* and *test-function*:

Also see the example in the directory examples/capi/buttons/.

1 CAPI Reference Entries

See also radio-button

check-button push-button

set-button-panel-enabled-items

calculate-constraints

Generic Function

Summary Calculates the internal constraints of a pane.

Package capi

Signature calculate-constraints pane

Arguments *pane* A CAPI pane or layout.

Description The generic function calculate-constraints calculates the

internal constraints for *pane* according to the sizes of its children, and sets these values into *pane*'s geometry cache.

When the pane does not scroll in the relevant dimension, all the geometry hints (:external-min-width, :visible-max-height and so on) override the values that are computed by calculate-constraints.

See "Width and Height Constraints" in the *CAPI User Guide* for description of internal and external constraints.

The CAPI calls calculate-constraints for each pane and layout that it displays.

When creating your own layout, you should define a method for calculate-constraints that sets the values of the following geometry slots based on the constraints of its children.

%min-width% The minimum width of pane.

%max-width% The maximum width of pane.

%min-height% The minimum height of pane.

%max-height% The maximum height of pane.

(See with-geometry.)

The constraints of any CAPI element can be found by calling get-constraints.

See also

calculate-layout
define-layout
get-constraints
element

element layout

with-geometry

calculate-layout

Generic Function

Summary The calculate-layout generic function is used to provide a

method for laying out the children of a new layout.

Package capi

Signature calculate-layout layout x y width height

Description The generic function calculate-layout is called by the

CAPI to layout the children of a layout. When defining a new class of layout using define-layout, a calculate-layout method must be provided that sets the x, y, width and height of each of the layout's children. This method must try to obey the constraints specified by its children (its minimum and maximum size) and should only break them when it becomes impossible to fit the constraints of all of the children.

To set the *x*, *y*, *width* and *height* of the layout, use the macro with-geometry which works in a similar way as with-slots.

1 CAPI Reference Entries

See also get-constraints

with-geometry

interpret-description

callbacks Class

Summary The class callbacks is used as a mixin by classes that pro-

vide callbacks.

Package capi

Superclasses capi-object

Subclasses collection

item

menu-object

Initargs :callback-typeThe type of arguments for the callbacks.

:selection-callback

The callback for selecting an item.

:extend-callback

The callback for extending the selection.

:retract-callback

The callback for deselecting an item.

:action-callback

The callback for an action.

:alternative-action-callback

The callback for an alternative action in

choice and its subclasses.

Accessors

callbacks-callback-type
callbacks-selection-callback
callbacks-extend-callback
callbacks-retract-callback
callbacks-action-callback

Description

Each callback function can be one of the following:

function Call the function.

list Apply the head of the list to the tail.

:redisplay-interface

Call redisplay-interface on the top-level interface.

:redisplay-menu-bar

Call redisplay-menu-bar on the top-level interface

The slot value *callback-type* determines which arguments get passed to each of the callbacks. It can be any of the following values, and passes the corresponding data to the callback function:

:collection-data

(collection data)

:data (item-data)

:data-element (item-data element)

:data-interface

(item-data interface)

:element (element)

:element-data (element item-data)

:element-item (element item)

:interface-data

(interface item-data)

:item (item)

callback-type can also be a list containing any of :focus, :data, :element, :interface, :collection, :item.

The *item-data* variable is the item's data if the item is of type item, otherwise it is the item itself, as for *item*. The *item* variable means the item itself. The *interface* is the element-interface of the element. *collection* is the element's collection, if there is one. The *element* variable means the element containing the callback itself.

In a choice, the *alternative-action-callback* is invoked by a gesture which is the *action-callback* gesture modified by the Shift key on Windows and GTK+, and modified by the Command key on Cocoa.

alternative-action-callback is applicable only to choice and its subclasses.

Apart from being invoked with a different gesture, the *alternative-action-callback* has exactly the same semantics as *action-callback*.

Examples examples/capi/choice/alternative-action-callback.lisp

See also abort-callback

choice

attach-interface-for-callback

call-editor Generic Function

Summary Executes an editor command in an editor-pane.

Package capi

Signature call-editor editor-pane command

Description The generic function call-editor executes the editor com-

mand command in the current buffer in editor-pane.

It can be used directly in a callback in *editor-pane*'s interface. See the demo interface example in the *CAPI User Guide*. In other cases, take care to modify displayed CAPI interfaces only in their own process: execute-with-interface and

apply-in-pane-process are useful for this.

The before-input-callback and after-input-callback of the editor-pane are called when call-editor is called.

Example (setq editor (capi:contain

(capi:apply-in-pane-process

editor 'capi:call-editor editor "End Of Buffer")

Also see the example in the directory

examples/capi/editor/.

See also apply-in-pane-process

editor-pane

execute-with-interface

can-use-metafile-p

Function

Summary Queries whether metafiles can be used.

Package capi

Signature can-use-metafile-p &optional screen => result

Arguments screen An object accepted by the function con-

vert-to-screen.

Values result A boolean.

Description The function can-use-metafile-p is the predicate for

whether the default library (if no argument is passed) or a specified screen (if an argument is passed) can use metafiles.

If the argument screen is supplied, it is converted to a screen

by convert-to-screen.

Examples There is an example in examples/capi/graphics/meta-

file.lisp.

See also convert-to-screen

default-library

capi-object Class

Summary The class capi-object is the superclass of all CAPI classes.

Package capi

Superclasses standard-class

Subclasses item

callbacks element interface

pinboard-object

Initargs : name The name of the object.

:plist A property list for storing miscellaneous

information.

ACCESSORS capi-object-name

capi-object-plist

Description The class capi-object provides a name and a property list

for general purposes, along with the accessors

capi-object-name and capi-object-plist respectively. A capi-object's name is defaulted by define-interface to

be the name of the slot into which the object is put.

Example (setq object (make-instance 'capi:capi-object

:name 'test))

(capi:capi-object-name object)

(setf (capi:capi-object-plist object)
 '(:red 1 :green 2 :blue 3))

(capi:capi-object-property object :green)

See also capi-object-property

capi-object-property

Function

Summary The capi-object-property function is used to get and set

properties in the property list of a capi-object.

Package capi

Signature capi-object-property object property

1 CAPI Reference Entries

Signature (setf capi-object-property) value object property

Description All CAPI objects contain a property list, similar to the symbol

plist. The recommended ways of setting properties are capi-object-property and (setf capi-object-property). To remove a property, use the function remove-capi-

object-property.

Example In this example a list panel is created, and a test property is

set and examined using capi-object-property.

(capi:capi-object-property pane 'test-property)

(setf (capi:capi-object-property pane 'test-property)
 "Test")

(capi:capi-object-property pane 'test-property)

(capi:remove-capi-object-property pane 'test-property)

(capi:capi-object-property pane 'test-property)

See also capi-object

remove-capi-object-property

check-button Class

Summary A check button is a button that can be either selected or dese-

lected, and its selection is independent of the selections of

any other buttons.

Package capi

Superclasses button

titled-object

Description

The class check-button inherits most of its behavior from the class button. Note that it is normally best to use a checkbutton-panel rather than make the individual buttons yourself, as the button panel provides functionality for handling groups of buttons. However, check-button can be used if you need to have more control over the button's behavior.

Example

The following code creates a check button.

The button can be selected and deselected using this code.

```
(capi:apply-in-pane-process
button #'(setf capi:button-selected) t button)
(capi:apply-in-pane-process
button #'(setf capi:button-selected) nil button)
```

The following code disables and enables the button.

```
(capi:apply-in-pane-process
button #'(setf capi:button-enabled) nil button)
(capi:apply-in-pane-process
button #'(setf capi:button-enabled) t button)
```

See also

push-button
radio-button
button-panel

check-button-panel

Class

Summary A check-button-panel is a pane containing a group of but-

tons each of which can be selected or deselected.

Package capi

Superclasses button-panel

1 CAPI Reference Entries

Description The class check-button-panel inherits all of its behavior

from button-panel, which itself inherits most of its behavior from choice. Thus, the check-button-panel can accept

items, callbacks, and so on.

Example (capi:contain (make-instance

'capi:check-button-panel

:title "Select some packages"

:items '("CAPI" "LISPWORKS" "CL-USER")))

(setq buttons (capi:contain

(make-instance
 'capi:check-button-panel

title "Gelest sems perboses

:title "Select some packages"

:items '("CAPI" "LISPWORKS" "CL-USER")
:layout-class 'capi:column-layout)))

(capi:choice-selected-items buttons)

Also see the example in the directory

examples/capi/buttons/.

See also check-button

push-button-panel
radio-button-panel

choice Class

Summary A choice is an abstract class that collects together a group of

items, and provides functionality for displaying and selecting

them.

Package capi

Superclasses collection

Subclasses button-panel

extended-selection-tree-view

graph-pane
list-panel
menu-component
option-pane
tree-view

Initargs :interaction The interaction style of the choice.

:selection The indexes of the choice's selected items.

:selected-item

The selected item for a single selection choice.

:selected-items

A list of the selected items.

:keep-selection-p

If t, retains any selection when the items change.

:initial-focus-item

If supplied, this should be an item in the choice.

ACCESSORS choice-selection

Readers choice-interaction

choice-initial-focus-item

Description The class choice inherits most of its behavior from

collection, and then provides the selection facilities itself. The classes list-panel, button-panel, option-pane, menu-component and graph-pane inherit from it, and so it plays a key role in CAPI applications.

plays a key role in CAPI applications.

A choice can have one of four different interaction styles, and these control how it behaves when an item is selected by

the user, interaction can be one of:

:no-selection The choice behaves just as a collection.

:single-selection

The choice can have only one selected item.

:multiple-selection

The choice can have multiple selected items, except on Mac OS X.

:extended-selection

An alternative to multiple-selection.

With *interaction*:no-selection, the choice cannot have a selection, and so behaves just as a collection would.

With *interaction*:single-selection, the choice can only have one item selected at a time. When a new selection is made, the old selection is cleared and its *selection-callback* is called. The *selection-callback* is also called when the user invokes the selection gesture on the selected item.

With *interaction*:multiple-selection, the choice can have any number of items selected, and selecting an item toggles its selection status. The *selection-callback* is called when an item becomes selected, and the *retract-callback* is called when an item is deselected. :multiple-selection is not supported for lists on Mac OS X.

With interaction: extended-selection, the choice can have any number of items selected as with:multiple-selection interaction, but the usual selection gesture removes the old selection. However, there is a window system-specific means of extending the selection. When an item is selected the selection-callback is called, when the selection is extended the extend-callback is called, and when an item is deselected the retract-callback is called.

On Mac OS X, the selection gesture is mouse (left button) click. De-selection and discontinuous selections are made by Command+Click, and a continuous selection is made by Shift+Click, regardless of whether if *interaction* is :multi-ple-selection or :extended-selection.

The choice's selection stores the indices of the currently selected item, and is a single number for single selection choices and a list for all other interactions. Therefore when calling (setf choice-selection) you must pass an integer or nil if interaction is :single-selection, and you must pass a list of integers if interaction is :multiple-selection or :extended-selection. The functions choice-selected-item and choice-selected-items treat the selection in terms of the items themselves as opposed to their indices.

Usually when a choice's items are changed using (setf collection-items) the selection is lost.

However, if the choice was created with :keep-selection-pt, then the selection is preserved over the change.

initial-focus-item, if supplied, specifies the item which has the input focus when the choice is first displayed.

Notes

When calling (setf choice-selection) you must pass an integer or nil when *interaction* is :single-selection. You must pass a list for other values of *interaction*.

Compatibility note

In LispWorks 5.0 and earlier versions, for interaction :sin-gle-selection the *selection-callback* is called only after a new selection is made.

Example

The following example defines a choice with three possible selections.

(capi:choice-selected-item choice)

Also see the examples in the directory

examples/capi/choice/ and in

examples/capi/graphics/graph-pane.lisp

See also choice-selected-item

choice-selected-item-p
choice-selected-items
choice-update-item

choice-selected-item

Generic Function

Summary The function choice-selected-item returns the currently

selected item in a single selection choice.

Package capi

Signature choice-selected-item choice

Signature (setf choice-selected-item) item choice

Description The function choice-selected-item returns the currently

selected item in a single selection choice. A setf method is provided as a means of setting the selection. Note that the items are compared by *choice*'s *test-function* - see collection

or the example below.

It is an error to call this function on choices with different interactions — in that case, you should use choice-

selected-items.

Example This example illustrates setting the selection. First we set up a

single selection choice — in this case, a list-panel.

The following code line returns the selection of the list panel.

```
(capi:choice-selected-item list)
```

The selection can be changed, and the change viewed, using the following code.

```
(capi:apply-in-pane-process
  list #'(setf capi:choice-selected-item) 'e list)
(capi:choice-selected-item list)
```

This example illustrates the effect of the *test-function*. Make a choice with *test-function* eq:

This call loses the selection since (eq "b" "b") fails:

```
(capi:apply-in-pane-process
 *list* #'(setf capi:choice-selected-item)
   "b" *list*)
```

Change the test function:

```
(capi:apply-in-pane-process
 *list* #'(setf capi:collection-test-function)
 'equal *list*)
```

This call sets the selection since (equal "b" "b") succeeds:

```
(capi:apply-in-pane-process
 *list* #'(setf capi:choice-selected-item)
   "b" *list*)
```

See also choice

choice-selected-items
collection

choice-selected-item-p

Function

Summary Checks if an item is currently selected in a choice.

Package capi

Signature choice-selected-item-p choice item

Description The function choice-selected-item-p is the predicate for

whether an item *item* of the choice *choice* is selected.

Note that the items are compared by choice's test-function - see

collection for details.

```
Example (setq list
```

(capi:choice-selected-item-p list 'c)
=>
t

Now click on another item.

(capi:choice-selected-item-p list 'c)
=>

nil

See also choice

collection

choice-selected-items

Generic Function

Summary The function choice-selected-items returns the currently

selected items in a choice as a list of the items.

Package capi

Signature choice-selected-items choice

Signature (setf choice-selected-items) items choice

Description

The function choice-selected-items returns the currently selected items in a choice as a list of the items. A setf method is provided as a means of setting the currently selected items. Note that the items are compared by *choice*'s *test-function* - see collection for details.

In the case of :single-selection choices, it is usually easier to use the complementary function choice-selected-item, which returns the selected item as its result.

Example

First we set up a :multiple-selection choice — in this case, a list panel.

The following code line returns the selections of the list.

```
(capi:choice-selected-items list)
```

The selections of the list panel can be changed and redisplayed using the following code.

```
(capi:apply-in-pane-process
list #'(setf capi:choice-selected-items)
'(a c e) list)
(capi:choice-selected-items list)
```

Note that *interaction*: multiple-selection is not supported for lists on Mac OS X.

See also choice

choice-selected-item

collection

choice-update-item

Function

Summary Updates an item in a choice.

Package capi

Signature choice-update-item choice item

Description The function choice-update-item updates the display of

the item *item* in the choice *choice*. It should be called if the display of *item* (that is, the string returned by the *print-function*)

changes.

Examples Create a list panel that displays the status of something

```
(defun my-print-an-item (item)
        (format nil "~a: ~a"
                (substitute-if-not #\space
                                    'alphanumericp
                                    (symbol-name item))
                (symbol-value item)))
(defvar *status-one* :on)
(defvar *status-two* :off)
(setq list
      (capi:contain
       (make-instance
        'capi:list-panel
        :items '(*status-one* *status-two*)
        :print-function 'my-print-an-item
        :visible-min-height :text-height
        :visible-min-width :text-width)))
```

Setting the status variables does not change the display:

```
(setq *status-one* :error)
```

Update the item to change the display:

(capi:choice-update-item list '*status-one*)

This example also demonstrates choice-update-item:

examples/capi/choice/alternative-action-callback.lisp

See also choice

clipboard Function

Summary Returns the contents of the system clipboard.

Package capi

Signature clipboard self &optional format => result

Arguments *self* A displayed CAPI pane or interface.

format A keyword.

Values result A string, an image, a Lisp object, or nil.

Description The function clipboard returns the contents of the system

clipboard as a string, or nil if the clipboard is empty.

format controls what kind of object is read. The following values of *format* are recognized:

:string The object is a string. This the default value.

: image The object is of type image, converted from

whatever format the platform supports.

:value The object is the Lisp value.

:metafile The object is a metafile.

When *format* is :image, the image returned by clipboard is associated with *self*, so you can free it explicitly with free-image or it will be freed automatically when the pane is destroyed.

When *format* is :metafile the object is a metafile which should be freed using free-metafile when no longer needed. See also draw-metafile and draw-metafile-to-image. *format* :metafile is not supported on GTK+ or X11/Motif.

The Microsoft Windows clipboard is usually set by the user with the Ctrl+C and Ctrl+X gestures. Note that the Lisp-Works editor uses these gestures when in Windows emulation mode.

On X11/Motif, various gestures may set the clipboard. Note that LispWorks uses Ctrl+C and Ctrl+x when in KDE/Gnome editor emulation mode. The X clipboard can also be accessed by running the program xclipboard or the Emacs function x-get-clipboard.

The Mac OS X clipboard is usually set by the user with the Command+C and Command+X gestures.

See also

clipboard-empty
draw-metafile
draw-metafile-to-image
free-image
free-metafile
image
selection
set-clipboard
text-input-pane-paste

clipboard-empty

Function

Summary Determines whether the system clipboard contains an object

of the specified kind.

Package capi

Signature clipboard-empty self &optional format => result

Arguments self A displayed CAPI pane or interface.

format A keyword.

Values result tor nil.

Description The function clipboard-empty returns nil if there is an

object of the kind indicated by format on the clipboard, or t

otherwise.

format controls what kind of object is checked. The allowed

values of format are as described for clipboard.

See also clipboard

image

clone Generic Function

Summary Creates a copy of a CAPI object.

Package capi

Signature clone capi-object => cloned-object

Arguments capi-object An instance of a subclass of capi-object

Values cloned-object A copy of capi-object.

1 CAPI Reference Entries

Description The generic function clone returns a new object cloned-object

which is a copy of capi-object. It does not share any data with

capi-object, but has a copy of the useful part of its state.

The system contains methods on clone. You may add meth-

ods on your own interface classes.

See also capi-object

cocoa-default-application-interface

Class

Summary The class supporting application menus and message pro-

cessing for a Cocoa application.

Package capi

Superclasses interface

Initargs :message-callback

A function or nil.

:application-menu

nil, a menu, or the name of a slot containing

a menu in the application interface.

:dock-menu nil, a menu, or a function designator.

ACCESSORS application-interface-message-callback

 ${\tt application-interface-application-menu}$

application-interface-dock-menu

Description The class cocoa-default-application-interface sup-

ports the application menu, application messages and other

functionality for a Cocoa application.

All Cocoa applications in LispWorks for Macintosh have an application interface, which is a hidden interface that pro-

vides the following:

- The application menu (the leftmost menu in the menu bar, named after the application). See application-menu below.
- 2. The menu bar items that are displayed when no other interfaces are on the screen. See *menu-bar-items* in interface and *menu-bar* in define-interface.
- 3. An optional Dock context menu. See dock-menu below.
- **4.** Optional application message processing. See *message-callback* below.
- **5.** Control over the lifecycle and *display-state* of the application as a whole.

If you wish to override the defaults, then you should first define a subclass of cocoa-default-application-interface with your changes. Then set a single instance of this subclass as the application interface by calling set-application-interface before any CAPI functions that make the screen object (such as convert-to-screen and display).

Do not call display with a subclass of cocoa-defaultapplication-interface - the application interface does not have a window on the screen and should be created in addition to the visible interfaces in your application.

When non-nil, *message-callback* should be a function with signature

interface message &rest args

message-callback will be called for various application messages. The *interface* argument will be the application interface and the *message* argument will be a keyword. The *message* argument will be one of the following:

copen-file This message is invoked when the user double-clicks on a document associated with the application or drags a document into the application icon. The args contain the name of the file to open.

:finished-launching

This message is invoked just after the user has started the application and all other initialization has been done (including any :open-file message if applicable). You can use it to open a default document for example. There are no args.

application-menu controls the application's main menu. If this is nil, then a minimal application menu will be made using the title of the application interface, otherwise it should be a menu containing the usual items or the name of a slot containing such a menu in the application interface. Note that the Quit item in the application-menu needs to call destroy on the interface, rather than call lw:quit.

dock-menu provides a menu for use by the Mac OS X Dock icon. If the value is nil (the default), then the standard menu is used. If dock-menu is a function designator, it is called with the application interface as its argument when the menu is popped up and should return a menu. Otherwise dock-menu should be a menu, which is used directly. The Dock will add the standard items such as Quit to the end of the menu you supply.

interface initargs are interpreted as follows:

- The *activate-callback* is called when the application is activated or deactivated.
- The *create-callback* is called when the application starts up.
- The *destroy-callback* is called when the application shuts down.
- The *confirm-destroy-function* is called to confirm whether the application should shut down.

All of these callbacks execute in the thread that runs the Cocoa event loop, so they can call CAPI and GP functions.

The application interface also allows you to control aspects of the application. In particular:

- The function destroy will cause the application to shut down.
- The function top-level-interface-display-state will return :hidden if the whole application is hidden and will return :normal otherwise.
- The function (setf top-level-interface-displaystate) can be used to perform some operations typically found on the application menu.

The *display-state* value can one of:

:normal Show the application and activate it

:restore Show the application again without activat-

ing it

:hidden Hide

:others-hidden

Hide Others

:all-normal Show All

Note: cocoa-default-application-interface is implemented only in LispWorks for Macintosh with the Cocoa IDE.

Example

See these files in the examples subdirectory of the LispWorks library:

capi/applications/cocoa-application.lisp

capi/applications/cocoa-application-single-window.lisp

delivery/macos/multiple-window-application.lisp
delivery/macos/single-window-application.lisp

See also

set-application-interface

cocoa-view-pane Class

Summary A cocoa-view-pane allows an arbitrary Cocoa view class to

be used on the Macintosh.

Package capi

Superclasses simple-pane

titled-object

Initargs :view-class A string naming the view class to use.

:init-function

A function that initializes the view class.

Accessors cocoa-view-pane-view-class

cocoa-view-pane-init-function

Description The cocoa-view-pane class allows an instance of an arbi-

trary Cocoa view class to be displayed within a CAPI inter-

face.

Note: cocoa-view-pane is implemented only in LispWorks

for Macintosh with the Cocoa IDE.

When the pane becomes visible, the CAPI allocates and initialize a Cocoa view object using the initargs as follows:

- If view-class is specified, then it should be a string naming the Cocoa view class to allocate. Otherwise the class NSView is allocated.
- If init-function is not nil, then it should be a function which is called with of two arguments, the pane and a foreign pointer to the newly allocated Cocoa view object. The function should initialize the Cocoa view object in whatever way is required, including invoking the appropriate Objective-C initialization method, and return the initialized view. If init-function is nil then the Objective-C method init is called and the result is returned.

After the Cocoa view has been initialized, the function cocoa-view-pane-view can be used the retrieve it.

You can use the functions (setf cocoa-view-pane-view-class) and (setf cocoa-view-pane-init-function) to modify the *view-class* and *init-function*, but the values will be ignored if this is done after the pane becomes visible.

See the LispWorks Objective-C and Cocoa Interface User Guide and Reference Manual for details on using Cocoa.

Example

The following code uses cocoa-view-pane to display an NSMovieView displaying an existing movie.

See also

cocoa-view-pane-view

cocoa-view-pane-view

Function

Summary Returns the Cocoa view of a cocoa-view-pane.

Package capi

Signature cocoa-view-pane-view pane => view

Arguments pane A cocoa-view-pane.

Values view A foreign pointer to a Cocoa view or nil.

1 CAPI Reference Entries

Description The function cocoa-view-pane-view returns the Cocoa

view for the cocoa-view-pane pane as a foreign pointer. This view is only accessible when the pane is visible and nil is

returned in other cases.

Note: cocoa-view-pane-view is implemented only in Lisp-Works for Macintosh with the Cocoa IDE. See the *LispWorks Objective-C* and *Cocoa Interface User Guide and Reference Manual*

for details on using Cocoa.

Example See the example in examples/objc/movie-view.lisp.

See also cocoa-view-pane

collect-interfaces

Generic Function

Summary Finds all interfaces of a given class.

Package capi

Signature collect-interfaces proto &key screen current-process-first sort-

by => interfaces

Arguments proto A class, class name, or an interface.

screen nil, the symbol: any, a screen, or a keyword

naming a library.

current-process-first

A boolean.

sort-by :visible or :create.

Values interfaces A list.

Description The generic function collect-interfaces returns a list of

CAPI interfaces which are instances of the class indicated by

proto, or subclasses thereof.

If screen is nil, the interfaces on the default screen are returned. This is the default. If screen is:any, interfaces includes those on any screen. If screen is a screen object, the interfaces on that screen are returned. screen can also be a library name, currently the accepted values are:win32,:motif and:cocoa.

If interfaces on multiple screens are returned, then those on each screen are grouped together in *interfaces*.

Amongst those for each screen, the interfaces are grouped as follows. If *current-process-first* is true, then the interfaces in the current process appear together at the beginning of the group. If *sort-by* is :create then these interfaces are sorted by creation time, otherwise *sort-by* is :visible and they are are sorted in Z-order. The interfaces of other processes appear at the end of the group, also sorted according to *sort-by*.

If *current-process-first* is nil, then the interfaces for each screen are sorted according to *sort-by*.

The default value of *sort-by* is :create and of *current-process-first* is t.

See also

find-interface installed-libraries

collection Class

Summary A collection collects together a set of items, and provides

functionality for accessing and displaying them.

Package capi

Superclasses capi-object

callbacks

Subclasses choice

Initargs :items The items in the collection.

:print-function

A function that prints an item.

:test-functionA comparison function between two items.

:items-count-function

A function which returns the length of items.

:items-get-function

A function that returns the *n*th item.

:items-map-function

A function that maps a function over the items.

:accepts-focus-p

Specifies that the collection should accept

input. The default value is ${\tt t}$.

:help-key An object used for lookup of help.

Accessors collection-items

collection-print-function collection-test-function

Readers collection-items-count-function

collection-items-get-function collection-items-map-function

help-key

Description The main use of collection is as a part of the class choice,

which provides selection capabilities on top of the collection handling, and which is used by list panels, button panels and

menus amongst others.

The items in the collection are printed by print-collec-

tion-item.

Items can be instances of the CAPI class item or any Lisp object. The main difference is that non-CAPI items use the callbacks specified for the collection, whilst the CAPI items will use their callbacks in preference if these are specified.

By default, *items* must be a sequence, but this can be changed by specifying *items-get-function*, *items-count-function*, and *items-map-function*.

items-get-function should take as arguments the items and an index, and should return the indexed item. The default is syref.

items-count-function should take the items as an argument and should return the number of them.

items-map-function should take as arguments the items, a function *function* and a flag *collect-results-p*, and should call *function* on each of the items in return. If *collect-results-p* is non-nil, then it should also return the results of these calls in a list.

test-function should be suitable for comparing the items in your collection. For example, if there are both strings and integers amongst your *items*, you should supply *test-function* equal.

You can change the items using (setf collection-items). Note that there is an optimization append-items that is sometimes useful when adding items.

accepts-focus-p and help-key are interreted as described in element.

Example

The following code uses push-button-panel, a subclass of collection.

The following example provides a collection with all values from 1 to 6 by providing an *items-get-function* and an *items-count-function*.

Here is an example demonstrating the use of CAPI items in a collections list of items to get more specific callbacks.

```
(defun specific-callback (data interface)
  (capi:display-message "Specific callback for ~S"
                        data))
(defun generic-callback (data interface)
  (capi:display-message "Ordinary callback for ~S"
                        data))
(capi:contain (make-instance
               'capi:list-panel
               :items (list (make-instance
                              'capi:item
                             :text "Special"
                             :data 1000
                             :selection-callback
                              'specific-callback)
                            2 3 4)
               :selection-callback 'generic-callback)
              :visible-min-width 200
              :visible-min-height 200)
append-items
count-collection-items
get-collection-item
item
```

See also

map-collection-items
print-collection-item
search-for-item

collection-find-next-string

Generic Function

Summary Finds the next occurrence of the string that was previously

searched for in a collection.

Package capi

Signature collection-find-next-string collection &key set => index

Arguments collection A collection.

set A boolean.

Values index A non-negative integer or nil.

Description The generic function collection-find-next-string must

be called after one of collection-search, collection-find-string or find-string-in-collection was called on *collection*. It searches for the next item in *collection* with printed representation matching the last string searched for

and returns its index, or mil if no match is found.

If set is true, then if an item matching the string is found, the

selection is set to this item. set defaults to t.

See also collection-find-string

collection-last-search

collection-search

find-string-in-collection

collection-find-string

Generic Function

Summary Finds the next occurrence of a string in a collection, prompting

for the string if it is not supplied.

Package capi

Signature collection-find-string collection &key set string => index

Arguments collection A collection.

set A boolean.

string A string, or nil.

Values index A non-negative integer or nil.

Description The generic function collection-find-string calls find-

string-in-collection with collection and set.

string is also passed if non-nil. If string is nil, collection-find-string first prompts the user for a string to pass.

set defaults to t.

See also collection-search

find-string-in-collection

collection-last-search

Generic Function

Summary Returns the last string searched for in a collection.

Package capi

Signature collection-last-search collection => string

Arguments collection A collection.

Values string A string, or nil.

Description The generic function collection-last-search returns the

last string searched for in collection by collection-search

or find-string-in-collection.

If neither of these functions has been called on *collection*, then

the return value string is mil.

See also collection-search

find-string-in-collection

collection-search

Generic Function

Summary The generic function collection-search calls

find-string-in-collection with a string provided by the

user.

Package capi

Signature collection-search collection &optional set

Description Prompts the user for a string and calls find-string-in-

collection with collection, set and this string.

set defaults to t.

See also collection

find-string-in-collection

collector-pane Class

Summary A collector-pane is an editor-pane which displays the

output sent to a particular type of character stream called an editor stream, the contents of which are stored in an editor

buffer.

Package capi

Superclasses editor-pane

Initargs :buffer-name The name of a buffer onto an editor stream.

:stream The editor stream to be collected.

Readers collector-pane-stream

Description A new collector-pane can be created to view an existing

editor stream by passing the stream itself or by passing the

buffer name of that stream.

To create a new stream, either specify *buffer-name* which does not match any existing buffer, or do not pass *buffer-name* in which case the CAPI will create a unique buffer name for you.

To access the stream, use the reader collector-panestream on the collector-pane.

Note that the editor buffer "Background Output" is a buffer onto the output stream *standard-output*.

Example

Here is an example that creates two collector panes onto a new stream (that is created by the first collector pane).

Finally, this example shows how to create a collector pane onto the "Background Output" stream.

See also with-random-typeout

map-typeout
unmap-typeout

color-screen Class

Package capi

Superclasses screen

Description This is a subclass of screen that gets created for color

screens. It is primarily available as a means of discriminating

on whether or not to use colors in an interface.

See also element-screen

mono-screen

column-layout Class

Summary The column-layout lays its children out in a column.

Package capi

Superclasses grid-layout

Initargs :ratios The size ratios between the layout's

children.

:adjust The horizontal adjustment for each child.

:gap The gap between each child.

:uniform-size-p

If t, each child in the column has the same

height.

Accessors layout-ratios

Description

The column-layout lays its children out by inheriting the behavior from grid-layout. The *description* is a list of the layout's children, and the layout also translates the initargs ratios, adjust, gap and uniform-size-p into the grid-layout's equivalent initargs y-ratios, x-adjust, y-gap and y-uniform-size-p.

description may also contain the keywords :divider and :separator which automatically create a divider or separator as a child of the column-layout. The user can move a divider, but cannot move a separator.

When specifying :ratios in a row with :divider or :separator, you should use nil to specify that the divider or separator is given its minimum size, as in the example below.

Compatibility note

layout-divider-default-size and column-layout-divider are not supported in LispWorks 4.4 and later.

Example

```
(setq column (capi:contain
              (make-instance
               'capi:column-layout
               :description
               (list
                (make-instance 'capi:push-button
                               :text "Press me")
                "Title:"
                (make-instance 'capi:list-panel
                               :items '(1 2 3)))
               :adjust :center)))
(capi:apply-in-pane-process
column #'(setf capi:layout-x-adjust) :right column)
(capi:apply-in-pane-process
column #'(setf capi:layout-x-adjust) :left column)
(capi:apply-in-pane-process
column #'(setf capi:layout-x-adjust) :center column)
(flet ((make-list-panel (x y)
         (make-instance
          'capi:list-panel
          :items
          (loop for i below x
                collect i)
          :selection
          (loop for i below x by y
                collect i)
          :interaction
          :multiple-selection)))
  (capi:contain
   (make-instance
    'capi:column-layout
    :description
    (list
     (make-list-panel 100 5)
     :divider
     (make-list-panel 100 10))
    :ratios '(1 nil 2))))
```

row-layout

See also

component-name

Function

Summary Gets and sets the *component-name* of an ole-control-pane.

Package capi

Signature component-name pane => name

(setf component-name) name pane => name

Description The function component-name accesses the component-name

of an ole-control-pane.

When the ole-control-pane is created, it automatically

opens the component and inserts it.

If (setf component-name) is called on a pane that is already created, any existing component is closed, and the new component is opened and inserted. (setf component-

name) also sets the pane's user-component to nil.

Notes component-name is implemented only in LispWorks for Win-

dows. Load the functionality by (require "embed").

Example See the example in

examples/com/ole/simple-container/doc-viewer-

pair.lisp

See also ole-control-pane

confirm-quit Function

Summary Quits the Lisp session, potentially after user confirmation.

Package capi

Signature confirm-quit application-name

Arguments application-name A string.

Description The function confirm-quit calls quit, potentially after confirmation from the user.

The behavior of confirm-quit when called within Lisp-Works is determined by a LispWorks user preference, which can be set by Tools > Preferences... > Environment > General > Confirm Before Exiting. This preference can also be set programmatically (for example in an application) by set-confirm-quit-flag.

If the value of the flag is :check-editor-files (the default), confirm-quit checks whether there are editor buffers which are associated with files and are modified. If there is at least one such modified buffer, confirm-quit prompts the user to decide between three options:

Save Changes Saves all modified buffers before quitting

Discard Changes Quits without saving

Cancel Does not save or quit

If there are no such modified buffers, confirm-quit simply calls quit.

If the flag is nil then confirm-quit simply calls quit.

If the flag is t then confirm-quit prompts the user. If there are unsaved buffers, the prompt is as described above, otherwise the prompt is a simple yes/no confirmer dialog.

application-name is used in the prompt to identify the application.

Notes The LispWorks IDE uses confirm-quit.

See also set-confirm-quit-flag

confirm-yes-or-no

Function

Summary The function confirm-yes-or-no pops up a dialog button

containing a message and a Yes and No button.

Package capi

Signature confirm-yes-or-no format-string &rest format-args

Description This pops up a dialog box containing a message and the but-

tons **Yes** and **No**, returns t when the **Yes** button is clicked, and nil when the **No** button is clicked. The message is obtained by applying the *format-string* and the *format-args* to the

Common Lisp function format.

This function is actually a convenient version of promptfor-confirmation, but has the disadvantage that you cannot specify any customization arguments. For more flexi-

bility, use prompt-for-confirmation itself.

Example (setq pane (capi:contain

(when (capi:confirm-yes-or-no "Close ~S?" pane)

(capi:apply-in-pane-process

pane 'capi:quit-interface pane))

See also prompt-for-confirmation

display-dialog
popup-confirmer

confirmer-pane

Function

Summary Returns the pane associated with a confirmer interface.

Package capi

Signature confirmer-pane interface => pane

Arguments interface A confirmer interface displayed by popup-

confirmer.

Values pane The pane argument passed to popup-con-

firmer.

Description The function confirmer-pane returns the pane associated

with a confirmer interface that has been displayed by popup-

confirmer.

In most cases the programmer does not have access to this interface, but it can be passed to the confirmer's callbacks when extra buttons are added via the *buttons* argument.

See also popup-confirmer

contain Function

Summary Displays a window containing an element.

Package capi

Signature contain element &rest interface-args &key screen process title

&allow-other-keys => element

Description The function contain creates and displays a container for the

CAPI element element. contain returns element as its result.

contain is provided as a convenient way of testing CAPI functionality and is useful mainly during interactive development. Many of the CAPI examples use it.

The container is created using make-container, which can

make containers for any of the following classes:

simple-pane layout interface pinboard-object menu menu-item menu-component list

In the case of a list, the CAPI tries to see what sort of objects they are and makes an appropriate container. For instance, if they were all simple-panes it would put them into a column-layout.

interface-args, after removing the arguments screen and process, are passed to make-container as the initargs to the interface. title is used as the title of the container.

The values of the arguments *screen* and *process* are passed to display when displaying the container.

convert-relative-position

Function

Summary Converts a screen position from one coordinate system to

another.

element

Package capi

Signature convert-relative-position from to $x y \Rightarrow to-x$, to-y

Arguments from A pane, interface or screen.

to A pane, interface or screen.

x An integer.

y An integer.

Values *to-x* An integer.

to-y An integer.

Description The function convert-relative-position converts the

position *x*, *y* in the coordinate system of *from* to that of *to*.

Example See the example file

examples/capi/elements/convert-relative-

position.lisp.

See also top-level-interface-geometry

with-geometry

convert-to-screen Function

Summary The convert-to-screen function finds the appropriate

screen or container for a CAPI object.

Package capi

Signature convert-to-screen &optional object => result

Arguments object A CAPI object, a plist, or nil.

Values result A screen or a container.

Description

This finds the appropriate screen or container for the CAPI object *object*.

If *object* is nil, *result* is the default screen. *object* defaults to nil.

If object is a pane inside a MDI interface, then result is the capi:container of the interface, rather than the real screen, because this is more useful in most cases. To obtain the real screen, call convert-to-screen on the top level interface. See document-frame for a description of MDI interfaces.

object can be a keyword representing the CAPI library. This is equivalent to using the :library key in the plist case below.

object can be a plist. The keys below are supported on GTK+ and Motif. Other libraries ignore them.

:display

The value is an X Window System display string describing the X display and screen to use. The default value is derived from the DISPLAY environment variable or (on Motif) the -display command-line option, or (on GTK+) the --display command-line option. If neither is supplied, the default is to use the default screen on the local host.

:host

The name of the host to use for the X Window System display. This key is valid only if no :display key/value is supplied. The default value is the local host.

:server-numberThe number of the display server to use for the X Window System display. This key is valid only if no :display key/value is supplied. The default value is 0.

: screen-numberThe number of the screen to use for the X
Window System display. This key is valid
only if no :display key/value is supplied.
The default value is the default screen of the
display.

:application-class

The value is a string naming the application class used for X Window System resources. The default value is "Lispworks". When running a delivered LispWorks image, you should specify the :application-class key if you want to provide application-specific resources.

On GTK+ the value is used for constructing the default *widget-name* for top-level interfaces. The application-class is prepended to the interface name followed by a ".", so if *application-class* is "my-application", a top-level-interface of class my-interface will have a default *widget-name* "my-application.my-interface".

See element for the description of widgetname.

Example GTK+ resource files are in lib/6-1-0-0/examples/gtk/

:fallback-resources

On GTK+ the fallback resources are global, so they cannot be used to define different resources for different screens. Each call to convert-to-screen where fallback-resources is passed overrides the previous call. The value of fallback-resources is either a single string or a list of strings. In either case each string must be a complete specification according to the standard resource specifica-

tion of GTK+ resource files
(gtk_rc_parse_string should be able to parse
it).

On Motif the value is a list of strings representing the set of application context fall-back resources to use (see XtAppSetFallbackResources). Each string corresponds to a single line of an X resource file.

:library

The value specifies the CAPI library. This is useful on Linux, FreeBSD and x86/x64 Solaris platforms, and in the Mac OS X/GTK+ image, to choose between :gtk and :motif if the deprecated "capi-motif" module is loaded.

This keys is supported on Motif only. Other libraries ignore it.

:command-line-args

The value is a list of strings representing the set of command-line arguments to pass to <code>xtOpenDisplay</code>. Each string corresponds to a single argument. The default value is derived from the command line used to start Lisp.

The resources are used only when no other system resource files can be found. When running a non-delivered LispWorks image, the default value of the :fallback-resources key is read from the file whose name is the value of the :application-class key in the app-defaults directory of the current LispWorks library. When running a delivered LispWorks image, you should specify the :fallback-resources key if your application needs fallback resources.

Example (capi:convert-to-screen)

See also document-frame

screen

count-collection-items

Generic Function

Summary Returns the number of items in a collection.

Package capi

Signature count-collection-items collection &optional representation

Description The count-collection-items generic function returns the

number of items in *collection* by calling the

items-count-function.

representation defaults to nil. If it is non-nil, it is used instead

of the items of collection.

Example The following example uses count-collection-items to

return the number of items in a list panel.

(capi:count-collection-items list)

The following example shows how to count the number of

items in a specified list.

(capi:count-collection-items list '(1 2))

See also collection

get-collection-item
search-for-item

current-dialog-handle

Function

Summary Returns the underlying handle of the current dialog.

Package capi

Signature current-dialog-handle => handle

Values handle A platform-specific value, or mil.

Description The function current-dialog-handle returns the underly-

ing handle of the current dialog, as follows:

Microsoft Windows

The hwnd of the dialog.

GTK+ A pointer to the GdkWindow.

Motif A windowid of the dialog.

Cocoa The value returned by the NSWindow's

windowNumber method.

This value is useful if you want to perform some operation on the underlying handle that the CAPI does not supply.

If there is no current dialog, current-dialog-handle returns nil.

Example Press on "Get handle" to see the handle of the dialog.

See also simple-pane-handle

current-document

Generic Function

Summary Returns the current document of a MDI interface.

Package capi

Signature current-document mdi-interface => child

Arguments mdi-interface An instance of a subclass of document-

frame.

Values *child* The current document of *mdi-interface*.

Description The generic function current-document returns the top

child interface of a MDI interface.

See also document-frame

current-pointer-position

Function

Summary Returns the current position of the pointer.

Package capi

Signature current-pointer-position &key relative-to pane-relative-p =>

x, *y*

Arguments relative-to A screen or a displayed interface or a

CAPI pane.

pane-relative-p A boolean.

Results x An integer.

y An integer.

1 CAPI Reference Entries

Description The function current-pointer-position returns the cur-

rent x,y position of the pointer on the screen of *relative-to*,

which defaults to the current screen.

If *pane-relative-p* is true then the position is returned relative to *relative-to*, otherwise it is returned relative to the screen.

The default value of pane-relative-p is t.

See also interface

screen

current-popup Function

Summary Returns the current popup pane if there is one.

Signature current-popup => result

Values result A pane or nil.

Description The function current-popup returns the current popup pane

or ${\tt mil}$ if there is none. A current popup exists in the scope of callbacks which are done while a dialog is displayed on the

screen in the current process.

If the dialog was raised by an explicit call to display-dialog or popup-confirmer, current-popup returns the first argument of display-dialog or popup-confirmer. For other functions that raise a dialog (such as the prompt-for-file, prompt-for-confirmation and so on), the result is CAPI

pane created by the system.

See also display-dialog

popup-confirmer

current-printer Function

Summary Returns the currently selected printer object.

Package capi

Signature current-printer &key interactive => printer

Arguments interactive A boolean.

Values *printer* A printer, or nil.

Description The current-printer function returns the currently

selected printer object for the default library.

If *interactive* is non-nil and there is no current printer, a confirmer is displayed warning the user and *printer* is nil.

The default value of interactive is mil.

See also page-setup-dialog

set-printer-options

default-editor-pane-line-wrap-marker

Variable

Summary The default line wrap marker for editor panes.

Package capi

Initial Value #\!

Description The variable *default-editor-pane-line-wrap-marker*

provides the default value for the *line-wrap-marker* of an editor-pane. The value should be a character object, or

nil

See also editor-pane

default-library Function

Summary Returns the default library.

Package capi

Signature default-library => library

Values *library* A library name.

Description The function default-library returns a keyword naming

the the default library.

On Linux, FreeBSD and xw86/x64 Solaris platforms, the default library is :gtk. If you load the deprecated "capi-

motif" module, then the library will be :motif.

On Microsoft Windows platforms, currently the only library

available is :win32, hence this is the default library.

On Mac OS X platforms, the only library available in the native GUI image is :cocoa, hence this is the default library. In the Mac OS X/GTK+ image, the default library is :gtk, but you load the deprecated "capi-motif" module, then the

library will be :motif.

In LispWorks for UNIX only (not LispWorks for Linux, FreeBSD, or x86/x64 Solaris) platforms, currently the only library available is :motif, hence this is the default library.

See also installed-libraries

define-command Macro

Summary The define-command macro defines an alias for a mouse or

keyboard gesture that can be used in the input model of an

output pane.

Package capi

Signature define-command name gesture &key translator host

Description

The macro define-command defines an alias for a mouse or keyboard gesture that can then be used in output-pane's input models. The *name* is the name of the alias and the *gesture* is one of the gestures accepted by output-pane. The *translator* is a function that gets passed the arguments that would be passed to the callback, and returns a list of arguments to be passed to the callback along with the output-pane (which will be the first argument). The *host* indicates which platforms this gesture should apply for (it defaults to all platforms).

For a full description of the gesture syntax, see output-pane.

Example

Firstly, here is an example of defining a command which maps onto a gesture.

Here is a more complicated example demonstrating the use of *translator* to affect the arguments passed to a callback.

```
(defun object-select-callback (output-pane
                                             &optional object)
                (when object (capi:display-message
                              "Pressed on ~S in ~S"
                              object output-pane)))
              (setg pinboard
                    (capi:contain (make-instance
                                  'capi:pinboard-layout
                                  :input-model '((:select-object
                                          object-select-callback)))))
              (make-instance 'capi:item-pinboard-object
                             :text "Press Me!"
                             :parent pinboard
                             :x 10 :y 20)
              (make-instance 'capi:line-pinboard-object
                             :parent pinboard
                             :start-x 20 :start-y 50
                             :end-x 120 :end-y 150)
             There is a further example in the file
             capi/output-panes/commands.lisp.
See also
             output-pane
             invoke-command
             invoke-untranslated-command
```

define-interface Macro

Summary The define-interface macro defines subclasses of

interface.

Package capi

Signature define-interface name superclasses slots &rest options

Description The macro define-interface is used to define subclasses of

interface, which when created with make-instance has the specified panes, layouts and menus created automatically. The slots and superclasses are used to describe the slots and superclasses of *name* as in the defclass macro, except that if *superclasses* is non-nil it must include interface or a subclass of it

define-interface accepts the same options as defclass, plus the following extra options:

:panes Descriptions of the interface's panes.
 :layouts Descriptions of the interface's layouts.
 :menus Descriptions of the interface's menus.
 :menu-bar A list of menus for the interface's menu bar.
 :definition Options to alter define-interface.

The class options :panes, :layouts and :menus add extra slots to the class that will contain the CAPI object described in their description. Within the scope of the extra options, the slots themselves are available by referencing the name of the slot, and the interface itself is available with the variable capi:interface. Each of the slots can be made to have readers, writers, accessors or documentation by passing the appropriate defclass keyword as one of the optional arguments in the description. Therefore, if you need to find a pane within an interface instance, you can provide an accessor, or simply use with-slots.

The :panes option is a list of pane descriptions of the following form

```
(:panes
  (slot-name pane-class initargs)
  ...
  (slot-name pane-class initargs)
```

where *slot-name* is a name for the slot, *pane-class* is the class of the pane being included in the interface, and *initargs* are the initialization arguments for the pane - the allowed forms are described below.

The :layouts option is a list of layout descriptions of the following form

```
(:layouts
(slot-name layout-class children initargs)
...
(slot-name layout-class children initargs)
```

where *slot-name* is a name for the slot, *layout-class* specifies the type of layout, *children* is a list of children for the layout, and *initargs* are the initialization arguments for the layout the allowed forms are described below. The primary layout for the interface defaults to the first layout described, but can be specified as the :layout initarg to the interface. If no layouts are specified, then the CAPI will place all of the defined panes into a column layout and make that the primary layout.

The :menus option is a list of menu and menu component descriptions of the following form

```
(:menus
  (slot-name title descriptions initargs)
...
  (slot-name title descriptions initargs)
```

slot-name is the slot name for each menu or menu component.

title is the menu's title, the keyword :menu, or the keyword :component.

descriptions is a list of menu item descriptions. Each menu item description is either a title, a slot name for a menu, or a list of items containing a title, descriptions, and a list of initialization arguments for the menu item.

initargs are the initialization arguments for the menu.

The values given in *initargs* under :panes, :layouts and :menus can be lists of the form

```
(:initarg keyword-name)
(:initarg key-spec)
(:initarg key-spec initarg-value)

key-spec := var | (var) | (var initform) | ((keyword-name var)) | ((keyword-name var) initform)
```

keyword-name := any keyword

key-spec is interpreted as in the &key symbol of ordinary Common Lisp lambda lists. When this form of value is used, the specified keyword-name is added as an extra initarg to the class defined by the define-interface form.

If *key-spec* is followed by *initarg-value*, then its value is used as the initarg of the pane. Otherwise the value from *key-spec* is used.

Additionally *initargs* may contain the keyword argument :make-instance-extra-apply-args which is useful when you want to supply initargs to the pane *slot-name* when the interface is initialized. The value *make-instance-extra-apply-args* should be a keyword which becomes an extra initarg to the interface class *name*. The value of that initarg should be a list of pane initargs and values which is passed when the pane is initialized. For an example, see

The :menu-bar option is a list of slot names, where each slot referred to contains a menu that should appear on the menu bar

examples/capi/applications/argument-passing.lisp.

The :definition option is a property list of arguments which define-interface uses to change the way that it behaves. Currently there is only one definition option:

```
:interface-variable
```

The name of the variable containing the interface.

Example Firstly, a couple of pane examples:

```
(capi:define-interface test1 ()
  (:panes
    (text capi:text-input-pane))
  (:default-initargs :title "Test1"))
(capi:display (make-instance 'test1))
(capi:define-interface test2 ()
  ()
  (:panes
    (text capi:text-input-pane)
    (buttons capi:button-panel :items '(1 2 3)
             :reader test2-buttons))
  (:layouts
    (main-layout capi:column-layout '(text buttons)))
  (:default-initargs :title "Test2"))
(test2-buttons
 (capi:display (make-instance 'test2)))
Here are a couple of menu examples:
(capi:define-interface test3 ()
  ()
  (:menus
    (color-menu "Colors" (:red :green :blue)
       :print-function 'string-capitalize))
  (:menu-bar color-menu)
  (:default-initargs :title "Test3"))
(capi:display (make-instance 'test3))
(capi:define-interface test4 ()
  ()
  (:menus
   (colors-menu "Colors"
                ((:component
                   (:red :green :blue)
                   :interaction :single-selection
                   :print-function
                   'string-capitalize)
                 more-colors-menu))
   (more-colors-menu "More Colors"
                      (:pink :yellow :cyan)
                      :print-function
                      'string-capitalize))
  (:menu-bar colors-menu)
  (:default-initargs :title "Test4"))
```

```
(capi:display (make-instance 'test4))
```

This example demonstrates inheritance amongst subclasses of interface:

```
(capi:define-interface test5 (test4 test1)
  ()
  (:default-initargs :title "Test5"))
(capi:display (make-instance 'test5))
```

The next three examples illustrate the use of :initarg in initarg specifications for :panes.

Here we initialize the :selected-items initarg of the pane foo to the value passed by :select when making the interface object, or mil otherwise:

Here we initialize the :selected-items initarg of pane foo to the value passed by :select initarg when making the interface object, or (1 3) otherwise:

```
(capi:define-interface init2 () ()
  (:panes
   (foo
     capi:list-panel
     :items '(0 1 2 3 4)
     :visible-min-height '(:character 5)
     :interaction :multiple-selection
     :selected-items
     (:initarg (select '(1 3))))))
(capi:contain (make-instance 'init2))
```

Here we increment the indices passed in the interface's :select initary before passing them in the :selected-items initary of pane foo:

There are many more examples in the directory examples/capi/.

See also

interface layout menu

define-layout Macro

Summary The macro define-layout creates new classes of layout.

Package capi

Signature define-layout name superclasses slots &rest options

Description The macro define-layout is used to create new classes of

layout. The macro is essentially the same as defclass

except that its default superclass is layout.

To implement a new class of layout, methods need to be provided for the following generic functions:

interpret-description

Translate the layout's child descriptions.

calculate-constraints

Calculate the constraints for the layout.

calculate-layout

Layout the children of the layout.

See also interpret-description

calculate-constraints

calculate-layout

layout

define-menu Macro

Summary The define-menu macro defines a menu function.

Package capi

Signature define-menu function-name (self) title menu-body &rest menu-

options

Description The macro define-menu defines a function called function-

name with a single argument *self* that will make a menu. The parameters *title*, *menu-body* and *menu-options* take the same

form as the :menus section of define-interface.

```
Example
              (capi:define-menu make-test-menu (self)
                 "Test"
                 ("Item1"
                  "Item2"
                  (:component
                   ("Item3"
                    "Item4")
                   :interaction :single-selection)
                  (:menu
                   ("Item5"
                    "Item6")
                   :title "More Items")))
              (setq interface (make-instance 'capi:interface))
              (setf (capi:interface-menu-bar-items interface)
                    (list (make-test-menu interface)))
              (capi:display interface)
See also
              define-interface
              menu
```

define-ole-control-component

Macro

Summary Defines a class that implements the OLE Control protocol for

a CAPI pane.

Package capi

Signature define-ole-control-component class-name (superclass-name*)

slots &rest class-options

Description The macro define-ole-control-component defines an

Automation component class *class-name* that also implements the OLE Control protocols and other named interfaces or a coclass. This allows a CAPI pane to be embedded in an OLE

Control container implemented outside LispWorks.

Each superclass-name argument specifies a direct superclass of the new class, which can be any standard-class provided that certain standard classes are included somewhere in the overall class precedence list. These standard classes depend on the other options and provide the default superclass list if none is specified. The following standard classes are available:

ole-control-component is always needed and provides an implementation of the OLE Control protocol.

com: standard-i-dispatch is always needed and provides a complete implementation of the i-dispatch interface, based on the type information in a type library.

com:standard-i-connection-point-container is needed if there are any source interfaces specified (via the :coclass or :source-interfaces options). This provides a complete implementation of the Connection Point protocols, used to support events.

slots is a list of standard defclass slot definitions.

class-options are standard defclass options. In addition the following options are recognized:

```
(:coclass coclass-name)
(:interfaces interface-name*)
(:source-interfaces interface-name*)
```

See com: define-automation-component in the *LispWorks COM/Automation User Guide and Reference Manual* for details of these options.

Typically the :pane-function and :create-callback initargs are supplied using the :default-initarg option.

Implementations of the methods in the :coclass and :interfaces options should be defined using com:define-com-method, com:define-dispinterface-method or com:com-object-dispinterface-invoke.

1 CAPI Reference Entries

Notes define-ole-control-component is implemented only in

LispWorks for Windows. Load the functionality by (require

"embed").

See also ole-control-component

destroy Generic Function

Summary Closes a window and calls the *destroy-callback*.

Package capi

Signature destroy interface

Description The generic function destroy closes the window associated

with interface, and then calls the interface's destroy-callback if it

has one.

There is a complementary function quit-interface which calls the interface's *confirm-destroy-function* to confirm that the destroy should be done, and it is advisable to always use this unless you want to make sure that the interface's

confirm-destroy-function is ignored.

Note: destroy must only be called in the process of *interface*. Menu callbacks on *interface* will be called in that process, but otherwise you probably need to use execute-with-inter-

face Or apply-in-pane-process.

Example (setq interface

(capi:apply-in-pane-process
interface 'capi:destroy interface)

See also interface

quit-interface

update-screen-interfaces-hooks

detach-simple-sink

Function

Summary Detaches a previously-attached simple sink object.

Package capi

Signature detach-simple-sink sink pane

Arguments *sink* A class instance.

pane An ole-control-pane.

Description The function detach-simple-sink detaches a sink that was

previously attached to the active component in the ole-con-

trol-pane pane by a call to attach-simple-sink.

sink is the value returned by attach-simple-sink when the

sink was attached.

pane is an ole-control-pane which is the pane where the

component is.

Attached sinks are automatically disconnected when the

object is closed.

Notes This function is implemented only in LispWorks for Win-

dows. Load the functionality by (require "embed").

See also attach-simple-sink

ole-control-pane

detach-sink Function

Summary Detaches a previously-attached sink.

Package capi

Signature detach-sink sink pane interface-name

Arguments *sink* A class instance.

pane An ole-control-pane.

interface-name A refguid or the symbol :default.

Description The function detach-sink detaches a sink which was previ-

ously attached to the active component in the ole-control-

pane pane.

sink is an instance of a class that implements the interface

interface-name.

pane is an ole-control-pane which is the pane where the

component is.

interface-name is either a string naming a source interface that
the component in pane supports or :default to disconnect

from the default source interface

from the default source interface.

Attached sinks are automatically disconnected when the

object is closed.

Notes This function is implemented only in LispWorks for Win-

dows. Load the functionality by (require "embed").

See also attach-sink

ole-control-pane

display Function

Summary Displays a CAPI interface on a specified screen.

Package capi

Signature display interface &key screen owner window-styles process =>

interface

Arguments *interface* A CAPI interface.

screen A screen, or any argument accepted by con-

vert-to-screen.

owner A CAPI interface.

window-styles A list of keywords.

process On GTK+, Windows or Motif, a CAPI pro-

cess, t or nil. On Cocoa, this argument is

not supported.

Values interface A CAPI interface.

Description The function display displays the CAPI interface interface on the specified screen (or the current one if not supplied).

If process is not supplied, then if owner is supplied interface runs in owner's process, otherwise interface runs in the process of the parent of interface if it is a document-container, or in a new process created for interface if not.

On Windows and Motif, if process is t, then interface runs in a newly-created process. If process is nil, interface runs in the current process. Otherwise process is expected to be a CAPI process, and interface runs in it. A CAPI process is a mp:process which was created by calling display. You can pass only a CAPI process as process, because it needs to handle messages using the LispWorks event loop. The default value of process is t.

On Cocoa, all CAPI interfaces run in the Cocoa Event Loop process (which is the main thread of LispWorks) and therefore the *process* argument is not supported. If the value of *process* is any process other than the Cocoa Event Loop process an error is signalled.

owner specifies an owner for *interface*, which should be another CAPI interface. *interface* inherits a number of attributes from *owner*, including the default process, default screen and default display state.

window-styles, if supplied, sets the window-styles slot of interface. See interface for information about window-styles.

display returns its interface argument.

Note: Use the function contain to display objects other than interfaces.

Note: A generic function interface-display is called immediately after display displays an interface. You can add post-display code by defining your own :after method.

```
Example (capi:display (make-instance 'capi:interface :title "Test"))

See also contain convert-to-screen display-dialog document-container execute-with-interface interface interface interface *update-screen-interfaces-hooks*
```

display-dialog

Generic Function

Summary The display-dialog function displays a CAPI interface as a

dialog box.

Package capi

Signature display-dialog interface &key screen focus modal owner x y

position-relative-to continuation callback-error-handler => result,

okp

Arguments interface A CAPI interface.

screen A screen.

focus A pane of interface.

modal t, :dismiss-on-input or nil.

owner A pane.

x, y Real numbers representing coordinates, or

keywords or lists specifying an adjusted

position.

position-relative-to

:owner Or nil.

continuation A function or mil.

callback-error-handler

A function designator or mil.

Values result An object.

okp A boolean.

Description This is a complementary function that displays the CAPI

interface interface as a dialog box.

screen is the screen for the dialog to be displayed on.

focus should be the pane within the interface that should be given the focus initially. If a focus is not supplied, then it lets the window system decide.

A true value of *modal* indicates that the dialog takes over all input to the application. Additionally, if *modal* is :dismiss-on-input then any user gesture (a button or key press) causes the dialog to disappear. :dismiss-on-input works on platforms other than Motif. The default value of *modal* is t.

owner specifies an owner window for the dialog. See the "Prompting for Input" chapter in the *CAPI User Guide* for details.

If x and y are numbers they specify the coordinates of the dialog. Alternatively x and y can be keywords like :left and :top, or lists like (:left 100), (:bottom 50) and so on.. These values cause the dialog to be positioned relative to its owner in the same way as the adjust argument to paneadjusted-position. The default location is at the center of the dialog's owner.

position-relative-to has a default value :owner, meaning that x and y are relative to dialog's owner. The value nil means that x and y are relative to the screen.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by display-dialog. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and display-dialog returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

The values returned depend on how the dialog is dismissed. Typically a user gesture will trigger a call to abort-dialog, causing the values nil, nil to be returned or to exit-dialog

causing the values *result*, to be returned, where *result* is the argument to <code>exit-dialog</code>. If *continuation* is non-nil, then the returned values are always :continuation, nil.

The CAPI also provides popup-confirmer which gives you the standard **OK** and **Cancel** button functionality.

callback-error-handler allows error handling in callbacks which is uniform across platforms, as described for popup-con-firmer.

Notes

- 1. If you need to replace one dialog with another, you can use display-replacable-dialog and replace-dialog.
- 2. In a modal dialog at least one button which aborts or exits the dialog must be provided in *interface*. This is the programmer's responsibility, as without such a button there is no way to clear the modal dialog. A straightforward way to add these buttons is to display the window via popup-confirmer which adds the buttons for you.

```
Example
```

There are further examples in the directory examples/capi/dialogs/.

See also

```
abort-dialog
display
display-replacable-dialog
exit-dialog
interface
```

popup-confirmer
with-dialog-results

update-screen-interfaces-hooks

display-errors Macro

Summary Displays a message if an error is signalled.

Package capi

Signature display-errors &body body

Description The macro display-errors executes the code of body inside

a handler-case form. If an error is signalled inside *body*, a message is displayed and the debugger is not entered.

display-message

Function

Summary The function display-message displays a message on the

current CAPI screen.

Package capi

Signature display-message format-string &rest format-args

Description The function display-message creates a message from the

arguments using format, and then displays it on the current

CAPI screen.

Note: If you need to make a window-modal sheet on Cocoa,

then use the function prompt-with-message.

Example (capi:display-message "Current screen = ~S"

(capi:convert-to-screen))

See also prompt-with-message

display-message-for-pane

display-dialog

display-message-for-pane

Function

Summary The function display-message-for-pane displays a mes-

sage on the same screen as a specified pane.

Package capi

Signature display-message-for-pane pane format-string &rest format-args

Description The function display-message-for-pane creates a message

from the arguments using format, and then displays it on the

same screen as pane.

Note: If you need to make a window-modal sheet on Cocoa,

then use the function prompt-with-message.

Compatibility

note

The function display-message-on-screen is retained for compatibility with previous versions of LispWorks. It is a

synonym for display-message-for-pane.

Example (setq pane (capi:contain (make-instance

'capi:text-input-pane)))

(capi:display-message-for-pane pane

"Just created ~S" pane)

See also prompt-with-message

display-message

display-pane

Summary The class display-pane is a pane that displays several lines

of text.

Class

```
Package
              capi
Superclasses
              titled-object
              simple-pane
Initargs
                               A string or a list of strings to be displayed.
              :text
Accessors
              display-pane-text
Description
              The text passed to a display pane can be provided either as a
              single string containing newlines, or else as a list of strings
              where each string represents a line.
              There are several classes which can display text, as follows:
              title-pane
                               Displays a single line of text.
              display-pane
                               Displays multiple lines of text.
              text-input-pane
                               Inputs a single line of text.
              editor-pane
                               Inputs multiple lines of text.
Example
               (capi:contain (make-instance
                               'capi:display-pane
                               :text
                                 '("One" "Line" "At" "A" "Time...")))
               (setq dp (capi:contain
                          (make-instance
                           'capi:display-pane
                           '("One" "Line" "At" "A" "Time...")
                           :visible-min-height
                           '(:character 5))))
               (capi:apply-in-pane-process
               dp #'(setf capi:display-pane-text)
                '("Some" "New" "Text") dp)
```

See also editor-pane

text-input-pane

title-pane

display-pane-selected-text

Function

Summary Returns the selected text in a display-pane.

Package capi

Signature display-pane => result

Arguments display-pane An instance of display-pane or a subclass.

Values result A string or nil.

Description The function display-pane-selected-text returns the

selected text in *display-pane*, or nil if there is no selection.

See also display-pane

display-pane-selection-p
display-pane-selection

display-pane-selection

Function

Summary Returns the bounds of the selection in a display-pane.

Package capi

Signature display-pane-selection pane => start, end

Arguments pane A display-pane.

Values *start, end* Non-negative integers.

1 CAPI Reference Entries

Description The function display-pane-selection returns as multiple

values the bounding indexes of the selection in *pane*. That is, *start* is the inclusive index of the first selected character, and *end* is one greater than the index of the last selected character.

If there is no selection, then both start and end are the caret

position in pane.

See also set-display-pane-selection

display-pane

display-pane-selected-text
display-pane-selection-p

display-pane-selection-p

Function

Summary Returns true if there is selected text in a display-pane.

Package capi

Signature display-pane-selection-p pane => selectionp

Arguments pane A display-pane.

Values selectionp A boolean.

Description The function display-pane-selection-p returns t if there

is a selected region in pane and nil otherwise.

See also set-display-pane-selection

display-pane

display-pane-selected-text
display-pane-selection

display-popup-menu

Function

Summary Displays a popup menu.

Package capi

Signature display-popup-menu menu &key owner x y button => result

Arguments *menu* A menu.

owner A pane.

x The horizontal coordinate of *menu*'s position

relative to *owner*.

y The vertical coordinate of *menu*'s position

relative to owner.

button The mouse button that raises the menu.

Description

The function display-popup-menu displays the menu menu at position x,y. display-popup-menu should be used in response to the user clicking a mouse button, and is typically used to implement contextual ("right button") menus.

The user may select an item in the menu, in which case the item's *selection-callback* is invoked, and display-popup-menu returns t.

Alternatively the user may cancel the menu, by clicking elsewhere or pressing the Escape key. In this case, display-popup-menu returns nil.

owner specifies the owner of the menu, that is, a pane that the menu is associated with. If *owner* is not supplied the system trys to find the appropriate owner, which usually suffices.

x and *y* default to the horizontal and vertical coordinates, relative to *owner*, of the location of the mouse pointer.

button defaults to :button-3.

display-replacable-dialog

Function

Summary Displays a replacable dialog.

Package capi

Signature display-replacable-dialog interface &rest args => result

Arguments interface An interface.

args Other arguments as for display-dialog.

Values result The value returned by the dialog.

Description The function display-replacable-dialog displays a

dialog that can be replaced by another dialog.

interface is a CAPI interface to be displayed as a dialog.

The arguments args are interpreted the same as the arguments to display-dialog, except that modal is ignored. display-replacable-dialog displays the dialog like dis-

play-dialog.

Within the scope of display-replacable-dialog (that is, inside the callbacks) the programmer can call replace-dialog which replaces the dialog by a new dialog and destroys the existing one. There can be many calls to replace-dialog inside the same scope of display-replacable-dialog.

display-replacable-dialog returns the last dialog that was displayed.

Inside display-replacable-dialog, the functions that use the current dialog, such as exit-dialog and abort-dialog, work in the same way that they work inside display-dialog, except that they don't affect the return value of display-replacable-dialog.

See also

abort-dialog display-dialog exit-dialog replace-dialog

display-tooltip

Generic Function

Summary	Displays tooltip help on an output pane.	
Package	capi	
Signature	display-tooltip output-pane &key x y text => result	
Arguments	output-pane	An instance of a subclass of output-pane.
	X	The horizontal coordinate of the tooltip position.
	У	The vertical coordinate of the tooltip position.
	text	The help text.

1 CAPI Reference Entries

Description The generic function display-tooltip displays text as

tooltip help at position *x*,*y* in *output-pane*.

Notes 1. On GTK+ display-tooltip is implemented only for

GTK+ versions 2.12 and later

2. On GTK+ the :x and :y arguments might not be han-

dled.

Compatibility

On GTK+ display-tooltip is not implemented in

note LispWorks 6.0.

Example See the example file

examples/capi/graphics/pinboard-help.lisp

docking-layout Class

Summary A class that implements docking of panes.

Package capi

Superclasses simple-layout

Initargs :items A list of pane specifications. The panes

become the items in the layout.

:controller A controller for the layout, which can make

multiple docking-layouts work together.

:docking-test-function

A function controlling whether a pane can

be docked in a docking-layout.

:docking-callback

A function called when a pane is docked or

undocked.

:divider-p A boolean allowing a visible edge around

the layout.

:orientation One of :horizontal or :vertical.

ACCESSORS docking-layout-controller

docking-layout-divider-p

docking-layout-docking-test-function

docking-layout-items

Readers docking-layout-orientation

Description The class docking-layout defines a region in which panes can be docked and undocked. The undocking functionality works only in LispWorks for Windows.

If controller is non-nil, it must be a controller object as returned by a call to make-docking-layout-controller. In this case the docking-layout is one of a group of docking-layouts which share that same controller, known as the Docking Group. The panes that can be docked and undocked are shared between the members of the Docking Group. If controller is nil (the default value), the docking-layout is in a Docking Group of one.

A pane pane is dockable in a Docking Group when it is an item of any member of the Docking Group. This is the case when it is one of the *items* passed to make-instance for some member of the group, or it has been set in some member by (setf docking-layout-items). The user can dock and undock pane in any member of the Docking Group. You can change the dockable status of panes programmatically by (setf docking-layout-items). You can query a pane's docked and visible status in a docking-layout by docking-layout-pane-docked-p and docking-layout-pane-visible-p. You can change a pane's docked and visible status in a docking-layout by (setf docking-layout-pane-docked-p) and (setf docking-layout-pane-visible-p).

By default, the context menu allows the user to alter the visibility status of each of the panes in the Docking Group.

items is a list of pane specifications. Each specification in the list is either an atom denoting a pane, or a list wherein the car is an object denoting a pane and the cdr is a plist of options and values. The object denoting the pane can be:

- The pane itself
- A symbol naming a slot in the interface which contains the docking-layout. The value in that slot, which must be a pane, is used. Typically the slot name is defined in the :panes or :layouts class option in the defineinterface form.
- A string, denoting a title-pane with that text.
- A list, wherein the car is the name of a pane class and the cdr is a list of initialization arguments for that class. This denotes the pane created by applying make-instance to the list. Note that in this case the list cannot be the item in the *items* list, because it would be wrongly interpreted as a list wherein the car denotes a pane directly and the cdr is a plist of options and values.

When an item in the *items* list is a list, the cdr is a plist of options and values, which can contain these options:

A string which is title associated with the pane. This is used when the pane is presented to the user, for example in the default context menu.

A boolean specifying whether the pane should be docked. The default value is t. When a pane is not docked and is visible, it is displayed in its own window.

:visible-p A boolean specifying whether the pane is visible. The default value is t.

:undocked-geometry

A list of four integers specifying the geometry of the pane when undocked, as (x y width height).

:start-new-line-p

A boolean specifying whether to place the pane on a new line in the docking-layout. The default value is nil.

docking-layout-items always returns the items as lists, with the cdr containing the options and values.

docking-test-function is a function of two arguments with a boolean return value. When the user attempts to dock a pane pane in the docking-layout, docking-test-function is called with the docking-layout and pane. If it returns nil, pane is not docked. If it returns true, pane is docked. The default behavior is that all panes under the controller which is the controller in this docking-layout, and only these panes, can be docked.

docking-callback, if non-nil, is a function of three arguments: the docking-layout, the pane and a boolean. This third argument is t when the pane is docked, and nil when the pane is undocked. The default value of docking-callback is nil.

divider-p controls whether a visible edge is drawn around the border of the docking-layout. The default value is nil.

orientation specifies whether the items are laid out horizontally or vertically. The default value is :horizontal.

Example See the file examples/capi/layouts/docking-layout.lisp

See also docking-layout-pane-docked-p docking-layout-pane-visible-p

docking-layout-pane-docked-p

Function

Package capi

Signature docking-layout-pane-docked-p docking-layout pane &key

anywhere => dockedp

Signature (setf docking-layout-pane-docked-p) dockedp docking-layout

pane => dockedp

Arguments docking-layout An instance of docking-layout or a sub-

class.

pane A pane.

anywhere A boolean.

Values dockedp A boolean.

Description The function docking-layout-pane-docked-p returns a

boolean indicating whether pane is currently docked.

If anywhere is t, dockedp is true if pane is docked in any member of the Docking Group of docking-layout. If anywhere is nil, dockedp is true only if pane is docked in docking-layout

itself. The default value of anywhere is nil.

(setf docking-layout-pane-docked-p) may be used to change the docking state of pane in *docking-layout* only when *pane* is dockable in the Docking Group of *docking-layout*.

See also docking-layout

docking-layout-pane-visible-p

Function

Package capi

Signature docking-layout-pane-visible-p docking-layout

pane => visiblep

Signature (setf docking-layout-pane-visible-p) visiblep docking-layout

pane => visiblep

Arguments docking-layout An instance of docking-layout or a sub-

class.

pane A pane.

Values visiblep A boolean.

Description The function docking-layout-pane-visible-p returns a

boolean indicating whether *pane* is currently visible in the Docking Group of *docking-layout*. *pane* may be docked in any

member of the Docking Group, or undocked.

(setf docking-layout-pane-visible-p) may be used to change the visiblity of pane in *docking-layout* only when *pane*

is dockable in the Docking Group of docking-layout.

See also docking-layout

document-container

Class

Package capi

Superclasses capi-object

Readers screen-interfaces

Description The class of the container in a document-frame.

A document container has some screen-like functionality, responding to screen-internal-geometry and screen-

active-interface.

This works only in LispWorks for Windows.

See also display

document-frame

screen-active-interface screen-internal-geometry

document-frame Class

Summary The class document-frame is used to implement MDI.

This works only in LispWorks for Windows.

Package capi

Superclasses interface

Readers document-frame-container

Description The class document-frame is used to implement Multiple-

Document Interface (MDI) which is a standard technique on Microsoft Windows (see the MSDN for documentation).

To use MDI in the CAPI, define an interface class that inherits

from document-frame, and use the two special slots capi:container and capi:windows-menu as described

below.

In your interface's layouts, use the symbol capi:container in the *description* to denote the pane inside the MDI interface in which child interfaces are added.

document-frame-container is a reader which returns the document-container of the document-frame.

Interfaces of any type other than subclasses of

document-frame may be added as children. To add a child interface in your MDI interface, call display on the child interface and pass the MDI interface as the *screen* argument. This will display the child interface inside the container pane.

To obtain a list of the child interfaces, call the screen reader function screen-interfaces, passing the frame's document-container as the screen argument.

You can use most of the normal CAPI window operations such as top-level-interface-geometry and activate-pane on windows displayed as children of a document-frame.

The capi:windows-menu slot contains the Windows Menu, which allows the user to manipulate child interfaces. The standard functionality of the Windows Menu is handled by the system and normally you will not need to modify it. However, you will want to specify its position in the menu bar. Do this by adding the symbol capi:windows-menu in the :menu-bar option of your define-interface form.

Note: capi:windows-menu is a special slot in documentframe and this symbol should not appear elsewhere in the define-interface form.

By default the menu bar is made by effectively appending the menu bar of the document-frame interface with the menu bar of the current child. You can customize this behavior with merge-menu-bars.

Example

This example uses document-frame to create a primitive apropos browser.

Firstly we define an interface that lists symbols. There is nothing special about this in itself.

Next we define the MDI interface. Note:

- 1. It inherits from document-frame.
- 2. capi:container is used in the layout description.
- 3. capi:windows-menu is in the :menu-bar list.
- **4.** When the interface showing the symbols is being displayed, the MDI interface is passed as the *screen* argument to display.

Otherwise, this example uses standard Common Lisp and CAPI functionality.

```
(capi:define-interface my-apropos-browser
                  (capi:document-frame)
                ((string :initarg :string))
                (:panes
                 (package-list
                  capi:list-panel
                  :items
                  (loop for package in (list-all-packages)
                        (let ((al (apropos-list string package)))
                          (when al
                            (cons (package-name package) al)))
                        collect it)
                  :print-function 'car
                  :action-callback
                  #'(lambda (mdi-interface name-and-symbols)
                      (capi:display
                       (make-instance
                        'symbols-listing
                        :symbols (cdr name-and-symbols)
                        :title (car name-and-symbols))
                       :screen mdi-interface))
                  :callback-type :interface-data)
                (:menu-bar capi:windows-menu)
                (:layouts
                 (main
                  capi:row-layout
                  '(package-list :divider capi:container)
                  :ratios '(1 nil 4)))
                (:default-initargs
                 :visible-min-height '(character 20)
                 :visible-min-width '(character 100)))
             To browse apropos of a specific string
              (capi:display
               (make-instance 'my-apropos-browser
                              :string "EDITOR"))
See also
             current-document
             merge-menu-bars
```

double-headed-arrow-pinboard-object

Class

Summary A pinboard-object that draws itself as an arrow, which can

switch dynamically from double-headed to single-headed.

Package capi

Superclasses arrow-pinboard-object

InitargS :double-head-predicate

A function determining whether a single or

double arrowhead is drawn.

Description double-head-predicate should be a function of two arguments

returning a boolean value. The first argument is the output pane on which the arrow pinboard object is drawn. The second argument is the arrow pinboard object itself.

double-head-predicate should return a true value if the arrow is to be double-headed, and nil if a single-headed arrow should be drawn. It is called each time the arrow object is

redrawn.

```
Example
              (defvar *doublep* t)
              (let ((dhr
                     (capi:contain
                      (make-instance
                       'capi:pinboard-layout
                       :description
                       (list
                        (make-instance
                         'capi:double-headed-arrow-pinboard-object
                         :double-head-predicate
                         #'(lambda (x y) *doublep*)
                         :start-x 5 :start-y 5 :end-x 95 :end-y 95)
                        (make-instance
                         'capi:double-headed-arrow-pinboard-object
                         :double-head-predicate
                         #'(lambda (x y) *doublep*)
                         :head-direction :backwards
                          :start-x 5 :start-y 95 :end-x 95 :end-y 5)))
                      :visible-min-width 100
                      :visible-min-height 100)))
                (dotimes (x 10)
                  (sleep 1)
                  (setg *doublep* (not *doublep*))
                  (mapcar 'capi:redraw-pinboard-object
                          (capi:layout-description dhr))))
```

double-list-panel

Class

Summary

A choice which displays its selected items and its unselected items in disjoint lists, and facilitates easy movement of items between these lists.

Package capi

Superclasses choice

interface

Description

The class double-list-panel is a choice which displays its *items* in two list-panels. One list contains the selected items and the other contains the unselected items. There is a pair of arrow buttons which move highlighted items between the lists.

The default *interaction* of double-list-panel is :extended-selection.

The selection-callback, extend-callback or retract-callback is called as appropriate when items are moved between the lists. There is no action-callback for double-list-panel.

The user selects and de-selects items in the double-list-panel by moving them between the two lists. There are three ways to move the items:

- 1. Highlight the items to move by normal list-panel selection gestures, then press an arrow button.
- 2. Highlight a single item to move by normal list-panel selection gestures, then press Return.
- 3. Double click on an item to move it.

Example

See also

list-panel

drag-pane-object

Function

Summary Initiates a dragging operation

Package capi

Signature drag-pane-object pane value &key string plist image-function

operations => operation

Arguments *pane* A pane

value An object to be dragged

string A string to be dragged or nil

plist A plist of formats and objects to be dragged

image-function A function or mil

operations A list of operation keywords allowed for the

dragged objects

Values *operation* One of the operation keywords

Description The function drag-pane-object initiates a dragging opera-

tion from within the pane pane. It can only be called from within the button :press or button :motion callbacks of the

input-model of an output-pane.

The value, string and plist arguments are combined to provide

an object to be dragged in various formats.

value can be any Lisp object (not necessarily a string) to make available for dropping into a pane within the local Lisp

image.

string can be a string representation of value to make available, or nil. If string is nil and value is a string, then that will

be made available as the string.

plist is a property list of additional format/value pairs to make available. The currently supported formats are as described for set-drop-object-supported-formats. You can make more than one format available simultaneously.

image-function provides a graphical image for use during the dragging operation on Cocoa. If image-function is supplied, then it should be a function of one argument. It might be called to provide an image for use during the dragging operation. The function image-function should return three values: a image object, an x offset and a y offset. The x and y offsets are the position within the image where the mouse should be located. If the image is nil or image-function is not supplied then a default image is generated. If the x or y offsets are nil or not returned then the image is positioned with the mouse at its center point. The image that is returned by image-function is freed automatically in the end of dragging operation. It must be a new image, and cannot be reused.

operations should be a list of operation keywords that the pane will allow the target application to perform. The operation keywords are :copy, :move and :link as described for the effect in drop-object-drop-effect. If certain platform-specific modifier keys are pressed, then some of the operations will be ignored.

The return value *operation* indicates which operation was performed by the application where the dragged object was dropped. The value will be :none if the object was not dropped anywhere or dragging was abandoned (for example, by the user hitting the Escape key). If *operation* is :move, then you should update the data structures in your application to remove the object that was dragged.

Notes

- 1. drag-pane-object is not supported on X11/Motif. See simple-pane for information about drop callbacks.
- **2.** *image-function* is only called on Cocoa. There is no way to specify an image when dragging on Microsoft Windows.

3. If :image is supplied in *plist*, the dragging mechanism automatically frees the image object as if by free-image when it no longer needs it.

Example See examples/capi/output-panes/drag-and-drop.lisp

See also simple-pane

draw-metafile Function

Summary Draws a metafile to a pane.

Package capi

Notes

Signature draw-metafile pane metafile x y width height

Arguments pane An output-pane.

metafile A metafile, as described in with-internal-

metafile.

x,y Integers.

width, height Non-negative integers.

 ${\tt Description} \qquad {\tt The \ function \ draw-metafile \ } draws \ the \ metafile \ metafile \ to$

the pane pane at position x,y with size width, height.

metafile should be a metafile as returned by with-internal-

metafile.

The graphics-state parameters transform, mask and mask-transform affect how the metafile is drawn. The other graph-

ics-state parameters are taken from the metafile.

1. draw-metafile is supported on GTK+ only where Cairo is supported (GTK+ 2.8 and later).

2. Metafiles look bad on GTK+, because they transform the image rather than the drawing.

3. draw-metafile is not implemented on X11/Motif.

Examples examples/capi/graphics/metafile.lisp

examples/capi/graphics/metafile-rotation.lisp

See also can-use-metafile-p

clipboard

draw-metafile-to-image

free-metafile

with-internal-metafile

draw-metafile-to-image

Function

Summary Draws a metafile as an image.

Package capi

Signature draw-metafile-to-image pane metafile &key width height max-

width max-height background alpha => image

Arguments pane An output-pane.

metafile A metafile.

width, height Non-negative integers, or nil.

max-width, max-height

Non-negative integers, or mil.

background A color specification.

alpha A generalized boolean.

Values image An image.

Description

The function draw-metafile-to-image returns a new image object for *pane*, with *metafile* drawn into the image.

metafile should be a metafile as returned by with-internal-metafile.

If width and height are both nil then the size of the image is computed from the metafile. If both width and height are integers, then they specify the size of the image and the metafile is scaled to fit. If one of width or height is nil, then it is computed from the other dimension, preserving the aspect ratio of the metafile. The default values of width and height are both nil.

The *max-width* and *max-height* arguments, if non-nil, constrain the computed or specified values of *width* and *height* respectively. The aspect ratio is retained when the size is constrained, so specifying a *max-width* can also reduce the actual height of the image. The default values of *max-width* and *max-height* are both nil.

background should be a color spec, which controls the non-drawn parts of the image. (A color spec can be obtained by get-color-spec, make-rgb and so on.) If background is omitted, then the background color of pane is used.

If *alpha* is non-nil, then the image will have an alpha component. The default value of *alpha* is nil.

Notes

- 1. draw-metafile-to-image is supported on GTK+ only where Cairo is supported (GTK+ 2.8 and later).
- **2.** Metafiles look bad on GTK+, because they transform the image rather than the drawing.
- **3.** draw-metafile-to-image is not implemented on X11/Motif.

See also clipboard

draw-metafile
free-metafile

with-internal-metafile

drawn-pinboard-object

Class

Summary The class drawn-pinboard-object is a subclass of pin-

board-object which is drawn by a supplied function, and is provided as a means of the user creating their own pinboard

objects.

Package capi

Superclasses pinboard-object

Initargs :display-callback

Called to display the object.

ACCESSOFS drawn-pinboard-object-display-callback

Description The *display-callback* is called with the output pane to draw on,

the drawn-pinboard-object itself, and the *x*, *y*, *width* and *height* of the object, and it is expected to redraw that section. The *display-callback* should not draw outside the object's

bounds.

An alternative way of doing this is to create a subclass of pinboard-object and to provide a method for draw-pin-

board-object.

draw-pinboard-object

See also

Generic Function

Summary Draws a pinboard object.

Package capi

Signature draw-pinboard-object pinboard object &key x y width height

&allow-other-keys

pinboard-layout

Description The generic function draw-pinboard-object is called when-

ever a pinboard object needs to be drawn. The x, y, width and

height arguments indicate the region that needs to be

redrawn, but a method is free to ignore these and draw the complete object. However, it should not draw outside the

pinboard object's bounds.

Example See the example in the file

examples/capi/graphics/circled-graph-nodes.lisp

See also pinboard-layout

pinboard-object

draw-pinboard-object-highlighted

Generic Function

Summary Draws highlighting on a pre-drawn pinboard object.

Package capi

Signature draw-pinboard-object-highlighted pinboard object &key

&allow-other-keys

Description The generic function draw-pinboard-object-high-

lighted draws the highlighting onto a pinboard object that has already been drawn. The default highlighting method draws a box around the object, and should be sufficient for

most purposes.

Example See the example in the file

examples/capi/graphics/circled-graph-nodes.lisp

See also draw-pinboard-object-unhighlighted

highlight-pinboard-object

draw-pinboard-object-unhighlighted

Generic Function

Summary Removes the highlighting from a pinboard object.

Package capi

Signature draw-pinboard-object-unhighlighted pinboard object &key

&allow-other-keys

Description The generic function draw-pinboard-object-unhigh-

lighted removes the highlighting from a pinboard object.

Example See the example in the file

examples/capi/graphics/circled-graph-nodes.lisp

See also draw-pinboard-object-highlighted

highlight-pinboard-object

drop-object-allows-drop-effect-p

Function

Summary Queries whether a dropping operation can be performed

with a given effect.

Package capi

Signature drop-object-allows-drop-effect-p drop-object effect => result

Arguments drop-object A drop-object, as passed to the drop-callback.

effect An effect keyword

Values result A boolean

Description The function drop-object-allows-drop-effect-p returns

non-nil if the dropping operation can be performed with the given effect effect. It returns nil if the dropping operation cannot be performed. See drop-object-drop-effect for

information on drop effect keywords.

Note: drop-object-allows-drop-effect-p should only be

called within a *drop-callback*. It is not supported on

X11/Motif. See simple-pane for information about drop

callbacks.

See also drop-object-drop-effect

simple-pane

drop-object-collection-index

Function

Summary Gets the index and relative place in the collection that an

object is being dropped over.

Signature drop-object-collection-index drop-object => index, placement

 $(\verb|setf| (drop-object-collection-index| \textit{drop-object}) \quad (\verb|values|)$

new-index new-placement))

Arguments drop-object A drop-object, as passed to the drop-callback.

new-index An integer.

new-placement One of :above, :item or :below.

Values *index* An integer.

placement One of :above, :item or :below.

Description The function drop-object-collection-index returns the

index and place relative to that index within the collection that the object *drop-object* is being dropped over. This information is only meaningful when the pane is an instance of

list-panel or tree-view.

The returned value *index* is the position in the collection (see get-collection-item or choice-selection). The returned value *placement* indicates whether the user is drop-

ping above, on or below the item at index.

There is also a setf expander that can be called with these two values within the :drag stage of the operation, to adjust

where the user will be allowed to drop the object.

Notes drop-object-collection-index should only be called

within a *drop-callback*. It is not supported on X11/Motif. See

simple-pane for information about drop callbacks.

Example For an example illustrating the use of drag and drop in a

choice, see

examples/capi/choice/drag-and-drop.lisp

See also drop-object-collection-item

drop-object-collection-item

Function

Summary Gets the item and relative place in the collection that an

object is being dropped over.

Signature drop-object-collection-item drop-object => item, placement

 $(\verb|setf| (drop-object-collection-item| \textit{drop-object}) \quad (\verb|values|)$

new-item new-placement))

Arguments drop-object A drop-object, as passed to the drop-callback.

new-item An item of a collection.

new-placement One of :above, :item or :below.

Values *item* An item of a collection.

placement One of :above, :item or :below.

Description The function drop-object-collection-item returns the

item and place relative to that item within the collection that the object *drop-object* is being dropped over. This information is only meaningful when the pane is an instance of

list-panel or tree-view.

The returned value *placement* indicates whether the user is

dropping above, on or below the item.

There is also a setf expander that can be called with these two

values within the :drag stage of the operation, to adjust

where the user will be allowed to drop the object.

Notes drop-object-collection-item should only be called

within a drop-callback. It is not supported on X11/Motif. See

simple-pane for information about drop callbacks.

Example For an example illustrating the use of drag and drop in a

choice, see

examples/capi/choice/drag-and-drop.lisp

See also drop-object-collection-index

drop-object-drop-effect

Function

Summary Reads or sets the current effect of a dropping operation.

Package capi

Signature drop-object-drop-effect drop-object => effect

Signature (setf drop-object-drop-effect) effect drop-object => effect

Arguments drop-object A drop-object, as passed to the drop-callback.

Values effect An effect keyword

Description The function drop-object-drop-effect gets or sets the

current effect of the dropping operation. *effect* can be one of:

:copy The object will be copied. This is the most

common value for operations between

applications.

:move The object will be moved. This is usually

triggered by the user dragging with a plat-

form-specific modifier key pressed.

:link A link to the object will be created. This is

usually triggered by the user dragging with a platform-specific modifier key pressed.

none No dragging is possible.

Notes drop-object-drop-effect should only be called within a

drop-callback. It is not supported on X11/Motif. See simple-

pane for information about drop callbacks.

Example See examples/capi/output-panes/drag-and-drop.lisp

See also simple-pane

drop-object-get-object

Function

Summary Returns a dropped object in a given format

Package capi

Signature drop-object-get-object drop-object format => object

Arguments drop-object A drop-object, as passed to the drop-callback.

format A format keyword

Values *object* An object in the given format

Description The function drop-object-get-object returns the dropped

object in the given format. See set-drop-object-sup-ported-formats for information on format keywords.

Notes

- 1. When receiving an image (by calling drop-object-get-object with the :image format), the received image should also be freed when you finish with it. However, it will be freed automatically when the pane supplied to drop-object-get-object is destroyed, so normally you do not need to free it explictly.
- 2. drop-object-get-object should only be called within a *drop-callback*. It is not supported on X11/Motif. See simple-pane for information about drop callbacks.

Example See

examples/capi/output-panes/drag-and-drop.lisp

and

examples/capi/choice/list-panel-drag-images.lisp.

See also set-drop-object-supported-formats

simple-pane

drop-object-pane-x drop-object-pane-y

Generic Functions

Summary Gets the coordinates in the pane that an object is being

dropped over.

Package capi

Signature drop-object-pane-x drop-object => x-coord

drop-object-pane-y drop-object => y-coord

Arguments drop-object A drop-object, as passed to the drop-callback.

Values *x-coord, y-coord* Integers.

Description The accessor functions drop-object-pane-x and drop-

object-pane-y return the x and y coordinates within the pane that the object is being dropped over. This information is only meaningful when the pane is an instance of output-

pane or one of its subclasses.

Notes drop-object-pane-x and drop-object-pane-y should

only be called within a *drop-callback*. They are not supported on X11/Motif. See simple-pane for information about drop

callbacks.

See also simple-pane

drop-object-provides-format

Function

Summary Queries whether a dropping operation can provide an object

in a given format.

Package capi

Signature drop-object-provides-format drop-object format => result

Arguments drop-object A drop-object, as passed to the drop-callback.

format A format keyword

Values result A boolean

Description The function drop-object-provides-format returns non-

nil if the dropping operation can provide an object in the given format. It returns nil if it cannot provide that format.

See set-drop-object-supported-formats for information

on format keywords.

Notes drop-object-provides-format should only be called

within a *drop-callback*. It is not supported on X11/Motif. See

simple-pane for information about drop callbacks.

Example See examples/capi/output-panes/drag-and-drop.lisp

See also set-drop-object-supported-formats

simple-pane

echo-area-cursor-inactive-style

Variable

Summary The drawing style of the Echo Area cursor when the window

is inactive.

Package capi

1 CAPI Reference Entries

Initial Value :invisible

Description The drawing style of the cursor in the Echo Area of an

inactive window in the LispWorks IDE.

The allowed values are :inverse, :outline, :underline

and:invisible.

echo-area-pane

Class

Summary The class of the Editor's echo area.

Package capi

Superclasses editor-pane

Description The class echo-area-pane is used to implement the small

window for user interaction, known as the Echo Area, which is at the bottom of Editor windows in the LispWorks IDE

development environment.

You should not normally need to work with this class directly. To add an Echo Area, pass:echo-area t when

making the editor-pane.

editor-cursor-color

Variable

Summary The background color of the cursor.

Package capi

Initial Value nil

Description When non-nil, the value is a color spec or color alias

determining the background color of the editor-pane cursor. See "The Color System" in the *CAPI User Guide* for infor-

mation about colors in LispWorks.

The value mil means that the cursor background color is the

same as the foreground color of the editor pane.

Example (setf capi:*editor-cursor-color* :red)

editor-cursor-active-style

Variable

Summary The drawing style of the editor's cursor when the window is

active.

Package capi

Initial Value :inverse

Description The drawing style of an editor-pane cursor when the

window is active.

The allowed values are :inverse, :outline, :underline,

:left-bar and :caret.

See also editor-pane-blink-rate

editor-cursor-drag-style

Variable

Summary The drawing style of the editor's cursor during a selection

drag.

Package capi

Initial Value :left-bar

1 CAPI Reference Entries

Description The drawing style of an editor-pane cursor during a

selection drag.

The allowed values are :inverse, :outline, :underline,

:left-bar and :caret.

editor-cursor-inactive-style

Variable

Summary The drawing style of the editor's cursor when the window is

inactive.

Package capi

Initial value :outline

Description The drawing style of an editor-pane cursor when the

window is inactive.

The allowed values are :inverse, :outline, :underline or

:invisible.

editor-pane Class

Summary An editor pane is an editor that has all of the functionality

described in the LispWorks Guide To The Editor.

Package capi

Superclasses output-pane

Subclasses interactive-pane

collector-pane

Initargs :text A string or nil.

:enabled t, nil Or :read-only.

:buffer-modes A list specifying the modes of the editor buffer.

:buffer-name The name of the editor buffer.

:change-callback

A function designator, or mil.

:before-input-callback

A function designator, or mil.

:after-input-callback

A function designator, or nil.

:echo-area A flag determining whether the editor pane has an Echo Area.

:fixed-fill An integer specifying the fill length, or mil.

:line-wrap-marker

A character, or nil.

:line-wrap-face

An editor: face object, or a symbol naming a face, or nil.

:wrap-style An integer specifying the fill length, or nil.

:composition-face

Changes the editor face that is used by editor-pane-default-composition-callback to display the composition string. The default value is :default.

Accessors

editor-pane-text
editor-pane-change-callback
editor-pane-enabled
editor-pane-fixed-fill
editor-pane-line-wrap-marker
editor-pane-line-wrap-face
editor-pane-wrap-style
editor-pane-composition-face

Description

enabled controls how user input affects the editor-pane. If enabled is nil, all input from the mouse and keyboard is ignored. When enabled is t, all input is processed according to the input-model. When enabled is :read-only, input to the pane by keyboard or mouse gestures cannot change the text. More accurately, input via the default input-model of editorpane cannot change the text. The Cut and Paste menu entries are also disabled. When a user tries to change the text, the operation quietly aborts. Programmatic modifications of the text are still allowed (see Notes below for more detail).

The enabled state can be set by the accessor editor-pane-enabled. capi:simple-pane-enabled has the same effect when applied to an editor-pane.

The editor-pane stores text in buffers which are uniquely named, and so to create an editor-pane using an existing buffer you should pass the *buffer-name*. To create an editor-pane with a new buffer, pass a *buffer-name* that does not match any existing buffer. If *buffer-name* is not passed, then the editor-pane uses some existing buffer.

A non-empty string value of *text* specifies the initial text displayed. Otherwise an existing editor buffer is displayed. The accessor editor-pane-text is provided to read and write the text in the editor buffer.

buffer-modes allows you to specify the initial major mode and minor modes of the editor-pane's buffer. It should be a list of the form (major-mode-name . minor-mode-names). See the LispWorks Editor User Guide for a description of major and minor modes in the LispWorks edtor. buffer-modes is used only when the CAPI creates the buffer, and not when it reuses a buffer.

If *echo-area* is non-nil. then an Echo Area is added. *echo-area* defaults to nil.

If *fixed-fill* is non-nil, the editor pane tries to form lines of length close to, but no more than, *fixed-fill*. It does this by forcing line breaks at spaces between words. *fixed-fill* defaults to nil.

The cursor in an editor-pane blinks on and off by the mechanism described in editor-pane-blink-rate.

change-callback, if non-nil, should be a function which is called whenever the editor buffer under the editor-pane changes. The value change-callback can be set either by:

```
(make-instance 'capi:editor-pane :change-callback ...)
Or
  (setf capi:editor-pane-change-callback)
```

The current value can be queried by the accessor editorpane-change-callback.

The *change-callback* function must have signature:

change-callback pane point old-length new-length pane is the editor-pane itself.

point is an editor:point object where the modification to the underlying buffer starts. point is a temporary point, and is not valid outside the scope of the change callback. For more information about editor:point objects, see "Points" in the LispWorks Editor User Guide.

old-length is the length of the affected text following *point*, prior to the modification.

new-length is the length of the affected text following *point*, after the modification has occurred.

Typical calls to the *change-callback* occur on insertion of text (when *old-length* is 0) and on deletion of text (when *new-length* is 0). There can be other combinations, for example, after executing the Uppercase Region editor command,

change-callback be called with both *old-length* and *new-length* being the length of the region. The same is true for changing editor text properties.

The *change-callback* is always executed in the process of *pane* (as if by apply-in-pane-process).

The *change-callback* is permitted to modify the buffer of *pane*, and other editor buffers. The callback is disabled inside the dynamic scope of the call, so there are no recursive calls to the *change-callback* of *pane*. However, changes done by the callback may trigger *change-callback* calls on other editorpanes, whether in the same process or in another process.

There is an example illustrating the use of *change-callback* in the file examples/capi/editor/change-callback.lisp.

You can use the initargs :before-input-callback and :after-input-callback to add input callbacks which are called when call-editor is called. Note that the default input-model also generates calls to call-editor, so unless you override the default input-model the input callbacks are called for all keyboard and mouse gestures (other than gestures that are processed by a non-focus completer window).

In both cases (before and after) the argument is a function that takes two arguments: the editor pane itself and the input gesture (the second argument to call-editor).

call-editor may redirect gestures to another pane. For example, gestures to an editor-pane are redirected to the echo area while it is used. In this case the *before* callback is called more than once for the same gesture. The *after* callback is called only once for each gesture, on the pane that actually processed the gesture.

line-wrap-marker specifies the marker to display at the end of a line that is wrapped to the next line, or truncated if wrap-style is nil. The value must be a character, or nil

(which is interpreted as #\Space). The default value is the value of *default-editor-pane-line-wrap-marker*. The value can be read by editor-pane-line-wrap-marker.

line-wrap-face specifies a face to use when displaying the line-wrap-marker. The argument can be nil, an editor:face object (the result of a call to editor:make-face), or a symbol naming a face (that is, the first argument to editor:make-face).

The default value of *line-wrap-face* is an internal symbol naming a face. The value can be accessed by editor-pane-line-wrap-face. The default face can be modified in the LispWorks IDE via Tools > Preferences... > Environment > Styles > Colors and Attributes, style name Line Wrap Marker.

wrap-style defines the wrapping of text lines that cannot be displayed in one line of the editor-pane. The argument can be one of:

t Normal wrapping. Display as many characters as possible in the editor-pane line.

Do not wrap. Text lines that are too long are truncated.

:split-on-space

Wrapping, but attempts to split lines on spaces. When the text reaches the end of a line, the code looks backwards for space, and wraps before it.

The default value of *wrap-style* is t and the value can accessed by editor-pane-wrap-style.

The input behaviour of an editor-pane is determined by its input-model (inherited from output-pane). By default, an editor-pane has an input-model that implements the functionality of the Editor tool in the LispWorks IDE, and always does it via call-editor. You can replace this behavior by supplying :input-model when you call make-instance or by (setf capi:output-pane-input-model), though this

has an effect only if called before the pane is displayed. It is possible to achieve a minor modification to the default input behavior by prepending the modification (see the example below). Note that functions performing editor operations must do this via call-editor.

Editor panes support GNU Emacs keys on all platforms. Additionally on Microsoft Windows they support Windows editor keys, on GTK+ and Motif they support KDE/Gnome keys, and on Cocoa they support Mac OS X editor keys. Exactly one style of emulation is active at any one time for each editor pane. By default, editor panes in the LispWorks IDE development environment use Emacs emulation on all platforms. By default, editor panes in delivered applications use Windows emulation on Microsoft Windows, Mac OS X editor emulation on Cocoa, and Emacs emulation on GTK+ and Motif. To alter the choice of emulation, see interface-keys-style or the deliver keyord :editor-style, described in the LispWorks Delivery User Guide.

Notes

- The output-pane initarg : drawing-mode controls antialiasing of the text displayed in an editor-pane on Microsoft Windows and GTK+.
- 2. For an editor-pane with enabled :read-only, Editor commands (predefined, and user-defined by editor:defcommand) may or may not be able to change the text, depending on how they are called. When executed by a key sequence they cannot change the text directly. However Editor commands can also be called via editor:process-character or call-editor, and then are programmatic input and so can change the text.
- 3. The effect of enabled :read-only is on the editor-pane. It does not affect the underlying Editor buffer, which can still be modified from other panes. The buffer that is displayed can be changed, and this does not affect the enabled state of the editor-pane.

- 4. To control whether the native input method is used to interpret keyboard input, you can supply the outputpane initarg :use-native-input-method or call setdefault-use-native-input-method.
- The default value of composition-callback (see outputpane) is editor-pane-default-composition-callback.

Compatibility note

In LispWorks 4.4 and previous versions editor-pane supports only fixed-width fonts.

On Cocoa, editor-pane supports only fixed-width fonts.

In LispWorks 6.1 and later, variable-width fonts can also be used on Microsoft Windows, GTK+ and Motif. Specify the font via the :font initarg (see simple-pane).

The :wrap-style initarg supersedes editor:set-window-split-on-space, which is deprecated.

Example

Note that you cannot type into the editor pane.

```
(capi:apply-in-pane-process
ed #'(setf capi:editor-pane-enabled) t ed)
```

Now you can enter text into the editor pane interactively.

You can also change the text programmatically:

```
(capi:apply-in-pane-process
ed #'(setf capi:editor-pane-text) "New text" ed)
```

In this example the callback modifies the buffer in the correct editor context so you that see the editor update immediately:

```
(capi:define-interface updating-editor ()
  (:panes
   (numbers capi:list-panel
          :items '(1 2 3)
          :selection-callback 'update-editor
          :callback-type :interface
          :visible-min-height '(:character 3))
   (editor capi:editor-pane
                 :text
                 "Select numbers in the list above."
                 :visible-min-width
                 (list :character 35))))
(defun update-editor (interface)
  (with-slots (numbers editor) interface
    (editor:process-character
     (list #'(setf capi:editor-pane-text)
           (format nil "~R"
                   (capi:choice-selected-item numbers))
           editor)
     (capi:editor-window editor))))
(capi:display (make-instance 'updating-editor))
```

This example illustrates the use of *buffer-modes* to specify a major mode:

```
(defclass my-lisp-editor (capi:editor-pane) ()
  (:default-initargs
   :buffer-modes '("Lisp")
   :echo-area t
   ";; Lisp mode functionality such as command bindings
and
;; parenthesis balancing work in this window.
(list 1 2 3)
   :visible-min-width '(:character 60)
   :name "My Lisp Editor Pane"))
(capi:define-interface my-lisp-editor-interface ()
  (:panes
   (ed
    my-lisp-editor
    ))
  (:default-initargs
   :title "My Lisp Editor Interface"))
;; Ensure Emacs-like bindings regardless of platform
(defmethod capi:interface-keys-style
           ((self my-lisp-editor-interface))
  :emacs)
(capi:display
 (make-instance 'my-lisp-editor-interface))
This example makes an editor-pane with no input behav-
ior:
(capi:contain
 (make-instance 'capi:editor-pane :input-model nil))
```

This example makes an editor-pane with the default input behavior, except that pressing the mouse button displays a message rather than setting the point. It then displays the pane:

```
(progn
               (defun foo (self x y)
                 (capi:display-message "Button-1 Press at ~a/~a"
                                      x y))
               (let ((ep (make-instance 'capi:editor-pane)))
                 (setf (capi:output-pane-input-model ep)
                       (list* '((:button-1 :press) foo)
                              (capi:output-pane-input-model ep)))
                 (capi:contain ep)))
             Also see the examples in the directory
             examples/capi/editor/.
See also
             call-editor
             *default-editor-pane-line-wrap-marker*
             editor-pane-blink-rate
             *editor-cursor-active-style*
             *editor-cursor-color*
             *editor-cursor-drag-style*
             *editor-cursor-inactive-style*
             interface-keys-style
             modify-editor-pane-buffer
             output-pane
             set-default-use-native-input-method
```

editor-pane-blink-rate

Generic Function

Summary Returns the cursor blinking rate for an editor pane.

Package capi

Signature editor-pane-blink-rate self => blink-rate

Arguments *self* An editor pane.

Values blink-rate A non-negative real number, or nil.

Description

The system calls the function editor-pane-blink-rate to determine the cursor blinking rate in milliseconds. The pane uses the value *blink-rate* each time it gets the focus.

If *blink-rate* is a positive real number, then it is the blinking rate in milliseconds. If *blink-rate* is 0, then there is no blinking. If *blink-rate* is nil, then the default blinking rate is used.

The default method on editor-pane-blink-rate returns nil, which means use the default blinking rate. set-default-editor-pane-blink-rate.

You can define your own methods on editor-pane-blink-rate for editor-pane and subclasses thereof.

See also

```
*editor-cursor-active-style*
editor-pane
editor-pane-native-blink-rate
set-default-editor-pane-blink-rate
```

editor-pane-buffer

Function

Summary Returns the editor buffer associated with an editor pane.

Package capi

Signature editor-pane-buffer pane

Description The function editor-pane-buffer returns the editor buffer

associated with an editor pane, which can be manipulated in the standard ways with the routines in the editor package.

(capi:editor-pane-buffer editor-pane))

(editor:insert-string (editor:buffers-end buffer)
 (format nil "~%Here's some more text..."))

See also editor-pane

editor-pane-composition-selected-range-face-plist Variable

Summary Can modify the face of the default editor composition string.

Initial Value (:inverse-p t)

Description The variable *editor-pane-composition-selected-

range-face-plist* is a plist that is used to modify the face of the composition string when :selected-range and :selection-needs-face are passed in the plist to editor-pane-default-composition-callback. The plist is merged into the plist that is passed into editor-pane-default-composition-callback, so keywords in it override the key-

words in the face.

See also editor-pane-default-composition-callback

editor-pane-default-composition-callback

Function

Summary The default composition callback of the editor. Composition

here means composing input characters into other characters

by an input method.

Signature editor-pane-default-composition-callback editor-pane what

Description The function editor-pane-default-composition-call-

back is the default composition-callback of editor-pane. It

may also be called by your program.

When called with what = :start, editor-pane-default-composition-callback sets the composition placement in the editor by calling set-composition-placement, and also makes it move the composition window following the user's mouse cursor movement

When called with what = :end, it stops the following of the mouse cursor.

When called with a list (which needs to be a plist), editorpane-default-composition-callback checks if it contains a keyword/value pair for :string-face-lists, and if it does displays it in the editor temporarily (until the next call to it). See the entry for output-pane for the description of the value string-face-lists.

By default, editor-pane-default-composition-call-back uses the faces that are supplied in *string-face-lists*, but if the plist contains :selection-needs-face and :selected-range, it displays the selected range with a different face, by merging *editor-pane-composition-selected-range-face-plist* into the given face of the selected range.

This can be overriden by setting the *composition-face* in the editor-pane, or the global *editor-pane-default-composition-face* if the *composition-face* of the pane is :default. If *composition-face* is a true value then the exact behavior depends on its type:

A plist

This is appended to each face plist in the the *string-face-lists*. In other words, it provides default values for the attributes of the face.

An editor: face

Overrides the supplied face completely.

A function or a symbol

For string-face-list, funcalls it with two arguments, the pane and the supplied face plist, and uses the result (which may be an editor:face or a face plist).

editor-pane-default-composition-callback is the default value of *composition-callback* for editor-pane. This can be overridden by passing :composition-callback or using output-pane-composition-callback (see entry for output-pane).

The user-supplied callback may call editor-pane-default-composition-callback to do the actual display, potentially after modifying the argument when it is a plist.

See also set-composition-placement

editor-pane-default-composition-face

Variable

Summary The default composition face for editor-pane.

Initial Value nil

Description The variable *editor-pane-default-composition-face*

gives the default composition face for all editor-panes

where the *composition-face* is set to :default.

:default is the default value for composition-face, so

normally setting this variable affects the *composition-face* of all

editor-panes.

See editor-pane-default-composition-callback for a

description of how it is used.

See also editor-pane-default-composition-callback

editor-pane-native-blink-rate

Function

Summary Returns the native cursor blinking rate for an editor-pane.

Package capi

Signature editor-pane-native-blink-rate pane => blink-rate

Arguments pane An editor-pane.

Values blink-rate A non-negative real number, or nil.

Description The function editor-pane-native-blink-rate returns the

native cursor blinking rate for the editor-pane pane, that is the rate that the GUI library (Motif, Microsoft Windows,

Cocoa) uses.

The value blink-rate is interpreted as a blinking rate as

described in editor-pane-blink-rate.

See also editor-pane-blink-rate

set-default-editor-pane-blink-rate

editor-pane-selected-text

Generic Function

Summary Returns the selected text in an editor-pane.

Package capi

Signature editor-pane-selected-text editor-pane => result

Arguments editor-pane An editor-pane.

Values result A string or nil.

1 CAPI Reference Entries

Description The function editor-pane-selected-text takes an

instance of editor-pane as its argument and returns the selected text in *editor-pane*, or nil if there is no selection.

See also editor-pane

editor-pane-selected-text-p

editor-pane-selected-text-p

Generic Function

Summary The predicate for a current selection in an editor-pane.

Package capi

Signature editor-pane-selected-text-p editor-pane => result

Arguments *editor-pane* An editor-pane.

Values result A boolean.

Description The generic function editor-pane-selected-text-p takes

an instance of editor-pane as its argument and returns t if there is text currently selected in *editor-pane*, or nil if there is

no selection.

See also editor-pane

editor-pane-selected-text

editor-pane-stream

Function

Summary Returns the output stream associated with an editor pane.

Package capi

Signature editor-pane-stream editor-pane => stream

Arguments editor-pane An editor-pane.

Values stream An output stream.

Description The function editor-pane-stream returns the stream where

the results of evaluation in the editor buffer currently

associated with *pane* are printed to.

See also editor-pane

editor-window Generic Function

Summary Returns the editor window object.

Package capi

Signature editor-window editor => editor-window

Arguments editor An editor-pane or an Editor interface in

the LispWorks IDE.

Values *editor-window* An editor window object.

Description The generic function editor-window returns the editor

window object associated with *editor*.

The functionality of editor windows is documented in the

LispWorks Editor User Guide.

See also editor-pane

element Class

Summary The class element is the superclass of all CAPI objects that

appear in a window.

1 CAPI Reference Entries

Package capi

Superclasses capi-object

Subclasses simple-pane

menu

Initargs :parent The element containing this element.

:interface The interface containing this element.

:accepts-focus-p

Specifies that the element should accept

input.

:help-key An object used for lookup of help. Default

value t.

:widget-name A string designator.

:initial-constraints

Specifies constraints (geometry hints) that apply to the element during the creation of the element's interface, but not after the

interface is displayed.

The following initargs are geometry hints, influencing the initial size and position of an element and constraining its size:

The x position of the element in a pinboard.

The y position of the element in a pinboard.

:external-min-width

The minimum width of the element in its parent.

:external-min-height

The minimum height of the element in its parent.

:external-max-width

The maximum width of the element in its parent.

:external-max-height

The maximum height of the element in its parent.

:visible-min-width

The minimum visible width of the element.

:visible-min-height

The minimum visible height of the element.

:visible-max-width

The maximum visible width of the element.

:visible-max-height

The maximum height of the element.

:internal-min-width

The minimum width of the display region.

:internal-min-height

The minimum height of the display region.

:internal-max-width

The maximum width of the display region.

:internal-max-height

The maximum height of the display region.

ACCESSORS element-parent

element-widget-name

Readers element-interface

help-key

Description The class element contains the slots parent and interface

which contain the element and the interface that the element

is contained in respectively. The writer method

element-parent can be used to re-parent an element into

another parent (or to remove it from a container entirely by setting its parent to nil). Note that an element should not be used in more than one place at a time.

The initarg accepts-focus-p specifies that the element can accept input. The default value is t. In some subclasses including display-pane and title-pane the default value of accepts-focus-p is nil. A pane accepts the input focus if and only if the function accepts-focus-p returns true.

accepts-focus-p also influences whether a pane is a tabstop on Microsoft Windows, where a pane acts as a tabstop if and only if the function accepts-focus-p returns true and the :accepts-focus-p initarg value is :force. On Motif and Cocoa, a pane acts as a tabstop if and only if the function accepts-focus-p returns true.

help-key is used to determine how help is displayed for the pane. The value nil means that no help is displayed. Otherwise, help-key is passed to the help-callback, except when help-key is t, when the name of the pane is passed to the help-callback. For details of help-callback, see interface.

widget-name specifies the widget name of the element. This is used to match resources on GTK+ and Motif. Note that this name will be in the path only if the element has a representation. tab-layout and pinboard-layout always have a representation, as do all elements that show anything on the screen. Other layouts may or may not have a representation and so you should not supply widget-name for these.

The actual widget name is the result of a call to cl:string, except when *widget-name* is a symbol, in which case the symbol name is downcased to derive the widget name.

If *widget-name* is not supplied, the system constructs a default widget name which is the name of the class of the widget (downcased), except for top level interfaces on GTK+ where the *application-class* is prepended followed by a dot.

Example GTK+ resource files are in lib/6-1-0-0/examples/gtk/

Note: When *widget-name* is supplied, the GTK+ library does not prepend the *application-class*.

The accessor element-widget-name gets and (with setf) sets the widget-name. widget-name is used when the widget is created, that is when display is called on the top level interface of the element. Setting widget-name afterwards has no effect.

All elements accept initargs (listed above) representing hints as to the initial size and position of the element. By default elements have a minimum pixel size of one by one, and a maximum size of nil (meaning no maximum), but the hints can be specified to change these values. The possible values for these hints are as follows:

integer The size in pixels.

t For :visible-max-width, t means use the

value of : visible-min-width.

For :visible-max-height, t means use the

value of :visible-min-height.

:text-width The width of any text in the element.

:text-height

The height of any text in the element.

:screen-width The width of the screen.

:screen-height The height of the screen.

Also, hints can be a list starting with any of the following operators, followed by one or more hints.

max The maximum size of the hints.

min The minimum size of the hints.

+ The sum of the hints.

- The subtraction of hints from the first.

The multiplication of the hints.

/ The division of hints from the first.

Also, a hint can be a two element list specifying the size of a certain amount of text when drawn in the element:

```
(:character integer)
(character integer)
```

The size of *integer* characters.

```
(:string string)
(string string)
```

The size of *string*.

A hint can be a two-element list interpreted as the value of a symbol:

```
(symbol-value foo)
```

The size of the symbol-value of foo.

Finally, you can choose to apply or funcall an arbitrary function, by passing a list starting with funcall or apply, followed by the function and then the arguments.

The hints of an element can be changed dynamically using set-hint-table: such a call might change the geometry.

initial-constraints must be a plist of constraints, where the keywords are geometry hints as described above.

Notes

- 1. If the *visible-max-width* is the same as the *visible-min-width*, then the element is not horizontally resizable. If the *visible-max-height* is the same as the *visible-min-height*, then the element is not vertically resizable.
- Some classes have default initargs providing useful hints.
 For example, display-pane has :text-height as the
 default value of :visible-min-height, ensuring that
 the text is visible.

3. The ratios, x-ratios and y-ratios settings in some layouts (for example grid-layout) also control the actual size of the pane when the constraints are not specified. In particular, if nil is used in the ratios then the associated pane(s) will be fixed at their minimum size.

Compatibility note

The initargs:min-width,:max-width,:min-height, and:max-height are still accepted for compatibility with Lisp-Works 3.2, but their use is discouraged.

In LispWorks 4, :visible-min-width means the same as :min-width, but takes precedence if both are specified. The use of :min-width can lead to confusion because some CAPI classes have default values for :visible-min-width which will override :min-width. Similarly for :min-height, :max-width, and :max-height. Therefore, your code should use :visible-min-width and friends.

Example

Here is a simple example that demonstrates the use of the element-parent accessor to place elements.

```
(setq pinboard (capi:contain
                 (make-instance
                  'capi:pinboard-layout)
                 :visible-min-width 520
                 :visible-min-height 395))
(setq object
      (make-instance
       'capi:image-pinboard-object
       :x 10 :y 10
       :image
       (sys:lispworks-file
        "examples/capi/graphics/Setup.bmp")
       :parent pinboard))
(capi:apply-in-pane-process
 pinboard #'(setf capi:element-parent) nil object)
(capi:apply-in-pane-process
 pinboard #'(setf capi:element-parent) pinboard object)
These final two examples illustrate the effect of initial-con-
straints.
Create a pane that starts at least 600 pixel high, but can be
made shorter by the user:
(capi:contain
 (make-instance 'capi:output-pane
                 :initial-constraints '(:visible-min-
height 600)))
Compare with this, which creates a pane at least 600 pixels
high but which cannot be made shorter.
(capi:contain
 (make-instance 'capi:output-pane
                 :visible-min-height 600))
```

element-container

See also

Function

Summary Returns the container of an element.

set-hint-table

Package capi

Signature element => container element => container

Arguments *element* An element.

Values container A screen or a document-frame.

Description The function element-container returns the container of

the element element.

If element is inside a standalone interface, then container is the

screen object.

If *element* is inside an interface that is inside a MDI interface, then *container* is the capi:container object of that MDI

interface. See document-frame for details.

See also document-frame

element

element-interface-for-callback

Generic Function

Summary Returns the interface that is used in an element's callbacks.

Package capi

Signature element-interface-for-callback element => interface

Description The function element-interface-for-callback returns

the interface that is passed to callbacks in *element*. Normally this is the interface that *element* is in, but that can be changed

by attach-interface-for-callback.

See also attach-interface-for-callback

element

element-screen Function

Summary Returns the screen that an element is associated with.

Package capi

Signature element-screen element => screen

Description The function element-screen returns the screen that the

element element is associated with.

See also element

ellipse Class

Summary A pinboard object that draws itself as an ellipse.

Package capi

Superclasses pinboard-object

Accessors filled

Initargs :filled A boolean.

Description The class ellipse is a pinboard-object that draws itself as

an ellipse.

If filled is true, then the ellipse is filled with the foreground

color. filled defaults to mil.

ensure-area-visible

Generic Function

Summary Ensures an area is visible in a scrollable pane.

Package capi

Signature ensure-area-visible self x y width height

Arguments self A simple-pane with internal scrolling.

x, *y* The coordinates of the origin of the area to

make visible.

width, height The dimensions of the area to make visible

Description The generic function ensure-area-visible ensures that the

area specified by x, y, width and height, or at least part of it, is

visible.

This function works only for subclasses of simple-pane that do internal scrolling (such as editor-pane). An error is sig-

nalled if it is called with other classes.

ensure-interface-screen

Function

Summary Ensures that a top level interface is displayed on a given

screen.

Package capi

Signature ensure-interface-screen self &key screen

Description The function ensure-interface-screen ensures that the

top level interface is displayed on the given *screen* (or the default) if display is called later without a *screen* argument. This allows the querying of font and color information associated with a particular screen. It returns the screen that is

used.

See also screen

display interface

execute-with-interface

Function

Summary Allows functions to be executed in the event process of a

given interface.

Package capi

Signature execute-with-interface interface function &rest args

Arguments interface An interface

function A function designator

args Arguments passed to function

Description The function execute-with-interface is a useful way of

operating on an interface owned by another process. It takes a top-level interface, a function and some arguments and queues the function to be run by that process when it next enters its event loop (for an interface owned by the cur-

rent process, it calls the function immediately).

Notes

- execute-with-interface applies function even if interface does not have a screen representation, for example when it is destroyed. To call function only if interface has a representation, use execute-with-interface-if-alive.
- 2. All accesses (reads as well as writes) on a CAPI interface and its sub-elements should be performed in the interface process. Within a callback on the interface this happens automatically, but execute-with-interface is a useful utility in other circumstances.
- **3.** execute-with-interface calls *function* on the current process if *interface* does not have a process.

4. apply-in-pane-process and apply-in-pane-process-if-alive are other ways to call a function in the appropriate CAPI process. They takes panes of all classes, not merely interface.

Example (setq a (capi:display (make-instance 'capi:interface)))

(capi:execute-with-interface

a 'break

"Break inside the interface process")

See also apply-in-pane-process

apply-in-pane-process-if-alive
execute-with-interface-if-alive

execute-with-interface-if-alive

Function

Summary Executes a function in the event process of a given interface if

it is alive.

Package capi

Signature execute-with-interface-if-alive interface function &rest

args => nil

Description The function execute-with-interface-if-alive applies

the function *function* to the arguments *args* in the process of the interface *interface*, if the interface is "alive". An interface is

alive if it has a representation on the screen.

If *interface* is not alive, *function* is not applied. This is in contrast to execute-with-interface, which in this case applies

the function in the current process.

execute-with-interface-if-alive is useful for automatic updating of interfaces that may be destroyed by the user, where the update is redundant if the interface is not alive.

1 CAPI Reference Entries

Notes All accesses (reads as well as writes) on a CAPI interface and

its sub-elements should be performed in the interface process. Using execute-with-interface-if-alive is one

way of ensuring this.

See also apply-in-pane-process-if-alive

execute-with-interface

exit-confirmer Function

Summary Called by the **OK** button on a dialog created with popup-con-

firmer.

Package capi

Signature exit-confirmer &rest dummy-args

Description The function exit-confirmer is called by the OK button on a

dialog created using popup-confirmer, and it is provided as an entry point so that other callbacks can behave in the same way. There is a full description of the **OK** button in popup-

confirmer.

Example This example demonstrates the use of exit-confirmer to

make the dialog exit when pressing Return in the text input pane. It also demonstrates the use of *value-function* as a means

of deciding the return value from popup-confirmer.

(capi:popup-confirmer (make-instance

'capi:text-input-pane

:callback 'capi:exit-confirmer)

"Enter some text:"
:value-function

'capi:text-input-pane-text)

See also popup-confirmer

display-dialog

interface

exit-dialog Function

Summary Exits the current dialog.

Package capi

Signature exit-dialog value

Description The function exit-dialog is the means to successfully

return a value from the current dialog. Hence, it might be called from an **OK** button so that pressing the button would cause the dialog to return successfully, whilst the **Cancel** button would call the counterpart function abort-dialog.

If there is no current dialog then exit-dialog does nothing

and returns mil. If there is a current dialog then

exit-dialog either returns non-nil or does a non-local exit. Therefore code that depends on exit-dialog returning must be written carefully - see the discussion under abort-dialog

for details.

Example (capi:display-dialog

(capi:make-container

:title "Test Dialog"))

There is another example in the file

 ${\tt examples/capi/dialogs/simple-dialog.lisp}.$

See also abort-dialog

display-dialog popup-confirmer

interface

expandable-item-pinboard-object

Class

Summary A class used to implement nodes in graph-pane.

Package capi

Superclasses item-pinboard-object

Description The class expandable-item-pinboard-object is a pin-

board-object that graph-pane uses by default to imple-

ment nodes in a graph.

expandable-item-pinboard-object draws itself with a

small circle to indicate that the node has children.

See also graph-pane

extended-selection-tree-view

Class

Summary A pane that displays a hierarchical list of items which (unlike

tree-view) allows extended selection.

Package capi

Superclasses tree-view

Description The class extended-selection-tree-view is like tree-

view but allows more than one item to be selected at once.

Notes

1. Although extended-selection-tree-view is a subclass of collection, it does its own items handling and you must not access its items and related slots directly. In particular for extended-selection-tree-view do not pass: items,:items-count-function,:items-get-function or:items-map-function, and do not use the corre-

sponding accessors.

2. The delete item callback (see *delete-item-callback* in tree-view) is called in extended-selection-tree-view with the second argument being a list of the selected items, unless *interaction* is :single-selection, in which case it behaves the same as in tree-view.

See also tree-view

filtering-layout Class

Summary A layout that can be used for filtering.

Package capi

Superclasses row-layout

Initargs :callback-object

The argument for the callbacks. If it is nil the top-level-interface of the layout is used.

:change-callback

A function of one argument (the *callback-object*). It is called whenever the text in the filter changes. Also if *callback* is not supplied, *change-callback* is called instead.

:callback

A function of one argument (the *callback-object*). It is called when the user presses Return, makes a selection from the menu, or clicks the **Confirm** button. If *callback* is not supplied, *change-callback* is called instead.

:text A string specifying the initial text of the fil-

ter, or nil.

:matches-title

A string, t or mil.

:help-string

A string, t or nil.

:label-style

:short, :medium or :long.

Accessors

filtering-layout-state
filtering-layout-matches-text

Description

The main part of a filtering layout is a text-input-pane which allows the user to enter a string. The string is used for filtering. The user can control how it is used by a menu that allows her to specify whether:

- the string is used as a regular expression or plain string
- the filter excludes matches or includes matches
- filtering is case-sensitive or case-insensitive

The filtering layout defines the parameters to use, and calls the callbacks to perform the filtering. It does not do any filtering itself.

To actually do the filtering, the using code needs to call filtering-layout-match-object-and-exclude-p, which returns as multiple values a precompiled regexp and a flag specifying whether to exclude matches. The regexp should be used to perform the filtering, typically by using lisp-works:find-regexp-in-string. Note that filtering-layout-match-object-and-exclude-p returns nil when there is no string in the text-input-pane, and that even when the filter is set to plain match it returns a regexp (which matches a plain string).

You supply a filtering-layout amongst the panes of your interface definition (not its *layouts*). The description of a filtering-layout is set by the initialize-instance method of the class, and therefore the description cannot be passed as an initarg and should not be manipulated.

filtering-layout-state returns a "state" object which can be used later to set the state of any filtering-layout by (setf capi:filtering-layout-state). When setting the state, the value can also be a string or nil. A string means setting the filter string to it and making the filtering state be plain string, includes matches, and case-insensitive. nil means the same as the empty string.

matches-title controls whether the filtering-layout contains a display-pane (the "matches pane") showing the number of matches. If matches-title is a string, it provides the title of the matches pane. If matches-title is the title is Matches:. Note that the actual text in the matches pane must be set by the caller by (setf capi:filtering-layout-matches-text).

If *help-string* is non-nil then the filter has a Help button which raises a default help text if *help-string* is t, or the text of *help-string* if it is a string.

If label-style is :short the filter menu has a short title. For example if the filter is set for case-sensitive plain inclusive matching the short label is PMC. If label-style is :medium then this label would be Filter:C. Any other value of label-style would make a long label Plain Match Cased.

```
Example
              (defvar *things* (list "Foo" "Bar" "Baz" 'car 'cdr))
              (capi:define-interface my-interface ()
                ((things :reader my-things
                         :initform *things*))
                (:panes
                 (my-things-list-panel
                  capi:list-panel
                  :reader my-interface-list-panel
                  :items things
                  :visible-min-height `(:character ,(length
              *things*)))
                 (my-filtering
                  capi:filtering-layout
                  :change-callback 'update-my-interface
                  :reader my-interface-filtering))
                (:lavouts
                 (a-layout
                 capi:column-layout
                  '(my-filtering my-things-list-panel)))
                (:default-initargs :title "Filtering example")
               )
              (defun update-my-interface (my-interface)
                (let* ((things (my-things my-interface))
                       (filtered-things
                        (multiple-value-bind (regexp excludep)
                            (capi:filtering-layout-match-object-and-
             exclude-p
                             (my-interface-filtering my-interface)
                             nil)
                          (if regexp
                              (loop for thing in things
                                    when (if (find-regexp-in-string
                                               regexp
                                               (string thing))
                                              (not excludep)
                                            excludep)
                                    collect thing)
                            things))))
                  (setf (capi:collection-items
                         (my-interface-list-panel my-interface))
                        filtered-things)))
See also
             filtering-layout-match-object-and-exclude-p
```

filtering-layout-match-object-and-exclude-p

Function

Summary Returns filtering parameters for a filtering-layout.

Package capi

Signature filtering-layout-match-object-and-exclude-p filtering-

layout display-message => regexp, excludep

Arguments filtering-layout A filtering-layout

display-message A generalized boolean

Values regexp A precompiled regular expression

excludep A boolean

Description The function filtering-layout-match-object-and-

exclude-p returns a regexp to use for filtering in the *filtering-layout*. The second returned value *excludep* specifies whether the filter should be used to exclude or include matches.

display-message is a generalised boolean controlling whether a message is displayed to the user if there is an error when

compiling the regexp.

See filtering-layout for details.

See also filtering-layout

find-graph-edge

Generic Function

Summary Finds and returns an edge in a graph given two items.

Package capi

Signature find-graph-edge graph from to => edge

Arguments graph A graph-pane.

1 CAPI Reference Entries

from An item in graph.

to An item in graph.

Values edge A graph edge, or nil.

Description The generic function find-graph-edge finds the edge that

goes from the node corresponding to from to the node corre-

sponding to to.

If there is no such edge, find-graph-edge returns nil.

See also find-graph-node

graph-pane

find-graph-node

Generic Function

Summary Finds and returns a node in a graph corresponding to an

item.

Package capi

Signature find-graph-node graph object => node

Arguments graph A graph-pane.

object An item in graph.

Values node A node of graph, or nil.

Description The generic function find-graph-node finds the node that

corresponds to the item object.

If there is no such node, find-graph-node returns nil.

See also find-graph-edge

graph-pane

find-interface Generic Function

Summary Displays an interface of a given class, making it if necessary.

Package capi

Signature find-interface class-name &rest initargs &key screen &allow-

other-keys => interface

Arguments class-name A specifier for a subclass of interface.

initargs Initialization arguments for class-name.

screen A screen or nil.

Values interface An interface of class class-name.

Description The generic function find-interface finds and displays an interface of the given class *class-name* that matches *initargs*

and screen.

class-name can be the name of a suitable class, the class itself, or an instance of the class.

screen can be a CAPI object as accepted by convert-to-

find-interface calls locate-interface to locate an existing interface:

- If an interface of the class specified by class-name matching initargs exists already on screen, then this interface is activated and returned.
- Otherwise, if an interface of the class specified by classname exists already on screen, then reinitializeinterface is applied to this interface which is then activated and returned.

If no instance of class *class-name* exists on *screen*, then find-interface creates one by passing *class-name* and *initargs* to make-instance, and displays the result on *screen*.

1 CAPI Reference Entries

Notes There are many uses of find-interface in the LispWorks

IDE development environment.

See also locate-interface

reinitialize-interface

find-string-in-collection

Generic Function

Summary The find-string-in-collection generic function returns

the next item whose printed representation matches a given

string.

Package capi

Signature find-string-in-collection self string &optional set

Description The find-string-in-collection generic function returns

the next item whose printed representation matches *string*. If *set* is non-nil, the choice selection is set to this item. The search is started from the previous search point. If the choice

selection is set, the next search will start from the first

selected item.

See also collection-search

collection

force-screen-update

Function

Summary Ensures a screen is up to date.

Package capi

Signature force-screen-update &key screen

Description The function force-screen-update makes sure that the

screen specified by screen is up to date.

screen can be a CAPI object as accepted by convert-to-

screen. The default for screen is nil.

See also force-update-all-screens

force-update-all-screens

Function

Summary Ensures a screen is up to date.

Package capi

Signature force-update-all-screens

Description The function force-update-all-screens makes sure that

all screens are up to date.

See also force-screen-update

foreign-owned-interface

Class

Package capi

Superclasses interface

Description The class foreign-owned-interface allows another appli-

cation's window to be the owner of a CAPI dialog. Instances should be created by calling make-foreign-owned-inter-

face.

foreign-owned-interface is implemented only on

Microsoft Windows.

See also make-foreign-owned-interface

form-layout Class **Summary** The class form-layout lays its children out in a form. Package capi **Superclasses** layout Initargs :vertical-gap The gap between rows in the form. :vertical-adjust The adjustment made to the rows. The gap between the two columns. :title-gap :title-adjust The adjustment made to the left column. Accessors form-vertical-gap form-vertical-adjust form-title-gap form-title-adjust Description The form layout lays its children out in two columns, where the children in the left column (which are usually titles) are right adjusted whilst the children in the right column are left adjusted. Compatibility This class has been superseded by grid-layout, and will probably be removed at some point in the future. The examnote ples below demonstrate the use of grid layouts as an alternative to forms. Example (setq children (list "Button:" (make-instance 'capi:push-button :text "Press Me") "Enter Text:" (make-instance 'capi:text-input-pane)

"List:"

(make-instance 'capi:list-panel

:items '(1 2 3))))

(capi:contain (make-instance

'capi:grid-layout
:description children
:x-adjust '(:right :left)

:y-adjust :center))

See also grid-layout

layout

free-metafile Function

Summary Frees a metafile.

Package capi

Signature free-metafile metafile

Arguments *metafile* A metafile.

 $\hbox{\it Description} \qquad \hbox{\it The function free-metafile releases the window system}$

storage used by the metafile.

free-metafile must be called when the metafile is no

longer needed, to avoid memory leaks.

 ${\tt free-metafile} \ \ is \ supported \ on \ GTK+\ only \ where \ Cairo \ is$

supported (GTK+ 2.8 and later).

Notes free-metafile is not implemented on X11/Motif.

Examples There is an example in examples/capi/graphics/meta-

file.lisp.

See also clipboard

draw-metafile

draw-metafile-to-image

1 CAPI Reference Entries

free-sound Function

Summary Frees a loaded sound object on Microsoft Windows and

Cocoa.

Package capi

Signature free-sound sound

Arguments sound An array returned by load-sound.

Description The function free-sound unloads (frees) the loaded sound

object sound.

Notes free-sound is not implemented on GTK+ and Motif.

See also load-sound

read-sound-file

get-collection-item

Generic Function

Summary Returns the item at a specified position in a collection.

Package capi

Signature get-collection-item self index

Description The generic function get-collection-item returns the item

at position *index* from the collection *self*. It achieves this by calling the *items-get-function* of the collection. There is also a complementary function, search-for-item which finds the

index for a given item in a collection.

See also collection

search-for-item

get-constraints Function

Summary Returns a list of the constraints for an element.

Package capi

Signature get-constraints element

Description The function get-constraints returns the constraints for

element as multiple values (the values are the minimum width, the minimum height, the maximum width and the

maximum height).

This function calls the generic function calculate-constraints to calculate these sizes initially, but then just uses the values in the geometry cache for the element. To force an element to take account of its new constraints, call the func-

tion invalidate-pane-constraints.

See also calculate-constraints

define-layout

element

invalidate-pane-constraints

get-horizontal-scroll-parameters

Generic Function

Summary Queries the scroll parameters of a horizontal scroll bar.

Package capi

Signature get-horizontal-scroll-parameters self &rest keys =>

parameter, parameter,...

Arguments self A displayed simple-pane.

keys Keywords as below.

Values parameter The parameters are returned as multiple val-

ues, one for each key passed in keys and in

the same order as the arguments.

Description Retrieves the specified parameters of the horizontal scroll bar

of *self*, which should be a displayed instance of a subclass of simple-pane which does internal scrolling (such as editor-

pane).

The valid keys are:

:min-range The minimum data coordinate.

:max-range The maximum data coordinate.

:slug-position

The current scroll position.

:slug-size The length of the scroll bar slug.

:page-size The scroll page size.

:step-size The scroll step size.

Note: For the other pane classes, such as list-panel, the underlying widget decides what the scroll range and units

are.

Example See the following CAPI example files:

output-panes/scroll-test.lisp

output-panes/scrolling-without-bar.lisp

See also get-scroll-position

scroll

set-horizontal-scroll-parameters

simple-pane

get-page-area Function

Summary Calculates the dimensions of suitable rectangles for use with

with-page-transform.

Package capi

Signature get-page-area printer &key scale dpi screen

Description The get-page-area function is provided to simplify the cal-

culation of suitable rectangles for use with with-pagetransform. It calculates and returns the width and height of the rectangle in the user's coordinate space that corresponds to one printable page, based on the logical resolution of the

user's coordinate space in dpi.

For example, if a logical resolution of 72 dpi was specified, this means that each unit in user space would map onto 1/72 of an inch on the printed page, assuming that no *scale* is specified.

If *dpi* is nil or unspecified, the logical resolution of the specified screen is used, or the logical resolution of the default screen if no screen is specified. The *dpi* argument can be a number, or a list of two elements representing the logical resolution of the coordinate spaces in the x and y directions respectively.

If *scale* is specified the rectangle is calculated so that the image is scaled by this factor when printed. It defaults to 1.0.

See also printer-metrics

with-page-transform

get-printer-metrics

Function

Summary Returns the metrics for a printer.

Package capi

Signature get-printer-metrics printer

1 CAPI Reference Entries

Description The get-printer-metrics functions takes a printer as its

argument and returns a printer-metrics object.

The metrics values in this object should be accessed by the

printer-metrics readers.

See also set-printer-metrics

printer-metrics
with-page-transform

get-scroll-position

Function

Summary Returns the current scroll position of a pane such as list-

panel, display-pane Or tree-view.

Package capi

Signature get-scroll-position pane dimension => position

Arguments pane A pane with built-in scrolling.

dimension A keyword, either:horizontal or

:vertical.

Values position An integer or nil.

Description The function get-scroll-position returns the scroll posi-

tion of the pane pane in the given dimension.

pane should be an instance of a pane class that has built-in scrolling. That is, the scrolling is implemented by the underlying widget. Examples include list-panel, display-pane

and tree-view.

In general, the units in the returned value *position* are unspecified, but they can be passed to the generic function scroll with *operation*:move to restore the position.

For a list-panel, the vertical units are items.

position is nil if pane is not displayed on the screen, for example if get-scroll-position is called after pane is destroyed.

See also

get-horizontal-scroll-parameters
get-vertical-scroll-parameters

scroll

get-vertical-scroll-parameters

Generic Function

Summary Queries the scroll parameters of a vertical scroll bar.

Package capi

Signature get-vertical-scroll-parameters self &rest keys =>

parameter, parameter,...

Arguments self A displayed output-pane or layout.

keys Keywords as below.

Values parameter The parameters are returned as multiple val-

ues, one for each key passed in keys and in

the same order as the arguments.

Description The function get-vertical-scroll-parameters retrieves

the specified parameters of the vertical scroll bar of *self*, which should be a displayed instance of a subclass of output-pane (such as editor-pane) or layout.

The valid *keys* are:

:min-range The minimum data coordinate.

:max-range The maximum data coordinate.

:slug-position

The current scroll position.

:slug-size The length of the scroll bar slug.

:page-size The scroll page size.

:step-size The scroll step size.

Note: For the other pane classes, such as list-panel, the underlying widget decides what the scroll range and units

are.

Example See the following CAPI example files:

output-panes/scroll-test.lisp

output-panes/scrolling-without-bar.lisp

See also get-scroll-position

scroll

get-horizontal-scroll-parameters

simple-pane

graph-edge Class

Summary The class of objects that represent edges in a graph.

Package capi

Superclasses graph-object

Initargs : from The node where the edge starts.

:to The node where the edge ends.

ACCESSORS graph-edge-from

graph-edge-to

Description The class of objects that represent edges in a graph-pane.

from and to are the nodes that the edge connects.

See also graph-pane

graph-node Class

Summary The class of objects that represent nodes in a graph.

Package capi

Superclasses graph-object

Readers graph-node-x

graph-node-y graph-node-width graph-node-height graph-node-in-edges graph-node-out-edges

Description The default class of nodes in a graph-pane.

The graph-pane generates a graph of graph-node and

graph-edge objects.

See also graph-edge

graph-pane

graph-node-children

Generic Function

Summary Returns the children of a graph node.

Package capi

Signature graph-node-children node => result

Arguments *node* A graph-node.

Values result A list.

1 CAPI Reference Entries

Description The generic function graph-node-children returns a list of

all the 'children' of the node *node*. These children are the nodes which are at the other end of some edge in the graph-

node-out-edges of the graph-node node.

See also graph-node

graph-object Class

Summary The superclass of node and edge objects.

Package capi

Subclasses graph-edge

graph-node

Readers graph-object-element

graph-object-object

Description The class graph-object is the superclass of graph-edge and

graph-node.

The reader graph-object-element returns the CAPI object

that is displayed.

The reader graph-object-object returns the user object

associated with the graph object.

graph-pane Class

Summary A graph pane is a pane that displays a hierarchy of items in a

graph.

Package capi

Superclasses simple-pinboard-layout

choice

Subclasses simple-network-pane

Initargs :roots The roots of the graph.

:children-function

Returns the children of a node.

:layout-function

A keyword denoting how to layout the nodes.

:layout-x-adjust

The adjust value for the *x* direction.

:layout-y-adjust

The adjust value for the *y* direction.

:node-pinboard-class

The class of pane to represent nodes.

:edge-pinboard-class

The class of pane to represent edges.

:node-pane-function

A function to return a pane for each node.

ACCESSORS graph-pane-layout-function

graph-pane-roots

Description A graph pane calculates the items of the graph by calling the

children-function on each of its roots, and then calling it again on each of the children recursively until no more children are found. The children-function gets called with an item of the graph and should return a list of the children of that item.

Each item is represented by a node in the graph.

The *layout-function* tells the graph pane how to lay out its nodes. It can be one these values:

:left-right Lay the graph out from the left to the right.

:top-down Lay the graph out from the top down.

:right-left Lay the graph out from the right to the left.

:bottom-up Lay the graph out from the bottom up.

layout-x-adjust and layout-y-adjust act on the underlying layout to decide where to place the nodes. The values should be a keyword or a list of the form (keyword n) where n is an integer. These values of adjust are interpreted as by pane-adjusted-position. :top is the default for layout-y-adjust and :left is the default for layout-x-adjust.

When a graph pane wants to display nodes and edges, it creates instances of node-pinboard-class and edge-pinboard-class which default to item-pinboard-object and line-pinboard-object respectively. These classes must be subclasses of simple-pane or pinboard-object, and there are some examples of the use of these keywords below.

The node-pane-function is called to create a pane for each node, and by default it creates an instance of node-pinboard-class. It gets passed the graph pane and the item corresponding to the node, and should return an instance of a subclass of simple-pane or pinboard-object.

To expand or contract a node, the user clicks on the circle next to the node. An expandable node has a unfilled circle and a collapsable node has a filled circle.

graph-pane is a subclass of choice, so for details of its selection handling, see choice.

The highlighting of the children is controlled as described for pinboard-layout, but for graph-pane the default value of highlight-style is:standard.

Notes

The output-pane initarg : drawing-mode controls quality of drawing in a graph-pane, including anti-aliasing of any text displayed on Microsoft Windows and GTK+.

Compatibility note

In LispWorks 4.3 the double click gesture on a graph-pane node always calls the *action-callback*, and the user gesture to expand or collapse a node is to click on the circle drawn alongside the node.

In LispWorks 4.2 and previous versions, the double click gesture was used for expansion and contraction of nodes and the *action-callback* was not always called.

Example

```
(defun node-children (node)
  (when (< node 16)
    (list (* node 2)
          (1+ (* node 2)))))
(setq graph
      (capi:contain
       (make-instance 'capi:graph-pane
                      :roots '(1)
                      :children-function
                      'node-children)
       :best-width 300 :best-height 400))
(capi:apply-in-pane-process
graph #'(setf capi:graph-pane-roots) '(2 6) graph)
(capi:contain
 (make-instance 'capi:graph-pane
                :roots '(1)
                :children-function
                'node-children
                :layout-function :top-down)
:best-width 300 :best-height 400)
(capi:contain
 (make-instance 'capi:graph-pane
                :roots '(1)
                :children-function
                'node-children
                :layout-function :top-down
                :layout-x-adjust :left)
 :best-width 300 :best-height 400)
```

This example demonstrates a different style of graph output with right-angle edges and parent nodes being adjusted towards the top instead of at the center.

```
(capi:contain
  (make-instance
   'capi:graph-pane
   :roots '(1)
   :children-function 'node-children
   :layout-y-adjust '(:top 10)
   :edge-pinboard-class
   'capi:right-angle-line-pinboard-object)
   :best-width 300
   :best-height 400)
```

This example demonstrates the use of :node-pinboard-class to specify that the nodes are drawn
as push buttons.

```
(capi:contain
  (make-instance
  'capi:graph-pane
  :roots '(1)
  :children-function 'node-children
  :node-pinboard-class 'capi:push-button)
:best-width 300
:best-height 400)
```

There are more examples in the directory examples/capi/graphics/.

See also

item-pinboard-object
line-pinboard-object

output-pane

graph-pane-add-graph-node

Generic Function

Summary Adds a node to a graph.

Package capi

Signature graph-pane-add-graph-node graph-pane object parent-node =>

new-node

Arguments graph-pane A graph-pane.

object An object.

parent-node A graph-node.

Values new-node A graph-node.

Description The generic function graph-pane-add-graph-node adds a

new node in the graph graph-pane corresponding to object,

and links it as a child of parent-node.

See also graph-node

graph-pane

graph-pane-delete-object

Generic Function

Summary Removes a node from a graph.

Package capi

Signature graph-pane-delete-object graph-pane object

Arguments graph-pane A graph-pane.

object An object.

Description The generic function graph-pane-delete-object deletes

the node corresponding to object in the graph graph-pane.

See also graph-node

graph-pane

graph-pane-add-graph-node
graph-pane-delete-objects

graph-pane-delete-objects

Generic Function

Summary Removes nodes from a graph.

1 CAPI Reference Entries

Package capi

Signature graph-pane-delete-objects graph-pane objects

Arguments graph-pane A graph-pane.

objects A list of objects.

Description The generic function graph-pane-delete-objects deletes

the node in the graph graph-pane corresponding to each object

in the list objects.

See also graph-node

graph-pane

graph-pane-delete-object

graph-pane-delete-selected-objects

Generic Function

Summary Removes selected nodes from a graph.

Package capi

Signature graph-pane-delete-selected-objects graph-pane

Arguments graph-pane A graph-pane.

Description The generic function graph-pane-delete-selected-

objects deletes the currently selected nodes in the graph

graph-pane.

See also graph-node

graph-pane

graph-pane-delete-object

graph-pane-direction

See also

graph-pane

Generic Function

Summary Returns or sets the direction of a graph. **Package** capi Signature graph-pane-direction graph-pane => direction (setf graph-pane-direction) direction graph-pane => direction Arguments graph-pane A graph-pane. Values direction One of : forwards or : backwards. Description The generic function graph-pane-direction returns the direction of the graph graph-pane. If the layout-function of graph-pane is :top-down or :left-right then direction is : forwards. Otherwise direction is :backwards. The generic function (setf graph-pane-direction) maintains the dimension of the *layout-function* but potentially reverses its direction. Example (setf gp (make-instance 'capi:graph-pane :layout-function :top-down)) #<CAPI:GRAPH-PANE [0 items] 20603294> (setf (capi:graph-pane-direction gp) :backwards) NIL (capi:graph-pane-layout-function gp) : TOP-DOWN

graph-pane-edges

Function

Summary Returns the edges of a graph.

Package capi

Signature graph-pane-edges graph-pane => edges

Arguments graph-pane A graph-pane.

Values *edges* A list.

Description The function graph-pane-edges returns a list of all the

graph-edge objects in the graph graph-pane.

See also graph-edge

graph-pane

graph-pane-nodes

Function

Summary Returns the nodes of a graph.

Package capi

Signature graph-pane => nodes

Arguments graph-pane A graph-pane.

Values nodes A list.

Description The function graph-pane-nodes returns a list of all the

graph-node objects in the graph graph-pane.

See also graph-node

graph-pane

graph-pane-object-at-position

Function

Summary Returns the graph object at a given position in a graph.

Package capi

Signature graph-pane-object-at-position graph-pane $x \ y \Rightarrow object$

Arguments graph-pane A graph-pane.

Values object A graph-object, or nil.

x, *y* Non-negative numbers.

Description The function graph-pane-object-at-position returns the

graph-object (either a graph-edge or a graph-node) at the

coordinates x, y in the graph graph-pane.

If there is no graph-object at position x, y then graph-pane-

object-at-position returns nil.

See also graph-pane

graph-pane-select-graph-nodes

Generic Function

Summary Selects nodes in a graph according to a predicate.

Package capi

Signature graph-pane-select-graph-nodes graph-pane predicate

Arguments graph-pane A graph-pane.

predicate A function of one argument with boolean

result.

1 CAPI Reference Entries

Description The generic function graph-pane-select-graph-nodes

applies *predicate* to all of the graph-nodes in *graph-pane*, and sets the *selected-items* to be the objects corresponding to those

nodes for which *predicate* returns a true value.

See also choice-selected-items

graph-node graph-pane

graph-pane-update-moved-objects

Generic Function

Summary Updates a graph after the user moves objects.

Package capi

Signature graph-pane-update-moved-objects graph-pane objects

Arguments graph-pane A graph-pane.

objects A list.

Description The generic function graph-pane-update-moved-objects

is called after some objects in the graph graph-pane were

moved by a user gesture.

objects is a list containing the objects that were moved.

The primary method updates the geometry of edges connected to the moved objects. You can add non-primary meth-

ods to perform other operations at that point.

See also graph-pane

grid-layout Class

Summary The grid-layout is a layout which positions its children on

a two dimensional grid.

Package capi

Superclasses x-y-adjustable-layout

Subclasses row-layout

column-layout

Initargs :columns The number of columns in the grid.

:has-title-column-p

A boolean specifying whether the first

column is a title column.

:orientation The orientation of the children.

:rows The number of rows in the grid.

:x-ratios The ratios between the columns.

:y-ratios The ratios between the rows.

:x-gap The gap between each column.

:y-gap The gap between each row.

:x-uniform-size-p

If t, make each of the columns the same size.

:y-uniform-size-p

If t. make each of the rows the same size.

ACCESSORS layout-x-ratios

layout-y-ratios
layout-x-gap
layout-y-gap

Description

The row and column sizes are controlled by the constraints on their children. For example, the *visible-min-width* of any column is the maximum of the *visible-min-width* in of the children in the column. The size of the layout is controlled by the constraints on the rows and columns.

For grid-layout description is either a two dimensional array or a list in the order specified by orientation (which defaults to :row). In the case of a list, one of columns or rows can be supplied to specify the dimensions (the default is two columns). As well as panes, slot names and strings, description may contain the element nil, which is interpreted as a special dummy pane with suitable geometry for resizable gaps. This special interpretation of nil in the description is specific to grid-layout and its subclasses.

The *x-ratios* and *y-ratios* slots control the sizes of the elements in a grid layout in the following manner:

The elements of *x-ratios* (or *y-ratios*) control the size of each child relative to the others. If an element in *x-ratios* (or *y-ratios*) is nil the child is fixed at its minimum size. Otherwise the size is calculated as follows

(round (* total ratio) ratio-sum)

where *ratio-sum* is the sum of the non-nil elements of *x-ratios* (or *y-ratios*) and *ratio* is the element of ratios corresponding to the child. If this ideal ratio size does not fit the maximum or minimum constraints on the child size, and the constraint means that changing the ratio size would not assist the sum of the child sizes fitting the total space available, then the child is fixed at its constrained size, the child is removed from the ratio calculation, and the calculation is performed again. If *x-ratios* (or *y-ratios*) has fewer elements than the number of children, 1 is used for each of the missing ratios. Leaving *x-ratios* (or *y-ratios*) nil causes all of the children to be the same size.

The positions of each pane in the layout can be specified using *x-adjust* and *y-adjust* like every other *x-y-adjustable-layout*, except that if there is one value then it is used for all of the panes, whereas if it is a list then each value in the list refers to one row or column. If the list does not contain a value for every row or column then the last value is taken to refer to all of the remaining panes.

Normally, the items in a grid-layout are arranged to look like a set of columns that are joined horizontally and rows that are joined vertically. All the cells in each column have the same width and all the cells in each row have the same height. The keyword :right-extend (or :bottom-extend) can be used to allow an item to span more than one column (or row). The keyword should be placed in the cell of the description that you want the item to expand into. For :right-extend, the cell immediately to the left will be extended to fill both columns in that row. For :bottom-extend, the cell immediately above will be extended to fill both rows in that column.

If *has-title-column-p* is true, then the items in the description which correspond to the first column are treated specially:

A string Equivalent to specifying (:title string)

A list of the form (:title string . options)

Make a title using the given list as initargs. options is a plist of options, which can include the keys :title-font, :title-args, :mnemonic or :mnemonic-escape. See titled-object for how these are processed.

A list of the form (:mnemonic-title string . options)

Make a title using the given list as initargs. string can contain the mnemonic escape. options is a plist of options, which can include the keys:title-font, :title-args, or :mnemonic-escape. See titled-object for how these are processed

Note: mnemonics are not supported on all platforms.

```
Example
              (capi:contain (make-instance
                             'capi:grid-layout
                             :description '("1" "2" "3"
                                             "4" "5" "6"
                                             "7" "8" "9")
                             :columns 3))
              (capi:contain (make-instance
                             'capi:grid-layout
                             :description (list "List:"
                                                  (make-instance
                                                  'capi:list-panel
                                                  :items '(1 2 3))
                                                  "Buttons:"
                                                  (make-instance
                                                  'capi:button-panel
                                                  :items '(1 2 3)))))
              (capi:contain (make-instance
                             'capi:grid-layout
                             :description (list "List:"
                                                  (make-instance
                                                  'capi:list-panel
                                                  :items '(1 2 3))
                                                 "Buttons:"
                                                  (make-instance
                                                  'capi:button-panel
                                                  :items '(1 2 3)))
                              :x-adjust '(:right :left)
                             :y-adjust '(:center :bottom)))
```

This example illustrates the special interpretation of mil in the *description*:

```
(capi:contain
 (make-instance
  'capi:grid-layout
  :description
  (cdr
   (loop for i below 5
         appending
         (list
          nil
          (make-instance 'capi:simple-pane
                          :background :red
                          :visible-min-width 50
                          :visible-max-width t
                          :visible-min-height 50
                          :visible-max-height t))))
 :columns 3)
 :height 150 :width 150 :title "Resize Me")
```

This example illustrates the use of :right-extend and :bottom-extend to make cells span multiple columns and rows:

```
examples/capi/layouts/extend.lisp
There are more examples in the directory
examples/capi/applications/.
```

This example is a grid with :has-title-column-p t: examples/capi/layouts/titles-in-grid.lisp

See also layout

hide-interface Function

Summary The function hide-interface hides the interface containing

a specified pane.

Package capi

Signature hide-interface pane &optional iconify

Description The function hide-interface hides the interface containing

pane from the screen. If *iconify* is non-nil then it will iconify it, else it will just remove it from the screen. To show it again,

use show-interface.

The default value of iconify is t.

See also interface

show-interface quit-interface

hide-pane Function

Summary Hides the specified pane.

Package capi

Signature hide-pane pane => pane

Arguments pane An instance of simple-pane or a subclass.

Description The function hide-pane hides the pane pane, removing it

from the screen. pane's children, if any, are hidden too.

To restore pane to the screen, use show-pane.

See also hide-interface

show-pane

highlight-pinboard-object

Generic Function

Summary Highlights a specified pinboard object.

Package capi

Signature highlight-pinboard-object pinboard object &key redisplay

Arguments pinboard A pinboard-layout.

object A pinboard-object.

redisplay A generalised boolean.

Description The generic function highlight-pinboard-object causes

the pinboard object object to become highlighted until

unhighlight-pinboard-object is called on it.

The pinboard object highlighting is drawn according to the

highlight-style of the pinboard-layout pinboard.

If redisplay is non-nil the highlighting is drawn immediately.

The default value for redisplay is t.

See also unhighlight-pinboard-object

draw-pinboard-object-highlighted

pinboard-object
pinboard-layout

image-list Class

Summary An object used to manage the images displayed by tree views

and list views.

Package capi

Superclasses capi-object

Initargs :image-width The width of the images in this image list.

:image-height The height of the images in this image list.

:image-sets A list of images or image sets.

Description The :image-sets initary specifies a list. Each item in the list

image-sets may be one of the following.

A pathname or string

This specifies the filename of a file suitable

for loading with load-image.

A symbol The symbol must be a predefined image

identifier, or have been registered by means of a call to register-image-translation.

An image object, as returned by load-image.

An image-set object

See image-set for further details.

Note that image sets are added in their entirety; it is not possible to use image-locators to extract a single image from an image set.

The images added to the image list are numbered in order, starting from zero. An image-set containing n images contributes n images to the image list, and hence consumes n consecutive integer indices.

Example See the files

examples/capi/choice/tree-view.lisp

examples/capi/choice/extended-selection-tree-

view.lisp

See also image-set

load-image

register-image-translation

image-pinboard-object

Class

Summary An image pinboard object is a pinboard object that displays

itself as an image.

Package capi

Superclasses pinboard-object

titled-object

Initargs : image The image to be displayed.

Accessors image-pinboard-object-image

Description The image initary for an image-pinboard-object should

either be an external-image or any other object accepted by

load-image. The image displayed in the object can be

changed dynamically using the writer function

(setf image-pinboard-object-image)

```
Example
              (cd (sys:lispworks-dir "examples/capi/"))
              (setf image
                    (capi:contain
                     (make-instance
                      'capi:image-pinboard-object
                      :image "applications/images/info.bmp")))
              (capi:apply-in-pane-process
               (capi:element-parent image)
               #'(setf capi:image-pinboard-object-image)
               "graphics/Setup.bmp" image)
              (capi:apply-in-pane-process
               (capi:element-parent image)
               #'(setf capi:image-pinboard-object-image)
               "applications/images/info.bmp" image)
              (capi:contain
               (make-instance
                'capi:image-pinboard-object
                :image "graphics/Setup.bmp"
                :title "LispWorks Splashscreen"
                :title-adjust :right
                :title-position :bottom))
See also
             pinboard-layout
```

image-set Class

Package capi

Description

An image set is an object that identifies the location of an image. The image is typically a large image to be broken down into sub-images. The sub-images must all have the same size and be positioned side by side.

The following functions are available to create image set objects:

See also make-general-image-set

make-icon-resource-image-set

make-scaled-image-set

make-scaled-general-image-set

make-resource-image-set

install-postscript-printer

Function

Summary Installs or modifies a Postscript printer definition.

Package capi

Signature install-postscript-printer name &key if-exists default savep

ppd-file description use-jcl command use-file always-print-to-file

orientation installed-options

Arguments *name* A string.

if-exists One of : supersede, : error or nil.

default One of t, nil or :when-none.

savep A boolean.

ppd-file A string or pathname.

description A string, or :preserve.

use-jcl A boolean, or :preserve.

command A string, or :preserve.

use-file A boolean, or :preserve.

always-print-to-file

A boolean, or :preserve.

orientation One of :landscape, :portrait or

:preserve.

installed-options An association list, or :preserve.

Description

The function install-postscript-printer installs or modifies a Postscript printer definition for the given printer name.

This applies only on GTK+ and Motif.

name is a string naming the printer.

if-exists controls what happens if the named printer is already known. The default value is :supersede.

default controls whether the default printer is set. The value to forces the default printer to be set. The value :when-none causes the default printer to be set if there is currently no default. The default value of default is nil.

savep, if true, causes the printer to be saved for subsequent sessions, by writing a file to the path specified by the first item of *printer-search-path*.

ppd-file, if non-nil, should be a pathname or string specifying the name of a PPD file (PostScript Printer Description File) which comes with the printer and specifies the printer properties. ppd-file must be supplied when installing a new printer. The default value is nil.

All the other arguments provide optional printer information. Each defaults to the value :preserve, which means that appropriate defaults are used. These correspond to the settings on the dialog displayed by printer-configuration-dialog. Non-default values are as follows:

description is a string describing the printer.

use-jcl controls whether to use Job Control Language (JCL).

command is the command to execute to print with the printer.

use-file controls how to pass data to the printer. A true value means a file is used, nil means a pipe is used.

always-print-to-file controls whether printing always goes to a file.

orientation controls the orientation of the output.

installed-options is an association list, with pairs of strings where the car is an option name and the cdr is its value. Which options are available and their potential values is defined by the *OpenUI/*CloseUI and *JCLO-penUI/*JCLCloseUI entries in the PPD file.

See also

printer-configuration-dialog

ppd-directory

printer-search-path

uninstall-postscript-printer

installed-libraries

Function

Summary Returns the installed libraries.

Package capi

Signature installed-libraries => libraries

Values *libraries* A list of library names.

Description The function installed-libraries returns the list of

installed CAPI libraries.

A library name is a keyword naming a library.

On Linux, FreeBSD and x86/x64 Solaris platforms, libraries is initially (:gtk) but may also include :motif if the deprecated "capi-motif" module is loaded.

On Microsoft Windows platforms, currently *libraries* is always (:win32).

On Mac OS X platforms, in the native GUI image *libraries* is always (:cocoa). In the Mac OS X/GTK+ image, libraries is initially (:gtk) but may also include :motif if the deprecated "capi-motif" module is loaded.

In LispWorks for UNIX only (not LispWorks for Linux, FreeBSD, or x86/x64 Solaris), currently *libraries* is always

(:motif).

See also default-library

interactive-pane

Class

Summary An interactive-pane is an editor with a process reading

and processing input, and that collects any output into itself. The class listener-pane is built upon this, and adds func-

tionality for handling Lisp forms.

Package capi

Superclasses editor-pane

Subclasses listener-pane

shell-pane

Initargs :top-level-function

The input processing function.

Readers interactive-pane-stream

interactive-pane-top-level-function

Description An interactive-pane contains its own GUI stream. The

top-level-function is called once, when the interactive pane is created: it needs to repeatedly take input from the GUI

stream and write output to it.

The first argument to *top-level-function* is the interface containing the interactive pane. The second argument is the interactive pane itself. The third argument is the GUI stream. The default for *top-level-function* is a function which runs a

Lisp listener top-loop.

Compatibility note

This class was named interactive-stream in LispWorks 3.2 but has been renamed to avoid confusion (this class is not a stream but a pane that contains a stream). The class interactive-stream and its accessors interactive-stream-top-level-function and interactive-stream-stream have been kept for compatibility but may be dropped in future versions of LispWorks.

Example

This example assumes there is just one line of output from each command sent to the pipe

```
(capi:contain
 (make-instance
  'capi:interactive-pane
  :top-level-function
 #'(lambda (interface pane stream)
      (declare (ignore interface pane))
      (with-open-stream (s (sys:open-pipe
                             '("/usr/local/bin/bash")
                             :direction :io))
        (100p
         (progn
           (format stream "primitive xterm$ ")
           (let ((input (read-line stream nil nil)))
             (if input
                 (progn
                    (write-line input s)
                    (force-output s))
               (return))))
         (let ((output (read-line s nil nil)))
           (if output
               (progn
                  (write-line output stream)
                 (force-output stream))
             (return))))))))
:best-height 300
 :best-width 300)
```

See also collector-pane

interactive-pane-execute-command

Generic Function

Summary Simulates user entry of commands in an interactive-pane.

Package capi

Signature interactive-pane-execute-command interactive-pane command

&key command-modification-function editp &allow-other-keys

Arguments interactive-pane An interactive-pane.

command A Lisp form.

command-modification-function

A function or mil.

editp A generalized boolean.

Description The generic function interactive-pane-execute-command

has the same effect as the user typing the Lisp form *command* into the interactive-pane interactive-pane, and pressing

Return.

interactive-pane-execute-command may be called from

any process.

If *command-modification-function* is non-nil, it is a function of one argument. It is called with argument *command* in the process in which *interactive-pane* runs. The result of this call is used as the command to enter. The default value of *command-*

modification-function is nil.

If editp is true then the command is left at the end of the pane for the user to edit before pressing Return. If editp is nil then interactive-pane-execute-command simulates the

user pressing **Return**. The default value of *editp* is nil.

See also interactive-pane

listener-pane-insert-value

interface Class

Summary The class interface is the top level window class, which

contains both menus and a hierarchy of panes and layouts. Interfaces can also themselves be contained within a layout,

in which case they appear without their menu bar.

Package capi

Superclasses simple-pane

titled-object

Initargs :title The title of the interface.

:layout The layout of the interface.

:menu-bar-items

The items on the menu bar.

:auto-menus A flag controlling the automatic addition of

system menu objects.

:create-callback

A callback done on creating the window,

before display and user interaction.

:destroy-callback

A callback done on closing the window.

:confirm-destroy-function

A function to verify closing of the window.

:best-x The best x position for the interface.

:best-y The best y position for the interface.

:best-width The best width of the interface.

:best-height The best height of the interface.

:geometry-change-callback

A function called when the interface geometry changes.

:activate-callback

A function called when the interface is activated or deactivated.

:iconify-callback

A function called when the interface is iconified or restored.

:override-cursor

A cursor that takes precedence over the cursors of panes inside the interface.

override-cursor is not supported on Cocoa.

override-cursor is ignored by text-inputpane on GTK+.

:message-area A boolean determining whether the interface has a message area.

:enable-pointer-documentation

A boolean determining whether Pointer Documentation is enabled.

enable-pointer-documentation is supported only on Motif. It is possible to implement equivalent functionality for output-pane and subclasses such as pinboard-layout by using the focus-callback of output-pane.

:enable-tooltips

A boolean determining whether Tooltip Help is enabled.

:help-callback

A function called when a user gesture requests help.

:top-level-hook

A function called around the top level event handler.

:external-border

An integer or mil.

:initial-focus

A pane, a symbol naming a pane, or mil.

:display-state

One of the keywords :normal, :maximized, :iconic and :hidden.

:transparency

A real number in the inclusive range [0,1], used on Cocoa, later versions of Microsoft Windows, and GTK+.

:window-styles

A list of keywords, or nil.

:toolbar-items

A list of items for the toolbar.

:toolbar-states

A toolbar state plist.

:default-toolbar-states

A toolbar state plist.

:pathname

A pathname designator.

:drag-image

nil, t or an image specifier (that is, a value acceptable as the id argument of loadimage). Accessors

interface-title
pane-layout

interface-menu-bar-items
interface-create-callback
interface-destroy-callback

interface-confirm-destroy-function
interface-geometry-change-callback

interface-activate-callback
interface-iconify-callback
interface-override-cursor
interface-message-area

interface-pointer-documentation-enabled

interface-tooltips-enabled
interface-help-callback

top-level-interface-external-border top-level-interface-transparency

interface-toolbar-items
interface-toolbar-states

interface-default-toolbar-states

interface-pathname
interface-drag-image

Readers

interface-window-styles

Description

Every interface can have a title *title* which when it is a top level interface is shown as a title on its window, and when it is contained within another layout is displayed as a decoration (see the class titled-object for more details).

The argument *layout* specifies a layout object that contains the children of the interface. To change this layout you can either use the writer pane-layout, or you can use the layout switchable-layout which allows you to easily switch the currently visible child.

The argument *menu-bar-items* specifies a list of menus to appear on the interface's menu bar.

auto-menus defaults to t, which means that an interface may have some automatic menus created by the environment in which it is running (for example the Works menu in the Lisp-Works IDE). To switch these automatic menus off, pass :auto-menus nil.

When you have an instance of an interface, you can display it either as an ordinary window or as a dialog using respectively display and display-dialog. The CAPI calls create-callback (if supplied) with the interface as its single argument, after all the widgets have been created but before the interface appears on screen. Then to remove the interface from the display, you use quit-interface and either exit-dialog or abort-dialog respectively. When the interface is about to be closed, the CAPI calls the confirm-destroy-function (if there is one) with the interface, and if this function returns non-nil the interface is closed. Once the interface is closed, the destroy-callback is called with the interface.

Note: create-callback should be used only for operations that must be done with the interface already created and cannot be done in interface-display. Otherwise they should be either done in initialize-instance or between your calls to make-instance and display. An operation that needs to run after the interface is created but just before displaying the interface as an ordinary window (typical cases are font queries and loading images) can be put in the interface-display:before method. An operation that needs to run just after displaying the interface as an ordinary window can be put in the interface-display:after method.

The interface also accepts a number of hints as to the size and position of the interface for when it is first displayed. The arguments best-x and best-y must be the position as an integer or nil (meaning anywhere), while the arguments best-width and best-height can be any hints accepted by :visible-max-width and :visible-max-height for elements.

Whether or not an interface window is resizable is indicated as allowed by the window system. For non-resizable windows on Cocoa the interface window's maximize button is disabled and the resize indicator is not shown, and on Microsoft Windows the maximize box is disabled.

geometry-change-callback may be nil, meaning there is no callback. This is the default value. Otherwise geometry-change-callback is a function of five arguments: the interface and the geometry. Its signature is:

geometry-change-callback interface x y width height

x and *y* are measured from the top-left of the screen rectangle representing the area of the primary monitor (the primary screen rectangle).

activate-callback may be mil, meaning there is no callback. This is the default value. Otherwise activate-callback is a function of two arguments: the interface and a boolean activatep which is true on activation and false on deactivation. Its signature is:

activate-callback interface activatep

inconify-callback may be nil, meaning there is no callback. This is the default value. Otherwise inconify-callback is a function of two arguments: the interface and a boolean iconify which is true when interface is iconified and false when it is restored. Its signature is:

iconify-callback interface iconifyp

override-cursor, if non-nil, specifies a cursor that is used instead of the cursor of each pane inside the interface. The default value of override-cursor is nil. See below for an example of setting and unsetting the override cursor. override-cursor is not supported on Cocoa. override-cursor is ignored by text-input-pane on GTK+.

If message-area is true, then the interface is created with a message area at the bottom. The text of the message area can be accessed using the titled-object accessor titled-object-message. The default value of message-area is nil.

enable-pointer-documentation is a boolean controlling whether Pointer Documentation is enabled, on Motif. The default value is t. The actual action is done by the *help-callback*.

enable-tooltips is a boolean controlling whether Tooltip Help is enabled. The default value is t. The actual action is done by the *help-callback*.

help-callback may be nil, meaning there is no callback. This is the default value. Otherwise help-callback is a function of four arguments: the interface, the pane inside interface where help is requested, the type of help requested, and the help key of the pane. Its signature is:

help-callback interface pane type help-key

Here *type* can be one of:

:tooltip A tooltip is requested. The function needs to

return a string to display in the tooltip, or nil if no tooltip should be displayed.

:help The function should display a detailed,

asynchronous help. This value is passed when the user presses the F1 key (not implemented on Cocoa). :help is also passed when the user clicks the '?' box in the title bar of a Microsoft Windows dialog with window style :contexthelp (see window-

styles below).

On Motif only, *type* can also be one of:

:pointer-documentation-enter

The cursor entered the pane. The function should set the pointer documentation.

:pointer-documentation-leave

The cursor left the pane. The function needs to reset the pointer documentation.

help-key is the help-key of pane, as described in element. There is an example illustrating help-callback in examples/capi/elements/help.lisp and there is another example below.

top-level-hook can be used on Microsoft Windows and Motif to specify a hook function that is called around the interface's top level event handler. The hook is passed two arguments: a continuation function (with no arguments) and the interface. The hook must call the continuation, which normally does not return. top-level-hook is designed especially for error handling (see below for an example). It can also be used for other purposes, for instance to bind special variables around the top level function. :top-level-hook is not supported on Cocoa.

external-border controls how close to the edge of the screen the interface can be placed with explicit positioning using the best-x, best-y, best-height and best-width initargs or implicit positioning when a dialog is centered within its owner. The value nil allows the window to be anywhere, on or off the screen. The value 0 allows the window can be anywhere on the screen. If external-border is a positive integer then the window can be anywhere within external-border pixels from the edge of the screen. If external-border is a negative integer then the window be anywhere on the screen or up to external-border pixels off the edge of the screen. This does not affect whether the use can move the window after it has been displayed. It also does not affect the default positioning of interfaces, where the window system chooses the position. The default value of external-border is 0.

initial-focus specifies a pane which has the input focus when the interface is first displayed. See pane-initial-focus for more information about the initial focus pane.

display-state controls the initial display of the interface window, as described for top-level-interface-display-state.

transparency is the overall transparency of the whole interface, where 0 is fully transparent and 1 is fully opaque. This has no effect on whether the user can click on the window. This is implemented for Cocoa and for Microsoft Windows,

excluding Windows 98, Millennium Edition and NT 4.0. It also works on GTK+, provided that GTK+ and the X server support it. On GTK+ it is supported in version 2.12 and later. The X server needs compositing manager to do it.:transparency should only be used for top-level interfaces.

window-styles is a list of keywords controlling various aspects of the top level window's appearance and behavior. Each keyword is supported only on the Window systems explicitly mentioned below.

The following keywords apply to ordinary windows:

:no-geometry-animation

Cocoa: Programmatic changes to window geometry happen without animation.

:hides-on-deactivate-window

Cocoa: The window is only visible when the application is the current application.

Microsoft Windows and GTK+: The window is only visible when it is the active window.

:toolbox

Cocoa, Microsoft Windows and GTK+: A window with a small title bar. This window style is used in docking-layout.

:borderless

Cocoa, Microsoft Windows, GTK+ and Motif: A window with no external decoration or frame.

:internal-borderless

Cocoa and Motif: Remove the default border between the window's edge and its contents.

Microsoft Windows: Remove the default border between the window's edge and its contents for dialogs.

:never-iconic

Cocoa, Microsoft Windows, GTK+ and Motif: The window cannot be minimized.

:movable-by-window-background

Cocoa and Microsoft Windows: The user can move the window by grabbing at any point not in an inner pane.

:shadowed

Cocoa: Force a shadow on windows with window style :borderless. (Other windows have a shadow by default.)

Windows XP (and later): The window has a shadow.

:shadowless

Cocoa: The window has no shadow.

:textured-background

Cocoa: The window has a textured background (like the Finder).

:always-on-top

Cocoa, Microsoft Windows and GTK+: The window is always above all other windows. Such a window is also known as a windoid.

:ignores-keyboard-input

Cocoa and GTK+: The window cannot be given the focus for keyboard input.

:no-character-palette

Cocoa: The **Special Characters...** menu item is not inserted automatically. (This menu item is added to the **Edit** menu by default.)

:motion-events-without-focus

Cocoa: output-panes in the window will see :motion input model events even if the output pane does not have the focus. This is the same behavior as on Microsoft Windows.

The following keywords are supported in *window-styles* when the interface is displayed as a dialog:

:resizable

Microsoft Windows: The dialog has a border to allow resizing. (Generally Windows dialogs do not allowing resizing.)

:contexthelp

Microsoft Windows: A '?' box appears in the window's title bar that sends *help-callback* type:help.

If toolbar-items is non-nil, then the interface will have a toolbar, which is typically displayed at the top of the window. The value of toolbar-items is a list of objects of type toolbar-button, toolbar-component or simple-pane, which are items that might be shown on the toolbar. The set of visible items, their order and their appearance is determined by the current toolbar-state, which can be changed if the user customizes the toolbar interactively. Each toolbar-button or simple-pane in the toolbar-items list (including those within a toolbar-component) should have a name that is not eql to any other item in the list. Each toolbar-button should have image and text specified, to control the image and title that is shown for the item. Each simple-pane should have toolbar-title specified, to control the title that is shown for the item.

toolbar-states is a plist containing information about the state of the toolbar. The user can also change this by customizing the toolbar, so you cannot assume that the value will be the same each time you read it. See interface-toolbar-state for a description of the keys and values in this plist.

default-toolbar-states is a plist containing information about the default state of the toolbar, which you can provide as the suggested toolbar state for the interface. The :items key will be used in the Customize dialog as the "default" set of toolbar buttons. If both default-toolbar-states and toolbar-states are supplied, then the value of any key in toolbar-states takes precedence over that of the same key in default-toolbar-states. See interface-toolbar-state for a description of the keys and values in this plist.

pathname specifies the interface pathname. You can get and set this with the accessor interface-pathname. The pathname may be displayed in some way to the user, depending on the GUI library.

Currently, only Cocoa uses *pathname*, in two ways:

- It makes the interface display a drag image on the title bar (This is the same image that is set by interface-drag-image, and the drag-image takes precedence if it not nil). The user can drag from the drag image, and if there is no drag-callback or if the drag-callback returns :default it will drag the pathname as a one item in a :filenames-list. For information about drag-callback, see simple-pane's description of :drag-callback and simple-pane-drag-callback.
- The context menu (invoked by right-mouse-click) on the drag image or on the title raises a menu containing the components of the path. Selecting a component opens the Finder with it.

drag-image is currently only effective on Cocoa. A non-nil value specifies that the interface should have a drag image, which on Cocoa is a small image (16x16px) to the left of the window title.

When the user drags this image, if the interface has a drag-callback it is called and if this returns non-nil LispWorks performs drag-and-drop with the image. See simple-pane for details of the drag-callback.

It is possible to have the image for aesthetic purposes only by supplying *drag-image* and not specifying a *drag-callback*. When *drag-callback* is non-nil, it can dynamically decide whether to allow a dragging, or to disallow dragging (by returning nil).

The image specification can be an already converted image (made by load-image, convert-external-image, make-sub-image or make-image-from-port). The image will be freed automatically when the interface is destroyed or when drag-image is set by (setf interface-drag-image). Otherwise the system uses load-image to create a new image, which is also freed automatically.

The value t for drag-image is interpreted specially: it means display <u>some</u> image. If drag-image is set to t after an image has already been set, it just displays the previous image. This is useful if an image was displayed but then removed by (setf interface-drag-image) with nil. If there was no previous image, a default image is displayed.

Notes

- create-callback can only be used for actions that are part of the creation of the pane, that is preparing the pane for display. The create-callback is called before the pane is actually displayed, and therefore cannot interact with the user.
- **2.** On Microsoft Windows **F1** always calls *help-callback* if it is non-nil.
- **3.** (setf capi:interface-message-area) has an effect only before display. After display, this writer has no effect unless the interface is destroyed and re-created.

- 4. Even though interface is a subclass of titled-object, the accessor titled-object-message-font cannot be used to get and set the font of the interface's message.
- 5. On Cocoa in the presence of a cocoa-default-application-interface, an interface with no menus of its own and with :auto-menus nil uses the menu bar from the application interface.

Compatibility interface-iconize-callback is deprecated. Use the synonym interface-iconify-callback instead.

Example

```
(capi:display (make-instance 'capi:interface
                              :title "Test Interface"))
(capi:display (make-instance
                'capi:interface
                :title "Test Interface"
                :destroy-callback
                  #'(lambda (interface)
                             (capi:display-message
                              "Quitting ~S"
                              interface))))
(capi:display (make-instance
                'capi:interface
                :title "Test Interface"
                :confirm-destroy-function
                #'(lambda (interface)
                           (capi:confirm-yes-or-no
                           "Really quit ~S"
                           interface))))
(capi:display (make-instance
                'capi:interface
                :menu-bar-items
                  (list
                    (make-instance 'capi:menu
                                    :title "Menu"
                                    :items '(1 2 3)))
                :title "Menu Test"))
```

```
(setq interface
      (capi:display
       (make-instance
        'capi:interface
        :title "Test Interface"
        :lavout
        (make-instance 'capi:simple-layout
                       :description
                       (list (make-instance
                               'capi:text-input-pane
                               :text "Text Pane"))))))
(capi:execute-with-interface interface
#'(setf capi:pane-layout) (make-instance
                             'capi:simple-layout
                            :description
                             (list (make-instance
                                    'capi:editor-pane
                                  :text "Editor Pane")))
interface)
(capi:display
 (make-instance
  'capi:interface
 :title "Test"
 :best-x 200
 :best-y 200
 :best-width '(/ :screen-width 2)
  :best-height 300))
```

The following forms illustrate the use of *help-callback*:

```
(capi:define-interface my-interface ()
  ()
  (:panes
   (a-pane
   capi:text-input-pane
    :help-key 'input)
   (another-pane
   capi:display-pane
   :help-kev 'output
    :text "some text"))
  (:menu-bar a-menu)
  (:menus
   (A-menu
   "A menu"
    (("An item" :help-key "item 1")
     ("Another item" :help-key "item 2"))
    :help-key "a menu"))
  (:layouts
   (main-layout
   capi:column-layout
    '(a-pane another-pane)))
  (:default-initargs
   :help-callback 'my-help-callback
   :message-area t))
(defun do-detailed-help (interface)
  (capi:contain
   (make-instance
    'capi:display-pane
   :text "Detailed help for my interface")
   :title
   (format nil "Help for ~a"
           (capi:capi-object-name interface))))
(defun my-help-callback (interface pane type key)
  (declare (ignore pane))
  (case type
    (:tooltip (if (eq key 'input)
                  "enter something"
                (when (stringp key) key)))
    (:pointer-documentation-enter
     (when (stringp key)
       (setf (capi:titled-object-message interface)
             key)))
    (:pointer-documentation-leave
     (setf (capi:titled-object-message interface)
```

```
"Something else"))
  (:help (do-detailed-help interface ))))
(capi:display
  (make-instance 'my-interface :name "Helpful"))
```

The following forms illustrate the use of *override-cursor* to set and then remove an override cursor.

Create an interface with panes that have various different cursors. Move the pointer across each pane.

Override the pane cursors by setting the override cursor on the interface, and move the pointer across each pane again.

```
(setf (capi:interface-override-cursor interface)
    :i-beam)
```

Remove the override cursor.

```
(setf (capi:interface-override-cursor interface)
    :default)
```

This example illustrates *top-level-hook*. Evaluate this form and then get an error by the interrupt gesture in the editor pane. (For example, the interrupt gesture is Meta+Control+C on Motif and Control+Break on Microsoft Windows). Then select the Destroy Interface restart.

The code in examples/capi/applications/simple-symbol-browser.lisp illustrates the use of *toolbar-items*.

See also layout

switchable-layout

menu display

display
display-dialog
interface-display
quit-interface
define-interface
activate-pane
titled-object

interface-document-modified-p
interface-toolbar-state
interface-customize-toolbar

interface-customize-toolbar

Function

Summary Displays a window which allows the user to customize the

toolbar.

Signature interface-customize-toolbar interface

Arguments interface A CAPI interface.

The function interface-customize-toolbar displays a window owned by the interface *interface* that allows the user to customize the toolbar of that interface.

interface must be displayed at the time interface-customize-toolbar is called.

See also

interface toolbar

interface-display

Generic Function

Summary The function called to display an interface on screen.

Package capi

Signature interface-display interface

Arguments interface An instance of a subclass of interface.

Description The generic function interface-display is called by display to display an interface on screen.

The primary method for interface actually does the work. You can add :before methods on your own interface classes for code that needs to be executed just before the interface appears, and :after methods for code that needs to be executed just after the interface appears.

interface-display is useful when you need to make changes to the interface which require it to be already be created. Font queries and loading images are typical cases.

Notes 1. interface-display is called in the process of *interface*.

interface-display is not called when interface is displayed as a dialog. Another way to run code before it appears on screen is to supply a create-callback for interface.

Example

This example shows how interface-display can be used to set the initial selection in a choice whose items are computed at display-time:

```
(capi:define-interface my-tree ()
  ((favorite-color :initform :blue))
  (:panes
   (tree
    capi:tree-view
    :roots '(:red :blue :green)
    :print-function
    'string-capitalize))
  (:default-initargs
   :width 200
   :height 200))
(defmethod capi:interface-display :after
  ((self my-tree))
  (with-slots (tree favorite-color) self
    (setf (capi:choice-selected-item tree)
          favorite-color)))
(capi:display (make-instance 'my-tree))
display
interface
```

interface-display-title

See also

Summary

Function

-	
Package	capi
Signature	<pre>interface-display-title interface => string</pre>

Returns the interface title to use on screen.

Arguments interface A CAPI interface.

Values *string* A string.

Description The function interface-display-title returns the title to

use when displaying the interface interface on screen.

This is equivalent to:

(capi:interface-extend-title

interface

(capi:interface-title interface))

See also interface-extend-title

set-default-interface-prefix-suffix

interface-document-modified-p

Function

Summary Gets and sets the document-modified flag in the interface.

Package capi

Signature interface-document-modified-p interface => value

(setf interface-document-modified-p) value interface

Arguments interface A CAPI interface.

Values value A boolean.

Description The function interface-document-modified-p gets and

sets the document-modified flag in the interface interface.

Currently this only has a visible effect on Cocoa, where an interface whose document is modified is flagged by adding a dark dot in the middle of its Close button (the red button at

top-left of the window).

1 CAPI Reference Entries

On other platforms the document-modified state is merely

remembered.

See also interface

interface-editor-pane

Generic Function

Summary Finds an editor-pane in an interface.

Package capi

Signature interface-editor-pane interface => pane

Arguments interface An instance of a subclass of interface.

ValueS pane An editor-pane or nil.

Description The generic function interface-editor-pane finds the first

pane of interface that is an editor-pane, and returns it.

If there is no editor-pane, then interface-editor-pane

returns nil.

See also editor-pane

interface

interface-extend-title

Generic Function

Summary Calculates the complete interface title.

Package capi

Signature interface-extend-title interface title => string

Arguments interface A CAPI interface.

title A string.

Description The generic function interface-extend-title is called by

the system with an interface and its title before actually displaying the title on the screen. The result must be a string, which is actually displayed. There is no requirement for any

relation between the title argument and the result.

The return value *string* is the title to display on the screen.

The default method uses the values set by set-default-interface-prefix-suffix. You can specialize interface-

extend-title to get other effects.

See also interface-display-title

set-default-interface-prefix-suffix

interface-geometry

Generic Function

Summary Returns the geometry of an interface. This function is depre-

cated. Use top-level-interface-geometry instead.

Package capi

Signature interface-geometry interface => geometry

Arguments interface An instance of a subclass of interface.

Values geometry A list.

Description The generic function interface-geometry returns a list rep-

resenting the geometry of interface in pixel values.

This function is deprecated. Use top-level-interface-

geometry instead.

See also top-level-interface-geometry

interface-iconified-p

Function

Summary The predicate for whether an interface is iconified.

Package capi

Signature interface-iconified-p pane => iconifiedp

Arguments pane A CAPI element.

Values iconifiedp A boolean.

Description The function interface-iconified-p returns t if the top

level interface containing *pane* is iconified. This means that the window is visible as an icon, also referred to as mini-

mized.

If the top level interface is not iconified, then

interface-iconified-p returns nil.

See also hide-interface

top-level-interface

top-level-interface-display-state

interface-keys-style

Generic Function

Summary Determines the emulation for an interface.

Package capi

Signature interface-keys-style interface => keys-style

Arguments interface An instance of a subclass of interface.

Values keys-style A keyword, :pc, :emacs or :mac.

Description

The generic function interface-keys-style returns a keyword indicating a keys style, or *emulation*. It is called when *interface* starts running in a new process, and *keys-style* determines how user input is interpreted by output panes (including editor-pane) in *interface*.

The editor (that is, instances of editor-pane and its subclasses) responds to user input gestures according to one of three basic models.

When keys-style is :emacs, the editor emulates GNU Emacs. This value is allowed on all platforms.

When *keys-style* is :pc, the editor emulates standard Microsoft Windows keys on Windows, and KDE/Gnome keys on GTK+ and Motif. This value is allowed in the Windows, GTK+ and X11/Motif implementations.

When *keys-style* is :mac, the editor emulates Mac OS X editor keys. This value is allowed only in the Mac OS X Cocoa implementation.

The most important differences between the styles are in the handling of the Alt key on Microsoft Windows, selected text, and accelerators:

:emacs

Alt is interpreted on Microsoft Windows as the Meta key (used to access many Emacs commands).

The :meta modifier is used in an outputpane input-model gesture specification.

Control characters such as Ctrl+s are not interpreted as accelerators.

The selection is not deleted on input.

:pc

Alt is interpreted as Alt on Microsoft Windows and can be used for shortcuts.

The :meta modifier is not used in an output-pane input-model gesture specification.

control keystrokes are interpreted as accelerators. Standard accelerators are added for standard menu commands, for example Ctrl+s for File > Save.

The selection is deleted on input, and movement keys behave like a typical Microsoft Windows or KDE/Gnome editor.

:mac

Emacs Control keys are available, since they do not clash with the Macintosh Command key.

The selection is deleted on input, and movement keys behave like a typical Mac OS X editor.

By default *keys-style* is :pc on Microsoft Windows platforms and :emacs on Unix/Linux and Mac OS X platforms. You can supply methods for interface-keys-style on your own interface classes that override the default methods.

In the Cocoa implementation, Command keystrokes such as Command+x are available if there is a suitable Edit menu, regardless of the Editor emulation.

See the chapter "Emulation" in the *LispWorks Editor User Guide* for more detail about the different styles.

Notes

On Motif the code to implement accelerators and mnemonics clashes with the LispWorks meta key support. Therefore the keyboard must be configured so that none of the keysyms connected to mod1 (see xmodmap) are listed in the variable capi-motif-library:*meta-keysym-search-list*,
which must be also be non-nil. Note also that Motif requires
Alt to be on mod1.

See also editor-pane

interface-match-p

Generic Function

Summary Determines whether an interface is suitable for displaying

initargs.

Package capi

Signature interface-match-p interface &rest initargs &key &allow-

other-keys => matchp

Arguments interface An instance of a subclass of interface.

initargs Initargs for interface.

Values matchp A boolean

Description The generic function interface-match-p returns a true

value if interface is suitable for displaying the initargs.

interface-match-p is used by locate-interface. When there is an existing interface for which interface-match-p

returns true, then locate-interface returns it.

The default method for interface-match-p always returns nil. You can add methods for your own interface classes.

See also locate-interface

interface-menu-groups

Generic Function

Summary Used when an embedded document sets the *menu-bar-items*

to its menus, on Windows.

Package capi

Signature interface-menu-groups interface => result

Arguments interface A CAPI interface.

Values result A list.

Description The generic function interface-menu-groups is called

when an embedded document sets the menu bar of its con-

taining interface.

Then, the menu bar for the embedded document includes three groups of menus that are supplied by the container (file-group, view-group, windows-group). interface-menu-

groups is used to define these groups of menus.

interface-menu-groups should return a list of length 3. Each element is a list of menus. In this list, each item is either a menu object, or a cons. When it is a cons, the car is a menu object and the cdr is a string, which overrides the the title of

the menu.

The default method, on interface, simply returns (nil nil

nil).

Notes interface-menu-groups is implemented only in LispWorks

for Windows. Load the functionality by (require "embed").

Example See the example in

examples/com/ole/simple-container/doc-viewer-

pair.lisp

See also ole-control-pane

interface-preserve-state

Generic Function

Summary Called before an interface is destroyed during session saving.

Signature interface-preserve-state interface

Arguments interface An interface.

Description The generic function interface-preserve-state is called

by hcl:save-current-session just before it destroys an interface, on the interface process. You can specialize this for your own interface classes. Your methods should not interact with the user or other external sources, and should not interact with other processes, because it is called after hcl:save-current-session already started to destroy interfaces.

The return value is not used.

The default method does nothing.

See also interface-preserving-state-p

interface-preserving-state-p

Function

Summary The predicate for whether an interface is in "preserving-state"

context.

Signature interface-preserving-state-p interface => result

Arguments interface An interface.

ValueS result t, :different-invocation or :keeping-

processes.

Description An interface enters "preserving-state" context just before it is

destroyed by hcl:save-current-session, and exits the

context just after interface-display returns.

If the interface interface is in "preserving-state" context, the result of :interface-preserving-state-p is either t or :different-invocation. The value t means that the current invocation of LispWorks is still the same invocation. The value :different-invocation means it is a different invocation, in other words it is the saved image that is restarted.

In other circumstances interface-preserving-state-p can return :keeping-processes, which means that the interfaces are destroyed but processes that are not associated with *interface* are not killed. That currently happens only on Microsoft Windows when the programmer changes the arrangement of IDE windows via Preferences... > Environment > General > Window Options.

interface-preserving-state-p is typically used in the destroy-callback of an interface or a pane to decide whether really to destroy the information, and in the create-callback or interface-display to decide whether the existing information can be used. Note that if it is a pane, it needs to find the top-level-interface.

Information that is made entirely of Lisp objects can be preserved in all cases. Information that is associated with external objects is invalid when the image is restarted. So when interface-preserving-state-p is used inside the *create-callback* or interface-display, external information can be preserved only if it returns t. When interface-preserving-state-p returns t, the external information may be preserved, unless it is tied to the lightweight process.

See also

interface
interface-display
interface-preserve-state

interface-reuse-p

Generic Function

Summary Determines whether an interface is suitable for re-use.

Package capi

Signature interface-reuse-p interface &rest initargs &key

&allow-other-keys => reusep

Arguments interface An instance of a subclass of interface.

initargs Initargs for interface.

Values reusep A boolean

Description The generic function interface-reuse-p returns a true

value if *interface* is suitable for reuse with *initargs*.

interface-reuse-p is used by locate-interface if no matching interface is found first by interface-match-p. In this case, when there is an interface for which interface-reuse-p returns true, then locate-interface reinitializes it

by reinitialize-interface and returns it.

Notes interface-reuse-p should not be confused with reuse-

interfaces-p, which determines the global re-use state.

See also interface-match-p

locate-interface

interface-toolbar-state

Function

Signature interface-toolbar-state interface key => value

(setf interface-toolbar-state) value interface key => value

Arguments interface An instance of interface or a subclass.

key One of the toolbar-states plist keys.

value The value associated with the toolbar-states

plist key.

Values

value

The value associated with the *toolbar-states* plist key.

Description

The functions interface-toolbar-state and (setf interface-toolbar-state) read or change the properties of a toolbar that give information about its state. The user can also change these properties by customizing the toolbar, so you cannot assume that the value will be the same each time you read it.

key can be one of the following, with the corresponding value:

:visible

visible is true if the toolbar is visible and false

if it is hidden. The default is true.

:items

items is a list of the names of the toolbar-items which are shown on the toolbar, in the order they are shown. The built-in names :separator, :space and :flexible-space represent various kinds of gap between items. On Microsoft Windows, an item can be a list of the form (:titled-separator title) which starts a dockable group of items that displays title when it is undocked. The default items includes all items in toolbar-items, with :separator between each toolbar-component.

:display

display is a keyword describing what is displayed for each item. It can be :image (just shows an image), :title (just shows the title), :image-and-title (shows both title and image) or :image-and-title-hori-zontal (shows title and image horizontally, only supported on GTK+). The default is

platform-specific.

:size

size is a keyword describing the size of the items. It can be one of :small, :normal or :large. Some of these sizes might be the same as others. The default is platform-specific.

You can set all of the keys simultaneously by setting the interface-toolbar-state accessor or providing the *toolbar-states* initarg.

See also

interface

interface-customize-toolbar

interface-visible-p

Function

Summary

The predicate for whether the interface containing a pane is visible.

VISIBI

Package capi

Signature

interface-visible-p pane => visiblep

Arguments

pane

A CAPI pane.

Values

visiblep

A boolean.

Description

The function interface-visible-p returns nil if

- 1. pane is not associated with any interface, or
- **2.** *pane* is associated with an interface which is not displayed, or
- **3.** *pane* is associated with an interface which is minimized or iconified. or
- **4.** *pane* is known to be fully obscured by other windows. This can happen on Motif, but is not detected on Microsoft Windows.

An error is signalled if *pane* is not a CAPI pane (that is, it is not an instance of a subclass of element, collection or pinboard-object).

Otherwise interface-visible-p returns t.

Notes On Microsoft Windows, interface-visible-p may return

t even though the interface is entirely obscured by another

window.

interpret-description

Generic Function

Summary Converts an abstract description of a layout's children into a

list of the children's geometry objects.

Package capi

Signature interpret-description layout description interface

Description The generic function interpret-description translates an

abstract description of the layout's children into a list of those

children's geometry objects.

For example, column-layout expects as its description a list of items where each item in the list is either the slot-name of the child or a string which should be turned into a title pane. This is the default handling of a layout's description, which is

done by calling the generic function parse-layout-descriptor to do the translation for each item.

Example See the examples in the directory examples/capi/layouts/.

See also parse-layout-descriptor

define-layout

layout interface

invalidate-pane-constraints

Function

Summary Causes the resizing of a pane if its minimum and maximum

size constraints have changed. It returns t if resizing was nec-

essary.

Package capi

Signature invalidate-pane-constraints pane

Description This function informs the CAPI that *pane*'s constraints (its

minimum and maximum size) may have changed. The CAPI then checks this, and if the pane is no longer within its constraints it resizes it so that it is and then makes the pane's parent layout lay its children out and display them again at their new positions and sizes. If the pane is resized, then

invalidate-pane-constraints returns t.

See also get-constraints

layout element

define-layout

invoke-command Function

Summary Invokes a command in the input model for a specified output

pane.

Package capi

Signature invoke-command command output-pane &rest event-args

Description This invokes the command in the input model for the given

output-pane, with the translator being called to process the gesture information. To avoid the translation, use invoke-

untranslated-command.

1 CAPI Reference Entries

See also invoke-untranslated-command

define-command
output-pane

invoke-untranslated-command

Function

Summary Invokes a command in the input model for a specified output

pane, without the translator being called.

Package capi

Signature invoke-untranslated-command command output-pane

&rest event-args

Description The function invoke-untranslated-command invokes the

command in the input model for the given *output-pane*, without the translator being called to process the gesture informa-

tion. To perform the translation, use invoke-command.

See also invoke-command

define-command
output-pane

item Class

Summary The class item groups together a title, some data and some

callbacks into a single object for use in collections and

choices.

Package capi

Superclasses callbacks

capi-object

Subclasses

menu-item

button

item-pinboard-object
popup-menu-button
toolbar-button

Initargs

:collection The collection in which item is displayed

:data The data associated with the item.

:text The text to appear in the item (or nil).

:print-function

If *text* is nil, this is called to print the data.

:selected If t the item is selected.

Accessors

item-collection

item-data
item-text

item-print-function

item-selected

Description

An item can provide its own callbacks to override those specified in its enclosing *collection*, and can also provide some data to get passed to those callbacks.

An item is printed in the collection by print-collectionitem. By default this returns a string using *item*'s *text* if specified, or else calls a print function on the item's *data*. The *printfunction* will either be the one specified in the item, or else the *print-function* for its parent collection.

The *selected* slot in an item is non-nil if the item is currently selected. The accessor item-selected is provided to access and to set this value.

Example

```
(defun item-callback (data interface)
                (capi:display-message "Item callback: ~S"
                                      data))
              (capi:contain (make-instance
                              'capi:list-panel
                              :items (list
                                        (make-instance
                                        'capi:item
                                        :text "Item"
                                        :data '(some data)
                                        :selection-callback
                                         'item-callback)
                                       "Non-Item 1"
                                       "Non-Item 2")
                              :selection-callback 'main-callback))
See also
             itemp
             collection
             choice
             print-collection-item
```

Generic Function itemp

Package capi

Signature itemp object

Description This is equivalent to

(typep object 'capi:item)

See also item

collection

item-pane-interface-copy-object

Generic Function

Summary Determines what pane-interface-copy-object returns

from a choice.

Signature

item-pane-interface-copy-object item choice interface =>
object, string, plist

Description

The generic function item-pane-interface-copy-object is used by the method of pane-interface-copy-object that specializes on choice to decide what to return.

If only one item is selected, the pane-interface-copyobject method for choice returns what item-pane-interface-copy-object returns for this item. In this case all three of the return values are used.

If multiple items are selected, pane-interface-copyobject applies item-pane-interface-copy-object to each one, and returns a list of the returned objects as the first value, and a concatenation of returned strings (separated by newlines) as the second value. The plist is ignored if the there more than one element.

The default method returns the item and its print representation (using the *print-function* of the choice), and no third return value.

You can define your own methods for item-pane-inter-face-copy-object. This is useful to make active-pane-copy work properly for a choice, in cases where the actual items in the choice are not the objects that are displayed in the choice as far as the user is concerned. For example, you may have a structure

```
(defstruct my-item
  real-object
  color)
```

To give different colors to different lines in a list-panel. In this case pane-interface-copy-object (and hence active-pane-copy when the list-panel is active) will return the my-item structure, while the user will expect the real object. This can be fixed by adding a method:

item-pinboard-object

Class

Summary An item-pinboard-object is a pinboard-object that dis-

plays a single piece of text.

Package capi

See also

Superclasses pinboard-object

item

Description The item-pinboard-object displays an item on a pinboard

layout. It displays the text specified by the item in the usual way (either by the text field, or through printing the data

with the print function).

Example (capi:contain (make-instance

'capi:item-pinboard-object

:text "Hello World"))

(capi:contain (make-instance 'capi:item-pinboard-object

:data :red
:print-function
 'string-capitalize))

pinboard-layout

image-pinboard-object

labelled-arrow-pinboard-object

Class

Package capi

Superclasses arrow-pinboard-object

labelled-line-pinboard-object

Description A subclass of pinboard-object which displays an arrow

and draws a label on it.

Example See labelled-line-pinboard-object.

See also pinboard-layout

labelled-line-pinboard-object

Class

Summary A subclass of pinboard-object which draws a labelled line.

Package capi

Superclasses item-pinboard-object

line-pinboard-object

Subclasses labelled-arrow-pinboard-object

Initargs :text-foreground

A valid color specification, as defined for the graphics-state parameter *foreground*.

:text-background

A valid color specification, as defined for the graphics-state parameter foreground, or

the keyword: background, or nil.

ACCESSORS labelled-line-text-foreground

labelled-line-text-background

Description

A subclass of pinboard-object which displays a line and draws a label in the middle of it.

Note that the label text is inherited from item.

text-foreground defines the color of the label text.

text-background defines the background for the text, which is the color used to draw a filled rectangle in the area of the text before drawing the text. The value :background means use the background of the pinboard-layout of the object. The value nil means do not draw a background rectangle. The default value of text-background is :background.

Example

See also

pinboard-layout

layout

Class

Summary

A layout is a simple pane that positions one or more child

panes within itself according to a layout policy.

Package capi

Superclasses titled-object simple-pane

Subclasses simple-layout

grid-layout pinboard-layout

Initargs :default A flag to mark the default layout for an

interface.

:description The list of the layout's children.

:initial-focus

A child of the layout, or its *name*, specifying where the input focus should be, or nil.

ACCESSORS layout-description

Description The layout's *description* is an abstract description of the children of the layout, and each layout defines its format.

Generally, *description* is a list, each element of which is one of:

a pane

- a slot name, where the name refers to a slot in the layout's interface containing a pane
- a string, where the string gets converted to a title-pane

For grid-layout and its subclasses, elements of *description* can also be nil. See grid-layout for the interpretation of this value.

Setting the layout description causes the layout to translate it, and then to layout the new children, adjusting the size of its parent if necessary.

A number of default layouts are provided which provide the majority of layout functionality that is needed. They are as follows:

simple-layout A layout for one child.

row-layout Lays its children out in a row.

column-layout Lays its children out in a column.

grid-layout Lays its children out in an n by m grid.
pinboard-layout

Places its children where the user specifies.

switchable-layout

Keeps only one of its children visible.

initial-focus specifies which child of the layout has the input focus when the layout is first displayed. Panes are compared by eq or capi-object-name.

Note: for a pinboard-layout, the order of the objects in *description* defines the Z-order, with the first object in the list being at the bottom. That is,

is equivalent to

See also define-layout

manipulate-pinboard

line-pinboard-object

Class

Summary A subclass of pinboard-object which displays a line drawn

between two corners of the area enclosed by the pinboard

object.

Package capi

Superclasses pinboard-object

Subclasses arrow-pinboard-object

right-angle-line-pinboard-object

Initargs :start-x The x coordinate of the start of the line.

:start-y The y coordinate of the start of the line.

:end-x The x coordinate of the end of the line.

:end-y The y coordinate of the end of the line.

Description

start-x, start-y, end-x and end-y default to values computed from the x, y, width and height. They are used to compute the size of the object, and the proper value of x and y. Note that width and height may be larger, for example to accommodate the label in a labelled-line-pinboard-object, and the x and y are adjusted for that.

To change the end points of the line, call move-line.

A complementary class right-angle-line-pinboardobject is provided which draws a line around the edge of the pinboard object.

Example

(capi:contain
 (make-instance)

'capi:line-pinboard-object
:start-x 0 :end-x 100
:start-y 100 :end-y 0))

See also

move-line

pinboard-layout

line-pinboard-object-coordinates

Function

Summary Returns the coordinates of a line-pinboard-object.

Package capi

Signature line-pinboard-object-coordinates object => start-x, start-y,

end-x, end-y

Arguments object A line-pinboard-object.

1 CAPI Reference Entries

Values	start-x	An integer.
	start-y	An integer.
	end-x	An integer.
	end-y	An integer.
Description	The function line-pinboard-object-coordinates returns the start and end coordinates of the line-pinboard-object object.	
See also	move-line	

list-panel	Class
Summary	The class list-panel is a pane that can display a group of items and provides support for selecting items and

performing actions on them. Each item may optionally have

an image.

Package capi

Superclasses choice

simple-pane sorted-object titled-object

Subclasses list-view

multi-column-list-panel

Initargs :right-click-selection-behavior

A keyword or ${\tt nil}$. Controls the behavior on

a right mouse button click.

:color-function

A function designator or mil. Controls item text color on Microsoft Windows, Cocoa and

GTK+.

:alternating-background

A boolean influencing the use of alternating background color on Cocoa and GTK+.

:filter A boolean. The default value is nil.

The following initargs take effect only when *filter* is non-nil.

:filter-automatic-p

A boolean. The default value is t.

:filter-callback

A function designator or the keyword :default, which is the default value.

:filter-change-callback-p

A boolean.

:filter-short-menu-text

A boolean. The default value is mil.

:filter-matches-title

A string, t or nil.

:filter-help-string

A string, t or nil.

:keyboard-search-callback

A function that is used to search for an item when the user types ordinary characters.

Initargs for handling images:

:image-function

Returns an image for an item.

:state-image-function

Returns a state image for an item.

:image-lists

A plist of keywords and image-list objects.

:use-images Flag to specify whether items have images.

Defaults to t.

:use-state-images

Flag to specify whether items have state images. Defaults to nil.

:image-width Defaults to 16.

:image-height Defaults to 16.

:state-image-width

Defaults to *image-width*.

:state-image-height

Defaults to image-height.

Accessors

list-panel-right-click-selection-behavior
list-panel-keyboard-search-callback
list-panel-image-function
list-panel-state-image-function

Description

The class list-panel gains much of its behavior from choice, which is an abstract class that handles items and their selection. By default, a list panel has both horizontal and vertical scrollbars.

The list-panel class does not support the :no-selection interaction style. For a non-interactive list use a displaypane.

To scroll a list-panel, call scroll with scroll-operation: move.

mnemonic-title is interpreted as for menu.

right-click-selection-behavior can take the following values:

Corresponds to the behavior in LispWorks 4.4 and earlier. The data is not passed.

All non-nil values pass the clicked item as data to the pane menu:

:existing-or-clicked/restore/discard

If the clicked item is not already selected, make it be the entire selection while the menu is displayed. If the clicked item is already selected, do not change the selection. If the menu is cancelled, the original selection is restored. If the user chooses an item from the menu, the selection is not restored.

:temporary-selection

A synonym for :existing-orclicked/restore/discard.

:existing-or-clicked/restore/restore

If the clicked item is not already selected, make it be the entire selection while the menu is displayed. If the clicked item is already selected, do not change the selection. If the user chooses an item from the menu and the item's callback does not set the selection then the original selection is restored after the callback. If the callback sets the selection, then this selection remains. The original selection is restored if the user cancels the menu.

:temporary-restore

A synonym for :existing-orclicked/restore/restore.

:clicked/restore/discard

Make the clicked item be the entire selection while the menu is displayed. If the menu is cancelled, the original selection is restored. If the user chooses an item from the menu, the selection is not restored.

:temporary-always

A synonym for :clicked/restore/discard.

:clicked/restore/restore

Make the clicked item be the entire selection while the menu is displayed. If the user chooses an item from the menu and the item's callback does not set the selection then the original selection is restored after the callback. If the callback sets the selection, then this selection remains. The original selection is restored if the user cancels the menu.

:existing-or-clicked/discard/discard

If the clicked item is not already selected, make it be the entire selection while the menu is displayed. If the clicked item is already selected, do not change the selection. The original selection is never restored, regardless of whether the user chooses an item from the menu or cancels the menu.

:discard-selection

A synonym for :existing-orclicked/discard/discard.

:clicked/discard/discard

Make the clicked item be the entire selection. The original selection is never restored, regardless of whether the user chooses an item from the menu or cancels the menu.

:discard-always

A synonym for :clicked/discard/discard.

:no-change

Does not affect the selection, but the clicked item is nonetheless passed as the data.

The default value of right-click-selection-behavior is :no-change.

color-function allows you to control the text colors on Microsoft Windows, Cocoa and GTK+. If *color-function* is non-nil, then it is a function used to compute the text color of each item, with signature

color-function list-panel item state => result

When alternating-background is true, the list panel is drawn with alternating background on Cocoa. On GTK+ it provides a hint, which the theme can override. Experience suggests that theme may draw with alternating background even when alternating-background is false, but when it is true they tend to draw it always. The default value of alternating-background is nil.

state is a keyword representing the state of the item. It can be one of :normal, :selected or :disabled. The value result should be a value suitable for the function convert-color. The pane uses the converted color as the foreground color for the item item. color-function is called while list-panel is being drawn, so it should not do heavyweight computations.

If filter is non-nil, the system automatically adds a filter-ing-layout above the list. The items in the list-panel are filtered by the value in the filtering-layout. Filtering displays only those items whose print representation matches the filter. (The print representation is the result of print-collection-item, and is what the user sees.) Only the items that match, or those that do not match if Exclude is set, are displayed in the list-panel.

Here filtering means mapping over the unfiltered items, collecting each item that matches the current setting in the filter, and then setting the items of the list-panel to the collected items.

For a list-panel with a filter, collection-items returns only the filtered items, and the selection (that is, the result of choice-selection and the argument to (setf choice-selection) index into the filtered items.

Calling (setf collection-items) on a filtered listpanel sets an internal unfiltered list, and then clears the filtering so that all items are visible.

To get and set the unfiltered items, use the accessor list-panel-unfiltered-items. To access the filter-state, use list-panel-filter-state. To access both the unfiltered items and the filter simultaneusly, which is especially useful when setting both of them at the same time, use list-panel-items-and-filter.

filter-automatic-p controls whether the filter automatically does the filtering whenever the text in the filter changes, and filter-callback defines the callback of the filtering-layout.

If filter-automatic-p is t, whenever a change occurs in the filter the list is refreshed against the new value in the filter. The filter-callback (if non-nil) is called with two arguments, the filtering-layout and the list-panel itself, when the user "confirms" (that is, she presses Return or clicks the Confirm button). If filter-automatic-p is false and filter-callback is :default, then the filtering-layout is given a callback that does the filtering when the user "confirms". If filter-automatic-p is false and filter-callback is non-nil, then no filtering is done explicitly, and it is the responsibility of the callback to do any filtering that is required.

filter-matches-title (default t) and filter-help-string (default t) are passed down to the filtering layout through the corresponding filtering-layout initargs:

filter-matches-title:matches-title

filter-help-string :help-string

See filtering-layout for a description of these initargs.

If *filter-short-menu-text* is true, the filter menu has a short title. For example if the filter is set for case-sensitive plain inclusive matching the short label is **PMC**. If *filter-short-menu-text* were false then this label would be **Filter:C**.

keyboard-search-callback should be a function with signature:

keyboard-search-callback pane string position => index, last-match, last-match-reset-time

pane is the list-panel, string is a string to match and position is the item index from which the system thinks that the search should start.

string contains the character that the user typed, appended to the "last match", if there is one. There is a "last match" if the previous call to *keyboard-search-callback* returned it (see below).

index is an index in the collection-items to move to. Apart from an integer inside the items range of the list-panel, this can be nil, which means do nothing, or :no-change, which selects the current item.

last-match is a string that should be recorded as the "last match" (if it is not a string, the "last match" is reset). This is prepended to the character in the next call, if the character is typed before the "last match" is reset.

last-match-reset-time is the time to wait before resetting the "last match", in seconds. Once this time passes, the last match is reset to nil. If last-match-reset-time is nil, the default value (which defaults to 1) is used. This default value can be changed by set-list-panel-keyboard-search-reset-time.

You can simplify the implementation of *keyboard-search-call-back* by using list-panel-search-with-function.

As a special case, passing :keyboard-search-callback t tells CAPI to use its own internal search mechanism in preference to the native one. That can be useful on GTK+, where the default is to use the native search mechanism (for GTK+ versions after 2.4).

The *image-function* is called on an item to return an image associated with the item. It can return one of the following:

A pathname or string

This specifies the filename of a file suitable for loading with load-image. Currently this must be a bitmap file.

A symbol

The symbol must have been previously registered by means of a call to registerimage-translation. It can also one of the following symbols, which map to standard images: :std-cut, :std-copy, :std-paste, :std-undo, :std-redo, :std-delete, :std-file-new, :std-file-open, :std-file-save, :std-print, :std-print-pre, :std-properties, :std-help, :std-find and :std-replace. On Microsoft Windows, the following symbols are also recognized. They map to view images: :view-large-icons, :view-small-icons, :view-list, :view-details. :view-sort-name. :view-sort-

size, :view-sort-date, :view-sort-

type, :view-parent-folder, :view-netconnect, :view-net-disconnect and
:view-new-folder.

Also on Microsoft Windows, these symbols are recognized. They map to history images: :hist-back, :hist-forward, :hist-favorites, :hist-addtofavorites and :hist-viewtree.

An image object, as returned by load-image.

An image locator object

This allowing a single bitmap to be created which contains several button images side by side. See make-image-locator for more information. On Microsoft Windows, it also allows access to bitmaps stored as resources in a DLL.

An integer

This is a zero-based index into the list panel's image lists. This is generally only useful if the image list is created explicitly. See image-list for more details.

The *state-image-function* is called on an item to determine the state image: an additional optional image used to indicate the state of an item. It can return one of the above, or nil to indicate that there is no state image.

If *image-lists* is specified, it should be a plist containing the following keywords as keys. The corresponding values should be <code>image-list</code> objects.

:normal

Specifies an image-list object that contains the item images. The *image-function* should return a numeric index into this image-list.

:state

Specifies an image-list object that contains the state images. The *state-image-function* should return a numeric index into this image-list.

Notes

If you use filter:

- You should not rely on the element-parent of the list-panel, because it is implemented by wrapping some layouts around the list-panel.
- **2.** The filter is actually a filtering layout, so it has the same interactive semantics as filtering-layout.

Example

```
(setq list (capi:contain
            (make-instance 'capi:list-panel
                           :items '(:red :blue :green)
                           :selected-item :blue
                           :print-function
                           'string-capitalize)))
(capi:apply-in-pane-process
list #'(setf capi:choice-selected-item) :red list)
(capi:apply-in-pane-process
list #'(setf capi:choice-selected-item) :green list)
(capi:contain (make-instance
               'capi:list-panel
               :items '(:red :blue :green)
               :print-function 'string-capitalize
               :selection-callback
                 #'(lambda (data interface)
                           (capi:display-message
                            "~S" data))))
```

This example illustrates the use of :right-click-selection-behavior:

```
(capi:define-interface click ()
                ((keyword :initarg :right-click-selection-behavior))
                (:panes
                 (list-panel
                 capi:list-panel
                  :items '("foo" "bar" "baz" "quux")
                 :visible-min-height '(:character 4)
                  :pane-menu 'my-menu
                  :interaction :multiple-selection
                  :right-click-selection-behavior keyword)))
              (defun my-menu (pane data x y)
                (declare (ignore pane x y))
                (make-instance 'capi:menu
                               :items (list "Hi There"
                                            "Here's the data:"
                                            data)))
              (capi:display
                 (make-instance 'click
                                :right-click-selection-behavior
                    :clicked/restore/restore))
             See also the example in examples/capi/choice/list-
             pane-pane-menu.lisp.
             There are further examples in the directory
             examples/capi/choice/.
             This example illustrates the use of color-function:
             examples/capi/applications/simple-symbol-
             browser.lisp
See also
             button-panel
```

list-panel-enabled

Generic Function

Summary Gets or sets the enabled state of a list-panel.

Package capi

1 CAPI Reference Entries

Signature list-panel-enabled list-panel => enabledp

Signature (setf list-panel-enabled) enabledp list-panel => enabledp

Arguments *list-panel* A list-panel.

Values enabledp A boolean.

Description The generic function list-panel-enabled determines

whether list-panel is currently enabled. It is equivalent to

the simple-pane accessor simple-pane-enabled.

The generic function (setf list-panel-enabled) enables *list-panel* when *enabledp* is true, and disables it otherwise. It is

equivalent to (setf simple-pane-enabled).

See also simple-pane

list-panel-filter-state

Generic Function

Summary Accesses the state of the filter in a filtered list-panel.

Signature list-panel-filter-state list-panel => filter-state

(setf list-panel-filter-state) new-state list-panel

Description The generic function list-panel-filter-state accesses

the state of the filter in a filtered list-panel (that is, a list-

panel created with filter t).

list-panel-filter-state returns the state of the filter in *list-panel*. The return value *filter-state* is the same type as the

state that is used in filtering-layout.

(setf list-panel-filter-state) sets the filter in *list-panel*, filters the unfiltered items and displays those that match the *new-state*. The *new-state* has the same semantics as the *new-value* of (setf filtering-layout-state). It can be

a result of a call to list-panel-filter-state or to filter-ing-layout-state (on a filtering-layout), or a string (meaning plain match, case-insensitive), or nil (meaning match everything).

On an unfiltered list-panel list-panel-filter-state returns nil, and (setf list-panel-filter-state) does nothing.

See also

list-panel
list-panel-unfiltered-items
filtering-layout

list-panel-items-and-filter

Function

Summary Accesses the unfiltered items and filter in a list-panel

Signature

list-panel-items-and-filter list-panel

(setf list-panel-items-and-filter) (values items filter) list-panel

The function list-panel-items-and-filter accesses the unfiltered items and the filter in the list panel *list-panel* simultanously. It is especially useful for setting the filter and the items without flickering.

list-panel-items-and-filter returns the items and filter in *list-panel* as multiple values. It is equivalent to

but is more efficient.

(setf list-panel-items-and-filter) takes the items and filters as two values and sets them in *list-panel*:

```
(setf (list-panel-items-and-filter list-panel)
     (values new-items new-filter))
```

ends up in the same state as

(progn

(setf (list-panel-unfiltered-items list-panel) new-items)
(setf (list-panel-filter-state list-panel) new-filter))

but the latter form will filter the *new-items* with the old filter and display the result, and then filter the *new-items* again with the *new-filter*, whereas (setf list-panel-items-and-filter) filters the *new-items* just once, with the *new-filter*.

See also

list-panel

list-panel-filter-state
list-panel-unfiltered-items

list-panel-search-with-function

Function

Summary Searches a list-panel.

Signature list-panel-search-with-function list-panel function arg &key

start-index wrap-around reset-time

Arguments *list-panel* A list-panel.

function A function taking two arguments. The first

is arg, the second is an item in list-panel.

arg Any Lisp object.

start-index An integer, default 0.

reset-time A real number. The default is an internal

value which can be set by set-list-panel-

keyboard-search-reset-time.

wrap-around A boolean, default t.

Description The function list-panel-search-with-function searches

list-panel using function. list-panel-search-with-function is intended to simplify the implementation of the key-

board-search-callback of list-panel.

list-panel-search-with-function searches *list-panel* for a match. It applies *function* to each item and *arg*, until *function* returns non-nil

When *function* returns non-nil, *list-panel-search-with-function* returns three values: the index of the item, *arg*, and *reset-time*.

The search starts at *start-index* if supplied, and at 0 otherwise. When the search reaches the end of the list panel and it did not start from 0, it wraps around to the beginning, unless *wrap-around* is supplied as nil. The default value of *wrap-around* is t.

Example

```
(defun string-equal-prefix (string item)
  (let* ((start 0)
         (len (length item))
         (end (+ start (length string))))
    (and (>= len end )
         (string-equal string item
                       :start2 start
                       :end2 end))))
(capi:contain
 (make-instance
  'capi:list-panel
  :items '("ae" "af" "bb" "cc")
  :kevboard-search-callback
 #'(lambda (pane string position)
      (capi:list-panel-search-with-function
      pane
       'string-equal-prefix ; or 'string-not-greaterp
      string
      :start position
       :reset-time 1
       :wrap-around t))))
```

Pressing "a" slowly cycles between "ae" and "af". Running the same example with string-not-greaterp instead causes "a" to cycle around all of the items.

```
See also list-panel set-list-panel-keyboard-search-reset-time
```

list-panel-unfiltered-items

Generic Function

Summary Accesses the unfiltered items of a filtered list-panel.

Signature list-panel-unfiltered-items list-panel

(setf list-panel-unfiltered-items) new-items list-panel

Description The generic function list-panel-unfiltered-items

accesses the unfiltered items of a filtered list-panel (that is,

a list-panel created with: filter t).

list-panel-unfiltered-items returns the unfiltered items of *list-panel* (that is all of them, as opposed to the accessor collection-items, which returns only those items that match the filter).

(setf list-panel-unfiltered-items) sets the items of list-panel without affecting the filter (as opposed to (setf collection-items) which resets the filter). The items are then filtered, and only those that match the filter are displayed.

list-panel-unfiltered-items behaves the same as collection-items when called on an unfiltered list-panel.

See also list-panel

list-panel-items-and-filter
list-panel-filter-state

list-view Class

Summary The list view pane is a choice that displays its items as icons

and text in a number of formats.

Note: list-view is not implemented on Cocoa

Package capi

Superclasses list-panel

Initargs :view Specifies which view the list view pane

shows. The default is :icon.

:subitem-function

Returns additional information to be dis-

played in report view.

:subitem-print-functions

Used in report view to print the additional

information.

:image-function

Returns an image for an item

:state-image-function

Returns a state image for an item.

:image-lists

A plist of keywords and image-list

objects.

:columns Defines the columns used in report view

:auto-reset-column-widths

Determines whether columns automatically

resize. Defaults to :all.

:auto-arrange-icons

Determines whether icons are automatically

arranged to fit the size of the window.

:use-large-images

Indicates whether large icons will be used (generally only if the icon view will be

used). Defaults to t.

:use-small-images

Indicates whether small icons will be used. Defaults to t.

:use-state-images

Indicates whether state images will be used. Defaults to nil.

:large-image-width

Width of a large image. Defaults to 32.

:large-image-height

Height of a large image. Defaults to 32.

:small-image-width

Width of a small image. Defaults to 16.

:small-image-height

Height of a small image. Defaults to 16.

:state-image-width

Width of a state image. Defaults to *small-image-width*.

:state-image-height

Height of a state image. Defaults to *small-image-height*.

Accessors

list-view-view

list-view-subitem-function

list-view-subitem-print-functions

list-view-image-function

list-view-state-image-function

list-view-columns

list-view-auto-reset-column-widths

list-view-auto-arrange-icons

Description

The list view inherits its functionality from choice. In many ways it may be regarded as a kind of enhanced list panel, although its behavior is not identical. It supports single selection and extended selection interactions.

The list view displays its items in one of four ways, determined by the value in the *view* slot. An application may use the list view pane in just a single view, or may change the view between all four available views using (setf list-view-view).

See the notes below on using both large and small icon views.

In all views, the text associated with the item (the label) is returned by the *print-function*, as with any other choice.

- The icon view :icon
 - In this view, large icons are displayed, together with their label, positioned in the space available. See also *auto-arrange-icons*, below.
- The small icon view : small-icon
 In this view, small icons are displayed, together with their label, positioned in the space available. See also auto-arrange-icons, below.
- The list view :list
 In this view, small icons are displayed, arranged in vertical columns.
- The report view :report

In this view, multiple columns are displayed. A small icon and the item's label is displayed in the first column. Additional pieces of information, known as subitems, are displayed in subsequent columns.

To use the view :report, columns must specify a list of column specifiers. Each column specifier is a plist, in which the following keywords are valid:

:title The column heading.

:width The width of the column in pixels. If this

keyword is omitted or has the value nil, the width of the column is automatically calculated, based on the widest item to be dis-

played in that column.

:align May be :left, :right or :center to indi-

cate how items should be aligned in this column. The default is :left. Only left

alignment is available for the first column.

If auto-arrange-icons is true, then the icons are automatically arranged to fit the size of the window when the view is showing :icon or :small-icon. The default value of auto-arrange-icons is nil.

The *subitem-function* is called on the item to return subitem objects that represent the additional information to be displayed in the subsequent columns. Hence, *subitem-function* should normally return a list, whose length is one less than the number of columns specified. Each subitem is then printed in its column using the appropriate subitem print function. *subitem-print-function* may be either a single print function, to be used for all subitems, or a list of functions: one for each subitem column.

Note that the first column always contains the item label, as determined by the *choice-print-function*.

The *image-function* is called on an item to return an image associated with the item. It can return one of the following:

A pathname or string

This specifies the filename of a file suitable for loading with load-image. Currently this

must be a bitmap file.

A symbol The symbol must have been previously reg-

istered by means of a call to register-

image-translation.

An image object

As returned by load-image.

An image locator object

Allowing a single bitmap to be created which contains several button images side by side. See make-image-locator for more information. On Microsoft Windows, this also allows access to bitmaps stored as resources in a DLL.

An integer

This is a zero-based index into the list view's image list. This is generally only useful if the image list is created explicitly. See image-list for more details.

The *state-image-function* is called on an item to determine the state image, an additional optional image used to indicate the state of an item. It can return one of the above, or nil to indicate that there is no state image. State images may be used in any view, but are typically used in the report and list views.

If *image-lists* is supplied, it should be a plist containing the following keywords as keys. The corresponding values should be <code>image-list</code> objects.

:normal

Specifies an image-list object that contains the large item images. The *image-function* should return a numeric index into this image-list.

:small

Specifies an image-list object that contains the small item images. The *image-function* should return a numeric index into this image-list.

:state

Specifies an image-list object that contains the state images. The *state-image-function* should return a numeric index into this image-list If both the large icon view (icon view) and one or more of the small icon views (small icon view, list view, report view) are to be used, special considerations apply.

The image lists must be created explicitly, using the :image-lists initarg, and the image-function must return an integer. Care must be taken to ensure that corresponding images in the :normal and :small image lists have the same numeric index.

Returning pathnames, strings or image-locators from the image function cause the CAPI to create the image-lists automatically; however, if large and small icon views are mixed, this will lead to incorrect icons (or no icons) being displayed in one or other view.

Notes

- 1. list-view is not implemented on Cocoa.
- 2. For some applications multi-column-list-panel will suffice instead of list-view.

See also

image-list
list-panel

make-image-locator

multi-column-list-panel

listener-pane Class

Package capi

Superclasses interactive-pane

Description

A listener pane is an editor pane that accepts Lisp forms, entered by the user at a prompt, which it then evaluates. All of the output that is sent to *standard-output* is sent to the listener, and finally the results of the evaluation are displayed.

Example (capi:contain (make-instance 'capi:listener-pane)

:best-width 300 :best-height 200)

See also collector-pane

interactive-pane

listener-pane-insert-value

Function

Summary Evaluates a form and inserts the result in a listener-pane.

Package capi

Signature listener-pane-insert-value pane form

Arguments pane A listener-pane.

form A Lisp form.

Description The function listener-pane-insert-value evaluates the

form form and inserts the result in the listener-pane pane, as if it resulted from user input. The result is printed, and the values of the history variables *, **, ***, /, //, and /// are

set.

listener-pane-insert-value may be called in any pro-

cess.

Multiple values in the result of evaluating form are not

supported: the first value only is inserted in pane

See also interactive-pane-execute-command

load-cursor Function

Summary Loads a cursor.

Package capi

1 CAPI Reference Entries

Signature load-cursor filename-or-list => cursor

Arguments filename-or-list A string or a list.

Values *cursor* A cursor object.

Description

The function load-cursor loads a cursor from your cursor file, or loads a built-in cursor. It returns a cursor object which can be supplied as the value of the simple-pane:cursor initarg.

The cursor object can also be set with (setf simple-pane-cursor) to change a pane's cursor. This must be done in the process of the pane's interface.

If *filename-or-list* is a string, then it names a file which should be in a suitable format for the platform, as follows:

Microsoft Windows

.cur or .ani format.

Cocoa TIFF format.

GTK+ Any image format that load-image sup-

ports.

Note: The image can be of any dimension, but it will be clipped to what the server thinks is an appropriate size, 32x32 or 16x16. Using large images would waste space, because the image would still be in memory.

The file is loaded at the time load-cursor is called, so the cursor object does not require the file at the time the cursor is displayed. The cursor object survives saving and delivering the image.

If *filename-or-list* is a list then it names a file or a built-in cursor to be loaded for a particular library, optionally together with arguments to be passed to the library. It should be of the form:

```
((libname_1 filename_1 arg_1a arg_1b ...)
(libname_2 filename_2 arg_2a arg_2b ...)
...
```

where <code>libname_n</code> is a keyword naming a supported library such as <code>:cocoa</code>, <code>:win32</code> or <code>:gtk</code> (see <code>default-library</code> for the values) and <code>filename_n</code> is either a string naming the cursor file to load for this library or a keyword naming one of the built-in cursors. <code>arg_na</code>, <code>arg_nb</code> and so on are library specific arguments. Currently these are not used on Microsoft Windows. Hotspot keyword arguments <code>:x-hot</code> and <code>:y-hot</code> are supported on Cocoa and GTK+ as in the example below. They specify the hotspot of the cursor. The values must be integers inside the image dimensions, that is they satisfy:

```
(and (> image-width x-hot -1)
      (> image-height y-hot -1))
```

On GTK+ the library specific arguments also include the keywords: transparent-color-index and:type, which are passed to read-external-image. Note that supplying the transparent-color-index allows making a useful cursor with a simple format image file which does not have transparency.

Example

This example loads a standard Microsoft Windows cursor file:

```
(setq cur1 (capi:load-cursor "arrow 1"))
```

This example loads a standard Windows cursor file, and on Motif uses one of the built-in cursors:

This example loads a horizontal double-arrow on Windows, and a vertical double-arrow on Motif:

This example loads a custom .cur file:

In this extended example, firstly we load a custom cursor for two platforms:

Now we display a pane with the custom cursor loaded above:

We can remove the custom cursor:

```
(capi:apply-in-pane-process
  oo
  (lambda ()
     (setf (capi:simple-pane-cursor oo)
          :default)))
```

And we can restore the custom cursor:

See also simple-pane

load-sound Function

Summary Converts data to a loaded sound object on Microsoft Win-

dows and Cocoa.

Package capi

Signature load-sound source &key owner => sound

Arguments source A pathname designator or an array returned

by read-sound-file.

owner A CAPI interface, or nil.

Values sound An array of element type (unsigned-byte

8).

Description The function load-sound converts *source* into a loaded sound

which can be played by play-sound.

source can be a pathname designator or an array returned by read-sound-file.

owner should be a CAPI interface object, or nil which means that the sound's owner is the current top level interface.

The loaded sound sound will be unloaded (freed) automatically when its owner is destroyed. To create a sound that is never unloaded, pass the screen as the argument owner.

Notes

1. The array *sound* contains the contents of the file. Its bytes are interpreted by the OS functions, so the format can be whatever they can deal with, for example WAV on

Microsoft Windows. The fact that this date is represented as an (unsigned-byte 8) array in Lisp does not constrain the output size.

2. load-sound is not implemented on GTK+ and Motif.

See also free-sound

play-sound

read-sound-file

locate-interface

Generic Function

Summary Finds an interface of a given class that matches supplied

initargs.

Package capi

Signature locate-interface class-spec &rest initargs

&key screen no-busy-interface &allow-other-keys => interface

Arguments class-spec A specifier for a subclass of interface.

initargs Initialization arguments for class-spec.

screen A screen or nil.

no-busy-interface

A boolean, defaulting to mil.

Values interface An interface of class class-spec, or nil.

Description The generic function locate-interface finds an interface of

the class specified by class-spec that matches initargs and

screen.

First, locate-interface finds all interfaces of the class specified by *class-spec* by calling collect-interfaces with *class-spec* and *screen*. The first of these which match *initargs* (by interface-match-p) is returned.

If there is no match, then locate-interface finds the first of these which can be reused for *initargs*, by interface-reuse-p. This reusable interface is reinitialized by reinitialize-interface and returned.

no-busy-interface controls the use of the busy cursor during reinitializing of a reusable interface. If *no-busy-interface* is nil, then this interface has the busy cursor during reinitialization. If *no-busy-interface* is true, then there is no busy cursor.

If no matching or reusable interface is found, or if global interface re-use is disabled by (setf reuse-interfaces-p), then locate-interface returns nil.

See also

collect-interfaces
interface-match-p
interface-reuse-p
reuse-interfaces-p

lower-interface Function

Summary The lower-interface function pushes the window contain-

ing a specified pane to the back of the screen.

Package capi

Signature lower-interface pane

Description This pushes the window containing *pane* to the back of the

screen. To bring it back use raise-interface, and to iconify

it use hide-interface.

See also hide-interface

interface

lower-interface raise-interface quit-interface

make-container

Generic Function

Summary The generic function make-container creates a container for

a specified element.

Package capi

Signature make-container element &rest interface-args

Description This creates a container for *element* such that calling display

on it will produce a window containing *element* on the screen. It will produce a container for any of the following classes of

object:

simple-pane layout interface

pinboard-object

menu

menu-item

menu-component

list

In the case of a list, the CAPI tries to see what sort of objects they are and makes an appropriate container. For instance, if they were all simple panes it would put them into a column layout.

The arguments *interface-args* will be passed through to the make-instance of the top-level interface, assuming that pane is not a top-level interface itself.

The complementary function contain uses make-container to create a container for an element which it then displays.

Example (capi:display (capi:make-container

(make-instance

'capi:text-input-pane)))

See also contain

display interface element

make-docking-layout-controller

Function

Package capi

Signature make-docking-layout-controller => controller

Values controller A docking layout controller.

Description The function make-docking-layout-controller returns a

docking layout controller object for use as the controller ini-

targ in docking-layout.

Layouts which share a docking layout controller are known as a Docking Group. See docking-layout for information

about Docking Groups.

See also docking-layout

make-foreign-owned-interface

Function

Summary Creates a dummy interface which allows another

application's window to be the owner of a CAPI dialog.

Package capi

Signature make-foreign-owned-interface &key handle name => interface

1 CAPI Reference Entries

Arguments handle A Microsoft Windows hwnd.

name A string naming interface.

ValueS interface An instance of foreign-owned-interface.

Description

The function make-foreign-owned-interface creates an instance of foreign-owned-interface. *interface* can be used as the *owner* argument when displaying a dialog. For information about dialog owners, see the "Prompting for Input" chapter in the *CAPI User Guide*.

handle must be supplied and is the window handle (Windows hwnd) of a window in some application. For a CAPI window this window handle can be obtained by simple-pane-handle. For non-CAPI applications, the method of finding the window handle will depend on the language and the way windows are represented, so you should consult the appropriate documentation.

name becomes the name of *interface*, and has no other meaning.

make-foreign-owned-interface is implemented only on Microsoft Windows.

Example

This example shows how a CAPI window can be the owner of a dialog in another LispWorks image.

Start LispWorks for Windows.

- 1. In the Listener, do Tools > Interface > Listen. This puts the Listener interface in the value of *.
- In the Listener enter (capi:simple-pane-handle *).
 The returned value is the window handle, it should be an integer. Denote this value by hwnd.

Start another LispWorks for Windows image (do not quit the first image). In the Listener of this second LispWorks image:

- Enter (setq foi (capi:make-foreign-owned-interface :handle hwnd)).
- Enter (capi:prompt-for-color "Color?" :owner foi).

Now note that the Color dialog is owned by the Listener of the first LispWorks image.

make-general-image-set

Function

Summary Creates an image-set object.

Package capi

Signature make-general-image-set &key image-count width height id =>

image-set

Arguments *image-count* An integer.

width An integer or nil.

height An integer or nil.

id A pathname, string or symbol.

Values image-set An image-set object.

Description The make-general-image-set function creates an image-set object that refers to an image or a file containing an image.

id is a pathname or string identifying an image file, or a symbol previously registered with register-image-translation.

width and height are the dimensions of a single sub-image within the main image, and image-count specifies the number of sub-images in the image.

1 CAPI Reference Entries

Example See the files

examples/capi/choice/tree-view.lisp

examples/capi/choice/extended-selection-tree-

view.lisp

examples/capi/elements/toolbar.lisp

See also image-set

make-resource-image-set

make-icon-resource-image-set

Function

Summary Constructs an image set object identifying a icon resource in a

Windows DLL.

Package capi

Signature make-icon-resource-image-set &key image-count width height

library id => image-set

Arguments *image-count* An integer.

width An integer.

height An integer.

library A string.

id A string or an integer.

Values image-set An image-set object.

Description The function make-icon-resource-image-set constructs

an image set object that identifies an image stored as a icon

resource in a DLL on Microsoft Windows.

width and height are the dimensions of a single sub-image within the main image, and image-count specifies the number

of sub-images in the image.

library should be a string specifying the name of the DLL.

id should be either an integer which is the resource identifier

of the icon, or a string naming the icon resource.

Notes make-icon-resource-image-set is only available in Lisp-

Works for Windows.

See also image-set

make-general-image-set

make-image-locator

Function

Summary Creates an image locator object to use with toolbars, list

views and tree views.

Package capi

Signature make-image-locator &key image-set index

Description The function make-image-locator creates an image locator

object for use with toolbars, list views, and tree views. It is used to specify a single sub-image from a larger image that contains many images side by side. It is also useful for accessing some images that can only be specified by means of

image sets.

See also image-set

make-menu-for-pane

Function

Summary Makes a menu or a menu-component for a pane.

Package capi

Signature make-menu-for-pane pane items &key title menu-name

component-p => menu

1 CAPI Reference Entries

Arguments pane A pane.

items A list of menu-objects.

title A string or nil.

menu-name A string or nil.

component-p A boolean.

Values menu A menu or a menu-component.

Description The function make-menu-for-pane makes a menu or a menu-component for the pane pane with the items specified by

items.

items should be a list in which each element is a menu-item,

menu-component or menu.

title and menu-name provide a title and name for menu. title

and menu-name both default to mil.

If component-p is true, then make-menu-for-pane creates a menu-component rather than a menu. The default value of

component-p is nil.

menu is set up so that by default each callback inside it is done on the pane pane itself. This is the useful feature of make-menu-for-pane because it avoids the need to set up

items to do their callbacks on pane explicitly.

Note that this is merely the default behavior. You can specify different callback behavior on a per-item basis, using *setup-callback-argument* and *callback-data-function* (see menu-object), *callback-type* (see callbacks) and *data* for menu-

item (see item).

See also make-pane-popup-menu

pane-popup-menu-items

make-pane-popup-menu

Generic Function

Summary Generates a popup menu or menu-component.

Package capi

Signature make-pane-popup-menu pane interface &key title menu-name

component-p => menu

Arguments pane A pane in an interface.

interface An interface or nil.

title A string or nil.

menu-name A string or nil.

component-p A boolean.

Values menu A menu or a menu-component.

Description The generic function make-pane-popup-menu generates a

popup menu for pane.

interface can be nil if pane has already been created, in which case the interface of pane is used (obtained by the element accessor element-interface).

title and menu-name provide a title and name for menu. title and menu-name both default to mil.

If component-p is true, then make-pane-popup-menu creates a menu-component rather than a menu. The default value of component-p is nil.

Example This code makes an interface with two graph-panes. The

initialize-instance method uses make-pane-popupmenu to add a menu to the menu bar from which the user can

perform operations on the graphs.

Note that, because make-pane-popup-menu calls make-menu-for-pane to make each menu, the callbacks in the menus are automatically done on the appropriate graph.

```
(capi:define-interface gg ()
  ()
  (:panes
   (gl capi:graph-pane)
   (g2 capi:graph-pane))
  (:layouts
   (main-layout capi:column-layout '(g1 g2)))
  (:menu-bar)
  (:default-initargs
   :visible-min-width 200
   :visible-min-height 300))
(defmethod initialize-instance :after ((self gg)
                                        &key)
  (with-slots (q1 q2) self
    (setf
     (capi:interface-menu-bar-items self)
     (append
      (capi:interface-menu-bar-items self)
      (list
       (make-instance
        'capi:menu
        :title "Graphs"
        :items
        (list
         (capi:make-pane-popup-menu
          g1 self :title "graph1")
         (capi:make-pane-popup-menu
          g2 self :title "graph2")))))))
(capi:display (make-instance 'gg))
```

310

See also

make-menu-for-pane

make-resource-image-set

Function

Summary Constructs an image set object identifying a bitmap resource

in a Windows DLL.

Package capi

Signature make-resource-image-set &key image-count width height library

id => image-set

Arguments *image-count* An integer.

width An integer.
height An integer.
library A string.

id A string or an integer.

Values image-set An image-set object.

Description The function make-resource-image-set constructs an

image set object that identifies an image stored as a bitmap

resource in a DLL on Microsoft Windows.

width and height are the dimensions of a single sub-image within the main image, and image-count specifies the number

of sub-images in the image.

library should be a string specifying the name of the DLL.

id should be either an integer which is the resource identifier

of the bitmap, or a string naming the bitmap resource.

Notes make-resource-image-set is only available in LispWorks

for Windows.

See also image-set

make-icon-resource-image-set

make-general-image-set

make-scaled-general-image-set

Function

Summary Constructs an image set object which scales images in

another image set on Windows.

Package capi

Signature make-scaled-general-image-set &key width height id image-

count => image-set

Arguments *width* An integer.

height An integer.

id A pathname, string or symbol.

i*mage-count* An integer.

Values image-set An image-set object.

Description The function make-scaled-general-image-set constructs

an image set that provides scaled images based on an image-

set object constructed from id as if by make-general-

image-set.

width and height are the dimensions of a single sub-image within the main image, and image-count specifies the number of sub-images in both images. That is, the sub-images are

scaled to this size.

The default value of *image-count* is 1.

Notes make-scaled-general-image-set is only available in Lisp-

Works for Windows.

See also image-set

make-general-image-set

make-scaled-image-set

Function

Summary Creates an image set by scaling the images of another image

set on Windows.

Package capi

Signature make-scaled-image-set &key image-count width height base-

image-set => image-set

Arguments *image-count* An integer.

width An integer.height An integer.

base-image-set An image-set object.

Values image-set An image-set object.

Description The function make-scaled-image-set constructs an image

set that provides scaled images based on an existing image

set object base-image-set.

width and height are the dimensions of a single sub-image within the main image. That is, the sub-images in base-image-set are scaled to this size to produce the sub-images of image-

set.

image-count specifies the number of sub-images in the image. It is unspecified what happens if *image-count* is different from

the image count in base-image-set.

Notes make-scaled-image-set is only available in LispWorks for

Windows.

See also image-set

make-general-image-set

make-sorting-description

Function

Summary Makes a sort description suitable for use in a sorted-

object.

Package capi

Signature make-sorting-description &key type key sort reverse-sort sort-

function => sorting-description

Arguments *type* A Lisp object naming the type of sorting.

key A function of one argument.

sort A function of two arguments.

reverse-sort A function of two arguments.

sort-function A sorting function.

Description The function make-sorting-description makes a sort

description object that can be used as one of the

sort-descriptions in a sorted-object such as a list-panel.

type is a name that should be unique amongst the sort-descrip-

tions of a sorted-object.

key is a function that is passed to sort-function as its : key

argument. The default value of key is identity.

sort is a predicate function that is passed to sort-function to

compare pairs of items.

reverse-sort is a predicate function that is passed to

sort-function for reverse sorting.

sort-function is the function that is called to actually do the

sorting. Its signature is

sort-function items predicate &key key

The default value of sort-function is sort.

```
Example
              (setq lp
                    (capi:contain
                     (make-instance
                      'capi:list-panel
                      :items '("Apple"
                               "Orange"
                               "Mangosteen"
                               "Pineapple")
                      :visible-min-height '(:character 5)
                      :sort-descriptions
                      (list (capi:make-sorting-description
                             :type :length
                             :sort
                             #'(lambda (x y)
                                  (> (length x) (length y)))
                             :reverse-sort
                             #'(lambda (x y)
                                  (< (length x) (length y))))</pre>
                             (capi:make-sorting-description
                             :type :alphabetic
                             :sort 'string-greaterp
                             :reverse-sort 'string-lessp)))))
              (capi:sorted-object-sort-by lp :length)
              (capi:sorted-object-sort-by lp :alphabetic)
See also
              sort-object-items-by
              sorted-object
              sorted-object-sort-by
```

manipulate-pinboard

Generic Function

Summary Adds or removes one or more pinboard-objects on a pin-

board.

Package capi

Signature manipulate-pinboard pinboard-layout pinboard-object action

&key position

Arguments pinboard-layout A pinboard-layout.

pinboard-object A pinboard-object to be added, or (with

action: add-many) a list of pinboard-

objects to be added.

With action :delete-if, pinboard-object can also be a function of one argument, for mul-

tiple deletion.

action One of :add, :add-top, :add-bottom,

:add-many or :delete. Can also be :delete-if, for multiple deletion.

position One of :top or :bottom, or a non-negative

integer.

Description

The generic function manipulate-pinboard adds pinboard-object to pinboard-layout, or removes one or more pinboard-objects from pinboard-layout. These operations can also be effected using (setf layout-description), but manipulate-pinboard is much more efficient and produces a better display.

If action is :add, then the pinboard-object is added according to the value of position:

:top On top of the other pinboard objects.

:bottom Below the other pinboard objects.

An integer At index *position* in the sequence of pinboard

objects, where 0 is the index of the topmost pinboard object. Values of *position* greater than the number of pinboard objects are

interpreted as :bottom.

action : add-top is the same as passing action : add and position : top.

action: add-bottom is the same as passing action: add and position: bottom.

action: add-many is like calling the function with action: add several times, but is more efficient. The value of pinboard-object must be a list of pinboard-objects, each of which is added at the specified position, as for: add.

action :delete deletes the pinboard-object pinboard-object from pinboard-layout.

When action is :delete-if, pinboard-object should be a function which takes one argument, a pinboard-object. This function is applied to each pinboard-object in pinboard-layout and each object for which it returns true is deleted from pinboard-layout.

Notes

You can control automatic resizing of *pinboard-object* using set-object-automatic-resize.

```
Example
              (setq pl
                    (capi:contain
                     (make-instance 'capi:pinboard-layout
                                    :visible-min-height 500
                                    :visible-min-width 200)))
             Add some pinboard-objects:
              (capi:apply-in-pane-process
              pl #'(lambda (pp)
                      (dotimes (y 10)
                        (let ((yy (* y 40)))
                          (capi:manipulate-pinboard
                           рp
                           (make-instance 'capi:line-pinboard-object
                                          :start-x 4 :start-y yy
                                         :end-x 54 :end-y (+ 6 yy))
                           :add-top)
                          (capi:manipulate-pinboard
                           рp
                           (make-instance 'capi:pinboard-object
                                          :x 4 :y (+ 20 yy)
                                          :width 50 :height 6
                                          :graphics-args
                                          '(:background :red))
                           :add-top))))
              p1)
```

```
Remove some pinboard-objects:
```

```
(capi:apply-in-pane-process
              pl
              #'(lambda (pp)
                   (dotimes (y 15)
                     (let ((po (capi:pinboard-object-at-position pp
                                                                 (* y
             30))))
                       (when po (capi:manipulate-pinboard pp
                                                          :delete)))))
              (1g
             Remove all line-pinboard-objects:
              (capi:apply-in-pane-process
              pl 'capi:manipulate-pinboard pl
              #'(lambda (x)
                   (typep x 'capi:line-pinboard-object))
              :delete-if)
See also
             pinboard-layout
             set-object-automatic-resize
```

map-collection-items

Generic Function

Summary The generic function map-collection-items calls a speci-

fied function on all the items in a collection.

Package capi

Signature map-collection-items collection function &optional collect-

results-p

Arguments collection A collection.

function A function designator for a function of one

argument.

collect-results-p A generalized boolean.

Description Calls function on each item in the collection by calling the col-

lection's items-map-function. If collect-results-p is true, the

results of these calls are returned in a list.

Example (setq collection (make-instance 'capi:collection

:items '(1 2 3 4 5)))

(capi:map-collection-items collection

'princ-to-string t)

See also collection

choice

map-pane-children

Generic Function

Summary Calls a function on each of a pane's children.

Package capi

Signature map-pane-children pane function &key visible test reverse

Arguments pane A CAPI pane.

function A function of one argument.

visible A boolean. The default value is nil.

test A function of one argument, or nil. The

default is nil.

reverse A boolean. The default value is nil.

Description The function map-pane-children applies function to pane's

immediate children.

If *visible* is true, then *function* is applied only to the visible children.

If *test* is non-nil, it is a function which is applied first to each child, and only those for which *test* returns a true value are then passed to *function*.

1 CAPI Reference Entries

If *reverse* is non-nil, the order in which the children are processed is reversed.

Example

This example constructs a pinboard containing random ellipses. A repainting function is mapped over them, restricted to those with width greater than height.

```
(defun random-color ()
                (aref #(:red :blue :green :yellow :cyan
                        :magenta :pink :purple :black :white)
                      (random 10)))
              (defun random-origin ()
                (list (random 350) (random 250)))
              (defun random-size ()
                (list (+ 10 (random 40))
                      (+ 10 (random 40))))
              (setf ellipses
                    (capi:contain
                     (make-instance
                      'capi:pinboard-layout
                      :children
                      (loop for i below 40
                            for origin = (random-origin)
                            for size = (random-size)
                            collect
                            (make-instance 'capi:ellipse
                                           :x (first origin)
                                           :y (second origin)
                                           :width (first size)
                                            :height (second size)
                                           :graphics-args
                                            (list :foreground
                                                  (random-color))
                                           :filled t)))))
              (defun repaint (ellipse)
                (setf (capi:pinboard-object-graphics-args ellipse)
                     (list :foreground (random-color)))
                (capi:redraw-pinboard-object ellipse t))
              (defun widep (ellipse)
                (capi:with-geometry ellipse
                    (> capi:%width% capi:%height%)))
              (capi:map-pane-children ellipses 'repaint :test 'widep)
See also
             map-pane-descendant-children
```

map-pane-descendant-children

Generic Function

Summary Calls a function on each of the descendant panes of a pane.

Package capi

Signature map-pane-descendant-children pane function &key visible test

reverse leaf-only

Arguments *pane* A CAPI pane.

function A function of one argument.

visible A boolean. The default value is nil.

test A function of one argument, or nil. The

default is nil.

reverse A boolean. The default value is nil.

leaf-only A generalized boolean. The default value is

nil.

Description The function map-pane-descendant-children applies func-

tion to pane's descendent panes (that is, the children and each

of their children recursively), depth first.

If visible is true, then function is applied only to the visible

descendant panes.

If *test* is non-nil, it is a function which is applied first to each descendant pane, and only those for which *test* returns a true

value are then passed to function.

If reverse is non-nil, the order in which the children are

processed is reversed.

If *leaf-only* is true, then *function* is applied only to those panes

which do not have children.

See also map-pane-children

pane-descendant-child-with-focus

map-typeout Function

Package capi

Signature map-typeout pane &rest args

Description Makes a collector-pane the visible child of a switchable-

 ${\tt layout},$ and returns it as well. The switchable layout is found

by looking up the parent hierarchy starting from pane.

The switchable layout should have one or more children. If it has one child, a new collector pane is made using *args* as the

initargs with buffer-name defaulting to

"Background Output". If it has more than one, it searches

through the children to find the first collector pane.

See also unmap-typeout

with-random-typeout

collector-pane

maximum-moving-objects-to-track-edges

Variable

Summary Limits the tracking of edges in a graph.

Package capi

Initial Value 15

Description If there are more than *maximum-moving-objects-to-

track-edges* objects being moved in a graph, then edges

are not tracked.

The value should be an integer.

menu Class

Summary The class menu creates a menu for an interface when specified

as part of the menu bar (or as a submenu of a menu on the menu bar). It can also be displayed as a context menu.

Package capi

Superclasses element

titled-menu-object

Initargs :items The items to appear in the menu.

:items-function

A function to dynamically compute the

items.

:mnemonic A character, integer or symbol specifying a

mnemonic for the menu.

:mnemonic-escape

A character specifying the mnemonic

escape. The default value is $\#\\&$.

:mnemonic-title

A string specifying the title and a mne-

monic.

:image-function

A function providing images for the menu

items, or nil.

Accessors menu-items

menu-image-function

Description A menu has a title, and has items appearing in it, where an

item can be either a menu-item, a menu-component or

another menu.

The simplest way of providing items to a menu is to pass them as the argument *items*, but if you need to compute the items dynamically you should provide the setup callback *items-function*. This function should return a list of menu items for the new menu. By default *items-function* is called on the menu's interface, but a different argument can be specified using the menu-object initarg *setup-callback-argument*.

Note: *items-function* is called before the menu is raised (in order to initialize accelerators) and in particular it may be called before the interface is created. Therefore *items-function*, if you supply it, should work at this early stage.

If an item is not of type menu-object, then it gets converted to a menu-object with the item as its data. This function is called before the *popup-callback* and the *enabled-function* which means that they can affect the new items.

To specify a mnemonic in the menu title, you can use the initarg :mnemonic. The value *mnemonic* can be:

An integer The index of the mnemonic in the title.

A character The mnemonic in the title.

A character is chosen from a list of common

mnemonics, or the :default behavior is fol-

lowed. This is the default.

:default A mnemonic is chosen using some rules.

none The title has no mnemonic.

An alternative way to specify a mnemonic is to pass *mnemonic-title* (rather than *title*) This is a string which provides the text for the menu title and also specifies the mnemonic character. The mnemonic character is preceded in *mnemonic-title* by *mnemonic-escape*, and *mnemonic-escape* is removed from *mnemonic-title* before the text is displayed. For example:

[:]mnemonic-title "&Open File..."

At most one character can be specified as the mnemonic in *mnemonic-title*. To make *mnemonic-escape* itself appear in the button, precede it in *mnemonic-title* with *mnemonic-escape*. For example:

:mnemonic-title "&Compile && Load File..."

If *image-function* is non-nil, it should be a function of one argument. *image-function* is called with the data of each menu item and should return one of:

nil No image is shown.

An image object

The menu displays this image.

An image id or external-image

The system converts the value to a temporary image for the menu item and frees it when it is no longer needed.

If *image-function* is nil, no items in the menu have images. This is the default value.

Notes

- 1. On Cocoa and GTK+, menu items can contain both images and strings, so the *print-function* should return the appropriate string or "" if no string is required. On Microsoft Windows and Motif, if there is an image then the string is ignored. You can test programmatically whether menus with images are supported with panesupports-menus-with-images.
- When debugging a menu, it may be useful to pop up a window containing a menu with the minimum of fuss. The function contain will do just that for you.
- 3. To display a menu as a context (right button) menu, use display-popup-menu, and to display a menu via a labelled button use popup-menu-button.

4. By default Microsoft Windows hides mnemonics when the user is not using the keyboard. In Windows XP (and later) a system preference controls this:

Display > Appearance > Effects > Hide underlined letters...

```
Example
```

```
(capi:contain (make-instance 'capi:menu
                             :title "Test"
                           :items '(:red :green :blue)))
(capi:contain (make-instance
                 'capi:menu :title "Test"
                            :items '(:red :green :blue)
                             :print-function
                             'string-capitalize))
(capi:contain (make-instance
               'capi:menu
               :title "Test"
               :items '(:red :green :blue)
               :print-function 'string-capitalize
               :callback #'(lambda (data interface)
                              (capi:display-message
                               "Pressed ~S" data))))
```

Here is an example showing how to add submenus to a menu:

Here is an example showing how to use the *items-function*:

Finally, some examples showing how to specify a mnemonic in a menu title:

There is an example showing how to make a menu with images in examples/capi/elements/menu-with-images.lisp.

There are further examples in the directory examples/capi/applications/.

See also

display-popup-menu
menu-component
menu-item
menu-object
ole-control-add-verbs
pane-supports-menus-with-images
popup-menu-button

menu-component

Class

Summary

The class menu-component is a choice that is used to group menu items and submenus both visually and functionally. The items contained by the menu-component appear separated from other items, menus, or menu components, by separators.

Package capi

Superclasses choice

titled-menu-object

Initargs :items The items to appear in the menu.

:items-function

A setup callback function to dynamically compute the items.

:selection-function

A setup callback function to dynamically compute the selection.

:selected-item-function

A setup callback function to dynamically compute the selected item.

:selected-items-function

A setup callback function to dynamically compute the selected items.

Description

Because menu-component is a choice, the component can have *interaction*:no-selection,:single-selection or:multiple-selection (extended selection does not apply here). This is represented visually in the menu as appropriate to the window system that the CAPI is running on (by ticks in Microsoft Windows, and by radio buttons and check buttons in Motif).

Note that it is not appropriate to have menu components or submenus inside :single-selection and :multiple-selection components, but it is OK in :no-selection components.

items and items-function behave as in menu.

No more than one of selection-function, selected-item-function and selected-items-function should be non-nil. Each defaults to nil. If one of these setup callbacks is supplied, it should be a function which is called before the menu-component is displayed and which determines which items are selected. By default the setup callback is called on the interface of the menu-component, but this argument can be changed by passing the menu-object initary setup-callback-argument.

selection-function, if non-nil, should return a value which is suitable for passing to the choice accessor (setf choice-selection). This will be nil, or a single index (for interaction:single-selection), or a list of item indices (for interaction:multiple-selection and:extended-selection).

selected-item-function, if non-nil, should return an object which is an item in the menu-component, or is equal to such an item when compared by the menu-component's test-function.

selected-items-function, if non-nil, should return a list of such objects.

```
Example
```

See also menu

menu-item

menu-item Class

Summary A menu item is an individual item in a menu or menu com-

ponent, and instances of menu-item are created automati-

cally by define-interface.

Package capi

Superclasses item

titled-menu-object

Initargs :accelerator

A character, string or plist, or the keyword

:default.

:alternative

A generalized boolean.

:help-key An object used for lookup of help. Default

value t.

:mnemonic A character, integer or symbol specifying a

mnemonic for the menu item.

:mnemonic-escape

A character specifying the mnemonic escape. The default value is #\&.

:mnemonic-title

A string specifying the text and a mnemonic.

:selected-function

A setup callback determining whether the item is selected.

:enabled-function-for-dialog

nil, t, :same-as-normal or a function designator. Determines enabled state when a dialog is on screen.

Readers

help-key

Description

The text displayed in the menu item is the contents of the *text* slot, or the contents of the *title* slot, otherwise it is the result of applying the *print-function* to the *data*.

If selected-function is non-nil it should a function which is called before the menu-item is displayed and which determines whether or not the menu-item is selected. By default selected-function is called on the interface of the menu-item, but this argument can be changed by passing the menu-object initary setup-callback-argument. The default value of selected-function is nil.

Callbacks are made in response to a user gesture on a menu-item. The callback-type (see callbacks), callback and callback-data-function (see menu-object) are found by looking for a non-nil value, first in the menu-item, then the menu-component (if any) and finally the menu. This allows a whole menu to have, for example, callback-type:data without having to specify this in each item. Some items could override this by having their callback-type slot non-nil if needed.

To specify a mnemonic in the menu item, you can use the initarg:mnemonic, or the initargs:mnemonic-title and:mnemonic-escape. These initargs are all interpreted just as in menu.

A menu item should not be used more in more than one place at a time.

help-key is interpreted as described for element.

accelerator can be a character or string specifying a key gesture which will be the accelerator for the menu item.

Note that both-case-p characters are not allowed with the single modifier Shift in the accelerator argument. So instead of

```
:accelerator "shift-x"
USe
:accelerator "X"
```

Note that the Shift modifier still appears in the menu.

A both-case-p character is allowed with shift if there are other modifiers, for example

```
:accelerator "alt-shift-x"
```

If accelerator is a character then the system adds the normal modifier for the platform. That is, Command on Cocoa and Control on Microsoft Windows. The shortcut is validated for the platform.

If accelerator is a string with modifier keys then the system uses it only if it follows the normal conventions for the platform. The shortcut is validated for the platform.

The special virtual modifier name "accelerator" is allowed in string values of *accelerator*. It is interpreted as the normal modifier key for the platform. For example:

```
:accelerator "accelerator-x"
```

means Control+X on Microsoft Windows and Motif, and Command+X on Cocoa.

If accelerator is a plist then its keys are keywords naming some or all of the supported libraries (as returned by default-library). The plist's values are characters or strings which the system interprets as above, except that no check is made that the keyboard shortcut is valid for the platform.

accelerator has a special default value :default, which means that, depending on interface-keys-style for the interface, a standard accelerator is added if the item title matches a standard menu command.

alternative, when true, makes the menu-item an "alternative item". Alternative items are invoked if modifiers are held while selecting the "main item". These modifiers are defined by the item's accelerator. The main item is the one before the first alternative item, and each alternative item must be within the same menu and menu component. For an example see examples/capi/elements/accelerators.lisp and for more information see the section "Alternative menu items" in the CAPI User Guide.

enabled-function-for-dialog determines whether the item is enabled when a dialog is on the screen. Items in the menu bar menus and sub-menus are disabled by default while a dialog is on the screen on top of the active window. You can override this by specifying enabled-function-for-dialog. The value can be one of:

t The item is enabled whenever there is a dialog.

The item is disabled whenever there is a dialog.

:same-as-normal

Do the same as when there is no dialog. This depends on the *enabled-function* (see menu-object).

A function

A function that is called instead of the enabled-function to decide if the item should be enabled. It is called with one argument, by the default the menu interface, which can be overriden by the initarg:setup-call-back-argument (see menu-object for details).

The default value of enabled-function-for-dialog is nil.

Notes

Some accelerators do not work on some platforms because they have other standard meanings, for example on Microsoft Windows F1 always invokes the *help-callback*.

On X11/Motif the accelerators of alternative items do not work.

Example

In this example note how the **File** menu gets accelerators automatically for its standard items:

```
(capi:display-message
                 (format nil "~A" (capi:item-data item))))
              (capi:define-interface mmm () ()
                (:menu-bar f-menu a-menu)
                (:menus
                 (f-menu
                   "File"
                  (("Open..." :data "Open...")
                   ("New"
                              :data "New"))
                  :callback 'do-menu-item
                  :callback-type :item)
                 (a-menu
                  "Another Menu"
                  (("Open..." :data "Another Open")
                   ("New" :data "Another New")
                   ("Blancmange" :data "Blancmange"
                                 :accelerator "accelerator-b"))
                  :callback 'do-menu-item
                  :callback-type :item))
                (:default-initargs
                 :width 300
                 :height 200))
             ;; This causes automatic accelerators on all platforms.
             ;; That is the default behavior on Microsoft Windows.
              (defmethod capi:interface-keys-style ((self mmm))
                :pc)
              (capi:contain (make-instance 'mmm))
             There are further examples in the files
             examples/capi/applications/hangman.lisp and
             examples/capi/printing/fit-to-page.lisp.
See also
             choice
             interface-keys-style
             menu
             menu-component
```

(defun do-menu-item (item)

menu-object Class

Summary The class menu-object is the superclass of all menu objects,

and provides functionality for handling generic aspects of

menus, menu components and menu items.

Package capi

Superclasses callbacks

Subclasses titled-menu-object

InitargS :popup-callback

Callback before the menu appears.

:enabled-function

Returns true if the menu is enabled.

:enabled-slot The object is enabled if the slot is non-nil.

:callback The selection callback for the object.

:callback-data-function

A function to return data for the callback.

:setup-callback-argument

If non-nil, specifies the argument to the setup callbacks (listed below) that are used

to set up the menu-object.

ACCESSORS menu-popup-callback

Readers menu-object-enabled

Description When the menu object is about to appear on the screen, the

CAPI does the following:

- 1. The setup callback *items-function* (if there is one) is called and the result is used to set the items, for menu and menucomponent. The argument passed to *items-function* is the same as for the other setup callbacks (see below).
- 2. The *popup-callback* (if there is one) is called and can make arbitrary changes to that object. The *popup-callback* is always called with the menu object, regardless of the value of *setup-callback-argument*.
- 3. The other setup callbacks are called to set up the selection, enabled state and title. These setup callbacks include enabled-function for all menu-objects and title-function for all titled-menu-objects. The additional setup callbacks for menu-component are selection-function, selected-itemfunction, and selected-items-function. menu-item has the additional setup callback selected-function.
 - By default setup-callback-argument is nil, which means that each of the setup callbacks is called on the interface of the menu-object. If setup-callback-argument is non-nil, then it is passed (instead of the interface) as the argument to each of the setup callbacks.
- **4.** The menu containing the object appears with all of the changes made.

Note that *enabled-slot* is a short-hand means of creating an *enabled-function* which checks the value of a slot in the menu object's interface.

The enabled state of a menu-object is computed each time the menu is displayed, using enabled-function or enabled-slot. Therefore the accessor menu-object-enabled is only useful as a reader.

The *callback* argument is placed in the *selection-callback*, *extend-callback* and *retract-callback* slots unless these are given explicitly, and so will get called when the menu object is selected or deselected.

The *callback-data-function* is a function that is called with no arguments and the value it returns is used as the data to the callbacks.

Notes

The function *enabled-function* should not display a dialog or do anything that may cause the system to hang. In general this means interacting with anything outside the Lisp image, including files, databases and so on.

Example

The next example illustrates the use of setup-callback-argument. The initialize-instance method adds to the "Some Numbers" menu a sub-menu that lists the selected items in the list-panel. By using setup-callback-argument in this menu, the setup callbacks (in this case enabled-function and items-function) are called directly on the list-panel.

Note that, while this example uses a CAPI object as the *setup-callback-argument*, any object of any type can be used.

```
(capi:define-interface my-interface ()
                (:panes
                 (list-panel
                  capi:list-panel
                  :items '(1 2 3 4 5 6 7 8 9 0)
                  :interaction :extended-selection
                  :visible-min-height '(character 10)))
                (:menus
                 (a-menu
                  "Some Numbers"
                  ("One" "Two")
                  ))
                (:menu-bar a-menu))
              (defmethod initialize-instance :after
                ((self my-interface) &key)
                (with-slots (a-menu list-panel) self
                  (setf (capi:menu-items a-menu)
                        (append
                         (capi:menu-items a-menu)
                         (list
                          (make-instance 'capi:menu
                                          :items-function
                                          'capi:choice-selected-items
                                          :setup-callback-argument
                                          list-panel
                                          :enabled-function
                                          'capi:choice-selection
                                          :title
                                          "Selected Items"))))))
              (capi:display (make-instance 'my-interface))
See also
             menu
             menu-item
             menu-component
```

merge-menu-bars

Generic Function

Summary Computes the menu bar for a document-frame on Windows.

Package capi

Signature merge-menu-bars frame document => menus

Arguments frame A document-frame.

document An interface or nil.

Values menus A list of menu objects.

Description The generic function merge-menu-bars is called by the

system to compute the menu bar for a document-frame

interface.

The set of visible menus in such an interface is typically made up from those of the frame and those of the active document within it

There is a built-in unspecialized method that appends the menu bars of the two interfaces and is equivalent to this:

You can customize the menu bar by adding methods which specialize on particular frame and document interface classes.

Notes merge-menu-bars is implemented only in LispWorks for

Windows.

See also document-frame

interface

menu

message-pane Class

Summary The class displaying the message when a pane is created with

the :message initarg.

Package capi

Superclasses title-pane

Description The class message-pane is used to implement the message

decoration on subclasses of titled-object.

A message-pane with text "Message" is created automatically when a titled-object is created with message "Message".

See also titled-object

modify-editor-pane-buffer

Function

Summary The modify-editor-pane-buffer function allows you to

modify the contents and fill mode of a specified buffer.

Package capi

Signature modify-editor-pane-buffer pane &key contents flag

fill fixed-fill force

Description The modify-editor-pane-buffer function modifies the

editor-pane pane according to the keyword arguments.

The argument contents (if non-nil) supplies a new string to

place in the buffer.

flag, if given, sets the flag slot of the editor buffer, which is

used to mark it for various specialized uses.

If *fill* is non-nil the editor fills each paragraph in the buffer. If *fill* is a fixnum then the buffer is filled at that width. If *fill* is :default (the default value) and *fixed-fill* is supplied then the value *fixed-fill* is used. Otherwise the buffer is filled to the window width.

fixed-fill defaults to mil.

See also editor-pane

mono-screen Class

Summary The mono-screen class is created for monochrome screen.

Package capi

Superclasses screen

Description This is a subclass of screen that gets created for mono-

chrome screens. It is primarily available as a means of discriminating on whether or not to use colors in an interface.

See also color-screen

move-line Generic Function

Summary Moves a line-pinboard-object.

Package capi

Signature move-line line-pinboard-object start-x start-y end-x end-y &key

redisplay

1 CAPI Reference Entries

Arguments	line-pinboard-object	
		An instance of line-pinboard-object or a subclass.
	start-x	The x coordinate of the start of the line.
	start-y	The y coordinate of the start of the line.
	end-x	The x coordinate of the end of the line.
	end-y	The y coordinate of the end of the line.
	redisplay	A boolean.
Description	The generic function move-line moves a line to a new location with end points specified by the corrdinate arguments. This automatically adjusts the geometry of the object, taking into account other constraints. Examples of such constraints are the label in a labelled-line-pinboard-object and the arrowhead in a arrow-pinboard-object.	
	The default value of <i>redisplay</i> is t, which means that the changed line is redrawn immediately. If you are moving many objects at the same time, it is useful to pass :redisplay nil.	
See also	line-pinboard-object line-pinboard-object-coordinates	

multi-column-list-panel

Class

Summary A list panel with multiple columns of text.

Package capi

Superclasses list-panel

Initargs

:column-function

A function of one argument. The default is identity.

:item-print-functions

A function of one argument, or a list of such functions.

:columns A list of column specifications.

:header-args A plist of keywords and values.

:auto-reset-column-widths

A boolean. The default is t.

Description

The class multi-column-list-panel is a list panel which displays multiple columns of text. The columns can each have a title.

Note that this is a subclass of list-panel, and hence of choice, and inherits the behavior of those classes.

Each item in a multi-column-list-panel is displayed in a line of multiple objects. The corresponding objects of each line are aligned in a column.

The *column-function* generates the objects for each item. It should take an item as its single argument and return a list of objects to be displayed. The default *column-function* is identity, which works if each item is a list.

The *item-print-functions* argument determines how to calculate the text to display for each element. If *item-print-functions* is a single function, it is called on each object, and must return a string. Otherwise *item-print-functions* should be a sequence of length no less than than the number of columns. The text to display for each object is the result (again, a string) of calling the corresponding element of *item-print-functions* on that object.

The *columns* argument specifies the number of columns, and whether the columns have titles and callbacks on these titles.

Each element of *columns* is a specification for a column. Each column specification is a plist of keyword and values, where the allowed keywords are as follows:

:title Specifies the title to use for the column. If

any of the columns has a title, a header object is created which displays the titles. The values of the :title keywords are passed as the *items* of the header, unless

header-args specifies: items.

:adjust Specifies how to adjust the column. The

value can be one of :right, :left, or :cen-

ter.

:width Specifies a fixed width of the column.

:default-width

Specifies the default initial width of the column. The user can resize it. If :width is supplied it overrides :default-width.

:visible-min-width

:gap

Minimum width of the column.

Specifies an additional gap alongside the text in the column. :gap is not supported consistently across platforms (see Notes

below).

The values of :width, :visible-min-width and :gap are interpreted as standard geometric hints. See element for information about these hints.

columns should indicate how many columns to display. At a minimum the value needs to be (() ()) for two columns without any titles

header-args is a plist of initargs passed to the header which displays the titles of the columns. The header object is a collection. The following collection initargs are useful to pass in header-args:

:selection-callback

The callback for clicking on the header.

:callback-type

Defines the arguments of the *selection-call-back*.

:items

The items of the header object. Note that :items overrides :title if that is supplied in *columns*.

:print-function

Controls how each of *items* is printed, providing the title of each column.

header-args may also contain the keyword :alignments. The value should be a list of alignment keywords, each of which is interpreted like an :adjust value in columns. The alignment is applied to the title only.

If auto-reset-column-widths is true, then the widths of the columns are recomputed when the items of the multi-column-list-panel are set.

Notes

- 1. Similar and enhanced functionality is provided by list-
- On Microsoft Windows, :width in a column specification does not actually make the column width be fixed, though it does supply the initial width.
- **3.** On Microsoft Windows, <code>:gap</code> in a column specification adds the gap on both sides of the text. On Motif it adds the gap only on the right side of the text. On GTK+ and Cocoa <code>:gap</code> is ignored.

Example This example uses the *columns* initarg:

This example uses *header-args* to add callbacks and independent alignment on the titles:

```
(defun mclp-header-callback (interface item)
  (declare (ignorable interface))
  (capi:display-message "Clicked on ~a" item))
(capi:contain
 (make-instance
  'capi:multi-column-list-panel
 :visible-min-width 300
  :visible-min-height :text-height
  :columns '((:adjust :right
              :width (character 15))
             (:adjust :left
              :visible-min-width (character 30)))
  :header-args '(:items ( "Fruits" "Vegetables")
                 :selection-callback
                 mclp-header-callback
                 :alignments (:left :right))
 :items '(("Apple" "Artichoke")
           ("Pomegranate" "Pumkpin"))))
```

This example uses *column-function* to implement a primitive process browser:

```
(defun get-process-elements (process)
                (list (mp:process-name process)
                      (mp:process-whostate process)
                      (mp:process-priority process)))
              (capi:contain
               (make-instance
                'capi:multi-column-list-panel
                :visible-min-width '(character 70)
                :visible-min-height '(character 15)
                :items (mp:list-all-processes)
                :columns '((:title "Name" :adjust :left
                            :visible-min-width (character 30))
                           (:title "State" :adjust :center
                            :visible-min-width (character 20))
                           (:title "Priority" :adjust :center
                            :visible-min-width (character 12)))
                :column-function 'get-process-elements))
See also
             collection
             list-panel
             list-view
```

multi-line-text-input-pane

Class

Summary A pane allowing several lines of text to be entered.

Package capi

Superclasses text-input-pane

Description The multi-line-text-input-pane class behaves like a

text-input-pane, except that the text entered by the user is allowed to span several lines — that is, it is allowed to con-

tain Newline characters.

See also text-input-pane

non-focus-list-interface

Class

Summary Created (and destroyed) only by prompt-with-list-non-

focus and text-input-pane-in-place-complete.

Superclasses interface

Description The class non-focus-list-interface is the class of inter-

face created and destroyed only by prompt-with-list-non-focus and text-input-pane-in-place-complete. Do not

instantiate this class directly.

See also prompt-with-list-non-focus

text-input-pane-in-place-complete

non-focus-list-toggle-enable-filter

Function

Summary Toggles the enabled state of the filter.

Signature non-focus-list-toggle-enable-filter non-focus-list-interface

Arguments non-focus-interface

A non-focus-list-interface.

Description The function non-focus-toggle-enable-filter toggles

the enabled state of the filter in a non-focus list created by prompt-with-list-non-focus Or text-input-pane-in-

place-complete. It has no effect if the filter is off.

It is used as the callback of the *filtering-toggle*.

See also prompt-with-list-non-focus

non-focus-list-toggle-filter non-focus-list-add-filter non-focus-list-remove-filter

Functions

Summary Add or remove the filter in a non-focus list.

Signature non-focus-list-toggle-filter non-focus-list-interface

non-focus-list-add-filter non-focus-list-interface

non-focus-list-remove-filter non-focus-list-interface

Arguments *non-focus-interface*

A non-focus-list-interface.

Description These functions add or remove the filter in a non-focus list.

non-focus-list-toggle-filter calls non-focus-list-add-filter if the filter is off, otherwise it calls non-focus-list-remove-filter (it is used as the callabck for the filter-

ing-gesture).

non-focus-list-add-filter adds a filter is it is not already

on, resets the text in it to empty string, and enables it.

non-focus-list-remove-filter removes the filter if it is

on.

See also prompt-with-list-non-focus

non-focus-maybe-capture-gesture

Generic Function

Summary Maybe capture a gesture by the non-focus-interface.

Signature non-focus-maybe-capture-gesture non-focus-interface gesture

=> result

Arguments non-focus-interface

 ${
m A}$ non-focus-list-interface.

gesture A gesture specifier.

Values result A generalized boolean.

Method Signature

non-focus-maybe-capture-gesture (non-focus-interface non-focus-list-interface) gesture

Description

The generic function non-focus-maybe-capture-gesture needs to return non-nil if the gesture gesture was captured, which means it should not be processed any more, or nil if gesture was not captured.

gesture should be a gesture specifier, which is an object that can be coerced to a Gesture Spec by sys:coerce-to-ges-ture-spec.

The method on non-focus-list-interface does the following:

- If the gesture is Escape it calls non-focus-terminate on the non-focus window.
- 2. It checks whether the gesture matches any of the gestures in the gesture-callbacks of the window. The gesture callbacks are either explicitly defined using the initargs :gesture-callbacks or :add-gesture-callbacks, or implicitly. By default, all the gestures that are used in inplace completion (see "In-place completion" in the CAPI User Guide) are defined implicitly. These include Up, Down, PageUp, PageDown (selection in the list panel), Return (action), Control+Return and Control+Shift+Return (control of the filter). The implicitly defined gestures are affected by gesture-callbacks, filtering-gesture and filtering-toggle.

If a match is found, it is invoked as described for *gesture-call-backs* in prompt-with-list-non-focus.

3. If filtering is enabled, it checks if the gesture is captured by the filter. A gesture is captured by the filter if it is:

A plain graphic character.

It is inserted to the filter

Backspace

The last character in the filter is deleted

One of the gestures which update the state of the filter (by default Control+Shift+R, Control+Shift+E. Control+Shift+C)

The state of the filter is updated.

In any case, where a gesture is captured by the filter the list panel is updated.

If the gesture is captured by one of the possibilities above, the method returns t. otherwise it returns mil.

See also

non-focus-terminate

prompt-with-list-non-focus

non-focus-terminate

Generic Function

Summary Terminates the non-focus interface. Signatures non-focus-terminate non-focus-interface Method Signon-focus-terminate (non-focus-interface non-focus-listinterface) nature Description The generic function non-focus-terminate closes the nonfocus interface.

It has no return value.

The method terminates a non-focus-list-interface. It destroys the interface in the correct process.

See also prompt-with-list-non-focus

non-focus-update

Generic Function

Summary Updates the non-focus-interface.

Signature non-focus-update non-focus-interface

Method Sig- non-focus-update (non-focus-interface non-focus-list-

nature interface)

Description The generic function non-focus-update updates the non-

focus-interface.

It has no return value.

The method on non-focus-list-interface needs to be invoked in the process in which the *list-updater* that was passed to prompt-with-list-non-focus is expecting to run.

It invokes the *list-updater* without arguments, and then updates the non-focus-interface with result. See the descrip-

tion of list-updater in prompt-with-list-non-focus.

Note that if list-updater returns : destroy, this invokes non-

focus-terminate on the interface.

See also prompt-with-list-non-focus

non-focus-terminate

ole-control-add-verbs

Function

Summary Adds to the menu entries for the "verbs" that a component in

an ole-control-pane supports.

Signature ole-control-add-verbs pane menu item-identifier

Arguments pane An ole-control-pane.

menu A menu.

item-identifier A string or symbol.

Description The function ole-control-add-verbs adds to the menu

entries for the "verbs" that the component supports. The olecontrol-pane pane must have an object already, and the menu menu must have already been created, so ole-control-add-verbs is typically called in the popup-callback of menu.

item-identifier identifies an item in the menu or a component in the menu (but not in a sub-menu), either by being eq to the name of the item or equalp to the title of the item. If the item is found, it is replaced either by a sub-menu with the verbs that the object supports, or, if the object supports only one verb, by an entry for this.

When the user selects an added menu item, the verb is passed to the object (by a call to IOleObject::DoVerb).

Notes This function is implemented only in LispWorks for Win-

dows. Load the functionality by (require "embed").

Example See the example in

examples/com/ole/simple-container/doc-viewer-

pair.lisp

See also menu

ole-control-pane

ole-control-close-object

Function

Summary Closes the object in an ole-control-pane.

Signature ole-control-close-object pane

1 CAPI Reference Entries

Arguments pane An ole-control-pane.

Description The function ole-control-close-object closes the object

that is currently in the ole-control-pane pane.

Notes This function is implemented only in LispWorks for Win-

dows. Load the functionality by (require "embed").

Example See the example in

examples/com/ole/simple-container/doc-viewer-

pair.lisp

See also ole-control-pane

ole-control-component

Class

Summary An implementation of the interfaces in the OLE Control pro-

tocol.

Package capi

Superclasses com:standard-i-unknown

Initargs :pane-function

A function that is called when OLE embeds

the Control in a container.

:create-callback

A function called just after the pane is cre-

ated.

:destroy-callback

A function called just before the pane is

destroyed.

Readers ole-control-component-pane

Description

The class ole-control-component provides an implementation of the interfaces in the OLE Control protocol, to allow a CAPI pane to be embedded in an OLE Control container implemented outside LispWorks. It is typically used with the macro define-ole-control-component to define a subclass of ole-control-component that implements a particular coclass from a type library. Instances of this class are usually created by the COM runtime system, not by explicit calls to make-instance.

A function designator *pane-function* must be supplied. *pane-function* that is called when OLE embeds the Control in a container. It receives the component as its argument and should return a CAPI pane that will implement the visual aspects of the control.

Note: The pane returned by *pane-function* must be a outputpane, layout or interface in the current implementation. The pane is stored in the component and can be accessed using the reader ole-control-component-pane.

create-callback, if non-nil, is a function called when the pane returned by *pane-function* has been created in the window system. The argument is the pane itself. *create-callback* can perform initialization such as loading images.

destroy-callback, if non-nil, is a function called when the pane returned by pane-function is going to be destroyed. The argument is the pane itself. destroy-callback can perform cleanups.

Notes

When using an ole-control-component, the normal hierarchy of CAPI objects such as a layout and an interface do not exist above it. The layout and control of the top level window is the responsibility of the application that embeds the control. It can communicate with the control by using COM/Automation.

ole-control-component is implemented only in LispWorks for Windows. Load the functionality by (require "embed").

See also define-ole-control-component

ole-control-doc Class

Summary A class that implements the document around the object

inside an ole-control-pane.

Package capi

Superclasses pinboard-layout

Sublcasses ole-control-frame

Description The pane class ole-control-doc can be used to implement

the document around the object inside an ole-controlpane. That is, it supports the IOleInPlaceUIWindow inter-

face. Note that this is optional, and is rarely useful.

To use it the ole-control-doc pane needs to be the parent, not necessarily directly, of an ole-control-pane. When the object calls IOleInPlaceSite::GetWindowContext, it will get (in the ppdoc [out] argument) an IOleInPlaceUIWindow interface associated with the ole-control-doc.

A ole-control-doc must have exactly one sub-pane (that is, the length of its *description* must be 1), but underneath this pane there can be many panes.

Normally the program does not need to do anything else with the ole-control-doc. It acts in response to resizing of the window and method calls from the object on the

IOleInPlaceUIWindow interface.

Notes ole-control-doc is implemented only in LispWorks for

Windows. Load the functionality by (require "embed").

Even though it is a subclass of pinboard-layout, normally you should not use the pinboard-layout functionality when using ole-control-doc.

Example See the example in

examples/com/ole/simple-container/doc-viewer-

pair.lisp

See also ole-control-pane

ole-control-frame Class

Summary Implements the frame of components in an ole-control-

pane.

Package capi

Superclasses ole-control-doc

Description The pane class ole-control-frame implements the frame of

components, that is it supports the IOleInPlaceFrame interface. When an ole-control-pane pane is created, it looks upwards in the hierarchy of panes, and if finds an ole-control-frame pane it uses this as the frame. It uses the first such pane found. When the object in the ole-control-pane calls IOleInPlaceSite::GetWindowContext, it gets back in the ppframe arg an interface associated with this frame.

Like ole-control-doc, a ole-control-frame can have only one sub-pane, which itself may contain many panes.

Normally the program does not need to do anything else with the ole-control-frame. It acts in response to resizing of the window and method calls from the object on the IOLeInPlaceFrame interface.

Note that having a frame is optional, and ActiveX does not need it. It is required when embedding an application by

ole-control-insert-object.

Notes ole-control-frame is implemented only in LispWorks for

Windows. Load the functionality by (require "embed").

Even though it is a subclass of pinboard-layout, normally you should not use the pinboard-layout functionality when

using ole-control-frame.

Example See the example in

examples/com/ole/simple-container/doc-viewer-

pair.lisp

See also ole-control-insert-object

ole-control-pane

ole-control-i-dispatch

Function

Summary Returns the com:i-dispatch of the component of an ole-

control-pane.

Signature ole-control-i-dispatch pane => result

Arguments pane An ole-control-pane.

Values result A com:i-dispatch or nil.

Description The function ole-control-i-dispatch returns the com:i-

dispatch (that is, the IDispatch interface) of the component, or nil if there isn't any. The com:i-dispatch is the one that would be returned by com:query-interface on the

I-Ole-object.

Notes Calling ole-control-i-dispatch does not affect the refer-

ence count of the interface.

This function is implemented only in LispWorks for Windows. Load the functionality by (require "embed").

See also ole-control-pane

ole-control-insert-object

Function

Summary Embeds a user-specified document in an ole-control-pane.

Signature ole-control-insert-object pane

Arguments pane An ole-control-pane.

Description The function ole-control-insert-object prompts the

user for a document using the Microsoft Windows function

OleUIInsertObject.

When the user specifies a document in the dialog presented, ole-control-insert-object embeds this document in the

ole-control-pane pane.

Notes This function is implemented only in LispWorks for Win-

dows. Load the functionality by (require "embed").

Example See the example in

examples/com/ole/simple-container/doc-viewer-

pair.lisp

See also ole-control-pane

ole-control-ole-object

Function

Summary Returns the com:i-ole-object of the component of an ole-

control-pane.

1 CAPI Reference Entries

Signature ole-control-ole-object pane => result

Arguments pane An ole-control-pane.

Values result A com:i-ole-object or nil.

Description The function ole-control-ole-object returns the com:i-

ole-object (that is, the IOleObject interface) of the component of the ole-control-pane *pane*, or nil if there isn't any.

Notes Calling ole-control-ole-object does not affect the

reference count of the interface.

This function is implemented only in LispWorks for Windows. Load the functionality by (require "embed")

See also ole-control-pane

ole-control-pane

Class

Summary A class that implements embedding of external components

on Microsoft Windows.

Package capi

Superclasses pinboard-layout

Initargs :component-name

A string or nil.

:user-component

A COM interface pointer or mil.

:save-name A string.

:insert-callback

A function.

:close-callback

A function.

:sinks

A list of sink specifications.

Description

The class ole-control-pane is used to implement embedding of external components.

Note: ole-control-pane is implemented only in LispWorks for Windows. Load the functionality by (require "embed").

Note: even though it is a subclass of pinboard-layout, normally you should not use the pinboard-layout functionality when using ole-control-pane.

component-name (if non-nil) specifies the component-name of the pane, as used by component-name.

user-component (if non-nil) is a COM interface pointer of an object that supports the I-OLE-OBJECT interface, and is ready to display as described in ole-control-user-component.

save-name is used when creating the Istorage object for this component.

insert-callback (if non-nil) is a function that takes a single argument, the pane. It is called immediately after a component was inserted into the pane. This can be used for any additional initialization that is required, for example setting the properties of the control.

close-callback (if non-nil) is a function that takes a single argument, the pane. It is called just before the component is going to be closed, and can be used to do any cleanups that may be required.

sinks is a list of sink specifications for attaching event handlers to the source interfaces of the control. Each element of sinks should be a list of the form:

(interface-name &key invoke-callback sink-class sink)

The interface-name is used to specify the name of the source interface in the control, which is either a string naming the interface or :default for the default source interface. If invoke-callback is given, then it should be a function which will be called with the pane, method-name, method-kind and arguments vector for each source event. The sink-class can be given to set the class of the internal object used for the sink interface. This is similar to calling attach-simple-sink. Alternatively, instead of calling invoke-callback, the sink can be specified directly. This is similar to calling attach-sink.

When the ole-control-pane is destroyed, the sinks are automatically detached.

There are currently three ways to insert an external component into an ole-control-pane. These are:

- Call ole-control-user-component, which asks the user for something to insert.
- Set the component-name of the pane. This can be done either via the initarg : component-name or by calling (setf component-name).
- 3. Set the user-component of the pane, either via the initarg :user-component or by calling (setf ole-control-user-component).

Example

See examples/com/ole/simple-container/sink.lisp for a full example.

See also

```
attach-sink
component-name
detach-sink
interface-menu-groups
ole-control-add-verbs
```

ole-control-close-object
ole-control-i-dispatch
ole-control-insert-object
ole-control-ole-object
ole-control-pane-frame
ole-control-user-component
report-active-component-failure

ole-control-pane-frame

Function

Summary Returns the ole-control-frame of an ole-control-pane.

Signature ole-control-pane-frame pane => result

Arguments pane An ole-control-pane.

Values result An ole-control-frame or nil.

Description The function ole-control-pane-frame returns the ole-

control-frame of the ole-control-pane pane, if there is

one.

Note: this function is implemented only in LispWorks for Windows. Load the functionality by (require "embed").

See also ole-control-frame

ole-control-pane

ole-control-pane-simple-sink

Class

Summary A class that implements a sink interface for an embedded

component on Microsoft Windows.

Package capi

1 CAPI Reference Entries

Superclasses com:simple-i-dispatch

Initargs :ole-control-pane

A class instance.

Description The class ole-control-pane-simple-sink is used by the

function attach-simple-sink to implement a sink interface

for an embedded component on Microsoft Windows.

ole-control-pane is the object of type ole-control-pane to

whose source interface the sink is being attached.

This class can be subclassed to provide additional functionality in callbacks. See com:simple-i-dispatch in the *LispWorks*COM/Automation User Guide and Reference Manual for more

details.

Note: ole-control-pane-simple-sink is implemented only in LispWorks for Windows. Load the functionality by

(require "embed").

See also attach-simple-sink

ole-control-pane

ole-control-user-component

Function

Summary Gets and sets the *user-component* of an ole-control-pane.

Signature ole-control-user-component pane => user-component

(setf ole-control-user-component) user-component pane =>

user-component

Arguments pane An ole-control-pane.

user-component A COM interface pointer.

Description The function ole-control-user-component gets and sets

the user-component of the ole-control-pane pane.

user-component (if non-nil) is a COM interface pointer of an object that supports the I-OLE-OBJECT interface, and has been opened and initialized and is ready to be displayed. This is typically created by calling OleCreate, OleCreate-FromFile, OleCreateFromData or OleLoad with pCLientSite null.

The user-component is closed and released by the ole-control-pane pane, so after you have called (setf ole-control-user-component) you should not try to use it again or release it. Setting user-component also sets the pane's component-name to nil.

Notes This function is implemented only in LispWorks for Win-

dows. Load the functionality by (require "embed").

See also ole-control-pane

option-pane Class

Summary A pane which offers a choice of items, but which displays

only the currently selected item.

Package capi

Superclasses choice

titled-object
simple-pane

Initargs : enabled Non-nil if the option pane is enabled.

:visible-items-count

An integer or the symbol :default.

:popup-callback

A function called just before the popup menu appears, or nil.

:image-function

A function providing images for items, or nil.

:image-lists

A plist of keywords and image-list objects.

:separator-item

An item that acts as a separator between other items, or nil.

:enabled-positions

A list of fixnums, or the keyword :all.

:window-styles

A list of keywords.

Accessors

option-pane-enabled
option-pane-image-function
option-pane-visible-items-count
option-pane-popup-callback
option-pane-separator-item
option-pane-enabled-positions

Description

The class option-pane provides a pane which offers a choice between a number of items via a popup menu. Only the currently selected item is displayed.

The class option-pane inherits from choice, and so has all of the standard choice behavior such as selection and callbacks. It also has an extra *enabled* slot along with an accessor which is used to enable and disable the option pane.

visible-items-count is implemented only on Microsoft Windows. If visible-items-count is an integer then the popup menu is no longer than this, and is scrollable if there are more items. If visible-items-count is :default, then the popup menu is no longer than 10. This is the default value.

When *popup-callback* is non-nil, it should be a function of one argument that will be called just before the popup menu appears when the user clicks on it. The single argument to the function is the option pane and the return value is ignored. If required, the function can change the items or selection of the pane. The default value of *popup-callback* is nil.

If *image-function* is non-nil, it should be a function of one argument which is called with each item. The return value depends on *image-lists*. If *image-lists* contains an <code>image-list</code> for the <code>:normal</code> key, then the result of *image-function* should be one of the following:

A pathname or string

This specifies the filename of a file suitable for loading with load-image. Currently this must be a bitmap file.

A symbol

The symbol must have been previously registered by means of a call to registerimage-translation.

An image object, as returned by load-image.

An image locator object

This allowing a single bitmap to be created which contains several button images side by side. See make-image-locator for more information. On Microsoft Windows, it also allows access to bitmaps stored as resources in a DLL.

An integer

This is a zero-based index into the optionpane's image-list. This is generally only useful if the image list is created explicitly. See image-list for more details.

Otherwise if there is no image-list then it should return one of:

nil No image is shown.

An image object

The pane displays this image.

An image id or external-image

The system converts the value to a temporary image for the item and frees it when it is no longer needed.

If *image-function* is nil, no items have images. This is the default value..

If *image-lists* is specified, it should be a plist containing the keyword :normal as a key. The corresponding value should be an image-list object. No other keys are supported at the present time. The image-list associated with the :normal key is used with the *image-function* (see above) to specify an image to display in each tab.

separator-item should be an item (compared using test-function) that acts as a separator between other items. A separator item is not selectable. The default value mil means that there are no separators (regardless of test-function).

If *enabled-positions* is :all then all the items can be selected. Otherwise the value is a list of fixnums indicating the positions in the item list which can be selected. The default value is :all.

On Microsoft Windows Vista and Windows 7, if window-styles contains the keyword :simple-text-only, then the option-pane is displayed using the UI theme and the enabled-positions, separator-item, image-function and visible-items-count initargs are not supported. Otherwise it is displayed without the UI theme and those options work as documented. This is a limitation in Microsoft Windows.

Notes

1. :image-function and :image-lists are currently only implemented for Microsoft Windows, GTK+ and Cocoa.

- **2.** On Motif, the separator is represented simply as a blank item between the other items.
- **3.** On Motif and GTK+ versions older than 2.12, there is no visible representation of the disabled items.

Example

This example sets the selection and changes the enabled state of an option-pane:

This example illustrates the use of *visible-items-count* (Windows only):

There are further examples in the files examples/capi/choice/option-pane.lisp and examples/capi/choice/option-pane-with-images.lisp.

output-pane

Class

Summary

An output pane is a pane whose display and input behavior can be controlled by the programmer.

1 CAPI Reference Entries

Package capi

Superclasses titled-object

simple-pane

gp:graphics-port-mixin

Subclasses pinboard-layout

editor-pane

Initargs :display-callback

A function called to redisplay the pane.

:drawing-mode

A keyword controlling quality of drawing,

especially anti-aliasing of text.

:graphics-options

A platform-specific plist of options control-

ling how graphics are drawn.

:draw-with-buffer

A boolean controlling whether output is

buffered, on Windows and Motif.

:input-model A list of input specifications, otherwise

known as a command table.

:scroll-callback

A function called when the pane is scrolled,

or nil. The default is nil.

:pane-can-scroll

A generalized boolean specifying whether the pane itself is responsible for drawing

into the visible area.

:focus-callback

A function called when the pane gets or loses the input focus, or nil. The default is nil.

:resize-callback

A function called when the pane is resized, or nil. The default is nil.

:create-callback

A function called just after the pane is created.

:destroy-callback

A function called just before the pane is destroyed.

:use-native-input-method

Controls whether to use native input method to interpret keyboard input. Currently this has an effect only on GTK+.

:composition-callback

This is called for various events related to composition, which here means composing input characters into other characters by an input method.

Accessors

```
output-pane-display-callback
output-pane-focus-callback
output-pane-resize-callback
output-pane-scroll-callback
output-pane-create-callback
output-pane-destroy-callback
output-pane-composition-callback
output-pane-input-model
```

Readers

output-pane-graphics-options

Description

The class output-pane is a subclass of <code>gp:graphics-port-mixin</code> which means that it supports many of the graphics ports drawing operations. When the CAPI needs to redisplay a region of the output pane, the <code>display-callback</code> gets called with the <code>output-pane</code> and the <code>x</code>, <code>y</code>, <code>width</code> and <code>height</code> of the region that needs redrawing. The <code>display-callback</code> should then use graphics port operations to redisplay that area. To force an area to be re-displayed, use the function <code>invalidate-rectangle</code>.

drawing-mode should be either :compatible which causes drawing to be the same as in LispWorks 6.0, or :quality which causes all the drawing to be transformed properly, and allows control over anti-aliasing on Microsoft Windows and GTK+. The default value of drawing-mode is :quality.

For more information about *drawing-mode*, see "Drawing mode and anti-aliasing" in the *CAPI User Guide*.

graphics-options is currently only used by the Mac OS X Cocoa
implementation. The single option defined is
:text-rendering, with allowed values:

glyph Draw glyphs directly using Core Graphics.

This only draws characters with glyphs in

the chosen font.

:atsui Draw using ATSUI APIs where

possible. This is slower but can handle more

characters.

When draw-with-buffer is true, display of the output-pane (that is drawing the background and calling the display-call-back) is done by first drawing to a pixmap buffer, and then drawing from that buffer. This is useful to avoid flickering if the display is complex. The default value of draw-with-buffer is nil.

The *input-model* provides a means to get callbacks on mouse and keyboard gestures. An *input-model* is a list of mappings from gesture to callback, where each mapping is a list

(gesture callback . extra-callback-args)

gesture specifies the type of gesture, which can be Gesture Spec, character, button, key, command or motion.

In a Gesture Spec mapping, *gesture* can be simply the keyword :gesture-spec, which matches any keyboard input. For specific mappings, *gesture* is a list

(:gesture-spec data [modifier]*)

in which data is a character object or an integer between 0 and char-code-limit (interpreted as the character object obtained by code-char), or a keyword naming a function key, and each modifier is one of the keywords:shift,:control and:meta. Note that the:meta modifier is received only when the keys style is:emacs (see interface-keys-style).

Also data can be a string which is interpreted as a Gesture Spec as if by sys:coerce-to-gesture-spec. See the Lisp-Works User Guide and Reference Manual for a description of this and other functions for manipulating Gesture Spec objects.

Note: on Cocoa you cannot receive Command key gestures via Gesture Spec mapping in *input-model*. To receive Command key gestures you should add corresponding menu items with accelerators. See menu-item for information about accelerators.

In a character mapping, gesture can be simply the keyword :character, which matches any character input. For specific mappings, gesture can be a list containing a single character object char, or a list

(char)

Note: where input would match both a Gesture Spec mapping and a character mapping, the Gesture Spec mapping takes precedence.

In a button mapping, gesture should be list

(button action [modifiers]*)

where button is one of :button-1, :button-2 or :button-3 denoting the mouse buttons. action is one of :press, :release, :second-press, :third-press, :nth-press and :motion, and each modifier is one of the keywords :shift, :control, :meta and :hyper. The :meta modifier will be the Alt key on most keyboards. On Cocoa, the :hyper modifier is interpreted as the Command key for button and motion gestures. On Windows, the :hyper modifier is currently never generated, so gestures mappings using it will never be invoked.:third-press and :nth-press are supported only on Cocoa and Motif.

Key mappings are intended for detecting low-level keyboard input. In a key mapping, *gesture* should be a list

(:key [keyname] action [modifiers] *)

where the optional keyname is a character naming a key (no modifiers) or one of the valid Gesture Spec keywords, action is one of :press or :release and each modifier is one of the keywords :shift, :control and :meta. The callback will receive a Gesture Spec object, with its data set to an integer ASCII code or a keyword representing the primary item on the key and its modifiers representing the set of modifiers pressed. The :meta modifier will be the Alt key on most keyboards. On Cocoa, the :hyper modifier is interpreted as the Command key for :key input.

In a motion mapping, gesture can either be defined in terms of dragging a button (in which case it is defined as a button gesture with action: motion), or it can be defined for motions whilst no button is down by just specifying the keyword: motion with no additional arguments.

In a command mapping, gesture should be a command which is defined using define-command, and provides an alias for a gesture. The following commands are predefined:

:control-post-menu

(:button-3 :press :control) on Microsoft Windows, Motif and Mac OS X.

:keyboard-post-menu

(:gesture-spec :f10 :shift) on Microsoft Windows, Motif and Mac OS X.

Note that it is recommended you follow the style guidelines and conventions of the platform you are developing for when mapping gestures to results.

When user input matches *gesture*, *callback* is called with standard arguments and any *extra-callback-args* as extra arguments. The standard arguments are the output-pane, the x cursor position, the y cursor position, and in the case of Gesture Spec, character or key mappings, the input object that matched.

Button mappings with action :press are matched on the first button click, and they pass the standard arguments to their callback. Button mappings with action :second-press and :third-press are matched on the second and third button click made in quick succession, and again they pass the standard arguments to their callback. Button mappings with action :nth-press are matched on the nth button click made in quick succession when there is not a more specific match with :press, :second-press or :third-press. Then the integer n is also passed as the fourth argument to callback, representing the number of times that the button has been pressed in quick succession. If there is a :press, :second-press or :third-press handler then that is invoked instead of :nth-press for the corresponding number of presses.

Note: mouse gestures with :press, :second-press, :third-press and :nth-press actions can each be expected to be followed by a :release action.

Note: In some circumstances :motion events can be received even when the output-pane does not have the input focus. See window style :motion-events-without-focus under interface for details.

input-model can be set before the pane is displayed, but changes after that are ignored.

Also note that some built-in subclasses of output-pane specify their own *input-model*, so care should be taken when setting it. Generally an initial value supplied using the :input-model initarg will be prepended to any *input-model* specified by the built-in subclass (so your input gestures will override matching supplied gestures). However this is not true of editor-pane, where the :input-model initarg replaces the specified default *input-model*.

If pane-can-scroll is true then the pane is responsible for handling scrolling, by redrawing. It should draw into the visible area according to the scroll parameters. This is known as internal scrolling and an example is editor-pane. If pane-can-scroll is nil, then the CAPI is responsible for scrolling over the data range. The default value is nil. This is known as ordinary scrolling and there is an example in output-panes/scroll-test.lisp.

When the output pane is scrolled, the CAPI calls the *scroll-callback* if this is non-nil. The arguments of the scroll callback are the output-pane, the direction (:vertical, :horizon-tal or :pan), the scroll operation (:move, :drag, :step or :page), the amount of scrolling (an integer), and a keyword argument :interactive. This has value t if the scroll was invoked interactively, and value nil if the scroll was programmatic, such as via the function scroll. In the Mac OS X Cocoa implementation the direction is always :pan. See the following CAPI example files:

```
output-panes/scroll-test.lisp
output-panes/scrolling-without-bar.lisp
graphics/scrolling-test.lisp
```

focus-callback, if non-nil, is a function of two arguments. The first argument is the output-pane itself, and the second is a boolean. When the output-pane gets the focus, focus-callback is called with second argument t, and when the output-pane loses the focus, focus-callback is called with second argument nil.

resize-callback, if non-nil, is a function of five arguments called when the output-pane is resized. The first argument is the output-pane itself, and the rest are its new geometry: x, y, width and height.

create-callback, if non-nil, is a function of one argument which is called just after the pane is created (but before it becomes visible). The argument is the pane itself. This function can perform initialization such as loading images.

destroy-callback, if non-nil, is a function of one argument which is called just before the pane is destroyed, for example when the window is closed or the pane is removed from its layout. The argument is the pane itself. This function can perform cleanup operations (though note that images associated with the pane are automatically freed).

use-native-input-method should be nil, tor:default. If use-native-input-method is not supplied, or is:default, the default is used, which is controlled by set-default-use-native-input-method. The default setting is always to use native input methods.

composition-callback is a function with signature

composition-callback pane what

where pane is the output pane and what can be one of:

:start The composition operation is starting.

end The composition ends.

A list

A plist describing the "preedit" string, which is a string containing the partial input that should be displayed while the composition is ongoing. These calls with a plist occur only when the underlying system does not display the partial input itself. Currently on Microsoft Windows the system always displays the preedit string itself, so these calls occur only on GTK+ and Cocoa.

During composition there will be repeated calls with a list, in general each time that the preedit string changes. Each call is a complete description of what needs to be displayed. The data from previous calls should be ignored.

The keys that can appear in the plist are currently:

:string-face-lists

The value is a list where each element is itself a list, where the first element is a string and the second a plist describing a face (a face plist). The strings are the strings that need to be displayed, and the face plist describing the face that the underlying GUI thinks that each string needs to be displayed. The face plist may contain any of the following keywords: :foreground, :back-ground, :font, :bold-p, :italic-p, :underline-p. The argument string-face-lists may be nil, which means display nothing.

:cursor

The argument is an integer describing where the "cursor" should be displayed. The index is into the string that is concatenation of the strings in *string-face-lists*.

:selected-range

If present, the value specifies the selected range as a cons of start and length in characters. The start is an index into the string that is a concatenation of the strings in the *string-face-list*.

:selection-needs-face

A boolean specifying whether the *selected-range* should have a different face to the unselected range.

The editor uses the :start call to position the composition window at the cursor by using set-composition-placement and the calls with a list to display the partial composition string.

Notes

- draw-with-buffer is typically useful for a pinboardlayout with large number of pinboard objects, or any other feature that may cause it to flicker.
- **2.** The GTK+ and Cocoa libraries always buffer, so *drawwith-buffer* is ignored on these platforms.
- 3. In GTK+ versions before 2.12 the :start and :end calls are not reliable.

Example

Firstly, here is an example that draws a circle in an output pane.

Here is an example that shows how to use a button gesture.

```
(defun test-callback (self x y)
  (capi:display-message
   "Pressed button 1 at (~S,~S) in ~S" x y self))
(capi:contain
 (make-instance
  'capi:output-pane
  :title "Press button 1:"
  :input-model `(((:button-1 :press)
                  test-callback)))
 :best-width 200 :best-height 200)
This example illustrates Gesture Spec mappings.
(defun draw-input (self x y gspec)
  (let ((data (sys:gesture-spec-data gspec))
        (mods (sys:gesture-spec-modifiers gspec)))
    (gp:draw-string
     self
     (with-output-to-string (ss)
       (sys:print-pretty-gesture-spec
        gspec ss :force-shift-for-upcase nil))
     x y)))
(capi:contain
 (make-instance
  'capi:output-pane
  :title "Press keys in the pane..."
  :input-model '((:gesture-spec
                  draw-input)))
 :best-width 200 :best-height 200)
(capi:contain
 (make-instance
  'capi:output-pane
  :title "Press Control-a in the pane..."
  :input-model '(((:gesture-spec "Control-a")
                  draw-input)))
 :best-width 200 :best-height 200)
```

Here is a simple example that draws the character typed at the cursor point.

```
(defun draw-character (self x y character)
  (gp:draw-character self character x y))
(capi:contain
 (make-instance
  'capi:output-pane
  :title "Press keys in the pane..."
  :input-model '((:character draw-character)))
 :best-width 200 :best-height 200)
This example shows how to use the motion gesture.
(defun draw-red-blob (self x y)
  (gp:draw-circle self x y 3
                   :filled t
                   :foreground :red))
(capi:contain
 (make-instance
  'capi:output-pane
  :title "Drag button-1 across this pane."
  :input-model '(((:button-1 :motion)
                   gp:draw-point)
                  ((:button-1 :motion :control)
                   draw-red-blob)))
 :best-width 200 :best-height 200)
This example illustrates the use of focus-callback:
(capi:contain
 (make-instance
  'capi:output-pane
  :focus-callback
  #'(lambda (x y)
      (format t
              "Pane ~a ~: [lost~;got~] the focus~%"
              x y))))
```

This example illustrates the use of *graphics-options* to specify ATSUI drawing on Cocoa:

```
(defvar *string*
                (coerce (loop for i from 0 below 60
                             collect (code-char (* 5 i)))
                        'text-string))
             (capi:contain
               (make-instance 'capi:output-pane
                             :visible-min-width 400
                              :visible-max-height 50
                              :display-callback
                             #'(lambda (pane x y w h)
                                  (gp:draw-string pane
                                                  *string*
                                                  10 10))
                              :graphics-options
                              '(:text-rendering :atsui)))
             This example illustrates some effects of drawing-mode:
             examples/capi/graphics/catherine-wheel.lisp
             There are further examples in the directory
             examples/capi/output-panes/.
See also
             define-command
             pinboard-object
             scroll
             set-default-use-native-input-method
             set-composition-placement
```

over-pinboard-object-p

Signature

Generic Function

Summary	Tests whether a point lies within the boundary of a pinboard object.
Package	capi

over-pinboard-object-p pinboard-object x y

Description

The generic function over-pinboard-object-p returns nonnil if the x and y coordinates specify a point within the boundary of a pinboard object. To find the actual object at this position, use pinboard-object-at-position.

The default method returns t if x and y are within the bounding area of the pinboard object. A method is supplied for line-pinboard-object and you may add methods for your own pinboard-object subclasses.

See also

pinboard-object-at-position
pinboard-object-overlap-p
pinboard-object
pinboard-layout

page-setup-dialog

Function

Summary Displays the page setup dialog for a given printer.

Package capi

Signature page-setup-dialog &key screen owner printer continuation

Description

The page-setup-dialog function displays the page setup dialog for *printer*. If *printer* is not specified, the dialog for the current printer is displayed.

The CAPI screen on which to display the dialog is given by *screen*, which is the current screen by default.

owner specifies an owner window for the dialog. See the "Prompting for Input" chapter in the *CAPI User Guide* for details.

If *continuation* is non-nil, then it must be a function with a lambda list that accepts one argument. The *continuation* function is called with the values that would normally be returned by page-setup-dialog. On Cocoa, passing *contin-*

uation causes the dialog to be made as a window-modal sheet and display-dialog returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

See also current-printer

pane-adjusted-offset

Generic Function

Summary The pane-adjusted-offset generic function calculates the

offset required to place a pane correctly in a layout.

Package capi

Signature pane-adjusted-offset pane adjust available-size actual-size

&key &allow-other-keys

Description This function calculates the offset required by the *adjust*

keyword so that the pane *pane* is placed correctly within the available space in its parent layout. It is called by all of the layouts that inherit from x-y-adjustable-layout to inter-

pret the values of *x-adjust* and *y-adjust*.

Typically the value of *adjust* will be a keyword or a list of the form (*keyword n*) where *n* is an integer. These values of *adjust* are interpreted as by pane-adjusted-position.

However, new methods can accept alternative values for *adjust* where required and can also add extra keywords. For example, grid-layout allows *adjust* to be a list of adjust values, and then passes the offset into this list as an additional

keyword.

Notes Only a keyword value for *adjust* should be supplied when

pane is a column-layout or row-layout.

Example (setq button-panel (make-instance 'capi:button-panel

:items '(1 2 3)))

See also layout

x-y-adjustable-layout

pane-adjusted-position

Generic Function

Summary Calculates how to place a pane correctly within a layout,

given a minimum and maximum position.

Package capi

Signature pane-adjusted-position pane adjust min-position max-position

&key &allow-other-keys

Description The pane-adjusted-position generic function calculates

the position required by the *adjust* argument so that the pane pane is placed correctly within the available space in its parent layout, given a minimum and maximum position. It is a complementary function to pane-adjusted-offset, and the default method actually calls pane-adjusted-offset with the gap between the two positions, and then adds on the minimum position to get the new position.

The default method accepts the following values for adjust.

Place pane at the top of the region.

:bottom Place pane at the bottom of the region.

:left Place *pane* at the left of the region.

right Place pane at the right of the region.

:center Place pane in the center of the region.

(:top n)	Place the top of <i>pane n</i> pixels below the top of the region.
(:bottom n)	Place the bottom of <i>pane n</i> pixels above the bottom of the region.
(:left <i>n</i>)	Place the left of <i>pane n</i> pixels after the left of the region.
(:right <i>n</i>)	Place the right of <i>pane n</i> pixels before the right of the region.
(:center n)	Place the center of <i>pane n</i> pixels below the center of the region.

However, new methods can accept alternative values for adjust where required and can also add extra keywords. For example, grid-layout allows adjust to be a list of adjust values, and then passes the offset into this list as an additional keyword. It is preferable to add new methods to pane-adjusted-offset as these changes will be seen by the default method of pane-adjusted-position.

```
Example (setq button-panel (make-instance 'capi:button-panel :items '(1 2 3)))

(capi:pane-adjusted-position button-panel :center 100 200)

(capi:pane-adjusted-position button-panel :right 100 200)

(capi:pane-adjusted-position button-panel :left 100 200)

See also layout graph-pane x-y-adjustable-layout
```

pane-close-display

Function

Summary Closes the X display of a pane.

Package capi

Signature pane-close-display pane => closedp

Arguments pane A CAPI element.

Values *closedp* A boolean.

Description The function pane-close-display closes the X display

connection on which *pane* is currently displayed. This destroys all the other panes on the same connection.

closedp is true if the connection was closed.

Notes pane-close-display works in the X11/Motif implementa-

tion only, and not on Microsoft Windows.

pane-descendant-child-with-focus

Function

Summary Finds the child with the input focus.

Signature pane-descendant-child-with-focus pane => result

Arguments pane A pane or layout.

Values result A pane or nil.

Description The function pane-descendant-child-with-focus

attempts to find the pane inside pane that currently has the

input focus, and returns this pane if successful.

pane-descendant-child-with-focus may return nil if it

does not find a pane with the focus.

See also pane-has-focus-p

pane-got-focus

Generic Function

Summary A function called when the focus is set programmatically.

Package capi

Signature pane-got-focus interface pane

Arguments interface The interface of pane.

pane A CAPI element.

Description The generic function pane-got-focus is called just before

the focus is set by set-object-automatic-resize.

The supplied primary method does nothing. You may add methods on your own interface classes, which can be useful for example when the focus is set programmatically to a pane which is hidden inside a tab-layout or switchable-layout. Your method can check for this case and modify the

layout as required.

See also set-object-automatic-resize

pane-has-focus-p

Generic Function

Summary Determines whether a pane has the focus.

Package capi

Signature pane-has-focus-p pane => focusp

Arguments pane A CAPI element.

Values *focusp* A boolean.

Description The function pane-has-focus-p is the predicate for whether

pane currently has the input focus.

Notes On Motif, pane-has-focus-p cannot be used in menu func-

tions such as the *enabled-function* or *popup-callback* of a menu item. It will always return mil, because the focus is on the

menu button when the user clicks on it.

See also accepts-focus-p

pane-descendant-child-with-focus
set-object-automatic-resize

pane-initial-focus

Generic Function

Summary Gets or sets the initial focus pane.

Package capi

Signature pane-initial-focus pane-with-children => pane

Signature (setf pane-initial-focus) pane pane-with-children => pane

Arguments pane-with-children

A pane with children.

Values pane A child of pane-with-children.

Description The generic function pane-initial-focus returns the child

of pane-with-children that has the input focus when pane-with-

children is first displayed.

(setf pane-initial-focus) may be used to set the initial focus pane, but only before *pane-with-children* has been created. If the setter is called after *pane-with-children* has been created, an error is signalled.

1 CAPI Reference Entries

pane-with-children should be a pane with child panes such as a layout, an interface, a button-panel or a toolbar.

See also pane-has-focus-p

pane-interface-copy-object pane-interface-cut-object pane-interface-cut-p pane-interface-deselect-all pane-interface-deselect-all-p pane-interface-paste-object pane-interface-select-all pane-interface-select-all-p pane-interface-undo pane-interface-undo

Generic Functions

Summary Implements "edit/select operations" and the associated pred-

icates for the active pane.

Signature pane-interface-copy-object pane interface => object, string,

plist

pane-interface-copy-p pane interface

pane-interface-cut-object pane interface

pane-interface-cut-p pane interface

pane-interface-deselect-all pane interface

pane-interface-deselect-all-p pane interface

pane-interface-paste-object pane interface

pane-interface-paste-p pane interface

pane-interface-select-all pane interface

pane-interface-select-all-p pane interface

pane-interface-undo pane interface

pane-interface-undo-p pane interface

Description

The active pane "edit/select operations" call these generic functions when the active pane does not specify how to perform the operation. Do not call these directly.

interface is the top level interface of the pane. The predicate functions (those with names ending with -p) should return true if the operation can be performed. The other functions should perform the operations.

You can implement your own methods specializing on pane and interface classes.

Notes

- 1. These generic functions should not display a dialog or do anything that may cause the system to hang. In general this means interacting with anything outside the Lisp image, including files, databases and so on.
- 2. The three return values of pane-interface-copyobject are passed to set-clipboard.

See also

active-pane-copy
item-pane-interface-copy-object
set-clipboard

pane-popup-menu-items

Generic Function

Summary Generates the items for the menu associated with a pane.

Package capi

Signature pane-popup-menu-items pane interface => items

Arguments pane A pane in interface interface.

interface An interface.

Values items A list in which each element is a menu-item,

menu-component or menu.

Description

The generic function pane-popup-menu-items generates the items for the menu associated with the pane pane. The default method of make-pane-popup-menu calls pane-popup-menu-items to find the items for the menu. If pane-popup-menu-items returns nil, then make-pane-popup-menu returns nil.

To specify items for menus associated with panes in your interfaces, define pane-popup-menu-items methods specialized on your interface class.

For most supplied CAPI pane classes, the system method returns nil. The exceptions are editor-pane and graph-pane. To inherit the items from the system method (or other more general method), call call-next-method.

Notes

- 1. pane-popup-menu-items is not supported for text panes on Cocoa such as rich-text-pane.
- 2. pane-popup-menu-items is intended to allow multiple calls on the same pane, to generate menus in different places (as in the example in make-pane-popup-menu). Therefore the menu-objects that it returns, and their descendent menu-objects, must be constructed each time that pane-popup-menu-items is called, so that no two menus share any menu item.
- 3. The *items* returned by pane-popup-menu-items may specify the arguments for their callbacks, but it is not required. If they do not specify the arguments, then make-pane-popup-menu (by calling make-menu-for-pane) sets up the callbacks such that they are called on the pane pane.

Example The methods below specialized on interface class edgraph:

- Append the items that were returned by the system method in the bottom of the menu for the editor-pane, and
- 2. Add them as a sub-menu for the menu of the graph-pane.

```
(capi:define-interface edgraph ()
  ()
  (:panes
   (el capi:editor-pane)
   (gl capi:graph-pane))
  (:layouts
   (main-layout capi:column-layout '(e1 g1)))
  (:menu-bar )
  (:default-initargs
   :visible-min-width 200
   :visible-min-height 300))
(defun my-callback (pane)
  (capi:display-message "Callback on pane ~S." pane))
(defmethod capi:pane-popup-menu-items
          ((self capi:editor-pane) (interface edgraph))
  (list*
   (make-instance 'capi:menu-item
                  :title "Item for My Editor Menu."
                  :selection-callback 'my-callback)
   (call-next-method)))
(defmethod capi:pane-popup-menu-items
           ((self capi:graph-pane) (interface edgraph))
  (list
   (make-instance 'capi:menu-item
                  :title "Item for My Graph Menu."
                  :selection-callback 'my-callback)
   (capi:make-menu-for-pane self (call-next-method)
                          :title "Default Graph Menu")))
(capi:display (make-instance 'edgraph))
There is a further example in:
examples/capi/elements/pane-popup-menu-items.lisp
```

See also make-pane-popup-menu

pane-screen-internal-geometry

Function

Summary Returns the internal geometry of the monitor in which a

pane's interface is displayed.

Package capi

Signature pane-screen-internal-geometry pane $\Rightarrow x, y, width, height$

Arguments *pane* A CAPI pane.

Values x An integer.

y An integer.

width A positive integer.

height A positive integer.

Description

The function pane-screen-internal-geometry returns the internal geometry of the "monitor" in which the interface that contains *pane* is displayed. A "monitor" is typically a physical monitor, but can be anything that the underlying GUI system considers a monitor.

pane must be inside an interface that is already displayed.

pane-screen-internal-geometry returns the internal
geometry of the monitor on which this interface is displayed.

If the interface spreads across multiple monitors, it returns
the geometry for the monitor on which the largest area of the
interface is displayed.

The internal geometry of a monitor is a rectangle which excludes "system areas" like taskbars and global menu bars and so on. Examples of these include the Windows taskbar, the Mac OS X menu bar, and the Mac OS X dock. See screen-internal-geometry for information about displaying CAPI windows in system areas.

x, *y*, *width* and *height* specify a screen rectangle, in which the *x* and *y* coordinates are offsets from the top-left of the primary monitor.

Notes

On GTK+ the internal geometry is of the workspace in which the interface is displayed. When there are multiple monitors these values may be incorrect. You can check the number of monitors by screen-monitor-geometries.

See also

screen-internal-geometry screen-internal-geometries virtual-screen-geometry

pane-string Generic Function

Summary Returns the text displayed in an editor-pane.

Package capi

Signature pane-string pane => text

Arguments pane An editor-pane.

Values *text* A string.

Description The generic function pane-string returns as a string the text

of the buffer that is currently displayed in the editor-pane

pane.

See also editor-pane

pane-supports-menus-with-images

Function

Summary Tests whether a pane supports menus with images.

Signature pane-supports-menus-with-images pane => result

Arguments pane A displayed CAPI pane.

Values result A boolean.

Description The function pane-supports-menus-with-images returns t

if the pane supports menus with images. This means that the menus display both the images and the text correctly.

See the $\it image-function$ of menu for details of creating a menu

with images.

When pane-supports-menus-with-images returns nil, menus can display images, but not together with text at the same item They may also display images with transparency incorrectly.

Whether the pane supports menus with images depends on the library in which it is displayed. Support is currently lim-

ited to GTK+ and Cocoa.

See also menu

parse-layout-descriptor

Generic Function

Summary Returns the geometry object associated with a layout's child.

Package capi

Signature parse-layout-descriptor child-descriptor interface layout

Description The generic function parse-layout-descriptor takes a

description of a layout's child, and returns the geometry object associated with that child. It is called by interpretdescription to parse individual children in a layout.

The default method accepts a *child-desc* argument which can be a pane (subclass of simple-pane or pinboard-object), a geometry object, or a symbol naming a slot in the interface

which contains such a pane.

See also interpret-description

define-layout

layout

password-pane Class

Summary The password pane is a pane designed for entering pass-

words, such that when the password is entered it is not visi-

ble on the screen.

Package capi

Superclasses text-input-pane

Initargs :overwrite-character

A base-char.

Readers password-pane-overwrite-character

Description The password pane inherits most of its functionality from

text-input-pane. It starts with the initial text and caret position specified by the arguments *text* and *caret-position* respectively, and limits the number of characters entered with the *max-characters* argument (which defaults to nil,

meaning there is no maximum).

The password pane can be enabled and disabled with the text-input-pane accessor text-input-pane-enabled.

overwrite-character is a base-char which is the character to display instead of the real characters. The default value of overwrite-character is #*.

Example

```
(setq password-pane (capi:contain
                      (make-instance
                      'capi:password-pane
                      :callback
                      #'(lambda (password interface)
                                 (capi:display-message
                                 "Password: ~A"
                                 password)))))
(capi:text-input-pane-text password-pane)
(setq password-pane
      (capi:contain
       (make-instance 'capi:password-pane
                      :max-characters 5
                      :text "abc"
                      :overwrite-character #\$)))
(capi:password-pane-overwrite-character password-pane2)
```

See also editor-pane

text-input-pane

play-sound

Function

Summary Plays a loaded sound on Microsoft Windows and Cocoa.

Package capi

Signature play-sound sound &key wait

Arguments sound A sound object returned by load-sound.

wait A generalized boolean.

Description The function play-sound plays the loaded sound sound.

If wait is true then play-sound will not return until sound has finished playing. That is, it plays the sound synchronously.

The default value of wait is nil.

Notes 1. :wait t is only implemented on Microsoft Windows.

2. play-sound is not implemented on GTK+ and Motif.

See also load-sound

stop-sound

pinboard-layout

Class

Summary The class pinboard-layout provides two very useful pieces

of functionality for displaying CAPI windows. Firstly it is a subclass of static-layout and so it allows its children to be positioned anywhere within itself (like a pinboard). Secondly it supports pinboard-objects which are rectangular areas within the layout which have size and drawing functionality.

Package capi

Superclasses output-pane

static-layout

Subclasses simple-pinboard-layout

InitargS :highlight-style

A keyword.

Description When a pinboard-layout lays out its children, it positions

them at the x and y specified as hints (using :x and :y), and sizes them to their minimum size (which can be specified using :visible-min-width and :visible-max-width).

By default, the pinboard-layout is made sufficiently large to accommodate all of its children, as specified by fit-size-to-children in the superclass static-layout. Note that results in the pinboard resizing itself automatically when objects are added, moved or removed. If you need the sizing capabilities, then use the class simple-pinboard-layout which surrounds a single child, and adopts the size constraints of that child.

The pinboard layout handles the display of pinboard objects itself by calculating which objects are visible in the region that needs redrawing, and then by calling the generic function draw-pinboard-object on these objects in the order that they are specified in the layout description. This means that if two pinboard objects overlap, the later one in the layout description will be on top of the other one. In other words, the description defines the Z-order for objects of type pinboard-object. For information about controlling this order, see layout and manipulate-pinboard.

Note: objects of type simple-pane are drawn directly by the windowing system and cannot be clipped relative to pin-board-objects, which are drawn by CAPI. Therefore simple-panes always appear on top in a pinboard, and their position in the description does not affect the Z-order.

Highlighting of the layout's children by highlight-pin-board-object is controlled by the value of *highlight-style*, as follows:

:invert Swaps the foreground and background col-

ors.

:standard Uses system colors.

:default Calls draw-pinboard-object-high-

lighted.

The default value of *highlight-style* is :default.

Notes

- The output-pane initarg :drawing-mode controls quality of drawing in a pinboard-layout, including antialiasing of any text displayed on Microsoft Windows and GTK+.
- 2. If redrawing flickers on Microsoft Windows or Motif, perhaps because there are many pinboard objects, you can pass the output-pane initarg :draw-with-buffer t, which uses a pixmap to buffer the output before drawing it to the screen. See output-pane for more information.

Example

Here are some examples of the use of pinboard objects with pinboard layouts.

```
(capi:contain
 (make-instance
  'capi:pinboard-layout
  :description
  (list
   (make-instance
    'capi:image-pinboard-object
   :image
    (sys:lispworks-file
     "examples/capi/graphics/Setup.bmp")
    :x 20 :y 20)))
:best-width 540 :best-height 415)
(capi:contain
 (make-instance
  'capi:pinboard-layout
  :description (list
                 (make-instance
                 'capi:item-pinboard-object
                 :text "Hello"
                 :x 40 :y 10)
                 (make-instance
                 'capi:line-pinboard-object
                 :x 10 :y 30
                 :visible-min-width 100)))
                :best-width 200 :best-height 200)
```

There are further examples in the directories examples/capi/applications/ and examples/capi/graphics/.

This example illustrates use of *draw-with-buffer* t:

examples/capi/graphics/compositing-mode.lisp

See also manipulate-pinboard

output-pane

pinboard-object

redraw-pinboard-object

static-layout

pinboard-object

Class

Summary Provides a rectangular area in a pinboard-layout with

drawing capabilities.

Package capi

Superclasses capi-object

Subclasses ellipse

item-pinboard-object
image-pinboard-object
line-pinboard-object
drawn-pinboard-object

rectangle

Initargs :pinboard The output pane on which the pinboard

object is drawn.

:activep If t, the pinboard object is made active.

:graphics-args

A plist of Graphics Ports drawing options.

:automatic-resize

A plist.

The following initargs are geometry hints, influencing the initial size and position of a pinboard-object:

The x position of the pinboard object in the pinboard.

The *y* position of the pinboard object in the pinboard.

:external-min-width

The minimum width of the pinboard object in the pinboard.

:external-min-height

The minimum height of the pinboard object in the pinboard.

:external-max-width

The maximum width of the pinboard object in the pinboard.

:external-max-height

The maximum height of the pinboard object in the pinboard.

:visible-min-width

The minimum visible width of the pinboard object.

:visible-min-height

The minimum visible height of the pinboard object.

:visible-max-width

The maximum visible width of the pinboard object.

:visible-max-height

The maximum height of the pinboard object.

:internal-min-width

The minimum width of the display region.

:internal-min-height

The minimum height of the display region.

:internal-max-width

The maximum width of the display region.

:internal-max-height

The maximum height of the display region.

Accessors pinboard-object-pinboard

pinboard-object-activep

pinboard-object-graphics-args

Description The class pinboard-object provides a rectangular area in a

pinboard-layout with drawing and highlighting capabilities. A pinboard object behaves just like a simple pane within layouts, meaning that they can be placed into rows, columns and other layouts, and that they size themselves in the same way. The main distinction is that a pinboard object is a much smaller object than a simple pane as it does not need to create a native window for itself.

Each pinboard object is placed into a pinboard layout (or into a layout itself inside a pinboard layout), and then when the pinboard layout wishes to redisplay a region of itself, it calls the function draw-pinboard-object on each of the pinboard objects that are contained in that region (in the order that they are specified as children to the layout).

The *graphics-args* slot allows drawing options to be set. These include the font, the background and foreground colors, and others (see graphics-state).

The geometry hints are interpreted as described for element.

By default a pinboard-object does not accept the input focus.

There are a number of predefined pinboard objects provided by the CAPI. They are as follows:

ellipse Draws an ellipse.

rectangle Draws a rectangle.

item-pinboard-object

Draws a title.

line-pinboard-object

Draws a line.

right-angle-line-pinboard-object

Draws a right-angled line.

image-pinboard-object

Draws an image.

drawn-pinboard-object

Uses a user-defined display function.

The main user of pinboard objects in the CAPI is the graph pane, which uses item-pinboard-object and line-pinboard-object to display its nodes and edges respectively.

To force a pinboard object to redraw itself, either call the function invalidate-rectangle on it (in which case the redrawing is done immediately), or call redraw-pinboard-object in which case the redrawing may be cached and displayed at a later date.

Call the generic functions highlight-pinboard-object and unhighlight-pinboard-object to highlight a pinboard and remove its highlighting. If you want non-standard highlighting, you can implement methods for your subclass of pinboard-object.

You can test whether a whether a point or region coincides with a pinboard object by the generic functions over-pin-board-object-p and pinboard-object-overlap-p. The default methods assume a rectangle based on the geometry, which must always be the enclosing rectangle of the whole pinboard object. Therefore you only need to implement methods if your subclass of pinboard-object has a non-rectangular shape.

automatic-resize makes the pinboard object resize automatically. This has an effect only if it is placed inside a static-layout (including subclasses like pinboard-layout). The effect is that when the static-layout is resized then the pinboard object also changes its geometry.

The value of *automatic-resize* defines how the pinboard object's geometry changes. It must be a plist of keywords and values which match the keywords of the function set-object-automatic-resize and are interpreted in the same way.

Notes You can also control automatic resizing of a pinboard object

using set-object-automatic-resize.

Example See the file examples/capi/graphics/pinboard-

test.lisp.

See also pinboard-layout

draw-pinboard-object

graph-pane

highlight-pinboard-object over-pinboard-object-p redraw-pinboard-object redraw-pinboard-layout pinboard-object-overlap-p set-object-automatic-resize unhighlight-pinboard-object

pinboard-object-at-position

Generic Function

Summary The generic function pinboard-object-at-position

returns the uppermost pinboard object containing a specified

point.

Package capi

Signature pinboard-object-at-position pinboard x y

Description This function returns the uppermost pinboard object in the

pinboard that contains the point specified by *x* and *y*. It determines this by mapping over every pinboard object within the pinboard until it finds one for which the generic function

over-pinboard-object-p returns t.

Example (setq pinboard

(capi:contain (make-instance

'capi:pinboard-layout)

:best-width 300
:best-height 300))

(make-instance 'capi:item-pinboard-object

:text "Hello world"
:x 100 :y 100
:parent pinboard)

(capi:pinboard-object-at-position pinboard 0 0)

(capi:pinboard-object-at-position pinboard 110 110)

See also over-pinboard-object-p

pinboard-object-overlap-p

pinboard-object
pinboard-layout

pinboard-object-graphics-arg

Generic Function

Summary Gets or sets the value of a particular drawing parameter in a

pinboard-object.

Package capi

Signature pinboard-object-graphics-arg self keyword => value

Signature (setf pinboard-object-graphics-arg) value self keyword =>

value

1 CAPI Reference Entries

Arguments self A pinboard-object.

keyword A keyword denoting a graphics state param-

eter.

Values value The value of the drawing option keyword in

self.

Description The generic function pinboard-object-graphics-arg

returns or sets the value of the graphics state parameter

keyword in self.

See graphics-state for details of the drawing parameters.

See also graphics-state

pinboard-object

pinboard-object-overlap-p

Generic Function

Summary Tests whether a specified region overlaps with the region of a

pinboard object.

Package capi

Signature pinboard-object-overlap-p pinboard-object top-left-x top-left-y

 $bottom\text{-}right\text{-}x\ bottom\text{-}right\text{-}y\ =>\ result$

Description The generic function pinboard-object-overlap-p returns

true if the region of the pinboard object pinboard-object over-

laps with the region specified by the other arguments.

See also pinboard-object-at-position

over-pinboard-object-p

pinboard-object
pinboard-layout

pinboard-pane-position

Generic Function

Summary Gets and sets the location of an object inside its parent pin-

board-layout.

Package capi

Signature pinboard-pane-position self => x, y

setf (pinboard-pane-position self) (values x y) => x, y

Arguments self A pinboard-object or simple-pane.

Values x, y The horizontal and vertical coordinates in

the pinboard-layout parent of self.

Description The generic function pinboard-pane-position returns as

multiple values *x*, *y* the coordinates of *self* inside its parent

pinboard-layout.

There is also a setf expansion which sets the location of self

in its parent.

```
Example
              (let* ((po (make-instance 'capi:item-pinboard-object
                                         :text "5x5" :x 5 :y 5
                                         :graphics-args
                                         '(:background :red)))
                     (pl (capi:contain
                          (make-instance 'capi:pinboard-layout
                                          :description (list po)
                                          :visible-min-width 200
                                          :visible-min-height 200))))
                (capi:execute-with-interface
                 (capi:element-interface pl)
                 #'(lambda (po)
                     (dotimes (x 20)
                       (mp:wait-processing-events 1)
                       (let ((new-x (* (1+ x) 10))
                             (new-y (* 5 (+ 2 x))))
                         (setf (capi:item-text po)
                                (format nil "~ax~a" new-x new-y))
                         (setf (capi:pinboard-pane-position po)
                               (values new-x new-y)))))
                 ((og
See also
             pinboard-layout
              pinboard-pane-size
```

pinboard-pane-size

self.

Generic Function

Gets and sets the size of an object inside its parent pinboard-layout.

Package capi

Signature pinboard-pane-size self => width, height

setf (pinboard-pane-size self) (values width height) => width, height

Description The generic function pinboard-pane-size returns as multiple values width, height the dimensions of self.

There is also a setf expansion which sets the dimensions of

412

```
Example
              (let* ((po (make-instance 'capi:pinboard-object
                                         :x 5 :v 5
                                         :width 5 :height 5
                                         :graphics-args
                                         '(:background :red)))
                     (pl (capi:contain
                          (make-instance 'capi:pinboard-layout
                                          :description (list po)
                                          :visible-min-width 200
                                          :visible-min-height 200))))
                (capi:execute-with-interface
                 (capi:element-interface pl)
                 #'(lambda(po)
                     (dotimes (x 20)
                       (mp:wait-processing-events 1)
                       (let ((new-x (* (1+ x) 10))
                             (new-y (* 5 (+ 2 x))))
                         (setf (capi:pinboard-pane-size po)
                               (values new-x new-y)))))
                 po))
See also
             pinboard-layout
              pinboard-pane-position
```

popup-confirmer

Function

Summary

The popup-confirmer function creates a dialog with predefined implementations of **OK** and **Cancel** buttons and a user specified pane in a layout with the buttons.

Package

capi

Signature

popup-confirmer pane message &rest interface-args &key modal title title-font value-function exit-function apply-function apply-check apply-button ok-function ok-check ok-button no-button no-function all-button all-function cancel-button help-button help-function buttons print-function callbacks callback-type button-position buttons-uniform-size-p foreground background font screen focus owner x y position-relative-to button-container button-font continuation callback-error-handler => result, successp

Arguments pane

A CAPI pane or interface.

message A string or nil.

modal, screen, focus, owner, x, y, and position-relative-to

These are passed to display-dialog.

title A string specifying the title of the dialog

window.

title-font The font used in the title.

value-function Controls the value returned, and whether a

value can be returned.

exit-function Called on exiting the dialog.

apply-function, apply-check, apply-button

Define the callback, check function and title

an Apply button.

ok-function, ok-check, ok-button

Define the callback, check function and title

of an OK button.

no-button, no-function

Define the title and callback of a **No** button.

all-button, all-function

Define the title and callback of an All button.

cancel-button Defines the title of a Cancel button.

help-button, help-function

Define the title and callback of a **Help** button.

buttons Defines extra buttons.

print-function Displays ok-button, no-button, cancel-button,

apply-button and all-button as button titles.

callbacks Defines callbacks for buttons.

callback-type Specifies the callback-type of buttons.

button-position One of :bottom, :top, :left, :right.

buttons-uniform-size-p

Controls relative button sizes.

foreground, background

Specify colors.

font A font or a font description.

button-font A font or a font description.

button-container A layout controlling where the buttons of

the dialog appear.

continuation A function or mil.

callback-error-handler

A function designator or nil.

Values result The result of value-function, or pane, or nil.

successp nil if the dialog was cancelled, t otherwise.

Description

The function popup-confirmer provides the quickest means to create new dialogs, as it will create and implement **OK**, **Cancel** and other buttons as required by your dialog, and will place a user-specified pane in a layout along with the buttons.

Generally the Return key selects the dialog's **OK** button and the Escape key selects the **Cancel** button, if there is one.

The argument *value-function* should provide a callback which is passed *pane* and should return the value to return from <code>popup-confirmer</code>. If *value-function* is not supplied, then *pane* itself will be returned as *result*. If the *value-function* wants to indicate that the dialog cannot return a value currently, then it should return a second value that is non-nil.

The *ok-check* function is passed the result returned by the *value-function* and should return true if it is acceptable for that value to be returned. These two functions are used by popup-confirmer to decide when the **OK** button should be

enabled, thus stopping the dialog from returning with invalid data. The **OK** button's state can be updated by a call to redisplay-interface on the top-level, so the dialog should call it when the button may enable or disable.

The arguments ok-button, no-button and cancel-button are the text strings for each button, or nil meaning do not include that button. The ok-button returns successfully from the dialog (with the result of value-function), the no-button means continue but return nil, and the cancel-button aborts the dialog. Note that there are clear expectations on the part of users as to the functions of these buttons — check the style guidelines of the platform you are developing for.

apply-button, if passed, specifies the title of an extra button which appears near to the **OK** button. *apply-check* and *apply-function* define its functionality.

all-button, if passed, specifies the title of an extra button which is always enabled and which appears near to the *apply-button* (if that exists) or the **OK** button. *all-function* defines its functionality.

help-button, if passed, specifies the title of a help button which appears to the right of the **Cancel** button. *help-function* defines its functionality.

print-function is called on the various *button* arguments to generate a string to display for each button title.

button-position specifies where to put the buttons. The default is :bottom.

buttons-uniform-size-p specifies whether the buttons are all the same size, regardless of the text on them. The default is t, but nil can be passed to make each button only as wide as its text.

foreground and *background* specify colors to use for the parts of the dialog other than *pane*, including the buttons

font specifies the font to use in the message.

button-font specifies the font to use in the buttons.

button-container indicates where the buttons of the dialog appear. It must be a layout which is a descendent of pane. The description of this layout is automatically set to the button-panel containing the buttons.

The arguments exit-function, ok-function and no-function are the callbacks that get done when exiting, pressing **OK** and pressing **No** respectively. The exit-function defaults to exit-confirmer, the ok-function defaults to the exit-function and the no-function defaults to a function exiting the dialog with nil.

The arguments buttons, callbacks and callback-type are provided as a means of extending the available buttons. The buttons provided by buttons will be placed after the buttons generated by popup-confirmer, with the functions in callbacks being associated with them. Finally callback-type will be provided as the callback type for the buttons.

If any of *callbacks* need to access *pane*, you could use confirmer-pane together with a *callback-type* that passes the interface.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by popup-confirmer. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and popup-confirmer returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

callback-error-handler, if non-nil, should be a function designator for a function of one argument which is a condition, like the handler-function in cl:handler-bind. The handler is established (by cl:handler-bind with type cl:error) around each callback call inside the scope of popup-confirmer or display-dialog. In recursive calls, only the handler of the innermost call to popup-confirmer or display-dialog is established.

callback-error-handler can use current-popup to find the popup (first argument to the innermost call of display-dialog or popup-confirmer).

If callback-error-handler wants to do a non-local exit, it should either call abort-callback to abort the callback but leave the dialog, or exit-dialog (or abort-dialog) to exit (or abort) the dialog.

All other arguments will be passed to the call to make-instance for the interface that will be displayed using display-dialog. Thus geometry information, colors, and so on can be passed in here as well. By default, the dialog will pick up the foreground, background and font of pane.

Notes

- 1. On Windows and Motif, the effect of callback-error-handler can be achieved by using cl:handler-bind around the call to display-dialog or popup-confirmer (the handler will also handle errors during raising the dialog, but these are not expected to happen). On Cocoa, using such an error handler does not necessarily work, because the callback may happen in another process. callback-error-handler ensures that the callback is in the scope of the handler on all plaforms. From the same reason the handler should not rely on the dynamic environment (including catchers and restarts), and needs to use current-popup to find its "context" and use abort-callback, exit-dialog or abort-dialog for non-local exit.
- 2. If the callback itself calls popup-confirmer or display-dialog, the callback-error-handler handler will stay until the callback returns. Unless the recursive call handles the error, the handler of the outer call may be called to handle it, and needs to be written to deal with this possibility correctly. If the handler inside a recursive call needs to

access the popup that was used in the same call that the handler was used, it should close over it, because current-popup returns the innermost one.

3. A handler that is established by the callback (by cl:handler-bind or cl:handler-case) is inside the scope of the callback-error-handler, and therefore will be called first.

Example

Here are two simple examples which implement the basic functionality of two CAPI prompters: the first implements a simple prompt-for-string, while the second implements prompt-for-confirmation.

This example demonstrates the use of :redisplay-interface to make the **OK** button enable and disable on each keystroke.

An example illustrating the use of :button-container:

```
(let* ((bt (make-instance 'capi:simple-layout
                          :title "Button Container"
                          :title-position :left))
       (tip1 (make-instance 'capi:text-input-pane
                            :title "Top"))
       (tip2 (make-instance 'capi:text-input-pane
                            :title "Bottom"))
       (layout (make-instance 'capi:column-layout
                              :description
                              (list tip1
                                    bt
                                    tip2))))
  (capi:popup-confirmer layout nil
                        :title
                       "Dialog using button-container"
                        :button-container bt))
```

An example with all the defined buttons in use:

```
(defun all-buttons-dialog (&optional (num 20))
  (let ((pane
         (make-instance 'capi:list-panel
                        :items
                         (loop for ii from 1
                              to num
                              collect
                               (format nil "~r" ii))
                        :visible-min-width
                        '(character 20))))
    (capi:popup-confirmer
    pane
     "All Buttons"
     :callback-type :none
     :button-position :right
     :cancel-button "Cancel Button"
     :ok-button "OK Button"
     :ok-function #'(lambda (x)
                      (declare (ignorable x))
                      (capi:exit-dialog
                      (capi:choice-selected-item pane)))
     :no-button "No Button"
     :no-function
    #'(lambda ()
         (capi:exit-dialog
          (cons :no
                (capi:choice-selected-item pane))))
     :apply-button "Apply Button"
     :apply-function
    #'(lambda ()
         (capi:display-message
          "Applying to ~a"
          (capi:choice-selected-item pane)))
     :help-button "Help Button"
     :help-function
    #'(lambda ()
         (capi:display-message
          "~a is ~: [an odd~;an even~] number"
          (capi:choice-selected-item pane)
          (oddp (capi:choice-selection pane))))
     :all-button "All Button"
     :all-function
    #'(lambda()
         (capi:exit-dialog
          (capi:collection-items pane))))))
(all-buttons-dialog)
```

A dialog with arbitrary buttons:

This example illustrates the use of callback-error-handler:

```
(defun my-error-handler (condition)
                (let ((pane (capi:current-popup)))
                  (capi:display-message
                  "Error inside dialog: ~a : ~a"
                  (capi:capi-object-name pane)
                  condition)
                  (capi:abort-callback)))
             (let*
                  ((foo-callback
                    (lambda ()
                      (let ((md (make-instance
                                 'capi:push-button
                                 :text "Error inside Callback-Error-
             Handler"
                                 :name "Chicken"
                                 :callback-type :data
                                 :data "Twisted ankle."
                                 :callback 'error)))
                        (capi:popup-confirmer
                        md nil
                        :callback-error-handler 'my-error-handler))))
                   (foo (make-instance
                        'capi:push-button
                        "Popup confirmer with Callback-Error-Handler"
                         :callback-type :none
                         :callback foo-callback))
                   (bar (make-instance
                         'capi:push-button
                         :text "Error without a handler"
                         :callback-type :data
                         :data "Broken leg."
                         :callback 'error)))
                (capi:contain (list foo bar)))
See also
             abort-dialog
             abort-exit-confirmer
             confirmer-pane
             display-dialog
             exit-confirmer
             exit-dialog
```

popup-menu-button

Class

Summary A button with a popup menu.

Package capi

Superclasses item

Initargs :menu A menu or nil.

:menu-function

A function designator or mil.

ACCESSORS popup-menu-button-menu

popup-menu-button-menu-function

Description The class popup-menu-button provides a button with a

popup menu, which is displayed when the user clicks on the

button.

If *menu-function* is non-nil, it should be function of one argument (the pane) and should return a menu object. Otherwise,

menu should be a menu object.

popup-menu-button inherits from item, so you can supply

text, data and so on.

Example See the example in capi/elements/popup-menu-but-

ton.lisp

See also menu

ppd-directory

Variable

Summary The directory in which LispWorks looks for PPD files.

Package capi

Initial value nil

Description The variable *ppd-directory* specifies where LispWorks

looks for PostScript Printer Definition (PPD) files.

This applies only on GTK+ and Motif.

The directory which is the value of *ppd-directory* should contain PPD files (files with extension ppd) either directly, or under subdirectories. The PPD files under each subdirectory are grouped together, with the name of the directory as the group name. PPD files in *ppd-directory* itself are

grouped under the "Other" group.

print-capi-button

Generic Function

Summary Generates the text for a button.

Package capi

Signature print-capi-button button => text

Arguments button A button.

Values *text* A string.

Description The generic function print-capi-button is used to generate

the text for a button.

You can add methods for your own button classes.

See also button

print-collection-item

Generic Function

Summary Prints an item as a string.

Package capi

Signature print-collection-item item collection

Arguments item An item or an Lisp object.

collection A collection or any Lisp object.

Description The generic function print-collection-item prints item as

a string. It is used when item is known to be an item in collec-

tion.

An item in a collection prints using the first of these which returns non-nil: the item's *text*, the item's *print-function*, the collection's *print-function* or the item's *data*. An item not known to be in the collection is printed simply using print-object.

The method on (t collection) uses the collection's *printfunction*.

Example

(capi:print-collection-item 2 collection)

In this example we provide our own print-collectionitem method:

print-dialog Function

Summary Displays a print dialog and returns a printer object.

Package capi

Signature print-dialog &key screen owner first-page last-page printselection-p print-pages-p print-copies-p continuation => printer

Values printer A printer, or nil.

Description The function print-dialog displays a print dialog and

returns a printer object. The printer object returned will print

multiple copies if requested by the user.

If *print-pages-p* is t, the user can select a range of pages to print. This should always be the case unless the application only produces single page output. If *print-pages* is t, *first-page* and *last-page* can be used to initialize the page range. For example, they could be set to be the first and last pages of the document.

The *print-copies-p* argument indicates whether the application handles production of multiple copies for drivers that do not support this function. Currently this should be nil if the application uses Page Sequential printing and t if the application uses Page on Demand printing.

If *print-selection-p* is t, the user is given the option of printing the current selection. Only specify this if the application has a notion of selection and selecting printing functionality is provided.

The dialog is displayed on the current screen unless *screen* specifies otherwise.

owner specifies an owner window for the dialog. See the "Prompting for Input" chapter in the *CAPI User Guide* for details.

If continuation is non-nil, then it must be a function with a lambda list that accepts one argument. The continuation function is called with the values that would normally be returned by print-dialog. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and print-dialog returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

Note that the printer object itself is opaque but programmatic setting of some printer options is available via the function set-printer-options.

See also

print-file
print-text
set-printer-options

print-editor-buffer

Function

Summary Prints the contents of an editor buffer to the printer.

Package capi

Signature print-editor-buffer buffer &key start end printer interactive

font

Description The print-editor-buffer function prints the contents of

buffer to printer, which is the current printer by default.

By default the entire editor buffer is printed, but by specifying *start* and *end* to be editor points, a part of the buffer can be printed. See the *LispWorks Editor User Guide* for information

about editor points.

If interactive is t, the default value, then a printer dialog is

displayed.

font is interpreted as described for print-text.

See also print-file

print-text

print-file Function

Summary Prints the contents of a specified file.

Package capi

Signature print-file file &key printer interactive font

Description The print-file function prints file to printer, which defaults

to the current printer. If interactive is t, then a print dialog is

displayed. This is the default behavior.

font is interpreted as described for print-text.

See also print-editor-buffer

print-text

print-rich-text-pane

Function

Summary Prints the contents of a rich-text-pane, on Microsoft Win-

dows.

Package capi

Signature print-rich-text-pane pane &key jobname printer interactive

selection => result

Arguments pane A rich-text-pane.

jobname A string, or mil.

printer A printer, or mil.

interactive A boolean.selection A boolean.

Values result A boolean.

Description The function print-rich-text-pane prints the contents in

pane.

jobname is the name of the print job. The default value is nil, meaning that the name "Document" is used.

printer is the printer to use. The default value is nil, meaning that the current-printer is used.

interactive, if true, specifies that a print-dialog is displayed before printing. The default value of interactive is t.

selection is a boolean specifiying what to print. If true, only the current selection is printed. If nil, all the contents of pane

are printed. The default value is mil.

Notes print-rich-text-pane is supported only on Microsoft

Windows.

See also rich-text-pane

print-text Function

Summary Prints plain text to a printer.

Package capi

Signature print-text line-function &key printer tab-spacing interactive font

Description The print-text function prints plain text to a printer specified by *printer*, and defaulting to the current printer.

The *line-function* is called repeatedly with no arguments to enumerate the lines of text. It should return nil when the text is exhausted.

The *tab-spacing* argument, which defaults to 8, specifies the number of spaces printed when a tab character is encountered.

If *interactive* is t, then a print dialog is displayed. This is the default behavior.

font should be a gp:font object, or a Font Description object, or a symbol which is a font alias as defined by define-font-alias. The printed text is line wrapped on the assumption that the font is fixed width, so be sure to pass a suitable font. The default value of font is a Font Description for a fixed pitch font of size 10.

See also print-editor-buffer

print-file

printer-configuration-dialog

Function

Summary Displays a dialog allowing the user to configure printers.

Package capi

1 CAPI Reference Entries

Signature printer-configuration-dialog &key screen owner

Description The printer-configuration-dialog function displays the

printer configuration dialog that allows users to add and con-

figure PostScript printers.

This applies only on GTK+ and Motif.

The *screen* argument specifies a CAPI screen on which to display the dialog. The *owner* argument controls which interface owns the dialog. If it is specified it should be a currently displayed CAPI interface; it defaults to the current top level interface.

The general options that are available are described under install-postscript-printer. In addition, printer-specific options (which are defined in the printer PPD file) are available.

The printers that are visible in the dialog are defined by files in the directories in the list *printer-search-path*.

See also install-postscript-printer

printer-search-path

printer-metrics

Structure Class

Summary The type of objects containing printer metrics.

Package capi

Description A printer-metrics object is returned by get-printer-

metrics. The readers for the slots of a printer-metrics

object are described below.

printer-metrics-device-height and

printer-metrics-device-width respectively return the height and width of the printable page in the internal units used by the printer driver or printing subsystem of the printer. These functions should not be used to determine the aspect ratio of the printable page as some printers have size units that differ in the x and y directions.

printer-metrics-dpi-x and printer-metrics-dpi-y return the number of printer device units per inch in the x and y directions respectively. This typically corresponds to the printer resolution, although in some cases this may not be known. For example, a generic PostScript language compatible driver might always return 300dpi, even though it cannot know the resolution of the printer the PostScript file will actually be printed on.

printer-metrics-height and printer-metrics-width respectively return the height and width of the printable area in millimeters.

printer-metrics-left-margin and printer-metrics-top-margin respectively return the current left margin and current top margin of the printable area in millimeters.

printer-metrics-max-height and printer-metrics-max-width respectively return the greatest possible height and width of the printable area in millimeters.

printer-metrics-min-left-margin and printer-metrics-min-top-margin respectively return the smallest possible left margin and top margin of the printable area in millimeters.

printer-metrics-paper-height and printer-metrics-paper-width respectively return the height and width of the paper selected for this printer in millimeters.

See also get-printer-metrics

printer-port-handle

Function

Summary Returns the underlying handle to a printer port.

Package capi

Signature printer-port-handle &optional port => handle

Arguments *port* A printer port.

Values handle Platform-dependent.

Description The function printer-port-handle returns a platform-

dependent value which represents the underlying handle to

the printer port.

On Microsoft Windows, handle is the HDC for the printer

device.

If *port* is passed it should be the value bound to *var* in with-print-job. If *port* is not supplied it defaults to the current printer port (dynamically bound within with-print-job).

See also with-print-job

printer-port-supports-p

Function

Summary Detects if the printer port can support a certain feature.

Package capi

Signature printer-port-supports-p feature &optional port =>

supportedp, validp

Arguments *feature* A keyword.

port A printer port.

Values *supportedp* A boolean.

validp A boolean.

Description The function printer-port-supports-p detects if the

printer port can support the feature named by feature.

If *port* is passed it should be the value bound to *var* in with-print-job. If *port* is not supplied it defaults to the current printer port (dynamically bound within with-print-job).

supportedp indicates if the feature is supported.

validp indicates if the feature was recognised.

Currently the only value of *feature* that is recognised is postscript and the *supportedp* value is true if the printer

supports PostScript.

See also with-print-job

printer-search-path

Variable

Summary Specifies where to look for printer definition files.

Package capi

Initial value ("~/.lispworks-printers/" nil)

Description The variable *printer-search-path* specifies where to

look for printer definition files.

This applies only on GTK+ and Motif.

The value is a list containing directory pathname designators specifying where to look for printer definition files. The list can also include the value nil, which is interpreted as the

printers directory in the LispWorks library.

To find known printers the system loads all files in these directories. If there are duplicate printer definitions, the printer in the first directory takes precedence.

The default path is useful when printing from the Common LispWorks IDE, but applications that want to allow users to use printers should set the list appropriately.

The first path in the *printer-search-path* list is regarded as the "local" path. New printers are saved in this path. When the user edits a printer that was found in another directory on *printer-search-path* and then tries to save it, the system prompts for whether to overwrite the original or save it in the "local" directory.

The printer files can be copied to other directories, on the same machine, and hence to install printers in different directories.

A printer file can be copied to other machines, provided the printer is installed on the other machine and the PPD file is available in the same path.

process-pending-messages

Function

Summary	Processes all the pending	messages in the current	process.

Package capi

Signature process-pending-messages ignored => nil

Arguments The single argument is ignored.

Description The function process-pending-messages processs all the

pending messages in the current process, and then returns nil. It is useful when your code needs to continuously do something, but also needs to respond to user input or other

messages.

progress-bar Class

Summary A pane that is used to show progress during a lengthy task.

Package capi

Superclasses range-pane

titled-object simple-pane

Description This pane is used to display progress during a lengthy task. It

has no interactive behavior.

The range-pane accessors (setf range-start) and (setf range-end) are used to specify integers delimiting the range

of values the progress bar can display.

The accessor (setf range-slug-start) is used to set an

integer value for the progress indicator.

See also range-pane

titled-object

prompt-for-color

Function

Summary Presents a dialog box allowing the user to choose a color.

Package capi

Signature prompt-for-color message &key color colors owner => result,

successp

Arguments *message* A string.

color A color specification.

colors A list.

owner An owner window.

1 CAPI Reference Entries

Values result A color specification, or nil.

successp A boolean.

Description The function prompt-for-color pops up a dialog box allow-

ing the user to choose a color.

message supplies a title for the dialog on GTK+ and Motif. On

Microsoft Windows message is ignored.

color provides the default color in the dialog.

colors is a list of custom color specifications that the user can

choose from.

For a description of color specifications, see the "The Color

System" chapter in the *CAPI User Guide*.

owner specifies an owner window for the dialog. See the

"Prompting for Input" chapter in the CAPI User Guide for

details.

prompt-for-confirmation

Function

Summary Displays a dialog box with a message and Yes and No but-

tons.

Package capi

Signature prompt-for-confirmation message &key screen owner cancel-

button default-button continuation => result, successp

Arguments *message* A string.

screen A screen.

owner An owner window.

cancel-button A boolean.

default-button A keyword, or mil.

continuation A function or mil.

Values result A boolean.

successp A boolean.

Description

The function prompt-for-confirmation displays a dialog box containing *message*, with **Yes** and **No** buttons. When either **Yes** or **No** is pressed, it returns two values:

- a boolean indicating whether Yes was pressed
- t (for compatibility with other prompt functions)

cancel-button specifies whether a Cancel button also appears on the dialog. When Cancel is pressed, abort is called and the dialog is dismissed. The default value of cancel-button is nil.

default-button specifies which button has the input focus when the dialog appears (and is thus selected when the user immediately presses Return). The value :ok means Yes, the value :cancel means Cancel, and any other value means No. The default value of default-button is nil.

owner specifies an owner window for the dialog. See the "Prompting for Input" chapter in the *CAPI User Guide* for details.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by prompt-for-continuation. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-for-confirmation returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

Example (capi:prompt-for-confirmation "Continue?")

See also confirm-yes-or-no

prompt-for-directory

Function

Summary Displays a dialog prompting the user for a directory.

Package capi

Signature prompt-for-directory message &key if-does-not-exist pathname

file-package-is-directory pane-args popup-args owner continuation =>

result, successp

Arguments *message* A string.

if-does-not-exist One of :ok, :prompt or :error.

pathname A pathname, or nil.

file-package-is-directory

A generalized boolean.

pane-args Arguments to pass to the pane.

popup-args Arguments to pass to the confirmer.

owner An owner window.

continuation A function or mil.

Values result A directory pathname, or nil.

successp A boolean.

Description

The function prompt-for-directory prompts the user for a directory pathname using a dialog box. Like all the prompters, prompt-for-directory returns two values: the directory pathname and a flag indicating success. The *successp* flag will be nil if the dialog was cancelled, and t otherwise.

On Windows and Motif, if *if-does-not-exist* is :ok, a non-existent directory can be chosen. When set to :prompt, if a non-existent directory is chosen, the user is prompted for whether the directory should be created. When set to :error, the user cannot choose a non existent directory. The default value of *if-does-not-exist* is :prompt.

On Cocoa it is never possible to choose a non-existent directory, and the value of *if-does-not-exist* is ignored.

pathname, if non-nil, supplies an initial directory for the dialog. The default value for pathname is nil, and with this value the dialog initializes with the current working directory.

file-package-is-directory is handled as by prompt-for-file.

owner specifies an owner window for the dialog. See the "Prompting for Input" chapter in the *CAPI User Guide* for details.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by prompt-for-directory. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-for-directory returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

The prompt itself is created by passing an appropriate pane to popup-confirmer. Arguments can be passed to the make-instance of the pane and the call to popup-confirmer using pane-args and popup-args respectively. Currently, the pane used to create the file prompter is internal to the CAPI.

1 CAPI Reference Entries

See also popup-confirmer

prompt-for-file

prompt-for-file Function

Summary Displays a dialog prompting the user for a filename.

Package capi

Signature prompt-for-file message &key pathname ok-check filter filters

if-exists if-does-not-exist file-package-is-directory operation owner pane-args popup-args continuation => filename, successp, filter-

name

Arguments *message* A string or nil.

pathname A pathname designator or mil.

ok-check A function or nil.

filter A string or nil.

filters A property list.

if-exists One of :ok or :prompt.

if-does-not-exist One of :ok, :prompt or :error.

file-package-is-directory

A generalized boolean.

operation One of :open or :save.

owner An owner window.

continuation A function or mil.

Values filename A pathname or nil.

successp A boolean.

filter-name A string.

Description

The function prompt-for-file prompts the user for a file using a dialog box.

pathname, if non-nil, is a pathname designator providing a default filename for the dialog.

ok-check, if non-nil, should be a function which takes a pathname designator argument and returns a true value if the pathname is valid.

filter specifies the initial filter expression. The default value is
"*.*". An example filter expression with multiple filters is
"*.LISP;*.LSP".

filter is used on all platforms. However on Motif, if *filter* contains multiple file types, only the first of these is used.

On Cocoa prompt-for-file supports the selection of application bundles as files if they match the filter. For example, they will match if the filter expression contains *.app or *.*.

filters is a property list of filter names and filter expressions, presenting filters which the user can select in the dialog. If the *filter* argument is not one of the expressions in *filters*, an extra filter called "Files" is added for this expression.

On Microsoft Windows the default value of *filters* is:

```
("Lisp Source Files" "*.LISP;*.LSP"
"Lisp Fasls" "*.OFASL"
"Text Documents" "*.DOC;*.TXT"
"Image Files" "*.BMP;*.DIB;*.ICO;*.CUR"
"All Files" "*.*")
```

The "Lisp Fasls" extension may vary depending on the implementation.

On Cocoa the default value of filters is:

```
("Lisp Source Files" "*.lisp;*.lsp"
"Text Documents" "*.txt;*.text"
"All Files" "*.*")
```

filters is ignored on Motif.

When *if-exists* is :ok, an existing file can be returned. Otherwise the user is prompted about whether the file can be overwritten. The default for *if-exists* is :ok when *operation* is :open and :prompt when operation is :save.

When if-does-not-exist is :ok, a non-existent file can be chosen. When it is :prompt, the user is prompted if a non-existent file is chosen. When it is :error, the user cannot choose a non-existent file. The default for if-does-not-exist is :prompt if operation is :open and :ok if operation is :save.

operation chooses the style of dialog used, in LispWorks for Windows only. The default value is :open.

owner, if non-nil, specifies an owner window for the dialog. See the "Prompting for Input" chapter in the *CAPI User Guide* for details.

If continuation is non-nil, then it must be a function with a lambda list that accepts three arguments. The continuation function is called with the values that would normally be returned by prompt-for-file. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-for-file returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

On Motif, the prompt itself is created by passing an appropriate pane to popup-confirmer. Arguments can be passed to the make-instance of the pane and the call to popup-confirmer using pane-args and popup-args respectively. Currently, the pane used to create the file prompter is internal to the CAPI. pane-args and popup-args are ignored on Microsoft Windows.

filename is the full pathname of the file selected, or mil if the dialog was cancelled.

successp is a flag which is mil if the dialog was cancelled, and totherwise.

On Microsoft Windows prompt-for-file returns a third value: *filter-name* is the name of the filter that was selected in the dialog.

file-package-is-directory controls how to treat file packages on Cocoa. By default it is nil, which means that a file package is treated as file. If file-package-is-directory is non-nil, the a file package is treated as a directory. file-package-is-directory corresponds to the treatsfilePackagesAsDirectories method of NSSavePanel in Cocoa. It has no effect on other platforms.

prompt-for-files

Function

Summary Displays a dialog which returns multiple filenames.

Package capi

Signature prompt-for-files message &key pathname ok-check filter filters

 $if-exists \ if-does-not-exist \ file-package-is-directory \ operation \ owner \\ pane-args \ popup-args \ continuation \ => \ filenames \ , \ successp, \ filter-package-is-directory \ operation \ owner \\ pane-args \ popup-args \ continuation \ => \ filenames \ , \ successp, \ filter-package-is-directory \ operation \ owner \\ pane-args \ popup-args \ continuation \ => \ filenames \ , \ successp, \ filter-package-is-directory \ operation \ owner \\ pane-args \ popup-args \ continuation \ => \ filenames \ , \ successp, \ filter-package-is-directory \ operation \ owner \\ pane-args \ popup-args \ continuation \ => \ filenames \ , \ successp, \ filter-package-is-directory \ operation \ owner \\ pane-args \ popup-args \ continuation \ => \ filenames \ , \ successp, \ filter-package-is-directory \ operation \ owner \\ pane-args \ popup-args \ continuation \ => \ filenames \ owner \ o$

name

Values *filenames* A list.

successp A boolean.

filter-name A string.

Description

The function prompt-for-files presents the user with a dialog box similarly to prompt-for-file, but in which multiple filenames can be selected.

The arguments are as for prompt-for-file, except that *filters* defaults to:

```
("MS Word files" "*.doc"
  "HTML files" "*.htm;*.html"
  "Plain Text files" "*.txt;*.text"
  "All files" "*.*")
```

filenames is a list of filenames, or nil if the user cancels the dialog.

successp is a flag which is mil if the dialog was cancelled, and totherwise.

filter-name is the name of the filter that was selected in the dialog.

If continuation is non-nil, then it must be a function with a lambda list that accepts three arguments. The continuation function is called with the values that would normally be returned by prompt-for-files. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-for-files returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

Notes

prompt-for-files is currently implemented only in Lisp-Works for Windows and Cocoa.

See also

prompt-for-file

prompt-for-font

Function

Summary Presents a dialog box allowing the user to choose a font.

Package capi

Signature prompt-for-font message &key font owner => result, successp

Arguments *message* A string.

font A font, a font description, or nil.

owner An owner window, or nil.

Values result A font, or nil.

successp A boolean.

Description The function prompt-for-font displays a dialog box

allowing the user to choose a font.

message supplies a title for the dialog.

font, if non-nil, provides defaults for the dialog box. The

default value is mil.

owner specifies an owner window for the dialog. See the "Prompting for Input" chapter in the *CAPI User Guide* for

details.

For a description of Graphics Ports fonts and font descrip-

tions, see the CAPI User Guide.

See also find-best-font

prompt-for-form Function

Summary Displays a text input pane and prompts the user for a form.

Package capi

Signature prompt-for-form message &key package initial-value evaluate

quotify ok-check value-function pane-args popup-args continuation

=> result, okp

Description

The function prompt-for-form prompts the user for a form by providing a text input pane that the form can be typed into.

The form is read in the *package* if specified or *package* if not. If *evaluate* is non-nil then the result is the evaluation of the form, otherwise it is just the form itself. The printed version of *initial-value* will be placed into the text input pane as a default, unless *quotify*, which defaults to *evaluate*, specifies otherwise. If *value-function* is provided it overrides the default value function which reads the form and evaluates it when required. If the *ok-check* is provided it will be passed the entered form and should return to if the form is a valid result.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by prompt-for-form. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-for-form returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

The prompter is created by calling prompt-for-string. Arguments can be passed to the make-instance of the pane and the call to popup-confirmer using pane-args and popupargs respectively, and an input history can be implemented by supplying a history-function or history-symbol in popup-args.

Example

Try the following examples, and each time enter (+ 1 2) into the input pane.

```
(capi:prompt-for-form "Enter a form:")
(capi:prompt-for-form "Enter a form:" :evaluate nil)
```

See also

```
prompt-for-forms
prompt-for-string
popup-confirmer
text-input-pane
```

prompt-for-forms

Function

Summary Displays a text input pane prompting the user for a number

of forms.

Package capi

Signature prompt-for-forms message &key package initial-value value-

function pane-args popup-args continuation => result, okp

Description The function prompt-for-forms prompts the user for a

number of forms by providing a text input pane that the forms can be typed into, and it returns the forms in a list. The forms are read in the specified *package* or *package* if not. If *evaluate* is non-nil then the result is the evaluation of the

form, else it is just the form itself.

The printed version of *initial-value* will be placed into the text input pane as a default.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by prompt-for-forms. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-for-forms returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

The prompter is created by passing an appropriate pane (in this case a text input pane) to popup-confirmer. Arguments can be passed to the make-instance of the pane and the call to popup-confirmer using pane-args and popup-args respectively.

Example

Try the following example, and enter 1 2 3 into the input pane.

(capi:prompt-for-forms "Enter some forms:")

See also prompt-for-form

prompt-for-string
popup-confirmer
text-input-pane

prompt-for-integer

Function

Summary Prompts the user for an integer.

Package capi

Signature prompt-for-integer message &key min max initial-value ok-

check pane-args popup-args continuation => result, successp

Arguments *message* A string.

min An integer or mil.

max An integer or mil.

initial-value An integer or mil.

ok-check A function or mil.

pane-args Arguments to pass to the pane.

popup-args Arguments to pass to the confirmer.

continuation A function or mil.

Description The function prompt-for-integer pops up a text-input-

pane and prompts the user for an integer, which is returned

in result.

When *min* or *max* are specified the allowable result is

constrained accordingly.

initial-value determines the initial value displayed in the dialog. *initial-value* defaults to the value of *min*, or if *min* is nil

then no initial value is displayed.

Further restrictions can be applied by passing an *ok-check* function. *ok-check* should take one argument, the currently entered number, and should return t if it is valid. If *ok-check* is nil (the default) then there is no further restriction.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by prompt-for-integer. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-for-integer returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

The prompter is created by passing text-input-pane to popup-confirmer. Arguments can be passed to the make-instance of the pane and the call to popup-confirmer using pane-args and popup-args respectively.

```
Example (capi:prompt-for-integer "Enter an integer:")

(capi:prompt-for-integer "Enter an integer:" :max 10)

(capi:prompt-for-integer "Enter an integer:" :min 100 :max 200)

(capi:prompt-for-integer "Enter an integer:" :ok-check 'evenp)

See also prompt-for-string popup-confirmer text-input-pane
```

prompt-for-items-from-list

Function

Summary Prompts with a choice of items.

Package capi

1 CAPI Reference Entries

Signature prompt-for-items-from-list items message &key pane-args

popup-args interaction choice-class continuation => result, successp

Arguments *items* A sequence.

message A string.

pane-args Arguments to pass to the pane.

popup-args Arguments to pass to the confirmer.

interaction One of :single-selection,

:multiple-selection, Or :extended-selection.

choice-class A class name.

continuation A function or nil.

Description The function prompt-for-items-from-list is similar to

prompt-with-list. interaction defaults to :extended-

selection.

See also prompt-with-list

prompt-for-number

Function

Summary Prompts the user for a number.

Package capi

Signature prompt-for-number message &key min max initial-value ok-check

pane-args popup-args continuation => result, successp

Arguments *message* A string.

min A number or nil.

max A number or nil.

initial-value A number or nil.

ok-check A function or nil.

pane-args Arguments to pass to the pane.

popup-args Arguments to pass to the confirmer.

continuation A function or nil.

Description The function prompt-for-number pops up a text-input-

pane and prompts the user for a number, which is returned in

result.

The functionality corresponds exactly to that of prompt-for-

integer, except that all types of numbers are allowed.

See also prompt-for-integer

prompt-for-string

Function

Summary Displays a text input pane and prompts the user for a string.

Package capi

Signature prompt-for-string message &key pane-args popup-args ok-check

value-function text initial-value print-function history-symbol

history-function continuation => result, okp

Description The function prompt-for-string prompts the user for a

string and returns that string in result and a flag okp indicating that the dialog was not cancelled. The initial string can either be supplied directly as a string using the text argument, or by passing initial-value and a print-function for that value. print-function defaults to princ-to-string. The value returned can be converted into a different value by passing a value-function, which by default is the identity function. This value-function gets passed the text that was entered into the pane, and should return both the value to return and a flag

that should be non-nil if the value that was entered is not acceptable. If an *ok-check* is passed, then it should return non-nil if the value about to be returned is acceptable.

prompt-for-string creates an instance of text-inputpane or text-input-choice depending on the value of history-function. Arguments can be passed to the makeinstance of this pane using pane-args. prompt-for-string then passes this pane to popup-confirmer. Arguments can be passed to the call to popup-confirmer using popup-args.

history-symbol, if non-nil, provides a symbol whose value is used to store an input history, when history-function is not supplied. The default value of history-symbol is nil.

history-function, if supplied, should be a function designator for a function with signature:

history-function &optional push-value

history-function is called with no argument to obtain the history which is used as the *items* of the text-input-choice, and with the latest input to update the history.

The default value of *history-function* is nil. In this case, if *history-symbol* is non-nil then a history function is constructed which stores its history in the value of that symbol.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by prompt-for-string. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-for-string returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

Example (capi:prompt-for-string "Enter a string:")

See also popup-confirmer

text-input-pane

prompt-for-symbol

Function

Summary Prompts the user for a symbol.

Package capi

Signature prompt-for-symbol message &key initial-value symbols package

ok-check pane-args popup-args continuation => result, okp

Description The function prompt-for-symbol prompts the user for a

symbol which they should enter into the pane.

initial-value, if non-nil, should be a symbol which is initially displayed in the pane.

The symbols that are valid can be constrained in a number of ways.

symbols, if non-nil, should be a list of all valid symbols. The default is nil, meaning all symbols are valid.

package, if non-nil, is a package in which the symbol must be available. The value mil means that the value of *package* is used, and this is the default.

ok-check is a function which when called on a symbol will return non-nil if the symbol is valid.

The prompter is created by calling prompt-for-string. Arguments can be passed to the make-instance of the pane and the call to popup-confirmer using pane-args and popupargs respectively, and an input history can be implemented by supplying a history-function or history-symbol in popupargs.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by prompt-for-symbol. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-for-symbol returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

```
Example
```

This last example shows how to implement a symbol prompter with an input history:

See also

```
prompt-for-form
prompt-for-string
popup-confirmer
text-input-pane
```

Summary Prompts the user for a form to evaluate.

Package capi

Signature prompt-for-value message &key package initial-value value-

function pane-args popup-args continuation

Description The function prompt-for-value prompts the user for a form

and returns the result of evaluating that form.

The form is read in the *package* if specified or *package* if not and the result is the evaluation of the form.

If initial-value is supplied it provides a default form.

If *value-function* is supplied it overrides the default value function which reads the form and evaluates it.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by prompt-for-value. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-for-value returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

The prompter is created by passing a text-input-pane to popup-confirmer. Arguments can be passed to the make-instance of the pane and the call to popup-confirmer using pane-args and popup-args respectively.

```
Example
```

See also prompt-for-form

prompt-with-list

Function

Summary Prompts the user to select an item or items from a choice.

Package capi

Signature prompt-with-list items message &key choice-class interaction

value-function pane-args popup-args continuation buttons callbacks

all-button none-button => result, successp

Arguments *items* A sequence.

message A string.

choice-class A class name.

interaction One of :single-selection,

:multiple-selection, Or :extended-selection.

value-function A function, or mil.

pane-args Arguments to pass to the pane.

popup-args Arguments to pass to the confirmer.

continuation A function or mil.

buttons A list of strings or the keyword :none.

callbacks A list of callback specs.

all-button A string, nil or t.

none-button A string, mil or t.

Description The function prompt-with-list prompts the user with a

choice. The user's selection is normally returned by the

prompter.

items supplies the items of the choice.

message supplies a title for the choice.

choice-class determines the type of choice used in the dialog. choice-class defaults to list-panel, and must be a sublass of choice.

interaction determines the interaction style of the choice in the dialog. By default interaction is :single-selection. For single selection, the dialog has an OK and a Cancel button, while for other selection styles it has Yes, No and Cancel buttons where Yes means accept the selection, No means accept a null selection and Cancel behaves as normal. Note that interaction:multiple-selection is not supported for lists on Mac OS X

The primary returned value is usually the selected items, but a *value-function* can be supplied that gets passed the result and can then return a new result. If *value-function* is nil (this is the default), then *result* is simply the selection.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by prompt-with-list. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-with-list returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

In addition to the choice showing the items, prompt-with-list can also display a panel of push buttons (the "action buttons") which perform actions related to the choice. Note that these buttons are separated from the "dialog buttons" such as **OK** and **Cancel**. The dialog buttons are controlled separately by keywords in *popup-args*.

By default, prompt-with-list does not display action buttons. However, if *interaction* is :multiple-selection, the default behavior is to display two action buttons, All and None. These change the selection to all of the items or none of the items respectively.

When *buttons* is :none, it specifies no action buttons in any case (including no All and None buttons). Otherwise *buttons* must be a list of strings specifying additional action buttons. Each of the strings specifies a button, and the string is displayed in the button.

callbacks specifies the callbacks of the buttons. It should be a list of callback specifiers matching the list in *buttons*. Each callback specifier is either a callable (a function or a symbol) which takes one argument, the choice, or a list where the car is a callable which is called as follows:

```
(apply (car callback-spec) choice (cdr callback-spec))
```

When all-button and none-button are supplied they override the default behavior of the AII and None buttons. If all-button (none-button) is nil, then AII (None) is not displayed. If all-button (none-button) is non-nil and buttons is not :none, the AII (None) button is displayed, and if the value is string, that string is used instead of the default string.

The prompter is created by passing an appropriate pane (in this case an instance of class *choice-class*) to popup-confirmer. Arguments can be passed to the make-instance of the pane and the call to popup-confirmer using *pane-args* and *popup-args* respectively. The initial selection can be specified using choice initargs:selection,:selected-item or:selected-items in *pane-args*.

```
Example (capi:prompt-with-list
'(1 2 3 4 5) "Select an item:")
```

```
(capi:prompt-with-list
               '(1 2 3 4 5) "Select some items:"
              :interaction :multiple-selection
              :selection '(0 2 4))
              (capi:prompt-with-list
               '(1 2 3 4 5) "Select an item:"
              :interaction :multiple-selection
              :choice-class 'capi:button-panel)
              (capi:prompt-with-list
                '(1 2 3 4 5) "Select an item:"
                :interaction :multiple-selection
                :choice-class 'capi:button-panel
                :pane-args
                '(:layout-class capi:column-layout))
             There is a more complex example in
             examples/capi/choice/prompt-with-buttons.lisp
See also
             popup-confirmer
             list-panel
             choice
```

prompt-with-list-non-focus

Function

Summary Raises a non-focus window.

Signature

prompt-with-list-non-focus items & key owner x y choice-class vertical-scroll print-function selection selected-item visible-items selection-callback action-callback destroy-callback list-updater gesture-callbacks add-gesture-callbacks alternative-y alternative-x alternative-bottom alternative-right widget-name filtering-gesture filtering-toggle & allow-other-keys => interface

Arguments *owner* A displayed CAPI pane.

x,y Integers.

alternative-x, alternative-y

Integers.

alternative-bottom, alternative-right

Integers or t.

choice-class A subclass of list-panel.

selection An integer.

selected-item An item.

visible-items A positive integer.

vertical-scroll A boolean.

print-function A function designator or mil.

selection-callback A function designator or mil.

action-callback A function designator or mil.

destroy-callback A function designator or nil.

list-updater A function designator or mil.

gesture-callbacks A list of pairs of the form (gesture . call-

back) .

add-gesture-callbacks

A list of pairs of the form (gesture . call-

back).

filtering-gesture A Gesture Spec.

filtering-toggle A Gesture Spec.

widget-name A string.

ValueS interface A non-focus-list-interface, or nil.

Description

The function prompt-with-list-non-focus raises a non-focus window, displaying the items *items* in a list of class *choice-class*, which should be list-panel or a subclass.

The non-focus window does not take the input focus, and hence does not see any keyboard input unless this is passed to it by non-focus-maybe-capture-gesture. It responds to mouse gestures.

Note that even moving the selection in the list vertically in response to the arrow keys cannot happen without non-focus-maybe-capture-gesture.

owner is required, and must be a CAPI pane visible on the screen. The position of the non-focus window is determined relative to *owner*, and the callbacks are invoked in the process of *owner*.

x and *y* are required pixel coordinates with respect to *owner* of the top left corner of the non-focus window.

alternative-bottom, alternative-right, alternative-x and alternative-y specify alternative locations for use when positioning the window at x or y would cause it to be off the screen. If alternative-bottom or alternative-right are specified, they specify alternative bottom or alternative right. For example, both Editor completion and text-input-pane completion specify a y coordinate below the text, and alternative-bottom above the text.

alternative-bottom and alternative-right can also take the special value t, which denotes the height or width of the screen.

alternative-x and alternative-y can be used to specify alternative x and alternative y. alternative-bottom overrides alternative-y and alternative-right overrides alternative-x.

The default value of *choice-class* is list-panel.

selection or *selected-item* can be used to specify the initially selected item in the list. If neither of these initargs is supplied, the first item is selected.

visible-items specifies the height of the list panel when the filter is not visible. The default value of *visible-items* is 20.

vertical-scroll is supplied to cl:make-instance when making the list. The default value of vertical-scroll is t.

print-function is also supplied to cl:make-instance when making the list. The default value of print-function is nil.

selection-callback, if non-nil, should be a function of two arguments, the selected item and the non-focus interface. selection-callback is called (in the process of owner) when an item is selected in the list panel. Note that callback-type does not affect the arguments passed to selection-callback.

action-callback, if non-nil, should also be a function of two arguments, the selected item and the non-focus interface. action-callback is called (in the process of owner) when an item is double-clicked in the list panel, or when Return is passed to non-focus-maybe-capture-gesture (by default, see gesture-callbacks). Note that callback-type does not affect the arguments passed to action-callback.

destroy-callback, if non-nil, should be a function of one argument, the non-focus window (a CAPI interface). destroy-callback is called when the non-focus window is destroyed. It is invoked in the process of owner.

list-updater, if non-nil, should be a function with signature

list-updater => result

list-updater is called in the process of owner whenever non-focus-update is called. result must be a list of items to put into the list panel, or one of the special values t (meaning no effect) and :destroy (meaning destroy the non-focus window).

gesture-callbacks and add-gesture-callbacks define gesture callbacks which the non-focus window can "capture" (when non-focus-maybe-capture-gesture is called). gesture-callbacks and add-gesture-callbacks should both be a list of pairs of the form (gesture . callback). Each gesture must be a gesture specifier, that is an object that sys:coerce-to-gesture-spec can coerce to a Gesture Spec. Each callback is either a callable (symbol or function) which takes one argument, the non-focus window, or a list of the form (function arguments). Note that when it is a list, the window is not automatically

passed to the function function amongst the arguments arguments. The gesture callbacks are used only when non-focus-maybe-capture-gesture is called.

add-gesture-callbacks adds more gesture callbacks to those that are implicitly defined for controlling the list panel (see non-focus-maybe-capture-gesture). gesture-callbacks, if supplied, replaces the gesture callbacks that are implicitly defined for the list panel. In both cases, a gesture callback that is defined explicitly overrides any implicitly define gesture callback.

filtering-gesture defines whether it is possible for the user to add a filter to the non-focus window with a keyboard gesture, and defines that gesture. The gesture is actually a toggle: it destroys a filter that is on, and adds a filter when none is present. When the filter is added, its text is reset and it is always enabled, that is it captures characters and Backspace. While the filter is visible, the list panel diplays only items that match the filter. The default value of filtering-gesture is a Gesture Spec matching Control+Return.

filtering-toggle defines whether it is possible for the user to disable/enable the filter with a keyboard gesture, and defines that gesture. When a filter is visible and enabled, the non-focus window captures characters and Backspace (when non-focus-maybe-capture-gesture is called) and passes them to the filter. When the filter is visible and disabled, characters and Backspace are captured. The default value of filtering-toggle is a Gesture Spec matching Control+Shift+Return.

widget-name has an effect only on Motif. It defines the widget name of the interface, which can then be used to define resources specific to the non-focus window. Note that the non-focus completers in editor-pane and text-input-pane use the default widget-name which is "non-focus-list-prompter", so defining resources for non-focus-list-prompter will affect them.

If *items* is nil, prompt-with-list-non-focus returns nil without doing anything. Otherwise, it raises the non-focus window and returns the interface, which is of class non-focus-list-interface.

The non-focus window is "passive", because it does not see keyboard input. It is the responsibility of the caller to pass any keyboard input that the non-focus window needs to process to the window, by using non-focus-maybe-capture-gesture. In general, that should be all keyboard gestures, and non-focus-maybe-capture-gesture decides which gestures it wants to process.

The caller can also use non-focus-terminate, non-focus-update, non-focus-list-toggle-filter, non-focus-list-add-filter, non-focus-list-remove-filter and non-focus-list-toggle-enable-filter to control the non-focus window.

See also

list-panel

non-focus-terminate

non-focus-update

non-focus-list-toggle-filter

non-focus-list-toggle-enable-filter

non-focus-maybe-capture-gesture

prompt-with-message

Function

Summary Prompts the user to select an item or items from a choice.

Package capi

Signature prompt-with-message message &key owner continuation

Arguments *message* A string.

owner An owner window, or mil.

continuation A function or mil.

Description The function prompt-with-message displays message in a

dialog owned by owner.

If continuation is non-nil, then it must be a function with a lambda list that accepts two arguments. The continuation function is called with the values that would normally be returned by prompt-with-message. On Cocoa, passing continuation causes the dialog to be made as a window-modal sheet and prompt-with-message returns immediately, leaving the dialog on the screen. The with-dialog-results macro provides a convenient way to create a continuation function.

Example (capi:prompt-with-message

"No items were deleted.")

See also display-message-for-pane

display-message

push-button Class

Summary A push-button is a pane that displays either a piece of text

or an image and when it is pressed it performs an action.

Package capi

Superclasses button

titled-object

Initarqs :alternate-callback

A callback invoked on Microsoft Windows, Cocoa and GTK+ when pressing the mouse button over the push-button while a platform-specific modifier key is held down.

:press-callback

A callback invoked on Microsoft Windows, GTK+ and Motif when pressing the mouse button over the push-button.

Accessors

button-alternate-callback
button-press-callback

Description

The class push-button inherits most of its behavior from button. Note that it is normally best to use a push-button-panel rather than make the individual buttons yourself, as the button panel provides functionality for handling groups of buttons. However, push buttons can be used if you need to have more control over the button's behavior.

press-callback, if non-nil, should be a function which is called when the user presses the mouse left button over the push button. The arguments to *press-callback* are as specified by *callback-type*. This initarg is not supported on Cocoa.

alternate-callback, if non-nil, should be a function. On Microsoft Windows and GTK+, it is called instead of callback when the button is clicked with the Control key held down. On Cocoa, it is called instead of callback when the button is clicked with the Command key held down. alternate-callback is not implemented for Motif or for other classes of button.

Notes

callback (from superclass button) is the general callback, triggered when the user clicks the button, either by pressing and releasing the mouse button or by a keyboard gesture.

press-callback is called only when the user presses the mouse button.

```
Example
               (setq button (capi:contain
                              (make-instance
                               'capi:push-button
                              :text "Press Me"
                              :data '(:some :data)
                              :callback #'(lambda (data interface)
                                             (capi:display-message
                                              "Pressed ~S"
                                              data)))))
               (capi:apply-in-pane-process
                button #'(setf capi:button-enabled) nil button)
               (capi:apply-in-pane-process
                button #'(setf capi:button-enabled) t button)
 See also
               radio-button
               check-button
               button-panel
               push-button-panel
push-button-panel
 Summary
```

Class

A push-button-panel is a pane containing a group of but-

tons.

Package capi

Superclasses button-panel

Description The class push-button-panel inherits all of its behavior

> from button-panel, which itself inherits most of its behavior from choice. Thus, the push button panel can accept items,

callbacks, and so on.

Example (defun test-callback (data interface)

(capi:display-message

"Pressed ~S" data))

```
(capi:contain (make-instance 'capi:push-button-panel
                                            :title "Press a button:"
                                               '("Press Me" "No, Me")
                                             :selection-callback
                                               'test-callback))
              (capi:contain (make-instance 'capi:push-button-panel
                                            :title "Press a button:"
                                            :items
                                               '("Press Me" "No, Me")
                                             :selection-callback
                                               'test-callback
                                             :layout-class
                                               'capi:column-layout))
              (capi:contain (make-instance 'capi:push-button-panel
                                              :title "Press a button:"
                                           :items '(1 2 3 4 5 6 7 8 9)
                                              :selection-callback
                                                'test-callback
                                              :layout-class
                                                'capi:grid-layout
                                              :layout-args
                                                '(:columns 3)))
             There is a further example in the file
             examples/capi/buttons/buttons.lisp.
See also
             push-button
             radio-button-panel
             check-button-panel
```

quit-interface Function

Summary Closes the top level interface containing a specified pane.

Package capi

Signature quit-interface pane &key force => result

Arguments *pane* A CAPI element.

force A boolean. The default value is nil.

Values result t if the interface was closed, nil otherwise.

Description

The function quit-interface closes the top level interface containing pane, but first it verifies that it is okay to do this by calling the interface's confirm-destroy-function. If it is OK to close the interface, it then calls destroy to do so. If force is true, then neither the confirm-destroy-function or the destroy-callback are called, and the window is just closed immediately.

Note: quit-interface must only be called in the process of the top level interface of *pane*. Menu callbacks on that interface will be called in that process, but otherwise you probably need to use execute-with-interface or apply-in-pane-process.

Example

Here are two examples demonstrating the use of quit-interface with the *destroy-callback* and the *confirm-destroy-function*.

With this second example, the user is prompted as to whether or not to quit the interface.

radio-button Class

Summary A button that can be either selected or deselected, but when

selecting it any other buttons in its group will be cleared.

Package capi

Superclasses button

titled-object

Description The class radio-button inherits most of its behavior from

button. Note that it is normally best to use a radio-buttonpanel rather than make the individual buttons yourself, as the button-panel provides functionality for handling groups of buttons. However, radio buttons are provided in case you need to have more control over the button's behav-

ior.

Example (setq button (capi:contain

(make-instance 'capi:radio-button

:text "Press Me")))

(capi:apply-in-pane-process

button #'(setf capi:button-selected) t button)

(capi:apply-in-pane-process

button #'(setf capi:button-selected) nil button)

(capi:apply-in-pane-process

button #'(setf capi:button-enabled) nil button)

(capi:apply-in-pane-process

button #'(setf capi:button-enabled) t button)

There is a further example in the file

examples/capi/buttons/buttons.lisp.

See also push-button

check-button
button-panel

radio-button-panel

radio-button-panel

Class

Summary A pane containing a group of buttons of which only one can

be selected at any time.

Package capi

Superclasses button-panel

Description The class radio-button-panel inherits all of its behavior

from button-panel, which itself inherits most of its behavior from choice. Thus, the radio button panel can accept items,

callbacks, and so forth.

1 CAPI Reference Entries

Example (capi:contain (make-instance 'capi:radio-button-panel :title "Select a color:" :items '(:red :green :blue) :print-function 'string-capitalize)) (setq buttons (capi:contain (make-instance 'capi:radio-button-panel :title "Select a color:" :items '(:red :green :blue) :print-function 'string-capitalize :layout-class 'capi:column-layout))) (capi:choice-selected-item buttons) There is a further example in the file examples/capi/buttons/buttons.lisp. See also radio-button push-button-panel check-button-panel

raise-interface Function

Summary Raises the interface containing a specified pane to the front of

the screen.

Package capi

Signature raise-interface pane

Description The function raise-interface raises the window contain-

ing pane to the front of the screen. To push it to the back use lower-interface, and to iconify it use hide-interface.

Example (setq pane (capi:contain

(make-instance

'capi:text-input-pane)))

(capi:apply-in-pane-process

pane 'capi:lower-interface pane)

(capi:apply-in-pane-process

pane 'capi:raise-interface pane)

See also activate-pane

hide-interface

interface

lower-interface
quit-interface

range-pane Class

Summary A class supporting progress-bar and slider.

Package capi

Superclasses None

Subclasses progress-bar

scroll-bar slider

Initargs :start An integer specifying the lowest value of the

range.

end An integer specifying the highest value of

the range.

:slug-start An integer specifying the start of the slug,

corresponding to the current value of the

range.

:slug-end An integer specifying the end of the slug.

:callback Called when the user changes the value.

:orientation One of :horizontal (the default) or :vertical.

ACCESSORS range-start

range-end

range-slug-start range-slug-end range-callback range-orientation

Description The class range-pane exists to support the progress-bar

and slider classes. Consult the reference pages for progress-bar and slider for further information.

See also progress-bar

slider

range-set-sizes

Function

Summary Set values in a range-pane.

Signature range-set-sizes range-pane &key start end slug-start slug-end

redisplay

Arguments range-pane A range-pane.

start A real number or nil.

end A real number or nil.

slug-start A real number or nil.

slug-end A real number or nil.

Description The function range-set-sizes set the values in the range-

pane range-pane for any value of start, end, slug-start or slug-

end that is supplied as non-nil.

For each of *start*, *end*, *slug-start* and *slug-end*, if the value is nil or not supplied, the corresponding value in *range-pane* is not changed.

If *redisplay* is true then *range-pane* is redisplayed with the new values.

The default value of redisplay is t.

Notes The values can be also set individually by the accessors

(setf range-start) and so on. range-set-sizes has the advantage over the accessors that it causes fewer calls to

redisplay.

See also range-pane

read-sound-file Function

Summary Reads data from a sound file on Microsoft Windows and

Cocoa.

Package capi

Signature read-sound-file source => array

Arguments source A pathname designator.

Values array An array of element type (unsigned-byte

8).

Description The function read-sound-file reads data from source and

returns an array of its contents.

Notes 1. read-sound-file can be called during image building.

2. read-sound-file is not implemented on GTK+ and Motif.

1 CAPI Reference Entries

See also load-sound

rectangle Class

Summary A pinboard-object that draws a rectangle.

Package capi

Superclasses pinboard-object

Subclasses None.

Initargs : filled A boolean, default value nil.

Accessors filled

Description The class rectangle provides a simple pinboard-object

that draws a rectangle.

The rectangle is always drawn with shape-mode :plain (that

is, without anti-aliasing).

filled determines whether the rectangle is filled.

redisplay-collection-item

Generic Function

Summary Redisplays the area in a collection that belongs to an item.

Package capi

Signature redisplay-collection-item collection item

Description The generic function redisplay-collection-item redis-

plays item in collection.

There are methods supplied for graph-pane and tree-view.

See also collection

redisplay-interface

Generic Function

Summary Updates the state of an interface.

Package capi

Signature redisplay-interface interface

Description The generic function redisplay-interface updates the

state of an interface, such as enabling and disabling menus, buttons, and so forth, that might have changed since the last call. When using this as a callback, you can use :redisplay-interface instead of the symbol, and then it will get passed

the correct arguments regardless of the callback type.

Notes This method is called by popup-confirmer to update its but-

ton's enabled state, and so it should be called when state

changes in a dialog.

See also interface

redisplay-menu-bar
redraw-pinboard-layout

display

redisplay-menu-bar

Function

Summary Updates the menu bar of an interface.

Package capi

Signature redisplay-menu-bar interface &key redo-items

Arguments interface An interface.

redo-items A generalized boolean.

Description

The function redisplay-menu-bar updates the interface's menu bar, such that menus become enabled and disabled as appropriate.

When redo-items is non-nil, redisplay-menu-bar redoes the items in menu and menu-component that have an items-function, by calling the items-function and setting the items. The default value of redo-items is t.

Notes

redo-items defaults to t in order to ensure that any accelerator associated with any item is up-to-date. When the menu bar contains menus (including sub-menus and menu-components) that have an items-function, redisplay-menu-bar may take a relatively long time (tens of milliseconds). If it is called often (for example, each time the user types a character), then it is better to call redisplay-menu-bar with redo-items nil.

Compatibility note

This function has been superseded by redisplay-interface, which updates the menu bar, but also updates other state objects such as buttons, list panels and so on.

See also interface

redisplay-interface

redraw-pinboard-layout

Function

Summary Redraws any pinboard objects within a specified rectangle.

Package capi

Signature redraw-pinboard-layout pinboard x y width height &optional

redisplay

Description The function redraw-pinboard-layout causes any pin-

board objects within the given rectangle of the pinboard

layout to get redrawn.

If redisplay is nil, then the redisplay will be cached until a

later update. The default for redisplay is t.

See also pinboard-object

redraw-pinboard-object

redraw-pinboard-object

Function

Summary Redraws a specified pinboard object.

Package capi

Signature redraw-pinboard-object object &optional redisplay

Description The function redraw-pinboard-object causes the pinboard

object *object* to be redrawn, unless *redisplay* is nil in which case the redisplay will be cached until a later update. The

default for redisplay is t.

Example There are examples in the directory

examples/capi/graphics/.

See also pinboard-object

pinboard-layout

redraw-pinboard-layout

reinitialize-interface

Generic Function

Summary Reinitializes an existing interface.

Package capi

Signature reinitialize-interface interface &rest initargs

Description The generic function reinitialize-interface reinitializes

an existing instance of a subclass of interface.

reinitialize-interface is called automatically by find-

interface when this re-uses an interface.

You can add methods to specialize on subclasses of inter-

face which you define.

See also find-interface

interface-reuse-p

remove-capi-object-property

Function

Summary Removes a property from the property list of an object.

Package capi

Signature remove-capi-object-property object property

Description The remove-capi-object-property function removes a

property from the property list of an object.

All CAPI objects contain a property list, similar to the symbol plist. The functions capi-object-property and (setf capi-object-property) are the recommended ways of setting properties, and remove-capi-object-property is the

way to remove a property.

Example (setq pane (make-instance 'capi:list-panel :items '(1 2 3)))

(capi:capi-object-property pane 'test-property)

(setf (capi:capi-object-property pane 'test-property)

"Test")

(capi:capi-object-property pane 'test-property)

(capi:remove-capi-object-property pane 'test-property)

(capi:capi-object-property pane 'test-property)

See also capi-object-property

capi-object

remove-items Generic Function

Summary Removes some items from a collection.

Package capi

Signature remove-items collection list-or-predicate

Arguments *collection* A collection.

list-or-predicate A list, or a function of one argument

returning a boolean value.

Description The generic function remove-items removes from the col-

lection collection those items determined by list-or-predicate.

If *list-or-predicate* is list, then the items removed are those matching some element of *list-or-predicate*, compared by the *test-function* of *collection*. Otherwise, the items removed are those for which the function *list-or-predicate* returns true.

This is logically equivalent to recalculating the collection items and then calling (setf collection-items). However, remove-items is more efficient and causes less flickering on screen.

remove-items can only be used when the collection has the default items-get-function svref.

See also append-items

collection replace-items

replace-dialog

Function

Summary Replaces a replacable dialog.

Package capi

Signature replace-dialog interface &rest args => nil

Arguments interface An interface.

args Other arguments as for display-dialog.

Description The function replace-dialog displays a dialog in the same

way the display-dialog does, except that it also destroys

the existing dialog.

interface is a CAPI interface to be displayed as a dialog.

The arguments *args* are interpreted the same as the

arguments to display-dialog, except that *modal* is ignored. replace-dialog displays the dialog like display-dialog.

See also display-replacable-dialog

replace-items

Generic Function

Summary Replaces some items in a collection.

Package capi

Signature replace-items collection items &key start new-selection

Arguments *collection* A collection.

items A list.

start A non-negative integer.

new-selection A list specifying the selection.

Description

The generic function replace-items replaces some items in the collection collection from items. replace-items can only be used when the collection has the default items-getfunction syref.

start should be a non-negative integer and less than the number of items in *collection*.

Items in *collection* are replaced starting at index *start*, and proceeding until the end of the list *items*, or the end of the items in *collection*. If *items* is too long, the surplus is quietly ignored. replace-items never alters the number of items in the collection.

If supplied, *new-selection* should be a list of items specifying the new selection in collection. To specify no selection, pass nil.

If new-selection is not supplied, then replace-items attempts to preserve the selection. If some of the selected items are replaced, then the selection on these items is removed, but if a selected item simply moves, then the selection moves with it.

See also

append-items collection remove-items

report-active-component-failure

Generic Function

Summary Reports on failures to find or create a component.

Package capi

Signature report-active-component-failure pane component-name error-

string function-name hresult

Arguments pane An ole-control-pane.

component-name A string or mil.

error-string A string.

hresult An integer or mil.

Description The generic function report-active-component-failure

is used to report on failures to find or create a component.

component-name is the name of the component it tried to find.

error-string is the error string.

function-name is the name of the function that actually failed.

hresult is the hresult that came back. It may be nil if the error is that the guid of the named component could not be found.

When the system fails to open the component, it calls report-active-component-failure, with the first argument the ole-control-pane pane. The default method for ole-control-pane tries to call

report-active-component-failure again on its top level interface. The default method on interface calls error.

You can add your own methods, specializing on subclasses of ole-control-pane or subclasses of interface.

Notes This function is implemented only in LispWorks for Win-

dows. Load the functionality by (require "embed").

Example See the example in

examples/com/ole/simple-container/doc-viewer-

pair.lisp

See also ole-control-pane

reuse-interfaces-p

Function

Summary Determines whether global interface re-use is enabled.

Package capi

Signature reuse-interfaces-p => result

Signature (setf reuse-interfaces-p) value => value

Arguments value A boolean.

Values result A boolean.

Description The function reuse-interfaces-p is the predicate for

whether global interface re-use is enabled.

The function (setf reuse-interfaces-p) enables or dis-

ables global interface re-use.

If global re-use is enabled, then locate-interface and find-interface may return existing interfaces. If global re-use is disabled, then locate-interface returns nil and

find-interface returns a new interface.

See also find-interface

locate-interface

rich-text-pane Class

Summary A text pane with extended formatting.

Package capi

Superclasses simple-pane

Initargs :character-format

A plist.

:paragraph-format

A plist.

:change-callback

A function called when a change is made.

:protected-callback

A function determining whether the user may edit a protected part of the text, on

Microsoft Windows.

:filename A file to display.

:text A string or nil.

:text-limit An integer.

ACCESSORS rich-text-pane-change-callback

rich-text-pane-limit rich-text-pane-text

Description

The class rich-text-pane provides a text editor which supports character and paragraph formatting of its text.

character-format is the default character format. It is a plist which is interpreted in the same way as the attributes-plist argument of set-rich-text-pane-character-format. The default value of character-format is nil.

paragraph-format is the default paragraph format. It is a plist which is interpreted in the same way as the attributes-plist argument of set-rich-text-pane-paragraph-format. The default value of paragraph-format is nil.

change-callback, if non-nil, is a function of two arguments: the pane itself, and a keyword denoting the type of change. This second argument is either :text or :selection. The default value of change-callback is nil.

protected-callback, if supplied, is called when the user tries to modify protected text (by setting the protected attribute, see set-rich-text-pane-character-format). It must be a function of four arguments: the pane itself, bounding indexes of the protected text, and a boolean which is true when the change would affect the selection. If the change would affect just a single character, this last argument is nil. If protected-callback returns nil, then the change is not performed. If protected-callback is not supplied, then the user cannot modify protected text. protected-callback is supported only on Microsoft Windows.

filename, if non-nil, should be a string or pathname naming a file to display in the pane. *filename* takes precedence over *text* if both are non-nil.

text, if non-nil, should be a string which is displayed in the pane if *filename* is nil.

text-limit, if non-nil, should be an integer which is an upper bound for the length of text displayed in the pane.

Notes

- rich-text-pane is supported only on Microsoft Windows, and Cocoa in Mac OS X 10.3 and later. Some of its features are supported only on Microsoft Windows, as mentioned above.
- **2.** *change-callback* and *protected-callback* are not yet implemented on Cocoa.
- 3. The functions that are specific to rich-text-pane cannot be called before the pane is created. If you need to perform operations on the pane before it appears, and which cannot be performed using the initargs, the best approach is to define an :after method on interface-display on the class of the interface containing the rich-text-pane, and perform the operations inside this method.

See also print-rich-text-pane

rich-text-pane-character-format

rich-text-pane-operation

set-rich-text-pane-character-format
rich-text-pane-paragraph-format
set-rich-text-pane-paragraph-format

rich-text-pane-character-format

Function

Summary Returns the character format.

Package capi

Signature rich-text-pane-character-format pane &key selection

=> result

Arguments pane A rich-text-pane.

selection Must be t. This argument is deprecated.

Values result A plist.

Description The function rich-text-pane-character-format returns

as a plist the current character attributes for pane.

If there is a current selection in the pane, then the attributes are those set for the selected text. If there is no selection, then it gets the "typing attributes", which are applied to characters that are typed by the user. Note that any cursor movement changes these attributes, so their values are ephemeral.

The *selection* argument is deprecated. If *selection* is nil an error is signalled. The default value of *selection* is t.

An attribute appears in *result* only if its value is the same over all of the range. Therefore this form

```
(getf
  (capi:rich-text-pane-character-format pane) :bold
  :unknown)
```

will return:

- t if all the selection is bold
- nil if all the selection is not bold
- :unknown if the selection is only partially bold.

For the possible attributes, see set-rich-text-pane-character-format.

Compatibility note

The value nil for the keyword argument :selection is not supported in LispWorks 6.1 and later. See the description above for details of the current behavior with respect to the current selection in the rich-text-pane.

See also

rich-text-pane

set-rich-text-pane-character-format

rich-text-pane-operation

Function

Summary

Gets and sets values and performs various operations on the

pane.

Package

capi

Signature

rich-text-pane-operation pane operation &rest args =>

result, result2

Arguments

pane A rich-text-pane.

operation A keyword specifying the operation to per-

form.

args The value or values to use, when the opera-

tion is setting something.

Values

result

Various, see below.

result2 Returned only for operation :get-selection. see below.

Description The valid values of *operation* on Microsoft Windows and Cocoa are:

:pastep, :cutp Or :copyp

result is a boolean indicating whether it is currently possible to perform a :paste, :cut or :copy operation.

:paste, :cut, Or :copy

Performs the indicated operation.

:select-all Selects all the text.

:set-selection

args should be two integers start and end. Sets the selection to the region bounded by start (inclusive) and end (exclusive).

:get-selection

Returns as multiple values the bounding indexes of the selection. *result* is the start (inclusive) and *result2* is the end (exclusive). If there is no selection, both values are the index of the insertion point.

:can-undo Or :can-redo

result is a boolean indicating whether it is currently possible to perform an :undo or :redo operation.

undo Undoes the last editing operation. Note that, after typing, it is the whole input, rather than a single character, that is undone. The

:undo operation may be repeated successively, to undo previous editing operations in turn.

Note: with RichEdit 1.0, :undo does not work repeatedly - it only undoes one previous editing operation. See rich-text-version

:redo

Undoes the effect of the last :undo operation. The :redo operation may be repeated successively, to cancel the effect of previous :undo operations in turn.

Note: with RichEdit 1.0, :redo does not work. See rich-text-version.

:get-modified result is the value of a boolean modified flag.

This flag can be set by the :set-modified operation. Also, editing the text sets it to true.

:set-modified Sets the modified flag. The argument is a boolean.

:save-file Saves the text to a file. Details below.

:load-file Loads the text from a file. Details below.

Additionally these values of *operation* are valid on Microsoft Windows, only:

:get-word-wrap

Returns a value indicating the word wrap, which can be the keyword :none. result can also be the keyword :window or a CAPI printer object, meaning that the text wraps according to the width of the window or the printer.

:set-word-wrap

Sets the word wrap. The argument can be as described for :get-word-wrap, and additionally it can be the keyword :printer, meaning the current-printer.

:hide-selection

Specifies whether the selection should be hidden (not highlighted) when *pane* does not have the focus. The argument is a boolean.

For operations :save-file and :load-file, args is a lambda list

filename &key selection format plain-text

filename is the file to save or load.

selection is a boolean, with default value mil.

format is mil or a keyword naming the file format. Values include :rtf and :text meaning Rich Text Format and text file respectively.

plain-text is a boolean, with default value mil.

With operation :save-file, if selection is true, only the current selection is saved. If selection is nil, all the text is saved. The default value of format is :rtf and there are two further allowed values, :rtfnoobjs and :textized. These are like :rtf and :text except in the way they deal with COM objects. See the documentation for SF_RTFNOOBJS and SF_TEXTIZED in the EM_STREAMOUT entry in the MSDN for details. When saving with format :rtf or :rtfnoobjs, if plain-text is true, then keywords that are not common to all languages are ignored. With other values of format, plain-text has no effect.

With *operation* :load-file, if *selection* is true, the unselected text is preserved. If there is a selection, the new text replaces it. If there is no selection, the new text is inserted at the cur-

rent insertion point. If *selection* is nil, all the text is replaced. The default value of *format* is nil, meaning that the RTF signature is relied upon to indicate a Rich Text Format file. If *plain-text* is true, then keywords that are not common to all languages are ignored.

```
Example
              (setq rtp
                    (capi:contain
                     (make-instance
                      'capi:rich-text-pane
                      :text (format nil "First paragraph.~%Second
              paragraph, a little longer.~%Another paragraph, which
              should be long long enough that it spans more than one
              line. ~%" ))))
              Set the selection to characters 9 to 18:
              (capi:rich-text-pane-operation rtp :set-selection 9 18)
              Write all the text to a file in text format:
              (capi:rich-text-pane-operation
               rtp :save-file "mydoc.txt" :format :text)
              Paste:
              (capi:rich-text-pane-operation rtp :paste)
See also
              rich-text-pane
              rich-text-version
```

rich-text-pane-paragraph-format

Function

Summary Returns the paragraph format.

Package capi

Signature rich-text-pane-paragraph-format pane => result

Arguments pane A rich-text-pane.

Values result A plist.

Description The function rich-text-pane-paragraph-format returns

as a plist the paragraph attributes of the current paragraphs

in pane.

For the possible attributes, see set-rich-text-pane-para-

graph-format.

See also rich-text-pane

rich-text-version Function

Summary Identifies the version of RichEdit in use, on Microsoft Win-

dows.

Package capi

Signature rich-text-version => result

Values result A keyword indicating the version of the

RichEdit control in use.

Description result is :rich-edit-2.0 if RichEdit 2.0 or newer is loaded.

Otherwise result is :rich-edit-1.0.

rich-text-version is supported only on Microsoft Win-

dows.

See also rich-text-pane

right-angle-line-pinboard-object

Class

Summary A subclass of pinboard-object that displays a line drawn

around two edges of the area enclosed by the pinboard

object.

Package capi

Superclasses line-pinboard-object

Initargs : type The type of line.

Description A subclass of line-pinboard-object which displays a line

around the edge of the pinboard object rather than diago-

nally.

type can be one of two values.

:vertical-first

Draw top-left to bottom-left to bottom-right.

:horizontal-first

Draw top-left to top-right to bottom-right.

The main use of this class is to produce graphs with rightangled edges rather than diagonal ones.

Example (capi:contain

(make-instance

'capi:right-angle-line-pinboard-object

:start-x 20 :start-y 20
:end-x 280 :end-y 100))

(capi:contain
 (make-instance)

'capi:right-angle-line-pinboard-object

:start-x 20 :start-y 120
:end-x 280 :end-y 200
:type :horizontal-first))

See also pinboard-layout

row-layout Class

Summary The row-layout class lays its children out in a row.

Package capi

Superclasses grid-layout

Initargs :ratios The size ratios between the layout's chil-

dren.

:adjust The vertical adjustment for each child.

gap The gap between each child.

:uniform-size-p

If t, each child in the row has the same

width.

Accessors layout-ratios

Description This lays its children out by inheriting the behavior from

grid-layout. The *description* is a list of the layout's children, and the layout also translates the initargs *ratios*, *adjust*, *gap* and *uniform-size-p* into the grid layout's equivalent arguments were the strong and a uniform size product of the layout and the layout are size as a layout and the layout are size as a layout and the layout are size as a layout are size as a layout and the layout are size as a layout are size as a layout and the layout are size as a layout are size as

ments *x-ratios*, *y-adjust*, *x-gap* and *x-uniform-size-p*.

description may also contain the keywords :divider and :separator which automatically create a divider or separator as a child of the row-layout. The user can move a

divider, but cannot move a separator.

When specifying :ratios in a row with :divider or :separator, you should use nil to specify that the divider or separator.

rator is given its minimum size.

Compatibility note

layout-divider-default-size and row-layout-divider are not supported in LispWorks 4.4 and later.

```
Example
              (setq row (capi:contain
                          (make-instance
                          'capi:row-layout
                          :description
                          (list
                           (make-instance 'capi:push-button
                                           :text "Press me")
                           (make-instance 'capi:title-pane
                                           :text "Title")
                           (make-instance 'capi:list-panel
                                           :items '(1 2 3)))
                          :adjust :center)))
              (capi:apply-in-pane-process
               row #'(setf capi:layout-y-adjust) :bottom row)
              (capi:apply-in-pane-process
               row #'(setf capi:layout-y-adjust) :top row)
              This last example shows a row with a stretchable dummy
             pane between two other elements which are fixed at their
              minimum size. Try resizing it:
              (capi:contain
               (make-instance 'capi:row-layout
                               :description
                               (list (make-instance 'capi:push-button
                                                    :text "foo")
                                     nil
                                     (make-instance 'capi:push-button
                                                     :text "bar"))
                               :ratios '(nil 1 nil)))
See also
             column-layout
```

screen Class

Summary A screen is an object that represents the known monitor

screens.

Package capi

Superclasses capi-object

Subclasses color-screen

mono-screen

Initargs :width The width in pixels of the screen.

:height The height in pixels of the screen.

:number The screen number.

:depth The number of color planes in the screen.

:interfaces A list of all of the interfaces visible on the

screen.

Readers screen-width

screen-height screen-number screen-depth screen-interfaces

screen-width-in-millimeters screen-height-in-millimeters

Description When the CAPI initializes itself it creates one or more screen

objects and they are then used to specify where a window is to appear. A screen object can also be queried for information that the program may need to know about the screen that it is working on, such as its width, height and depth.

On Microsoft Windows and Cocoa there is exactly one CAPI screen. When there are multiple monitors, there are several

rectangles of pixels within the single CAPI screen.

On Motif, there is one CAPI screen for each X11 screen.

Compatibility

note

In LispWorks for Macintosh 4.3 there is one CAPI screen for each Cocoa screen. In LispWorks for Macintosh 4.4 and later,

there is exactly one CAPI screen.

Example (setq screen (capi:convert-to-screen))

(capi:screen-width screen)

(capi:screen-height screen)

(capi:display (make-instance

(capi:screen-interfaces screen)

See also convert-to-screen

screen-active-interface

Function

Summary Returns the active interface on a screen.

Package capi

Signature screen-active-interface screen => interface

Arguments screen A screen or document-container

Values interface An interface, or nil.

Description The function screen-active-interface returns the cur-

rently active interface on the screen, or nil if no CAPI

interface is active or if this cannot be determined.

screen-active-interface also works with document-container, returning the active interface within the con-

tainer.

See also document-container

screen

screen-active-p

Function

Summary Determines whether a screen is active.

Package capi

Signature screen-active-p screen => result

Arguments screen A screen.

Values result A boolean.

Description The function screen-active-p is the predicate for whether a

screen is active.

See also screen

screen-logical-resolution

Function

Summary Returns the logical resolution of *screen*.

Package capi

Signature screen-logical-resolution screen => xlogres, ylogres

Arguments screen A screen.

Values *xlogres, ylogres* Integers representing the logical resolution

of screen in DPI.

Description The function screen-logical-resolution returns the logi-

cal resolution of screen, as dots per inch in the x and y direc-

tions.

See also screen

screen-internal-geometries

Function

Summary Returns the internal geometries of all the monitors of a

screen.

Package capi

Signature screen-internal-geometries screen => internal-geometries

Arguments *screen* A CAPI screen.

Values internal-geometries A list of screen rectangles.

Description The function screen-internal-geometries returns the

internal geometries of all the "monitors" of screen. A "monitor" typically corresponds to a physical monitor, but can be anything that the underlying GUI system considers a moni-

tor.

The internal geometry of a monitor is a rectangle which excludes "system areas" like taskbars and global menu bars and so on. Examples of these include the Windows taskbar, the Mac OS X menu bar, and the Mac OS X dock. See screeninternal-geometry for information about displaying CAPI windows in system areas.

Each internal geometry is represented as a screen rectangle. A screen rectangle is a list of four numbers: *x* and *y* being the coordinates as offsets from the top-left of the primary monitor, and *width* and *height*.

The first screen rectangle in the *internal-geometries* list corresponds to the usable area of the primary monitor.

Notes On GTK+ when using a desktop with separate workspaces,

the workspaces may be considered as separate "monitors". When there are multiple real monitors, the values may be incorrect. You can use screen-monitor-geometries to check the number of monitors, and to check the full size of the monitors

See also pane-screen-internal-geometry

virtual-screen-geometry
screen-internal-geometry
screen-monitor-geometries

screen-monitor-geometries

Function

Summary Returns the geometries of all of a screen's monitors.

Package capi

Signature screen-monitor-geometries screen => monitor-geometries

Arguments screen A CAPI screen.

Values *monitor-geometries*A list of screen rectangles.

Description The function screen-monitor-geometries returns the

geometries of all the monitors of screen. A monitor corresponds to an entity that the host machine regards as a physical monitor. screen-monitor-geometries ignores software

manipulations like the desktop on GTK+.

The monitor geometry is a rectangle which includes all of its display area, including "system areas" like menubar and taskbar and so on. Examples of these include the Windows taskbar, the Mac OS X menu bar and the Mac OS X dock.

Each monitor geometry screen rectangle is represented by a list of four numbers: the *x* and *y* coordinates as offsets from the top-left of the primary monitor, and the *width* and *height*.

The first screen rectangle in the *monitor-geometries* list corresponds to the primary monitor.

504

Notes

- screen-monitor-geometries differs from screeninternal-geometries by returning screen rectangles which include all the monitor areas, and also by ignoring desktop manipulations.
- 2. You cannot display a CAPI window on the Mac OS X menu bar. You can display a CAPI window in the area occupied by the Mac OS X dock or the Windows task bar, but the window will be obscured.

See also

pane-screen-internal-geometry
screen-internal-geometries
virtual-screen-geometry

screen-internal-geometry

Function

Summary Returns the geometry of the unobscured region of a screen or

document container.

Package capi

Signature screen-internal-geometry screen => x, y, width, height

Arguments screen A screen.

Values x An integer.

y An integer.

width A positive integer.height A positive integer.

Description

The function screen-internal-geometry returns the geometry (as multiple values representing a screen rectangle) of the region of the screen that can be used to display windows without obstruction. This region excludes "system"

areas" like menubar and taskbar and so on. Examples of these include the Windows taskbar, the Mac OS X menu bar and the Mac OS X dock.

x and *y* are the screen rectangle's coordinates as offsets from the top-left of the primary monitor, and *width* and *height* are its dimensions.

On Microsoft Windows screen-internal-geometry works with document-container, returning the current size of the container (which may vary over time).

Notes

- The internal geometry is a snapshot of the unobscured region of a screen. If a system area moves or changes size, then the screen rectangle returned by screen-internalgeometry changes.
- It may be possible to display a CAPI window outside the screen's internal geometry, for example under the Mac OS X dock, but it will be obscured.
- The primary monitor is that represented by the first screen rectangle in the list returned by screen-internal-geometries.

See also

document-container
pane-screen-internal-geometry
screen
screen-internal-geometries

screens Function

Summary Returns the active screens for a library.

Package capi

Signature screens &optional library => result

Arguments library A library name, a list, or :any.

Values result A list.

Description The function screens returns as a list all the active screens

for library.

A library name is a keyword naming a library, currently :win32 on Microsoft Windows, :gtk on GTK+, :motif on Motif and :cocoa on Mac OS X with the native GUI.

library can be a library name, or a list of library names, or the keyword :any, meaning all the libraries. The default value of

library is the result of default-library.

See also default-library

screen

Scroll Generic Function

Summary Moves the scrollbar and calls the *scroll-callback*.

Package capi

Signature scroll self scroll-dimension scroll-operation scroll-value &rest

options

Arguments *self* A pane that supports scrolling.

scroll-dimension :vertical,:horizontal or:pan.

scroll-operation :move, :step Or :page.

scroll-value An integer, or a list of two integers, or a key-

word, or a list of two keywords.

options A list.

Description The generic function scroll works for panes that support

scrolling - these are subclasses of output-pane and layout.

scroll moves the scrollbar of a scrollable pane according to scroll-dimension, scroll-operation and scroll-value. It then calls the scroll-callback (see output-pane) with these arguments and options.

scroll-dimension determines whether the scrolling is vertical, horizontal or, if the value is :pan, in both dimensions.

scroll-operation determines the extent of the scroll. The value <code>:move</code> means that the pane scrolls to the position on the scroll range given by scroll-value, regardless of the current scroll position. The value <code>:step</code> means scroll from the current scroll position by scroll-value times the scroll step size. In the case of panes which do their own scrolling the scroll step size is determined by the operating system (OS). In the case of panes for which the CAPI computes the scroll, the scroll step size is as described in <code>with-geometry</code>. The value <code>:page</code> means scroll from the current scroll position by scroll-value times the scroll page size (which is also determined by the OS or the pane's geometry).

scroll-value should be an integer or keyword if scroll-dimension is :horizontal or :vertical. Allowed keyword values are :start and :end. scroll-value should be a list of two integers or keywords representing the horizontal and vertical scroll values if scroll-dimension is :pan.

options is a list containing arbitrary user data.

```
Compatibility note
```

scroll supersedes set-scroll-position, which is deprecated and no longer exported. The call

```
(capi:scroll pane :pan :move (list x y))
is equivalent to
(capi:set-scroll-position pane x y)
ensure-area-visible
```

See also

ensure-area-visible get-scroll-position output-pane set-horizontal-scroll-parameters
set-vertical-scroll-parameters
with-geometry

scroll-bar Class

Summary A pane which displays a scroll bar.

Package capi

Superclasses range-pane

simple-pane titled-object

Initargs :line-size The distance scrolled by the scroll-line

gesture.

:page-size The distance scrolled by clicking inside the

scroll bar.

:callback A function called after a scroll gesture, or

nil.

Accessors scroll-bar-line-size

scroll-bar-page-size

Description The class scroll-bar implements panes which display a

scroll bar and call a callback when the user scrolls. It is not however the most usual way to add scroll bars - see the note

below about simple-pane.

line-size is the logical size of a line, and is the distance moved when the user enters a scroll-line gesture, that is clicking on one of the arrow buttons at either end of the scroll bar or using a suitable arrow key. The default value of *line-size* is 1.

page-size is the logical size of a page, and is the distance moved when the user clicks inside the scroll bar. The default

value of page-size is 10.

callback can be mil, meaning there is no callback. This is the default value. Otherwise, is a function of four arguments, the interface containing the scroll-bar, the scroll-bar itself, the mode of scrolling and the amount of scrolling. It has this signature:

callback interface scroll-bar how where

how can be one of :line, :page, :move, or :drag.

If *how* is :line, then *where* is an integer indicating how many lines were scrolled.

If *how* is :page, then *where* is an integer indicating how many pages were scrolled.

If how is :move or :drag, then where is an integer giving the new location of the *slug-start*, or :start or :end.

Note: the location of the slug can be found by the rangepane accessor range-slug-start.

Note: Rather than using scroll-bar, it is more usual to add scroll bars to a pane by the simple-pane initargs:horizon-tal-scroll and:vertical-scroll

```
Example
```

See also

simple-pane

scroll-if-not-visible-p

Generic Function

Summary Accesses the *scroll-if-not-visible-p* attribute of a pane.

Signature scroll-if-not-visible-p pane => value

(setf scroll-if-not-visible-p) value pane

Values value One of t. nil or :non-mouse.

Method Sigscroll-if-not-visible-p simple-pane

nature (setf scroll-if-not-visible-p) value simple-pane

Description The generic function scroll-if-not-visible-p accesses

the *scroll-if-not-visible-p* attribute of a pane.

The value of this attribute has these meanings:

t When pane is given the input focus, and it is

> not fully visible, and its parent can be scrolled to make the pane visible, then the parent is scrolled automatically. This is the

default value.

nil Never scroll the parent to make a pane visi-

ble.

Like t, except that it does not scroll when :non-mouse

the focus is given as a result of a mouse click

in pane.

scroll-if-not-visible-p is called by CAPI each time it may need to scroll the parent. The method on simple-pane returns a value that is kept internally, and can be set by the default setf method.

You can specialize scroll-if-not-visible-p on your classes, but note that it is called often when the user clicks on any pane, so it must be reasonably fast.

The setter sets the *scroll-if-not-visible-p* attribute. It is called when the initarg :scroll-if-not-visible-p is used in making a simple-pane (or a subclass) instance, and can be called by your program. *value* must be t, nil or :non-mouse.

The method on simple-pane sets the internal value that is used by scroll-if-not-visible-p on simple-pane.

See also simple-pane

search-for-item

Generic Function

Summary The generic function search-for-item returns the index of

an item in a collection.

Package capi

Signature search-for-item collection item

Description Returns the index of *item* in the *collection*, using the

collection-test-function to determine equality, and returns mil

if no match is found.

search-for-item is the counterpart function to get-collection-item which given an index, finds the appropriate

item.

See also get-collection-item

collection

selection Function

Summary Returns the primary selection.

Package capi

Signature selection self &optional format => result

Arguments self A displayed CAPI pane or interface.

format A keyword.

Values result A string, an image, a Lisp object, or nil.

Description The function selection returns the contents of the primary selection as a string, or nil if there is no selection.

format controls what kind of object is read. The following values of *format* are recognized:

:string The object is a string. This the default value.

:image The object is of type image, converted from

whatever format the platform supports.

:value The object is the Lisp value.

When *format* is :image, the image returned by selection is associated with *self*, so you can free it explicitly with free-image or it will be freed automatically when the pane is destroyed.

On Microsoft Windows there is no notion of selection, so this mechanism is internal to Lisp.

Note that X applications may or may not use the primary selection for their paste operations. For instance, Emacs is configurable by the variable interprogram-paste-function.

See also clipboard

free-image

image

selection-empty
set-selection

selection-empty

Function

Summary Determines whether there is a primary selection of a particu-

lar kind.

Package capi

Signature selection-empty self &optional format => result

Arguments *self* A displayed CAPI pane or interface.

format A keyword.

Values result tornil.

Description The function selection-empty returns nil if there is a pri-

mary selection of the kind indicated by format, or t if there is

no such selection.

format controls what kind of object is checked. The following

values of format are recognized:

:string The object is a string. This the default value.

: image The object is of type image, converted from

whatever format the platform supports.

:value The object is the Lisp value.

See also image

selection

set-application-interface

Function

Summary Specifies the main Cocoa application interface.

Package capi

Signature set-application-interface interface

Arguments

interface

An object of type cocoa-default-application-interface

Description

The function set-application-interface sets *interface* as the main application interface. This interface is used to supply the application menu and receives various callbacks associated with the application.

set-application-interface must be called before any CAPI functions that make the screen object (such as convert-to-screen and display).

interface should not be displayed like a normal interface.

An application can only have one application menu and one dock menu. Because the LispWorks IDE already provides these menus, calling <code>set-application-interface</code> while running the LispWorks IDE will add a submenu to the <code>Lisp-Works</code> application menu to contain the application-menu and menu-bar-items of your application, and you can test them there. Likewise, a submenu will be added to the LispWorks Dock icon menu. Other aspects of the application interface can only be tested when running it standalone.

set-application-interface is only applicable when running under Cocoa.

Example

See these files in the examples subdirectory of the LispWorks library:

capi/applications/cocoa-application.lisp

capi/applications/cocoa-application-single-window.lisp

delivery/macos/multiple-window-application.lisp
delivery/macos/single-window-application.lisp

See also

cocoa-default-application-interface

set-button-panel-enabled-items

Generic Function

Summary Sets the enabled state of the items in a button panel.

Package capi

Signature set-button-panel-enabled-items button-panel &key enable

disable set test key

Description The generic function set-button-panel-enabled-items

sets the enabled state of the items in a button panel. If *set* is t, then *enable* is ignored and all items are enabled except those in the *disable* list. If *set* is nil, *disable* is ignored and all items are disabled except those in the *enable* list. If *set* is not given, the items in the *enable* list are enabled and the items in the *disable* list are disabled. If an item is in both lists, it is enabled. A button is in a list when the data of the button matches one of the items in the list. A match is defined as a non-nil return value from the test function. The default test function is

equal.

See also button-panel

redisplay-interface

set-clipboard Function

Summary Sets the contents of the system clipboard.

Package capi

Signature set-clipboard self value &optional string plist => result

Arguments self A displayed CAPI pane or interface.

value A Lisp object (not necessarily a string) to

make available within the local Lisp image.

string The string representation of *value* to export,

or nil. If nil and value is a string, then that

will be exported as the string.

plist A property list of additional format/value

pairs to export. The currently supported formats are as described for clipboard. You can export more than one format simulta-

neously.

Values result A string, or nil.

Description The function set-clipboard sets the contents of the system clipboard to be the text of *string*.

In Microsoft Windows applications (including LispWorks in Windows emulation mode), the contents of the system clipboard is usually accessed by the user with the Ctrl+v gesture.

The X clipboard can be accessed by the Ctrl+v gesture in KDE/Gnome emulation, or by running the program xclipboard or the Emacs function x-get-clipboard. The most likely explanation for apparent inconsistencies after set-clipboard is that the pasting application doesn't use the X clipboard.

In Cocoa applications (including LispWorks), the contents of the system clipboard is usually accessed by the user with the Command+V gesture.

Example To export an image:

```
(capi:set-clipboard pane nil nil (list :image image))
```

To export an image with a text description

See also clipboard

selection

text-input-pane-copy

set-composition-placement

Function

Summary Specifies the placement of the composition window relative

to the pane. Composition here mean composing input char-

acters into other characters by an input method.

Signature set-composition-placement pane x y &key width height force

Description The function set-composition-placement tells the system

where to place the composition window in pixel coordinates

relative to the pane pane.

On systems where the composition text is displayed by the application (rather than by the system, when the composition callback is called with a plist), the placement coordinates are

used to place the composition menu when it is raised.

x and *y* are the top left coordinates. If both *width* and *height* are supplied, they specify the dimensions of the composition window. If *force* is supplied with a true value, the coordinates are forced, overriding adjustments that the system may oth-

erwise do.

x, y and, when supplied, width and height must all be positive

integers.

Notes set-composition-placement does not raise the

composition window. It merely tells the system where to

place the composition window when it does appear.

See also output-pane

set-confirm-quit-flag

Function

Summary Controls the behavior of confirm-quit

Package capi

Signature set-confirm-quit-flag flag

Arguments flag One of t, nil or :check-editor-files

Description The function set-confirm-quit-flag sets a flag which con-

trols the behavior of confirm-quit.

See confirm-quit for the effect.

Note: on initialization, the LispWorks IDE sets the flag to the stored value of the option **Tools > Preferences... > Environment**

> General > Confirm Before Exiting.

See also confirm-quit

set-default-editor-pane-blink-rate

Function

Summary Sets the default cursor blinking rate for editor panes.

Package capi

Signature set-default-editor-pane-blink-rate blink-rate

Arguments blink-rate A non-negative real number, or nil.

Description The function set-default-editor-pane-blink-rate sets

the default to use for the editor pane cursor blinking rate.

This default value is used when editor-pane-blink-rate

returns nil.

Initially the setting is if this call has been made:

(set-default-editor-pane-blink-rate nil)

This means that the native blink rate will be used.

The argument *blink-rate* is interpreted as a blinking rate as

described in editor-pane-blink-rate.

See also editor-pane-blink-rate

editor-pane-native-blink-rate

set-default-interface-prefix-suffix

Function

Summary Sets the default suffix and prefix that are added to each inter-

face title.

Package capi

Signature set-default-interface-prefix-suffix &key prefix suffix

child-prefix child-suffix => prefix, suffix, child-prefix, child-suffix

Arguments prefix A string or mil.

> suffix A string or mil.

> child-prefix A string or mil.

> child-suffix A string or mil.

Values prefix A string or mil.

> suffix A string or nil.

child-prefix

child-suffix A string or mil.

Description The function set-default-interface-prefix-suffix sets

A string or mil.

the global default suffix and prefix that are added to each interface title. The prefix and suffix are added by the

default method of interface-extend-title.

If *prefix*, *suffix*, *child-prefix* or *child-suffix* are supplied, their value must be either a string or nil. If any of them is not passed, the corresponding previously set value is not changed.

prefix and suffix specify the prefix and suffix to use for interfaces that are children of a screen object. These values do not affect child-prefix and child-suffix.

child-prefix and child-suffix specify the prefix and suffix to use for interfaces that are not children of a screen object, such as an interface inside a Multiple Document Interface (MDI) window. These values do not affect prefix and suffix.

The return values are the settings of the prefix, suffix, child prefix and child suffix after the call.

To check the current settings, call set-default-interfaceprefix-suffix with no arguments. This does not change the current settings.

Before setting the title on a window on the screen, the system calls interface-extend-title with the interface and the title of the interface, and uses the result for the actual title. The default method of interface-extend-title checks prefix and suffix (or child-prefix and child-suffix for MDI) as were set by set-default-interface-prefix-suffix, and if they are non-nil adds the value to the title.

set-default-interface-prefix-suffix can be called after some windows are displayed. It automatically updates all current interface windows as if by calling update-all-interface-titles.

Example

If you work in an environment when it is not always obvious on which machine your image is running, you can add the name of the machine to all windows by:

See also interface-extend-title

update-all-interface-titles

set-default-use-native-input-method

Function

Summary Controls the default of using native input method on GTK+.

Signature set-default-use-native-input-method &key output-pane

editor-pane => t

Arguments *output-pane* A boolean.

editor-pane A boolean.

Values set-default-use-native-input-method returns t.

Description The function set-default-use-native-input-method

controls whether the native input method is used by default.

Currently it has an effect only on GTK+.

The values of the keyword arguments are booleans. *editorpane* changes the default for editor-pane and subclasses. *output-pane* controls the default for output-pane and sub-

classes, except editor-pane and its subclasses.

If a keyword argument is not supplied, the corresponding

default is not set.

See also output-pane

editor-pane

set-display-pane-selection

Generic Function

Summary Sets the selection in a display-pane.

Package capi

Signature set-display-pane-selection pane start end

Arguments pane A display-pane.

start, end Bounding indexes for a subsequence of the

text of pane.

Description The generic function set-display-pane-selection sets the

selection in pane to be the text bounded by the indexes start

(inclusive) and end (exclusive).

See also display-pane-selection

display-pane

set-drop-object-supported-formats

Function

Summary Sets the list of formats for a drop object

Package capi

Signature set-drop-object-supported-formats drop-object formats

Arguments drop-object A drop-object, as passed to the drop-callback

formats A list of format keywords

Description The function set-drop-object-supported-formats sets

the list of formats that the drop object drop-object wants to

receive.

The :string format can be used to receive a string from another application and the :filename-list format can be used to receive a list of filenames from another application such as the Macintosh Finder or the Windows Explorer.

GTK+ supports dragging of list of URIs. LispWorks uses a list of URIs to pass/receive the data with the format :filename-list, and also adds the format :uris. The behavior is as follows:

- For dragging with format :filename-list (that is, call drag-pane-object with a plist containing :filename-list, or including :filename-list in the value that drag-callback returns) the argument must be a list of pathname designators. LispWorks canonicalizes the pathnames and converts them to file URIs.
- For dragging with format :uris, each value in the list must either a string containing a colon, or a pathname designator. A string containing a colon is passed unchanged. Other it is assumed to be a pathname designator, and is converted to a file URI.
- For dropping with format :filename-list (that is, calling drop-object-get-object with :filename-list),
 LispWorks converts each file URI to the corresponding filename string (without checking whether it is a proper file name), and discards all other URIs.
- For dropping with format :uris, LispWorks returns all the URIs as strings.

There is an example of :filename-list and :uris in examples/capi/elements/gtk-filename-list-and-uris.lisp

On Cocoa and GTK+ the :image format can be used to receive images. The value passed needs to be an image obtect.

Any other keyword in *formats* is assumed to be a private format that can only be used to receive objects from with the same Lisp image.

Notes set-drop-object-supported-formats should only be

called within a drop-callback. See simple-pane for informa-

tion about drop callbacks.

Example See

examples/capi/output-panes/drag-and-drop.lisp

examples/capi/choice/drag-and-drop.lisp

examples/capi/choice/list-panel-drag-images.lisp

See also drop-object-provides-format

simple-pane

set-editor-parenthesis-colors

Function

Summary Sets the colors that are used for parenthesis coloring.

Signature set-editor-parenthesis-colors colors

Arguments colors A list of colors, t or nil.

Description The function set-editor-parenthesis-colors sets the

colors that are used for parenthesis coloring in an editor-

pane in Lisp mode.

If *colors* is a non-nil list, each of its elements must be a valid color specification or a defined color alias. See "The Color System" in the *CAPI User Guide* for information about colors.

If it is called when CAPI is running, set-editor-parenthesis-colors checks that the colors are valid. If it is called when CAPI is not running, set-editor-parenthesis-colors does not check the colors, and a bad color will cause an error later. The colors have an effect only on coloring that happens after the call.

If *colors* is t or nil, parenthesis coloring is switched on or off, without changing the list of colors.

1 CAPI Reference Entries

When parenthesis coloring is off, parentheses are drawn like other characters.

See also editor-pane

set-geometric-hint

Function

Summary The set-geometric-hint function sets the hint associated

with a key.

Package capi

Signature set-geometric-hint element key value &optional override

Description Set the hint associated with key to value. If override is nil, the

value is not changed when there is already a hint for this key.

The default is t.

See also set-hint-table

element

set-hint-table Function

Summary Modifies the hint table for an element.

Package capi

Signature set-hint-table element plist

Description The function set-hint-table modifies the hint table for the

element element to include plist. All existing hints are retained

for keys not in the plist.

This may or may not change the on-screen geometry. To change the geometry of an interface, use set-top-level-interface-geometry.

Notes If a hint keyword is repeated in *plist*, the first value is used.

See also element

set-geometric-hint

set-top-level-interface-geometry

set-horizontal-scroll-parameters

Generic Function

Summary Allows programmatic control of the parameters of a horizon-

tal scroll bar.

Package capi

Signature set-horizontal-scroll-parameters self &key min-range max-

range slug-position slug-size page-size step-size

Description The function set-horizontal-scroll-parameters sets the

specified parameters of the horizontal scroll bar of *self*, which should be a displayed instance of a subclass of output-pane

(such as editor-pane) or layout.

The other arguments are:

min-range The minimum data coordinate.

max-range The maximum data coordinate.

slug-position The current scroll position.

slug-size The length of the scroll bar slug.

page-size The scroll page size.

step-size The scroll step size.

Compatibility note

The function set-horizontal-scroll-parameters supersedes the function set-scroll-range, which is deprecated and no longer exported.

The call

(set-horizontal-scroll-parameters pane

:min-range 0
:max-range 42)

is equivalent to

(set-scroll-range pane 42 nil)

Example See the following files:

examples/capi/output-panes/scroll-test.lisp

examples/capi/output-panes/scrolling-without-bar.lisp

See also scroll

get-horizontal-scroll-parameters

simple-pane

set-interactive-break-gestures

Function

Summary Sets the break gestures on GTK+ and Motif.

Signature set-interactive-break-gestures gestures => result

Arguments gestures A list of gesture specifiers, or t

The function set-interactive-break-gestures sets the gestures that can be used to break by typing at an interface.

gestures is a list of gesture specifiers. A gesture specifier is an object that sys:coerce-to-gesture-spec can recognize.

When an interface is created, the break gestures are set such that typing any one of them when the interface is on top causes an "interface break". This means that, if the interface process is busy, it tries to break it. In a Listener tool, it tries to break the REPL. Otherwise it tries to find a process that

appears busy, and breaks that. In the LispWorks IDE, if there is no busy process it raises the Process Browser tool. Otherwise it breaks the current process.

set-interactive-break-gestures always returns the list of interactive break gestures.

gestures can also be t, which means do not change the gestures. This is useful to get the current list.

Notes

- 1. set-interactive-break-gestures has an effect only on GTK+ and Motif.
- **2.** set-interactive-break-gestures has no effect on interfaces that are already created.
- 3. On GTK+ the list can be overriden by the resources file as illustrated in examples/gtk/gtkrc-break-gestures

set-list-panel-keyboard-search-reset-time

Function

Summary

Sets the default length of time before resetting the "last match" in keyboard searching in a list-panel.

Signature

set-list-panel-keyboard-search-reset-time time

Arguments

time

A positive real number.

Description

The function set-list-panel-keyboard-search-resettime sets the default length of time before resetting the "last match" in keyboard searching in a list-panel. The argument *time* specifies this time in seconds.

When the user types a character into a list-panel, if there is a "last match" the system searches for a string made of the "last match" followed by the character, otherwise it searches for a string made of the character only. The system sets the "last match" when it matches, and remembers the "last

match" for one second by default. set-list-panel-key-board-search-reset-time can be used to change the time

for which the "last match" is kept.

Notes When keyboard-search-callback returns a third value non-nil,

the value that set-list-panel-keyboard-search-reset-

time sets is ignored.

See also list-panel

list-panel-search-with-function

set-object-automatic-resize

Function

Summary Controls automatic resizing and repositioning of objects in a

static layout.

Package capi

Signature set-object-automatic-resize object &key x-align y-align x-

offset y-offset x-ratio y-ratio width-ratio height-ratio aspect-ratio

aspect-ratio-y-weight pinboard

Arguments object A pinboard-object or a simple-pane.

x-align nil, :left, :center Or :right.

y-align nil, :top, :center or :bottom.

x-offset A real number, default value 0.

y-offset A real number, default value 0.

x-ratio A positive real number or nil.

y-ratio A positive real number or nil.

width-ratio A positive real number or nil.

height-ratio A positive real number or nil.

aspect-ratio A positive real number, t or mil.

aspect-ratio-y-weight

A real number, default value 0.5.

pinboard

A static-layout, if supplied. This argument is deprecated, and can always be omitted.

Description

The function set-object-automatic-resize arranges for *object* to be resized and/or re-positioned automatically when *pinboard* is resized, or removes such a setting.

The value of *aspect-ratio* can be t, which means use the current aspect ratio of *object* (that is, its height divided by its width).

object should be either a pinboard-object or a simple-pane which is (or will be) displayed in a static-layout. This object will be added to the description of the layout by one of its:description initarg, (setf capi:layout-description) or manipulate-pinboard.

pinboard is the layout for *object*. If *pinboard* is already displayed with *object* in its *description*, the argument *pinboard* can be omitted.

When *pinboard* is resized, *object* is resized if either *height-ratio* or *width-ratio* are set.

The new width of *object* is calculated as follows:

- If width-ratio, height-ratio and aspect-ratio are all set, the new width is the width of pinboard multiplied by width-ratio, and then modified as described below.
- If width-ratio is set and either height-ratio or aspect-ratio is not set, the new width is the width of pinboard multiplied by width-ratio.
- If width-ratio is not set, and both height-ratio and aspectratio are set, the new width is the new height divided by aspect-ratio.

Otherwise, the new width is the same as the old width.

The new height of *object* is calculated as follows:

- If width-ratio and aspect-ratio are set, the new height is the new width multiplied by the aspect ratio. Note that if height-ratio is set, the new width will depend on height-ratio too.
- If height-ratio is set and either width-ratio or aspect-ratio are not set, the new height is the height of pinboard multiplied by height-ratio.
- If height-ratio is not set, but both width-ratio and aspect-ratio are set, the new height is the new width multiplied by aspect-ratio.
- Otherwise, the new height is the same as the old height.

If all of width-ratio, height-ratio and aspect-ratio are set, the new width and height of object are calculated as follows:

- Compute calculated-width as the width of pinboard multiplied by width-ratio, and calculated-height as the height of pinboard multiplied by height-ratio.
- 2. Compute aspect-ratio-ratio as
- (/ (/ calculated-height calculated-width) aspect-ratio)
- 3. Compute correction as

(expt aspect-ratio-ratio aspect-ratio-y-weight)

4. Compute the new width as *calculated-width* multiplied by *correction*, and the new height as the new width multiplied by *aspect-ratio*.

The result is that if *aspect-ratio-y-weight* is 0, *correction* is 1 and *height-ratio* is effectively ignored, while if *aspect-ratio-y-weight* is 1, *correction* cancels the effect of *width-ratio*. With the default value of 0.5, the resulting position is in the (geometric) middle, and *object* takes a fixed fraction of the area of the pinboard.

After resizing (if needed), *object* is also positioned horizontally if *x-align* is non-nil, and vertically if *y-align* is non-nil.

The new x coordinate of *object* is calculated as follows:

- If *x-ratio* is set, the new x coordinate is the sum of *x-ratio* multipled by the width of *pinboard* plus *x-offset*, otherwise it is simply *x-offset*.
- The actual value of the x coordinate for *object* is adjusted according to the value of *x-align* such that the left, center or right of *object* align with the new coordinate.

The new y coordinate of object is calculated similarly, using *y-ratio* and *y-offset*, with an adjustment such that the top, center or bottom of *object* aligns with the new coordinate according to *y-align*.

If all of width-ratio, height-ratio, x-align and y-align are mil, automatic resizing/re-positioning of object is removed.

set-object-automatic-resize can be called before *object* is actually displayed, and its effect persists over calls adding and removing *object* to/from static-layouts. The effect of set-object-automatic-resize also persists if *object* is removed and added again, either to the same layout or another layout.

Repeated calls to set-object-automatic-resize set only the values that are passed to set-object-automatic-resize. Keys that are not passed are left with their previous value. A call that removes the automatic resizing (because width-ratio, height-ratio, x-align and y-align are all nil) erases all the values.

set-object-automatic-resize returns t if the object is set up for automatic resizing, or nil if the object is set up for no automatic resizing.

Notes

1. The initarg :automatic-resize can be used to set up automatic resizing in the call to make-instance.

2. The name set-object-automatic-resize is slightly inaccurate, because this function can alter an object's position without actually changing its size.

Compatibility note

In LispWorks 6.0 the effect of set-object-automatic-resize does not persist if the object is removed and then added, to any layout.

In LispWorks 6.0 each call to set-object-automatic-resize sets all the values.

Example

Put an object of fixed size at the top right corner:

Put an object in the bottom-right quadrant:

```
(set-object-automatic-resize
object
:x-ratio 0.5 :y-ratio 0.5
:width-ratio 0.5 :height-ratio 0.5)
```

Put an object with a fixed aspect ratio and object width linear with the width of the layout in the center:

```
(set-object-automatic-resize
object
:x-align :center :y-align :center
:x-ratio 0.5 :y-ratio 0.5
:aspect-ratio 0.6 :width-ratio 0.1)
```

There is a further example in

```
(example-file "capi/layouts/automatic-resize.lisp")
```

See also

```
manipulate-pinboard
static-layout
pinboard-object
simple-pane
```

set-pane-focus

Generic Function

Summary Sets the input focus to a pane.

Package capi

Signature set-pane-focus pane

Arguments pane An instance of a subclass of simple-pane or

choice.

Description The function set-pane-focus sets the input focus to pane or

one of its children.

See also pane-has-focus-p

set-rich-text-pane-character-format

Function

Summary Sets the character format.

Package capi

Signature set-rich-text-pane-character-format pane &key selection

attributes-plist => result

Arguments pane A rich-text-pane.

selection Must be t. This argument is deprecated.

attributes-plist A plist or :default.

Values result A plist.

Description The function set-rich-text-pane-character-format sets

current character attributes for text in pane.

If there is a current selection in the pane, then the attributes are set for the selected text. If there is no selection, then it sets the "typing attributes", which are applied to characters that are typed by the user. Note that any cursor movement changes these attributes, so the setting is ephemeral.

The *selection* argument is deprecated. If *selection* is nil an error is signalled. The default value of *selection* is t.

If attributes-plist is the symbol :default then the default character format of the pane (that is, the value of the richtext-pane initarg :character-format) is used. Otherwise attributes-plist is a plist of keywords and values. These are the valid keywords on Microsoft Windows and Cocoa:

:bold A boolean.

:italic A boolean.

:underline A boolean.

:face A string naming a font.

:color A color spec or alias specifying the fore-

ground color.

:size The size of the font.

Additionally these *attributes-plist* keywords are valid on Microsoft Windows only:

:strikeout A boolean.

:offset An integer specifying the vertical offset of

characters from the line (a positive value makes them superscript and a negative

value makes them subscript).

:protected A boolean. See the description of protected-

callback in rich-text-pane.

:charset A cons (charset . pitch-and-family) where

charset has the value of a Microsoft Windows charset identifier, and pitch-and-family is the

value of (logior pitch family) where pitch and family have the value of a Windows pitch and a Windows font family respectively.

Compatibility note

The value nil for the keyword argument :selection is not supported in LispWorks 6.1 and later. See the description above for details of the current behavior with respect to the current selection in the rich-text-pane.

Example

Note: This example uses some features which are supported only on Microsoft Windows:

```
(defun ok-to-edit-p (pane start end s)
  (declare (ignore pane))
  (capi:prompt-for-confirmation
   (format nil "Editing~: [ ~; selection ~] from ~a to ~a"
           s start end)))
(setq rtp
      (capi:contain
       (make-instance
        'capi:rich-text-pane
        :protected-callback 'ok-to-edit-p
        :character-format
        '(:size 14 :color :red)
        :visible-min-height 300
        :visible-min-width 400
        :paragraph-format
        '(:start-indent 20 :offset -15)
        :text-limit 160
        :text (format nil "First paragraph.~%Second
paragraph, a little longer.~%Another paragraph, which
should be long long enough that it spans more than one
line. ~%" ))))
```

Enter some characters in the rich text window and select a range.

Set the selection to blue:

(capi:set-rich-text-pane-character-format
rtp

:attributes-plist '(:color :blue))

Make it protected:

(capi:set-rich-text-pane-character-format
rtp :attributes-plist '(:protected t))

Now try to delete a character, and also to delete the selection.

In both cases the ok-to-edit-p callback is called.

See also rich-text-pane

rich-text-pane-character-format

set-rich-text-pane-paragraph-format

Function

Summary Sets the paragraph format.

Package capi

Signature set-rich-text-pane-paragraph-format pane attributes-

plist

=> result

Arguments pane A rich-text-pane.

attributes-plist A plist, or :default.

Values result A plist.

Description The function set-rich-text-pane-paragraph-format sets

paragraph attributes for the current paragraphs in pane.

The current paragraphs are those paragraphs which overlap the current selection, or the paragraph containing the inser-

tion point if there is no selection.

If attributes-plist is the symbol :default then the default paragraph format of the pane is used. Otherwise attributes-plist is a plist of keywords and values. These are the valid keywords on Microsoft Windows and Cocoa:

```
:alignment :left, :right or :center.
```

:start-indent A number setting the indentation.

:offset-indentA number modifying the indentation.

A number setting the relative indentation of subsequent lines in a paragraph.

:right-indent A number setting the right margin.

:tab-stops A list of numbers.

Additionally this *attributes-list* keyword is valid on Microsoft Windows, only:

```
:numbering nil, t, :bullet, :arabic, :lowercase,
:uppercase, :lower-roman Or
:upper-roman.
```

numbering specifies the numbering style. Rich Edit 3.0 supports all the above values of numbering. Please note that the Arabic and Roman styles start numbering from zero, and that only t and :bullet work with versions of Rich Edit before 3.0 (other values of numbering are quietly ignored).

start-indent specifies the indentation of the first line of a paragraph. A negative value removes the indentation.

offset-indent takes effect only when *start-indent* is not passed. It specifies an increase in the current indentation. Therefore, a negative value of *offset-indent* decreases the indentation.

offset specifies the offset of the second and following lines relative to the first line of the paragraph. That is, when the indentation of the first line is *indent*, the indentation of the second and subsequent lines is *indent* + *offset*. When *offset* is

negative, the second and subsequent lines are indented less than the first line. If *indent* + *offset* is negative, then these lines are not indented.

tab-stops should be a list of numbers specifiying the locations of tabs. No more than 32 tabs are allowed.

```
Example
              (setq rtp
                    (capi:contain
                     (make-instance
                      'capi:rich-text-pane
                      :visible-min-height 300
                      :visible-min-width 400
                      :paragraph-format
                      '(:start-indent 20 :offset -15)
                      :text (format nil "First paragraph.~%Second
             paragraph, a little longer.~%Another paragraph, which
             should be long long enough that it spans more than one
             line. ~%" ))))
              (capi:set-rich-text-pane-paragraph-format
              rtp '(:offset-indent 30 :numbering :lowercase))
See also
             rich-text-pane
             rich-text-pane-paragraph-format
```

set-selection Function

Summary Sets the primary selection.

Package capi

Signature set-selection self value & optional string plist => result

Arguments self A displayed CAPI pane or interface.

value A Lisp object (not necessarily a string) to

make available within the local Lisp image.

string The string representation of *value* to export,

or nil. If nil and value is a string, then that

will be exported as the string.

plist A property list of additional format/value

pairs to export. The currently supported formats are :string, whose value should be a string, and :image whose value should be a image object. This allows you to export more than one format simultaneously.

Values result A string, or nil.

Description The function set-selection sets the primary selection to be

the text of string.

On Microsoft Windows there is no notion of selection, so this

mechanism is internal to Lisp.

Note that X applications may or may not use the primary selection for their paste operations. The most likely explanation for apparent inconsistencies after set-selection is that the pasting application doesn't use the primary selection. For instance, Emacs is configurable by the variable

interprogram-paste-function.

See also selection

set-clipboard

set-printer-metrics

Function

Summary Sets the metrics in the given printer.

Package capi

Signature set-printer-metrics printer & key left-margin top-margin width

height

Description The function set-printer-metrics sets the left margin and

top margin, and the printable width and printable height, of the given printer. Values outside the bounds of the printer

will be corrected.

Example To set the margins as large as possible:

Actually this sets the margins to the whole paper size, but the printer driver will move these in to take account of the minimum margins of the device.

See also get-printer-metrics

set-printer-options

print-dialog

set-printer-options

Function

Summary Sets various options in the given printer.

Package capi

Signature set-printer-options printer &key output-file first-page last-

page orientation copies

Description The function set-printer-options allows some printer

options for the current job to be set programmatically. Note that the user can change the various printer options in the

dialog displayed by print-dialog.

The *printer* argument should be a printer object returned by current-printer or print-dialog. This *printer* should then be passed to with-print-job to print using the options specified.

The keyword arguments control which options are set. If a keyword is not passed then the option remains unchanged.

Values of output-file are:

nil Print directly to the device.

t Print to a file chosen by the user at printing

time.

A pathname Print to the file given by pathname.

Values of first-page are:

:all Print all pages.

A integer Print from this page to the page given by

last-page.

Values of *orientation* are:

:landscape Print in landscape mode.

:portrait Print in portrait mode.

Values of copies:

A integer The number of copies to print.

Notes

Printer objects cannot be reused after changing their options or metrics. Call current-printer after set-printer-options to get a new printer object containing the latest settings.

Example

1 CAPI Reference Entries

See also print-dialog

current-printer
with-print-job

set-text-input-pane-selection

Generic Function

Summary Sets the selection in a text-input-pane.

Package capi

Signature set-text-input-pane-selection pane start end

Arguments pane A text-input-pane.

start, end Bounding indexes for a subsequence of the

text of pane.

Description The function set-text-input-pane-selection sets the

selection in pane to be the text bounded by the indexes start

(inclusive) and end (exclusive).

See also text-input-pane-selection

text-input-pane

set-top-level-interface-geometry

Generic Function

Summary Sets the geometry of a top level interface.

Package capi

Signature set-top-level-interface-geometry interface &key x y width

height

Arguments interface A CAPI interface.

x, y, width, height

Integers specifying the new geometry.

Description

The coordinates of *interface* are modified according to the keyword arguments passed. The value of *interface* should be a top level interface. If a keyword is omitted then that part of the coordinates is not changed.

x and *y* are measured from the top-left of the screen rectangle representing the area of the primary monitor (the primary screen rectangle).

Notes

On Cocoa set-top-level-interface-geometry behaves as if an interface toolbar is not present, even if *interface* does contain an interface toolbar.

```
Example
             (setf ii
                    (capi:element-interface
                     (capi:contain
                      (make-instance 'capi:text-input-pane))))
             (multiple-value-bind (x y width height)
                  (capi:top-level-interface-geometry ii)
                (capi:execute-with-interface
                ii
                'capi:set-top-level-interface-geometry
                :x (round (+ x (/ width 4)))
                :width (round (* 0.75 width))
                :height height))
See also
             top-level-interface-p
             top-level-interface-geometry
             top-level-interface-display-state
             interface
```

set-vertical-scroll-parameters

Generic Function

Summary Allows programmatic control of the parameters of a vertical

scroll bar.

Package capi

Signature set-vertical-scroll-parameters self & key min-range max-

range slug-position slug-size page-size step-size

Description The function set-vertical-scroll-parameters sets the

specified parameters of the vertical scroll bar of *self*, which should be a displayed instance of a subclass of output-pane

(such as editor-pane) or layout.

The other arguments are:

min-range The minimum data coordinate.

max-range The maximum data coordinate.

slug-position The current scroll position.

slug-size The length of the scroll bar slug.

page-size The scroll page size.

step-size The scroll step size.

Compatibility

note

The function set-vertical-scroll-parameters supersedes the function set-scroll-range, which is deprecated

and no longer exported.

The call

(set-vertical-scroll-parameters pane

:min-range 0
:max-range 42)

is equivalent to

(set-scroll-range pane nil 42)

Example See the following CAPI example files:

examples/capi/output-panes/scroll-test.lisp
examples/capi/output-panes/scrolling-without-bar.lisp

See also scroll

set-horizontal-scroll-parameters

simple-pane

shell-pane Class

Summary A pane allowing the user to interact with a subprocess.

Package capi

Superclasses interactive-pane

Initargs : command which is run as a subprocess.

Accessors shell-pane-command

Description The class shell-pane creates an editor in which a subprocess

runs.

User input is interpreted as input to the subprocess. In particular, when the user enters Return in the last line, the line is sent to the subprocess. The output of the subprocess is displayed in the pane.

The default value of command is nil, which means that the actual command is determined as follows:

On Unix/Linux and Mac OS X, the value of the environment variable ESHELL is used if set, and otherwise the environment variable SHELL is consulted. If that is not set, then /bin/csh (/bin/sh on SVR4 platforms) is run.

On Microsoft Windows 98/ME, command is run.

On Windows 2000/XP/Vista/Windows 7, cmd is run.

Example This function emulates user input on *pane*:

This function trampolines to send-keys-to-pane-aux on the right process:

This call emulates the user typing dir followed by Return:

(send-keys-to-pane sp "dir" t)

show-interface Function

Summary The show-interface function brings the interface contain-

ing a specified pane back onto the screen.

Package capi

Signature show-interface pane

Description This brings the interface containing *pane* back onto the screen.

To hide it again, use hide-interface.

See also hide-interface

activate-pane

show-pane Function

Summary Restores the specified pane to the screen.

Package capi

Signature show-pane pane => pane

Arguments pane An instance of simple-pane or a subclass.

Description The function show-pane restores the pane pane to the screen

if it is hidden (for instance by hide-pane) or iconified.

See also hide-pane

show-interface

simple-layout Class

Summary A simple-layout is a layout with a single child, and the

child is resized to fill the space (where possible).

Package capi

Superclasses x-y-adjustable-layout

Subclasses switchable-layout

Description A simple layout's description can be either a single child, or a

list containing just one child. The simple layout then adopts the size constraints of its child, and lays the child out inside

itself.

Example (capi:contain (make-instance

'capi:simple-layout

:description (list (make-instance

'capi:text-input-pane))))

1 CAPI Reference Entries

See also layout

row-layout column-layout

simple-network-pane

Class

Summary A graph pane which arranges its nodes in a grid.

Package capi

Superclasses graph-pane

Initargs :x-gap The horizontal node spacing.

:y-gap The vertical node spacing.

Description The class simple-network-pane provides a graph which

lays out its nodes in a rectangular grid by a simple algorithm.

The default values of x-gap and y-gap are 200 and 100 respec-

tively.

simple-network-pane is a subclass of choice, so for details

of its selection handling, see choice.

Example See the file examples/capi/graphics/network.lisp.

simple-pane Class

Summary The class simple-pane is the superclass for any elements

that actually appear as a native window, and is itself an

empty window.

Package capi

Superclasses element

Subclasses

display-pane
interface
title-pane
button-panel
list-panel
option-pane
output-pane
progress-bar
slider
text-input-pane
tree-view

tree-view toolbar layout button

Initargs

: enabled A boolean controlling whether the pane is

enabled.

:background The background color of the pane.

:foreground The foreground color of the pane.

:font The default font for the pane.

:horizontal-scroll

t, :without-bar, or nil. If true the pane

can scroll horizontally.

:vertical-scroll

t, :without-bar, or nil. If true the pane

can scroll vertically.

:visible-border

A boolean or a keyword controlling whether the pane has a border, for some pane classes.

:internal-border

A non-negative integer, or nil. Controls the

width of the internal border.

:cursor A keyword naming a built-in cursor, or a

cursor object, or mil.

:pane-menu Specifies a menu to be raised by the
:post-menu gesture.

:drop-callback

Specifies a drop callback for output-pane, interface, list-panel or tree-view.

Note that this is now supported for listpanel and tree-view on Cocoa and GTK+.

:drag-callback

Specifies a drag callback for list-panel or tree-view.

:automatic-resize

A plist.

:scroll-if-not-visible-p

Defines whether, when the focus is given to the pane and the pane is not fully visible, the pane's parent is automatically scrolled to show it.

:toolbar-titleA string.

Accessors simple-pane-enabled

simple-pane-background simple-pane-foreground

simple-pane-font
simple-pane-cursor

simple-pane-scroll-callback simple-pane-drop-callback simple-pane-drag-callback

Readers simple-pane-horizontal-scroll

simple-pane-vertical-scroll simple-pane-visible-border

Description enabled determines whether the pane is enabled. The default

value is t. Note that changing the enabled state of a visible

pane changes its appearance.

background and foreground are colors specified using the Graphics Ports color system. Additionally on Cocoa, the special value :transparent is supported, which makes the pane's background match that of its parent.

font should be a font, a font-description, or nil. If it is not a font, it is converted to a font when the pane is created. nil is converted to the default font, and a font-description is converted as if by calling find-best-font.

The value for *visible-border* can be any of the following, with the stated meanings where applicable:

nil Has no border.

t Has a border.

:default Use the default for the window type.

:outline Add an outline border.

There are various platform/pane class combinations which do not respond to all values of *visible-border*. For instance, on Windows XP with the default theme, text-input-choice and option-pane always have a visible border regardless of the value of *visible-border*, while other classes including display-pane, text-input-pane, list-panel, editor-pane and graph-pane have three distinct border styles, with *visible-border*:default meaning the same as *visible-border* t.

If *internal-border* is non-nil, it should be a non-negative integer specifying the width of an empty region around the edge of the pane.

Any simple pane can be made scrollable by specifying t to :horizontal-scroll or :vertical-scroll. By default these values are nil, but some subclasses of simple-pane default them to t where appropriate (for instance editor-panes always default to having a vertical scroll-bar).

For a pane which is scrollable but does not display a scroll bar, pass the value :without-bar for :horizontal-scroll or :vertical-scroll. See the example in output-panes/scrolling-without-bar.lisp.

The height and width of a scrollable simple pane can be specified by the initargs :scroll-height and :scroll-width, which have the same meaning as :internal-min-height and :internal-min-width. See the CAPI User Guide for more information about height and width initargs.

cursor specifies a cursor for the pane. nil means use the default cursor, and this is the default value. cursor can also be a cursor object as returned by load-cursor. The other allowed values are keywords naming built-in cursors which are supported on each platform as shown in the table below.

cursor	Cocoa	Windows	Motif
:busy	No	Yes	Yes
:i-beam	Yes	Yes	Yes
:top-left-arrow	Yes	Yes	Yes
:h-double-arrow	Yes	Yes	Yes
:v-double-arrow	Yes	Yes	Yes
:left-side	Yes	Yes	Yes
:right-side	Yes	Yes	Yes
:top-side	Yes	Yes	Yes
:bottom-side	Yes	Yes	Yes
:wait	No	Yes	Yes
:crosshair	Yes	Yes	Yes
:gc-notification	No	Yes	Yes
:top-left-corner	No	Yes	Yes
:top-right-corner	No	Yes	Yes

Table 1.2

cursor	Cocoa	Windows	Motif
:bottom-left-corner	No	Yes	Yes
:bottom-right- corner	No	Yes	Yes
:hand	Yes	Yes	Yes
:fleur	Yes	Yes	Yes
:move	Yes	Yes	Yes
:closed-hand	Yes	No	No
:open-hand	Yes	No	No
:disappearing-item	Yes	No	No

Table 1.2

pane-menu can be used to specify or create a menu to be displayed when the :post-menu gesture is received by the pane. It has the default value :default which means that make-pane-popup-menu is called to create the menu. For a full description of pane-menu, see the section "Popup menus for panes" in the CAPI User Guide.

drop-callback can be specified for a pane that is an instance of output-pane, interface, list-panel, tree-view or a subclass of one of these. When the user drags an object over a window, the CAPI first tries to call the drop-callback of any pane under the mouse and otherwise calls the drop-callback of the top-level interface. The default value of drop-callback is nil, which means that there is no support for dropping into the pane.

For editor-pane, *drop-callback* can be :default, which provides support for dropping a string into the pane and inserting the string into the pane's editor buffer.

If *drop-callback* is any other non-nil value, it should be either a list (for simple cases) or function designator (to use all options). When it is a function designator, it needs to have this signature:

drop-callback pane drop-object stage

The function *drop-callback* is called by the CAPI at various times such as when the pane is displayed and when the user attempts to drop data into the pane. *pane* is the pane itself, *drop-object* is an object used to communicate information about the current dropping operation (see below) and *stage* is a keyword. *drop-callback* should handle these values of *stage*:

:formats

This might occur when the pane is being displayed or might occur each time the user drags or drops an object over the pane. It should call set-drop-object-supported-formats with the *drop-object* and a list of formats that the pane wants to receive. Each format is a keyword. The list of the formats must be the same each time it is called.

:enter

This occurs when the user drags an object over the pane which is an output-pane or interface (not tree-view or list-panel). It can query the drop-object using drop-object-provides-format and drop-object-allows-drop-effect-p to discover what the user is dragging. It can also use drop-object-pane-x and drop-object-pane-y to query the mouse position relative to the pane. It should call (setf drop-object-drop-effect) with an effect if it wants to allow the object to be dropped. If this is not called, then the object cannot be dropped into the pane.

:drag

This occurs while the user is dragging an object over the pane. It can query the *drop-object* using drop-object-provides-format and drop-object-allows-drop-effect-p to discover what the user is dragging. For output-pane, it can use drop-

object-pane-x and drop-object-pane-y to query the mouse position relative to the pane. For list-panel and tree-view, it can use drop-object-collection-index or drop-object-collection-item to query where the user is attempting to drop the object and can call their setf functions to adjust this position. It should call (setf drop-object-drop-effect) with an effect if it wants to allow the object to be dropped. If this is not called, then the object cannot be dropped into the pane. For output-pane and interface, it might also want to update the pane to indicate where the object will be dropped.

:drop

This occurs when the user drops an object over the pane. It can query the drop-object as for the :drag stage, but can also obtain the object itself using drop-object-get-object for one of the formats in the list returned by drop-object-provides-format. Once the object is received, it should call (setf drop-object-drop-effect) with the effect that has been used by the callback. It should also update the pane to incorporate the object in whatever way the application requires.

When *drop-callback* is a list, it specifies a simple response. The list should be of the form:

(effects formats drop-stage-callback &optional checker)

Both *effects* and *formats* can be either a list of effects or formats, or an atom which is interpreted as a list of one element. *effects* and *formats* specify which effects and formats are allowed.

For the stages except :formats, the first effect of the given effects that the drop-object allows is set (by calling (setf drop-object-drop-effect)), except when checker is supplied. In the latter case, before setting an effect it loops through the formats and calls the checker with three arguments:

funcall checker pane effect format

If *checker* returns non-nil it sets the effect. If *checker* returns nil for the formats, it goes to the next effect.

In the :drop stage, after setting the effect, it gets the object with first format that is provided by the *drop-object*, and then calls the *drop-stage-callback* with four arguments:

funcall drop-stage-callback pane object x-or-index y-or-placement

If the pane is a tree-view or list-panel, the last two arguments are the item index (for get-collection-item) and placement (:above, :item, :below), which are the results of drop-object-collection-index. Otherwise, the last two arguments are the x and y (results of drop-object-pane-x and drop-object-pane-y). It is the responsibility of the drop-stage-callback to perform whatever dropping should mean.

drag-callback can be specified for a pane that is an instance of list-panel or tree-view. The default value of drag-callback is nil, which means that there is no support for dragging from the pane. Otherwise, it should be a function designator with this signature:

drag-callback pane info => result

When the user drags items in the pane, the CAPI calls the drag-callback. pane is the pane itself and info is a list of item indices that are being dragged (compare with choice-selection).

The *drag-callback* should normally return a plist *result* whose keys are the data formats to be dragged, with a value associated with each format. Formats are arbitrary keywords that must be interpreted by the pane where you intend to drop the values (see the *drop-callback*). The :string format is understood by some other panes that expect text.

The plist result returned by drag-callback can contain the key :image-function with a function image-function as value.

This function is used to generate the image that is used in the dragging itself, exactly as the *image-function* in drag-pane-object is used. On Cocoa, tree-view and list-panel ignore this key in *result*.

drag-callback can also be used in top-level interfaces. In this case the second argument *info* is a flag describing the gesture that caused the call. Currently the only value is :drag-image, which means it was invoked by dragging the drag-image (see interface).

drag-callback is allowed to return the result :default rather than a plist. :default tells the system to do default dragging if there is any. At the time of writing the only place where there is default dragging is on Cocoa for an interface with an :interface-pathname. drag-callback is allowed to return the result nil, meaning do not do dragging.

On output-pane you add dragging by adding an entry to the *input-model* and which initiates the dragging by calling drag-pane-object.

automatic-resize makes the pane resize automatically. This has an effect only if it is placed inside a static-layout (including subclasses like pinboard-layout). The effect is that when the static-layout is resized then the pane also changes its geometry.

The value of *automatic-resize* defines how the pane's geometry changes. It must be a plist of keywords and values which match the keywords of the function set-object-automatic-resize and are interpreted in the same way.

scroll-if-not-visible-p controls scrolling behavior of the parent when the pane is given the input focus. scroll-if-not-visible-p can be t, nil, or :non-mouse. See scroll-if-not-visible-p for details. When this initarg is supplied, the generic function (setf scroll-if-not-visible-p) is called with it.

If the pane is used in the *toolbar-items* list of an interface, then *toolbar-title* should be a short string that will be shown near to the pane if required for the toolbar.

Notes

- 1. foreground is ignored for buttons on Windows and Cocoa.
- 2. In order to display a simple pane, it needs to be contained within an interface. The two convenience functions make-container and contain are provided to create an interface with enough support for that pane. The function make-container just returns a container for an element, and the function contain displays an interface created for the pane using make-container.
- 3. On Cocoa in Mac OS X 10.2, the only supported *cursor* is :i-beam.
- 4. If :image is supplied in the *plist* returned by *drag-callback*, the dragging mechanism automatically frees the image object as if by free-image when it no longer needs it.
- You can also control automatic resizing of a simple-pane using set-object-automatic-resize.

simple-pane-handle

Function

Summary Returns the window handle of a pane.

Package capi

Signature simple-pane-handle pane => handle

Values handle An integer, or nil.

Description The function simple-pane-handle returns the handle of

pane in the system that displays it, if there is an underlying

window.

On Microsoft Windows *handle* is the hwnd of *pane*.

On X11/Motif, *handle* is the windowid of the main part of *pane* (type Window in the X library).

If pane is not displayed, or if pane does not have an underlying window, then handle is nil. Note that layouts do not

always have an underlying window.

1 CAPI Reference Entries

Use this function with caution: in general, drawing and moving of CAPI windows should be done through the CAPI.

See also current-dialog-handle

simple-pane-visible-height

Generic Function

Summary Gets the visible height of a pane.

Package capi

Signature simple-pane-visible-height pane => result

Arguments *pane* A simple pane.

Values result The height of the visible part of pane, or nil.

Description The generic function simple-pane-visible-height returns

the height in pixels of the visible part of *pane*, that is the height of the viewport, not including any borders or scroll bars. If *pane* is not displayed the function returns nil.

See the CAPI User Guide for a description of the visible size of

a pane.

See also simple-pane-visible-size

simple-pane-visible-width

with-geometry

simple-pane-visible-size

Generic Function

Summary Gets the visible size of a pane.

Package capi

Signature simple-pane-visible-size pane => width, height

Arguments *pane* A simple pane.

Values width The width of the visible part of pane, or nil.

height The height of the visible part of pane, or nil.

Description The generic function simple-pane-visible-size returns

the size in pixels of the visible part of *pane*, that is the width and height of the viewport, not including any borders or scroll bars. If *pane* is not displayed the return values are nil.

See the CAPI User Guide for a description of the visible size of

a pane.

See also simple-pane-visible-height

simple-pane-visible-width

with-geometry

simple-pane-visible-width

Generic Function

Summary Gets the visible width of a pane.

Package capi

Signature simple-pane-visible-width pane => result

Arguments *pane* A simple pane.

Values result The width of the visible part of pane, or nil.

Description The generic function simple-pane-visible-width returns

the width in pixels of the visible part of *pane*, that is the width of the viewport, not including any borders or scroll bars. If

pane is not displayed the function returns mil.

1 CAPI Reference Entries

See the $\it CAPI$ User $\it Guide$ for a description of the visible size of

a pane.

See also simple-pane-visible-height

simple-pane-visible-size

with-geometry

simple-pinboard-layout

Class

Summary A simple-pinboard-layout is a pinboard-layout that can

contain just one pinboard object or pane as its child, and it

adopts the size constraints of that child.

Package capi

Superclasses pinboard-layout

simple-layout

Subclasses graph-pane

Initargs :child The child of the pinboard layout.

Description The class simple-pinboard-layout is normally used to

place pinboard objects in a layout by placing the layout inside a simple-pinboard-layout, thus displaying the pin-

board objects. It inherits all of its layout behavior from

simple-layout.

```
Example
              (setq column
                    (make-instance
                     'capi:column-layout
                     :description
                     (list
                      (make-instance
                       'capi:image-pinboard-object
                       :image
                       (sys:lispworks-file
                        "examples/capi/graphics/Setup.bmp"))
                      (make-instance
                       'capi:item-pinboard-object
                       :text "LispWorks"))
                     :x-adiust :center))
              (capi:contain (make-instance
                             'capi:simple-pinboard-layout
                             :child column))
See also
              pinboard-object
```

simple-print-port

Function

Summary Prints the contents of an output pane to a printer.

Package capi

Signature simple-print-port port &key jobname scale dpi printer drawing-

mode interactive background

Description The simple-print-port function prints the output pane

specified by *port* to the default printer, unless specified otherwise by *printer*. The arguments of *scale* and *dpi* are used to determine how to transform the output pane's coordinate space to physical units. Their meaning here is the same as in <code>get-page-area</code>, except that *scale* may also take the value <code>:scale-to-fit</code>, in which case the pane is printed as large as possible on a single sheet.

The background color of the pane is ignored, and the value given by *background* is used instead. This defaults to :white.

drawing-mode should be either :compatible which causes drawing to be the same as in LispWorks 6.0, or :quality which causes all the drawing to be transformed properly, and allows control over anti-aliasing on Microsoft Windows and GTK+. The default value of drawing-mode is :quality.

For more information about *drawing-mode*, see "Drawing mode and anti-aliasing" in the *CAPI User Guide*.

If *interactive* is t, a print dialog is displayed. This is the default. If *interactive* is nil, then the document is printed to the current printer without prompting the user.

See also print-dialog

slider Class

Summary A pane with a sliding marker, which allows the user to con-

trol a numerical value within a specified range.

Package capi

Superclasses range-pane

titled-object simple-pane

Initargs :print-function

A function of two arguments, or a format

string.

:show-value-p A generalized boolean.

:start-point A keyword.

:tick-frequency

An integer, a ratio or the keyword

:default.

Accessors slider-print-function

Readers slider-show-value-p

slider-start-point
slider-tick-frequency

Description

The slider class allows the user to enter a number by moving a marker on a sliding scale to the desired value.

show-value-p determines whether the slider displays the current value, on Microsoft Windows and GTK+. The default value is t. *show-value-p* is ignored on Cocoa.

start-point specifies which end of the slider is the start point in the range. The values allowed depend on the *orientation* of the slider. For horizontal sliders, *start-point* can take these values:

:left The start point is on the left.

:right The start point is on the right.

:default The start point is at the default side (the left).

For vertical sliders, *start-point* can take these values:

top The start point is at the top.

:bottom The start point is at the bottom.

:default The start point is at the default position,

which is the top on Microsoft Windows and

Motif, and the bottom on Cocoa.

tick-frequency specifies the spacing of tick marks drawn on the slider. If tick-frequency is :default, then the slider may or may not draw tick marks according the OS conventions. If tick-frequency is 0, then no tick marks are drawn. If tick-frequency is a ratio 1/N for integer N>1, then tick marks are drawn to divide the slider range into N sections. Otherwise tick-frequency should be an integer greater than 1 which specifies the spacing of tick marks in units between start and end. The default value of tick-frequency is :default.

print-function, when supplied, should be a function with signature

print-function pane value => result

where *pane* is the slider pane, *value* is its current value, and *result* is a string or mil. When the slider pane displays the current value, it calls *print-function* and displays the value as *result*, unless that is mil, in which case the value is printed normally.

As a special case, *print-function* can also be a string, which is used as the format string in a call to format with one additional argument, the value, that is

(format nil print-function value)

and the result of this call to format is displayed.

Notes

- 1. :print-function is not implemented on Motif.
- 2. :print-function has no effect on Cocoa because the slider pane never displays the value
- 3. Use of the *print-function* is determined when the slider pane is displayed. Setting the *print-function* in a slider that did not have a *print-function* when it was first displayed does not work until the slider is destroyed and displayed again. Therefore, if you want to display a <code>slider</code> without a *print-function* but set it later, initially you should supply a *print-function* that always returns <code>nil</code>, for example:

- 4. print-function is useful for displaying fractional values or values that grow logarithmically (or any other non-linear function), because the actual values in a slider are always integers that increase linearly as the slider moves.
- 5. On Windows the slider's value is displayed (when *show-value-p* is true) in a tooltip that is visible only while the user moves the marker with a mouse.

Compatibility

In LispWorks 6.0 and earlier versions, ticks are drawn as if *tick-frequency* is :default.

Example

note

Given the default *start* and *end* of 0 and 100, this gives ticks at 0, 25, 50, 75 and 100:

(make-instance 'slider :tick-frequency 25) whilst this gives ticks at 0, 20, 40, 60, 80 and 100:

(make-instance 'slider :tick-frequency 1/5)

This example illustrates the use of print-function to display

fractional and non-linear values ranges:

capi/elements/slider-print-function.lisp

sort-object-items-by

Function

Summary Sorts items according to a sorted-object.

Package capi

Signature sort-object-items-by sorted-object items => result

Arguments sorted-object An instance of sorted-object or a sub-

class.

items A list.

Values result A permutation of items.

Description The function sort-object-items-by sorts items according

to the current sort type of sorted-object, as set by sorted-

object-sort-by.

Note: if the sort type is reversed, items will be sorted in

reverse order.

1 CAPI Reference Entries

See also sorted-object

sorted-object-sort-by
sorted-object-sorted-by

sorted-object Class

Summary Defines sorting operations.

Package capi

Superclasses standard-object

Subclasses list-panel

Initargs :sort-descriptions

A list.

Description The sorted-object class defines sorting operations.

Each element of *sort-descriptions* is a sort description object, as returned by make-sorting-description. These define various sorting options and are used by sorted-object-sort-

by and sort-object-items-by.

See also make-sorting-description

sort-object-items-by
sorted-object-sort-by
sorted-object-sorted-by

sorted-object-sort-by

Generic Function

Summary Sets the sorting type of a sorted-object.

Package capi

Signature sorted-object-sort-by pane new-sort-type &key allow-reverse

Arguments pane An instance of sorted-object or a sub-

class.

new-sort-type The sort type to set.

allow-reverse A boolean.

Description The generic function sorted-object-sort-by sets the sort

type of pane to new-sort-type.

new-sort-type must match the type of one of the sort descrip-

tions of pane.

If *allow-reverse* is non-nil and the sort type already matches *new-sort-type*, then the sort reverses the order of the *items*. The

default value of allow-reverse is t.

If pane is a list-panel, then sorted-object-sort-by also calls sort-object-items-by to sort the items with the new sort type. For your own subclasses of sorted-object which are not subclasses of list-panel, if you need this behavior define an :after method that calls sort-object-items-by. You can also define :after methods on subclasses of list-panel to perform other tasks each time the items are sorted.

See also sort-object-items-by

sorted-object

sorted-object-sorted-by

sorted-object-sorted-by

Function

Summary Returns the current sorting type and reverse flag of a

sorted-object.

Package capi

Signature sorted-object-sorted-by pane => sort-type, reversed

1 CAPI Reference Entries

Arguments pane An instance of sorted-object or a sub-

class.

Values *sort-type* A sort type.

reversed A boolean.

Description The function sorted-object-sorted-by returns the current

sorting type *sort-type* and reverse flag *reversed* of *pane*.

sort-type is the *type* of one of the sort descriptions of *pane*. *reversed* is true if the pane is sorted in reverse order and false

if it is sorted in normal order.

See also sorted-object

sorted-object-sort-by

start-gc-monitor

Function

Summary Starts a Lisp Monitor window.

Package capi

Signature start-gc-monitor screen => result

Arguments screen A screen.

Values result A boolean.

Description The function start-gc-monitor starts a Lisp Monitor

window (otherwise known as the GC or Garbage Collector

monitor) on the screen screen.

result is t if it started a Lisp monitor, and nil if a Lisp moni-

tor was already running on screen.

Note that this works only on Motif. There is no Lisp Monitor

window on other platforms.

On Motif, start-gc-monitor is called automatically when the LispWorks IDE starts, but you can call stop-gc-monitor and start-gc-monitor any time.

See also stop-gc-monitor

static-layout Class

Summary A layout that allows its children to be positioned anywhere

within itself.

Package capi

Superclasses layout

Subclasses pinboard-layout

Initarqs :fit-size-to-children

A generalized boolean.

Description The class static-layout is a layout that allows its children to be positioned anywhere within itself

to be positioned anywhere within itself.

When a static-layout lays out its children, it positions them at the x and y specified as hints (using :x and :y), and sizes them to their minimum size (which can be specified using :visible-min-width and :visible-max-width).

If fit-size-to-children is true, the static-layout is made sufficiently large to accommodate all of its children, and grows if necessary when a child is added. This is the default behavior. Otherwise the static layout has a minimum size of one pixel by one pixel which is not affected by the size of its children. If you need the sizing capabilities, then use the class simple-layout which surrounds a single child, and adopts the size constraints of that child.

Example

Here is an example of a static layout placing simple panes at arbitrary positions inside itself.

See also

pinboard-layout

stop-gc-monitor

Function

Summary Stop a Lisp Monitor.

Package capi

Signature stop-gc-monitor screen => result

Arguments *screen* A screen.

Values result A boolean.

Description The function stop-gc-monitor stops the Lisp Monitor

window on the screen screen.

result is t if it stopped a Lisp monitor, and mil if there was no

Lisp monitor running on screen.

Note that this works only on Motif. The Lisp monitor can be

restarted with start-gc-monitor.

See also start-gc-monitor

stop-sound Function

Summary Stops a sound from playing.

Signature stop-sound sound

Arguments sound A sound object returned by load-sound.

Description The function stop-sound stops the sound from play-

ing.

See also play-sound

switchable-layout

Class

Summary A subclass of simple-layout that displays only one of its

children at a time, and provides functionality for switching

the displayed child to one of the other children.

Package capi

Superclasses simple-layout

Initargs :visible-child

The currently visible pane from the children.

:combine-child-constraints

A generalized boolean.

Readers switchable-layout-visible-child

switchable-layout-combine-child-constraints

Description

The switchable-layout has a *description* which is its list of children. The argument *visible-child* specifies the initially visible child (which defaults to the first of the children).

switchable-layout inherits most of its layout behavior from simple-layout as it only ever lays out one child at a time.

combine-child-constraints influences the initial size of the layout. When combine-child-constraints is nil the constraints of the switchable layout depend only on its currently visible child pane. Switching to a different child pane might cause the layout to resize. When combine-child-constraints is non-nil, the constraints depend on all of the child panes, including those that are not visible. This might increase the time taken to create the switchable layout initially, but can prevent unexpected resizing later. The default value of combine-child-constraints is nil.

Example

There is a further example in the file

examples/capi/layouts/switchable.lisp.

See also simple-layout

switchable-layout-switchable-children

switchable-layout-switchable-children

Generic Function

Summary Finds the switchable children of a switchable-layout.

Package capi

Signature switchable-layout-switchable-children switchable-layout

=> result

Arguments switchable-layout

An instance of switchable-layout or a

subclass.

Values result A list of panes.

Description The generic function switchable-layout-switchable-

children returns as a list all the children of switchable-layout that could be made visible by calling the switchable-layout accessor (setf switchable-layout-visible-

child).

See also switchable-layout

tab-layout Class

Summary The class tab-layout has two distinct modes. Switchable

mode lays a number of panes in a switchable layout. Each pane has an associated tab which, when clicked on, pulls the pane to the front. In callback mode the tabs are linked to a

selection-callback as for button-panel.

Package capi

1 CAPI Reference Entries

Superclasses choice

layout

Initargs :description The main layout description.

:items Specifies the tabs of the tab layout.

:visible-child-function

Returns the visible child for a given selection in switchable mode.

:combine-child-constraints

A generalized boolean which influences the initial size of the layout.

: key-function Specifies a function to use in referring to items in the *items* list.

:print-function

The function used to print a name on each tab.

:callback-typeThe type of data passed to the callback function in callback mode.

:selection-callback

The function called when a tab is selected, in callback mode.

:image-function

Returns an image for an item, on Microsoft Windows

:image-lists

A plist of keywords and image-list objects, on Microsoft Windows.

ACCESSORS tab-layout-visible-child-function

Readers tab-layout-combine-child-constraints

tab-layout-image-function

Description

A tab-layout has one of two distinct modes. It is in switchable mode if *visible-child-function* is supplied and non-nil. It is in callback mode otherwise.

In switchable mode, the tab layout consists of a number of panes, each with its own tab. Clicking on a tab pulls the corresponding pane to the front. In this mode the tab layout is like a switchable-layout with the switching performed by the user selecting a tab. In this mode the *visible-child-function* is used to specify which child to make visible for a given tab selection.

In callback mode the tab layout does not work as a switchable layout, and the result of any selection is specified using a callback specified by *selection-callback*, in a similar way to a button-panel callback. In this mode the *description* slot is used to describe the main layout of the tab pane.

In either mode *combine-child-constraints* influences the initial size of the layout. When *combine-child-constraints* is nil the constraints of the tab layout depend only on its currently visible tab. Switching to a different tab might cause the layout to resize. When *combine-child-constraints* is non-nil, the constraints depend on all of the tabs, including those that are not visible. This might increase the time taken to create the tab layout initially, but can prevent unexpected resizing later. The default value of *combine-child-constraints* is nil.

If image-lists is specified, it should be a plist containing the keyword :normal as a key. The corresponding value should be an image-list object. No other keys are supported at the present time. The image-list associated with the :normal key is used with the image-function to specify an image to display in each tab.

The *image-function* is called on an item to return an image associated with the item. It can return one of the following:

A pathname or string

This specifies the filename of a file suitable for loading with load-image. Currently this must be a bitmap file.

A symbol

The symbol must have been previously registered by means of a call to registerimage-translation.

An image object, as returned by load-image.

An image locator object

This allowing a single bitmap to be created which contains several button images side by side. See make-image-locator for more information. On Microsoft Windows, it also allows access to bitmaps stored as resources in a DLL.

An integer

This is a zero-based index into the tab-layout's image-list. This is generally only useful if the image list is created explicitly. See image-list for more details.

Notes

image-lists and *image-function* are implemented only on Microsoft Windows.

Example

The following example shows the use of the switchable mode of tab-layout. Each tab is linked to an output pane by pairing them in the *items* list.

```
(defun switchable-tab-layout ()
  (let* ((red-pane (make-instance
                    'capi:output-pane
                    :background :red))
         (blue-pane (make-instance
                     'capi:output-pane
                     :background :blue))
         (tl (make-instance
              'capi:tab-layout
              :items
              (list (list "Red" red-pane)
                    (list "Blue" blue-pane))
              :print-function 'car
              :visible-child-function 'second)))
    (capi:contain tl)))
(switchable-tab-layout)
```

Here is an example of the callback mode of tab-layout, which uses the selection of a tab to change the nodes of a graph pane through the *selection-callback*.

```
(defun non-switchable-tab-layout (tabs)
  (let* ((gp (make-instance
              'capi:graph-pane))
         (tl (make-instance
              'capi:tab-layout
              :description (list gp)
              :items tabs
              :visible-child-function nil
              :key-function nil
              :print-function
              (lambda (x)
                (format nil "~R" x))
              :callback-type :data
              :selection-callback
              #'(lambda (data)
                  (setf (capi:graph-pane-roots gp)
                         (list data))))))
    (capi:contain tl)))
(non-switchable-tab-layout '(1 2 4 5 6))
```

1 CAPI Reference Entries

See also callbacks

simple-layout

switchable-layout
tab-layout-panes

tab-layout-visible-child

tab-layout-panes

Function

Summary Returns the panes in a tab-layout.

Package capi

Signature tab-layout => panes

Arguments tab-layout A tab-layout.

Values panes A list.

Description The function tab-layout-panes returns the panes in a tab-

layout. Note that this is not necessarily the same as the items of *tab-layout*, since *visible-child-function* and/or *key* may be

specified.

See also tab-layout

tab-layout-visible-child

Function

Summary Returns the visible child in a tab-layout.

Package capi

Signature tab-layout-visible-child tab-layout => result

Arguments tab-layout A tab-layout.

Values result A pane.

Description The function tab-layout-visible-child returns the cur-

rently-visible pane in a tab-layout.

See also tab-layout

text-input-choice

Class

Summary This pane consists of a text input area, and a button. Clicking

on the button displays a drop-down list of strings, and selecting one of the strings automatically pastes it into the text

input area.

Package capi

Superclasses choice

text-input-pane

InitarqS :visible-items-count

An integer specifying the maximum length

of the drop-down list, or the symbol

:default.

:popup-callback

A function called just before the drop-down

list appears, or nil.

Description The text-input-choice class behaves in the same way as a

text-input-pane, but has additional functionality. The element inherits from choice, and the choice *items* are used as the items to display when the user clicks on the button.

The callback is called when the user presses the Return key.

The selection-callback is called when the user selects an item

using the drop-down list.

1 CAPI Reference Entries

Compatibility In LispWorks 6.0 and earlier versions the text-input-pane note

initary value enabled : read-only is not supported for text-

input-choice on Microsoft Windows. This restriction is

removed for LispWorks 6.1 and later versions.

Examples See examples/capi/elements/text-input-choice.lisp.

See also choice

text-input-pane

Class text-input-pane

Summary The class text-input-pane is a pane for entering a single

line of text.

Package capi

Superclasses titled-object

simple-pane

Subclasses multi-line-text-input-pane

> password-pane text-input-choice

Initargs The text in the pane. :text

:caret-position

The position of the caret in the text (from 0).

:max-characters

The maximum number of characters

allowed.

Controls the enabled state of the pane. :enabled

:completion-function

A function called to complete the text.

:in-place-completion-function

A function designator.

:file-completion

t, nil or a pathname designator.

:in-place-filter

A boolean.

:directories-only

A boolean.

:ignore-file-suffices

A list of strings or the keyword :default.

:callback-typeThe type of arguments to callback.

:callback A function usually called when the user presses Return.

:change-callback-type

The type of arguments to *change-callback*.

:change-callback

A function called when a change is made.

:confirm-change-function

A function called to validate a change. **Note:** Implemented for Motif only, not Microsoft Windows or Mac OS X.

:navigation-callback

A function called when certain keyboard gestures occur in the pane.

:editing-callback

A function called when editing starts or stops.

:gesture-callbacks

A list of pairs (gesture . callback).

:complete-do-action

A boolean.

:text-change-callback

A function designator.

:buttons A plist specifying buttons to add, or t or

nil.

:search-field

Along with the next four initargs, this is implemented only on Cocoa. It specifies that the pane has "recent-items", which also

means using NSSearchField.

:recent-items

See :search-field above.

:recent-items-name

See : search-field above.

:maximum-recent-items

See :search-field above.

:recent-items-mode

See :search-field above.

Accessors text-input-pane-text

text-input-pane-max-characters

text-input-pane-completion-function

text-input-pane-callback

text-input-pane-confirm-change-function

text-input-pane-change-callback text-input-pane-navigation-callback text-input-pane-editing-callback

text-input-pane-enabled

text-input-pane-buttons-enabled

Readers text-input-pane-caret-position

Description The class text-input-pane provides a great deal of flexibil-

ity in its handling of the text being entered. It starts with the initial text and caret-position specified by the arguments *text*

and *caret-position* respectively. It limits the number of characters entered with the *max-characters* argument (which defaults to nil, meaning there is no maximum).

If enabled is nil, the pane is disabled. If enabled is :read-only, then the pane shows the text and allows it to be selected without it being editable. In this case the visual appearance varies between window systems, but often the text can be copied and the caret position altered. If enabled is any other true value, then the pane is fully enabled. The default value of enabled is t.

A completion-function can be specified which will get called when the completion gesture is made by the user (by pressing the Tab key) or when text-input-pane-complete-text is called. The function should have signature:

completion-function pane string => completions, start, end

where pane is the text-input-pane itself and string is the string to complete. When completion is invoked completion-function is called with pane and a string containing the text of pane to the left of the cursor.

The *completion-function* is called with the pane and the text to complete and should return either nil, the completed text as a string or a list *completions* of candidate completions. In the latter case, the CAPI will prompt the user for the completion they wish, and this will become the new text. In addition, the *completion-function* can return two more values, *start* and *end*, which specify a range in the text that is to be replaced if the completion is successful.

in-place-completion-function tells the pane to do in-place completion and specifies the function to use. The function should have signature:

in-place-completion-function pane string => completions,
start, end

where pane is the text-input-pane itself and string is the string to complete. When in-place completion is invoked *in-place-completion-function* is called with pane and a string containing the text of pane to the left of the cursor.

completions needs to be a list of strings that are possible completions, a single string that is a unique completion, or the symbol :destroy. :destroy means that the in-place completion needs to stop and close the in-place window. In addition, the completion function can return two more values, start and end, which specify a range in the text that is to be replaced if the completion is successful. The function is called repeatedly whenever there is a change to the text that should be completed.

Note: If *in-place-completion-function* needs some dynamic information, it can put it in a property of the pane (using capi-object-property).

Note: The initarg:file-completion overrides:in-place-completion-function.

Note: The in-place completion mechanism uses *gesture-call-backs* to implement the functionality.

Note: :in-place-filter can be used to specify that the inplace window can have a filter.

See "In-place completion" in the *CAPI User Guide* for the user interaction.

file-completion, if non-nil, tells the pane to do file completion using an in-place window. See "In-place completion" in the *CAPI User Guide* for the interaction.

If *file-completion* is a pathname designator, its location is used as the root path for the completion.

Note::file-completion overrides:in-place-completion-function.

Note: The behavior of in-place completion is somewhat different from other completion.

Note: The initargs :directories-only and :ignore-filesuffices can be used to change the behavior of the completion.

The default value of *file-completion* and *in-place-completion-function* is nil.

in-place-filter takes effect only when either in-place-completion-function or file-completion is non-nil. If in-place-filter is t then the in-place window can have a filter. Note that the filter needs to requested by a user gesture. Control+Return is the default in-place filter gesture. The default value of in-place-filter is t.

directories-only takes effect only if file-completion is used. If directories-only is then in-place completion shows only directories. The default value of directories-only is mil.

ignore-file-suffices takes effect only if file-completion is used. It tells in-place completion to ignore files whose file namestring (the result of cl:file-namestring) ends with any of the strings in the list ignore-file-suffices. If ignore-file-suffices is :default, then completion uses the default value, which is the value of editor:*ignorable-file-suffices* (see config/a-dot-lispworks.lisp).

callback, if non-nil, is called when the user presses Return, unless navigation-callback is non-nil, in which case navigation-callback is called instead. If the pane has "recent-items" (implemented only on Cocoa) then the timing of calls to callback is modified: see the discussion of recent-items below for the details.

When the *text* or *caret-position* is changed, the callback *change-callback* is called with the *text*, the pane itself, the interface and the *caret-position*. The arguments that are passed to the *change-callback* can be altered by specifying the *change-callback-type* (see the callbacks class for details of possible values).

Note: the *change-callback* is potentially called more than once for each user gesture.

With the Motif implementation it is possible to check changes that the user makes to the text-input-pane by providing a confirm-change-function which gets passed the new text, the pane itself, its interface and the new caret position, and which should return non-nil if it is OK to make the change. If nil is returned, then the pane will be unaltered and a beep will be signalled to indicate that the new values were invalid.

navigation-callback, if non-nil, is a function that will be called when certain navigation gestures are used in the text-input-pane. The function is called with two arguments, the pane itself, and one of the following keywords:

:tab-forward

Tab was pressed.

:tab-backward Tab Backwards (usually Shift+Tab) Was pressed.

:return Return was pressed.

:shift-return Shift+Return Was pressed.

:enter Enter was pressed.

:shift-enter

Shift+Enter was pressed.

Note: Enter is the key usually found on the numeric keypad.

When navigation-callback is non-nil, it is called instead of callback when Return is pressed. callback is still called via an OK button if there is one (see buttons below).

navigation-callback is implemented only on Microsoft Windows and Cocoa.

editing-callback, if non-nil, is a function of two arguments:

editing-callback pane type

pane is the text-input-pane and type is a keyword. editing-callback is called with type:start when the user starts editing and type:end when the user stops editing. In general, this occurs when the focus changes, but on Cocoa type:start is passed when the first change is made to the text.

gesture-callbacks provides callbacks to perform for specific keyboard gestures. Each gesture must be an object that sys:coerce-to-gesture-spec can coerce to a gesture-spec. Each callback can be a callable (symbol or function) which takes one argument, the pane. Alternatively each callback can be a list of the form (function arguments). Note that in this case, the pane itself is not automatically passed to the function amongst arguments.

When the user enters a gesture that matches *gesture* in any pair amongst *gesture-callbacks*, the *callback* is executed and the gesture is not processed any more.

Note: The interaction of in-place completion is implemented using *gesture-callbacks*. Gestures which you define explicitly by *gesture-callbacks* override the gestures which are defined implicitly by the in-place completion mechanism.

Note: For gestures that change the text, *text-change-callback* is probably better than *gesture-callbacks*.

When *complete-do-action* is non-nil, completion of the text in the pane automatically invokes *callback* (if *callback* is non-nil). The default value of *complete-do-action* is nil.

text-change-callback is a change callback (see change-callback) that is called only when the text in the pane changes. In contrast, change-callback is also called when the caret moves. If both text-change-callback and change-callback are supplied, only text-change-callback is invoked.

buttons specifies toolbar buttons which appear next to the pane and facilitate user actions on it. It also specifies the position of the buttons relative to the pane. This feature appears in the LispWorks IDE, for example the Class box of the Class Browser.

The allowed keys and values of the plist *buttons* are:

:ok

A boolean or a plist, default value t. If true, a button which calls *callback* appears. If the value is a plist then this plist supplies details for the button, as described below.

:cancel

A boolean or a plist, default value nil. If true, a button which calls cancel-function appears. A plist value is interpreted as for :ok and can also contain the key :accelerator which specifies an accelerator used for the button. There is no default accelerator.

:completion

A boolean or a plist. If true, a button which calls *completion-function* appears. The default value is t if *completion-function* is non-nil, and nil otherwise. A plist value is interpreted as for :ok.

:browse-file

A keyword or a plist. If true, a button which invokes prompt-for-file appears. If the value is :save or :open then it is passed as the operation argument to prompt-for-file, replacing the text in the pane if successful. If the value is a plist, then it supplies details for the button, as described below, and can also contain the keywords :mes-sage to specify a message for the file prompter; :pathname to specify the default pathname of the file prompter (defaults to the text in the text-input-pane) or any of the keywords :ok-check, :filter,:fil-

ters, :if-exists, :if-does-not-exist, :operation, :owner, :pane-args Or :popup-args Which are passed directly to prompt-for-file.

:cancel-function

A function that expects the pane as its single argument. The default is a function which sets *text* to the empty string.

:help

Specifies a help button. The value must be a plist containing either keys:function and optionally:arguments, or the keys:title,:message and optionally:dialog-p.

If *function* is supplied, when the user presses the help button it calls

(apply function pane arguments)

where pane is the text-input-pane. *title*, *message* and *dialog-p* are ignored in this case.

Otherwise when the user presses the help button it opens a window with title title displaying the string message in a display-pane. The message can be long, and can include newlines. The window is owned by the pane, but is not modal, so the user can interact with the pane while the help window is displayed. If dialog-p is true, the help window is raised as a dialog. The default value for dialog-p is nil. function and arguments are ignored in this case.

The plist can contain other keys as described below.

:orientation

The value is either :horizontal or :vertical. orientation controls the orientation of the toolbar. This is useful for multi-line-text-input-pane. The default value is :horizontal.

:adjust

The value is :top, :center, :centre or :bottom. adjust controls how the buttons are adjusted vertically relative to the text input pane. This is useful for multi-line-text-input-pane. The default value is :center.

:position

The value is :top, :bottom, :left or :right. position determines whether the buttons appear above, below, left or right of the text input pane. If :position is not supplied, then the buttons appear to the right of the pane.

The value mil for *buttons* means there are no buttons - this is the default. When *buttons* is true the buttons appear or not according to their specified values or their default values.

All of the button plists (for :ok, :cancel, :help and so on) can contain the following keys and values in addition to those mentioned above:

:enabled

A value that controls whether the button is enabled. (See the reader text-input-pane-buttons-enabled).

:image

The image to use for the button. This should be either a pathname or string naming an image file to load, a symbol giving the id of an image registered with register-image-translation, an image object as returned by load-image or an external-image. The default image is one of the symbols ok-but-

ton, cancel-button or complete-button, which are pre-registered image identifiers corresponding to each button.

:help-key

The *help-key* used to find a tooltip for the button.

The text-input-pane-buttons-enabled reader returns a list containing keywords such as:ok, :cancel and :completion, one for each corresponding button (as specified by buttons) that is currently enabled.

The (setf text-input-pane-buttons-enabled) writer takes a list of keywords as described for the reader and sets the enabled state of the buttons, enabling each button if it appears in the list and disabling it otherwise. The value t can also be passed: this enables all the buttons.

For more than one line of input, use multi-line-text-input-pane.

If *search-field* is a string and *recent-items-name* is not supplied, then the value *search-field* is used as the name. See the discussion of *recent-items* below.

If any of search-field, recent-items or recent-items-name is supplied and is non-nil, the pane uses NSSearchField, and also has "recent items". The NSSearchField has a different appearance from text-input-pane, can display recent items menu, and its input behavior is a little different too.

If *recent-items* is non-nil, it must be a list of strings, or t. When it is a list of strings, it specifies the initial list of "recent items". When it is t, it simply specifies that the pane should handle recent items.

If *recent-items-name* is non-nil, it should be a string. The string specifies the autosave name of the pane. When a pane has an autosave name, Cocoa remembers the list of recent items for pane with the same autosave name and same application. The record persists between invocations of the application.

If *recent-items-name* is not supplied or is nil, and *search-field* is a string, it is used instead as the name.

The maximum number of recent items defaults to 50 and can be controlled by the initary value *maximum-recent-items*. The value 0 can be used to switch off the "recent items" feature, including the menu.

The recent items list can be read and set by text-inputpane-recent-items, or modified by any of text-inputpane-replace-recent-items, text-input-pane-deleterecent-items, text-input-pane-append-recent-items, text-input-pane-prepend-recent-items and textinput-pane-set-recent-items.

The input behavior of text-input-pane with "recent items" is the same is that of other text-input-panes except for the timing of calls to *callback*. Note that this refers to the function that is passed with the initarg :callback. The :change-callback is not affected.

By default, each time the user types a character it causes a scheduling of *callback* some short time later. If the user types another character before the callback, it is re-scheduled later. The result is that as long as the user types, there are no callbacks, but once the user stops a callback is generated.

The behavior of callback can be controlled by the initarg value recent-items-mode, which can be one of :explicit, :delayed or :immediate. :explicit gives the same behavior as a normal text-input-pane, :delayed is the default described above, and :immediate means doing a callback immediately after each character. In addition, when the user selects an item from the recent items menu or clicks its Cancel button, the callback is called. In the case of the Cancel button, the string would be empty.

Compatibility note

The confirm-change-function was called before-change-callback in LispWorks 3.1. Both the old initiarg :before-change-callback and the old accessor text-input-pane-before-change-callback are still supported, but may not be in future releases.

Example

```
(capi:contain (make-instance 'capi:text-input-pane
                             :text "Hello world"))
(setq tip (capi:contain
                       (make-instance
                        'capi:text-input-pane
                        :enabled nil)))
(capi:apply-in-pane-process
 tip #'(setf capi:text-input-pane-enabled) t tip)
(capi:apply-in-pane-process
tip #'(setf capi:text-input-pane-enabled) nil tip)
(capi:apply-in-pane-process
tip #'(setf capi:text-input-pane-text) "New text" tip)
(capi:contain (make-instance
               'capi:text-input-pane
               :text "Hello world"
               :callback #'(lambda (text interface)
                             (capi:display-message
                              "Interface ~S's text: ~S"
                              interface text))))
```

This example uses a plist value for the *buttons* key :cancel to specify that the Cancel button is initially disabled:

This example shows how to specify a Help button which displays a help message:

```
(defvar *help-message* "A long help message.")
(capi:contain
 (make-instance 'capi:text-input-pane
                :buttons
                 `(:help
                   (:title "help window"
                    :message ,*help-message*))))
This example illustrates the use of gesture-callbacks. Ctrl+e
moves the cursor to the end of the input, Ctrl+a moves it to
the start, and Ctrl+6 does something else:
(capi:contain
 (make-instance
  'capi:text-input-pane
  :gesture-callbacks
  (list
   (cons
    #\Ctrl-\e
    #'(lambda (tip)
        (setf (capi:text-input-pane-caret-position tip)
               (length (capi:text-input-pane-text
tip)))))
   (cons
    #\Ctrl-\a
    #'(lambda (tip)
        (setf (capi:text-input-pane-caret-position tip)
              0)))
   (cons
    #\Ctrl-6 'do-something-else))))
There is a further example in the file
examples/capi/elements/text-input-pane.lisp
display-pane
editor-pane
multi-line-text-input-pane
text-input-choice
text-input-pane-complete-text
text-input-range
```

See also

title-pane

text-input-pane-append-recent-items

Function

Summary Modifies the recent items list in a text-input-pane on

Cocoa.

Signature text-input-pane-append-recent-items text-input-pane &rest

strings

Arguments text-input-pane A text-input-pane with recent items.

strings Strings.

Values There is no meaningful return value.

Description The function text-input-pane-append-recent-items

modifies the recent items list in a text-input-pane that has recent-items (see text-input-pane initargs :search-field, :recent-items and :recent-items-name). It appends the strings at the end of the recent items, using text-input-

pane-set-recent-items with where = :end.

Notes text-input-pane-append-recent-items is implemented

only on Cocoa.

See also text-input-pane

text-input-pane-set-recent-items

text-input-pane-delete-recent-items

Function

Summary Modifies the recent items list in a text-input-pane on

Cocoa.

Signature text-input-pane-delete-recent-items text-input-pane &rest

strings

Arguments text-input-pane A text-input-pane with recent items.

strings Strings.

Values There is no meaningful return value.

Description The function text-input-pane-delete-recent-items

modifies the recent items list in a text-input-pane that has recent-items (see text-input-pane initargs :search-field, :recent-items and :recent-items-name). It deletes from the recent items any item that matches any of the strings (compared using cl:string-equal), using text-input-

pane-set-recent-items with where = :delete.

Notes text-input-pane-delete-recent-items is implemented

only on Cocoa.

See also text-input-pane

text-input-pane-set-recent-items

text-input-pane-prepend-recent-items

Function

Summary Modifies the recent items list in a text-input-pane on

Cocoa.

Signature text-input-pane-prepend-recent-items text-input-pane &rest

strings

Arguments text-input-pane A text-input-pane with recent items.

strings Strings.

Values There is no meaningful return value.

Description The function text-input-pane-prepend-recent-items

modifies the recent items list in a text-input-pane that has recent-items (see text-input-pane initargs :search-field, :recent-items and :recent-items-name). It prepends the strings at the beginning of the recent items, using text-input-pane-set-recent-items with where = :start.

Notes text-input-pane-prepend-recent-items is implemented

only on Cocoa.

See also text-input-pane

text-input-pane-set-recent-items

text-input-pane-recent-items

Function

Summary Gets and sets the recent items in a text-input-pane on

Cocoa.

Signature text-input-pane-recent-items text-input-pane => list-of-strings

(setf text-input-pane-recent-items) list-of-strings text-

input-pane => list-of-strings

Arguments text-input-pane A text-input-pane with recent items.

list-of-strings A list of strings.

Description The function text-input-pane-recent-items gets and sets

the recent items in a text-input-pane that has recent-items. (see text-input-pane initargs :search-field, :recent-

items and :recent-items-name).

The value list-of-strings passed to (setf text-input-pane-

recent-items) must be a list of strings.

Notes text-input-pane-recent-items is implemented only on

Cocoa.

text-input-pane-recent-items does not work properly

before the pane is displayed.

See also text-input-pane

text-input-pane-set-recent-items

text-input-pane-replace-recent-items

Function

Summary Modifies the recent items list in a text-input-pane on

Cocoa.

Signature text-input-pane-replace-recent-items text-input-pane &rest

strings

Arguments text-input-pane A text-input-pane with recent items.

strings Strings.

Values There is no meaningful return value.

Description The function text-input-pane-replace-recent-items

modifies the recent items list in a text-input-pane that has recent-items (see text-input-pane, initargs :search-field, :recent-items and :recent-items-name), using

text-input-pane-set-recent-items With where =

:replace.

recent items in the pane by the strings. It has the same effect as (setf text-input-pane-recent-items), but takes the

strings as &rest arguments.

Notes text-input-pane-replace-recent-items is implemented

only on Cocoa.

See also text-input-pane

text-input-pane-set-recent-items

text-input-pane-set-recent-items

Function

Summary Sets the recent items in a text-input-pane.

Signature text-input-pane-set-recent-items text-input-pane strings

where

Arguments text-input-pane A text-input-pane with recent items.

strings A list of strings.

where One of the keywords :replace, :delete,

:start and :end, or a non-negative integer.

Values text-input-pane-set-recent-items does not return a

meaningful value.

Description The function text-input-pane-set-recent-items sets the

recent items in a text-input-pane. The text-input-pane must have recent items, that is it must have been created with one of the keyword arguments :search-field, :recent-items or :recent-items-name. The strings argument must

be a list of strings.

text-input-pane-set-recent-items modifies the recent items according to the argument *where*, which can one of:

:replace The strings replace the recent items in the

text-input-pane.

:delete Delete from the recent items any item that

matches any of the string (using cl:string-

equal).

:start Insert the strings at the beginning of the

recent items.

: end Insert the strings at the end of the recent

items.

A non-negative integer

Insert the strings at the position indicated by the value. 0 means the same as :start. If the integer is greater than the length of the current recent items list, the strings are inserted

in the end of the list.

In all cases, if any of the strings is already in the recent-items list (as compared by cl:string-equal), it is first deleted from the list. This means that passing strings that already exist just moves them around in the list.

Notes text-input-pane-set-recent-items is a little more effi-

cient than using text-input-pane-recent-items and (setf text-input-pane-recent-items) but the different

is unlikely to be significant.

See also text-input-pane

text-input-pane-replace-recent-items text-input-pane-delete-recent-items text-input-pane-append-recent-items text-input-pane-prepend-recent-items

text-input-pane-complete-text

Function

Summary Calls the *completion-function* in a text-input-pane.

Package capi

Signature text-input-pane-complete-text pane => result

Arguments pane A text-input-pane.

Values result A string, or nil.

Description The function text-input-pane-complete-text calls the

completion-function of pane with the current text. If this call is successful, then the text of pane is set to the result, and text-input-pane-complete-text returns this result. Otherwise,

result is nil.

Note: the *completion-function* may return a list of completion candidates, in which case text-input-pane-complete-text prompts the user to select one of the candidates.

See also text-input-pane

text-input-pane-copy

Function

Summary Copies the selected text in a text-input-pane to the clip-

board

Package capi

Signature text-input-pane-copy text-input-pane

Arguments text-input-pane An instance of text-input-pane or a sub-

class.

Description The function text-input-pane-copy performs the clip-

board copy operation on the selected text in *text-input-pane*. It

does nothing if there is no selection.

See also clipboard

text-input-pane

text-input-pane-selection

text-input-pane-cut
text-input-pane-delete
text-input-pane-paste

text-input-pane-cut

Function

Summary Cuts the selected text in a text-input-pane to the clipboard

Package capi

Signature text-input-pane-cut text-input-pane

Arguments text-input-pane An instance of text-input-pane or a sub-

class.

1 CAPI Reference Entries

Description The function text-input-pane-cut performs the clipboard

cut operation on the selected text in text-input-pane. It does

nothing if there is no selection.

See also clipboard

text-input-pane

text-input-pane-selection

text-input-pane-copy text-input-pane-delete text-input-pane-paste

text-input-pane-delete

Function

Summary Deletes the selected text in a text-input-pane.

Package capi

Signature text-input-pane-delete text-input-pane

Arguments text-input-pane An instance of text-input-pane or a sub-

class.

Description The function text-input-pane-delete deletes the selected

text in *text-input-pane*. It does nothing if there is no selection.

See also clipboard

text-input-pane

text-input-pane-selection

text-input-pane-cut
text-input-pane-copy
text-input-pane-paste

text-input-pane-in-place-complete

Function

Summary Raises the non-focus completion window.

Signature text-input-pane-in-place-complete text-input-pane

Arguments text-input-pane A text-input-pane

Description The function text-input-pane-in-place-complete raises

the non-focus completion window.

The pane *text-input-pane* must have been made with either *in- place-completion-function* or *file-completion*. See the description

of this functionality in text-input-pane.

See also text-input-pane

text-input-pane-paste

Function

Summary Pastes the clipboard text into a text-input-pane.

Package capi

Signature text-input-pane-paste text-input-pane

Arguments text-input-pane An instance of text-input-pane or a sub-

class.

Description The function text-input-pane-paste performs the clip-

board paste operation on text-input-pane, replacing any

selected text.

See also clipboard

text-input-pane

text-input-pane-selection

text-input-pane-cut
text-input-pane-copy
text-input-pane-delete

text-input-pane-selected-text

Function

Summary Returns the selected text in a text-input-pane.

Package capi

Signature text-input-pane-selected-text text-input-pane => result

Arguments text-input-pane An instance of text-input-pane or a sub-

class.

Values result A string or nil.

Description The function text-input-pane-selected-text returns the

selected text in *text-input-pane*, or nil if there is no selection.

See also text-input-pane

text-input-pane-selection
text-input-pane-selection-p

text-input-pane-selection

Function

Summary Returns the bounds of the selection in a text-input-pane.

Package capi

Signature text-input-pane-selection pane => start, end

Arguments pane A text-input-pane.

Values *start, end* Non-negative integers.

Description The function text-input-pane-selection returns as multi-

ple values the bounding indexes of the selection in *pane*. That is, *start* is the inclusive index of the first selected character, and *end* is one greater than the index of the last selected character.

acter.

If there is no selection, then both *start* and *end* are the caret

position in pane.

See also set-text-input-pane-selection

text-input-pane

text-input-pane-selected-text
text-input-pane-selection-p

text-input-pane-selection-p

Function

Summary Returns true if there is selected text in a text-input-pane.

Package capi

Signature text-input-pane-selection-p pane => selectionp

Arguments pane A text-input-pane.

Values selectionp A boolean.

Description The function text-input-pane-selection-p returns t if

there is a selected region in pane and nil otherwise.

See also set-text-input-pane-selection

text-input-pane

text-input-pane-selected-text
text-input-pane-selection

Summary The class text-input-range is a pane for entering a number

in a given range. Typically there are up and down buttons at

the side which can used to quickly adjust the value.

Package capi

Superclasses titled-object

simple-pane

Initargs :start An integer specifying the lowest possible

value in the range.

end An integer specifying the highest possible

value in the range.

:wraps-p A generalized boolean.

:value An integer specifying the current value in

the pane.

:callback A function called when the value is changed

by the user.

:change-callback

A function called called when the user edits

the text in the pane.

:callback-typeThe type of arguments passed to the call-

back.

Accessors text-input-range-start

text-input-range-end
text-input-range-wraps-p
text-input-range-value
text-input-range-callback

text-input-range-change-callback text-input-range-callback-type Description

The class text-input-range provides numeric input of integers in a given range (some systems refer to this a spinner or spin-box).

The range is controlled by the :start and :end initargs. start defaults to 0 and end defaults to 10. The initial value is set with the argument value (which defaults to 0).

wraps-p controls what happens if the user presses the up or down button until the start or end is reached. If wraps-p is nil, then it stops at the limit. If wraps-p is true then it wraps around to the other end. The default value of wraps-p is nil.

callback, if non-nil, should be a function to be called whenever the value is changed by the user. The arguments to callback are specified by callback-type (see the callbacks class for details of possible values, noting that the "data" is the value and the "item" is the pane itself). The default callback-type is (:item :data). Note that, if the value is changed by the user editing the text, then change-callback, if supplied, is called as well.

change-callback, if non-nil, should be a function of four arguments, to be called when the user edits the text in the pane. It should have this signature:

change-callback string pane interface caret-position

where the arguments are interpreted just as for the change-callback of text-input-pane. Note that editing of the text may or may not change the value in the text-input-range (that is, what text-input-range-value returns). If the value does change, then callback is called too.

Notes

On Cocoa, change-callback is not called for a cursor move only.

```
Example
```

See also text-input-pane

text-input-choice

option-pane

title-pane Class

Summary This class provides a pane that displays a single line of text.

Package capi

Superclasses titled-object

simple-pane

Subclasses message-pane

Initargs : text The text to appear in the title pane.

ACCESSORS title-pane-text

Description The most common use of title panes is as a title decoration for

a pane, and so the class titled-object is provided as a class

that supports placing title panes around itself.

A title-pane with *text* "Title" is created automatically

when a titled-object is created with title "Title".

By default, a title-pane is constrained so that it cannot

resize (that is, the values of visible-max-width and

visible-max-height are t). This can be overidden by passing
:visible-max-width nil or :visible-max-height nil.

Example (setq title-pane (capi:contain

(make-instance
 'capi:title-pane

:text "This is a title pane")))

(capi:apply-in-pane-process

title-pane #'(setf capi:title-pane-text)

"New title" title-pane)

See also display-pane

text-input-pane editor-pane

titled-menu-object

Class

Summary The class titled-menu-object is a subclass of menu-object

which supports titles, and it is used by menus, menu compo-

nents and menu items.

Package capi

Superclasses menu-object

Subclasses menu

menu-component

menu-item

Initargs :title The title for the object.

:title-function

A setup callback which returns the title for the object, and optionally a mnemonic for

the title.

Accessors menu-title

menu-title-function

Description The simplest way to give a title to a titled-menu-object is

to just supply a *title* string, and this will then appear as the

title of the object.

Alternatively, a *title-function* can be provided which will be called when the menu is about to appear and which should return the title to use. By default *title-function* is called on the interface of the titled-menu-object, but this argument can be changed by passing the menu-object initarg *setup-call*-

back-argument.

To specify a mnemonic in the title returned by *title-function*, make *title-function* return the mnemonic as a second value. This value is interpreted in the same way as the *mnemonic* argument for menu.

Example

titled-object

Class

Summary

The class titled-object is a mixin class which provides support for decorating a pane with a title (a piece of text positioned next to the pane) and with a message (a piece of text below the pane).

Package

capi

Subclasses

interface
layout
title-pane
display-pane
text-input-pane

toolbar
button-panel
list-panel
option-pane
progress-bar
output-pane
slider

Initargs

:title A title string for the pane (or nil).

:title-args Initargs to the title make-instance.

:title-font The font used for the title.

:title-position

The position of the title.

:title-adjust How to adjust the title relative to the pane.

:title-gap The gap between the title and the pane.

:message A message string for the pane (or nil).

:mnemonic-title

A string specifying the title and a mnemonic. Applies only to the subclasses specified below.

:message-gap

The gap between the message and the pane.

Accessors

titled-object-title titled-object-title-font titled-object-message titled-object-message-font

Description

The titled pane makes its title decoration from a title-pane and the message decoration from a message-pane.

The text of the title-pane is passed via the titled-object initarg title and the text of the message-pane is passed via the titled-object initarg message.

The initargs and font for the title-pane are passed via the titled-object initargs title-args and title-font respectively.

title-gap specifies the size in pixels of the gap between the title and the pane. The default value of *title-gap* is 3.

For subclasses other than interface, the font used for the *message* can be found by titled-object-message-font and set by (setf titled-object-message-font).

message-gap specifies the size in pixels of the gap between the message and the pane. The default value of *message-gap* is 3.

The message is always placed below the pane, but the title's position can be adjusted by specifying *title-position* which can be any of the following.

:left Place the title to the left of the pane.
:right Place the title to the right of the pane.
:top Place the title above the pane.
:bottom Place the title below the pane.
:frame Place the title in a frame (like a groupbox) around the pane.

The title-adjust slot is used to adjust the title so that it is left justified, right justified or centered. The value of title-adjust can be any of the values accepted by the function pane-adjusted-offset, which are :left, :right, :top, :bottom, :center and :centre.

Note: *title-adjust* cannot handle both x and y. It is designed for cases like this:

mnemonic-title offers an alternate way to provide the pane's title, and with a mnemonic. It takes effect only for button-panel, list-panel, list-view, option-pane, output-pane, progress-bar, scroll-bar, slider, text-input-pane, text-input-range, tree-view and their subclasses, and is interpreted as described for menu.

Note: titles and mnemonic titles can now be added in a grid-layout.

Compatibility note

titled-object corresponds to the LispWorks 4.1 class titled-pane. For backwards compatibility the accessors titled-pane-title and titled-pane-message, including setf methods, are provided. These simply trampoline to titled-object-title and titled-object-message, and may not be supported in future releases.

Example

Try each of these examples to see some of the effects that titled panes can produce. Note that text-input-pane is a subclass of titled-object, and that it has a default title-position of :left.

```
(capi:contain (make-instance 'capi:text-input-pane))
(capi:contain (make-instance 'capi:text-input-pane
                            :title "Enter some text:"))
(capi:contain (make-instance
               'capi:text-input-pane
               :title "Enter some text:"
               :title-position :top))
(capi:contain (make-instance 'capi:text-input-pane
                              :title "Enter some text:"
                              :title-position :top
                              :title-adjust :center))
(capi:contain (make-instance 'capi:text-input-pane
                             :title "Enter some text:"
                             :title-position :top
                             :title-adjust :right))
(capi:contain (make-instance 'capi:text-input-pane
                              :message "A message"))
(capi:contain (make-instance 'capi:text-input-pane
                              :message "A message"
                            :title "Enter some text:"))
(capi:contain (make-instance 'capi:text-input-pane
                             :title "Enter some text:"
                             :title-args
                              '(:foreground :red)))
```

See also message-pane title-pane

titled-pinboard-object

Class

Summary A pinboard object with a title.

Package capi

Superclasses pinboard-object

titled-object

Subclasses image-pinboard-object

Description The class titled-pinboard-object provides a pinboard

object with a title. The title is regarded as part of the object in

geometry calculations.

Note: titled-pinboard-object does not allow the value :frame for the titled-object initarg title-position. The values :top, :bottom, :left and :right are allowed.

Example

This example creates three instances of titled-pinboardobject and one of item-pinboard-object, all with with a yellow background. Note that:

- The title does not have the yellow background in the titled-pinboard-object, as opposed to the item-pinboard-object. To specify the title background, we pass it in the title-args.
- 2. The width of the title area is determined by the title, but passing :visible-min-width (and other geometric hints) can be used to override this.
- 3. Setting the titled-object-title of the titled-pin-board-object does not reset its width.

```
(setq tpo1 (make-instance 'capi:titled-pinboard-object
                                         :graphics-args
                                         '(:background :yellow)
                                         :x 10 :y 10
                                         :width 150 :height 20
                                         :title "Short"
                                         :title-position :left
                                         :title-args
                                         '(:background :red ))
                          (make-instance 'capi:titled-pinboard-object
                   tpo2
                                         :graphics-args
                                         '(:background :yellow)
                                         :x 10 :y 40
                                         :width 150 :height 20
                                         :title "Long title"
                                         :title-position :left)
                   tpo3
                          (make-instance 'capi:titled-pinboard-object
                                         :graphics-args
                                         '(:background :yellow)
                                         :x 10 :y 70
                                         :width 150 :height 20
                                         :title "Short"
                                         :title-position :left
                                         :title-args
                                         '(:visible-min-width 100))
                         (make-instance 'capi:item-pinboard-object
                   ipo
                                        :graphics-args
                                        '(:background :yellow)
                                        :x 10 :y 100
                                        :width 150 :height 20
                                        :text "Item Pinboard" ))
              (setq pl (capi:contain
                        (make-instance 'capi:pinboard-layout
                                       :visible-min-width 200
                                       :visible-min-height 200
                                       :description
                                       (list tpo1 tpo2 tpo3 ipo))))
              (capi:apply-in-pane-process
              pl
              #'(lambda()
                   (setf (capi:titled-object-title tpo1)
                         "Longer...")))
See also
             item-pinboard-object
```

toolbar Class

Summary This class provides a pane containing toolbar buttons and

panes.

Package capi

Superclasses collection

simple-pane titled-object toolbar-object

Initargs : dividerp If t, a divider line is drawn above the tool-

bar, to separate it from the menu bar. The

default value is nil.

:images A list of images.

:callbacks A list of callback functions.

:tooltips A list of tooltip strings used on Microsoft

Windows.

:button-width The width of the toolbar buttons.

:button-heightThe height of the toolbar buttons.

:stretch-text-p

A generalized boolean.

:image-width The width of images in the toolbar.

:image-height The height of images in the toolbar.

:default-image-set

An optional image-set object which can be used to specify images. See toolbar-button and image-set for more details.

:flatp A generalized boolean.

Readers toolbar-flat-p

Description

The class toolbar inherits from collection, and therefore has a list of *items*. It behaves in a similar manner to pushbutton-panel, which inherits from choice.

The *items* argument may be used to specify a mixture of toolbar-buttons and toolbar-components, or it may contain arbitrary objects as items. The list may also contain CAPI panes, which will appear within the toolbar. This is typically used with text-input-pane, option-pane, and text-input-choice.

For items that are not toolbar buttons or toolbar components, a toolbar button is automatically created, using the appropriate elements of the *images*, *callbacks* and *tooltips* lists. If no image is specified, the item itself is used as the image. For more information on acceptable values for *images*, see toolbar-button.

Each of the *images*, *callbacks* and *tooltips* lists should be in one-to-one correspondence with the items. Elements of these lists corresponding to toolbar-button items or toolbar-component items are ignored.

Note: :tooltips is now deprecated. Use the interface *help-callback* with *help-key* :tooltip instead.

All toolbar buttons within the item list behave as push buttons. However, toolbar button components may have :single-selection or :multiple-selection interaction. See toolbar-component for further details.

button-width and button-height specify the size of each button in the toolbar. If a button contains text and *stretch-text-p* is true, then the button stretches to the width of the toolbar if needed.

images, if supplied, must specify images all of the same size.

image-width and *image-height* must match the sub-image dimensions in *default-image-set* or the dimensions of the *images*.

flatp specifies whether the toolbar is 'flat' on Cocoa. If flatp is true, then the buttons do not have a visible outline until the user moves the mouse over them. flatp is only implemented on Cocoa. (On Microsoft Windows, all toolbars are flat. On Motif, no toolbar is flat.) The default value of flatp is

:default.

Notes text-input-pane, option-pane, and text-input-choice

and so on cannot contain titles when embedded in a toolbar.

See also collection

image-set

push-button-panel
toolbar-component

toolbar-button Class

Summary This class is used to create instances of toolbar buttons.

Package capi

Superclasses item

toolbar-object

Initargs :callback A function that is called when the user

presses the toolbar button and *popup-inter-*

face is non-nil.

:image Specifies the image to use for the toolbar

button.

:selected-image

Specifies the image to use for the toolbar

button when it is selected.

:tooltip An optional string which is displayed, on

Microsoft Windows, when the mouse moves over the button. :tooltip is deprecated.

:help-key An object used for lookup of help. Default

value t.

:remapped Links the button to a menu item.

:dropdown-menu

A menu or nil.

:dropdown-menu-function

A function of no arguments, or mil.

:dropdown-menu-kind

One of the keywords :button, :only and

:delayed.

:popup-interface

An interface or nil.

Accessors toolbar-button-image

toolbar-button-selected-image toolbar-button-dropdown-menu

toolbar-button-dropdown-menu-function toolbar-button-dropdown-menu-kind toolbar-button-popup-interface

Readers help-key

Description Toolbar buttons may be placed within toolbars and toolbar

components. However, there is usually no need to create toolbar buttons explicitly; instead, the *callbacks* and *images* arguments to toolbar or toolbar-component can be used. To add tooltips, use the interface *help-callback* with *help-key*

:tooltip.

In addition, an interface can have its own toolbar buttons, specified by its *toolbar-items*. There is no toolbar object in that situation.

image and selected-image may each be one of the following:

A pathname or string

This specifies the filename of a file suitable for loading with load-image. Currently this must be a bitmap file.

A symbol

The symbol must either have been previously registered by means of a call to register-image-translation, or be one of the following symbols, which map to standard images: :std-cut, :std-copy, :std-paste, :std-undo, :std-redo, :std-delete, :std-file-new, :std-file-open, :std-file-save, :std-print, :std-print-pre, :std-properties, :std-help, :std-find and :std-replace

On Microsoft Windows, the following symbols are also recognized for view images: :view-large-icons, :view-small-icons, :view-list, :view-details, :view-sort-name, :view-sort-size, :view-sort-date, :view-sort-type, :view-parent-folder, :view-net-connect, :view-net-disconnect and :view-new-folder.

Also on Microsoft Windows, these symbols are recognized for history images: :hist-back, :hist-forward, :hist-favorites, :hist-addtofavorites and :hist-viewtree.

An image object, as returned by load-image.

An image locator object

This allows a single bitmap to be created which contains several button images side by side. See make-image-locator for more

information. On Microsoft Windows, this also allows access to bitmaps stored as

resources in a DLL.

An integer This is a zero-based index into the *default-*

image-set of the toolbar or toolbar component in which the toolbar button is used.

Each image should be of the correct size for the toolbar. By default, this is 16 pixels wide and 16 pixels high.

help-key is interpreted as described for element.

remapped, if non-nil, should match the name of a menu-item in the same interface as the button. Then, the action of pressing the button is remapped to selecting that menu-item and calling its callback. The default value of remapped is nil.

Toolbar buttons can be made with an associated dropdown menu by passing the :dropdown-menu or :dropdown-menu-function initargs.

If *dropdown-menu* is non-nil then it should be a menu object to display for the button.

If dropdown-menu-function is non-nil then it should be a function which will be called with the toolbar-button as its single argument. It should return a menu object to display for the button.

dropdown-menu-kind can have the following values:

:button	There is a separate smaller button for the
	dropdown menu next to the main button.

:only There is no main button, only the smaller

button for the dropdown.

:delayed There is only one button and the menu is

displayed when the user holds the mouse down over the button for some short delay. If the user clicks on the button then the

normal callback is called.

Note: *dropdown-menu-kind* is not supported for toolbar buttons in the interface *toolbar-items* list.

popup-interface, if non-nil, should be an interface. When the user clicks on the toolbar button, the interface popup-interface is displayed near to the button. The normal callback is not called, but you can detect when the interface appears by using its activate-callback. popup-interface is useful for popping up windows with more complex interaction than a menu can provide. The default value of popup-interface is nil.

Note: *popup-interface* is not supported for toolbar buttons in the interface *toolbar-items* list.

Toolbar buttons can display text, which should be in the *data* or *text* slot inherited from item.

Note: display of text in toolbar buttons is implemented only on Motif and Cocoa.

Example

A callback function:

```
(defun do-redo (data interface)
  (declare (ignorable data interface))
  (capi:display-message "Doing Redo"))
```

A simple interface:

```
(capi:define-interface redo ()
  (:panes
   (toolbar
   capi:toolbar
   :items
    (list
     (make-instance
      'capi:toolbar-component
     :items
      (list (make-instance
             'capi:toolbar-button
             ;; remap it to the menu item
             :remapped 'redo-menu-item
             :image :std-redo))))))
  (:menu-bar a-menu)
  (:menus
   (a-menu
   "A menu"
    (("Redo" :name 'redo-menu-item
             :selection-callback 'do-redo
             :accelerator "accelerator-y"))))
  (:layouts
   (main
   capi:row-layout
    '(toolbar)))
  (:default-initargs
   :title "Redo"))
```

In this interface, pressing the toolbar button invokes the menu item callback:

```
(capi:display (make-instance 'redo))
```

This last example illustrates the use of :selected-image.

```
(capi:contain
               (make-instance
                'capi:toolbar
                :items
                (list
                 (make-instance
                  'capi:toolbar-component
                  :interaction :multiple-selection
                  :items
                  (list (make-instance 'capi:toolbar-button
                                       :image 0
                                       :selected-image 1))
                  ))))
See also
             item
             make-image-locator
             menu-item
             toolbar
             toolbar-component
```

toolbar-component

Class

Summary

A toolbar component is used to group several toolbar buttons together. Each component is separated from the surrounding components and buttons.

Toolbar components are choices, and may be used to implement toolbars on which groups of button have single-selection or multiple-selection functionality.

Package capi

Superclasses toolbar-object

choice

Initargs : images A list of images, in one-to-one correspon-

dence with the items. Elements corresponding to toolbar-button items or toolbar-

component items are ignored

:callbacks

A list of callback functions, in one-to-one correspondence with the items. Elements corresponding to toolbar-button items or toolbar-component items are ignored

:tooltips

A list of tooltip strings, in one-to-one correspondence with the items. Elements corresponding to toolbar-button items or toolbar-component items are ignored

:default-image-set

An optional image-set object which can be used to specify images. See toolbar-button and image-set for more details.

:selection-function

A function to dynamically compute the selection.

:selected-item-function

A function to dynamically compute the selected item.

:selected-items-function

A function to dynamically compute the selected items.

Description

The class toolbar-component inherits from choice, and hence has a list of *items*. Its behavior is broadly similar to button-panel.

The *items* argument may be used to specify a mixture of toolbar-buttons and toolbar-components, or may contain arbitrary objects as items. The list may also contain CAPI panes, which will appear within the toolbar. This is typically used with text-input-pane, option-pane, and text-input-choice.

For items that are not toolbar buttons or toolbar components, a toolbar button is automatically created, using the appropriate elements of the *images*, *callbacks* and *tooltips* lists. If no image is specified, the item itself is used as the image. For more information on acceptable values for images, see toolbar-button.

No more than one of selection-function, selected-item-function and selected-items-function should be non-nil. Each defaults to nil. If one of these is non-nil, it should be a function which is called before the toolbar-component is displayed and when update-toolbar is called and which determines which items are selected. The function takes a single argument, which is the interface of the toolbar-component.

selection-function, if non-nil, should return a list of indices suitable for passing to the choice accessor (setf choice-selection).

selected-item-function, if non-nil, should return an object which is an item in the toolbar-component, or is equal to such an item when compared by the toolbar-component's test-function and key-function.

selected-items-function, if non-nil, should return a list of such objects.

Example See examples/capi/elements/toolbar.lisp.

See also toolbar

toolbar-button

toolbar-object Class

Summary This is a common superclass of all toolbar objects.

Package capi

Superclasses None

Subclasses toolbar

toolbar-button
toolbar-component

Initargs : enabled If t, the toolbar object is enabled.

:enabled-function

A function determining the enabled state.

ACCESSORS simple-pane-enabled

toolbar-object-enabled-function

Description Any toolbar object may be disabled, by setting its *enabled* slot

to mil. Disabling a toolbar or toolbar component prevents the

user from interacting with any buttons contained in it.

All toolbar objects may also have an *enabled-function* specified. This is called whenever update-toolbar is called. If it returns t, the toolbar object will be enabled; if it returns nil,

the object will be disabled.

Notes The function enabled-function should not display a dialog or

do anything that may cause the system to hang. In general this means interacting with anything outside the Lisp image,

including files, databases and so on.

See also toolbar

toolbar-button toolbar-component update-toolbar

top-level-interface

Generic Function

Summary Returns the top level interface containing a specified pane.

Package capi

1 CAPI Reference Entries

Signature top-level-interface pane

Description Returns the top level interface that contains *pane*.

See also top-level-interface-p

interface element

top-level-interface-display-state

Generic Function

Summary Returns a value which indicates how the top level interface is

displayed.

Package capi

Signature top-level-interface-display-state interface

Arguments interface A top level interface or dialog window

Description Top level interfaces and dialogs can be manipulated by the

user, such as being iconifed or maximized. The program can manipulate these windows too. The function top-level-interface-display-state returns a value that indicates the current state of the interface interface. The following values can be returned:

:normal The window is visible and has its normal

size.

:maximized The window is visible and has been maxi-

mized.

:iconic The window is visible as an icon.

:hidden The window is not visible.

These values can also be passed as the :display-state initary when making a top level interface.

In addition, the function (setf top-level-interface-display-state) can be used to change the state of a top level interface. The value can be set to one of the above, or to :restore if the current state is :iconic or :hidden. When set to :restore, the state will become :normal or :maxi-mized depending on how the interface was visible in the past.

See also

top-level-interface-p
top-level-interface-geometry
set-top-level-interface-geometry
interface

top-level-interface-geometry

Generic Function

Summary Returns the geometry of the top level interface.

Package capi

Signature top-level-interface-geometry interface => tx, ty, twidth,

theight

Arguments *interface* An interface.

Values tx, ty, twidth, theight

Integers.

Description

The generic function top-level-interface-geometry returns the coordinates of the given interface in a form suitable for use as the :best-x, :best-y, :best-width and :best-height initargs to interface. The value of interface should be a top level interface.

tx and *ty* are measured from the top-left of the screen rectangle representing the area of the primary monitor (the primary screen rectangle).

Notes

On Cocoa, the result does not account for the size of the interface toolbar, if present in *interface*.

Example

```
;; Define and display an interface.
             (capi:define-interface test ()
               ()
               (:panes (panel capi:list-panel)))
             (setq int (capi:display (make-instance 'test)))
             ;; Now manually position the interface somewhere.
             ;; Find where the interface is.
             (multiple-value-setg (tx ty twidth theight)
               (capi:top-level-interface-geometry int))
             ;; Now manually close the interface.
             ;; Create a new interface in the same place.
             (setq int
                    (capi:display
                     (make-instance
                     'test
                     :best-x tx
                     :best-y ty
                     :best-width twidth
                     :best-height theight)))
See also
             top-level-interface-p
             top-level-interface-display-state
             set-top-level-interface-geometry
             interface
```

top-level-interface-geometry-key

Generic Function

Summary Determines where the geometry of an interface is saved.

Package capi

Signature top-level-interface-geometry-key interface => key, product-

name

Arguments interface A top level interface.

Values key A symbol.

product-name A symbol, a string or a list of strings.

Description

The generic function top-level-interface-geometry-key returns as multiple values a key and a product name, which determine where the geometry of *interface* is saved. The saved geometry is used when displaying a future instance.

The supplied method on interface returns the class name of *interface* as the *key*, and nil as the *product-name*. You can define methods for your interfaces and products.

key must be a symbol.

product-name is used to derive the *product-registry-path*.

product-name can be a symbol which was previously defined to have a registry path by

(setf sys:product-registry-path).

product-name can alternatively be a string, which is taken directly as *product-registry-path*.

product-name can alternatively be a list of strings, denoting multiple path components. These are concatenated together with the appropriate separator for the platform to give product-registry-path.

The geometry of *interface* is saved at the path which is constructed by concatenating (with appropriate separators) these values:

user-path product-registry-path "Environment" (symbolpackage key) (symbol-name key)

where *user-path* is the registry branch HKEY_CURRENT_USER on Microsoft Windows and the home directory on Unix/Linux and Mac OS X.

CAPI Reference Entries

Note: for your interface classes for which you want the geometry to be saved, define a method on top-level-interface-save-geometry-p.

Note: in an image delivered at delivery level 5, symbol names are removed by default. This breaks the saved geometry mechanism as the registry path is constructed using symbol-name. To make this work in a level 5 delivered image, explicitly keep the *key* symbol. See the *LispWorks Delivery User Guide* for details.

See also top-level-interface-save-geometry-p

top-level-interface-p

Generic Function

Summary The predicate for top level interfaces.

Package capi

Signature top-level-interface-p pane

Description The generic function top-level-interface-p returns true if

pane is a top level interface.

See also top-level-interface

top-level-interface-geometry

top-level-interface-display-state

interface element

top-level-interface-save-geometry-p

Generic Function

Package capi

Signature top-level-interface-save-geometry-p interface => result

Description The generic function top-level-interface-save-geome-

try-p returns true if the geometry of interface should be

saved for use by a future instance.

The default method (on interface) returns nil.

See also top-level-interface-geometry-key

tracking-pinboard-layout

Class

Summary A pinboard with automatic highlighting.

Package capi

Superclasses pinboard-layout

Description The class tracking-pinboard-layout provides a pinboard

which tracks mouse movement by highlighting its objects as

the mouse cursor moves over them.

This functionality is implemented via a :motion specification in the *input-model*. Therefore, you may not specify :motion in

the input-model of a tracking-pinboard-layout. See

output-pane for a description of input-model.

```
Example
              (defclass my-ellipse (capi:drawn-pinboard-object)
                ((color :initarg :color
                        :initform :red
                        :accessor my-ellipse-color)))
              (defun draw-my-ellipse
                     (output-pane self x y width height)
                     (let ((x-radius (floor width 2))
                           (y-radius (floor height 2)))
                            (gp:draw-ellipse output-pane
                               (+ x x-radius) (+ y y-radius)
                              x-radius y-radius
                              :foreground
                               (mv-ellipse-color self)
                              :filled t)))
              (defun change-ellipse-color (pinboard x y)
                (let ((ellipse
                       (capi:pinboard-object-at-position
                        pinboard x y)))
                  (when ellipse
                    (let ((color
                           (capi:prompt-for-color
                            "New color"
                            :color
                            (my-ellipse-color ellipse)
                            :owner
                            (capi:convert-to-screen))))
                      (when color
                        (setf (my-ellipse-color ellipse) color)
                        (capi:with-geometry ellipse
                          (gp:invalidate-rectangle
                           pinboard
                           capi:%x%
                           capi:%y%
                           capi:%width%
                           capi:%height%)))))))
              (capi:contain
               (make-instance
                'capi:tracking-pinboard-layout
                :description
                (loop for i below 20
                      collect
                      (make-instance 'my-ellipse
                                     :x (+ 5 (random 290))
                                      :y (+ 5 (random 290))
```

tree-view Class

Summary A tree view is a pane that displays a hierarchical list of items.

Each item may optionally have an image and a checkbox.

Package capi

Superclasses choice

titled-object simple-pane

Initargs :roots A list of the root nodes.

:children-function

Returns the children of a node.

:leaf-node-p-function

Optional function which determines whether a node is a leaf node (that is, has no children). This is useful if it can be computed faster than the *children-function*.

:retain-expanded-nodes

Specifies if the tree view remembers whether hidden nodes were expanded.

:expandp-function

A designator for a function of one argument, or nil.

:action-callback-expand-p

A boolean. The default value is nil.

:delete-item-callback

A function designator for a function of two arguments.

:right-click-extended-match

Controls the area within which selection by the mouse right button occurs. Default t.

:has-root-line

Controls whether the line and expanding boxes of the root nodes are drawn. Default t.

Initargs for handling check boxes. Note that these do not work on Cocoa:

:checkbox-status

Controls whether the tree has checkboxes, except on Cocoa. If non-nil, the value should be a non-negative integer less than the length of the image-list, or t.

An integer specifies the default initial status, and t means the same as 2 (that is, by default the checkboxes are checked initially).

The default is mil, meaning no checkboxes.

:checkbox-next-map

Controls the change in status when the user clicks on a checkbox. Can be an array, a function or an integer. Default # (2 2 0).

:checkbox-parent-function

Controls the changes in the ancestors when the status of an item is changed. :checkbox-child-function

Controls the changes in the descendents when the status of an item is changed.

:checkbox-change-callback

A function called when the status of an item is changed interactively.

:checkbox-initial-status

Specifies the initial status of specific items.

Initargs for handling images:

:image-function

Returns an image for a node.

:state-image-function

Returns a state image for a node.

:image-lists

A plist of keywords and image-list objects.

:use-images Flag to specify whether items have images.

Defaults to t.

:use-state-images

Flag to specify whether items have state images. Defaults to nil.

:image-width Defaults to 16.

:image-height Defaults to 16.

:state-image-width

Defaults to image-width.

:state-image-height

Defaults to *image-height*.

Accessors

tree-view-roots

tree-view-children-function tree-view-image-function

tree-view-state-image-function
tree-view-leaf-node-p-function
tree-view-retain-expanded-nodes

tree-view-expandp-function

tree-view-action-callback-expand-p
tree-view-right-click-extended-match

tree-view-has-root-line
tree-view-checkbox-next-map

tree-view-checkbox-parent-function

tree-view-checkbox-status

tree-view-checkbox-child-function tree-view-checkbox-change-callback tree-view-checkbox-initial-status

Readers

tree-view-checkbox-status

Description

The tree view pane allows the user to select between items displayed in a hierarchical list. Although it is a choice, only single selection interaction is supported. Use extended-selection-tree-view if you need other selection interaction styles.

expandp-function controls automatic expansion of nodes (items) in the tree-view. By default, initially only the items specified by the roots argument are displayed. This initial display can be altered by supplying a function expandp-function which allows further items to be displayed. If supplied, expandp-function should be a function which is called on the roots and is called recursively on the children if it returns true. When the user expands a node, expandp-function is called on each newly created child node, which is expanded if this call returns true, and so on recursively. The default value of expandp-function is nil so that there is no automatic expansion and only the root nodes are visible initially.

The default value of retain-expanded-nodes is t.

Any item which has children has a small expansion button next to it to indicate that it can be expanded. When the user clicks on this button, the children nodes (as determined by the children function) are displayed.

If *action-callback-expand-p* is true, then the activate gesture expands a collapsed node, and collapses an expanded node. This expansion and contraction of the node is additional to any supplied *action-callback*.

delete-item-callback is called when the user presses the Delete key. Two arguments are passed: the tree-view and the selected item item. Note that, apart from calling the callback, the system does nothing in response to the Delete key. In particular, if you want to remove the selected item, delete-item-callback needs to do it by changing what the children-function returns when called on the parent of item. Normally you also need to to call tree-view-update-item with in-parent = t to actually update the tree on the screen.

Note also that in extended-selection-tree-view (a subclass of tree-view), if the *interaction* was not explictly changed to :single-selection, the second argument to *delete-item-callback* is a list of the selected items (even when only one item is selected).

The *image-function* is called on an item to return an image associated with the item. It can return one of the following:

A pathname or string

This specifies the filename of a file suitable for loading with load-image. Currently this must be a bitmap file.

A symbol

The symbol must have been previously registered by means of a call to registerimage-translation. It can also one of the following symbols, which map to standard images: :std-cut, :std-copy, :std-paste, :std-undo, :std-redo, :std-delete,

:std-file-new, :std-file-open,
:std-file-save, :std-print,
:std-print-pre, :std-properties,
:std-help, :std-find and :std-replace.

On Microsoft Windows, the following symbols are also recognized. They map to view images: :view-large-icons, :view-small-icons, :view-list, :view-details, :view-sort-name, :view-sort-size, :view-sort-date, :view-sort-type, :view-parent-folder, :view-net-connect, :view-net-disconnect and :view-new-folder.

Also on Microsoft Windows, these symbols are recognized. They map to history images: :hist-back, :hist-forward, :hist-favorites, :hist-addtofavorites and :hist-viewtree.

An image object, as returned by load-image.

An image locator object

This allowing a single bitmap to be created which contains several button images side by side. See make-image-locator for more information. On Microsoft Windows, it also allows access to bitmaps stored as resources in a DLL.

An integer

This is a zero-based index into the treeview's image lists. This is generally only useful if the image list is created explicitly. See image-list for more details.

The *state-image-function* is called on an item to determine the state image: an additional optional image used to indicate the state of an item. It can return one of the objects listed above,

just as for *image-function*, or nil to indicate that there is no state image. See also *checkbox-status*, which overrides the *state-image-function*.

If *image-lists* is specified, it should be a plist containing the following keywords as keys. The corresponding values should be <code>image-list</code> objects.

:normal Specifies an image-list object that contains

the item images. The *image-function* should return a numeric index into this *image-*

list.

state Specifies an image-list object that contains

the state images. The *state-image-function* should return a numeric index into this

image-list.

If right-click-extended-match is nil, the mouse right button gesture within the tree view selects an item only when the cursor is on the item. Otherwise, this gesture also selects an item to the left or right of the cursor. The default for right-click-extended-match is t.

If has-root-line is mil, the vertical root line and expanding boxes of the root nodes are not drawn. This is useful in two cases:

- When the tree view needs to be neater. Note that the user does not have a mouse gesture to expand the root node.
 Normally the programmer would compensate for this by making some other gesture call (setf tree-view-expanded-p).
- If a children-function is not supplied, this can be used to create a pane like a list view with checkboxes (see below for details of checkboxes). This pane can be handled as if it is a typical choice, except that setting the items is done by (setf tree-view-roots) or by passing :roots to

make-instance. In a typical choice, you would do (setf collection-items) or pass:items to make-instance.

The default for has-root-line is t.

If the *checkbox-status* is non-nil then the tree view provides an automatic way of using the state images as checkboxes (except on Cocoa where check boxes are not supported). The *state-image* is defaulted to a set of images containing checkboxes and the *state-image-function* is ignored, but each *item* has a status that is a non-negative integer no greater than the number of images in *state-image-list*. The status specifies which image is displayed alongside *item*.

When *item* is expanded in the tree for the first time, the status of each child is set to *item*'s status. The status can be changed interactively by the user:

- Left mouse button on a checkbox changes its status
- Space changes the status of all selected items.

The status can also be read and set programmatically (see tree-view-item-checkbox-status).

When the status of an item changes:

- The statuses of its ancestors may change if a checkboxparent-function was supplied.
- The statuses of an items descendents may change if a checkbox-child-function was supplied.
- A callback given by *checkbox-callback-function* will be called, if this was supplied.

By default checkboxes have three statuses indicated by images: un-checked(0), grey-checked(1) and checked(2). If an item is checked or un-checked, then all its decendents have the same status. If an item is grey-checked, then its descen-

dents have various statuses. When the status of an item changes, all the descendents of that item change to the same status, and all its ancestors change to grey-checked.

For non-default status-changing behavior, specify *checkbox-next-map*. The value can be

- An array of statuses. When the user clicks on *item*'s checkbox, the status of *item* is used to index into *checkbox-next-map*, and the status at that index becomes the new status of *item*. For example, with the default checkbox-next-map, checked(0) changes to unchecked(2), grey-checked(1) changes to un-checked(2), and un-checked(2) changes to checked(0).
- A function of two arguments. The first argument is a list
 of items and the second argument is their current status
 (and if the items have various statuses, the most common
 is used). checkbox-next-map should return the new status
 to use.
- An integer: the status is increased by 1, until this integer is reached, at which point the status becomes 0 again.

When the status of an item is changed, the statuses of items above and below it in the tree may also be changed: the system recurses up and down the tree using *checkbox-parent-function* and *checkbox-child-function* respectively.

To recurse upwards, *checkbox-parent-function* is called on the parent with five arguments: the parent, the parent's status, the item, the item's status and an flag which is non-nil if all the items at the same level as the item now have the same status:

checkbox-parent-function parent parent-status item item-status
all-items-same-p => new-parent-status, recurse-up, recurse-down

If new-parent-status differs from parent-status, then the status of parent is set to new-parent-status. If recurse-up is non-nil, then the system recurses up from parent, and if recurse-down

is non-nil, the system recurses down. The default *checkbox-parent-function* returns (values *new-item-status* t nil) where *new-item-status* is *item-status* if *all-items-same-p* is non-nil and 1 otherwise.

To recurse downwards, *checkbox-child-function* is called on each child with four arguments and the results are used similarly to those of *checkbox-parent-function*:

checkbox-child-function child child-status item item-status =>
new-child-status, recurse-up, recurse-down

The default *checkbox-child-function* returns (values *parent-status* nil t).

Note: if an item has never been expanded, then it has no children. If an item has been collapsed, then it has children even though they are not currently visible.

checkbox-parent-function and *checkbox-child-function* should not modify the tree in any way.

checkbox-change-callback takes three arguments: the tree, a list of items and their new status:

checkbox-change-callback tree items new-status

This is called after the new statuses of *items* and their ancestors and descendents have been resolved.

checkbox-initial-status is used the first time that each specified item, which can be anywhere in the tree, appears. The value is a list of conses of items and their initial statuses, for example ((item1. 2) (item2. 0)). When item is displayed, its status is set from this list or, if item is not specified, from checkbox-status. Items are removed from the list when they are displayed and setting the list does not affect the checkbox status of items that have already been displayed. Note that check boxes are not supported on Cocoa.

The default value of vertical-scroll in a tree-view is t.

Notes

- Since the items of a tree view are not computed until display time, the choice initarg :selected-item has no effect. See the examples in interface-display for a way to set the selected item in a tree view.
- 2. Although tree-view is a subclass of collection, it does its own items handling and you must not access its *items* and related slots directly. In particular for tree-view do not pass:items,:items-count-function,:items-get-function or:items-map-function, and do not use the corresponding accessors.
- 3. On Microsoft Windows, the system always sets the input focus to the tree-view after its selection-callback returns. If you need this callback to set the focus elsewhere, call set-pane-focus outside the callback, like this:

```
(mp:process-send process
  (list 'capi:set-pane-focus pane))
```

See also

choice

extended-selection-tree-view tree-view-ensure-visible tree-view-expanded-p

tree-view-item-checkbox-status
tree-view-item-children-checkbox-status

tree-view-update-item

tree-view-ensure-visible

Function

Summary Ensures that an item in a tree-view is visible.

Package capi

Signature tree-view-ensure-visible tree-view item

Arguments *tree-view* A tree view.

item A displayed item of tree-view.

1 CAPI Reference Entries

Description The function tree-view-ensure-visible ensures that an

item in a tree view is visible, scrolling the tree view if neces-

sary.

Note that *item* must be an item that is displayed in *tree-view*.

See also tree-view

tree-view-expanded-p

Generic Function

Summary Gets and sets the expanded state of an item in a tree-view.

Package capi

Signature tree-view-expanded-p tree-view item

Signature (setf tree-view-expanded-p) on tree-view item

Arguments tree-view A tree-view.

item An item.

on A boolean.

Description The generic function tree-view-expanded-p is the predi-

cate for whether item is expanded in tree-view. If item is not in

tree-view, the function returns mil.

(setf tree-view-expanded-p) sets the expanded state of *item* in *tree-view* to *on*. If *item* is not in *tree-view*, the function

does nothing.

See also tree-view

tree-view-item-checkbox-status

Function

Summary Gets and sets the checkbox status of an item in a tree-view.

Package capi

Signature tree-view-item-checkbox-status tree-view item => status

Signature (setf tree-view-item-checkbox-status) status tree-view item

Arguments *tree-view* A tree view.

item An item.

status A non-negative integer.

Description The function tree-view-item-checkbox-status retrieves

the checkbox status of *item* in *tree-view*, except on Cocoa.

(setf tree-view-item-checkbox-status) sets the checkbox status of *item* in *tree-view*. The *status* must be an non-negative integer smaller than the number of images in *tree-view*'s

state-image-list.

See also tree-view

tree-view-item-children-checkbox-status

tree-view-item-children-checkbox-status

Function

Summary Gets the checkbox statuses of a tree-view item's children.

Package capi

Signature tree-view-item-children-checkbox-status tree-view item

=> result

Arguments tree-view A tree-view.

item An item.

Values result A list of conses (child . status) where each

child is a child of item and status is child's

checkbox status.

1 CAPI Reference Entries

Description The function tree-view-item-children-checkbox-sta-

tus returns item's children together with their checkbox sta-

tuses, except on Cocoa.

Note that, if item has not been expanded in tree-view, then it

has no children and result will be mil.

See also tree-view

tree-view-item-checkbox-status

tree-view-update-an-item

Generic Function

Summary Updates an item in a tree-view.

Package capi

Signature tree-view-update-an-item tree-view item in-parent

Description The generic function tree-view-update-an-item is a syn-

onym for tree-view-update-item.

Note: tree-view-update-an-item is deprecated. Please use

tree-view-update-item instead.

See also tree-view

tree-view-update-item

tree-view-update-item

Generic Function

Summary Updates an item in a tree-view.

Package capi

Signature tree-view-update-item tree-view item in-parent

Arguments tree-view A tree-view.

item An item.

in-parent A boolean.

Description The generic function tree-view-update-item updates the

item *item* in *tree-view*. This includes recomputing the text, images and children of *item*. This is useful when the data in

tree-view changes, but the entire tree does not need

recomputing.

When *in-parent* is non-nil, tree-view-update-item updates the children of the parent of *item*. This is useful when *item* is actually removed from *tree-view*, causing the children of its

parent to be re-positioned.

See also tree-view

undefine-menu Macro

Package capi

Signature undefine-menu function-name &rest args

Description This function undefines a menu created with define-menu.

See also define-menu

menu

unhighlight-pinboard-object

Generic Function

Summary Removes the highlighting from a pinboard-object.

Package capi

Signature unhighlight-pinboard-object pinboard object &key redisplay

1 CAPI Reference Entries

Description This removes the highlighting from a pinboard object if nec-

essary, and then if *redisplay* is non-nil it redisplays it. The

default value of redisplay is t.

To highlight a pinboard object use highlight-pinboard-

object.

See also highlight-pinboard-object

pinboard-object

uninstall-postscript-printer

Function

Summary Uninstalls a Postscript printer definition.

Package capi

Signature uninstall-postscript-printer name &key if-does-not-exist

deletep

Arguments *name* A string.

if-does-not-exist One of nil or :error.

deletep A boolean.

Description Uninstalls a PostScript printer definition for the given device

name.

This applies only on GTK+ and Motif.

if-does-not-exist controls what happens if the named printer

does not exist. The default value is :error.

deletep, if true, causes the printer to be removed for subsequent sessions as well as the current session, by deleting the

file on the disk. The default value of *deletep* is mil.

See also install-postscript-printer

unmap-typeout Function

Package capi

Signature unmap-typeout collector-pane

Description This switches the *collector-pane* out from its switchable layout,

and brings back the pane that was there before map-typeout

was called.

See also map-typeout

with-random-typeout

collector-pane

update-all-interface-titles

Function

Summary Updates interface window titles.

Package capi

Signature update-all-interface-titles

Description The function update-all-interface-titles can be used to

update all the interface window titles when needed.

This is useful when interface-extend-title may return a

new, different, value.

update-all-interface-titles Calls update-screen-

interface-titles on all the screens.

See also interface-extend-title

update-screen-interface-titles

update-interface-title

Generic Function

Summary Updates the title of an interface window.

Package capi

Signature update-interface-title interface

Arguments inteface A CAPI interface.

Description The generic function update-interface-title updates the

title of interface interface. This is useful when interface-

extend-title may return a new, different, value.

You can specialize update-interface-title if needed.

To update all the interface titles, use update-all-interface-titles or update-screen-interface-titles.

See also interface-extend-title

update-all-interface-titles update-screen-interface-titles

update-pinboard-object

Function

Package capi

Signature update-pinboard-object ${\it object}$

Description This function checks the *object*'s constraints, and adjusts the

object's size as necessary. It then forces the layout to redisplay the *object* at its new size. Finally, it returns t if a resize was

necessary.

See also redraw-pinboard-object

pinboard-object

update-screen-interface-titles

Function

Summary Updates interface window titles.

Package capi

Signature update-screen-interface-titles screen

Arguments screen A CAPI screen.

Description The function update-screen-interface-titles can be

used to update the titles of all the interface windows on the

screen screen when needed.

This is useful when interface-extend-title may return a

new, different, value.

update-screen-interface-titles calls update-inter-

face-title on all the relevant interfaces.

See also interface-extend-title

update-interface-title

update-screen-interfaces-hooks

Variable

Summary A list of functions that are called when a CAPI interface is

created or destroyed.

Package capi

Description Each function in the list

 $\verb"*update-screen-interfaces-hooks*" is called when an$

interface interface is created or destroyed.

Each function takes two arguments: the screen and interface.

You should not remove system functions from this variable so take care if setting its value. Only add or delete your own functions.

update-toolbar

Function

Summary Updates a toolbar object.

Package capi

Signature update-toolbar self

Description The update-toolbar function updates the toolbar object self.

It computes the enabled function of *self* and the enabled functions of any toolbar components or toolbar buttons contained in it. Each toolbar object is enabled if the enabled function

returns t, and is disabled if it returns mil.

See also toolbar

toolbar-button toolbar-component

virtual-screen-geometry

Function

Summary Returns, as multiple values, a screen rectangle covering the

full area of all the monitors associated with a screen.

Package capi

Signature virtual-screen-geometry screen => x, y, width, height

Arguments *screen* A CAPI screen.

Values x An integer.

y An integer.

width A positive integer.

height A positive integer.

Description The function virtual-screen-geometry returns the "vir-

tual" geometry of the screen screen, which is a screen rectan-

gle covering the full area of all the monitors that are

associated with screen.

The screen rectangle is at coordinates *x* and *y* as offsets from the top-left of the primary screen, with dimensions *width* and

height.

See also pane-screen-internal-geometry

screen-internal-geometries screen-monitor-geometries

with-atomic-redisplay

Macro

Summary The with-atomic-redisplay macro delays the updating of

specified panes until all state changes have been performed.

Package capi

Signature with-atomic-redisplay (&rest panes) &body body

Description Most CAPI pane slot writers update the visual appearance of

the pane at the point that their state changes, but it is sometimes necessary to cause all updates to the pane to be left

until after they are all completed. The macro

with-atomic-redisplay defers all visible changes to the state of each pane in *panes* until the end of the scope of the

macro.

Notes with-atomic-redisplay does not cause Graphics Ports

drawing operations to the panes to be deferred.

See also display

simple-pane

with-busy-interface

Macro

Summary Displays an alternate cursor during the execution of some

code, on platforms other than Cocoa.

Package capi

Signature with-busy-interface (pane &key cursor delay) &body body

Description The macro with-busy-interface switches the cursor of the

interface containing *pane* to be the busy cursor, evaluates *body*, and then restores the cursor. This is useful when a piece of code may take significant time to run, and visual feedback

should be provided.

cursor specifies the cursor to use while body is running. The default value is :busy. For other allowed values, see simple-

pane.

delay specifies a time in seconds before the cursor is switched, so if body runs in less than delay seconds, then the cursor is not switched at all. This is usually more useful behavior than switching the cursor immediately. The default value of delay

is 0.5.

with-busy-interface must be called in the process of the

interface containing pane.

with-busy-interface has no effect on Cocoa.

See also simple-pane

with-dialog-results

Macro

Summary Displays a dialog and executes a body when the dialog is dis-

missed.

Package capi

Signature with-dialog-results (&rest results) dialog-form &body body

=> :continuation, nil

Arguments results Variables.

dialog-form A function call form.

body Forms.

Description

The macro with-dialog-results is designed to evaluate the *dialog-form* in a special way to allow dialogs on Cocoa to use window-modal sheets. It is not needed unless you want to make code that is portable to Cocoa. The *dialog-form* should be a function call form that displays a dialog.

The overall effect is that the *body* forms are evaluated with the *results* variables bound to the values returned by the *dialog-form* when the dialog is dismissed.

The dynamic environment in which the body is evaluated varies between platforms:

- On Microsoft Windows, GTK+ and Motif, the withdialog-results macro waits until the dialog has been dismissed and then evaluates the body forms.
- On Cocoa, the dialog-form creates a sheet attached to the
 active window and the with-dialog-results macro
 returns immediately. The body forms are evaluated when
 the user dismisses the sheet.

The *dialog-form* must be a cons with one of the following two formats:

• (function-name . arguments)

(apply function-name . arguments)

The function-name is called with all the given arguments, plus an additional pair of arguments, :continuation and a continuation function created from body. In the first format, the additional arguments are placed after all the given arguments. In the second format, the additional arguments are placed just before the last of the given arguments (i.e. before the list of remaining argument to apply).

The continuation function binds the *results* variables to its arguments and evaluates the *body* forms. If there are more arguments than *results* variables, the extra arguments are discarded.

This macro is designed for use with *function-name*s such as popup-confirmer or prompt-for-string, which take a :continuation keyword. You can define your own such functions provided that they call one of the CAPI functions, passing the received *continuation* argument.

Examples

On Microsoft Windows, GTK+ and Motif, this displays a dialog, calls record-label-in-database when the user clicks OK and then returns. On Cocoa, this creates a sheet and returns; record-label-in-database will be called when the user clicks OK.

Here is an example with skeleton code for using with-dialog-results. Note that the dialog function (choosefile below) that is called by with-dialog-results must take a *continuation* keyword argument and pass it to a CAPI prompting function. Also note that the call to the CAPI prompting function must be the last form in the dialog func-

tion. Forms after the CAPI prompting function will be executed at an indeterminate time, and their values will not be used in the body of with-dialog-results

```
(defun choose-file (&key continuation)
                (print 'in-choose-file)
                (capi:prompt-for-file "Choose File"
                                       :pathname "~/Desktop/"
                                       :continuation continuation))
              (defun open-file (rep)
                (format t "~%Opening ~a~%" rep))
              (defun my-callback ()
                (print 'doing-something-before)
                (capi:with-dialog-results (res ok-p)
                    (choose-file)
                  (print 'after-choose-file)
                  (if ok-p
                      (open-file res)
                    (print 'cancelled))))
              (defun prompt-for-file-working ()
                (capi:contain
                 (make-instance
                  'capi:push-button
                  :text "Click Here"
                  :callback-type :none
                  :callback 'my-callback)))
              (prompt-for-file-working)
See also
             display-dialog
             popup-confirmer
```

with-document-pages

Macro

Summary Executes a body of code repeatedly with a variable bound to

the number of the page to be printed each iteration.

Package capi

Signature with-document-pages page-var first-page last-page abody body

Description The with-document-pages evaluates body repeatedly, with

page-var bound to the number of the page to print on each iteration. It is used to by applications providing Page on

Demand printing.

The *first-page* and *last-page* arguments are evaluated to yield the page numbers of the first and last pages in the document.

with-document-pages takes care of *first-page* and *last-page* when the user sets them in print-dialog, by evaluating *body* for the pages that are in the intersection of what user chose and the other arguments.

See also print-dialog

with-page

with-print-job

with-external-metafile

Macro

Summary Creates a metafile on disk using Graphics Ports operations.

Package capi

Signature with-external-metafile (var &key pane bounds format

pathname drawing-mode) &body body => nil

Arguments var A variable.

pane A graphics port, or nil.

bounds A list of four integers. Can also be nil on

Microsoft Windows.

format One of the keywords : enhanced,

:enhanced-plus, :enhanced-gdi and

:windows.

pathname A pathname or string.

drawing-mode One of the keywords:compatible and

:quality.

body Code containing Graphic Ports operations

that draw to var.

Description

The macro with-external-metafile creates a metafile at the location given by *pathname* containing records corresponding to the Graphics Ports operations in *body* that draw to *var*.

On Microsoft Windows the metafile is a device-independent format for storing pictures. For more information about metafiles, see the Microsoft documentation.

On Cocoa and GTK+ the metafile format is PDF.

If pane is nil, the macro binds var to a graphics port object representing the metafile. If pane is non-nil then it must be an instance of output-pane or a subclass. In this case var is bound to pane, and pane is modified within the dynamic extent of with-external-metafile so all drawing operations draw to the metafile instead of pane. This can be useful when reusing existing redisplay code that is written expecting an output-pane. The default value of pane is nil.

If *bounds* is nil the metafile size will be computed from the drawing done within the body. This value is not allowed on Cocoa.

If *bounds* is non-nil (required on Cocoa), it should be a list of integers specifying the coordinate rectangle (*x y width height*) that the metafile contains.

format is used only on Microsoft Windows. It can be one of:

: enhanced Generate an Enhanced-metafile file containing "dual drawing" both in GDI+ and GDI.

:enhanced-plus

Generate an Enhanced-metafile file containing drawing only in GDI+.

: enhanced-gdi Generate an Enhanced-metafile file containing drawing only in GDI.

:windows Generate a Windows-metafile.

The default value of format is : enhanced.

When drawing-mode is :compatible (rather than the default value :quality) :enhanced and :enhanced-plus behave like :enhanced-gdi.

Note: GDI+ gives the best quality, so normally that is what you would want. However some programs may be able to display only GDI (and not GDI+), which is why the default is dual drawing. This however generates a larger file and is presumably slightly slower, so if you are sure that the file will be used only by programs that can draw GDI+ emf files (sometimes called EMF+), you can use *format*:enhanced-plus.

On Cocoa the metafile format is always PDF as a single page, and the *format* argument is ignored.

pathname specifies the filename of the metafile. If its pathname-type is nil, then the file extension "EMF" is used for an Enhanced-metafile, or "WMF" for a Windows-metafile.

drawing-mode should be either :compatible which causes drawing to be the same as in LispWorks 6.0, or :quality which causes all the drawing to be transformed properly, and allows control over anti-aliasing on Microsoft Windows and GTK+. The default value of drawing-mode is :quality.

For more information about *drawing-mode*, see "Drawing mode and anti-aliasing" in the *CAPI User Guide*.

Notes with-external-metafile is not implemented on X11/Motif.

See also draw-metafile

with-internal-metafile

with-geometry Macro

Summary The with-geometry macro is used for defining layouts and

for creating new pinboard-object subclasses, by binding a

set of variables to a pane's geometry.

Package capi

Signature with-geometry pane &body body

Description The main uses of the macro with-geometry are defining layouts and for creating new pinboard-object subclasses.

with-geometry binds the following variables across the forms in *body* to slots in the pane's geometry in much the same way as the Common Lisp macro with-slots. Except the special cases which are mentioned below, these variables are read-only and should not be set.

Four variables define the geometry of the pane. If you define define your own calculate-layout method, it can set these variables:

%x% An integer specifying the x position of the

pane in pixels relative to its parent.

%y% An integer specifying the y position of the

pane in pixels relative to its parent.

%width% An integer specifying the width in pixels of

the pane.

%height% An integer specifying the height in pixels of

the pane.

Four variables specify constraints on the pane. If you define your own calculate-constraints method, it can set these variables:

%min-width% A real number specifying the minimum

width of the pane.

%min-height% A real number specifying the minimum height of the pane.

%max-width% A real number specifying the maximum
width of the pane.

%max-height% A real number specifying the maximum height of the pane.

The following variables are also bound but apply only to classes with internal scrolling, such as editor-pane. They can be retrieved by get-horizontal-scroll-parameters and get-vertical-scroll-parameters. They can be set by set-horizontal-scroll-parameters and set-vertical-scroll-parameters.

%scroll-width%

The extent of the horizontal scroll range.

%scroll-height%

The extent of the vertical scroll range.

%scroll-horizontal-page-size%

The horizontal scroll page size.

%scroll-horizontal-slug-size%

The width of the scroll bar slug.

%scroll-horizontal-step-size%

The horizontal scroll step size.

%scroll-start-x%

The start of the horizontal scroll range.

%scroll-start-y%

The start of the vertical scroll range.

%scroll-vertical-page-size%

The vertical scroll page size.

%scroll-vertical-slug-size%

The height of the scroll bar slug.

%scroll-vertical-step-size%

The vertical scroll step size.

%scroll-x% x coordinate of the current scroll position.

%scroll-y% y coordinate of the current scroll position

The following two variables access the object for which the representation is:

%object% The object whose geometry this is.

%child% The same as %object% (kept for compatibil-

ity with LispWorks 3.1).

See also calculate-constraints

calculate-layout

convert-relative-position

element

get-horizontal-scroll-parameters
get-vertical-scroll-parameters

scroll

set-horizontal-scroll-parameters
set-vertical-scroll-parameters

with-internal-metafile

Macro

Summary Creates a metafile in memory using Graphics Ports

operations.

Package capi

Signature with-internal-metafile (var &key pane bounds format

drawing-mode) &body body => metafile

Arguments var A variable.

pane A graphics port, or nil.

bounds A list of four integers. Can also be nil on

Microsoft Windows.

format One of the keywords: enhanced,

:enhanced-plus and :enhanced-gdi.

drawing-mode One of the keywords:compatible and

:quality.

body Lisp code.

Values *metafile* A metafile.

Description

The macrowith-internal-metafile creates a metafile containing records corresponding to the Graphics Ports operations in *body* that draw to *var*.

with-internal-metafile behaves like with-external-metafile except that an object representing the metafile is returned, and no file is created on disk.

var, pane, bounds, format, drawing-mode and body are interpreted as for with-external-metafile except that format cannot have the value :windows.

Note: GDI+ gives the best quality, so normally that what you want. But you cannot put a GDI+ only metafile on the clipboard, which is why the default is to make a "dual" metafile containing both GDI and GDI+ drawing. If are not going to put the metafile on the clipboard (by calling set-clipboard with format :metafile) you can use format :enhanced-plus which is slightly faster and uses less memory.

metafile must be freed after use, by calling free-metafile.

Notes

- with-internal-metafile is supported on GTK+ only where Cairo is supported (GTK+ version 2.8 and later).
- **2.** On GTK+, the internal metafile is slow to resize, so it is probably not useful when it is frequently resized (that is, drawn with different width or height).

with-internal-metafile is not implemented on X11/Motif.

Examples examples/capi/graphics/metafile.lisp

examples/capi/graphics/metafile-rotation.lisp

See also draw-metafile

free-metafile

with-external-metafile

with-output-to-printer

Macro

Summary Binds a stream variable and prints its output.

Package capi

Signature with-output-to-printer (stream &key printer

tab-spacing interactive jobname)

&body body => result

Arguments stream A variable.

printer A printer or mil.

tab-spacing An integer.
interactive A boolean.

jobname A string.

Values result The result of evaluating body.

 ${\color{blue} \textbf{Description}} \qquad \textbf{The macro with-output-to-printer binds the variable}$

stream to a stream object, and prints everything is that is writ-

ten to it in the code of body.

If interactive is then print-dialog is called to select the printer to use. If interactive is nil then printer is used unless it is nil in which case the current-printer is used. The default value of interactive is t and the default value of printer is nil.

The values of *jobname* and *tab-spacing* are passed to printtext, which is used to actually do the printing. The default value of *tab-spacing* is 8 and the default value of *jobname* is "Text".

See also current-printer

print-dialog print-text

with-page Macro

Summary Binds a variable to either t or nil, and executes a body of

code to print a page only if the variable is t.

Package capi

Signature with-page (printp) &body body

Description The with-page macro binds *printp* to t if a page is to be

printed, or \mathtt{nil} if it is to be skipped. The *body* is executed once, and is expected to draw the document only if *printp* is

t.

Each call to with-page contributes a new page to the docu-

ment.

Note: with-page does not work on Cocoa.

See also with-document-pages

with-page-transform

with-page-transform

Macro

Summary Defines a rectangular region within the coordinate space of

an output pane or printer port.

Package capi

Signature with-page-transform (x y width height) &body body

Description The with-page-transform macro evaluates x, y, width and

height to define a rectangular region within the coordinate space of an output pane or printer port. Within body the region is mapped onto the printable area of the page. If the specified rectangle does not have the same aspect ratio as the printable area of the page, then non-isotropic scaling will

occur.

Any number of calls to with-page-transform can occur during the printing of a page; for example, it is sometimes convenient to use a different page transform from that used to print the main body of the page when printing headers

and footers.

See also get-printer-metrics

with-print-job Macro

Summary Creates a print job that prints to the specified printer.

Package capi

Signature with-print-job (var &key pane jobname printer drawing-mode)

&body body

Description

The with-print-job macro creates a print job which prints to *printer*. If *printer* is not specified, the default printer is used. The macro binds *var* to a graphics port object, and printing is performed by using graphics port operations to draw the object.

If pane is specified it must be an instance of output-pane or a subclass. In this case var is bound to pane, and pane is modified within the dynamic extent of the with-print-job so all drawing operations draw to the printer instead of pane. This can be useful when implementing printing by modifying existing redisplay code that is written expecting an output-pane.

jobname is the name of the print job. The default value is nil, meaning that the name "Document" is used.

drawing-mode should be either :compatible which causes drawing to be the same as in LispWorks 6.0, or :quality which causes all the drawing to be transformed properly, and allows control over anti-aliasing on Microsoft Windows and GTK+. The default value of drawing-mode is :quality.

For more information about *drawing-mode*, see "Drawing mode and anti-aliasing" in the *CAPI User Guide*.

See also

printer-port-handle
printer-port-supports-p
set-printer-options
with-document-pages
with-page
with-page-transform

with-random-typeout

Macro

Summary Binds a stream variable to a collector pane.

Package capi

Signature with-random-typeout (stream-variable pane) &body body

Description The macro with-random-typeout binds the variable stream-

variable to a collector pane stream associated with *pane* for the scope of the macro. The collector pane is automatically mapped and unmapped around the body. If the body exits normally, the typeout is not unmapped until the space bar is

pressed or the mouse is clicked.

See also map-typeout

unmap-typeout collector-pane

wrap-text Function

Summary Wraps text for a given character width.

Package capi

Signature wrap-text text width &key start end => strings

Arguments *text* A string.

width A positive integer.

start, end Bounding index designators of text.

Values strings A list of strings.

Description The function wrap-text takes a string text and returns a list

of strings, each of which is no longer than *width*. Together the strings in *strings* contain all the non-whitespace characters of *text* between *start* and *end* and are suitable for displaying this

text on multiple lines of length width.

See also wrap-text-for-pane

wrap-text-for-pane

Function

Summary Wraps text for a given pane.

Package capi

Signature wrap-text-for-pane pane text &key external-width visible-width

font start end => strings

Arguments *text* A string.

pane A displayed CAPI pane.

external-width An integer or nil.

visible-width An integer or nil.

font A font object.

start An integer.

end An integer or mil.

Values strings A list of strings.

Description The function wrap-text-for-pane takes a string text and

returns a list of strings. Together the strings in *strings* contain all the non-whitespace characters of *text* and are suitable for displaying this text on *pane*. That is, each string has a display width no greater than the width of *pane* when drawn using the font of *pane*. The arguments *start* and *end* are used as bounding index designators for *text* and characters outside

these bounds are ignored.

If visible-width is non-nil then text is wrapped to that width. Otherwise, if external-width is non-nil then text is wrapped as if the pane had that external width (that is, taking account of any borders in the pane). If both visible-width and external-width are nil, then the text is wrapped to the current visible width of the pane. The default value of both visible-width and external-width is nil.

The *font* is used to perform the wrapping calculations. If it is nil (the default), then the graphics-state-font is used for panes such as output-pane that have a graphics-state and the simple-pane-font is used for other panes.

See also wrap-text

x-y-adjustable-layout

Class

Summary The class x-y-adjustable-layout provides functionality

for positioning panes in a space larger than themselves (for example, it is used to choose whether to center them, or left

justify them).

Package capi

Superclasses layout

Subclasses simple-layout

grid-layout

Initargs x-adjust The adjust value for the x direction.

:y-adjust The adjust value for the *y* direction.

Accessors layout-x-adjust

layout-y-adjust

Description The values *x-adjust* and *y-adjust* of the slots are used by lay-

outs to decide what to do when a pane is smaller than the space in which it is being laid out. Typically the values will be a keyword or a list of the form (keyword n) where n is an integer. These values of adjust are interpreted as by pane-

adjusted-position.

:top is the default for y-adjust and :left is the default for x-

adjust.

Example Note: column-layout is a subclass of x-y-adjustablelayout. (setq column (capi:contain (make-instance 'capi:column-layout :description (list (make-instance 'capi:push-button :text "Ok") (make-instance 'capi:list-panel :items '(1 2 3 4 5)))))) (capi:apply-in-pane-process column #'(setf capi:layout-x-adjust) :right column) (capi:apply-in-pane-process column #'(setf capi:layout-x-adjust) :center column)

See also

pane-adjusted-position

GP Reference Entries

The following chapter provides reference entries for the symbols exported from the <code>graphics-ports</code> package. You can use these to draw graphics in CAPI output panes, which are a kind of graphics port. See the Graphics Ports chapter in the *CAPI User Guide* for more information on graphics ports and their associated types.

2pi Constant

Summary (* 2 pi) as a double-float.

Package graphics-ports

Description The constant 2pi is the result of (* 2 cl:pi). It is a cl:dou-

ble-float.

See also fpi

pi-by-2

analyze-external-image

Function

Summary Gets the properties of DIB data in an external image.

Package graphics-ports

Signature analyze-external-image external-image => width height color-

table number

Arguments external-image An external-image.

Values width An integer.

height An integer.

color-table A color table.

number An integer.

Description The analyze-external-image function returns the width,

height, color-table, and number of important colors for the

external image external-image.

The image data in external-image must be in Device Indepen-

dent Bitmap (DIB) format.

apply-rotation Function

Summary Modifies a transform such that a rotation of a given number

of radians is performed on any points multiplied by the

transform.

Package graphics-ports

Signature apply-rotation transform theta => transform

Arguments *transform* A transform.

theta A real number.

Description The function apply-rotation modifies transform such that a

rotation of theta radians is performed on any points

multiplied by the transform. Any operations already contained in the transform occur before the new rotation.

The rotation is around the point (0,0).

If *theta* is positive, then the rotation is clockwise.

apply-rotation returns the transform.

Examples examples/capi/graphics/metafile-rotation.lisp

See also apply-rotation-around-point

apply-scale

apply-translation

apply-rotation-around-point

Function

Summary Modifies a transform such that a specified rotation around a

specified point is performed on any points multiplied by the

transform.

Package graphics-ports

Signature apply-rotation-around-point transform theta $x \ y \Rightarrow transform$

Arguments transform A transform.

theta A real number.

x A real number.

y A real number.

Description The function apply-rotation-around-point modifies

transform such that a clockwise rotation of theta radians around the point (x,y) is performed on any points multiplied by the transform. Any operations already contained in the

transform occur before the new rotation.

apply-rotation-around-point returns the transform.

Examples examples/capi/graphics/rotation-around-point.lisp

See also apply-rotation

apply-scale Function

Summary Modifies a transform such that a scaling occurs on any points

multiplied by the transform.

Package graphics-ports

Signature apply-scale transform sx sy => transform

Arguments transform A transform.

sx A real number.

sy A real number.

Description The function apply-scale modifies transform such that a

scaling of *sx* in *x* and *sy* in *y* is performed on any points multiplied by the transform. Any operations already contained in

the transform occur before the new scaling.

apply-scale returns the transform.

Examples examples/capi/graphics/metafile-rotation.lisp

See also apply-rotation

apply-rotation-around-point

apply-translation

apply-translation

Function

Summary Modifies a transform such that a translation is performed on

any points multiplied by the transform.

Package graphics-ports

Signature apply-translation transform dx dy = transform

Arguments *transform* A transform.

dx A real number.

dy A real number.

Description The function apply-translation modifies transform such

that a translation of (dx dy) is performed on any points multiplied by the transform. Any operations already contained in

the transform occur before the new translation.

apply-translation returns the transform.

Examples examples/capi/graphics/metafile-rotation.lisp

See also apply-rotation

apply-rotation-around-point

apply-scale

augment-font-description

Function

Summary Returns a font description combining the attributes of a given

font description with a set of font attributes.

2 GP Reference Entries

Package graphics-ports

Signature augment-font-description fdesc &rest font-attribute* => return

Arguments *fdesc* A font description.

font-attribute A font attribute.

Values return A font description.

Description The augment-font-description function returns a font

description that contains all the attributes of *fdesc* combined with the extra *font-attributes*. The :stock attribute is handled specially: it is omitted from *return*, unless it is the only

attribute specified.

If an attribute appears in both *fdesc* and a *font-attribute*, the value in the *font-attribute* is used. The contents of *fdesc* are not

modified.

See also make-font-description

clear-external-image-conversions

Function

Summary Clears external image conversions for a port.

Package graphics-ports

Signature clear-external-image-conversions external-image gp-or-null & key free-image all errorp

Arguments external-image An external image.

gp-or-null A graphics port or nil.

free-image A boolean.all A boolean.errorp A boolean.

Description

The clear-external-image-conversions function clears the external image conversions for a port. If *gp-or-null* is nil all conversions are cleared using the image-color-users. If *all* is non-nil all conversions for all ports are cleared using *gp-or-null*. Conversions are also freed if *free-image* is non-nil. By default, *free-image* is t, *all* is (null *gp-or-null*), and *errorp* is t.

clear-graphics-port

Function

Summary Draws a filled rectangle covering the entire port in the port's

background color.

Package graphics-ports

Signature clear-graphics-port port

Arguments *port* A graphics port.

Description The clear-graphics-port function draws a filled rectangle

covering the entire port in the port's *background*. All other

graphics state parameters are ignored.

clear-graphics-port-state

Function

Summary Sets the graphics state of a port back to its default values.

Package graphics-ports

Signature clear-graphics-port-state port

Arguments *port* A graphics port.

Description The clear-graphics-port-state function sets the graphics

state of *port* back to its default values, which are the ones it

possessed immediately after creation.

See also graphics-state

clear-rectangle

Function

Summary Draws a rectangle in the port's background color.

clear-rectangle is deprecated.

Package graphics-ports

Signature clear-rectangle port x y width height

Arguments *port* A graphics port.

x A real number.
 y A real number.
 width A real number.
 height A real number.

Description

The deprecated function clear-rectangle draws the rectangle specified by *x*, *y*, *width*, and *height* in *port*'s background color. All other graphics-state parameters are ignored.

clear-rectangle is deprecated because it ignores the graphics state args, which means it does not work properly with other drawing functions. In particular, it does not work properly in the *display-callback* of output-pane.

Use instead:

compositing-mode is needed only when the color has alpha.

foreground is needed only if it is different from the foreground in the graphics state.

Note that draw-rectangle does take into account the transformation in the graphics-state.

See also draw-rectangle

compress-external-image

Function

Summary Compresses DIB data in an external image.

Package graphics-ports

Signature compress-external-image external-image => result

Arguments external-image An external-image.

Values result The difference in bytes between size of the

original image and the size of the com-

pressed version.

Description The compress-external-image function converts the exter-

nal-image data into compressed DIB format.

The image data in external-image must be in Device Indepen-

dent Bitmap (DIB) format.

compute-char-extents

Function

Summary Returns the x coordinates of the end of each of the characters

in a string if the string was printed to a graphics port.

Package graphics-ports

Signature compute-char-extents port string &optional font => extents

2 GP Reference Entries

Arguments *port* A CAPI pane.

string A string.

font A font.

Values *extents* An array of integers.

Description Returns the *extents* of the characters in *string* in the font asso-

ciated with *port*, or the *font* given. The extents are an array, one element per character, which gives the ending *x* coordi-

nate of that character if the string was drawn to port.

Note: To compute the extents of the entire string for a given port or font, use port-string-width or get-string-

extent.

See also get-string-extent

port-string-width

convert-external-image

Function

Summary Returns an image derived from an external image format.

Package graphics-ports

Signature convert-external-image gp external-image

&key cache force-new => image

Arguments *gp* A CAPI pane.

external-image An external image.

cache A boolean.
force-new A boolean.

Values image An image.

Description

The convert-external-image function returns an image derived from *external-image*. The image is ready for drawing to the given graphics port.

If *cache* is non-nil image conversions are cached in the *exter-nal-image*. The default value of *cache* is nil.

If *force-new* is non-nil a new image is always created, and put in the cache. The default value of *force-new* is nil.

convert-to-font-description

Function

Summary Converts a font-spec to a font description.

Package graphics-ports

Signature convert-to-font-description port font-spec => fdesc

Arguments *port* A graphics port

font-spec A font description object, font or symbol

Values *fdesc* A font-description

Description The function convert-to-font-description converts font-

spec to a font description object fdesc for the graphics port port. If font-spec is a font, then its description is returned. If font-spec is a font description object, then it is returned. If font-spec is a symbol naming a font alias, then convert-to-font-description converts this alias to a font and returns its font description. Other platform-specific values of font-

spec are also accepted.

See also font-description

make-font-description

copy-area Function

Summary Copies a rectangular area from one port to another.

Package graphics-ports

Signature copy-area to-port from-port to-x to-y width height from-x from-y

&rest args

Arguments *to-port* A graphics port.

from-port A graphics port.

to-x A real number.

to-y A real number.

width A real number.

height A real number.

from-x A real number.

from-y A real number.

args graphics-state parameters passed as key-

word arguments.

Description The function copy-area copies a rectangular area from one

port to another, taking account of transformations.

In drawing-mode: compatible (old drawing mode), copy-

area does exactly the same as copy-pixels.

In drawing-mode: quality (the default) it copies a rectangular area from one port to another. The transform, mask, mask-transform, compositing-mode and shape-mode of to-port's graphics-state are used. The to-port and from-port need not be the same depth. They can be the same object. The from-x and from-y values are interpreted as pixel positions in the window coordinates of from-port, that is, they are not transformed by from-port's transform.

Notes

The main difference between copy-area and copy-pixels in *drawing-mode*: quality is when copying from a displayed window.

copy-area always copies using the right transformation of the target, but it means that it may copy from an obscured part of the window and hence copy the wrong thing. copypixels generates an exposure event on the target port instead of copying obscure areas, but to do that it has to ignore the transformation.

Examples examples/capi/graphics/compositing-mode.lisp

See also copy-pixels

graphics-state

copy-external-image

Function

Summary Returns a copy of an external image.

Package graphics-ports

Signature copy-external-image external-image

&key new-color-table => new-external-image

Arguments external-image An external image.

new-color-table A color table.

Values new-external-image

An external image.

Description The copy-external-image function returns a copy of the

external-image, optionally supplying a *new-color-table*. An error is signalled if this is a different size from the existing

color-table.

copy-pixels Function

Summary Copies a rectangular area from one port to another.

Package graphics-ports

Signature copy-pixels to-port from-port to-x to-y width height

from-x from-y &rest args

Arguments *to-port* A graphics port.

from-port A graphics port.

to-x A real number.

to-y A real number.

width A real number.

height A real number.

from-x A real number.

from-y A real number.

args graphics-state parameters passed as key-

word arguments.

Description The copy-pixels function copies a rectangular area from

one port to another. The transform, mask, mask-transform, compositing-mode and shape-mode from to-port's graphics-state

are used.

The (to-x to-y) is transformed according to to-port's transform. When to-port's drawing-mode is :quality the target is generally fully transformed, except that when it copies from a visible window it may generate expose events when copying from an obscured part, and in drawing-mode :quality it ignores the transformation in this case.

If to-port's drawing-mode is :compatible then the image is not scaled or rotated. For more information about drawing-mode, see "Drawing mode and anti-aliasing" in the CAPI User Guide.

The *to-port* and *from-port* need not be the same depth and can be the same object. The *from-x* and *from-y* values are interpreted as pixel positions in the window coordinates of *from-port*, that is, they are not transformed by *from-port*'s transform.

Notes

copy-pixels can be used to draw to an output-pane inside the *display-callback* of that pane, but it cannot be used to copy from the output-pane inside its *display-callback* (the result of such an operation is not defined).

See also

copy-area
output-pane

copy-transform

Function (inline)

Summary Returns a copy of a transform.

Package graphics-ports

Signature copy-transform transform => result

Arguments *transform* A transform.

Values result A transform.

Description The copy-transform function returns a copy of transform.

create-pixmap-port

Function

Summary Creates a pixmap port and its window system representation.

Package graphics-ports

Signature

create-pixmap-port pane width height & key background collect

relative clear drawing-mode => pixmap-port

Arguments

pane A graphics port for a window.

width An integer.height An integer.

background A color designator.

collect A boolean.
relative A boolean.

clear A list or t.

drawing-mode One of the keywords:compatible and

:quality.

Values

pixmap-port

A pixmap graphics port.

Description

The create-pixmap-port function creates a pixmap-port and its window system representation. The *pane* argument specifies the color-user, used for color conversions, and its representation may also be used by the library to match the pixmap port properties. The value of *background* is used to initialize the graphics-state-background.

If *clear* is t, the pixmap is cleared to its background color, otherwise the initial pixel values will be non-deterministic. If *clear* is a list of the form (*x y width height*), only that part of the pixmap is cleared initially. The default value is nil.

If *relative* is non-nil, the pixmap graphics port collects pixel coordinates corresponding to the left, top, right, and bottom extremes of the drawing operations taking place within the body forms, and if these extend beyond the edges of the pixmap (into negative coordinates for example) the entire drawing is offset by an amount which ensures it remains within the port. It is as if the port moves its relative origin in

order to accommodate the drawing. If the drawing size is greater than the screen size, then some of it is lost. The default value is nil.

If *collect* is non-nil, this causes the drawing extremes to be collected but without having the pixmap shift to accommodate the drawing, as *relative* does. The extreme values can be read using the get-bounds function, and make-image-fromport.

See also with-pixmap-graphics-port

default-image-translation-table

Variable

Summary The default image translation table.

Package graphics-ports

Description The *default-image-translation-table* variable con-

tains the default image translation table. It is used if no image translation table is specified in calls to image translation table

functions.

See also load-image

define-font-alias Function

Summary Defines an alias for a font.

Package graphics-ports

Signature define-font-alias keyword font

Arguments *keyword* A keyword.

font A font.

2 GP Reference Entries

Description The function define-font-alias defines keyword as an alias

for font.

destroy-pixmap-port

Function

Summary Destroys a pixmap port, thereby freeing any window system

resources it used.

Package graphics-ports

Signature destroy-pixmap-port pixmap-port

Arguments *pixmap-port* A pixmap port.

Description The destroy-pixmap-port function destroys a pixmap-port,

freeing any window system resources.

dither-color-spec

Function

Summary Returns t if the color specification for a given pixel should

result in a pixel that is on in a 1 bit dithered bitmap.

Package graphics-ports

Signature dither-color-spec y x

Arguments *rgb-color-spec* An RGB specification.

y An integer.

x An integer.

Values result A boolean.

Description The dither-color-spec returns t if rgb-color-spec should

result in a pixel that is on in a 1-bit dithered bitmap. The cur-

rent set of dithers is used in the decision.

Notes Dithers do not affect drawing or the anti-aliasing that occurs

when drawing in Cocoa.

See also initialize-dithers

make-dither
with-dither

draw-arc Function

Summary Draws an arc.

Package graphics-ports

Signature draw-arc port x y width height start-angle sweep-angle &rest

args &key filled

Arguments *port* A graphics port.

x A real number.

y A real number.

width A real number.

height A real number.

start-angle A real number.

sweep-angle A real number.

args graphics-state parameters passed as key-

word arguments.

filled A boolean.

Description

The draw-arc function draws an arc contained in the rectangle from (x y) to (x+width y+height) from start-angle to start-angle+sweep-angle. Both angles are specified in radians. Currently, arcs are parts of ellipses whose major and minor axes are parallel to the screen axes. When port's drawing-mode is :quality the arc is transformed properly, but if drawing-mode is :compatible and port has rotation in its transform, the enclosing rectangle is modified to be the external enclosing orthogonal rectangle of the rotated rectangle. The start angle is rotated. The transform, foreground, background, operation, thickness, scale-thickness, mask, shape-mode and compositing-mode from the port's graphics-state are all used, unless overridden in args. Additionally on Unix only, stipple and pattern are used. When filled is non-nil, a sector is drawn.

See also

draw-arcs

make-graphics-state

draw-arcs Function

Summary Draws several arcs.

Package graphics-ports

Signature draw-arcs port description &rest args &key filled

Arguments *port* A graphics port.

description A description sequence.

filled A boolean.

args graphics-state parameters passed as key-

word arguments.

Description The draw-arcs function draws several arcs as specified by

the *description* sequence. This is usually more efficient than making several calls to draw-arc. The *description* argument is a sequence of values of the form x y *width height start-angle*

sweep-angle. See draw-arc for more information.

See also draw-arc

draw-character Function

Summary Draws a character in a given graphics port.

Package graphics-ports

Signature draw-character port character x y &rest args &key block

Arguments *port* A graphics port.

character A character.

x A real number.

y A real number.

block A boolean.

args graphics-state parameters passed as key-

word arguments.

Description The draw-character function draws the character character

at $(x \ y)$ on the port. The transform, foreground, background, operation, stipple, pattern, mask, mask-transform, font, text-mode and compositing-mode from the port's graphics-state are all

used, unless overridden in args.

(x y) specifies the leftmost point of the character's baseline.

block, if non-nil, causes the character to be drawn in a character cell filled with the port's graphics-state background.

Notes

The graphics-state parameter *operation* is not supported for drawing text on Windows.

draw-circle Function

Summary Draws a circle.

Package graphics-ports

Signature draw-circle port x y radius &rest args &key filled

Arguments *port* A graphics port.

x A real number.

y A real number.

radius A real number.

args graphics-state parameters passed as key-

word arguments.

filled A boolean.

Description The draw-circle function draws a circle of the given radius

centered on (x y). The transform, foreground, background, operation, thickness, scale-thickness, mask, shape-mode and compositing-mode from the port's graphics-state are all used, unless overridden in args. When filled is non-nil, the circle is filled

with the foreground color.

Notes draw-circle does not work properly under a rotation trans-

form (see make-transform). A workaround is to use a many-

sided polygon drawn by draw-polygon which will be

rotated correctly.

Example (gp:draw-circle port 100 100 20)

(gp:draw-circle port 100 100 50 :filled t :foreground :green)

See also graphics-state

draw-ellipse Function

Summary Draws an ellipse.

Package graphics-ports

Signature draw-ellipse port x y x-radius y-radius &rest args &key filled

Arguments *port* A graphics port.

x A real number.

y A real number.

x-radius A real number.y-radius A real number.

radius A real number.

args graphics-state parameters passed as key-

word arguments.

filled A boolean.

Description The draw-ellipse function draws an ellipse of the given

radii centered on (x y). The transform, foreground, background, operation, thickness, scale-thickness, mask, shape-mode and compositing-mode from the port's graphics-state are all used, unless overridden in args. When filled is non-nil, the ellipse

is filled with the foreground color.

Notes draw-ellipse does not work properly under a rotation

transform when *port's drawing-mode* is :compatible. A workaround is to use a many-sided polygon drawn by draw-

polygon which will be rotated correctly.

draw-ellipse does work properly under any transform

when port's drawing-mode is :quality.

See make-transform for information about rotation trans-

forms.

For more information about drawing-mode, see "Drawing

mode and anti-aliasing" in the CAPI User Guide.

Example (gp:draw-ellipse port 100 100 20 40)

(gp:draw-ellipse port 100 100 50 10 :filled t

:foreground :green)

See also graphics-state

draw-image Function

Summary Displays an image on a graphics port at a given position.

Package graphics-ports

Signature draw-image port image to-x to-y &rest args &key from-x from-y

to-width to-height from-width from-height global-alpha

Arguments *port* A graphics port.

image An image.

to-x A real number.

to-y A real number.

args graphics-state parameters passed as key-

word arguments.

from-x A real number.

from-y A real number.

to-width A real number.

to-height A real number.

from-width A real number.

from-height A real number.

global-alpha A real number in the inclusive range [0,1], or

nil.

Description

The draw-image function displays *image* on the port at *to-x to-y*.

The default value of *from-x* and *from-y* is 0. The *width* and *height* arguments default to the size of the image.

When *port*'s *drawing-mode* is :compatible, graphics state translation is guaranteed to be supported but support for scaling and rotation are library dependent. Specifically, scaling is supported in the Windows, Cocoa and GTK+ implementations, but not on X11/Motif.

When *port*'s *drawing-mode* is :quality, the target coordinates are fully transformed according to the transformation in the graphics-state.

For more information about *drawing-mode*, see "Drawing mode and anti-aliasing" in the *CAPI User Guide*.

global-alpha, if non-nil, is a blending factor that applies to the whole image, in the Windows and Cocoa implementations, but not on X11/Motif or GTK+. The value 0 means use only the target (that is, do not draw anything) and the value 1 means use only the source (that is, normal drawing). Intermediate real values mean use proportions of both the target and source. The value nil also means normal drawing, and this is the default value.

Notes

On Microsoft Windows, if the image was loaded from a .ico file then draw-image ignores from-x, from-y, from-width, from-height and the graphics-state operation when drawing the image, and also global-alpha is ignored.

draw-line Function

Summary Draws a line between two given points.

Package graphics-ports

Signature draw-line port from-x from-y to-x to-y &rest args

Arguments *port* A graphics port.

from-x A real number.

from-v A real number.

from-y A real number.

to-x A real number.

to-y A real number.

args graphics-state parameters passed as key-

word arguments.

Description The draw-line function draws a line from (from-x from-y) to

(to-x to-y).

The graphics-state parameters transform, foreground, background, operation, thickness, scale-thickness, dashed, dash, line-end-style, mask, shape-mode and compositing-mode are used. Additionally on Unix only, stipple and pattern are used.

See also draw-lines

graphics-state

draw-lines Function

Summary Draws several lines between pairs of two given points.

Package graphics-ports

Signature draw-lines port description &rest args

Arguments *port* A graphics port.

description A description sequence.

args graphics-state parameters passed as key-

word arguments.

Description The draw-lines function draws several lines as specified by

the *description* sequence. This is usually more efficient than making several calls to $\mathtt{draw-line}$. The *description* argument is a sequence of values of the form $x1\ y1\ x2\ y2$. See $\mathtt{draw-line}$

for more information.

See also draw-line

draw-path Function

Summary Draws a path at a given point, optionally closing it or filling

it.

Package graphics-ports

Signature draw-path port path x y &rest args &key closed filled fill-rule

Arguments *port* A graphics port.

path A path specification.

x A real number.

y A real number.

closed A boolean.

filled A boolean.

fill-rule One of the keywords : even-odd and

:winding.

args graphics-state parameters passed as key-

word arguments.

Description

The function draw-path draws the path path at (x y) in port.

When closed is non-nil, a line is drawn from the last point in the path to the start of the last figure in the path. When filled is non-nil, the path is filled, otherwise its outline is drawn; the closed argument is ignored if filled is non-nil. transform, foreground, background, thickness, scale-thickness, dashed, dash, line-end-style, line-joint-style and mask from port's graphics state (see graphics-state) are all used. fill-rule specifies how overlapping regions are filled. Possible values for fill-rule are: even-odd and: winding.

path is a path specification, which consists of path elements that describe a number of disconnected figures. The origin of the path is (*x y*), so all other coordinates within the path are translated relative to that point.

The following formats of path specification are supported:

- A sequence of lists, each of which is a path element as described below.
- A function designator to generate the path elements.
 Graphics ports calls the function when it wants to obtain the path elements. The function takes a single argument, which is a function that should be called with each path elements as its arguments.

The following path elements can be used:

:close Closes the current figure by adding a

straight line from the current point to the

start point.

- :move x y Closes the current figure and starts a new one at (x y).
- Adds a straight line to the current figure, from the current point to (*x y*) and makes (*x y*) be the current point.

:arc x y width height start-angle sweep &optional movep

Adds an elliptical arc to the current figure, contained in the rectangle from (x y) to (x+width y+width) from start-angle to start-angle+sweep-angle. Both angles are specified in radians and positive values mean anti-clockwise. If movep is nil (the default), then a straight line is also added from the current point to the start of the arc, otherwise a new figure is started from the start of the arc. The end of the arc becomes the new current point.

:bezier cx1 cy1 cx2 cy2 x y

Adds a cubic Bézier curve to the current figure, from the current point to (*x y*) using control points (*cx1 cy1*) and (*cx2 cy2*).

:rectangle x y width height

Adds a self contained figure, a rectangle from (*x y*) to (*x*+*width y*+*width*).

:ellipse x y x-radius y-radius

Adds a self contained figure, an ellipse of the given radii centered on (x y).

:scale sx sy elements

Adds the path elements *elements*, scaling them by *sx* and *sy*.

:rotate theta elements

Adds the path elements *elements*, rotating them *theta* radians about the origin. If *theta* is positive, then the rotation is clockwise.

:translate dx dy elements

Adds the path elements *elements*, translating them by *dx* and *dy*.

:transform transform elements

Adds the path elements *elements*, transformed by *transform*.

Examples

Draws two lines from (40 30) to (140 30) and from (140 30) to (140 130):

```
(draw-path port '((:line 100 0) (:line 100 100)) 40 30)
```

Draws an outline triangle with vertices (40 30), (140 30) and (140 130):

```
(draw-path port '((:line 100 0) (:line 100 100))
40 30 :closed t)
```

Draws a filled triangle with vertices (40 30), (140 30) and (140 130):

```
(draw-path port '((:line 100 0) (:line 100 100))
40 30 :filled t)
```

Draws a filled triangle exactly as in the previous example but using a function to generate the path elements:

Draws 6 copies of a shape consisting of two lines and an arc:

There are more examples in

examples/capi/graphics/paths.lisp

See also draw-polygon

draw-line
draw-arc
draw-ellipse

graphics-state

draw-point Function

Summary Draws a pixel or unit square at a given point.

Package graphics-ports

Signature draw-point port x y &rest args

Arguments *port* A graphics port.

x A real number.y A real number.

args graphics-state parameters passed as key-

word arguments.

Description The draw-point function draws a single-pixel point at (x y).

The transform, foreground, background, operation, mask, shape-mode and compositing-mode graphics-state parameters are used. Additionally on Unix only, stipple and pattern are used.

When *drawing-mode* is :compatible the output is a single pixel. Note that its position is transformed in the normal way.

When *drawing-mode* is :quality this draws a unit square as if by draw-rectangle, transformed in the normal way.

See also draw-points

graphics-state

draw-points Function

Summary Draws pixels or unit squares at given points.

Package graphics-ports

Signature draw-points port description &rest args

Arguments *port* A graphics port.

description A description sequence.

args graphics-state parameters passed as key-

word arguments.

Description The draw-points function draws several points (as if by

draw-point) as specified by the *description* argument, which is a sequence of *x y* pairs. It is usually faster than several calls to draw-point. See draw-point for more information.

See also draw-point

draw-polygon Function

Summary Draws a polygon.

Package graphics-ports

Signature draw-polygon port points &rest args &key filled closed fill-rule

Arguments *port* A graphics port.

points A description sequence.

filled A boolean.

closed A boolean.

A keyword

fill-rule A keyword.

args graphics-state parameters passed as key-

word arguments.

Description The draw-polygon function draws a polygon using alternat-

ing *x* and *y* values in the *points* argument as the vertices. When *closed* is non-nil the edge from the last vertex to the first to be drawn. When *filled* is non-nil a filled, closed polygon is drawn; the *closed* argument is ignored if *filled* is non-

nil.

transform, foreground, background, operation, thickness, scale-thickness, dashed, dash, line-end-style, line-joint-style, mask, shape-mode and compositing-mode from port's graphics-state are all used, unless overridden in args. Additionally on Unix only, stipple and pattern are used.

fill-rule specifies how overlapping regions are filled. Possible values are :even-odd and :winding.

See also draw-polygons

graphics-state

draw-polygons Function

Summary Draws several polygons.

Package graphics-ports

Signature draw-polygons port description &rest args &key filled closed

fill-rule

Arguments *port* A graphics port.

description A sequence of sequences of real numbers.

filled A boolean.

closed A boolean.

fill-rule A keyword.

graphics-state parameters passed as keyargs word arguments.

Description

The draw-polygons function draws several polygons. The description argument should be a sequence containing sequences with alternating x and y values representing the vertices. The description arguments consists of groups of points as in draw-polygon.

When *closed* is non-nil the edge from the last vertex to the first to be drawn.

When *filled* is non-nil a filled, closed polygons are drawn; the *closed* argument is ignored if *filled* is non-nil.

transform, foreground, background, operation, thickness, scalethickness, dashed, dash, line-end-style, line-joint-style, mask, shape-mode and compositing-mode from the port's graphicsstate are all used, unless overridden in args. Additionally on Unix only, *stipple* and *pattern* are used.

fill-rule specifies how overlapping regions are filled. Possible values are :even-odd and :winding.

Example

This draws two hexagons, one inside the other:

```
(gp:draw-polygons oo
          '((150 100 200 100 235 150 200
             200 150 200 115 150)
             (140 90 210 90 250 150
             210 210 140 210 100 150))
          :closed t)
```

See also draw-polygon

draw-rectangle

Function

Summary Draws a rectangle.

Package graphics-ports Signature draw-rectangle port x y width height &rest args &key filled

Arguments *port* A graphics port.

x A real number.y A real number.width A real number.

height A real number.

filled A boolean.

args graphics-state parameters passed as key-

word arguments.

Description The draw-rectangle function draws a rectangle whose cor-

ners are (x y), (x+width y), (x+width y+height) and (x y+height).

filled, if non-nil, causes a filled rectangle to be drawn. While the exact results are host-specific, it is intended that a filled rectangle does not include the lines (x = x+width) and (y = y+height) while a non-filled rectangle does. This function works correctly if the *port*'s transform includes rotation.

The graphics-state parameters transform, foreground, background, operation, thickness, scale-thickness, dashed, dash, line-joint-style, mask, shape-mode and compositing-mode are used. Additionally on Unix only, stipple and pattern are used.

See also draw-rectangles

graphics-state

draw-rectangles

Function

Summary Draws several rectangles.

Package graphics-ports

Signature draw-rectangles port description &rest args &key filled

2 GP Reference Entries

Arguments *port* A graphics port.

description A description sequence.

filled A boolean.

args graphics-state parameters passed as key-

word arguments.

Description The draw-rectangles function draws several rectangles as

specified in *description* which consists of a group of values

given as *x y width height*.

filled, if non-nil, causes filled rectangles to be drawn. While the exact results are host-specific, it is intended that a filled rectangle does not include the lines (x = x+width) and (y = y+height) while a non-filled rectangle does. This function works correctly if the *port*'s transform includes rotation.

The graphics-state parameters transform, foreground, background, operation, thickness, scale-thickness, dashed, dash, line-joint-style, mask, shape-mode and compositing-mode are used. Additionally on Unix only, stipple and pattern are used.

See also draw-rectangle

draw-string Function

Summary Draws a string with the baseline positioned at a given point.

Package graphics-ports

Signature draw-string port string x y &rest args &key start end block

Arguments *port* A graphics port.

string A string.

x A real number.

y A real number.

start A real number.

end A real number.

block A boolean.

args graphics-state parameters passed as key-

word arguments.

Description

Draws the string with the baseline starting at (x y). The transform, foreground, background, operation, stipple, pattern, mask, mask-transform, font, text-mode and compositing-mode from port's graphics-state are all used, unless overridden in args.

start and end specify which elements of the string to draw. The default value of start is 0.

block, if non-nil, causes each character to be drawn in a character cell filled with the background of port's graphics-state.

You can draw with the system highlight by setting graphics-state parameter foreground:color_highlighttext and background:color highlight.

Notes

The graphics-state parameter *operation* is not supported for drawing text on Microsoft Windows.

Example

See also

graphics-state

ensure-gdiplus Function

Summary Ensures GDI+ is present and running, or shuts it down.

Needed only when writing FLI graphics code on Windows.

Package graphics-ports

Signature ensure-gdiplus &key event-func force shutdown => result

Arguments event-func A function, or nil.

force A boolean.

shutdown A boolean.

Values result A boolean.

Description The function ensure-gdiplus checks that the GDI+ module

gdiplus.dll is loaded and that GdiplusStartup has been

called, or shuts down GDI+.

Most users will not need to call <code>ensure-gdiplus</code>. This is because when LispWorks itself uses GDI+, for instance via <code>read-external-image</code>, it calls <code>ensure-gdiplus</code> automatically, and never shuts GDI+ down.

However, if your code uses GDI+ directly (by calling it through the Foreign Language Interface), then you should call <code>ensure-gdiplus</code> instead of using <code>GdiplusStartup</code> directly. Then, LispWorks will know that GDI+ has already started. This is the only circumstance in which you need to call <code>ensure-gdiplus</code>.

Note: ensure-gdiplus is implemented only in LispWorks for Windows.

If *shutdown* is nil, ensure-gdiplus ensures GDI+ is started, by the following steps:

1. Load the GDI+ module gdiplus.dll, if it is not already loaded.

- 2. If
 - a) GDI+ was already started by a previous call to ensure-gdiplus, and
 - b) force is mil, and
 - c) *event-func* was either not passed or is eq to the value that was passed for point a)

then ensure-gdiplus simply returns nil.

- 3. If GDI+ was already started, shut it down.
- 4. Start GDI+, and return the result of GdiplusStartup. This is 0 for success. For he meaning of other values, see the documentation of gpStatus in the MSDN.

If *shutdown* is true, then if GDI+ was started ensure-gdiplus shuts it down, and returns t, otherwise ensure-gdiplus returns nil. The default value of *shutdown* is nil.

The default value of both event-func and force is mil.

See also read-external-image

external-image Class

Summary A class representing a color image.

Package graphics-ports

Description The class external-image provides a representation of a

color image that is subject to write-external-image, read-external-image and convert-external-image operations.

See also convert-external-image

read-external-image
write-external-image

external-image-color-table

Function

Summary Returns a vector containing RGB color specifications of an

external image.

Package graphics-ports

Signature external-image-color-table external-image => color-table

Arguments external-image An external image.

Values *color-table* A color table.

Description The external-image-color-table function returns a

vector containing RGB color specifications representing the color table as specified in the external image. If the result is nil, the external image is a 24-bit DIB, with the colors

defined in each pixel instead of through a table.

external-image-color-table

Setf Expander

Summary Replaces the color table in an external image.

Package graphics-ports

Signature (setf external-image-color-table) replacement-color-table

external-image

Arguments external-image An external image.

replacement-color-table

A color table.

Description

(setf external-image-color-table) replaces the color table in *external-image*. The color table specified by *replace-ment-color-table* must be the same length as the external image's original color table. It is a vector of RGB color-specifications.

externalize-and-write-image

Function

Summary Externalizes and writes an image to file.

Package graphics-ports

Signature externalize-and-write-image gp image filename &key type if-

exists errorp x-hot y-hot quality &allow-other-keys => result

Arguments gp A CAPI pane.

image An image object.

filename A file namestring or a pathname.

type One of the keywords :bmp, :jpg, :jpeg,

:png and :tiff. Other keywords may be supported, depending on the platform.

if-exists One of the keywords :error, :new-ver-

sion, :rename, :rename-and-delete,
:overwrite, :append and :supersede, or

nil.

errorp A boolean.

x-hot A non-negative integer.

y-hot A non-negative integer.

quality An integer in the range [0,100].

Values result A filename or nil.

Description

The function externalize-and-write-image externalizes and writes an image object to file.

The output image type can be specified by the argument *type*. If *type* is not supplied then the output image type is determined by the file type in the *filename*.

If type is supplied, it must be a keyword which specifies a known type, as returned by list-known-image-formats with for-writing-too t. The types :bmp, :jpg, :png and :tiff are known on all platforms (except Motif). Additionally, :jpeg is an as alias for :jpg.

If *type* is not supplied, then the file extension of the filename is used to "guess" the type. In general it is the extension uppercased and interned in the keyword package. It also recognizes some special cases:

File extension	Image type
"TIF"	:tiff
"DIB"	:bmp
"JPE"	:jpg
"JPEG"	:jpg
"JFIF"	:jpg
"JP2"	:jpg2000

Table 2.1 Image type from file extension: special cases

Note: Image type :jpg2000 is implemented on Cocoa only. errorp controls what happens if externalize-and-write-image does not recognize the type. If errorp is non-nil, it calls error, otherwise it returns nil. The default value of errorp is t.

if-exists controls what to do if the filename already exists, in the same way as the if-exists argument to open. However, unlike open, the default value of if-exists is :supersede.

x-hot and y-hot are used only when generating a CUR file, which is currently implemented on GTK+ only. They specify the hotspot coordinates when the image is used as a cursor (in a LispWorks application by load-cursor and (setf capi:simple-pane-cursor), or in other applications). Their values must be integers within the width/height of the image. The default value of both x-hot and y-hot is 0.

quality is used for writing a JPG image on GTK+. It must be an integer in the inclusive range [0,100]. High values generate better images and larger files.

result is filename on success, or nil for an unknown type when errorp is nil. It signals an error in other cases (for example, failure to open the file because of permissions).

Examples There is a simple example in:

examples/capi/graphics/images-with-alpha.lisp

See also list-known-image-formats

externalize-image

Function

Summary Returns an external image containing color information from

an image.

Package graphics-ports

Signature externalize-image gp image &key maximum-colors

important-colors &allow-other-keys

=> external-image

Arguments gp A CAPI pane.

image An image.

maximum-colors An integer or mil. The default is mil.

important-colors An integer or nil

Values *external-image* An external image.

Description The externalize-image function returns an external-image containing color information from *image*.

If maximum-colors is nil or if the screen has no palette, an external-image using all the colors in image is created.

If maximum-colors is an integer, the external-image containing image will be created using no more than that number of colors. If the image contains more than maximum-colors colors, the maximum-colors most frequently used colors will be accurately stored; the remainder will be approximated by nearest colors out of the accurate ones, using internal Color System parameters as the weighting factors for the color distance.

The value of *important-color* is recorded in the *external-image* for later use, and specifies the number of colors required to draw a good likeness of the image. The default value is the number of colors in the image.

See also make-image-from-port write-external-image

f2pi Constant

Summary (* 2 pi) as a single-float.

Package graphics-ports

Description The constant f2pi is the result of (float (* 2.0 cl:pi) 1.0). It is a cl:single-float.

See also fpi

fpi-by-2

find-best-font Function

Summary Returns the best font for a CAPI pane.

Package graphics-ports

Signature find-best-font pane fdesc => font

Arguments *pane* A graphic port.

fdesc A font description.

Values font A font.

Description The function find-best-font returns the best font for pane

which matches *fdesc*. When there alternative fonts available the choice of best font is operating system dependent.

When fdesc contains the attribute :stock with value :system-font or :system-fixed-font, the lookup will

always find a stock font.

By default ${\tt find-best-font}$ looks only for Truetype fonts in

LispWorks 6.1 and later.

Notes With the default *drawing-mode*: quality only Truetype fonts

are supported. Non-Truetype fonts are supported only when

using drawing-mode:compatible.

Compatibility To get the

note

To get the LispWorks 6.0 behavior where non-Truetype fonts are also found, pass:type:wildtomake-font-descrip-

tion.

Examples examples/capi/graphics/catherine-wheel.lisp

See also find-matching-fonts

make-font-description

prompt-for-font

find-matching-fonts

Function

Summary Returns a list of the font objects available for a pane.

Package graphics-ports

Signature find-matching-fonts pane fdesc => fonts

Arguments *pane* A CAPI pane.

fdesc A font description.

Values fonts A list of fonts.

Description The find-matching-fonts function returns a list of the font

objects available for *pane* which match the attributes in *fdesc*.

nil is returned if none match.

When fdesc contains the attribute :stock with value

 $\verb":system-font" or : \verb"system-fixed-font", the lookup will$

always find a stock font.

See also find-best-font

list-all-font-names
make-font-description

font Type

Summary An object corresponding to a font in the native system.

Description font objects are returned by find-best-font and find-

matching-fonts.

font objects are used to specify fonts for drawing, either in the graphics-state of the port or in the drawing functions themselves. font objects can also be used for querying the actual attributes of the font (ascent, descent, etc) and the dimensions of character and strings.

Notes font objects are not externalizable objects.

See also

font-description
find-best-font
find-matching-fonts
graphics-state
get-font-ascent
get-font-descent
get-font-width
get-font-height
get-font-average-width
get-char-width
get-char-descent

get-char-descent
get-character-extent
get-string-extent
compute-char-extents
font-single-width-p
font-fixed-width-p
font-description

font-description

Type

Summary An object used in CAPI to describe a font.

Description

Objects of type font-description contain a description of a font. The description can be partial, with only some attributes given values. font-description objects are the normal way of specifying fonts in CAPI.

font-description objects are created or returned by makefont-description, convert-to-font-description, font-description, merge-font-descriptions and augment-font-description.

font-description objects are used as the font specification for CAPI panes (see simple-pane). They can also be used directly in calls to find-best-font and find-matching-fonts.

Notes

- 1. font-description objects do not contain native system dependent values, and are externalizable objects.
- 2. A font-description cannot be used directly as an argument to draw-string or draw-character, or as the value of the graphics state parameter *font* in a graphics-state. These require the result of find-best-font or find-matching-fonts.

See also

make-font-description convert-to-font-description font-description merge-font-descriptions augment-font-description font-description-attributes

font-description

Function

Summary Returns a font description object for a given font.

Package graphics-ports

Signature font-description font => fdesc

Arguments *font* A font.

Values *fdesc* A font description.

Description The font-description function returns a font description

object for *font*. Using this font description in a later call to find-matching-fonts or find-best-font on the original

pane is expected to return a similar font.

See also convert-to-font-description

make-font-description

font-description-attributes

Function

Summary Returns the attributes of a given font description.

Package graphics-ports

Signature font-description-attributes fdesc => font-attributes

Arguments *fdesc* A font description.

Values font-attributes A list of font attributes.

Description The font-description-attributes function returns the

attributes of the *fdesc*. The list should not be destructively

modified.

font-description-attribute-value

Function

Summary Returns the values of a given font attribute in a font descrip-

tion.

Package graphics-ports

Signature font-description-attribute-value fdesc font-attribute =>

value

Arguments *fdesc* A font description.

2 GP Reference Entries

font-attribute A font attribute.

Values value A font attribute value.

Description The font-description-attribute-value function returns

the value of font-attribute in fdesc, or :wild if font-attribute is

not specified in fdesc.

font-dual-width-p

Function

Summary The predicate for dual-width fonts.

Signature font-dual-width-p port &optional font => result

Arguments *port* A graphics port.

font A font or a font-description object.

Values result A boolean.

Description The function font-dual-width-p returns t when the font is

fixed-width and contains double width characters. Such a

font is dual-width.

See also font-fixed-width-p

font-single-width-p

font-fixed-width-p

Function

Summary The predicate for fixed-width fonts.

Package graphics-ports

Signature font-fixed-width-p port &optional font => result

Arguments *port* A graphics port.

font A font or a font-description object.

Values result A boolean.

Description The function font-fixed-width-p returns t if the option-

ally specified font, or otherwise the font associated with port,

is fixed-width.

fixed-width is not exactly the same as single-width. A fixed-width font with double width characters is dual-width; other

fixed-width fonts are single-width.

Notes editor-pane supports variable width fonts on Microsoft

Windows, GTK+ and Motif.

See also font-description

font-single-width-p

font-single-width-p

Function

Summary The predicate for single-width fonts.

Signature font-single-width-p port &optional font => result

Arguments font A font or a font-description object.

Values result A boolean.

Description The function font-single-width-p returns t when all char-

acters in the font specified by *font* are of the same width.

A single-width font is fixed-width.

See also font-fixed-width-p

font-description

fpi Constant

Summary pi as a single-float.

Package graphics-ports

Description The constant fpi is the result of (float cl:pi 1.0). It is a

cl:single-float.

See also 2pi

f2pi

fpi-by-2

fpi-by-2 Constant

Summary (/ pi 2) as a single-float

Package graphics-ports

Description The constant fpi-by-2 is the result of (float (* 0.5

cl:pi) 1.0). It is a cl:single-float

See also fpi

f2pi

free-image Function

Summary Frees the library resources allocated with an image.

Package graphics-ports

Signature free-image port image

Arguments *port* A CAPI pane.

image An image.

Description The free-image function frees the library resources associ-

ated with image. This should be done when an image is no

longer needed.

free-image-access

Function

Summary Frees an Image Access object.

Package graphics-ports

Signature free-image-access image-access

Arguments image-access An Image Access object

Description The function free-image-access discards image-access,

which should be an Image Access object returned by make-

image-access.

See also image-access-transfer-from-image

image-access-transfer-to-image

image-access-pixel
make-image-access

get-bounds Function

Summary Returns the four values of the currently collected drawing

extremes.

Package graphics-ports

Signature get-bounds pixmap-port => left, top, right, bottom

Arguments *pixmap-port* A graphics port.

Values *left* An integer.

top An integer.
right An integer.
bottom An integer.

Description The get-bounds functions returns the four values *left*, *top*,

right, bottom of the currently collected drawing extremes. The

values can be used to get an image from the port.

Example (with-pixmap-graphics-port (pl pane width height

:relative t)

(with-graphics-rotation (p1 0.123)

(draw-rectangle p1 100 100 200 120 :filled t

:foreground :red)

(get-bounds p1)))

produces the following output:

72 112

285

255

See also make-image-from-port

get-character-extent

Function

Summary Returns the extent of a character in pixels.

Package graphics-ports

Signature get-character-extent port character & optional font =>

left, top, right, bottom

Arguments *port* A CAPI pane.

character A character.

font A font.

Values *left* An integer.

top An integer.
right An integer.
bottom An integer.

Description The get-character-extent function returns the extent in

pixels of the *character* in the font associated with *port*, or the

font given.

get-char-ascent

Function

Summary Returns the ascent of a character in pixels.

Package graphics-ports

Signature get-char-ascent port character font => ascent

Arguments *port* A CAPI pane.

character A character.

font A font.

Values ascent An integer.

Description The get-character-ascent function returns the ascent in

pixels of the *character* in the font associated with *port*, or the

font given.

get-char-descent

Function

Summary Returns the descent of a character in pixels.

Package graphics-ports

2 GP Reference Entries

Signature get-char-descent port character font => descent

Arguments *port* A CAPI pane.

character A character.

font A font.

Values *descent* An integer.

Description The get-char-descent function returns the descent in pixels

of the *character* in the font associated with *port*, or the *font*

given.

get-char-width Function

Summary Returns the width of a character in pixels.

Package graphics-ports

Signature get-char-width port character font => width

Arguments *port* A CAPI pane.

character A character.

font A font.

Values width An integer.

Description The get-char-width function returns the width in pixels of

the *character* in the font associated with *port*, or the *font* given.

get-enclosing-rectangle

Function

Summary Returns the smallest rectangle enclosing the given points.

Package graphics-ports

Signature get-enclosing-rectangle &rest points => left, top, right,

bottom

Arguments *points* Real numbers.

Values *left* A real number.

top A real number.right A real number.bottom A real number.

Description The get-enclosing-rectangle function returns four val-

ues, describing the rectangle which exactly encloses the input points. The *points* argument must be a (possibly empty) list of alternating x and y values. If no *points* are given the function returns the null (unspecified) rectangle, which is four nils.

get-font-ascent Function

Summary Returns the ascent of a font.

Package graphics-ports

Signature get-font-ascent port &optional font => ascent

Arguments *port* A CAPI pane.

font A font.

Values ascent An integer.

Description The get-font-ascent function returns the ascent in pixels of

the font associated with *port*, or the *font* given.

get-font-average-width

Function

Summary Returns the average width of a font in pixels.

Package graphics-ports

Signature get-font-average-width port &optional font => average-width

Arguments *port* A CAPI pane.

font A font.

Values average-width An integer.

Description The get-font-average-width function returns the average-

width in pixels of the font associated with port, or the font

given.

get-font-descent

Function

Summary Returns the descent in pixels of a font.

Package graphics-ports

Signature get-font-descent port &optional font => descent

Arguments *port* A CAPI pane.

font A font.

Values *descent* An integer.

Description The get-font-descent function returns the descent in pixels

of the font associated with port, or the font given.

get-font-height Function

Summary Returns the height of a font.

Package graphics-ports

Signature get-font-height port &optional font => height

Arguments *port* A CAPI pane.

font A font.

Values height An integer.

Description The get-font-height function returns the height in pixels of

the font associated with *port*, or the *font* given.

get-font-width Function

Summary Returns the width of a font.

Package graphics-ports

Signature get-font-width port &optional font => width

Arguments *port* A graphics port.

font A font.

Values width An integer.

Description The function get-font-width returns the width in pixels of

the font associated with *port*, or the *font* given.

get-graphics-state

Function

Summary Returns the graphics-state object for a graphics port. get-

graphics-state is deprecated. Use port-graphics-state

instead.

Package graphics-ports

Signature get-graphics-state port => state

Arguments *port* A graphics port.

ValueS state A graphics-state object.

Description get-graphics-state is deprecated. Use port-graphics-

state instead.

See also port-graphics-state

get-origin Function

Summary Returns the coordinate origin of a pixmap graphics port.

Package graphics-ports

Signature get-origin pixmap-port => x y

Arguments *pixmap-port* A graphics port.

Values x An integer.

y An integer.

Description This returns two values being the coordinate origin of the

pixmap graphics port. Normally this is (0 0) but after a series of drawing function calls with :relative t, the drawing

may have been shifted. The get-origin values tell you by how much. The values are not needed when making images from the port's drawing.

Example

```
(with-pixmap-graphics-port (pl pane width height
:relative t)
    (with-graphics-rotation (p1 0.123)
      (draw-rectangle p1 0 0 200 120 :filled t
                                       :foreground :red)
      (get-origin p1)))
produces:
-15
```

get-string-extent

Function

Summary Returns the extent in pixels of a string. Package graphics-ports Signature get-string-extent port string &optional font => left, top, right, bottom **Arguments**

A CAPI pane. port

string A string.

Values left An integer.

> top An integer. right An integer. bottom An integer.

Description The get-string-extent function returns the extent in pixels of the *string* in the font associated with *port*, or the *font* given.

739

2 GP Reference Entries

Note: To compute the horizontal extents of each successive character in a string for a given port or font, use compute-

char-extents.

See also compute-char-extents

get-transform-scale

Function

Summary Returns the overall scaling factor of a transform.

Package graphics-ports

Signature get-transform-scale transform => result

Arguments transform A transform object.

Values result A real number.

Description The get-transform-scale function returns a single number

representing the overall scaling factor present in the *trans*-

form.

graphics-port-background graphics-port-font graphics-port-foreground graphics-port-transform

Functions

Summary Accesses the background, font, foreground or transform in the

graphics state of a graphics port.

Package graphics-ports

Signature graphics-port-background port => color-spec

graphics-port-font port => font

graphics-port-foreground port => color-spec

graphics-port-transform port => transform

(setf graphics-port-background) color-spec port => color-spec

(setf graphics-port-font) font port => font

(setf graphics-port-foreground) color-spec port => color-spec

(setf graphics-port-transform) transform port => transform

Arguments *port* A graphics port.

Values color-spec A color specification, or nil.

font A font object, or nil.

transform A transform object.

Description The functions graphics-port-background, graphics-port-

font, graphics-port-foreground and graphics-port-tranform access the background, font, foreground or transform in the graphics-state associated with port. This can be used

to set the value by setf.

See the graphics-state entry for the types and acceptable

values of the specific slots.

See also graphics-state

port-graphics-state
set-graphics-state

transform

with-graphics-state

graphics-state Function

Summary The graphics state object, holding default parameters for

drawing operations on an associated port.

Package graphics-ports

Slots

transform

A transform object which determines the coordinate transformation applying to the graphics port. The default value is the unit transform which leaves the port coordinates unchanged from those used by the host window system — origin at top left, X increasing to the right and Y increasing down the screen. Allowed values are anything returned by the transform functions, described in section "Graphics state transforms" of the *CAPI User Guide*.

foreground

Determines the foreground color used in drawing functions. The value can be a pixel value, a color name symbol, a color name string or a color spec object. Using pixel values results in better performance. The default value is :black. The value :color_highlighttext is useful for drawing text with the system highlighting.

background

Determines the background color used in drawing functions which use a stipple. Valid values are the same as for *foreground*. The default value is :white. The value :color_highlight is useful for drawing text with the system highlighting.

operation

Determines the color combination used in the drawing primitives when the port's drawing-mode is :compatible. Valid values are 0 to 15, being the same logical values as the op arg to the Common Lisp function boole. The default value is boole-1. The section "Graphics state operation" in the CAPI User Guide shows how to use operation.

stipple

A 1-bit pixmap ("bitmap") or nil (which is the default value). The bitmap is used in conjunction with the fill-style when drawing. Here, nil means that all pixels are drawn in the foreground color. A stipple is not transformed by the transform parameter. Its origin is assumed to coincide with the origin of the port. The stipple is tiled across the drawing. stipple is ignored if a pattern is given. If no fill-style is given, or it is specified as :solid, when a stipple is given, then fill-style defaults to :opaque-stippled.

fill-style

Determines how the drawing is done. The value should be one of <code>:solid</code>, <code>:opaque-stippled</code>, <code>:stippled</code> or <code>:tiled</code>. The default value <code>:solid</code> means that the foreground is used everywhere. <code>:opaque-stip-pled</code> means that the stipple bitmap is used with stipple 1s giving the foreground and 0s the background. <code>:stippled</code> means that the stipple bitmap is used with foreground where there are 1s and where the are 0s, no drawing is done. If you specify a stipple but no fill-style, or a fill-style of <code>:solid</code>, it defaults to <code>:opaque-stipple</code>.

pattern

An image the same depth as the port, or nil. If non-nil, pattern is used as the source of color for drawing instead of the foreground and background parameters. A pattern is not transformed by the transform parameter. The pattern is tiled across the drawing. When pattern is specified, the stipple value is ignored. The default value of pattern is nil.

See "Working with images" in the *CAPI User Guide* for information on creating an image.

thickness A number (defaulting to 1) specifying the

thickness of lines drawn. If *scale-thickness* is non-nil, the value *thickness* is in *port* (transformed) coordinates, otherwise *thickness* is

in pixels.

scale-thickness A boolean, defaulting to t which means

interpret the *thickness* parameter in transformed port coordinates. If *scale-thickness* is

nil, thickness is interpreted in pixels.

dashed A boolean, defaulting to mil. If dashed is t

then lines are drawn as a dashed line using

dash as the mark-space specifier.

dash A list of two or more integer, or nil. A list of

integers specifies the alternate mark and space sizes for dashed lines. These mark and space values are interpreted in pixels only.

The default value of dash is (4 4).

line-end-style The value should be one of :butt, :round

or :projecting and specifies how to draw the ends of lines. The default value is :butt.

line-joint-style The value should be one of :bevel, :miter

or :round and specifies how to draw the areas where the edges of polygons meet. The

default value is :miter.

mask nil, or a list specifying a shape inside which

the drawing is done.

mask-x An integer specifying in window coordi-

nates where in the port the X coordinate of the mask origin is to be considered to be.

The default value is 0.

The *mask-x* parameter works only when the *drawing-mode* is :compatible and the plat-

form is GTK+ or X11/Motif.

mask-x is deprecated.

mask-y An integer specifying in window coordi-

nates where in the port the Y coordinate of the mask origin is to be considered to be.

The default value is 0.

The *mask-y* parameter works only when the *drawing-mode* is :compatible and the plat-

form is GTK+ or X11/Motif.

mask-y is deprecated.

mask-transform A transform object which determines the

coordinate transformation use for the mask

in drawing-mode : quality.

font Either nil or a font object to be used by the

draw-character and draw-string func-

tions. The default value is mil.

Note that *font* cannot be a font-description. Use find-best-font to convert a

font-description to a font.

text-mode A keyword controlling the mode of render-

ing text, most importantly anti-aliasing.

shape-mode A keyword controlling the mode of drawing

shapes (that is, anything except text).

compositing-mode

A keyword controlling the combining of new drawing with existing drawing.

Accessors

graphics-state-transform graphics-state-foreground graphics-state-background graphics-state-operation graphics-state-stipple graphics-state-pattern graphics-state-thickness graphics-state-scale-thickness graphics-state-dashed graphics-state-dash graphics-state-fill-style graphics-state-line-end-style graphics-state-line-joint-style graphics-state-mask graphics-state-mask-x graphics-state-mask-y graphics-state-mask-transform graphics-state-font graphics-state-text-mode graphics-state-shape-mode graphics-state-compositing-mode

Description

Each graphics port has a graphics-state object associated with it, providing the default values of graphics parameters for drawing operations. The drawing operations such as draw-ellipse, draw-rectangle and draw-string can override specific parameters by passing them as keyword arguments.

graphics-state objects are used in the with-graphicsstate macro and modified using the accessor functions listed above. See "Setting the graphics state" in the *CAPI User Guide* for examples.

mask should be mil (the default), a list of the form (x y width height), defining a rectangle inside which the drawing is done or a list of the form (:path path :fill-rule) specifying a path inside which the drawing is done. The mask is not tiled.

In the latter case *path* should be a path specification (see draw-path). The *fill-rule* specifies how overlapping regions are filled. Possible values are :even-odd and :winding. The *mask* will be transformed by the *mask-transform* parameter.

There some examples of path masks in examples/capi/graphics/paths.lisp.

mask-transform is used only in drawing-mode:quality. It is ignored in drawing-mode:compatible. The default value is the unit transform, which can also be specified as nil. Other allowed values include anything returned by the transform functions, described in the section "Graphics state transforms" of the CAPI User Guide. The other allowed value of mask-transform is the keyword:dynamic which is replaced by the current value of the transform graphics state parameter when the drawing operation uses the mask.

Each of *text-mode* and *shape-mode* can be one of:

:plain No anti-aliasing.

:antialias With anti-aliasing.

:fastest Fastest rendering. The same as :plain

except on Windows

:best Best display.

:default The system default (which is :antialias).

Additionally text-mode can be :compatible, which causes text to be drawn the way it would be drawn if drawing-mode was :compatible. This makes a difference only on Microsoft Windows, because on other platforms the default text-mode draws like the :compatible one.

The default of both text-mode and shape-mode is :default.

compositing-mode is a keyword or an integer controlling the compositing mode, that is the way that a new drawing is combined with the existing value in the target of the drawing to generate the result.

Two values of *compositing-mode* are supported on all platforms other than Motif:

:over

Draw over the existing values. If the source is a solid color, then the result is simply the source. If the source has alpha value *alpha*, then it is blended with the destination, with the destination multiplied by the remainder of the alpha, that is (- 1 *alpha*).

:copy

The source is written to the destination ignoring the existing values. If the source has alpha and the target does not, that has the effect of converting semi-transparent source to solid.

The default value of compositing-mode is :over.

The :copy value of compositing-mode is especially useful for creating a transparent or semi-transparent pixmap-port, which can be displayed directly or converted to an image by make-image-from-port.

On Cocoa 10.5 and later and GTK+ 2.8 or later, these additional keyword values of *compositing-mode* are supported: :clear, :over, :in, :out, :atop, :dest-over, :dest-in, :dest-out, :dest-atop, :xor and :add. These correspond to the CAIRO_OPERATOR_* operators in Cairo, which are documented in cairographics.org/operators and the CGBlendMode values which are documented in the CGContext Reference at developer.apple.com.

Note: on GTK+, the "unbounded" operators (:in, :out, :dest-in and :dest-atop) do not work properly for shape drawings. They can only be used for image drawing and copying operations.

Both Cocoa and GTK+ also allow *compositing-mode* to be an integer, which is simply passed through to the underlying system. This allows using modes that are not available via keywords, but it is not portable. For Cocoa, it is a CGBlend-

Mode as documented in the CGContext Reference. For GTK+ it is cairo_operator_t, as documented in the entry for cairo t in the Gnome documentation for Cairo.

Note: For drawing images on Cocoa, only values that corresponding to available keywords work properly.

Notes

- **1.** *operation* is not supported for drawing text on Microsoft Windows.
- 2. *stipple* and *fill-style* are supported only on X11/Motif.
- 3. mask-x and mask-y are supported only on GTK+ and X11/Motif, and only when the drawing-mode is :compatible.
- **4.** *pattern* is supported only on Microsoft Windows, GTK+ and X11/Motif.
- **5.** *operation* is not supported by Cocoa/Core Graphics so this slot or argument is ignored on Cocoa.
- **6.** *operation* is ignored when the port's *drawing-mode* is :quality.
- 7. text-mode and shape-mode are supported only on Cocoa, Cairo and GDI+, which are used on Macintosh, GTK and Windows respectively when the drawing-mode is :qual-ity. For more information about drawing-mode, see "Drawing mode and anti-aliasing" in the CAPI User Guide.

Examples

examples/capi/graphics/compositing-mode-simple.lisp examples/capi/graphics/compositing-mode.lisp

See also

make-graphics-state
set-graphics-state
with-graphics-state

image Class

Summary An abstract image object. An image can be drawn via

draw-image.

Package graphics-ports

Accessors image-height

image-width

Description The image class is the abstract image object class. An image

can be drawn using draw-image.

image-height and image-width return the image size in

pixels.

Notes On Cocoa and GTK+ you can drag and drop images. See

set-drop-object-supported-formats for more informa-

tion.

See also convert-external-image

draw-image
load-image

make-image-from-port

make-sub-image

read-and-convert-external-image

image-access-height image-access-width

Functions

Summary Return the dimensions of the underlying image in an Image

Access object.

Package graphics-ports

Signature image-access-height image-access => height

image-access-width image-access => width

Arguments image-access An Image Access object

Values *height* An integer.

width An integer.

Description The functions image-access-height and image-access-

width return the height and width of the underlying image

in image-access.

image-access must be an Image Access object returned by

make-image-access.

Notes It is an error to call image-access-height or image-

access-width on an Image Access object that has been freed

by free-image-access.

Example See these example files:

examples/capi/graphics/image-access.lisp

examples/capi/graphics/image-access-alpha.lisp

See also free-image-access

make-image-access

image-access-pixel

Function

Summary Gets and sets the pixels in an Image Access object.

Package graphics-ports

Signature image-access-pixel image-access $x \ y => color-rep$

(setf image-access-pixel) $color-rep\ image-access\ x\ y$ =>

color-rep

Arguments image-access An Image Access object

x An integer.

y An integer.

Values *color-rep* A color reference.

Description The function image-access-pixel returns the pixel value at

position x, y in the Image Access object image-access.

The pixel value *color-rep* is a color representation like that returned by convert-color. If needed, *color-rep* can be converted to an RGB value using unconvert-color. *color-rep* can contain an alpha value, for images with an alpha channel.

The function (setf image-access-pixel) sets the value of the pixel at position x, y in the Image Access object image-access.

image-access must be an Image Access object returned by

make-image-access.

Example See these example files:

examples/capi/graphics/image-access.lisp

examples/capi/graphics/image-access-alpha.lisp

See also image-access-pixels-from-bgra

image-access-pixels-to-bgra
image-access-transfer-to-image
image-access-transfer-from-image

free-image-access make-image-access

image-access-pixels-from-bgra

Function

Summary Copies a vector of pixel values into an Image Access object.

Package graphics-ports

Signature image-access-pixels-from-bgra image-access vector

Arguments image-access An Image Access object.

vector A vector.

Description The function image-access-pixels-from-bgra copies all

the pixels to the Image Access object *image-access* from the vector *vector*. *vector* should contain a sequence of integer values in the range 0-255 for blue, green, red and alpha of each pixel. This function is optimized for the case where *vector* has element type (unsigned-byte 8).

An error is signalled if *vector* is not of the correct length for the Image Access object, that is (* 4 *width height*) where

width and height represent the size of image-access.

Note: image-access-pixels-to-bgra must be called after this function (similarly to (setf image-access-pixel)).

image-access must be an Image Access object returned by

make-image-access.

Example See the file

examples/capi/graphics/image-access-bgra.lisp.

See also image-access-pixel

image-access-pixels-to-bgra

image-access-pixels-to-bgra

Function

Summary Copies pixel values from an Image Access object into a vec-

tor.

Package graphics-ports

Signature image-access-pixels-to-bgra image-access vector

Arguments image-access An Image Access object.

vector A vector.

Description The function image-access-pixels-to-bgra copies all the

pixels in the Image Access object *image-access* into the vector *vector* as a sequence of integer values in the range 0-255 for the blue, green, red and alpha components of each pixel. This function is optimized for the case where *vector* has element

type (unsigned-byte 8).

An error is signalled if *vector* is not of the correct length for the Image Access object, that is (* 4 *width height*) where *width* and *height* represent the size of *image-access*.

Note: image-access-pixels-from-bgra must be called before this function (similarly to image-access-pixel).

image-access must be an Image Access object returned by

make-image-access.

Example See the file

examples/capi/graphics/image-access-bgra.lisp.

See also image-access-pixel

image-access-pixels-from-bgra

image-access-transfer-from-image

Function

Summary Gets the pixel values from an image.

Package graphics-ports

Signature image-access-transfer-from-image image-access

Arguments image-access An Image Access object

Description

The function image-access-transfer-from-image gets the pixel values from an image object, making them accessible via a corresponding Image Access object *image-access*.

image-access must be an Image Access object returned by

make-image-access.

Notionally image-access-transfer-from-image transfers the pixel data from the window system into *image-access*, though it might do nothing on platforms where the window system allows direct access to the pixel data.

The pixel data can be accessed using image-access-pixel.

Example See the file

examples/capi/graphics/image-access.lisp.

See also image-access-transfer-to-image

> image-access-pixel free-image-access make-image-access

image-access-transfer-to-image

Function

Summary Sets the pixel values in an image.

Package graphics-ports

Signature image-access-transfer-to-image image-access

Arguments An Image Access object image-access

Description The function image-access-transfer-to-image sets the

> pixel values in an image object from the values in a corresponding Image Access object image-access.

image-access must be an Image Access object returned by

make-image-access.

Notionally image-access-transfer-to-image transfers the pixel data from *image-access to* the window system, though it might do nothing on platforms where the window

system allows direct access to the pixel data.

Example See the file

examples/capi/graphics/image-access.lisp.

See also free-image-access

image-access-transfer-from-image

image-access-pixel
make-image-access

image-freed-p Function

Summary Determines whether an image has been freed.

Package graphics-ports

Signature image-freed-p image => bool

Arguments image An image object.

Values *bool* A boolean.

Description The image-freed-p function returns non-nil if the image

has been freed, and nil otherwise.

image-loader Function

Summary Returns the image load function.

Package graphics-ports

Signature image-loader image-id &key image-translation-table => loader

Arguments image-id An image identifier.

image-translation-table

An image translation table.

Values *loader* An image load function.

Description The image-loader function returns the image load function

that would be called to load the image associated with *image-id* in *image-translation-table*. If the *image-id* is not registered with a load function, the default image load function is returned. The default value of *image-translation-table* is

default-image-translation-table.

See also register-image-load-function

register-image-translation

image-translation

Function

Summary Returns the translation for an image registered in its image

translation table.

Package graphics-ports

Signature image-translation image-id &key image-translation-table =>

translation

Arguments image-id An image identifier.

image-translation-table

An image translation table.

Values translation A translation.

2 GP Reference Entries

Description The image-translation function returns the translation for

image-id registered in image-translation-table. The default value
of image-translation-table is *default-image-translation-

table*.

See also register-image-load-function

register-image-translation

initialize-dithers Function

Summary Initialize dither objects up to a given order.

Package graphics-ports

Signature initialize-dithers & optional order

Arguments *order* An integer.

Description The initialize-dithers function initializes dither objects

up to the given order (size = 2 $^{\circ}$ order). By default, order is 3.

Note: dithers do not affect drawing or the anti-aliasing that

occurs when drawing in Cocoa.

See also dither-color-spec

make-dither with-dither

inset-rectangle

Function (inline)

Summary Moves the corners of a rectangle inwards by a given amount.

Package graphics-ports

Signature inset-rectangle rectangle dx dy &optional dx-right dy-bottom

Arguments rectangle A list of integers.

dx An integer.
dy An integer.
dx-right An integer.
dy-bottom An integer.

Description The inset-rectangle function moves the left, top, right and

bottom elements of *rectangle* inwards towards the center by the distances *dx*, *dy*, *dx-right* and *dy-bottom* respectively.

By default, *dx-right* is *dx*, and *dy-bottom* is *dy*.

inside-rectangle

Function

Summary Determines if a point lies inside a rectangle.

Package graphics-ports

Signature inside-rectangle rectangle $x \ y \Rightarrow result$

Arguments rectangle A list of integers.

x An integer.y An integer.

Values result A boolean.

Description The inside-rectangle function returns t if the point (x y) is

inside rectangle. The rectangle is expected to be ordered; if the rectangle is specified by (left top right bottom), then left must be less than right, and bottom must be less than top. The lines y = bottom and x = right are not considered to be inside

the rectangle.

invalidate-rectangle

Generic Function

Summary Invalidates the rectangle associated with the object, which

causes it to be redisplayed.

Package graphics-ports

Signature invalidate-rectangle object &optional x y width height =>

result

Arguments object An instance of a subclass of graphics-

ports-mixin or a subclass of pinboard-

object.

x A real number.

y A real number.

width A real number.

height A real number.

Values result A boolean.

Description By default, the generic function invalidate-rectangle

invalidates the whole rectangle, but this can be limited by

passing the optional arguments.

The effect of invalidating an area is to cause the area to be redrawn. It has no effect on pixmap-port. When the pane has a supplied display-callback, this callback is called with an area containing the area specified by the argument to invalidate-rectangle. However, the call to display-callback is asynchronous, and the system coalesces areas from calls to invalidate-rectangle and actual expose events, so there is not a one-to-one relation between calls to invalidate-rectangle and invocations of display-callback.

In general, invalidate-rectangle should not be called inside the *display-callback*. If it is called, it must be conditional, otherwise this will cause repeated redisplay.

Notes

With *drawing-mode*: quality, drawings are done with antialiasing, which means that they affect pixels which are not obviously part of the drawing. For example, drawing a rectangle with x = 10 may affect the pixel at x = 9. This needs to be taken into account when computing the arguments to invalidate-rectangle.

For pinboard objects the recommended way of forcing redraw is redraw-pinboard-object, which takes anti-

aliasing into account.

See also validate-rectangle

invert-transform Function

Summary Constructs the inverse of a transform.

Package graphics-ports

Signature invert-transform transform & optional into => inverse

Arguments transform A transform object.

into A transform object or nil.

Values inverse A transform object.

Description This function constructs the inverse of *transform*. If *T* is *trans-*

form and T is its inverse, then TT = I. If into is non-nil it is modified to contain T and returned, otherwise a new trans-

form is constructed and returned.

list-all-font-names Function

Summary Finds the names of the available fonts.

2 GP Reference Entries

Package graphics-ports

Signature list-all-font-names pane => fdescs

Arguments pane A graphics port.

Values *fdescs* A list of font description objects.

Description The function list-all-font-names returns a list of par-

tially-specified font description objects which contain the "name" attributes for each known font that is available for

pane.

On Microsoft Windows and Cocoa the "name" attributes are

just the :family attribute.

On X11 the "name" attributes are :foundry and :family.

See also font-description-attributes

find-matching-fonts

list-known-image-formats

Function

Summary Returns the known image formats.

Package graphics-ports

Signature list-known-image-formats screen-spec &optional for-writing-

too => formats

Arguments screen-spec A CAPI object, a plist, or nil.

for-writing-too A generalized boolean.

Values formats A list of keywords.

Description The function list-known-image-formats returns a list of

keywords which specify known image formats.

screen-spec is an object that convert-to-screen can recognize, typically a pane or simply nil.

If *for-writing-too* is not supplied or is nil, then *formats* is a list of formats that can be loaded. All the formats in the list can be loaded, but on Cocoa and Windows the list is not exhaustive, and it may be possible to load formats that are not listed.

If for-writing-too is supplied as non-nil, then formats is a list of types that externalize-and-write-image can write. In this case the list is exhaustive on all platforms, and external-ize-and-write-image can write a format if and only if it appears in the list.

All platforms (except Motif) can read and write :bmp, :jpg, :png and :tiff images, and also recognize :jpeg as an alias for :jpg, so the list will always include all of these keywords.

See also

convert-to-screen

externalize-and-write-image

load-icon-image

Function

Summary Loads a Windows icon image, and returns the image object.

Package graphics-ports

Signature load-icon-image port id &key width height => image

Arguments *port* A graphics port or CAPI object.

id A keyword, string or pathname.

width The desired width in pixels, or nil.

height The desired height in pixels, or nil.

Values image An image object.

Description

The load-icon-image function loads an icon specified by *id* which should be either a keyword describing a standard icon, or a string or a pathname naming a Windows format icon (.ico) file.

The following keyword values of *id* are recognized:

:sample A rectangle

:hand A cross in a circle

: ques A question mark in a bubble

:bang An exclamation mark in a triangle

:note An 'I' in a bubble

:winlogo The Windows logo

:warning Same as :bang

:error Same as :hand

:information

Same as :note

load-icon-image returns an image object which can be drawn to *port* using draw-image and which must be freed using free-image when no longer needed.

When *id* specifies a file and *width* and *height* are specified, then the most appropriate image is chosen from the icon file and is scaled accordingly. If *width* and *height* are nil the first image in the file is used at its natural size. *width* defaults to nil and *height* defaults to *width*.

Note: load-icon-image is defined only in LispWorks for Windows.

See also draw-image

free-image

load-image

load-image Function

Summary Loads an image and returns the image object.

Package graphics-ports

Signature load-image gp id &key cache type editable image-translation-table

=> image

Arguments *gp* A graphics port.

id An image identifier, a file, an external-

image, or an image.

cache A boolean.

type A keyword, or nil.

editable One of the keywords: with-alpha and

:without-alpha, or a boolean.

image-translation-table

An image translation table.

Values image An image object.

Description The load-image function loads an image identified by id via

the *image-translation-table* using the image load function registered with it. It returns an <code>image</code> object with the representation slot initialized. The *gp* argument specifies a graphics port used to identify the library. It also specifies the resource in which colors are defined and if necessary allocated for the image. If *id* is in the table but the translation is not an external image, and the image loader returns an external image as the second value, that external image replaces the translation in the table. The default value of *image-translation-table* is

default-image-translation-table.

id can be an image, which is just associated with the port gp and returned if it is a Plain Image or if editable is nil. Otherwise a new Plain Image object is returned, as described below.

id can also be a string or pathname denoting a file, and in this case the image is loaded according to type, as described below.

The *cache* argument controls whether the image translation is cached. See the convert-external-image function for more details.

type tells load-image that the image is in a particular graphics format. Currently the only recognised value is :bmp, which means the image is a Bitmap. Other values of type cause load-image to load the image according to the file type of id, if id denotes a file, as described for read-external-image. See the Graphics Ports chapter in the CAPI User Guide for a discussion of image handling. The default value of type is nil.

editable controls whether the image image is a Plain Image suitable for use with the Image Access API. The values of editable have the following effects:

nil The image is not editable.

:without-alpha

The image is editable, but does not have an alpha channel.

The image is editable, but does not have an t alpha channel if the source of the image has an alpha channel (for example, a TIFF file with alpha channel).

The image is editable and has an alpha :with-alpha channel. It will be fully opaque when loading files without an alpha channel.

Given an image my-image, call

(load-image port my-image :editable t)

to create an image guaranteed to work with make-image-access. The default value of *editable* is nil.

Normally the image is freed automatically, when *gp* is destroyed. However there are circumstances where you need to explicitly free an image, for example when you want it to go away before the port. If the image is not freed, a memory leak occurs.

Note: *gp* must already be created at the time <code>load-image</code> is called. If you need to delay loading the image, for example if you are computing the image dynamically, then you can call <code>load-image</code> in the *create-callback* of the port or even in its first <code>display-callback</code>.

Compatibility note

In LispWorks 4.4 there is a keyword argument :force-plain with the same effect as :editable. :force-plain is still accepted in LispWorks 6.1 for backwards compatibility, but you should now use :editable instead.

See also

convert-external-image
default-image-translation-table
load-icon-image
make-image

make-image-access

make-dither Function

Summary Makes a dither matrix of a given size.

Package graphics-ports

Signature make-dither size => matrix

Arguments *size* An integer.

Values *matrix* A dither matrix.

Description The make-dither function makes a dither matrix of the

given size.

Note: dithers do not affect drawing or the anti-aliasing that

occurs when drawing in Cocoa.

See also dither-color-spec

initialize-dithers

with-dither

make-font-description

Function

Summary Returns a new font description object containing given font

attributes.

Package graphics-ports

Signature make-font-description &rest font-attribute* => fdesc

Arguments font-attribute A font attribute.

Values *fdesc* A font description object.

Description The make-font-description function returns a new font

description object containing the given font attributes. There

is no error checking of the attributes at this point.

The :stock attribute is handled specially: it is omitted from

fdesc, unless it is the only attribute specified.

See also augment-font-description

convert-to-font-description

find-best-font

find-matching-fonts
font-description
merge-font-descriptions

make-graphics-state

Function

Summary Creates a graphics-state object.

Package graphics-ports

Signature make-graphics-state &key transform foreground background

operation thickness scale-thickness dashed dash line-end-style linejoint-style mask fill-style stipple pattern mask-x mask-y font textmode shape-mode compositing-mode mask-transform => state

Arguments See graphics-state for interpretation of the arguments.

ValueS state A graphics-state object.

Description The make-graphics-state function creates a graphics-

state object. Each graphics port has a graphics state associated with it, but you may want to create your own individual graphics states for use in specialized drawing operations. Graphics state objects do not consume local resources beyond dynamic memory for the structure (so you can be relaxed about creating them in some number if you really need to).

See also graphics-state

set-graphics-state

make-image Function

Summary Makes a new, empty, image object.

Package graphics-ports

Signature make-image port width height &key alpha => image

Arguments *port* A graphics port.

width A positive integer.height A positive integer.

alpha A generalized boolean.

Values image An image object.

Description The function make-image makes a new blank, editable image

object associated with port and of the given width and height.

On Windows and Cocoa, if alpha is true, then the image will

have an alpha channel.

The initial pixels in *image* are undefined. *image* is editable, that is, it is suitable for use with the Image Access API. To set

the pixels, see make-image-access.

See also load-image

make-image-access

make-image-access

Generic Function

Summary Creates an Image Access object.

Package graphics-ports

Signature make-image-access port image => image-access

Arguments *port* A graphics port.

image An image object.

Values image-access An Image Access object.

Description

The generic function make-image-access returns an Image Access object for the given image image.

image can be any image object returned by make-image-from-port. An image object returned by load-image is also suitable, but only if it is a Plain Image (see below).

image-access is used when reading and writing the pixel values of the image. For an overview of using Image Access objects, see the Graphics Ports chapter in the *CAPI User Guide*.

Note: on some platforms (currently Windows) not every image object is a Plain Image. If needed, forcibly create a Plain Image suitable for passing to make-image-access as described in load-image.

Note: ensure that you eventually discard *image-access*, using free-image-access.

Example

See the file

examples/capi/graphics/image-access.lisp.

See also

free-image-access

image-access-transfer-from-image
image-access-transfer-to-image

image-access-height
image-access-pixel

load-image
make-image

make-image-from-port

Function

Summary

Makes an image out of a specified rectangle of a graphics

port's contents.

Package

graphics-ports

Signature make-image-from-port port & optional x y width height => image

Arguments *port* A graphics port.

x An integer.
 y An integer.
 width An integer.
 height An integer.

Values *image* An image.

Description The make-image-from-port function makes an image out of

the specified rectangle of the port's contents. The default is the whole port, but a region can be specified using *x*, *y*, *width*,

and height. The default value of x and y is 0.

Normally the image is freed automatically, when *port* is destroyed. However there are circumstances where you need to explicitly free an image, for example when you want it to go away before the port. If the image is not freed, a memory

leak occurs.

See also externalize-image

make-sub-image Function

Summary Makes a new image from part of an image.

Package graphics-ports

Signature make-sub-image port image &optional x y width height

=> sub-image

Arguments *port* A graphics port.

image An image.

x An integer.

y An integer.

width An integer.

height An integer.

Values sub-image An image.

Description The function make-sub-image makes a new image object

from the rectangular region of the supplied image specified

by x, y, width and height.

The default values of x and y are 0.

The default value of width is the width of image.

The default value of *height* is the *height* of *image*.

See also image

make-transform Function

Summary Returns a new transform object initialized according to a set

of optional arguments.

Package graphics-ports

Signature make-transform & optional $a \ b \ c \ d \ e \ f \Rightarrow transform$

Arguments a A real number.

b A real number.

c A real number.

d A real number.

e A real number.

f A real number.

Values transform A transform object.

Description The make-transform function returns a new transform

object initialized according to the optional args. The default

args make the unit transform.

Default values are as follows: *a* and *d* are 1; *b*, *c*, *e*, and *f* are 0.

The transform matrix is

ab 0

c d (

e f 1

for generalized two dimensional points of the form $(x \ y \ 1)$.

Example This transform will cause rotation by pi/4 radians:

```
(let ((s (sin (/ pi 4)))
        (c (cos (/ pi 4))))
        (qp:make-transform c s (- s) c 0 0))
```

merge-font-descriptions

Function

Summary Returns a font description containing the attributes of two

specified font descriptions.

Package graphics-ports

Signature merge-font-descriptions fdesc1 fdesc2 => fdesc

Arguments *fdesc1* A font description.

fdesc2 A font description.

Values *fdesc* A font description.

Description The merge-font-description function returns a font

description containing all the attributes of *fdesc1* and *fdesc2*. If an attribute appears in both *fdesc1* and *fdesc2*, the value in

fdesc1 is used. The :stock attribute is handled specially: it is omitted from fdesc, unless it is the only attribute in fdesc1 and fdesc2.

The contents of *fdesc1* and *fdesc2* are not modified.

See also make-font-description

offset-rectangle

Function (inline)

Summary Offsets a rectangle by a given distance.

Package graphics-ports

Signature offset-rectangle rectangle dx dy

Arguments rectangle A list of integers.

dx A real number.

dy A real number.

Description The offset-rectangle function offsets the rectangle by the

distance (dx dy).

rectangle is a list (left top right bottom).

ordered-rectangle-union

Function

Summary Returns the union of two rectangles.

Package graphics-ports

Signature ordered-rectangle-union left-1 top-1 right-1 bottom-1

left-2 top-2 right-2 bottom-2
=> left, top, right, bottom

Arguments *left-1* A real number.

top-1	A real number.
right-1	A real number.
bottom-1	A real number.
left-2	A real number.
top-2	A real number.
right-2	A real number.
bottom-2	A real number.
left	A real number.
top	A real number.

Values

тор A real number. right A real number. A real number. bottom

Description

The ordered-rectangle-union function returns four values: the left, top, right and bottom of the union of the two rectangles specified in the arguments. The caller guarantees that each input rectangle is ordered, that is, the left values must be smaller or equal to the right values, and the top values must be greater than or equal to the bottom ones.

See also rectangle-union

Constant pi-by-2

Summary (/ pi 2) as a double-float.

Package graphics-ports

Description The constant pi-by-2 is the result of (/ cl:pi 2). It is a

cl:double-float.

See also 2pi

fpi

pixblt Function

Summary Copies one area of a graphics port to another area of a differ-

ent graphics port.

pixblt is deprecated.

Package graphics-ports

Signature pixblt to-port operation from-port to-x to-y width height from-x

from-y

Arguments *to-port* A graphics port.

operation A graphics state operation.

from-port A graphics port.

to-x A real number.

to-y A real number.

width A real number.

height A real number.

from-x A real number.

from-y A real number.

Description The pixblt function copies one area of from-port to another

area of *to-port* using the specified *operation* and *mask*. Both ports should be the same depth. The graphics port trans-

forms are not used.

operation is ignored when the drawing-mode is :quality (the default). See the "Graphics state" section in the CAPI User

Guide for valid values for operation.

pixblt is deprecated, because the :quality drawing-mode does not support operation, and because it ignores the transformations, which means it does not always work as expected. In particular, it can draw at the wrong place inside the display-callback of output-pane.

Use instead copy-area, which does take account of the transform. See also graphics-state parameter compositing-mode for a way to control how copy-area blends the source and the target.

See also copy-area

graphics-state

pixmap-port Class

Summary The class of pixmap graphics port objects.

Package graphics-ports

Description The pixmap-port class is the class of pixmap graphics port

objects which can be used for drawing operations.

See also create-pixmap-port

destroy-pixmap-port

with-pixmap-graphics-port

port-drawing-mode-quality-p

Generic Function

Summary Tests whether a port does quality drawing.

Package graphics-ports

Signature port-drawing-mode-quality-p port => result

Arguments *port* A graphics port.

Value result A boolean.

Description The generic function port-drawing-mode-quality-p

returns true if the graphics port port does quality drawing.

A port does quality drawing if both

1. it was not made with drawing-mode: compatible, and

2. the underlying library supports quality drawing.

Microsoft Windows and Cocoa always support quality drawing, GTK+ supports it from version 2.8 and greater, but Motif

never supports it.

ExampleS (example-file "capi/graphics/images-with-alpha")

See also Section "Drawing mode and anti-aliasing" in the CAPI User

Guide.

port-graphics-state

Function

Summary Returns the graphics-state object for a graphics port.

Package graphics-ports

Signature port-graphics-state port => state

Arguments *port* A graphics port.

Values state A graphics-state object.

Description The function port-graphics-state returns the graphics-

state object for *port*. The individual slots can be accessed using the accessor functions documented for graphics-

state.

See also graphics-state

port-height Function

Summary Returns the pixel height of a port.

Package graphics-ports

Signature port-height port => result

Arguments *port* A graphics port.

Values result An integer.

Description The function port-height returns the pixel height of port.

port-string-height

Function

Summary Returns the height of a string drawn to a given port in pixels.

Package graphics-ports

Signature port-string-height port string => height

Arguments *port* A graphics port.

string A string.

Values *height* An integer.

Description The port-string-height function returns the *height* in

pixels of *string* when drawn to *port*. The font used is the *font*

currently in the port's graphics-state.

port-string-width

Function

Summary Returns the width of a string drawn to a given port in pixels.

Package graphics-ports

Signature port-string-width port string => width

Arguments *port* A graphics port.

string A string.

Values width An integer.

Description The port-string-width function returns the width in pixels

of string when drawn to port. The font used is the font cur-

rently in the port's graphics-state.

Notes To compute the horizontal extents of each successive charac-

ter in a string for a given port or font, use compute-char-

extents.

See also compute-char-extents

port-width Function

Summary Returns the pixel width of a port.

Package graphics-ports

Signature port-width port => width

Arguments *port* A graphics port.

Values width An integer.

Description The function port-width returns the pixel width of *port*.

postmultiply-transforms

Function

Summary Postmultiplies two transforms.

Package graphics-ports

Signature postmultiply-transforms transform1 transform2

Arguments transform1 A transform object.

> transfrom2 A transform object.

Description The postmultiply-transforms function postmultiplies the

> partial 3 x 3 matrix represented by *transform1* by the partial 3 x 3 matrix represented by transform2, storing the result in *transform1*. In the result, the translation, scaling and rotation operations contained in transform2 are effectively performed

after those in transform1.

transform1 = transform1 . transform2

premultiply-transforms

Function

Summary Premultiplies two transforms.

Package graphics-ports

Signature premultiply-transforms transform1 transform2

Arguments transform1 A transform object.

> transform2 A transform object.

Description The premultiply-transforms function premultiplies the

> partial 3 x 3 matrix represented by transform 1 by the partial 3 x 3 matrix represented by *transform2*, storing the result in

transform1. In the result, the translation, scaling and rotation operations contained in *transform2* are effectively performed *before* those in *transform1*

transform1 = transform2 . transform1

read-and-convert-external-image

Function

Summary Returns an image converted from an external image read

from a file.

Package graphics-ports

Signature read-and-convert-external-image gp file &key transparent-

color-index => image, external-image

Arguments *gp* A CAPI pane.

file A pathname designator.

transparent-color-index

An integer or mil.

Values image An image.

external-image An external image.

Description Returns an image converted from an external image read

from file. The external image is returned as a second value.

transparent-color-index is interpreted as described for read-

external-image.

See also convert-external-image

external-image

read-external-image

read-external-image

Function

Summary Returns an external image read from a file.

Package graphics-ports

Signature read-external-image file &key transparent-color-index type =>

image

color.

Arguments *file* A pathname designator.

transparent-color-index

An integer or mil.

type A keyword, or nil.

Values image An external image.

Description The read-external-image function returns an external

image read from *file*.

transparent-color-index specifies the index of the transparent color in the color map. transparent-color-index works only for images with a color map, that is, those with 256 colors or less. The default value is nil, meaning that there is no transparent

type tells read-external-image that the image is in a particular graphics format. Currently the only recognised value is :bmp, which means the image is read as a Bitmap. Other values of type cause read-external-image to read the image according to the file type of file. "bmp" or "dib" mean that the image is read as a Bitmap. Other file types are handled in Operating System-specific ways. See the Graphics Ports chapter in the CAPI User Guide for details. The default value of type is zil

of *type* is nil.

Example To see the effect of *transparent-color-index*, edit

examples/capi/graphics/images.lisp.

Specify a non-white :background for the viewer pane. Use an image editing tool to find the transparent color index (183 in this image) and change the call to read-external-image like this:

(gp:read-external-image file :transparent-color-index
183)

Then compile and run the example, click the **Change...** button and select the **Setup.bmp** file.

See also external-image

rectangle-bind Macro

Summary Binds four variables to the corners of a rectangle across a

body of code.

Package graphics-ports

Signature rectangle-bind ((abcd) rectangle) &body body => result

Arguments *a* A variable.

b A variable.c A variable.

d A variable.

rectangles A rectangle.

body A body of code.

Values result The return value of the last form in body.

Description The rectangle-bind macro binds the variables $a\ b\ c\ d$ to left

top right bottom of rectangle for the body of the macro.

rectangle-bottom

Macro

Summary Get and sets the *bottom* element of a rectangle.

Package graphics-ports

Signature rectangle-bottom rectangle => bottom

Signature (setf rectangle-bottom) bottom rectangle => bottom

Arguments rectangle A rectangle.

Values *bottom* A real number.

Description Returns and via setf sets the *bottom* element of *rectangle*.

rectangle is a list of numbers (left top right bottom).

rectangle-height

Macro

Summary Returns the *height* element of a rectangle.

Package graphics-ports

Signature rectangle-height rectangle => height

Arguments rectangle A rectangle.

Values *height* A real number.

 ${\hbox{\tt Description}} \qquad {\hbox{\tt The}} \ {\hbox{\tt rectangle-height}} \ {\hbox{\tt macro}} \ {\hbox{\tt returns}} \ {\hbox{\tt the}} \ {\hbox{\tt difference}}$

between the *bottom* and *top* elements of *rectangle*.

rectangle is a list of numbers (*left top right bottom*).

rectangle-left Macro

Summary Gets and set the *left* element of a rectangle.

Package graphics-ports

Signature rectangle-left rectangle => left

Signature (setf rectangle-left) left rectangle => left

Arguments rectangle A rectangle.

Values *left* A real number.

Description The rectangle-left macro returns and via setf sets the *left*

element of rectangle.

rectangle is a list of numbers (left top right bottom).

rectangle-right Macro

Summary Gets aand sets the *right* element of a rectangle.

Package graphics-ports

Signature rectangle-right rectangle => right

Signature (setf rectangle-right) right rectangle => right

Arguments rectangle A rectangle.

Values right A real number.

Description The rectangle-right macro returns and via setf sets the

right element of rectangle.

rectangle is a list of numbers (left top right bottom).

rectangle-top Macro

Summary Gets and sets the *top* element of a rectangle.

Package graphics-ports

Signature rectangle-top rectangle => top

Signature (setf rectangle-top) top rectangle => top

Arguments rectangle A rectangle.

Values top A real number.

Description The rectangle-top macro returns and via setf sets the top

element of rectangle.

rectangle is a list of numbers (left top right bottom).

rectangle-union

Function

Summary Returns the four values representing a union of two rectan-

gles.

Package graphics-ports

Signature rectangle-union left-1 top-1 right-1 bottom-1

left-2 top-2 right-2 bottom-2 => left, top, right, bottom

Arguments *left-1* A real number.

top-1 A real number.
right-1 A real number.

bottom-1 A real number.

left-2 A real number.

top-2 A real number.

right-2 A real number.

bottom-2 A real number.

Values *left* A real number.

top A real number.

right A real number.

bottom A real number.

Description The rectangle-union function returns four values: the *left*,

top, *right* and *bottom* of the union of the two rectangles specified in the arguments. The values input for the two rectangles

are ordered by this function before it uses them.

See also ordered-rectangle-union

rectangle-width Macro

Summary Returns the difference between the *left* and *right* elements of a

rectangle.

Package graphics-ports

Signature rectangle-width rectangle => width

Arguments rectangle A rectangle

Values width A real number

Description The rectangle-width macro returns the difference between

right and left elements of rectangle.

rectangle is a list of numbers (left top right bottom).

rect-bind Macro

Summary Binds four variables to the elements of a rectangle across a

body of code.

Package graphics-ports

Signature rect-bind ((x y width height) rectangle) &body body => result

Arguments x A variable.

y A variable.
 width A variable.
 height A variable.
 rectangle A rectangle.

body A body of Lisp code.

Values result The return value of the last form in body.

Description The rect-bind macro binds x y width height to the appropri-

ate values from *rectangle* and executes the *body* forms. The

rectangle is a list of the form (left top right bottom).

register-image-load-function

Function

Summary Registers one or more image identifiers with an image load-

ing function.

Package graphics-ports

Signature register-image-load-function image-id image-load-function

&key image-translation-table

Arguments image-id An image identifier or a list of image identi-

fiers.

image-load-function

A function.

image-translation-table

An image translation table.

Description

The register-image-load-function function registers one or more *image-ids* with an *image-load-function* in the *image-translation-table*. If *image-load-function* is nil it causes the default loader to be used in subsequent calls to load-image. The *image-id* argument can be a list of identifiers or a single identifier. The default value of *image-translation-table* is

default-image-translation-table.

See also

default-image-translation-table

load-image

register-image-translation

Function

Summary Registers an image identifier and image loading function

with a translation in an image translation table.

Package graphics-ports

Signature register-image-translation image-id translation &key

image-translation-table image-load-fn

Arguments image-id An image identifier.

translation An image translation.

image-translation-table

An image translation table.

image-load-fn An image loading function.

Description

The register-image-translation function registers image-id and image-load-fn with the translation in the image-translation-table. When load-image is called with second argument image-id, the image-load-fn is called with translation as its second argument. If image-load-fn is nil, the image translation table's default image loader is used; this converts an external image object or file to an image. If translation is nil the identifier is deregistered. Returns the image-id and the image-load-fn. The default value of image-translation-table is *default-image-translation-table*.

actuate image cranbiactor

See also

default-image-translation-table

load-image

reset-image-translation-table

reset-image-translation-table

Function

Summary Clears the image translation table hash tables.

Package graphics-ports

Signature reset-image-translation-table &key image-translation-table

Arguments image-translation-table

An image translation table.

Description The reset-image-translation-table function clears the

image translation table hash tables and set the default *image-load-fn* to read-and-convert-external-image. The default value of *image-translation-table* is *default-image-transla-

tion-table*.

See also *default-image-translation-table*

read-and-convert-external-image

register-image-translation

separation Function

Summary Returns the distance between two points.

Package graphics-ports

Signature separation x1 y1 x2 y2 => dist

Arguments x1 An integer.

y1 An integer.x2 An integer.y2 An integer.

Values dist A real number.

Description The separation function returns the distance between

points $(x1 \ y1)$ and $(x2 \ y2)$.

set-default-image-load-function

Function

Summary Sets the default image load function of an image translation

table.

Package graphics-ports

Signature set-default-image-load-function image-load-function

&key image-translation-table

Arguments image-load-function

An image load function.

image-translation-table

An image translation function.

Description

The set-default-image-load-function function sets the default image load function of *image-translation-table*. The default image load function is read-and-convert-external-image. The default value of *image-translation-table* is *default-image-translation-table*.

set-graphics-port-coordinates

Function

Summary Modifies the transform of a port such that the edges of the

port correspond to the arguments given.

Package graphics-ports

Signature set-graphics-port-coordinates port &key left top right

bottom

Arguments *port* A graphics port.

left A real number.

top A real number.

right A real number

bottom A real number.

Description The generic function set-graphics-port-coordinates

modifies the transform of the graphics port port permanently such that the edges of port correspond to the values of the

other arguments.

Example The following code

:bottom -1.0)

changes the coordinates of the port so that the point (0 0) is in the exact center of the port and the edges are a unit distance away, with a right-handed coordinate system.

By default, left and top are 1.

set-graphics-state

Function

Summary Directly alters the graphics-state of a graphics port

according to the keyword arguments supplied.

Package graphics-ports

Signature set-graphics-state port &rest args &key transform foreground

background operation stipple pattern fill-style thickness scalethickness dashed dash line-end-style line-joint-style mask mask-x mask-y font shape-mode text-mode compositing-mode mask-

transform

Arguments *port* A graphics port.

Description The function set-graphics-state directly alters the graph-

ics state of *port* according to the values of the keyword arguments *args*. Unspecified keywords leave the associated slots

unchanged.

See graphics-state for valid values for args.

See also graphics-state

with-graphics-state

transform Type

Summary The transform type, defined for transform objects.

Package graphics-ports

Description The transform type is the type defined for transform objects,

which are six-element lists of numbers.

See also graphics-port-transform

transform-area Function

Summary Transforms a set of points and returns the resulting rectangle.

Package graphics-ports

Signature transform-area transform x y width height => rectangle

Arguments transform A transform.

x A real number.

y A real number.

width A real number.

height A real number.

Values rectangle A rectangle.

Description The transform-area function transforms the points (x y)

and (x+width y+height) and returns the transformed rectangle

as (x y width height) values.

transform-distance Function

Summary Transforms a distance vector by the rotation and scale of a

transform.

Package graphics-ports

Signature transform-distance transform $dx dy => dx^2$, dy^2

Arguments *transform* A transform.

dx A real number.

dy A real number.

Values dx^2 A real number.

dy2 A real number.

Description The transform-distance function transforms the distance

(dx dy) by the rotation and scale in the *transform*. The transla-

tion in the transform is ignored. Transformed $(dx\ dy)$ is

returned as two values.

transform-distances

Function

Summary Transforms a list of alternating distance vectors by a given

transform.

Package graphics-ports

Signature transform-distances transform distances => result

Arguments *transform* A transform.

distances A list of pairs of real numbers.

Values result A list of pairs of real numbers.

Description The transform-distances function transforms a list of

alternating (dx dy) pairs in distances by the transform. Trans-

formed values are returned as a new list.

transform-is-rotated

Function

Summary Returns t if a given transform contains a rotation.

Package graphics-ports

Signature transform-is-rotated transform => bool

Arguments transform A transform.

Values *bool* A boolean.

Description The transform-is-rotated function returns t if transform

contains any rotation.

transform-point

Function

Summary Transforms a point by multiplying it by a transform.

Package graphics-ports

Signature transform-point transform $x \ y => xnew \ ynew$

Arguments transform A transform.

x A real number.

y A real number.

Values *xnew* A real number.

ynew A real number.

Description The transform-point function transforms the point (x y) by

multiplying it by *transform*. The transformed (x y) is returned

as two values.

transform-points

Function

Summary Transforms a list of points by a transform.

Package graphics-ports

Signature transform-points transform points & optional into => result

Arguments *transform* A transform.

points A list of pairs of real numbers.

into A list.

Values result A list of pairs of real numbers.

Description The transform-points function transforms a list of alternat-

ing (*x y*) pairs in *points* by the *transform*. If *into* is supplied it is modified to contain the result and must be a list the same length as *points*. If *into* is not supplied, a new list is returned.

transform-rect Function

Summary Returns the transform of two points representing the top-left

and bottom-right of a rectangle.

Package graphics-ports

Signature transform-rect transform left top right bottom =>

left2 top2 right2 bottom2

Arguments transform A transform.

left A real number.

top A real number.

right A real number.

bottom A real number.

Values *left2* A real number.

top2 A real number.

right2 A real number.

bottom2 A real number.

Description The transform-rect function transforms the rectangle rep-

resented by the two points (left top) and (right bottom) by

transform.

undefine-font-alias

Function

Summary Removes a font alias.

Package graphics-ports

Signature undefine-font-alias keyword

Arguments *keyword* A keyword.

Description The undefine-font-alias function removes the font alias

named by keyword.

union-rectangle

Macro

Summary Modifies a rectangle to be a union of itself and another rect-

angle.

Package graphics-ports

Signature union-rectangle rectangle left top right bottom => rectangle

Arguments rectangle A rectangle.

left A real number.
right A real number.

top A real number.

bottom A real number.

Values rectangle A rectangle.

Description The union-rectangle macro modifies the rectangle to be the

union of rectangle and (left top right bottom).

unit-transform Variable

Summary The list (1 0 0 1 0 0).

Package graphics-ports

Signature *unit-transform*

Description The *unit-transform* variable holds the list (1 0 0 1 0

0) which is the unit transform I, such that X = XI, where X is a 3-vector. Graphics ports are initialized with the unit transform in their graphics-state. This means that port coordi-

nate axes are initially the same as the window axes.

unit-transform-p

Function

Summary Returns t if a given transform is a unit transform.

Package graphics-ports

Signature unit-transform-p transform => bool

Arguments transform A transform.

Values bool A boolean.

Description The unit-transform-p returns t if transform is the unit

transform.

unless-empty-rect-bind

Macro

Summary Binds the elements of a rectangle to four variables, and if the

rectangle has a non-zero area, executes a body of code.

Package graphics-ports

Signature unless-empty-rect-bind ((x y width height) rectangle)

&body body => result

Arguments x A variable.

y A variable.

width A variable.

height A variable.

rectangle A rectangle.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description The unless-empty-rect-bind macro binds x, y, width, and

height to the appropriate values from rectangle and if the width

and *height* are both positive, executes the *body* forms.

untransform-distance

Function

Summary Transforms a distance by the rotation and scale of the inverse

of a given transform.

Package graphics-ports

Signature untransform-distance transform dx dy => x, y

Arguments transform A transform.

dx A real number.

dy A real number.

Values x A real number.

y A real number.

Description The untransform-distance function transform the distance

 $(dx\ dy)$ by the rotation and scale of the effective inverse of *transform*. The translation in the inverse transform is ignored. The transformed distance $(dx\ dy)$ is returned as two values.

untransform-distances

Function

Summary Transforms a list of integer pairs representing distances by

the inverse of a transform.

Package graphics-ports

Signature untransform-distances transform distances => result

Arguments *transform* A transform.

distances A list of pairs of real numbers.

Values result A list of pairs of real numbers.

Description The untransform-distances function transforms a list of

alternating (*dx dy*) pairs in *distances* by the effective inverse of *transform*. Transformed values are returned as a new list.

untransform-point

Function

Summary Transforms a point by multiplying it by the inverse of a given

transform.

2 GP Reference Entries

Package graphics-ports

Signature untransform-point transform $x y \Rightarrow x^2$, y^2

Arguments transform A transform.

x A real number.

y A real number.

Values x^2 A real number.

y2 A real number.

Description The untransform-point function transform the point (x y)

by effectively multiplying it by the inverse of transform. The

transformed (x y) is returned as two values.

untransform-points

Function

Summary Transforms a list of points by the inverse of a given trans-

form.

Package graphics-ports

Signature untransform-points transform points &optional into => result

Arguments *transform* A transform.

points A list of pairs of real numbers.

into A list.

Values result A list of pairs of real numbers.

Description The untransform-points function transforms a list of alter-

nating (*x y*) pairs in *points* by the effective inverse of *trans-form*. If *into* is supplied it must be a list the same length as

points. If *into* is not supplied, a new list is returned.

validate-rectangle

Generic Function

Summary Validates the rectangle associated with the object, marks it as

already drawn.

Package graphics-ports

Signature validate-rectangle object &optional x y width height =>

result

Arguments object An instance of a subclass of graphics-

ports-mixin or a subclass of pinboard-

object.

x A real number.

y A real number.

width A real number.

height A real number.

Values result A boolean.

Description The given area of *object* is marked as not needing to be dis-

played. This can be useful if you want to draw that area immediately and avoid it being drawn again by the window system. By default it validates the whole rectangle, but this

can be limited by passing the &optional arguments.

The result is non-mil if the function succeeds and mil if it

fails (doing nothing).

Notes validate-rectangle is not fully implemented on all plat-

forms.

On Windows, it succeeds for all valid values of *x*, *y*, *width* and

height.

On Cocoa, it fails if x, y, width and height are passed.

On Motif, it fails in all cases.

See also invalidate-rectangle

with-dither Macro

Summary Specifies a dither for use within a specified body of code.

Package graphics-ports

Signature with-dither (dither-or-size) &body => result

Arguments *dither-or-size* See Description.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description The with-dither function specifies a dither for use within

body. The dither-or-size argument can be a dither mask object from make-dither or a size, in which case a dither of that

size is created.

Note: dithers do not affect drawing or the anti-aliasing that

occurs when drawing in Cocoa.

See also dither-color-spec

make-dither

initialize-dithers

with-graphics-mask

Macro

Summary Binds the *mask* slot of a port's graphics state across the execu-

tion of a body of code.

Package graphics-ports

Signature

with-graphics-mask (port mask &key mask-x mask-y mask-transform) &body body => result

Arguments

port A graphics port.

mask nil or a list specifying a shape.

mask-x An integer. This argument is deprecated.

mask-y An integer. This argument is deprecated.

mask-transform nil, t, the keyword :dynamic, or a trans-

form.

body A body of Lisp code.

Values result

The return value of the last form executed in

body.

Description

The macro with-graphics-mask binds the mask slot of port's graphics-state while evaluating body. The mask can be a rectangular area specified by a list of the form (x y width height) or a path specified by a list of the form (:path path :fill-rule).

mask-x and mask-y are deprecated. They work only when the drawing-mode is :compatible and the platform is GTK+ or X11/Motif. By default, mask-x and mask-y are both 0.

The mask-transform argument is used to set the mask-transform graphics state parameter. If mask-transform is nil, then the mask is not transformed. If mask-transform is t, then the mask is transformed by the current graphics state transform at the time that with-graphics-mask is used. If mask-transform is :dynamic, then the mask is transformed by the graphics state transform that is in effect when the drawing operation uses the mask. Otherwise mask-transform should be a transform object. The default value of the mask-transform argument is nil.

Examples

This example file demonstrates the use of *mask-transform*:

examples/capi/graphics/paths.lisp

See also graphics-state

with-graphics-post-translation

Macro

Summary Like with-graphics-translation except that the transla-

tion is done after applying all existing transforms.

Signature with-graphics-post-translation (port dx dy) &body body =>

result

Arguments *port* A graphics port.

dx A real number.

dy A real number.

body Lisp forms.

Values result The value returned by the last form of body.

Description The macro with-graphics-post-translation is the same

as with-graphics-translation, but the translation is done after applying all existing transforms. That means that the translation is "absolute", not transformed. In contrast, when using with-graphics-translation the translation is trans-

formed by any existing transform(s).

Examples This form draws a 40x40 rectangle at (100,100), because the

scale is applied to the coordinates of the rectangle, but not to

the translation.

Compare with this form, using with-graphics-translation instead, which draws a 40x40 rectangle at (200,200), because the scale applies to the translation too:

See also with-graphics-transform-reset

with-graphics-translation

with-graphics-rotation

Macro

Summary Performs a call to apply-rotation with a given angle for the

duration of the macro's body.

Package graphics-ports

Signature with-graphics-rotation (port angle) &body => result

Arguments *port* A graphics port.

angle A real number.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description The with-graphics-rotation macro performs a call to

(apply-rotation transform angle)

on the port's transform for the duration of the body of the

macro.

angle is in radians. If angle is positive, then the rotation is

clockwise.

Examples examples/capi/graphics/catherine-wheel.lisp

See also apply-rotation

with-graphics-scale

Macro

Summary Performs a call to apply-scale with a given scale for the

duration of the macro's body.

Package graphics-ports

Signature with-graphics-scale (port sx sy) &body body => result

Arguments *port* A graphics port.

sx A real number.sy A real number.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description The with-graphics-scale macro performs a call to

(apply-scale transform sx sy)

on the port's transform for the duration of the body of the

macro.

See also apply-scale

with-graphics-state

Macro

Summary Binds the graphics state values of a port to a list of arguments

and executes a body of code.

Package graphics-ports

Signature

with-graphics-state (port &rest args &key transform foreground background operation thickness scale-thickness dashed dash line-end-style line-joint-style mask font state fill-style stipple pattern mask-x mask-y shape-mode text-mode compositing-mode mask-transform) body => result

Arguments

port A graphics port.

body A body of Lisp code.

Values

result The return value of the last form executed in

body.

Description

The with-graphics-state macro binds the graphics state values for the specified port to the values specified in the args list. The keyword arguments args correspond to the slots in the graphics state, as described in graphics-state.

For example:

Arguments that are not supplied default to the current state of that slot in the graphics-state. The arguments *fill-style* and *stipple* are used only on Unix.

mask-x and mask-y are deprecated. They work only when the drawing-mode is :compatible and the platform is GTK+ or X11/Motif.

An extra keyword argument :state can be used. The value must be a graphics-state object created by a call to makegraphics-state. The contents of the graphics-state object passed are used instead of the port's state.

```
Example
```

```
(setf gstate (make-graphics-state))
(setf (graphics-state-foreground gstate) my-color)
(with-graphics-state (port :state gstate)
    (draw-rectangle port image-1 100 100))
```

See also graphics-state

set-graphics-state

with-graphics-translation

with-graphics-post-translation

with-graphics-scale with-graphics-rotation with-graphics-transform

with-graphics-transform-reset

with-graphics-mask

with-graphics-transform

Macro

Summary Combines a given transform with the transform of a port for

the duration of the macro.

Package graphics-ports

Signature with-graphics-transform (port transform) &body body

=> result

Arguments *port* A graphics port.

transform A transform.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description The with-graphics-transform macro combines the trans-

form associated with the graphics port *port* with *transform* during the body of the macro. The port is given a new transform obtained by pre-multiplying its current transform with *transform*. This has the effect of *preceding* any translation, scaling and rotation operations specified in the body of the

macro by those operations embodied in transform.

with-graphics-transform-reset

Macro

Summary Like with-graphics-transform except that it ignores exist-

ing transforms.

Signature with-graphics-transform-reset (port &optional transform)

&body body => result

Arguments *port* A graphics port.

transform A transform.

body Lisp forms.

Values result The value returned by the last form of body.

Description The macro with-graphics-transform-reset works the

same as with-graphics-transform except that it ignores

existing transforms.

If the argument *transform* is nil, the *body* is applied without

transform (that is, with the unit transform).

Examples This form ignores the translation, and applies only the

explicit transform (which is really just scale), so that the over-

all effect is to draw a 30x20 rectangle at (0,0).

(gp:with-graphics-translation (port 100 100)

(gp:with-graphics-transform-reset (port (gp:maketransform 3 0 0 2 0 0))

(gp:draw-rectangle port 0 0 10 10)))

(gp.draw-rectangle port 0 0 10 10)))

Compare with using with-graphics-transform, which applies both the translation and the explict transform, so that the overall effect is to draw a rectangle 30x20 at (100,100).

```
(gp:with-graphics-translation (port 100 100)
  (gp:with-graphics-transform (port (gp:make-transform
3 0 0 2 0 0 ))
        (gp:draw-rectangle port 0 0 10 10)))
```

See also with-graphics-post-translation

with-graphics-transform

with-graphics-translation

Macro

Summary Applies a translation to a given port for the duration of the

macro.

Package graphics-ports

Signature with-graphics-translation (port dx dy) &body body => result

Arguments *port* A graphics port.

dx A real number. dy A real number.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description The with-graphics-translation macro performs a call to

(apply-translation transform dx dy)

on the port's transform for the duration of body of the macro.

Examples examples/capi/graphics/catherine-wheel.lisp

with-inverse-graphics

Macro

Summary Executes all drawing function calls to a given port within the

body of the macro with foreground and background colors

swapped.

Package graphics-ports

Signature with-inverse-graphics (port) &body body => result

Arguments *port* A graphics port.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description The macro with-inverse-graphics ensures that all draw-

ing function calls to *port* within the body of the macro are executed with the *foreground* and *background* slots of the

graphics-state of port swapped.

without-relative-drawing

Macro

Summary Evaluates a body of Lisp code with the *relative* and *collect*

internal variables of the port set to mil.

Package graphics-ports

Signature without-relative-drawing (port) &body => result

Arguments *port* A graphic port.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description

The with-relative-drawing macro evaluates the code in body with the relative and collect internal variables of the pixmap graphics port port set to nil to turn off the port's collecting of drawing bounds and automatic shifting of its origins. Use this macro only within a with-pixmap-graphics-port macro.

with-pixmap-graphics-port

Macro

Summary Binds a port to a new pixmap graphics port for the duration

of the macro's code body.

Package graphics-ports

Signature with-pixmap-graphics-port (port pane width height &key

background collect relative clear drawing-mode)

&body body) => result

Arguments *port* A graphics port.

pane An output pane.

width An integer.height An integer.

background A color keyword.

collect A boolean.
relative A boolean.

clear A list or t.

drawing-mode One of the keywords:compatible and

:quality.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description

The with-pixmap-graphics-port macro binds *port* to a new pixmap graphics-port. *pane* and the other arguments are passed to create-pixmap-port. The *body* is then evaluated. The port is destroyed when *body* returns.

The *background* and *foreground* default to the values in the graphics state of *pane*.

Example

In the code below the background in *p2* inherits from *p1*, so it draws two green rectangles.

with-transformed-area

Macro

Summary

Transforms a rectangle using a port's transform, and binds the resulting values to a variable across the evaluation of the macro's body.

Package

graphics-ports

Signature

with-transformed-area (points port left top right bottom) &body body

Arguments

points A variable.

port A graphics port.

left A real number.

top A real number.

right A real number.

bottom A real number.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description The with-transformed-area macro transforms a rectangle,

binding the resulting four corner points to *points* for the duration of *body*. The *left top right bottom values* represent a rectangular area bounded by four points. The four points are transformed by the *port*'s transform and the list of eight values (alternating *x* and *y* values for four points) bound to the *points* variable for the duration of the macro body.

with-transformed-point

Macro

Summary Binds a point transformed by a given ports transform to two

variables across the body of the macro.

Package graphics-ports

Signature with-transformed-point (new-x new-y port x y) &body body

=> result

Arguments *new-x* A variable.

new-y A variable.

port A graphics port.

x A real number.

y A real number.

body A body of Lisp code.

Values result The return value of the last form executed in

body.

Description

The with-transformed-point macro transforms the point given by (*x y*) using the *port*'s transform and the resulting values are bound to the *new-x* and *new-y* variables. The *body* of the macro is then evaluated with this binding.

with-transformed-points

Macro

Summary Binds a list of transformed points in a port to a list across the

execution of the macro's body.

Package graphics-ports

Signature with-transformed-points (points port) &body body => result

Arguments *points* A list of real numbers.

port A graphics port.

Values result The return value of the last form executed in

body.

Description The with-transformed-points macro binds points to a new

list of *x* and *y* values obtained by post-multiplying them by the current transform of *port*, and then evaluates *body*. The *points* symbol must be bound to a list of alternating *x* and *y*

values representing coordinate points in the *port*.

with-transformed-rect

Macro

Summary Transforms the coordinates of a rectangle and binds them to

four variables for the duration of the macro's body.

Package graphics-ports

Signature with-transformed-rect (nx1 ny1 nx2 ny2 port x1 y1 x2 y2)

&body body => result

2 GP Reference Entries

Arguments	nx1	A variable.
	ny1	A variable.
	nx2	A variable.
	ny2	A variable.
	port	A graphics port.
	x1	A real number.
	y1	A real number.
	x2	A real number.
	<i>y2</i>	A real number.
	body	A body of Lisp code.

Values result The return value of the last form executed in body.

Do

During the evaluation of the with-transformed-rect macro *body*, the two points (*x1*, *y1*) and (*x2*, *y2*) are transformed by the port's current transform and the resulting values bound to the variables named by the *nx1 ny1 nx2 ny2* args.

write-external-image

Description

Function

Summary Writes external image data to a file.

Package graphics-ports

Signature write-external-image external-image file &key if-exists

Arguments external-image An external-image.

file A file.

if-exists A keyword.

Description The write-external-image function writes an external

image to a file file. It writes the image data byte-for-byte with-

out attempting any conversion of the image format.

if-exists is passed to open when opening file. The default

value of if-exists is :error.

See also externalize-image

3

COLOR Reference Entries

This chapter describes symbols available in the color package.

apropos-color-alias-names

Function

Summary Returns color aliases containing a given string.

Package color

Signature apropos-color-alias-names substring => list

Arguments *substring* A string.

Values list A list of symbols.

Description Returns a list of symbols whose symbol-names contain *sub*-

string and which are defined as aliases in the color-database defining color aliases. By convention these are in the key-

word package.

Example

In this example, a color alias is defined for the color indianred1. apropos-color-alias-names only returns this alias, rather than both the alias and the original color, despite the similarity in the names.

COLOR 8 > (define-color-alias :myindianred1 :indianred1)
(#S(COLOR-ALIAS COLOR :INDIANRED1))

COLOR 9 > (apropos-color-names "INDIANRED1")
(:INDIANRED1 :MYINDIANRED1)

COLOR 10 > (apropos-color-alias-names "INDIANRED1")
(:MYINDIANRED1)

COLOR 11 >

See also

apropos-color-names

apropos-color-spec-names
get-all-color-names

apropos-color-names

Function

Summary Returns colors and color aliases containing a given string.

Package color

Signature apropos-color-names substring => list

Arguments *substring* A string.

Values *list* A list of symbols.

Description Returns a list of symbols whose symbol-names contain *sub*-

string and which are present in the color-database defining color aliases. By convention these are in the keyword pack-

age.

apropos-color-spec-names

Function

Summary Returns colors containing a given string.

Package color

Signature apropos-color-spec-names substring => list

Arguments *substring* A string.

Values list A list of symbols.

Description Returns a list of symbols whose symbol-names contain *sub-*

string and which are defined as original entries in the colordatabase defining color aliases. By convention these are in

the keyword package.

Example coLor 14 > (define-color-alias :mygray100 :gray100)

(#S(COLOR-ALIAS COLOR :GRAY100))

COLOR 15 > (apropos-color-names "GRAY100")
(:MYGRAY100 :GRAY100)

COLOR 16 > (ap]ropos-color-spec-names "GRAY100")
(:GRAY100)

COLOR 17 >

3 COLOR Reference Entries

See also apropos-color-alias-names

apropos-color-names
get-all-color-names

color-alpha Function

Summary Returns the alpha component of a color specification.

Package color

Signature color-alpha color-spec & optional default => alpha

Arguments *color-spec* A color specification.

default A number between 0 and 1.

Values alpha The alpha component of color-spec.

Description *color-spec* is a color specification in any model.

color-alpha returns the alpha component of *color-spec*. If *color-spec* does not have an alpha component, then *default* is

returned.

The default value of *default* is 1.0.

See also make-hsv

make-rgb make-gray

color-<component>

Function

Summary Returns the associated component of a color specification.

Package color

Signature

color-red color-spec => color-component
color-green color-spec => color-component
color-blue color-spec => color-component
color-hue color-spec => color-component
color-saturation color-spec => color-component

color-saturation color-spec => color-component
color-value color-spec => color-component

Arguments

color-spec

A color specification.

Values

color-component A color component from the appropriate color model.

Description

If *color-spec* is not from the appropriate color model (:rgb in the case of color-red, color-green and color-blue, and :hsv in the case of color-hue, color-saturation and color-value) then the component is calculated.

Example

```
COLOR 31 > (color:make-rgb 1.0s0 0.0s0 0.0s0)
#(:RGB 1.0s0 0.0s0 0.0s0)

COLOR 32 > (color-red *)
1.0s0

COLOR 33 > (color-green **)
0.0s0

COLOR 34 > (color-value ***)
1.0s0

COLOR 35 >

make-hsv
```

See also

make-rgb
make-gray
color-model
color-level

color-database

Variable

Summary The current color-database.

3 COLOR Reference Entries

Package color

Description This should contain definitions for all the colors used in the

environment when you start it. Those colors are determinable

from the file config/colors.db.

Example To replace the current color database with a new one, do the

following:

(setf color:*color-database* (color:make-color-db))

See also delete-color-translation

read-color-db

load-color-database

color-level Function

Summary Returns the gray level of a color specification.

Package color

Signature color-level color-spec => gray-level

Arguments *color-spec* A color specification.

Values gray-level Color component from the :gray model.

Description Return the gray level of *color-spec*. If *color-spec* is not from the

:GRAY model, the component is calculated.

Example coLor 2 > (color:make-gray 0.66667s0)

#(:GRAY 0.66667S0)

COLOR 3 > (color-level *)

0.6666750

COLOR 4 >

See also make-hsv

make-rgb
make-gray
color-model

color-<component>

color-model Function

Summary Returns the color-model for a color-spec.

Package color

Signature color-model color-spec => color-model

Arguments *color-spec* A color specification.

Values color-model :gray, :rgb, or :hsv.

Example color 29 > (color:make-gray 0.66667s0)

#(:GRAY 0.66667S0)

COLOR 30 > (color-model *)

:GRAY

COLOR 31 >

See also make-hsv

make-rgb make-gray

color-<component>

color-level

color-with-alpha

Function

Summary Adds a specified alpha component to a color.

Package graphics-ports

3 COLOR Reference Entries

Signature color-with-alpha color alpha => color-spec

Arguments *color* A color specification.

alpha A real in the inclusive range [0,1].

Values color-spec A color specification, or nil.

Description The function color-with-alpha returns a color like the

argument color but with alpha component alpha.

color needs to be a color specification, either a keyword
naming a color (a member of the result of calling get-allcolor-names), or a color-spec (for example the result of

make-rgb).

alpha must be a real in the inclusive range [0,1], otherwise an error is signaled. *alpha* = 0 means *color-spec* is transparent,

alpha = 1 means it is solid.

color-with-alpha returns a color-spec, or nil if color is not

recognized.

See also get-all-color-names

make-rgb

colors= Function

Summary Tests to see if two colors are equal.

Package color

Signature colors= color1 color2 &optional tolerance => bool

Arguments *color1* A color specification.

color2 A color specification.

tolerance A tolerance level within which color1 and

color2 may vary. The default value is

0.001s0.

Values bool t if the two colors are equal within the given

tolerance, nil otherwise.

Description Return t if the two colors are equal to the given tolerance.

See also ensure-<command>

convert-color

convert-color Function

Summary Return the representation of a color specification on a given

graphics port.

Package color

Signature convert-color port color &key errorp => color-rep

Arguments *port* A graphics port.

color A color specification.

errorp If t, check for errors. By default, this is t.

Values color-rep Representation of color on port.

Description Return the representation of *color* on the given graphics port

port. In CLX, this is the "pixel" value, which corresponds to an index into the default colormap. It is more efficient to use the result of convert-color in place of its argument in drawing function calls, but the penalty is the risk of erroneous colors being displayed should the colormap or the color-

map entry be changed.

3 COLOR Reference Entries

See also colors=

ensure-<command>
unconvert-color

define-color-alias Function

Summary Lets you define an alias for a color specification or alias.

Package color

Signature define-color-alias name color &optional if-exists => alias

Arguments name The name of the new alias.

color A color specification for the new alias.

if-exists This can be one of the following:

:replace — Replace any existing alias.

:error — Raise an error if alias is already

defined.

:ignore — Ignore redefinition of an alias.

By default, it is :replace.

Values alias The color alias.

Description Define *name* to be a color alias for *color*, which may be another

color alias or a color-spec.

Example 1 COLOR 16 > (define-color-alias :mygray :darkslategray)

(#S(COLOR-ALIAS COLOR :DARKSLATEGRAY))

 ${\tt COLOR~17~>~(define-color-alias~:mygray~:darkslategray)}$

:error)

```
Error: :MYGRAY names an existing alias for #(:RGB
             0.1843133S0 0.309803S0 0.309803S0)
               1 (continue) Replace : MYGRAY with the alias
             : DARKSLATEGRAY
               2 Continue, without redefining alias :MYGRAY
               3 Try a new name for the alias, instead of :MYGRAY
               4 (abort) Return to level 0.
               5 Return to top loop level 0.
               6 Destroy process.
             Type :c followed by a number to proceed or type :? for
             other options
             COLOR 18 : 1 >
Example 2
             COLOR 19 > (define-color-alias :lispworks-blue
                              (make-rgb 0.70s0 0.90s0 0.99s0))
             (#S(COLOR-ALIAS COLOR #(:RGB 0.699999S0 0.9S0 0.99S0)))
             COLOR 20 >
See also
             get-color-alias-translation
             get-color-spec
```

define-color-models

Macro

Summary	Defines <i>all</i> the color models.	
Package	color	
Signature	define-color-models model-descriptors=> color-models	
Arguments	model-descriptors A list, each element being a model-descriptor.	
Values	color-models The color models defined.	
Description	A model descriptor has the syntax: (model-name component-descr*)	
	A component-descr is a list:	

(component-name lowest-value highest-value)

The default color models are defined by the following form:

If you want to keep existing color models, add your new ones to this list: only one define-color-models form is recognized. The form should be compiled.

Example

To replace the HSV color model with a CMYK model, while retaining the other color models:

delete-color-translation

Function

Summary	Removes an entr	ry from the color-database.

Package color

Signature delete-color-translation color-name => <no values>

Arguments color-name A defined color spec or alias.

Values None.

Description Both original entries and aliases can be removed.

See also load-color-database

color-database
read-color-db

ensure-<command>

Function

Summary Return a color specification for a given model. The model

depends on the particular function called

Package color

Signature ensure-rgb color-spec => result

ensure-hsv color-spec => result
ensure-gray color-spec => result

ensure-model-color color-spec model => result
ensure-color color-spec match-color-spec => result

Arguments For all functions:

color-spec A color specification.match-color-spec A color specification.

model A color-model (:rgb, :hsv or :gray).

Values result A color specification.

Description These functions all return a color specification, given (at

least) a color specification as argument.

ensure-rgb, ensure-hsv and ensure-gray all return a color specification in the appropriate model. If *color-spec* is in the same model, it is just returned. Otherwise a new color specification for that model is calculated. Thus, ensure-rgb returns a color specification in the RGB color model, whatever color model is used in *color-spec*.

If *color-spec* has an alpha component, then *result* has that same alpha component.

ensure-model-color is similar to the above three functions, except that a color-model *model* is explicitly passed as an argument to the function. The color-spec returned is in the color-model specified by *model*.

ensure-color returns a color specification for *color-spec*, in the color model specified by *match-color-spec*. Thus, color specifications may be converted from one model to another with having to explicitly state the color model.

```
Example

COLOR 36 > (ensure-hsv (make-rgb 0.70s0 0.90s0 0.99s0))

#(:HSV 4.31033S0 0.707069S0 0.99S0)

COLOR 37 > (ensure-gray (make-rgb 0.70s0 0.90s0 0.99s0))

#(:GRAY 0.863331S0)

COLOR 39 > (ensure-model-color (make-rgb 0.70s0 0.90s0 0.99s0) :hsv)

#(:HSV 4.31033S0 0.707069S0 0.99S0)

COLOR 43 > (ensure-color (make-hsv 0.70s0 0.90s0 0.99s0) (make-rgb 0.70s0 0.90s0 0.99s0))

#(:RGB 0.99S0 0.890999S0 0.92069924)

See also

convert-color
```

get-all-color-names

colors=

Function

Summary	Returns a list of all color-names in the color database.		
Package	color		
Signature	get-all-color-names &optional sort => color-names		
Arguments	sort	If t, sort list of color names alphanumerically. By default, this is nil.	

Values color-names A list of all color names in the color data-

base.

Description Returns a list of all color-names in the color database. By con-

vention these are symbols in the keyword package. The returned list is alphanumerically sorted on the symbol-names

if the optional argument is non-nil.

See also apropos-color-names

apropos-color-spec-names apropos-color-alias-names

get-color-alias-translation

Function

Summary Return the ultimate color name associated with *color-alias*.

Package color

Signature get-color-alias-translation color-alias => color-name

Arguments color-alias A defined color alias.

Values color-name The color name associated with color-alias.

Example color 23 > (color:define-color-alias :lispworks-blue (color:make-rgb 0.70s0 0.90s0 0.99s0))

(#S(COLOR-ALIAS COLOR #(:RGB 0.699999S0 0.9S0 0.99S0)))

COLOR 24 > (color:define-color-alias

:color-background :lispworks-blue)

(#S(COLOR-ALIAS COLOR :LISPWORKS-BLUE))

COLOR 25 > (color:define-color-alias

:listener-background :color-background)

(#S(COLOR-ALIAS COLOR :COLOR-BACKGROUND))

COLOR 26 > (get-color-alias-translation

:listener-background)

:LISPWORKS-BLUE

:LISPWORKS-BLUE

COLOR 28 >

See also define-color-alias

get-color-spec

get-color-spec Function

Summary Returns the color-spec for a color.

Package color

Signature get-color-spec color => color-spec

Arguments color A defined color specification, color alias, or

an original color name.

Values *color-spec* A color specification.

Description Returns the color-spec for *color*, which can be a color-spec, a

color-alias, or an original color name.

Example color 28 > (color:define-color-alias :lispworks-blue

(color:make-rgb 0.70s0 0.90s0 0.99s0))

(#S(COLOR-ALIAS COLOR #(:RGB 0.699999S0 0.9S0 0.99S0)))

COLOR 29 > (color:define-color-alias

:color-background :lispworks-blue)

(#S(COLOR-ALIAS COLOR :LISPWORKS-BLUE))

COLOR 30 > (color:define-color-alias

:listener-background :color-background)

(#S(COLOR-ALIAS COLOR : COLOR-BACKGROUND))

COLOR 31 > (get-color-spec :listener-background)

#(:RGB 0.699999S0 0.9S0 0.99S0)

COLOR 32 > (get-color-spec :color-background)

#(:RGB 0.699999S0 0.9S0 0.99S0)

COLOR 33 > (get-color-spec :lispworks-blue)

#(:RGB 0.699999S0 0.9S0 0.99S0)

COLOR 34 > (get-color-spec

#(:RGB 0.70s0 0.90s0 0.99s0))

#(:RGB 0.699999S0 0.9S0 0.99S0)

COLOR 35 >

See also define-color-alias

get-color-alias-translation

load-color-database

Function

Summary Loads a color database.

Package color

Signature load-color-database data => <no values>

Arguments data A description of a color database.

Values None.

Description This loads the color database with color definitions contained

in *data*, which should have been obtained via the functions color:read-color-db. The colors thus defined may not be

replaced by color aliases.

See also *color-database*

delete-color-translation

read-color-db

make-gray Function

Summary Returns a color specification in the gray model.

3 COLOR Reference Entries

Package color

Signature make-gray level &optional alpha => color-spec

Arguments level A color component used to define the gray

level required.

alpha A number between 0 and 1, or nil.

Values *color-spec* A color specification.

Description Return a color-spec in the : GRAY model with component level.

Note that short-floats are used for the component; this results in the most efficient color conversion process. However, any

floating point number type can be used.

alpha indicates the alpha value of the color. 0 means it is transparent, 1 means it is solid. If alpha is nil or not specified then the color does not have an alpha component and it is

assumed to be solid.

Example color 25 > (color:make-gray 0.66667s0)

#(:GRAY 0.66667S0)

See also make-hsv

make-rgb
color-model

color-<component>

color-level color-alpha

make-hsv Function

Summary Returns a color specification in the hue-saturation-value

model.

Package color

Signature make-hsv hue saturation value &optional alpha => color-spec

Arguments *hue* A hue component.

saturation A saturation component.

value A value component.

alpha A number between 0 and 1, or nil.

Values *color-spec* A color specification.

Description Return a color-spec in the :HSV model with components *hue*,

saturation and value.

Note that short-floats are used for each component; this results in the most efficient color conversion process. How-

ever, any floating-point number type can be used.

alpha indicates the alpha value of the color. 0 means it is transparent, 1 means it is solid. If alpha is nil or not specified then the color does not have an alpha component and it is

assumed to be solid.

Example color 27 > (color:make-hsv 1.2s0 0.5s0 0.9s0)

#(:HSV 1.2S0 0.5S0 0.9S0)

See also make-rgb

make-gray
color-model

color-<component>

color-level color-alpha

make-rgb Function

Summary Returns a color specification in the red-green-blue model.

Package color

Signature make-rgb red green blue &optional alpha => color-spec

Arguments *red* A red component.

green A green component.

blue A blue component.

alpha A number between 0 and 1, or nil.

Values *color-spec* A color specification.

Description Return a color-spec in the :RGB model with components red,

green and blue.

Note that short floats are used for each component; this results in the most efficient color conversion process. How-

ever, any floating point number type can be used.

alpha indicates the alpha value of the color. 0 means it is transparent, 1 means it is solid. If alpha is nil or not specified then the color does not have an alpha component and it is

assumed to be solid.

Example The object returned by the following call defines the color red

in the RGB model:

COLOR 25 > (color:make-rgb 1.0s0 0.0s0 0.0s0)

#(:RGB 1.0S0 0.0S0 0.0S0)

See also make-hsv

make-gray color-model

color-<component>

color-level color-alpha

read-color-db Function

Summary Reads the color definitions contained in a file.

Package color

Signature read-color-db &optional file => color-database

Arguments file A filename or pathname containing the

color definitions to be read. If *file* is not given, read-color-db uses the default color definitions file in the LispWorks library.

Values color-database A database definition.

Description This reads color definitions from the given file (a filename or

pathname). The returned data structure can be passed to color:load-color-database. The format of the file is:

#(:RGB 1.0s0 0.980391s0 0.980391s0) snow

#(:RGB 0.972548s0 0.972548s0 1.0s0) GhostWhite

. . .

Each line contains a color definition which consists of a colorspec and a name. The names are converted to uppercase and interned in the keyword package. Whitespace in names is

preserved.

See also load-color-database

color-database

delete-color-translation

unconvert-color Function

Summary Returns a color specification for a color representation.

Package color

Signature unconvert-color port color-rep => color

Arguments *port* A graphics port.

3 COLOR Reference Entries

color-rep A color representation on *port*.

Values *color* A color specification.

Description The function unconvert-color returns a color specification

corresponding to the color representation *color-rep* on the

Graphics Port port.

If *color-rep* is a color specification, a symbol or a color alias, then it is simply returned since the color system can interpret

these directly.

Otherwise *color-rep* is assumed to be a color representation on *port*, like those returned by convert-color and image-access-pixel, and a corresponding RGB value is returned.

See also convert-color

image-access-pixel

Index

Numerics

Α

2pi constant 679

abort-callback function 1 abort-dialog function 2 abort-exit-confirmer function 3 :accelerator initarg 331 Accelerators 251, 331 accepts-focus-p generic function 4 :accepts-focus-p initarg 66, 166 accessor functions application-interfaceapplication-menu 58 application-interface-dockmenu 58 application-interface-message-callback 58 browser-pane-before-navigate-callback 16 browser-pane-debug 16 browser-pane-document-complete-callback 16 browser-pane-internet-

explorer-callback 16

browser-pane-navigate-com-

plete-callback 16

browser-pane-navigate-

error-callback 16

browser-pane-new-window-

```
callback 16
browser-pane-progress-call-
   back 16
browser-pane-status-text-
   change-callback 16
browser-pane-successful-p 16
browser-pane-title 16
browser-pane-title-change-
   callback 16
browser-pane-update-com-
   mands-callback 16
browser-pane-url 16
button-alternate-callback
   468
button-armed-image 27
button-cancel-p 27
button-default-p 27
button-disabled-image 27
button-enabled 27
button-image 27
button-press-callback 468
button-selected 27
button-selected-disabled-
   image 27
button-selected-image 27
callbacks-action-callback 39
callbacks-callback-type 39
callbacks-extend-callback 39
callbacks-retract-callback
callbacks-selection-call-
   back 39
capi-object-name 43
capi-object-plist 43
choice-initial-focus-item 47
choice-interaction 47
```

choice-selection 47	form-title-gap 190
cocoa-view-pane-init-	form-vertical-adjust 190
function 62	form-vertical-gap 190
cocoa-view-pane-view-	graph-edge-from 198
class 62	graph-edge-to 198
collection-items 66	graph-node-height 199
collection-items-count-	graph-node-in-edges 199
function 66	graph-node-out-edges 199
collection-items-get-	graph-node-width 199
$\verb function 66$	graph-node-x 199
collection-items-map-	graph-node-y 199
function 66	${\tt graph-object-element}~200$
collection-print-function	${ t graph-object-object} \ 200$
66	graph-pane-layout-function
collection-test-function	201
66	graph-pane-roots 201
collector-pane-stream 72	help-key 66, 167, 332, 623
display-pane-text 112	image-height 750
docking-layout-controller 119	image-pinboard-object-image 219
docking-layout-divider-p	image-width 750
119	interactive-pane-stream 224
docking-layout-docking-	interactive-pane-top-level-
test-function 119	function 224
docking-layout-items 119	interface-activate-call-
docking-layout-orienta-	back 230
tion 119	interface-confirm-destroy-
document-frame-container	function 230
124	interface-create-callback
drawn-pinboard-object-	230
display-callback 136	interface-default-toolbar-
editor-pane-buffer 159	states 230
editor-pane-change-call-	interface-destroy-callback
back 149	230
editor-pane-composition-	interface-drag-image 230
face 149	interface-geometry-change-
editor-pane-enabled 149	callback 230
editor-pane-fixed-fill 149	interface-help-callback 230
editor-pane-line-wrap- face 149	interface-iconify-callback 230, 240
editor-pane-line-wrap-	interface-menu-bar-items 230
marker 149	interface-message-area 230,
editor-pane-text 149	239
editor-pane-wrap-style 149	interface-override-cursor
element-interface 167	230
element-parent 167	interface-pathname 230
element-widget-name 167	interface-pointer-documen-
filled 174, 478	tation-enabled 230
filtering-layout-matches-	interface-title 230
text 182	interface-toolbar-items 230
filtering-layout-state 182	interface-toolbar-states 230
form-title-adjust 190	interface-tooltips-enabled
	-

230	368
interface-window-styles 230	option-pane-popup-callback
item-collection 263	368
item-data 263	option-pane-separator-item
item-print-function 263	368
item-selected 263	option-pane-visible-items-
item-text 263	count 368
labelled-line-text-back-	output-pane-composition-
ground 267	callback 373
labelled-line-text-fore-	output-pane-create-call-
ground 267	back 373
layout-description 269	output-pane-destroy-call-
layout-ratios 74, 498	back 373
layout-x-adjust 677	output-pane-display-call-
layout-x-gap 211	back 373
layout-x-ratios 211	output-pane-focus-callback
layout-y-adjust 677	373
layout-y-gap 211	output-pane-graphics-
layout-y-ratios 211	options 373
list-panel-image-function	output-pane-input-model 373
274	output-pane-resize-call-
list-panel-keyboard-search-	back 373
callback 274	output-pane-scroll-call-
list-panel-right-click-	back 373
selection-behavior 274	pane-layout 32, 230
list-panel-state-image-	password-pane-overwrite-
function 274	character 399
list-view-auto-arrange-	pinboard-object-activep 406
icons 290	pinboard-object-graphics-
list-view-auto-reset-col-	args 406
umn-widths 290	pinboard-object-pinboard 406
list-view-columns 290	popup-menu-button-menu 424
list-view-image-function 290	popup-menu-button-menu-
list-view-state-image-func-	function 424
tion 290	range-callback 476
list-view-subitem-function	range-end 476
290	range-orientation 476
list-view-subitem-print-	range-slug-end 476
functions 290	range-slug-start 476
list-view-view 290	range-start 476
menu-image-function 324	rich-text-pane-change-call-
menu-items 324	back 488
menu-object-enabled 337	rich-text-pane-limit 488
menu-popup-callback 337	rich-text-pane-text 488
menu-title 613	screen-depth 500
menu-title-function 613	screen-height 500
ole-control-component-pane	screen-height-in-millime-
356	ters 500
option-pane-enabled 368	screen-interfaces 123, 500
option-pane-enabled-posi-	screen-number 500
tions 368	screen-width 500
option-pane-image-function	screen-width-in-millime-

ters 500 callback 586 scroll-bar-line-size 509 text-input-pane-enabled 586 scroll-bar-page-size 509 text-input-pane-max-characshell-pane-command 547 ters 586 simple-pane-background 552 text-input-pane-navigationcallback 586 simple-pane-cursor 552 simple-pane-drag-callback text-input-pane-text 586 text-input-range-callback simple-pane-drop-callback text-input-range-callbacksimple-pane-enabled 182, 552, type 610 text-input-range-changesimple-pane-font 552 callback 610 simple-pane-foreground 552 text-input-range-end 610 simple-pane-horizontaltext-input-range-start 610 scroll 552 text-input-range-value 610 simple-pane-scroll-calltext-input-range-wraps-p 610 back 552 titled-object-message 615 simple-pane-verticaltitled-object-message-font scroll 552 240, 615 simple-pane-visible-bortitled-object-title 615 der 552 titled-object-title-font 615 slider-print-function 566 title-pane-text 612 slider-show-value-p 567 toolbar-button-dropdownslider-start-point 567 menu 623 slider-tick-frequency 567 toolbar-button-dropdownswitchable-layout-commenu-function 623 bine-child-constraints toolbar-button-dropdownmenu-kind 623 switchable-layout-visitoolbar-button-image 623 ble-child 575 toolbar-button-popup-intertab-layout-combine-childface 623 constraints 578 toolbar-button-selectedtab-layout-image-function image 623 toolbar-flat-p 620 tab-layout-visible-childtoolbar-object-enabledfunction 578 function 631 top-level-interface-extertext-input-pane-beforechange-callback 597 nal-border 230 text-input-pane-buttonstop-level-interface-transenabled 586 parency 230 text-input-pane-callback tree-view-action-callbackexpand-p 642 text-input-pane-carettree-view-checkbox-changeposition 586 callback 642 tree-view-checkbox-childtext-input-pane-changecallback 586 function 642 text-input-pane-completree-view-checkbox-initialtion-function 586 status 642 text-input-pane-confirmtree-view-checkbox-next-map change-function 586 text-input-pane-editingtree-view-checkbox-parent-

function 642	:alternative-action-callback
tree-view-checkbox-status	initarg 38
642	analyze-external-image function
tree-view-children-func-	680
tion 642	anti-aliasing 154, 202, 374, 566, 666, 674,
tree-view-expandp-function	745, 749
642	text on GTK+ 403
tree-view-has-root-line 642	text on Microsoft Windows 403
tree-view-image-function 642	append-items generic function 7
tree-view-leaf-node-p-func- tion 642	Application menu 58 application-interface-appli-
tree-view-retain-expanded-	cation-menu accessor func-
nodes 642	tion 58
tree-view-right-click-	application-interface-dock-
extended-match 642	menu accessor function 58
tree-view-roots 642	application-interface-mes-
tree-view-state-image-func-	sage-callback accessor func-
tion 642	tion 58
:action-callback initarg 38	:application-menu initarg 58
:action-callback-expand-p ini-	apply-in-pane-process function 8
targ 640	apply-in-pane-process-if-
:activate-callback initarg 228	alive function 9
activate-pane function 5	apply-rotation function 680
: activep initarg 404, 475	apply-rotation-around-point
active-pane-copy function 6	function 681
active-pane-copy-p function 6	apply-scale function 682
active-pane-cut function 6	apply-translation function 683
active-pane-cut-p function 6	apropos-color-alias-names
active-pane-deselect-all func-	function 823
tion 6 active-pane-deselect-all-p	apropos-color-names function 824 apropos-color-spec-names func-
function 6	tion 825
active-pane-paste function 6	Arguments screen A screen. 574
active-pane-paste-p function 6	: armed-image initarg 26
active-pane-select-all function	:armed-images initarg 31
6	arrow-pinboard-object class 10
active-pane-select-all-p func-	attach-interface-for-call-
tion 6	back function 11
active-pane-undo function 6	attach-simple-sink function 12
active-pane-undo-p function 6	attach-sink function 13
ActiveX 362	augment-font-description func-
:adjust initarg 73, 498	tion 683
:adjust item in :buttons initarg 594	:auto-arrange-icons initarg 289
:after-input-callback initarg 149	:automatic-resize initarg 404, 552
'alive" interface	:auto-menus initarg 227
definition 177	:auto-reset-column-widths ini-
'alive" pane	targ 289, 345
definition 9	D.
: alternate-callback initary 467	В
: alternating-background initarg	background graphics state parameter 742
273	:background initarg 551
:alternative initarg 331	beep-pane function 14

:before-change-callback ini- targ 597	browser-pane-stop generic function 23
:before-input-callback ini- targ 149	browser-pane-successful-p accessor function 16
:before-navigate-callback initarg 15	browser-pane-title accessor func- tion 16
:best-height initarg 227	browser-pane-title-change-
:best-width initarg 227	callback accessor function 16
:best-x initarg 227	browser-pane-update-com-
:best-y initarg 227	mands-callback accessor
:browse-file item in :buttons	function 16
initarg 592	browser-pane-url accessor function
browser-pane class 15	16
browser-pane-before-navi- gate-callback accessor	:buffer-modes initarg 149 :buffer-name initarg 72, 149
function 16	built-in scrolling 196
browser-pane-busy generic func-	button class 25
tion 23	button-alternate-callback
browser-pane-debug accessor	accessor function 468
function 16	button-armed-image accessor func-
browser-pane-document-com-	tion 27
plete-callback accessor	button-cancel-paccessor function 27
function 16	:button-class initarg 31
browser-pane-go-back generic	button-default-p accessor function
function 23	27
browser-pane-go-forward generic function 23	button-disabled-image accessor function 27
browser-pane-internet-	button-enabled accessor function 27
explorer-callback	:button-height initarg 620
accessor function 16	button-image accessor function 27
browser-pane-navigate generic	button-panel class 31
function 23	button-press-callback accessor
browser-pane-navigate-com-	function 468
plete-callback accessor function 16	:buttons initarg 586 button-selected accessor function 27
browser-pane-navigate-	button-selected-disabled-
error-callback accessor	image accessor function 27
function 16	button-selected-image accessor
browser-pane-new-window-	function 27
callback accessor function	:button-width initarg 620
16	J
browser-pane-progress-call-	С
back accessor function 16	calculate-constraints generic
browser-pane-property-get	function 36
generic function 25	calculate-layout generic function
browser-pane-property-put	37
generic function 25	:callback initarg 26, 28, 181, 337, 475,
browser-pane-refresh generic function 23	509, 585, 610, 622
browser-pane-status-text-	:callback-data-function initarg
change-callback acces-	337
sor function 16	:callback-object initarg 181 callbacks 38

for button panels 31	choice class 46
for buttons 28	choice-initial-focus-item
passing different variables 12	accessor function 47
callbacks class 38	choice-interaction accessor func-
:callbacks initarg 31, 620, 629	tion 47
callbacks-action-callback	choice-selected-item generic
accessor function 39	function 50
callbacks-callback-type acces-	choice-selected-item-p function
sor function 39	52
callbacks-extend-callback	choice-selected-items generic
accessor function 39	function 52
callbacks-retract-callback	choice-selection accessor function
accessor function 39	47
callbacks-selection-callback	choice-update-item function 54
accessor function 39	class options
:callback-type initarg 38, 578, 585,	:coclass 101
610	:definition 93
call-editor generic function 41	:interfaces 101
:cancel item in :buttons initarg 592	:layouts 93
cancel-button image identifier 595	:menu-bar 93
:cancel-button initarg 31	:menus 93
:cancel-function item in :but-	:panes 93
tons initarg 593	:source-interfaces 101
:cancel-pinitarg 26	classes
can-use-metafile-p function 42	arrow-pinboard-object 10
CAPI process 105	browser-pane 15
capi-object class 42	button 25
capi-object-name accessor function	button-panel 31
43	callbacks 38
capi-object-plist accessor func-	capi-object 42
tion 43	check-button 44
capi-object-property function 43	check-button-panel 45
:caret-position initarg 584	choice 46
:change-callback initarg 149, 181,	cocoa-default-application-
488, 585, 610	interface 58
:change-callback-type initarg 585	${ t cocoa-view-pane} \ 62$
:character-format initarg 488	$\verb"collection" 65"$
:checkbox-change-callback ini-	collector-pane 71
targ 641	color-screen 73
:checkbox-child-function ini-	column-layout 73
targ 641	display-pane 111
:checkbox-initial-status ini-	docking-layout 118
targ 641	document-container 123
:checkbox-next-map initarg 640	document-frame 124
:checkbox-parent-function ini-	double-headed-arrow-pin-
targ 640	board-object 128
:checkbox-status initarg 640	double-list-panel 129
check-button class 44	drawn-pinboard-object 136
check-button-panel class 45	echo-area-pane 146
%child% geometry slot 669	editor-pane 148
:child initarg 564	element 165
:children-function initarg 201, 639	ellipse 174

expandable-item-pinboard-	pinboard-layout 401
object 180	pinboard-object 404
extended-selection-tree-	pixmap-port 778
view 180	popup-menu-button 424
external-image 717	progress-bar 437
filtering-layout 181	push-button 467
foreign-owned-interface	push-button-panel 469
189	radio-button 472
form-layout 190	radio-button-panel 473
graph-edge 198	range-pane 475
graph-node 199	rectangle 478
graph-object 200	rich-text-pane 487
graph-pane 200	right-angle-line-pinboard-
grid-layout 211	object 496
image 750	row-layout 497
image-list 217	screen 499
image-pinboard-object 219	${ t scroll-bar}\ 509$
image-set 220	shell-pane 547
interactive-pane 224	$ exttt{simple-layout } 549$
interface 227	$ exttt{simple-network-pane}~550$
item 262	$ exttt{simple-pane} 550$
item-pinboard-object 266	${ t simple-pinboard-layout}~564$
labelled-arrow-pinboard-	slider 566
object 267	sorted-object 570
labelled-line-pinboard-	static-layout 573
object 267	switchable-layout 575
layout 268	tab-layout 577
line-pinboard-object 270	text-input-choice 583
listener-pane 294	text-input-pane 584
list-panel 272	${ t text - input - range} \ 610$
list-view 288	titled-menu-object 613
menu 324	titled-object 614
menu-component 328	titled-pinboard-object 618
menu-item 331	title-pane 612
menu-object 337	toolbar 620
message-pane 342	toolbar-button 622
mono-screen 343	toolbar-component 628
multi-column-list-panel	toolbar-object 630
344	tracking-pinboard-layout 637
multi-line-text-input-	tree-view 639
pane 349	x-y-adjustable-layout 677
non-focus-list-interface	clear-external-image-conver-
350	sions function 684
ole-control-component 356	clear-graphics-port function 685
ole-control-doc 358	clear-graphics-port-state
ole-control-frame 359	function 685
ole-control-pane 362	clear-rectangle function 686
ole-control-pane-simple-	clipboard function 55
sink 365	clipboard-empty function 57
option-pane 367	clone generic function 57
output-pane 371	:close-callback initarg 363
password-pane 399	:coclass class option 101
E E	· · · · · · · · · · · · · · · · · · ·

Cocoa Event Loop process 106	command table 372
cocoa-default-application-	complete-button image identifier 595
interface class 58	:complete-do-action initarg 586
cocoa-view-pane class 62	:completion item in :buttons ini-
cocoa-view-pane-init-func-	targ 592
tion accessor function 62	:completion-function initarg 584
cocoa-view-pane-view function 63	component-name function 76
cocoa-view-pane-view-class	:component-name initarg 362, 366
accessor function 62	compositing-mode graphics state parameter
collect-interfaces generic func-	745
tion 64	:composition-callback initarg 373
collection class 65	:composition-face initarg 149
:collection initarg 263	compress-external-image func-
collection-find-next-string	tion 687
generic function 69	compute-char-extents function 687
collection-find-string generic	comtab 372
function 70	Confirm Before Exiting 77, 519
collection-items accessor function	:confirm-change-function ini-
66	targ 585
collection-items-count-func-	:confirm-destroy-function ini-
tion accessor function 66	targ 227
collection-items-get-func-	confirmer-pane function 78
tion accessor function 66	confirm-quit function 76
collection-items-map-func-	confirm-yes-or-no function 78
tion accessor function 66	constants
collection-last-search generic function 70	2pi 679
collection-print-function	f2pi 722 fpi 730
accessor function 66	fpi-by-2 730
collection-search generic function	pi-by-2 776
71	contain function 79
collection-test-function acces-	container 124
sor function 66	container special slot 124
collector-pane class 71	continuation function, dialog
collector-pane-stream accessor	creating 662
function 72	using 108, 385, 417, 428, 439, 441, 444,
color- <component>function 826</component>	446, 448, 449, 451, 454, 456, 457,
color-database variable 827	459, 467
:color-function initarg 272	:controller initarg 118
color-level function 826, 828	convert-color function 831
color-model function 829	convert-external-image function
colors= function 830	688
color-screen class 73	convert-relative-position
color-with-alpha function 829	function 80
:column initarg 211	convert-to-font-description
:column-function initarg 345	function 689
column-layout class 73	convert-to-screen function 81
column-layout-divider 74	copy-area function 690
:columns initarg 345	copy-external-image function 691
:combine-child-constraints	copy-pixels function 692
initarg 575, 578	copy-transform function 693
command initary 547	count-collection-items generic

function 85	removal 235
:create-callbackinitarg 227, 356,	destroy generic function 102
373	:destroy-callback initarg 227, 356,
create-pixmap-port function 693	373
current-dialog-handle function	destroy-pixmap-port function 696
85	detach-simple-sink function 103
current-document generic function	detach-sink function 104
87	dialog continuation function
current-pointer-position	creating 662
function 87	using 108, 385, 417, 428, 439, 441, 444,
current-popup function 88	446, 448, 449, 451, 454, 456, 457,
current-printer function 89	459, 467
cursor format	dialogs
on Cocoa 296	aborting 2
on GTK+ 296	:directories-only initarg 585
on Microsoft Windows 296	:disabled-image initarg 26
: cursor initarg 551	:disabled-images initarg 31
O	display function 104
D	:display-callback initarg 136, 372
dash graphics state parameter 744	display-dialog generic function 107
dashed graphics state parameter 744	display-errors macro 110
:data initarg 263	display-message function 110
: debug initarg 16	display-message-for-pane func-
:default initarg 269	tion 111
:default-button initarg 31	display-message-on-screen
*default-editor-pane-line-	function 111
wrap-marker* variable 89	display-pane class 111
:default-image-set initarg 620,	display-pane-selected-text
629	function 113
*default-image-translation-	display-pane-selection function
table* variable 695, 758	113
default-library function 90	display-pane-selection-p func-
:default-p initarg 26	tion 114
:default-toolbar-states ini-	display-pane-text accessor func-
targ 229	tion 112
define-color-alias function 832	display-popup-menu function 115
define-color-models macro 833	display-replacable-dialog
define-command macro 90	function 116
define-font-alias function 695	:display-state initarg 229
define-interface macro 92	display-tooltip generic function
define-layout macro 98	117
define-menu macro 99	dither-color-spec function 696
define-ole-control-compo-	:divider-p initarg 118
nent macro 100	:dividerp initarg 620
:definition class option 93	Dock menu 58
delete-color-translation	:docking-callback initarg 118
function 834	docking-layout class 118
:delete-item-callback initarg	docking-layout-controller accessor function 119
640	
:depth initarg 500	docking-layout-divider-pacces-
:description initarg 269, 578	sor function 119
destroy button	docking-layout-docking-test-

function accessor function 119	tion 136
docking-layout-items accessor	draw-path function 705
function 119	draw-pinboard-object generic
docking-layout-orientation	function 137
accessor function 119	draw-pinboard-object-high-
docking-layout-pane-docked-p	lighted generic function 138
function 122	draw-pinboard-object-unhigh-
docking-layout-pane-visible-	lighted generic function 138
p function 122	draw-point function 709
:docking-test-function initarg	draw-points function 710
118	draw-polygon function 710
:dock-menu initarg 58	draw-polygons function 711
document modified	draw-rectangle function 712
on Cocoa 247	draw-rectangles function 713
document unsaved	draw-string function 714
on Cocoa 247	:draw-with-buffer initarg 372
:document-complete-callback	:drop-callback initarg 552
initarg 15	: dropdown-menu initarg 623
document-container class 123	:dropdown-menu-function initarg
document-frame class 124	623
document-frame-container acces-	:dropdown-menu-kind initarg 623
sor function 124	drop-object-allows-drop-
double-headed-arrow-pin-	effect-p function 139
board-object class 128	drop-object-collection-index
:double-head-predicate initarg	function 139
128	drop-object-collection-item
double-list-panel class 129	function 141
Drag and drop	drop-object-drop-effect func-
coordinates 144	tion 142
dragging 131	drop-object-get-object function
dropping 552	143
effect 139, 142	drop-object-pane-x generic func-
formats 145, 523	tion 144
object 143	drop-object-pane-y generic func-
:drag-callback initarg 552	tion 144
:drag-image initarg 229	drop-object-provides-format
drag-pane-object function 131	function 145
draw-arc function 697	_
draw-arcs function 698	E
draw-character function 699	:echo-area initarg 149
draw-circle function 700	*echo-area-cursor-inactive-
draw-ellipse function 701	style* variable 145
draw-image function 702	echo-area-pane class 146
:drawing-mode initarg 372	:edge-pinboard-class initarg 201
draw-line function 704	:editing-callback initarg 585
draw-lines function 705	*editor-cursor-active-style*
draw-metafile function 133	variable 147
draw-metafile-to-image function	*editor-cursor-color* variable
134	146
drawn-pinboard-object class 136	<pre>*editor-cursor-drag-style*</pre>
drawn-pinboard-object-dis-	variable 147
play-callback accessor func-	*editor-cursor-inactive-

style* variable 148	log initarg 332
editor-pane class 148	:enabled-positions initarg 368
editor-pane-blink-rate	:enabled-slot initarg 337
generic function 158	:enable-pointer-documenta-
editor-pane-buffer accessor	tion initarg 228
function 159	:enable-tooltips initarg 228
editor-pane-change-call-	:end-x initarg 271
back accessor function 149	:end-y initarg 271
editor-pane-composition-	ensure- <command/> function 835
face accessor function 149	ensure-area-visible generic func-
*editor-pane-composition-	tion 174
selected-range-face-	ensure-gdiplus function 716
plist* variable 160	ensure-interface-screen func-
*editor-pane-default-compo-	tion 175
sition-face* variable 162	Escape key 415
editor-pane-enabled accessor	event handler
function 149	key strokes 374
editor-pane-fixed-fill acces-	mouse click 374
sor function 149	mouse gestures 374
editor-pane-line-wrap-face	mouse move 374
accessor function 149	execute-with-interface function
editor-pane-line-wrap-	176
marker accessor function 149	execute-with-interface-if-
editor-pane-native-blink-	alive function 177
rate function 163	exit-confirmer function 178
editor-pane-selected-text	exit-dialog function 179
generic function 163	expandable-item-pinboard-
editor-pane-selected-text-p	object class 180
generic function 164	:expandp-function initarg 640
editor-pane-stream function 164	:extend-callback initarg 38
editor-pane-text accessor func-	extended-selection-tree-view
tion 149	class 180
editor-pane-wrap-style acces-	:external-border initarg 229
sor function 149	external-image class 717
editor-window generic function 165	external-image-color-table
element class 165	function 718
element-container function 172	externalize-and-write-image
element-interface accessor func-	function 719
tion 167	externalize-image function 721
element-interface-for-call-	:external-max-height initarg 167,
back generic function 173	405
element-parent accessor function	:external-max-width initarg 167,
167	405
element-screen function 174	:external-min-height initarg 166,
element-widget-name accessor	405
function 167	:external-min-width initarg 166,
ellipse class 174	405
:enabled initarg 26, 148, 181, 337,	_
367, 551, 584, 631	F
:enabled-function initarg 337,	f2pi constant 722
631	:file-completion initarg 585
:enabled-function-for-dia-	:filename initarg 488

filled accessor function 174, 478	font-single-width-p function 729
:filled initarg 174, 478	force-screen-update function 188
fill-style graphics state parameter 743	force-update-all-screens func-
:filter initarg 273	tion 189
:filter-automatic-p initarg 273	foreground graphics state parameter 742
:filter-callback initarg 273	: foreground initarg 551
: filter-change-callback-p ini- targ 273	foreign-owned-interface class 189
:filter-help-string initarg 273	form-layout class 190
filtering-layout class 181	form-title-adjust accessor func-
filtering-layout-matches-	tion 190
text accessor function 182	form-title-gap accessor function 190
filtering-layout-match-	form-vertical-adjust accessor
object-and-exclude-p	function 190
function 185	form-vertical-gap accessor func-
filtering-layout-state accessor	tion 190
function 182	fpi constant 730
:filter-matches-title initarg 273	fpi-by-2 constant 730
:filter-short-menu-text initarg	frame 616
273	free-image function 730
find-best-font function 723	free-image-access function 731
find-graph-edge generic function	free-metafile function 191
185	free-sound function 192
find-graph-node generic function	:from initarg 198
186	functions
finding panes	abort-callback 1
interfaces 93	abort-dialog 2
find-interface generic function 187	abort-exit-confirmer 3
find-matching-fonts function 724	${ t activate-pane} \ 5$
find-pane 93	active-pane-copy 6
find-string-in-collection	active-pane-copy-p 6
generic function 188	${ t active-pane-cut} \ 6$
:fit-size-to-children initarg 573	$ exttt{active-pane-cut-p} 6$
:fixed-fill initarg 149	t active-pane-deselect-all 6
:flatp initarg 620	active-pane-deselect-all-p
focus	6
keyboard input on Cocoa 236	$\verb"active-pane-paste" 6$
mouse events on Cocoa 237	active-pane-paste-p 6
moving to a new pane 5	$\verb"active-pane-select-all" 6$
setting to a pane 390, 535	$\verb"active-pane-select-all-p" 6$
:focus-callback initarg 373	active-pane-undo 6
font graphics state parameter 745	$\verb"active-pane-undo-p" 6$
: font initarg 551	analyze-external-image 680
font type 724	$\verb"apply-in-pane-process" 8$
font-description function 726	apply-in-pane-process-if-
font-description type 725	$\verb"alive"9$
font-description-attributes	apply-rotation 680
function 727	apply-rotation-around-point
font-description-attribute-	681
value function 727	$\mathtt{apply} ext{-}\mathtt{scale}~682$
font-dual-width-p function 726	apply-translation 683
font-fixed-width-p function 728	apropos-color-alias-names

823	current-popup 88
apropos-color-names 824	current-printer 89
apropos-color-spec-names	default-library 90
825	define-color-alias 832
attach-interface-for-	define-font-alias 695
callback 11	delete-color-translation 834
attach-simple-sink 12	destroy-pixmap-port 696
attach-sink 13	detach-simple-sink 103
augment-font-description	detach-sink 104
683	display 104
beep-pane 14	display-message 110
can-use-metafile-p 42	display-message-for-pane 111
capi-object-property 43	display-message-on-screen
choice-selected-item-p 52	111
choice-update-item 54	display-pane-selected-text
clear-external-image-con-	113
versions 684	display-pane-selection 113
clear-graphics-port 685	display-pane-selection-p 114
clear-graphics-port-state	display-popup-menu 115
685	display-replacable-dialog
clear-rectangle 686	116
clipboard 55	dither-color-spec 696
clipboard-empty 57	docking-layout-pane-docked-
cocoa-view-pane-view 63	p 122
color- <component>826</component>	docking-layout-pane-visi-
color-level 826, 828	ble-p 122
color-model 829	drag-pane-object 131
colors= 830	draw-arc 697
color-with-alpha 829	draw-arcs 698
component-name 76	draw-character 699
compress-external-image	draw-circle 700
687	draw-ellipse 701
compute-char-extents 687	draw-image 702
confirmer-pane 78	draw-line 704
confirm-quit 76	draw-lines 705
confirm-yes-or-no 78	draw-metafile 133
contain 79	draw-metafile-to-image 134
convert-color 831	draw-path 705
convert-external-image 688	draw-point 709
convert-relative-position	draw-points 710
80	draw-polygon 710
convert-to-font-descrip-	draw-polygons 711
$\verb tion 689$	draw-rectangle 712
convert-to-screen 81	draw-rectangles 713
copy-area 690	draw-string 714
copy-external-image 691	drop-object-allows-drop-
copy-pixels 692	effect-p 139
copy-transform 693	drop-object-collection-
create-pixmap-port 693	index 139
current-dialog-handle 85	<pre>drop-object-collection-item</pre>
current-pointer-position	141
87	drop-object-drop-effect 142

drop-object-get-object 143	get-font-descent 736
drop-object-provides-for-	get-font-height 737
mat 145	get-font-width 737
editor-pane-native-blink-	get-graphics-state 738
rate 163	get-origin 738
editor-pane-stream 164	get-page-area 194
element-container 172	get-printer-metrics 195
element-screen 174	get-scroll-position 196
ensure- <command/> 835	get-string-extent 739
ensure-gdiplus 716 ensure-interface-screen 175	get-transform-scale 740
execute-with-interface 176	graphics-port-background 740 graphics-port-font 740
execute-with-interface-if-	graphics-port-foreground 740
alive 177	graphics-port-transform 740
exit-confirmer 178	graphics-state-background
exit-dialog 179	746
external-image-color-table	graphics-state-compositing-
718	mode 746
externalize-and-write-image	graphics-state-dash 746
719	graphics-state-dashed 746
externalize-image 721	graphics-state-fill-style
filtering-layout-match-	746
object-and-exclude-p 185	${ t graphics-state-font}\ 746$
find-best-font 723	graphics-state-foreground
find-matching-fonts 724	746
font-description 726	graphics-state-line-end-
font-description-attributes	style 746
727	graphics-state-line-joint-
font-description-attribute-	t style 746
value 727	graphics-state-mask 746
font-dual-width-p 726	graphics-state-mask-trans-
font-fixed-width-p 728	form 746
font-single-width-p 729	graphics-state-mask-x 746
force-screen-update 188	graphics-state-mask-y 746
force-update-all-screens 189	graphics-state-operation 746
free-image 730	graphics-state-pattern 746
free-image-access 731	graphics-state-scale-thick-
free-metafile 191	ness 746
free-sound 192	graphics-state-shape-mode
get-all-color-names 836	746
get-bounds 731	graphics-state-stipple 746
get-character-extent 732	graphics-state-text-mode 746
get-char-ascent 733	graphics-state-thickness 746
get-char-descent 733	graphics-state-transform 746
get-char-width 734	graph-pane-edges 208
get-color-alias-transla-	graph-pane-nodes 208
tion 837	graph-pane-object-at-posi-
get-color-spec 838 get-constraints 193	tion 209 hide-interface 216
-	
get-enclosing-rectangle 734 get-font-ascent 735	hide-pane 216 image-access-height 750
get-font-average-width 736	image-access-neight 750
GCC TOTTO GACTAGE MIGHT 1/10	THICAS COSSIDINATE IN

image-access-pixels-from-	make-dither 767
bgra 752	make-docking-layout-con-
image-access-pixels-to-	$ exttt{troller}\ 303$
bgra 753	make-font-description 768
image-access-transfer-	make-foreign-owned-inter-
from-image 754	$\mathtt{face}\ 303$
image-access-transfer-to-	$ exttt{make-general-image-set} 305$
image 755	$ exttt{make-graphics-state}\ 769$
image-freed-p 756	make-gray 839
image-loader 756	make-hsv 840
image-translation 757	make-icon-resource-image-
initialize-dithers 758	set 306
inset-rectangle 758	make-image 769
inside-rectangle 759	make-image-from-port 771
installed-libraries 223	make-image-locator 307
install-postscript-	make-menu-for-pane 307
printer 221	make-resource-image-set 311
interface-customize-tool-	make-rgb 841
bar 244	make-scaled-general-image-
interface-display-title	set 312
246	make-scaled-image-set 313
interface-document-modi-	make-sorting-description 314
fied-p 247	make-sub-image 772
interface-iconified-p 250	make-transform 773
interface-preserving-	map-typeout 323
state-p 255	merge-font-descriptions 774
interface-toolbar-state 257	$\begin{array}{c} \mathtt{modify-editor-pane-buffer} \\ 342 \end{array}$
interface-visible-p 259	non-focus-list-add-filter
invalidate-pane-con-	351
straints 261	non-focus-list-remove-fil-
invert-transform 761	ter 351
invoke-command 261	non-focus-list-toggle-
invoke-untranslated-com-	enable-filter 350
mand 262	non-focus-list-toggle-fil-
line-pinboard-object-	ter 351
coordinates 271	offset-rectangle 775
list-all-font-names 761	ole-control-add-verbs 354
listener-pane-insert-	ole-control-close-object 355
value 295	ole-control-i-dispatch 360
list-known-image-formats 762	ole-control-insert-object 361
list-panel-items-and-fil-	ole-control-ole-object 361
ter 285	${ t ole-control-pane-frame}\ 365$
list-panel-search-with- function 286	ole-control-user-component 366
load-color-database 839	ordered-rectangle-union 775
load-cursor 295	t page-setup-dialog~385
load-icon-image 763	pane-close-display 388
load-image 765	pane-descendant-child-with-
load-sound 299	focus 389
lower-interface 301	pane-screen-internal-geome-

try 396	prompt-for-font 446
pane-supports-menus-with-	prompt-for-form 447
images 398	prompt-for-forms 449
pixblt 777	prompt-for-integer 450
play-sound 400	prompt-for-items-from-list
popup-confirmer 413	$\overline{451}$
port-graphics-state 779	prompt-for-number 452
port-height 780	prompt-for-string 453
port-string-height 780	prompt-for-symbol 455
port-string-width 781	prompt-for-value 457
port-width 781	t prompt-with-list 458
postmultiply-transforms 782	prompt-with-list-non-focus
premultiply-transforms 782	461
print-dialog 427	${\tt prompt-with-message}~466$
print-editor-buffer 428	$\mathtt{quit}\ 60$
printer-configuration-dia-	quit-interface 470
log 431	raise-interface 474
printer-metrics-device-	range-set-sizes 476
height 432	read-and-convert-external-
printer-metrics-device-	image 783
width 432	read-color-db 842
printer-metrics-dpi-x 433	read-external-image 784
printer-metrics-dpi-y 433	read-sound-file 477
printer-metrics-height 433	rectangle-union 788
printer-metrics-left-mar-	redisplay-menu-bar 479
gin 433	redraw-pinboard-layout 480
${ t printer-metrics-max-height} \ 433$	redraw-pinboard-object 481 register-image-load-func-
printer-metrics-max-width	tion 790
433	register-image-translation
printer-metrics-min-left-	791
margin 433	remove-capi-object-prop-
printer-metrics-min-top-	erty 482
margin 433	replace-dialog 484
printer-metrics-paper-	reset-image-translation-
height 433	table 792
printer-metrics-paper-width	reuse-interfaces-p 487
433	rich-text-pane-character-
printer-metrics-top-margin	format 490
433	rich-text-pane-operation 491
printer-metrics-width 433	rich-text-pane-paragraph-
printer-port-handle 434	format 495
printer-port-supports-p 434	rich-text-version 496
print-file 429	screen-active-interface 501
print-rich-text-pane 430	screen-active-p 501
print-text 431	screen-internal-geometries
process-pending-messages 436	503
prompt-for-color 437	screen-internal-geometry 505
prompt-for-confirmation 438	screen-logical-resolution
prompt-for-directory 440	502
prompt-for-file 442 prompt-for-files 445	screen-monitor-geometries 504
	JUI

screens 506	tab-layout-panes 582
selection 512	tab-layout-visible-child 582
selection-empty 514	text-input-pane-append-
separation $79\overline{3}$	recent-items 599
set-application-interface 514	text-input-pane-complete- text 604
set-clipboard 516	text-input-pane-copy 605
set-composition-placement	text-input-pane-cut 605
518	text-input-pane-delete 606
set-confirm-quit-flag 519	text-input-pane-delete-
set-default-editor-pane-	recent-items 599
blink-rate 519	text-input-pane-in-place-
set-default-image-load-	complete 606
function 793	text-input-pane-paste 607
set-default-interface-	text-input-pane-prepend-
prefix-suffix 520	recent-items 600
set-default-use-native-	text-input-pane-recent-
${ t input-method}\ 522$	items 601
set-drop-object-sup-	text-input-pane-replace-
ported-formats 523	recent-items 602
set-editor-parenthesis-	text-input-pane-selected-
$colors 52\overline{5}$	text 113, 608
set-geometric-hint 526	text-input-pane-selection
set-graphics-port-coordi-	113, 608
nates 794	text-input-pane-selection-p
set-graphics-state 795	114, 609
set-hint-table 526	text-input-pane-set-recent-
set-interactive-break-	items 602
gestures 528	transform-area 796
set-list-panel-keyboard-	transform-distance 796
${ t search-reset-time}\ 529$	transform-distances 797
set-object-automatic-	${ t transform-is-rotated}\ 797$
resize 530	transform-point 798
set-printer-metrics 541	transform-points 798
set-printer-options 542	transform-rect 799
set-rich-text-pane-char-	tree-view-ensure-visible 649
acter-format 535	tree-view-item-checkbox-
set-rich-text-pane-para-	${ t status} \ 650$
graph-format 538	tree-view-item-children-
set-selection 540	${ t checkbox\text{-}status}\ 651$
set-text-input-pane-	unconvert-color 843
selection 522	undefine-font-alias 800
show-interface 548	uninstall-postscript-
show-pane 549	printer 654
simple-pane-handle 561	unit-transform-p 801
simple-print-port 565	unmap-typeout 655
sorted-object-sorted-by	untransform-distance 802
571	untransform-distances 803
sort-object-items-by 569	untransform-point 803
start-gc-monitor 572	untransform-points 804
stop-gc-monitor 574	update-all-interface-titles
stop-sound 575	655

update-pinboard-object 656 update-screen-interface-	element-interface-for-call- back 173
titles 657	ensure-area-visible 174
update-toolbar 658	find-graph-edge 185
virtual-screen-geometry 658	${ t find-graph-node}\ 186$
wrap-text 675	find-interface 187
wrap-text-for-pane 676 write-external-image 820	find-string-in-collection 188
	${ t get-collection-item}\ 192$
G	get-horizontal-scroll-
:gap initarg 73, 498	parameters 193
generic functions	get-vertical-scroll-parame-
accepts-focus-p 4	ters 197
append-items 7	graph-node-children 199
browser-pane-busy 23	graph-pane-add-graph-node
browser-pane-go-back 23	204
browser-pane-go-forward 23	graph-pane-delete-object 205
browser-pane-navigate 23	graph-pane-delete-objects
browser-pane-property-get 25	205
browser-pane-property-put 25	graph-pane-delete-selected-
browser-pane-refresh 23	objects 206
browser-pane-stop 23	graph-pane-direction 207
calculate-constraints 36	graph-pane-select-graph-
calculate-layout 37	nodes 209
call-editor 41	graph-pane-update-moved-
$\verb choice-selected-item 50 $	objects 210
choice-selected-items 52	highlight-pinboard-object
clone 57	217
collect-interfaces 64	interactive-pane-execute-
collection-find-next-string	command 226
69	interface-display 245
$ t collection ext{-find-string}\ 70$	interface-editor-pane 248
$ t collection ext{-last-search}\ 70$	interface-extend-title 248
collection-search 71	interface-geometry 249
$ exttt{count-collection-items} 85$	interface-keys-style 250
current-document 87	interface-match-p 253
destroy 102	interface-menu-groups 254
display-dialog 107	interface-preserve-state 255
display-tooltip 117	interface-reuse-p 256
draw-pinboard-object 137	interpret-description 260
draw-pinboard-object-high-	invalidate-rectangle 760
lighted 138	itemp 264
draw-pinboard-object-	item-pane-interface-copy-
unhighlighted 138	object 264
drop-object-pane-x 144	list-panel-enabled 283
drop-object-pane-y 144	list-panel-filter-state 284
editor-pane-blink-rate 158	list-panel-unfiltered-items
editor-pane-selected-text	288 locate-interface 300
163	make-container 302
editor-pane-selected-text-p	
164	make-image-access 770
editor-window 165	make-pane-popup-menu 309

manipulate-pinboard 315	redisplay-collection-item 478
map-collection-items 318	1.0
map-pane-children 319	redisplay-interface 479
map-pane-descendant-chil-	reinitialize-interface 481
dren 322	remove-items 483
merge-menu-bars 340	replace-items 484
move-line 343	report-active-component-
non-focus-maybe-capture-	failure 485
gesture 351	scroll 507
non-focus-terminate 353	scroll-if-not-visible-p 511
non-focus-update 354	search-for-item 512
over-pinboard-object-p 384	set-button-panel-enabled-
pane-adjusted-offset 386	items 516
pane-adjusted-position 387	set-display-pane-selection
pane-got-focus 390	522
pane-has-focus-p 390	set-horizontal-scroll-
pane-initial-focus 391	parameters 527
pane-interface-copy-	set-pane-focus 535
object 392	set-scroll-position 508
pane-interface-copy-p 392	set-scroll-range 528, 546
pane-interface-cut-object	set-text-input-pane-selec-
392	tion 544
pane-interface-cut-p 392	set-top-level-interface-
pane-interface-deselect-	geometry 544
all 392	set-vertical-scroll-parame-
pane-interface-deselect-	ters 546
all-p 392	simple-pane-visible-height
pane-interface-paste-	562
object 392	$ exttt{simple-pane-visible-size} 562$
pane-interface-paste-p 392	simple-pane-visible-width
pane-interface-select-all	563
392	sorted-object-sort-by 570
pane-interface-select-	switchable-layout-switch-
all-p 392	able-children 577
pane-interface-undo 392	top-level-interface 631
pane-interface-undo-p 392	top-level-interface-dis-
pane-popup-menu-items 393	play-state 632
pane-string 397	top-level-interface-geome-
parse-layout-descriptor	try 633
398	top-level-interface-geome-
pinboard-object-at-posi-	try-key 634
$\verb tion 408 $	$\verb"top-level-interface-p" 636"$
pinboard-object-graphics-	top-level-interface-save-
$\verb"arg"409"$	geometry-p 636
pinboard-object-overlap-p	${ t tree-view-expanded-p}~650$
410	${ t tree-view-update-an-item}~652$
pinboard-pane-position 411	$\verb tree-view-update-item 652 $
pinboard-pane-size 412	unhighlight-pinboard-object
port-drawing-mode-qual-	653
ity-p 778	update-interface-title 656
print-capi-button 425	$ exttt{validate-rectangle}~805$
print-collection-item 425	geometry slots

\$child $$$ 669	get-font-width function 737
%height% 667	get-graphics-state function 738
%max-height% 668	get-horizontal-scroll-param-
%max-width% 668	eters generic function 193
%min-height% 668	get-origin function 738
%min-width% 667	get-page-area function 194
%object% 669	get-pane 93
%scroll-height% 668	get-printer-metrics function 195
%scroll-horizontal-page-	get-scroll-position function 196
size% 668	get-string-extent function 739
%scroll-horizontal-slug-	get-transform-scale function 740
size% 668	get-vertical-scroll-parame-
%scroll-horizontal-step-	ters generic function 197
size% 668	graph-edge class 198
%scroll-start-x% 668	graph-edge-from accessor function
%scroll-start-y% 668	198
%scroll-vertical-page-size%	graph-edge-to accessor function 198
668	:graphics-args initarg 404
%scroll-vertical-slug-size%	:graphics-options initarg 372
668	graphics-port-background func-
%scroll-vertical-step-size%	tion 740
669	graphics-port-font function 740
%scroll-width% 668	graphics-port-foreground func-
%scroll-x% 669	tion 740
%scroll-y% 669	graphics-port-transform func-
%width% 667	tion 740
% x % 667	graphics-state structure class 741
% y % 667	graphics-state-background
:geometry-change-callback ini-	function 746
targ 228	graphics-state-compositing-
:gesture-callbacks initarg 585	mode function 746
get pane	graphics-state-dash function 746
interface 93	graphics-state-dashed function
get-all-color-names function 836	746
get-bounds function 731	graphics-state-fill-style
get-character-extent function 732	function 746
get-char-ascent function 733	graphics-state-font function 746
get-char-descent function 733	graphics-state-foreground
get-char-width function 734	function 746
get-collection-item generic func-	graphics-state-line-end-
tion 192	style function 746
get-color-alias-translation	graphics-state-line-joint-
function 837	style function 746
get-color-spec function 838	graphics-state-mask function 746
get-constraints function 193	graphics-state-mask-trans-
get-enclosing-rectangle func-	form function 746
tion 734	graphics-state-mask-x function
get-font-ascent function 735	746
get-font-average-width function	graphics-state-mask-y function
736	746
get-font-descent function 736	graphics-state-operation func-
get-font-height function 737	tion 746

graphics-state-pattern func-	nodes generic function 209
tion 746	graph-pane-update-moved-
graphics-state-scale-thick-	objects generic function 210
ness function 746	grid-layout class 211
graphics-state-shape-mode	groupbox 616
function 746	GTK+ resources 83, 168, 529
graphics-state-stipple func-	
tion 746	H
graphics-state-text-mode	
function 746	:has-root-line initarg 640
graphics-state-thickness	:has-title-column-p initarg 211
function 746	: head initary 10
graphics-state-transform	: head-breadth initarg 10
function 746	:head-direction initarg 10
graph-node class 199	: header-args initarg 345
graph-node-children generic	:head-graphics-args initarg 10
function 199	: head-length initarg 10
_	%height% geometry slot 667
graph-node-height accessor func-	:height initarg 500
tion 199	help
graph-node-in-edges accessor	context help 237
function 199	help-callback 233
graph-node-out-edges accessor	:help item in :buttons initarg 593
function 199	: help-callback initarg 228, 229
graph-node-width accessor func-	help-key accessor function 66, 167, 332,
tion 199	623
graph-node-x accessor function 199	:help-key initarg 66, 166, 331, 623
graph-node-y accessor function 199	:help-keys initarg 31
graph-object class 200	:help-string initarg 182
graph-object-element accessor	hide-interface function 216
function 200	hide-pane function 216
graph-object-object accessor	highlight-pinboard-object
function 200	generic function 217
graph-pane class 200	:highlight-style initarg 401
graph-pane-add-graph-node	:hist-addtofavorites
generic function 204	image symbol 281, 624, 644
graph-pane-delete-object	:hist-back
generic function 205	image symbol 281, 624, 644
graph-pane-delete-objects	:hist-favorites
generic function 205	
graph-pane-delete-selected-	image symbol 281, 624, 644 :hist-forward
objects generic function 206	
graph-pane-direction generic	image symbol 281, 624, 644
function 207	:hist-viewtree
graph-pane-edges function 208	image symbol 281, 624, 644
graph-pane-layout-function	:horizontal-scroll initarg 510, 551
accessor function 201	HWND 85, 561
graph-pane-nodes function 208	_
graph-pane-object-at-posi-	I
tion function 209	:iconify-callback initarg 228
graph-pane-roots accessor func-	:ignore-fle-suffices initarg 585
tion 201	image class 750
	image identifiers
graph-pane-select-graph-	5

cancel-button 595 function 221 complete-button 595 :interaction initarg 26, 47 ok-button 594 interaction styles 28 :image initarg 26, 219, 622 interactions image-access-height function 750 for choice 47 image-access-pixel function 751 interactive-pane class 224 image-access-pixels-frominteractive-pane-executebgra function 752 command generic function 226 image-access-pixels-to-bgra interactive-pane-stream accesfunction 753 sor function 224 image-access-transfer-frominteractive-pane-top-levelfunction accessor function 224 image function 754 interactive-stream 225 image-access-transfer-toimage function 755 interactive-stream-stream 225 image-freed-p function 756 interactive-stream-top-level-function 225 :image-function initarg 273, 289, interface class 227 324, 368, 578, 641 :interface initarg 166 interface-activate-callback image-height accessor function 750 :image-height initarg 218, 274, 620, accessor function 230 interface-confirm-destroy-641 image-list class 217 function accessor function 230 :image-lists initarg 273, 289, 368, interface-create-callback 578, 641 accessor function 230 image-loader function 756 interface-customize-toolbar image-pinboard-object class 219 function 244 image-pinboard-object-image interface-default-toolbaraccessor function 219 states accessor function 230 :images initarg 31, 620, 628 interface-destroy-callback image-set class 220 accessor function 230 :image-sets initarg 218 interface-display generic function image-translation function 757 image-width accessor function 750 interface-display-title func-:image-width initarg 218, 274, 620, tion 246 interface-document-modified-641 **IME 373** p function 247 index of selected item 47 interface-drag-image accessor :init-function initarg 62 function 230 :initial-constraints initarg 166 interface-editor-pane generic :initial-focus initarg 229, 269 function 248 :initial-focus-item initarg 47 interface-extend-title generic initialize-dithers function 758 function 248 :in-place-completion-funcinterface-geometry generic function initarg 585 tion 249 :in-place-filter initarg 585 interface-geometry-changeinput focus 4 callback accessor function 230 input method 373 interface-help-callback accessor function 230 :input-model initarg 372 :insert-callback initarg 362 interface-iconified-p function inset-rectangle function 758 inside-rectangle function 759 interface-iconify-callback installed-libraries function 223 accessor function 230, 240 install-postscript-printer interface-keys-style generic

function 250 Interrupt playing a MIDI file 575 interface-match-p generic funcinvalidate-pane-constraints tion 253 function 261 interface-menu-bar-items invalidate-rectangle generic accessor function 230 function 760 invert-transform function 761 interface-menu-groups generic function 254 invoke-command function 261 interface-message-area accesinvoke-untranslated-command sor function 230, 239 function 262 interface-override-cursor item class 262 accessor function 230 item-collection accessor function interface-pathname accessor function 230 item-data accessor function 263 interface-pointer-documenitemp generic function 264 tation-enabled accessor item-pane-interface-copyfunction 230 object generic function 264 interface-preserve-state item-pinboard-object class 266 item-print-function accessor funcgeneric function 255 interface-preserving-statep function 255 :item-print-functions initarg 345 interface-reuse-p generic func-:items initarg 66, 118, 180, 324, 329, tion 256 578, 649 :interfaces class option 101 :items-count-function initarg 66, :interfaces initarg 500 180, 649 interface-title accessor function item-selected accessor function 263 :items-function initarg 324, 329 interface-toolbar-items :items-get-function initarg 66, accessor function 230 180, 649 interface-toolbar-state func-:items-map-function initarg 66, tion 257 180, 649 interface-toolbar-states item-text accessor function 263 accessor function 230 interface-tooltips-enabled accessor function 230 :keep-selection-p initarg 47 interface-visible-p function key press event handler 374 :keyboard-search-callback iniinterface-window-styles targ 273 accessor function 230 :key-function initarg 578 internal scrolling 378 key-press events 374 :internal-border initarg 551 :internal-max-height initarg 167, 406 labelled-arrow-pinboard-:internal-max-widthinitarg 167, object class 267 labelled-line-pinboard-:internal-min-height initarg object class 267 167, 405 labelled-line-text-back-:internal-min-width initarg 167, ground accessor function 267 labelled-line-text-fore-:internet-explorer-callground accessor function 267 back initarg 16 :label-style initarg 182 interpret-description generic :large-image-height initarg 290 function 260

:large-image-width initarg 290	selection-behavior acces-
layout class 268	sor function 274
:layout initarg 227	list-panel-search-with-func-
:layout-args initarg 31	tion function 286
:layout-class initarg 31	list-panel-state-image-func-
layout-description accessor func-	tion accessor function 274
tion 269	list-panel-unfiltered-items
layout-divider-default-size 74, 498	generic function 288
:layout-function initarg 201	list-view class 288
layout-ratios accessor function 74,	list-view-auto-arrange-icons
498	accessor function 290
:layouts class option 93	list-view-auto-reset-column-
layout-x-adjust accessor function	widths accessor function 290
677	list-view-columns accessor func-
:layout-x-adjust initarg 201	tion 290
layout-x-gap accessor function 211	list-view-image-function acces-
layout-x-ratios accessor function	sor function 290
211	list-view-state-image-func-
layout-y-adjust accessor function	tion accessor function 290
677	list-view-subitem-function
:layout-y-adjust initarg 201	accessor function 290
layout-y-gap accessor function 211	list-view-subitem-print-
layout-y-ratios accessor function	functions accessor function
211	290
:leaf-node-p-function initarg 639	list-view-view accessor function 290
line-end-style graphics state parameter 744	load-color-database function 839
line-joint-style graphics state parameter 744	load-cursor function 295
line-pinboard-object class 270	load-icon-image function 763
line-pinboard-object-coordi-	load-image function 765
nates function 271	load-sound function 299
:line-size initarg 509	locate-interface generic function
:line-wrap-face initarg 149	300
:line-wrap-marker initarg 149	lookup pane
LispWorks as ActiveX control 100, 356	interface 93
list-all-font-names function 761	lookup-pane 93
listener-pane class 294	lower-interface function 301
listener-pane-insert-value	
function 295	M
list-known-image-formats func-	Mac OS X Dock 58
tion 762	macros
list-panel class 272	define-color-models 833
list-panel-enabled generic func-	define-command 90
tion 283	define-interface 92
list-panel-filter-state generic	define-layout 98
function 284	define-menu 99
list-panel-image-function	define-ole-control-compo-
accessor function 274	nent 100
list-panel-items-and-filter	display-errors 110
function 285	rectangle-bind 785
list-panel-keyboard-search-	rectangle-bottom 786
callback accessor function 274	rectangle-beight 786
list-panel-right-click-	rectangle-left 787

rectangle-right 787	tion 305
rectangle-top 788	make-graphics-state function 769
rectangle-width 789	make-gray function 839
rect-bind 790	make-hsv function 840
undefine-menu 653 union-rectangle 800	make-icon-resource-image-set function 306
unless-empty-rect-bind 802	make-image function 769
with-atomic-redisplay 659	make-image-access generic function
with-busy-interface 660	770
with-dialog-results 661	make-image-from-port function 771
with-dither 806	make-image-locator function 307
with-document-pages 663	make-menu-for-pane function 307
with-external-metafile 664	make-pane-popup-menu generic
with-geometry 667	function 309
with-graphics-mask 806	make-resource-image-set func-
with-graphics-post-trans-	tion 311
lation 808	make-rgb function 841
with-graphics-rotation 809	make-scaled-general-image-
with-graphics-scale 810	set function 312
with-graphics-state 810	make-scaled-image-set function
with-graphics-transform	313
812	make-sorting-description func-
with-graphics-transform-	tion 314
reset 813	make-sub-image function 772
with-graphics-translation	make-transform function 773
814	manipulate-pinboard generic func-
with-internal-metafile 669	tion 315
with-inverse-graphics 815	map-collection-items generic
with-output-to-printer 671	function 318
without-relative-drawing	map-pane-children generic function
815	319
with-page 672	map-pane-descendant-children
with-page-transform 673	generic function 322
with-pixmap-graphics-port	map-typeout function 323
816	mask graphics state parameter 744
with-print-job 673	mask-transform graphics state parameter
with-random-typeout 674	745
with-transformed-area 817	mask-x graphics state parameter, depre-
with-transformed-point 818	cated 745
with-transformed-points	mask-y graphics state parameter, depre-
819	cated 745
with-transformed-rect 819	:matches-title initarg 181
make-container generic function	:max-characters initarg 584
302	%max-height% geometry slot 668
make-dither function 767	*maximum-moving-objects-to-
make-docking-layout-con-	track-edges* variable 323
troller function 303	:maximum-recent-items initarg 586
make-font-description function	%max-width% geometry slot 668
768	MDI 81, 87, 124
make-foreign-owned-inter-	menu class 324
face function 303	: menu initarg 424
make-general-image-set func-	:menu-bar class option 93

:menu-bar-items initarg 227	N
menu-component class 328	:name initarg 43
:menu-function initarg 424	:navigate-complete-callback
menu-image-function accessor func-	initarg 15
tion 324	:navigate-error-callback ini-
menu-item class 331	targ 16
menu-items accessor function 324	:navigation-callback initarg 585
menu-object class 337	New in LispWorks 6.1
menu-object-enabled accessor func-	all-button argument for prompt -
tion 337	with-list 458
menu-popup-callback accessor func-	:alternating-background ini-
tion 337	targ for list-panel 273
:menus class option 93	:alternative-action-call-
menu-title accessor function 613	back initarg for callbacks 38
menu-title-function accessor func-	apply-in-pane-process-if-
tion 613	$\verb"alive"9$
merge-font-descriptions func-	apply-rotation-around-point
tion 774	681
merge-menu-bars generic function	:auto-arrange-icons initarg for
340	list-view 289
:message initary 615	:automatic-resize initarg for
<pre>:message-area initarg 228 :message-callback initarg 58</pre>	pinboard-object 404
:message-caliback initing 36	:automatic-resize initarg for
message-pane class 342	simple-pane 552
MIDI files	browser-pane 15
interrupting 575	buttons argument for prompt-with-
%min-height% geometry slot 668	list 458
%min-width% geometry slot 667	callbacks argument for prompt-with-
:mnemonic initarg 26, 32, 324, 331	list 458
:mnemonic-escape initarg 27, 32,	can-use-metafile-p 42
324, 332	: change-callback initiary for
:mnemonic-text initarg 27, 32	text-input-range 610
:mnemonic-title initarg 32, 324, 332,	changed behavior of set-object-
615	automatic-resize 534
modal dialogs 108, 417, 661	:color-function initarg for
modify-editor-pane-buffer	list-panel on Cocoa 272 color-with-alpha 829
function 342	compositing-mode graphics state parame-
mono-screen class 343	ter 745
Motif resources 168	:composition-callback initarg
mouse clicks 374	for output-pane 373
mouse coordinates 87	:composition-face initarg for
mouse events 374	editor-pane 149
mouse position 87	copy-area 690
move-line generic function 343	:delete-item-callback initarg
multi-column-list-panel class	for tree-view 640
344	display-pane-selected-text
multi-line-text-input-pane	113
class 349	display-pane-selection 113
Multiple Document Interface 81, 87, 124	display-pane-selection-p 114
multiple-selection interaction	display-tooltip supported on
style 27	CTK ₊ 117

:documentation option in define-interface 93 drag and drop images 524, 750 : drag-image initarg for interface 229 :drawing-mode argument for simple-print-port 566 :drawing-mode argument for with-print-job 674 :drawing-mode argument to create-pixmap-port 694 :drawing-mode argument to with-external-metafile :drawing-mode argument to with-internal-metafile :drawing-mode argument to with-pixmap-graphicsport 816 :drawing-mode initarg for editor-pane 154 :drawing-mode initarg for graph-pane 202 :drawing-mode initarg for output-pane 372 :drawing-mode initarg for pinboard-layout 403 draw-path 705 : drop-callback supported for list-panel and tree-view on Cocoa and GTK+ 552 *editor-pane-compositionselected-range-faceplist* 160 editor-pane-default-composition-callback 160 *editor-pane-default-composition-face* 162 : enhanced-qdi metafile format on Windows 664, 670 :enhanced-plus metafile format on Windows 664, 670 Example illustrating display of fractional and logorithmic values in slider 569 externalize-and-writeimage 719 :finished-launching message callback 60 Graphics state mask can be a path 807

image-access-height 750

image-count argument for makescaled-general-image-set :image-function initarg for tablavout 578 :image-lists initarg for optionpane 368 :image-lists initarg for tablayout 578 Initargs for handling images in listpanel 273 :initial-constraints initarg for element 166 interface-document-modified-p 247 interface-drag-image 230 interface-pathname 230 item-pane-interface-copyobject 264 :keyboard-search-callback initarg for list-panel 273 list-known-image-formats 762 list-panel supports images 272 list-panel-image-function list-panel-search-withfunction 286 list-panel-state-imagefunction 274 list-view-auto-arrangeicons 290 :mask-transform argument in with-graphics-mask 807 *mask-transform* graphics state parameter :maximum-recent-items initarg for text-input-pane 586 none-button argument for promptwith-list 458 pane-screen-internal-geometry 396 :pathname initarg for interface port-drawing-mode-quality-p 778 :print-function initarg for slider 566 :recent-items initarg for textinput-pane 586 :recent-items-mode initarg for text-input-pane 586

image-access-width 750

:recent-items-name initarg for text-input-pane-set-recenttext-input-pane 586 items 602 :redo-items argument to redistext-mode graphics state parameter 745 play-menu-bar 479 :tick-frequency initarg for screen-internal-geometries slider 566 :use-native-input-method iniscreen-monitor-geometries targ for output-pane 373 virtual-screen-geometry 658 :search-field initarg for text-:window-styles initarg for input-pane 586 option-pane 368 :selected-item-function iniwith-graphics-post-translatarg for toolbar-component tion 808 629 with-graphics-transform-:selected-items-function inireset 813 targ for toolbar-component :new-window-callback initarg 15 :node-pane-function initarg 201 :selection-function initarg for :node-pinboard-class initarg 201 toolbar-component 629 non-focus-list-add-filter set-composition-placement function 351 non-focus-list-interface class 518 set-default-use-nativeinput-method 522 non-focus-list-remove-filter set-display-pane-selection function 351 non-focus-list-toggleenable-filter function 350 set-list-panel-keyboardsearch-reset-time 529 non-focus-list-toggle-filter shape-mode graphics state parameter 745 function 351 :show-value-p initiarg for non-focus-maybe-capture-gesslider supported on Windows ture generic function 351 non-focus-terminate generic funcslider-print-function 566 tion 353 slider-tick-frequency 567 non-focus-update generic function sorted-object-sorted-by 571 Symbols loading history images on Winno-selection interaction style 27 dows 281, 624, 644 :number initarg 500 Symbols loading view images on Windows 280, 624, 644 0 tab-layout-image-function %object% geometry slot 669 578 offset-rectangle function 775 : text-background initarg for :ok item in :buttons initarg 592 labelled-line-pinboardok-button image identifier 594 object 267 OLE control 100, 356 text-input-pane-append-OLE embedding 100, 356 recent-items 599 ole-control-add-verbs function text-input-pane-delete-354 recent-items 599 ole-control-close-object functext-input-pane-prependtion 355 recent-items 600 ole-control-component class 356 text-input-pane-recentole-control-component-pane items 601 accessor function 356 text-input-pane-replaceole-control-doc class 358 recent-items 602 ole-control-frame class 359

ole-control-i-dispatch funcoutput-pane-scroll-callback tion 360 accessor function 373 ole-control-insert-object over-pinboard-object-p generic function 361 function 384 ole-control-ole-object func-:override-cursor initarg 228 tion 361 ole-control-pane class 362 ole-control-pane-frame funcpage-setup-dialog function 385 tion 365 :page-size initarg 509 ole-control-pane-simplepane-adjusted-offset generic sink class 365 function 386 ole-control-user-component pane-adjusted-position generic function 366 function 387 operation graphics state parameter 742 :pane-can-scroll initarg 372 option-pane class 367 pane-close-display function 388 option-pane-enabled accessor pane-descendant-child-withfunction 368 focus function 389 option-pane-enabled-posi-:pane-function initarg 356 tions accessor function 368 pane-got-focus generic function 390 option-pane-image-function pane-has-focus-p generic function accessor function 368 option-pane-popup-callback pane-initial-focus generic funcaccessor function 368 tion 391 option-pane-separator-item pane-interface-copy-object accessor function 368 generic function 392 option-pane-visible-itemspane-interface-copy-p generic count accessor function 368 function 392 ordered-rectangle-union funcpane-interface-cut-object tion 775 generic function 392 ordinary scrolling 378 pane-interface-cut-p generic :orientation initarg 119, 211, 476 function 392 :orientation item in :buttons pane-interface-deselect-all initarg 594 generic function 392 output-pane class 371 pane-interface-deselect-alloutput-pane-compositionp generic function 392 callback accessor function pane-interface-paste-object generic function 392 output-pane-create-callpane-interface-paste-p generic back accessor function 373 function 392 output-pane-destroy-callpane-interface-select-all back accessor function 373 generic function 392 output-pane-display-callpane-interface-select-all-p back accessor function 373 generic function 392 output-pane-focus-callback pane-interface-undo generic funcaccessor function 373 tion 392 output-pane-graphicspane-interface-undo-p generic options accessor function function 392 pane-layout accessor function 32, 230 output-pane-input-model :pane-menu initarg 552 accessor function 373 pane-popup-menu-items generic output-pane-resize-callfunction 393 back accessor function 373 :panes class option 93

pane-screen-internal-geomeport-string-height function 780 try function 396 port-string-width function 781 port-width function 781 pane-string generic function 397 pane-supports-menus-with-:position item in :buttons initarg images function 398 :paragraph-format initarg 488 postmultiply-transforms func-:parent initarg 166 tion 782 parse-layout-descriptor generic *ppd-directory* variable 424 function 398 premultiply-transforms function password-pane class 399 password-pane-overwrite-:press-callback initarg 468 character accessor function printable area 673 399 print-capi-button generic function :pathname initarg 229 425 pattern graphics state parameter 743 print-collection-item generic pi-by-2 constant 776 function 425 :pinboard initarg 404 print-dialog function 427 pinboard-layout class 401 print-editor-buffer function 428 pinboard-object class 404 printer-configuration-dialog pinboard-object-activep accesfunction 431 sor function 406 printer-metrics structure class 432 pinboard-object-at-position printer-metrics-devicegeneric function 408 height function 432 printer-metrics-device-width pinboard-object-graphics-arg generic function 409 function 432 pinboard-object-graphicsprinter-metrics-dpi-x function args accessor function 406 pinboard-object-overlap-p printer-metrics-dpi-y function generic function 410 pinboard-object-pinboard accesprinter-metrics-height function sor function 406 pinboard-pane-position generic printer-metrics-left-margin function 411 function 433 printer-metrics-max-height pinboard-pane-size generic function 412 function 433 pixblt function 777 printer-metrics-max-width pixmap-port class 778 function 433 play-sound function 400 printer-metrics-min-left-:plist initarg 43 margin function 433 :popup-callback initarg 337, 367, printer-metrics-min-top-margin function 433 583 printer-metrics-paper-height popup-confirmer function 413 :popup-interface initarg 623 function 433 popup-menu-button class 424 printer-metrics-paper-width popup-menu-button-menu accessor function 433 printer-metrics-top-margin function 424 popup-menu-button-menu-funcfunction 433 printer-metrics-width function tion accessor function 424 port-drawing-mode-quality-p 433 generic function 778 printer-port-handle function 434 port-graphics-state function 779 printer-port-supports-p funcport-height function 780 tion 434

printer-search-path variable 435	range-orientation accessor func- tion 476
print-file function 429	range-pane class 475
:print-function initarg 66, 263,	range-set-sizes function 476
566, 578	range-slug-end accessor function 476
print-rich-text-pane function 430	range-slug-start accessor function 476
print-text function 431	range-start accessor function 476
process	:ratios initarg 73, 498
CAPI 105	read-and-convert-external-
Cocoa Event Loop 106	image function 783
process-pending-messages	read-color-db function 842
function 436	read-external-image function 784
progress-bar class 437	read-sound-file function 477
prompt-for-color function 437	:recent-items initarg 586
prompt-for-confirmation func-	:recent-items-mode initarg 586
tion 438	:recent-items-name initarg 586
prompt-for-directory function	rectangle class 478
440	rectangle-bind macro 785
prompt-for-file function 442	rectangle-bottom macro 786
prompt-for-files function 445	rectangle-height macro 786
prompt-for-font function 446	rectangle-left macro 787
prompt-for-form function 447	rectangle-right macro 787
prompt-for-forms function 449	rectangle-top macro 788
prompt-for-integer function 450	rectangle-union function 788
prompt-for-items-from-list	rectangle-width macro 789
function 451	rect-bind macro 790
prompt-for-number function 452	red Close button
prompt-for-string function 453	on Cocoa 247
prompt-for-symbol function 455	redisplay-collection-item
prompt-for-value function 457	generic function 478
prompt-with-list function 458	redisplay-interface generic func-
prompt-with-list-non-focus	tion 479
function 461	redisplay-menu-bar function 479
prompt-with-message function 466	redraw-pinboard-layout function 480
:protected-callback initarg 488 push-button class 467	redraw-pinboard-object function 481
push-button-panel class 469	register-image-load-function function 790
Q	register-image-translation function 791
quit function 60	reinitialize-interface generic
quit-interface function 470	function 481
R	:remapped initarg 623
radio-button class 472	remove-capi-object-property
radio-button-panel class 473	function 482
raise-interface function 474	remove-items generic function 483
range-callback accessor function	replace-dialog function 484
476	replace-items generic function 484
range-end accessor function 476	report-active-component-
- ang - and accessor ranction 170	failure generic function 485

reset-image-translation-	tion 501
table function 792	screen-active-p function 501
resizable	screen-depth accessor function 500
dialogs 237	screen-height accessor function 500
elements 170	screen-height-in-millimeters
windows 231	accessor function 500
:resize-callback initarg 373	screen-interfaces accessor func-
resizing 170, 231, 237	tion 123, 500
resolution	screen-internal-geometries
of display 502	function 503
of printer 195	screen-internal-geometry func-
:retain-expanded-nodes initarg	tion 505
639	screen-logical-resolution
:retract-callback initarg 28, 38	function 502
Return key 415	screen-monitor-geometries
reuse-interfaces-p function 487	function 504
rich-text-pane class 487	screen-number accessor function 500
rich-text-pane-change-call-	screens function 506
back accessor function 488	screen-width accessor function 500
rich-text-pane-character-	screen-width-in-millimeters
format function 490	accessor function 500
rich-text-pane-limit accessor	scroll generic function 507
function 488	scroll-bar class 509
rich-text-pane-operation func-	scroll-bar-line-size accessor
tion 491	function 509
rich-text-pane-paragraph- format function 495	scroll-bar-page-size accessor function 509
_	scroll-callback initarg 372
rich-text-pane-text accessor func- tion 488	%scroll-height% geometry slot 668
rich-text-version function 496	%scroll-horizontal-page-
right-angle-line-pinboard-	size% geometry slot 668
object class 496	%scroll-horizontal-slug-
:right-click-extended-match	size% geometry slot 668
initarg 640	%scroll-horizontal-step-
:right-click-selection-	size% geometry slot 668
behavior initarg 272	scroll-if-not-visible-p generic
:roots initarg 201, 639	function 511
row-layout class 497	:scroll-if-not-visible-pini-
row-layout-divider 498	targ 552
:rows initarg 211	scrolling
	built-in 196
S	internal 378
:save-name initarg 362	ordinary 378
scale	%scroll-start-x% geometry slot 668
for a printer 195	%scroll-start-y% geometry slot 668
scale-thickness graphics state parameter 744	%scroll-vertical-page-size%
scaling	geometry slot 668
while printing 673	%scroll-vertical-slug-size%
screen	geometry slot 668
usable region of 505	%scroll-vertical-step-size%
screen class 499	geometry slot 669
screen-active-interface func-	%scroll-width% geometry slot 668

```
%scroll-x% geometry slot 669
                                         set-geometric-hint function 526
%scroll-y% geometry slot 669
                                         set-graphics-port-coordi-
:search-field initarg 586
                                                nates function 794
search-for-item generic function
                                         set-graphics-state function 795
                                         set-hint-table function 526
:selected initarg 26, 263
                                         set-horizontal-scroll-param-
:selected-disabled-image ini-
                                                eters generic function 527
                                         set-interactive-break-ges-
:selected-disabled-images
                                                tures function 528
       initarg 31
                                         set-list-panel-keyboard-
:selected-function initarg 332
                                                search-reset-time func-
:selected-image initarg 26, 622
:selected-images initarg 31
                                         set-object-automatic-resize
:selected-item initarg 47, 649
                                                function 530
:selected-item-function ini-
                                         set-pane-focus generic function 535
       targ 329, 629
                                         set-printer-metrics function 541
:selected-items initarg 47
                                         set-printer-options function 542
:selected-items-function ini-
                                         set-rich-text-pane-charac-
       targ 329, 629
                                                 ter-format function 535
selecting nth item 47
                                         set-rich-text-pane-para-
selection function 512
                                                graph-format function 538
:selection initarg 47
                                         set-scroll-position generic func-
:selection-callback initarg 28,
                                                tion 508
       38, 578
                                         set-scroll-range generic function
selection-empty function 514
                                                528, 546
:selection-functioninitarg 329,
                                         set-selection function 540
                                         set-text-input-pane-selec-
                                                tion function 522
separation function 793
:separator-item initarg 368
                                         set-text-input-pane-selec-
set-application-interface
                                                tion generic function 544
       function 514
                                         set-top-level-interface-
set-button-panel-enabled-
                                                geometry generic function 544
       items generic function 516
                                         :setup-callback-argument ini-
set-clipboard function 516
                                                targ 337
set-composition-placement
                                         set-vertical-scroll-parame-
       function 518
                                                ters generic function 546
set-confirm-quit-flag function
                                         shape-mode graphics state parameter 745
                                         shell-pane class 547
                                         shell-pane-command accessor func-
set-default-editor-pane-
       blink-rate function 519
                                                tion 547
set-default-image-load-
                                         show-interface function 548
       function function 793
                                         show-pane function 549
set-default-interface-pre-
                                         :show-value-p initarg 566, 570
       fix-suffix function 520
                                         simple-layout class 549
set-default-use-native-
                                         simple-network-pane class 550
       input-method function 522
                                         simple-pane class 550
set-display-pane-selection
                                         simple-pane-background accessor
       generic function 522
                                                function 552
set-drop-object-supported-
                                         simple-pane-cursor accessor func-
       formats function 523
                                                tion 552
set-editor-parenthesis-col-
                                         simple-pane-drag-callback
       ors function 525
                                                accessor function 552
```

simple-pane-drop-callback accessor function 552	standard image symbol :std-copy 280, 624, 643
simple-pane-enabled accessor func-	:std-cut 280, 624, 643
tion 182, 552, 631	:std-delete 280, 624, 643
simple-pane-font accessor function	:std-file-new 280, 624, 644
552	:std-file-open 280, 624, 644
simple-pane-foreground accessor	:std-file-save 280, 624, 644
function 552	:std-find 280, 624, 644
simple-pane-handle function 561	:std-help 280, 624, 644
simple-pane-horizontal-	:std-paste 280, 624, 643
scroll accessor function 552	:std-print 280, 624, 644
simple-pane-scroll-callback	:std-print-pre 280, 624, 644
accessor function 552	:std-properties 280, 624, 644
simple-pane-vertical-scroll	:std-redo 280, 624, 643
accessor function 552	:std-replace 280, 624, 644
simple-pane-visible-border	:std-undo 280, 624, 643
accessor function 552	:start initarg 475, 610
simple-pane-visible-height	start-gc-monitor function 572
generic function 562	:start-point initarg 566
simple-pane-visible-size	:start-x initarg 271
generic function 562	:start-y initarg 271
simple-pane-visible-width	:state-image-function initarg
generic function 563	273, 289, 641
simple-pinboard-layout class 564	:state-image-height initarg 274,
simple-print-port function 565	290, 641
single-selection interaction style	:state-image-width initarg 274,
27	290, 641
:sinks initarg 363	static-layout class 573
slider class 566	:status-text-change-callback
slider-print-function accessor	initarg 15
function 566	:std-copy
slider-show-value-paccessor func-	image symbol 280, 643
tion 567	:std-cut
slider-start-point accessor func-	image symbol 280, 643
tion 567	:std-delete
slider-tick-frequency accessor	image symbol 280, 643
function 567	:std-file-new
:slug-end initarg 475	image symbol 280, 644
•	:std-file-open
:slug-start initarg 475	
: small-image-height initary 290	image symbol 280, 644
:small-image-width initarg 290	:std-file-save
sorted-object class 570	image symbol 280, 644
sorted-object-sort-by generic	:std-find
function 570	image symbol 280, 644
sorted-object-sorted-by func-	:std-help
tion 571	image symbol 280, 644
sort-object-items-by function 569	:std-paste
:source-interfaces class option	image symbol 280, 643
101	:std-print
special slots	image symbol 280, 644
container 124	:std-print-pre
windows-menu 124	image symbol 280, 644

:std-properties	text-input-pane class 584
image symbol 280, 644	text-input-pane-append-
:std-redo	recent-items function 599
image symbol 280, 643	text-input-pane-before-
:std-replace	change-callback accessor
image symbol 280, 644	function 597
:std-undo	text-input-pane-buttons-
image symbol 280, 643	enabled accessor function 586
stipple graphics state parameter 743	text-input-pane-callback acces-
stop-gc-monitor function 574	sor function 586
stop-sound function 575	text-input-pane-caret-posi-
:stream initarg 72	tion accessor function 586
streams 72	text-input-pane-change-call-
:stretch-text-p initarg 620	back accessor function 586
structure classes	text-input-pane-complete-
graphics-state 741	text function 604
printer-metrics 432	text-input-pane-completion-
: subitem-function initarg 289	function accessor function 586
:subitem-print-functions ini-	
	text-input-pane-confirm-
targ 289	change-function accessor
switchable-layout class 575	function 586
switchable-layout-combine-	text-input-pane-copy function 605
child-constraints	text-input-pane-cut function 605
accessor function 575	text-input-pane-delete function
switchable-layout-switch-	606
able-children generic	text-input-pane-delete-
function 577	recent-items function 599
switchable-layout-visible-	text-input-pane-editing-
child accessor function 575	callback accessor function 586
	text-input-pane-enabled acces-
T	sor function 586
tab-layout class 577	text-input-pane-in-place-
tab-layout-combine-child-	complete function 606
constraints accessor func-	text-input-pane-max-charac-
tion 578	ters accessor function 586
tab-layout-image-function	text-input-pane-navigation-
accessor function 578	callback accessor function 586
tab-layout-panes function 582	text-input-pane-paste function
tab-layout-visible-child	607
function 582	text-input-pane-prepend-
tab-layout-visible-child-	recent-items function 600
function accessor function	text-input-pane-recent-items
	function 601
578	text-input-pane-replace-
tabstops 4	recent-items function 602
test-function initary 66	text-input-pane-selected-
: text initarg 112, 148, 181, 263, 488,	text function 113, 608
584, 610, 612	text-input-pane-selection
:text-background initarg 267	function 113, 608
:text-change-callback initarg	
586	text-input-pane-selection-p
: text-foreground initarg 267	function 114, 609
text-input-choice class 583	text-input-pane-set-recent-

items function 602 toolbar-button class 622 text-input-pane-text accessor toolbar-button-dropdown-menu function 586 accessor function 623 toolbar-button-dropdowntext-input-range class 610 text-input-range-callback menu-function accessor funcaccessor function 610 tion 623 text-input-range-callbacktoolbar-button-dropdowntype accessor function 610 menu-kind accessor function text-input-range-changecallback accessor function 610 toolbar-button-image accessor text-input-range-end accessor function 623 function 610 toolbar-button-popup-intertext-input-range-start accessor face accessor function 623 function 610 toolbar-button-selectedtext-input-range-value accessor image accessor function 623 function 610 toolbar-component class 628 text-input-range-wraps-p accestoolbar-flat-p accessor function 620 :toolbar-items initarg 229 sor function 610 :text-limit initarg 488 toolbar-object class 630 text-mode graphics state parameter 745 toolbar-object-enabled-functhickness graphics state parameter 744 tion accessor function 631 :tick-frequency initarg 566 :toolbar-states initarg 229 title bar :toolbar-title initarg 552 removal 235 :tooltip initarg 622 :tooltips initarg 620, 629 :title initarg 227, 613, 614 :title-adjust initarg 190, 615 :top-level-function initarg 224 :title-args initarg 614 :top-level-hook initarg 229 :title-change-callback initarg top-level-interface generic function 631 titled-menu-object class 613 top-level-interface-displaytitled-object class 614 state generic function 632 titled-object-message accessor top-level-interface-external-border accessor function function 615 titled-object-message-font accessor function 240, 615 top-level-interface-geometry titled-object-title accessor funcgeneric function 633 tion 615 top-level-interface-geometitled-object-title-font accestry-key generic function 634 sor function 615 top-level-interface-p generic titled-pane 617 function 636 titled-pane-message 617 top-level-interface-savetitled-pane-title 617 geometry-p generic function titled-pinboard-object class 618 :title-font initarg 614 top-level-interface-trans-:title-function initarg 613 parency accessor function 230 tracking-pinboard-layout class :title-gap initarg 190, 615 title-pane class 612 637 transform graphics state parameter 742 title-pane-text accessor function 612 transform type 795 :title-position initarg 615 transform-area function 796 transform-distance function 796 : to initarg 198 toolbar class 620 transform-distances function 797

transform-is-rotated function tion accessor function 642 tree-view-update-an-item transform-point function 798 generic function 652 transform-points function 798 tree-view-update-item generic transform-rect function 799 function 652 :transparency initarg 229 : type initarg 497 tree-view class 639 types tree-view-action-callbackfont 724 expand-p accessor function font-description 725 transform 795 tree-view-checkbox-changecallback accessor function IJ 642 unconvert-color function 843 tree-view-checkbox-childundefine-font-alias function 800 function accessor function undefine-menu macro 653 unhighlight-pinboard-object tree-view-checkbox-initialgeneric function 653 status accessor function 642 :uniform-size-p initarg 73, 498 tree-view-checkbox-next-map uninstall-postscript-printer accessor function 642 function 654 tree-view-checkbox-parentunion-rectangle macro 800 function accessor function *unit-transform* variable 801 unit-transform-p function 801 tree-view-checkbox-status unless-empty-rect-bind macro accessor function 642 tree-view-children-funcunmap-typeout function 655 tion accessor function 642 untransform-distance function 802 tree-view-ensure-visible untransform-distances function function 649 tree-view-expanded-p generic untransform-point function 803 function 650 untransform-points function 804 tree-view-expandp-function update-all-interface-titles accessor function 642 function 655 tree-view-has-root-line :update-commands-callback iniaccessor function 642 targ 15 tree-view-image-function update-interface-title generic accessor function 642 function 656 tree-view-item-checkboxupdate-pinboard-object function status function 650 tree-view-item-children-*update-screen-interfacescheckbox-status function hooks* variable 657 update-screen-interfacetree-view-leaf-node-p-functitles function 657 tion accessor function 642 update-toolbar function 658 tree-view-retain-expanded-:url initarg 16 nodes accessor function 642 :use-images initarg 274, 641 tree-view-right-click-:use-large-images initarg 289 extended-match accessor :use-native-input-method inifunction 642 targ 155, 373 tree-view-roots accessor function :user-component initarg 362 :use-small-images initarg 290 tree-view-state-image-func-:use-state-images initarg 274, 290,

641	image symbol 280, 624, 644
	:view-sort-date
V	image symbol 280, 624, 644
validate-rectangle generic func-	:view-sort-name
tion 805	image symbol 280, 624, 644
variables	:view-sort-size
color-database 827	image symbol 280, 624, 644
*default-editor-pane-line-	:view-sort-type
wrap-marker* 89	image symbol 280, 624, 644
*default-image-translation-	virtual-screen-geometry func-
table* 695, 758	tion 658
*echo-area-cursor-inactive-	:visible-border initarg 551
style* 145	:visible-child initarg 575
*editor-cursor-active-	:visible-child-function initarg
style* 147	578
editor-cursor-color 146	:visible-items-count initarg 367,
editor-cursor-drag-style	583
147	:visible-max-height initarg 167,
*editor-cursor-inactive-	405
style* 148	:visible-max-width initarg 167, 405
*editor-pane-composition-	:visible-min-height initarg 167,
selected-range-face-	405
plist* 160	:visible-min-width initarg 167, 405
*editor-pane-default-compo-	5 ,
sition-face* 162	W
*maximum-moving-objects-to-	WAV sound files 299
track-edges* 323	:widget-name initarg 166
ppd-directory 424	%width% geometry slot 667
printer-search-path 435	:width initarg 500
unit-transform 801	windoid 236
*update-screen-interfaces-	Window handle 85, 561
hooks* 657	window title
:vertical-adjustment initarg 190	removal 235
:vertical-gap initarg 190	window-modal dialogs 108, 417, 661
:vertical-scroll initarg 510, 551	Windows history image symbol
:view initarg 289	:hist-addtofavorites 281, 624,
:view-class initarg 62	644
:view-details	:hist-back 281, 624, 644
image symbol 280, 624, 644	:hist-favorites 281, 624, 644
:view-large-icons	:hist-forward 281, 624, 644
image symbol 280, 624, 644	:hist-viewtree 281, 624, 644
:view-list	Windows view image symbol
image symbol 280, 624, 644	:view-details 280, 624, 644
:view-net-connect	:view-large-icons 280, 624, 644
image symbol 281, 624, 644	:view-list 280, 624, 644
:view-net-disconnect	:view-net-connect 281, 624, 644
image symbol 281, 624, 644	:view-net-disconnect 281, 624,
:view-new-folder	644
image symbol 281, 624, 644	:view-new-folder 281, 624, 644
:view-parent-folder	:view-parent-folder 281, 624,
image symbol 281, 624, 644	644
·view-small-icons	:view-small-icons 280, 624, 644

```
:view-sort-date 280, 624, 644
                                         :wrap-style initarg 149
  :view-sort-name 280, 624, 644
                                         wrap-text function 675
  :view-sort-size 280, 624, 644
                                         wrap-text-for-pane function 676
  :view-sort-type 280, 624, 644
                                         write-external-image function 820
windows-menu 125
windows-menu special slot 124
                                         X
:window-styles initarg 229, 368
                                         %x% geometry slot 667
with-atomic-redisplay macro
                                         :x initarg 166, 405
       659
                                         X window ID 85, 561
with-busy-interface macro 660
                                         X Window System
with-dialog-results macro 661
                                           display 81
with-dither macro 806
                                           fallback resources 81
with-document-pages macro 663
                                         :x-adjust initarg 677
with-external-metafile macro
                                         :x-gap initarg 211, 550
                                         :x-ratios initarg 211
with-geometry macro 667
                                         :x-uniform-size-p initarg 211
with-graphics-mask macro 806
                                         x-y-adjustable-layout class 677
with-graphics-post-transla-
       tion macro 808
                                         Y
with-graphics-rotation macro
                                         %y% geometry slot 667
                                         : y initarg 166, 405
with-graphics-scale macro 810
                                         :y-adjust initarg 677
with-graphics-state macro 810
                                         :y-gap initarg 211
with-graphics-transform
                                         :y-ratios initarg 211
       macro 812
                                         :y-uniform-size-p initarg 211
with-graphics-transform-
       reset macro 813
                                         7.
with-graphics-translation
                                         Z-order
       macro 814
                                           of interfaces 65
with-internal-metafile macro
                                           of pinboard-objects 270, 402
with-inverse-graphics macro
with-output-to-printer macro
without-relative-drawing
       macro 815
with-page macro 672
with-page-transform macro 673
with-pixmap-graphics-port
       macro 816
with-print-job macro 673
with-random-typeout macro 674
with-transformed-area macro
with-transformed-point macro
       818
with-transformed-points
       macro 819
with-transformed-rect macro
       819
:wraps-p initarg 610
```