## Vector products

$$\mathbf{a} \cdot \mathbf{b} = ab \cos \theta$$

$$\mathbf{a} \times \mathbf{b} = ab\sin\theta\hat{\mathbf{n}}$$

$$\mathbf{a} \times \mathbf{b} = -\mathbf{b} \times \mathbf{a}$$
 and  $\mathbf{a} \times \mathbf{a} = \mathbf{0}$ 

$$a \times (b \times c) = b(a \cdot c) - c(a \cdot b)$$

#### **Suffix notation**

- 1. A suffix that appears <u>twice</u> implies a summation.
- 2. Any suffix <u>cannot appear</u> more than twice in any term.

We define the **Kronecker delta** as:

$$\delta_{ij} = \left\{ \begin{array}{ll} 1 & i = j \\ 0 & i \neq j \end{array} \right.$$

and the Levi-Civita as:

$$\epsilon_{ijk} = \left\{ \begin{array}{ll} +1 & 123, 312, 231 \\ -1 & 132, 213, 321 \\ 0 & \text{repeat indices.} \end{array} \right.$$

Consequently:

$$\epsilon_{ijk} = \epsilon_{kij} = \epsilon_{jki}$$
$$= -\epsilon_{ijk} = -\epsilon_{ijk} = -\epsilon_{ijk}$$

and we have the following identities:

$$\boldsymbol{a} = \sum_{i=1}^{3} a_i \boldsymbol{e}_i = a_i \boldsymbol{e}_i$$

 $A\mathbf{x} = a_{ij}x_j\mathbf{e}_i$  for  $m \times n$  matrix A

$$\delta_{ii} = 3$$

$$[\ldots]_i \delta_{ik} = [\ldots]_k$$

$$e_i \cdot e_j = \delta_{ij}$$

$$e_i \times e_j = \epsilon_{ijk} e_k$$

$$\boldsymbol{a} \times \boldsymbol{b} = \epsilon_{ijk} a_i b_k \boldsymbol{e}_i$$

$$\boldsymbol{a} \cdot (\boldsymbol{b} \times \boldsymbol{c}) = \epsilon_{ijk} a_i b_j c_k$$

$$\epsilon_{ijk}\epsilon_{klm} = \delta_{il}\delta_{jm} - \delta_{im}\delta_{jl}$$

$$\epsilon_{ijk}\epsilon_{ijl} = 2\delta_{kl}$$
 and  $\epsilon_{ijk}\epsilon_{ijk} = 6$ .

### **Transformations**

Let matrix L relate basis  $\{e_i\}$  to basis  $\{e'_i\}$  with rule:

$$e'_i = \ell_{ij}e_j$$
 where  $(L)_{ij} = \ell_{ij}$ .

Then  $L^T L = L L^T = I$ , and:

$$\ell_{ik}\ell_{jk} = \ell_{ki}\ell_{kj} = \delta_{ij}$$

$$p'_i = \ell_{ij} p_j$$
 for  $\boldsymbol{p} = p_i \boldsymbol{e}_i = p'_i \boldsymbol{e}'_i$ .

#### Tensors

A rank 3 tensor is defined as:

$$T'_{ijk} = \ell_{ip}\ell_{jq}\ell_{kr}T_{pqr}$$

which relates frame S in  $\{e_i\}$  to frame S' in  $\{e'_i\}$  with rule  $e'_i = \ell_{ij}e_j$ , etc.

Properties of tensors:

- 1. The <u>addition</u> of two rank n tensors is also a rank n tensor.
- 2. The <u>multiplication</u> of a rank m tensor with a rank n tensor yields a rank m + n tensor.
- 3. If  $T_{ijk...s}$  is a rank m tensor then  $T_{iik...s}$  is a rank m-2 tensor.
- 4. If  $T_{ij}$  is a tensor then  $T_{ji}$  is also a tensor. Explicitly:

$$T'_{ij} = \ell_{ip}\ell_{jq}T_{pq} \implies T' = LTL^T$$
$$T'_{ii} = \ell_{jp}\ell_{iq}T_{pq}.$$

## Symmetric tensors

 $T_{ij}$  is a symmetric tensor when  $T_{ij} = T_{ji}$  in frame S. Then  $T'_{ij} = T'_{ji}$  in frame S'.

Similarly  $T_{ij}$  is an anti-symmetric tensor if  $T_{ij} = -T_{ji}$  and  $\overline{T'_{ij}} = -T'_{ji}$ .

Finally any tensor can be written as a sum of symmetric and anti-symmetric parts:

$$T_{ij} = \frac{1}{2}(T_{ij} + T_{ji}) + \frac{1}{2}(T_{ij} - T_{ji}).$$

#### Quotient theorem

Consider 9 entities  $T_{ij}$  in frame S and  $T'_{ij}$  in frame S'. Let  $b_i = T_{ij}a_j$  where  $a_j$  is a vector. If  $b_i$  always transforms as a vector then  $T_{ij}$  is a rank 2 tensor.

Generalising, let  $R_{ijk...r}$  be a rank m tensor and  $T_{ijk...s}$  a set of  $3^n$  numbers where n > m. If  $T_{ijk...s}R_{ijk...r}$  is a rank n - m tensor then  $T_{ijk...s}$  is a rank n tensor.

# Matrices

We define a  $m \times n$  matrix A as  $(A)_{ij} = a_{ij}$  where i = 1, ..., m and j = 1, ..., n.

- $\operatorname{Tr} A = a_{ii}$
- $\bullet$   $(A^T)_{ij} = a_{ii}$
- $\bullet \ (AB)^T = B^T A^T$
- $(I)_{ij} = \delta_{ij}$

The determinant of a  $3 \times 3$  matrix A is:

$$\det A = \begin{vmatrix} a_{11} & a_{12} & a_{13} \\ a_{21} & a_{22} & a_{23} \\ a_{31} & a_{32} & a_{33} \end{vmatrix}$$
$$= \epsilon_{lmn} a_{1l} a_{2m} a_{3n}$$
$$= \epsilon_{lmn} a_{l1} a_{m2} a_{n3}.$$

Furthermore:

$$\epsilon_{ijk} \det A = \epsilon_{lmn} a_{il} a_{jm} a_{kn}$$

$$\epsilon_{lmn} \det A = \epsilon_{ijk} a_{il} a_{jkm} a_{kn}$$

$$\det A = \frac{1}{3!} \epsilon_{ijk} \epsilon_{lmn} a_{il} a_{jm} a_{kn}.$$

Properties of determinants:

- 1. Adding rows to each other does not change the determinant.
- 2. Interchanging two rows changes determinant signs.
- 3.  $\det A = \det A^T$
- 4.  $det(AB) = det A \cdot det B$

These also apply to columns. Finally:

$$\epsilon_{ijk}\epsilon_{lmn} \det A = \begin{vmatrix} a_{il} & a_{im} & a_{in} \\ a_{jl} & a_{jm} & a_{jn} \\ a_{kl} & a_{km} & a_{kn} \end{vmatrix}$$

and setting A = I yields:

$$\epsilon_{ijk}\epsilon_{lmn} = \left| \begin{array}{ccc} \delta_{il} & \delta_{im} & \delta_{in} \\ \delta_{jl} & \delta_{jm} & \delta_{jn} \\ \delta_{kl} & \delta_{km} & \delta_{kn} \end{array} \right|.$$

## Linear equations

Let  $\mathbf{y} = A\mathbf{x}$ . Then  $x_i = A_{ij}^{-1}y_i$  with:

$$\begin{split} A_{ij}^{-1} &= \frac{1}{2} \frac{1}{\det A} \epsilon_{imn} \epsilon_{jpq} a_{pm} a_{qn} \\ &= \frac{1}{\det A} C_{ij}^T \end{split}$$

where C is the cofactor matrix of A.

#### Pseudotensors

A rank 2 pseudotensor is defined as:

$$T'_{ij} = (\det L)\ell_{ip}\ell_{jq}T_{pq}$$

where  $(L)_{ij} = \ell_{ij}$  and  $\det L = \pm 1$ .

Pseudovectors are rank 1 pseudotensors.

## Invariant tensors

Tensor T is <u>invariant</u> or isotropic if:

$$T_{ijk...} = \ell_{i\alpha}\ell_{j\beta}\ell_{k\gamma}\cdots T_{\alpha\beta\gamma...}$$

for every orthogonal matrix L.

- If  $a_{ij}$  is a rank 2 invariant tensor then  $a_{ij} = \lambda \delta_{ij}$ .
- The most general rank 3 invariant pseudotensor is  $a_{ijk} = \lambda \epsilon_{ijk}$ . There are no rank 3 invariant true tensors.
- Invariant true tensors can only be even ranked.
- Invariant pseudotensors can only be odd ranked.

#### Rotation tensors

The clockwise <u>rotation</u> of position vector x to y about unit vector  $\hat{n}$  is given by:

$$y_i = R_{ij}(\theta, \hat{\boldsymbol{n}})x_j$$

$$R_{ij}(\theta, \hat{\boldsymbol{n}}) = \delta_{ij} \cos \theta + (1 - \cos \theta) n_i n_j - \epsilon_{ijk} n_k \sin \theta$$

and is the rotation tensor.

#### Reflections and inversions

The <u>reflection</u> of vector  $\boldsymbol{x}$  to  $\boldsymbol{y}$  in plane with unit vector  $\hat{\boldsymbol{n}}$  is:

$$y_i = \sigma_{ij} x_j$$

$$\sigma_{ij} = \delta_{ij} - 2n_i n_j.$$

The <u>inversion</u> of vector x to y is given by y = -x and is defined as:

$$y_i = P_{ij}x_j$$

$$P_{ij} = \delta_{ij}$$
.

## **Projections**

We define P to be a <u>parallel</u> projection operator to vector  $\boldsymbol{u}$  if:

$$Pu = u$$
 and  $Pv = 0$ 

where  $\boldsymbol{u} \cdot \boldsymbol{v} = \boldsymbol{0}$ . Then:

$$P_{ij} = \frac{u_i u_j}{u^2}.$$

Similarly we define Q to be an <u>orthogonal</u> projection to vector  $\boldsymbol{u}$  if:

$$Q\mathbf{u} = \mathbf{0}$$
 and  $Q\mathbf{v} = \mathbf{v}$ .

Here Q = I - P.

### Inertia tensors

Let L denote the angular momentum of a rigid body about the origin of mass m, volume V and density  $\rho$  at position r with velocity v. Then:

$$L_i = I_{ij}\omega_i$$

$$I_{ij} = I_{ij}(O) = \int_{V} \rho(r^2 \delta_{ij} - x_i x_j) dV$$

where  $I_{ij}(O)$  is the inertia tensor about the origin. The <u>kinetic energy</u> of such a body is:

$$T = \frac{1}{2} I_{ij} \omega_i \omega_j = \frac{1}{2} \mathbf{L} \cdot \boldsymbol{\omega}.$$

## Parallel axis theorem

Consider the same rigid body now with centre of mass G and let  $\overrightarrow{OG} = \mathbf{R}$ . Then:

$$I_{ij}(O) = I_{ij}(G) + M(R^2 \delta_{ij} - X_i X_j)$$
$$M = \int_V \rho'(\mathbf{r}') dV'.$$

### Diagonalisation

Let  $L = I_{ij}\omega_j$  where  $I_{ij}$  is a rank 2 tensor and let  $L = \lambda \omega$ . Then:

$$(I_{ij} - \lambda \delta_{ij})\omega_j = 0 \implies \det(I_{ij} - \lambda \delta_{ij}) = 0$$

where expanding this gives:

$$P - Q\lambda + R\lambda^2 - \lambda^3 = 0$$

for  $P = \det I$ ,  $Q = \frac{1}{2}[(\operatorname{tr} I)^2 - \operatorname{tr}(I^2)]$  and  $R = \operatorname{tr} I$  given tensor I.

# Real symmetric tensors

Let rank 2 real symmetric tensor T be diagonalisable with real eigenvalues  $\lambda^{(i)}$  and orthonormal eigenvectors  $\boldsymbol{\ell}^{(i)}$  where i=1,2,3. Let transformation matrix be:

$$L_{ij} = \ell_j^{(i)} = \begin{pmatrix} \ell_1^{(1)} & \ell_2^{(1)} & \ell_3^{(1)} \\ \ell_1^{(2)} & \ell_2^{(2)} & \ell_3^{(2)} \\ \ell_1^{(3)} & \ell_2^{(3)} & \ell_3^{(3)} \end{pmatrix}_{ij}$$

and always defined such that  $\det L = +1$  which transforms frame  $S \to S'$ .

Then since  $T_{pq}\ell_q^{(i)} = \lambda^{(i)}\ell_p^{(i)}$ :

$$T'_{ij} = \ell_{ip}\ell_{jq}T_{pq}$$

$$= \lambda^{(i)} \delta_{ij} = \begin{pmatrix} \lambda^{(1)} & 0 & 0 \\ 0 & \lambda^{(2)} & 0 \\ 0 & 0 & \lambda^{(3)} \end{pmatrix}_{ii}.$$

# Taylor expansions

In the one-dimensional case we have:

$$f(x) = \sum_{n=0}^{\infty} \frac{1}{n!} f^{(n)}(a) (x - a)^n$$

and is f expanded about x = a.

Trignometric expansions are in radians!

$$\therefore f(x+a) = \sum_{n=0}^{\infty} \frac{1}{n!} f^{(n)}(x) a^n$$
$$= \exp\left(a \frac{d}{dx}\right) f(x)$$

Then for three dimensions:

$$\phi(\mathbf{r} + \mathbf{a}) = \sum_{n=0}^{\infty} \frac{1}{n!} (\mathbf{a} \cdot \nabla_r)^n \phi(\mathbf{r})$$
$$= \exp(\mathbf{a} \cdot \nabla_r) \phi(\mathbf{r}).$$

## Curvilinear coordinates

Let  $x_i$  denote Cartesian coordinates and  $u_i$  denote curvilinear coordinates. Then:

$$(x_1, x_2, x_3) \rightarrow (u_1, u_2, u_3)$$

where each  $u_i = u_i(x_1, x_2, x_3)$  and:

$$r = x_1 e_1 + x_2 e_2 + x_3 e_3$$
  
=  $u_1 e_{u_1} + u_2 e_{u_2} + u_3 e_{u_3}$ .

#### Scale factors

Let  $u_1 \to u_1 + du_1$  in  $\mathbf{r} = \mathbf{r}(u_1, u_2, u_3)$ . Then  $d\mathbf{r}$  in  $\mathbf{r} \to \mathbf{r} + d\mathbf{r}$  is defined as:

$$\mathrm{d}\boldsymbol{r} = \frac{\partial \boldsymbol{r}}{\partial u_1} \mathrm{d}u_1 := h_1 \boldsymbol{e}_1 \mathrm{d}u_1.$$

 $h_1$  is the scale factor of unit vector  $e_1$ :

$$h_1 = \left| \frac{\partial \boldsymbol{r}}{\partial u_1} \right| \text{ and } \boldsymbol{e}_1 = \frac{1}{h_1} \frac{\partial \boldsymbol{r}}{\partial u_1}.$$

If  $e_i \cdot e_j = \delta_{ij}$  then  $u_i$  is an **orthogonal** curvilinear coordinate system.

## Vector and arc length

The vector length  $d\mathbf{r}$  of  $\mathbf{r}$  is defined as:

$$\mathrm{d}\boldsymbol{r} = \sum_{i=1}^{3} h_i \mathrm{d}u_i \boldsymbol{e}_i$$

where  $u_i \to u_i + du_i$  for  $\forall i = 1, 2, 3$ .

Then the arc length ds is defined as:

$$(\mathrm{d}s)^2 = \mathrm{d}\mathbf{r} \cdot \mathrm{d}\mathbf{r}$$
$$= g_{ij} \, \mathrm{d}u_i \, \mathrm{d}u_j$$

where  $g_{ij}$  is the metric tensor:

$$g_{ij} = g_{ji} = \frac{\partial x_k}{\partial u_i} \frac{\partial x_k}{\partial u_j}$$
$$= h_i h_j (\mathbf{e}_i \cdot \mathbf{e}_j).$$

# Area and volume

Let  $d\mathbf{r}_i = h_i \mathbf{e}_i du_i$  denote vector length when  $u_i \to u_i + du_i$ . (**No** sum!)

The infinitesimal <u>vector area</u> or **surface element** formed by  $d\mathbf{r}_1$  and  $d\mathbf{r}_2$  is:

$$d\mathbf{S} = (h_1 d\mathbf{u}_1 \mathbf{e}_1) \times (h_2 d\mathbf{u}_2 \mathbf{e}_2).$$

Similarly the infinitesimal volume formed by edges  $d\mathbf{r}_1$ ,  $d\mathbf{r}_2$  and  $d\mathbf{r}_3$  is:

$$dV = |(d\mathbf{r}_1 \times d\mathbf{r}_2) \cdot d\mathbf{r}_3|$$
$$= \sqrt{g} du_1 du_2 du_3$$

where  $g = \det(g_{ij})$ .

### Cylindrical coordinates

 $(u_1, u_2, u_3) = (\rho, \phi, z)$  where  $\rho$  represents the radial distance from the origin and  $\phi$ is the anticlockwise rotation angle on the x-y plane. In Cartesian unit vectors:

$$r = \rho \cos \phi e_1 + \rho \sin \phi e_2 + z e_3$$
  
 $h_\rho = 1, \quad e_\rho = \cos \phi e_1 + \sin \phi e_2$ 

$$h_{\phi} = \rho, \quad \boldsymbol{e}_{\phi} = -\sin\phi \boldsymbol{e}_1 + \cos\phi \boldsymbol{e}_2$$

$$h_z = 1$$
,  $e_z = e_3$ 

and forms an orthogonal set.

### Spherical coordinates

 $(u_1, u_2, u_3) = (r, \theta, \phi)$  where  $\theta$  represents the clockwise rotation angle in y-z plane and  $\phi$  the anticlockwise rotation angle in x-y plane. In Cartesian unit vectors:

 $r = r \sin \theta \cos \phi e_1 + r \sin \theta \sin \phi e_2 + r \cos \theta e_3$  where curve  $\delta C$  encloses plane  $\delta S$ .


$$h_r = 1, \ h_\theta = r, \ h_\phi = r \sin \theta$$

 $\mathbf{e}_r = \sin\theta\cos\phi\mathbf{e}_1 + \sin\theta\sin\phi\mathbf{e}_2 + \cos\theta\mathbf{e}_3$ 

 $\mathbf{e}_{\theta} = \cos\theta\cos\phi\mathbf{e}_1 + \cos\theta\sin\phi\mathbf{e}_2 - \sin\theta\mathbf{e}_3$ 

$$\boldsymbol{e}_{\phi} = -\sin\phi \boldsymbol{e}_1 + \cos\phi \boldsymbol{e}_2$$

and also forms an orthogonal set.



The inverse relations are given by:

$$e_1 = \sin \theta \cos \phi e_r + \cos \theta \cos \phi e_\theta - \sin \phi e_\phi$$

 $e_2 = \sin \theta \sin \phi e_r + \cos \theta \sin \phi e_\theta + \cos \phi e_\phi$ 

$$\boldsymbol{e}_3 = \cos\theta \boldsymbol{e}_r - \sin\theta \boldsymbol{e}_\theta.$$

We notice that the transformation is an orthogonal matrix – its inverse is simply its transpose.

## Gradient

The gradient of a scalar field  $f(\mathbf{r})$  is:

$$\mathrm{d}f(\boldsymbol{r}) := \boldsymbol{\nabla}f(\boldsymbol{r}) \cdot \mathrm{d}\boldsymbol{r}$$

when  $r \to r + dr \implies f \to f + df$ . Taking the total differential of f yields:

$$\nabla f = \sum_{i=1}^{3} \frac{1}{h_i} \frac{\partial f}{\partial u_i} e_i$$

where  $\{e_i\}$  is orthogonal.

## Divergence

The divergence of a <u>vector</u> field F is:

$$\boldsymbol{\nabla} \cdot \boldsymbol{F} := \lim_{\delta V \to 0} \frac{1}{\delta V} \int_{\delta S} \boldsymbol{F} \cdot \mathrm{d}\boldsymbol{S}$$

for surface  $\delta S$  bounds infinitesimal  $\delta V$ . In orthogonal curvilinear coordinates:

$$\nabla \cdot \mathbf{F} = \frac{1}{h_1 h_2 h_3} \left\{ \frac{\partial}{\partial u_1} (F_1 h_2 h_3) + \frac{\partial}{\partial u_2} (h_1 F_2 h_3) + \frac{\partial}{\partial u_3} (h_1 h_2 F_3) \right\}.$$

### Curl

The curl of a vector field F in the direction of unit vector  $\hat{n}$  is:

$$\hat{m{n}}\cdot(m{
abla} imesm{F})\coloneqq\lim_{\delta S o 0}rac{1}{\delta S}\oint_{\delta C}m{F}\cdot\mathrm{d}m{r}$$

where curve  $\delta C$  encloses plane  $\delta S$ . In orthogonal curvilinear coordinates:

$$\boldsymbol{\nabla} \times \boldsymbol{F} = \frac{1}{h_1 h_2 h_3} \begin{vmatrix} h_1 \boldsymbol{e}_1 & h_2 \boldsymbol{e}_2 & h_3 \boldsymbol{e}_3 \\ \frac{\partial}{\partial u_1} & \frac{\partial}{\partial u_2} & \frac{\partial}{\partial u_3} \\ h_1 F_1 & h_2 F_2 & h_3 F_3 \end{vmatrix}.$$

## Laplacian

The Laplacian of a scalar field f is:

$$\nabla^2 f = \nabla \cdot (\nabla f)$$

and in orthogonal curvilinear coordinates:

$$\nabla^2 f = \frac{1}{h_1 h_2 h_3} \left\{ \frac{\partial}{\partial u_1} \left( \frac{h_2 h_3}{h_1} \frac{\partial f}{\partial u_1} \right) + \frac{\partial}{\partial u_2} \left( \frac{h_3 h_1}{h_2} \frac{\partial f}{\partial u_2} \right) + \frac{\partial}{\partial u_3} \left( \frac{h_1 h_2}{h_3} \frac{\partial f}{\partial u_3} \right) \right\}.$$

The Laplacian of a vector field F is:

$$\nabla^2 \mathbf{F} = \nabla(\nabla \cdot \mathbf{F}) - \nabla \times (\nabla \times \mathbf{F}).$$

#### Vector calculus identities

Particularly for Cartesian coordinates we can apply the suffix notation:

$$\nabla f = \frac{\partial f}{\partial x_i} e_i$$

$$\nabla \cdot \boldsymbol{F} = \frac{\partial F_i}{\partial x_i}$$

$$\mathbf{\nabla} \times \mathbf{F} = \epsilon_{ijk} \frac{\partial F_k}{\partial x_i} \mathbf{e}_i$$

$$\frac{\partial x_i}{\partial x_j} = \delta_{ij}$$
 and  $\frac{\partial x_i}{\partial x_i} = \delta_{ii} = 3$ .

The following operator acts on **both** scalar and vector fields:

$$(\boldsymbol{u}\cdot\boldsymbol{\nabla})\boldsymbol{F}=u_j\frac{\partial}{\partial x_j}F_i.$$

If  $\psi$  is a scalar field and  $\boldsymbol{v}$  a vector field:

$$\nabla \times (\nabla \psi) = \mathbf{0}$$

$$oldsymbol{
abla}\cdot(oldsymbol{
abla} imesoldsymbol{v})=oldsymbol{0}$$

$$\nabla \cdot (\psi v) = \nabla \psi \cdot v + \psi \nabla \cdot v$$

$$\nabla \times (\psi \boldsymbol{v}) = \nabla \psi \times \boldsymbol{v} + \psi \nabla \times \boldsymbol{v}.$$

Let  $\mathbf{r} = x_i \mathbf{e}_i$  and  $r = (x_i^2)^{1/2}$ . Then:

• 
$$\nabla r = \frac{r}{r}$$
 and  $\nabla \left(\frac{1}{r}\right) = -\frac{r}{r^3}$ 

- $\nabla \cdot r = 3$  and  $\nabla \times r = 0$
- $\nabla \times (\boldsymbol{c} \times \boldsymbol{r}) = 2\boldsymbol{c}$
- $\nabla \cdot (c \times r) = 0$  for constant c.

### Divergence theorem

Let surface S enclose volume V. Then:

$$\int_{V} \mathbf{\nabla} \cdot \mathbf{F} dV = \oint_{S} \mathbf{F} \cdot d\mathbf{S}$$

where  $\boldsymbol{F}$  is a vector field.

#### Stokes' theorem

Let closed curve C bound open surface S and let F be a vector field. Then:

$$\oint_C m{F} \cdot \mathrm{d}m{r} = \int_S (m{
abla} imes m{F}) \cdot \mathrm{d}m{S}$$

for C is traversed in anticlockwise sense.

#### Dirac delta function

The Dirac delta in 1D is defined as:

$$\delta(x-a) := \left\{ \begin{array}{ll} \infty & x = a \\ 0 & \text{otherwise.} \end{array} \right.$$

In three dimensions this becomes:

$$\delta^{(3)}(\boldsymbol{r} - \boldsymbol{r}_0) := \delta(\boldsymbol{r} - \boldsymbol{r}_0)$$
$$= \delta(x - x_0)\delta(y - y_0)\delta(z - z_0)$$

where (x, y, z) are Cartesian coordinates.

In orthogonal curvilinear coordinates:

$$\delta(\mathbf{r} - \mathbf{a}) = \frac{1}{h_1 h_2 h_3} \delta(u_1 - a_1)$$
$$\cdot \delta(u_2 - a_2) \delta(u_3 - a_3).$$

Importantly we have the **sift** property:

$$\int_{-\infty}^{\infty} f(x)\delta(x-a)dx = f(a)$$

$$\int_{-\infty}^{\infty} \delta(x) \mathrm{d}x = 1$$

which yields:

$$x\delta(x) = 0$$
 and  $\delta(cx) = \frac{1}{|c|}\delta(x)$ .

If simple solutions of g(x) = 0 are  $x_i$ :

$$\int_{-\infty}^{\infty} f(x)\delta(g(x))dx = \sum_{i} \frac{f(x_i)}{|g'(x_i)|}$$

### Coulomb's law

Consider charges q and  $q_1$  at positions r and  $r_1$ . The force on charge q at r due to charge  $q_1$  at  $r_1$  is:

$$\boldsymbol{F}_1(\boldsymbol{r}) = \frac{1}{4\pi\epsilon_0} \frac{qq_1(\boldsymbol{r} - \boldsymbol{r}_1)}{|\boldsymbol{r} - \boldsymbol{r}_1|^3}$$

where  $qq_1 > 0$  denotes repulsion.

The permittivity of free space is given by:

$$\epsilon_0 = 8.85419 \times 10^{-12} \text{C}^2 \text{N}^{-1} \text{m}^{-2}.$$

Charge has units Coulombs (C) and an electron has charge  $-1.60218 \times 10^{-19}$  C.

### Electric fields

The electric field is induced by a charge distribution and defined in terms of the force on a small positive test charge q:

$$oldsymbol{E}(oldsymbol{r}) \coloneqq \lim_{q \to 0} \frac{1}{q} oldsymbol{F}.$$

Then for our two charges q and  $q_1$ :

$$\boldsymbol{F}_1(\boldsymbol{r}) = q\boldsymbol{E}_1(\boldsymbol{r})$$

where  $q_1$  produces electric field  $E_1$ .

$$\therefore \boldsymbol{E}_1(\boldsymbol{r}) = \frac{1}{4\pi\epsilon_0} \frac{q_1(\boldsymbol{r} - \boldsymbol{r}_1)}{|\boldsymbol{r} - \boldsymbol{r}_1|^3}$$

$$\therefore \phi_1(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \frac{q_1}{|\mathbf{r} - \mathbf{r}_1|}$$

# Principle of superposition

For a set of charges  $q_i$  at position  $r_i$  the total electric field at r is:

$$\boldsymbol{E}(\boldsymbol{r}) = \frac{1}{4\pi\epsilon_0} \sum_i \frac{q_i(\boldsymbol{r} - \boldsymbol{r}_i)}{|\boldsymbol{r} - \boldsymbol{r}_i|^3}.$$

For object with **charge density**  $\rho(\mathbf{r}')$  its overall electric field at  $\mathbf{r}$  is:

$$\boldsymbol{E}(\boldsymbol{r}) = \frac{1}{4\pi\epsilon_0} \int_{V} \rho(\boldsymbol{r}') \frac{\boldsymbol{r} - \boldsymbol{r}'}{|\boldsymbol{r} - \boldsymbol{r}'|^3} dV'$$

where  $\rho(\mathbf{r}')$  is charge divided by volume. The **type** of integral (surface or line) is dependent on the object in consideration.

## Electrostatic Maxwell's equations

Because 
$$\nabla \left( \frac{1}{|\boldsymbol{r} - \boldsymbol{r}'|} \right) = -\frac{\boldsymbol{r} - \boldsymbol{r}'}{|\boldsymbol{r} - \boldsymbol{r}'|^3}$$
:

$$\boldsymbol{E}(\boldsymbol{r}) = -\boldsymbol{\nabla} \left( \frac{1}{4\pi\epsilon_0} \int_{V} \frac{\rho(\boldsymbol{r}')}{|\boldsymbol{r} - \boldsymbol{r}'|} dV' \right)$$

and therefore for all static electric fields:


$$\nabla \times E = 0$$
.

**E** is a **conservative** vector field where its line integral is independent of path. Furthermore it may be written as:

$$E(r) = -\nabla \phi(r)$$

for  $\phi(\mathbf{r})$  is the potential of  $\mathbf{E}$ .

$$\therefore \phi(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int_{V} \frac{\rho(\mathbf{r}')}{|\mathbf{r} - \mathbf{r}'|} dV'$$



The **potential difference** between two points A and B is the energy per unit charge needed to move a small charge q from A to B:

$$V_{A \to B} = \lim_{q \to 0} \frac{1}{q} W_{A \to B}$$
$$= -\frac{1}{q} \int_{C} \mathbf{F} \cdot d\mathbf{r}$$
$$= \phi_{B} - \phi_{A}.$$

A charge distribution  $\rho(\mathbf{r}')$  in an <u>external</u> electric field has potential energy:

$$W = \int_{V} \rho(\mathbf{r}') \phi_{ext}(\mathbf{r}') \mathrm{d}V'.$$

Because  $\nabla^2 \left( \frac{1}{|\boldsymbol{r} - \boldsymbol{r'}|} \right) = -4\pi \delta(\boldsymbol{r} - \boldsymbol{r'})$ :

$$oldsymbol{
abla} \cdot oldsymbol{E} = rac{
ho(oldsymbol{r})}{\epsilon_0}.$$

## Electric dipoles


An electric dipole at  $r_0$  is defined as two charges -q at  $r_0$  and +q at  $r_0 + d$  which generates **dipole moment**:

$$p = qd$$

and in the dipole limit this is defined as:

$$oldsymbol{p} \coloneqq \lim_{\substack{q o \infty \ oldsymbol{d} o oldsymbol{0}}} q oldsymbol{d}$$

known as an ideal dipole.



The electrostatic potential generated by this ideal dipole at  $\mathbf{r}_0$  is given by:

$$egin{aligned} \phi(oldsymbol{r}) &= \phi_q + \phi_{-q} \ &= rac{q}{4\pi\epsilon_0} \left( rac{1}{|oldsymbol{r} - oldsymbol{r}_0 - oldsymbol{d}|} - rac{1}{|oldsymbol{r} - oldsymbol{r}_0|} 
ight) \ &pprox rac{1}{4\pi\epsilon_0} rac{oldsymbol{p} \cdot (oldsymbol{r} - oldsymbol{r}_0)}{|oldsymbol{r} - oldsymbol{r}_0|^3} \end{aligned}$$

for the first term is expanded in powers of  $-\mathbf{d}$  about  $\mathbf{r} - \mathbf{r}_0$ .

The electric field generated is:

$$egin{aligned} E(m{r}) = & rac{1}{4\pi\epsilon_0} igg[ -rac{m{p}}{|m{r}-m{r}_0|^3} \ & + rac{3m{p}\cdot(m{r}-m{r}_0)}{|m{r}-m{r}_0|^5}(m{r}-m{r}_0) igg]. \end{aligned}$$

If the ideal dipole is at the origin:

$$\phi(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \frac{\mathbf{p} \cdot \mathbf{r}}{r^3}$$

$$\boldsymbol{E}(\boldsymbol{r}) = \frac{1}{4\pi\epsilon_0} \left( \frac{3\boldsymbol{p} \cdot \boldsymbol{r}}{r^5} \boldsymbol{r} - \frac{\boldsymbol{p}}{r^3} \right).$$

Let ideal dipole moment p be parallel to the z-axis. Then in spherical coordinates  $(r, \theta, \chi), r = re_r, p = pe_z$  and:

$$\phi(\mathbf{r}) = \frac{p}{4\pi\epsilon_0} \frac{\cos\theta}{r^2}$$

$$\boldsymbol{E}(\boldsymbol{r}) = \frac{p}{4\pi\epsilon_0} \left( \frac{2\cos\theta}{r^3} \boldsymbol{e}_r + \frac{\sin\theta}{r^3} \boldsymbol{e}_\theta \right).$$

## Force, torque and energy

The force on a dipole at r from external electric field  $E_{ext}(r)$  is:

$$egin{aligned} m{F} &= -q m{E}_{ext}(m{r}) + q m{E}_{ext}(m{r} + m{d}) \ &pprox (m{p} \cdot m{\nabla}) m{E}_{ext}(m{r}). \end{aligned}$$

The **torque** on a dipole at r about the axis r due to  $E_{ext}(r)$  is:

$$egin{aligned} m{G} &= m{ au}_{-q} + m{ au}_q \ &= -q m{0} imes m{E}_{ext}(m{r}) + q m{d} imes m{E}_{ext}(m{r} + m{d}) \ &pprox m{p} imes m{E}_{ext}(m{r}). \end{aligned}$$

The **energy** of a dipole at r from external electric field  $E_{ext}(r) = -\nabla \phi_{ext}(r)$  is:

$$W = -q\phi_{ext}(\mathbf{r}) + q\phi_{ext}(\mathbf{r} + \mathbf{d})$$
  
 
$$\approx -\mathbf{p} \cdot \mathbf{E}_{ext}(\mathbf{r})$$

and  $\mathbf{F} = -\nabla W$ .

# Multipole expansion

Consider object with volume V and charge distribution  $\rho(\mathbf{r}')$ . Let origin be in the object. Then the potential at  $\mathbf{r}$  is:

$$\phi(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int_V \frac{\rho(\mathbf{r}')}{|\mathbf{r} - \mathbf{r}'|} dV'$$

$$\approx \frac{1}{4\pi\epsilon_0} \left( \frac{Q}{r} + \frac{\mathbf{p} \cdot \mathbf{r}}{r^3} + \frac{Q_{ij} x_i x_j}{2r^5} \right)$$

where Q is the **total charge** in V:

$$Q = \int_{V} \rho(\mathbf{r}') \mathrm{d}V'$$

p the dipole moment about the origin:

$$p = \int_{V} r' \rho(r') dV'$$

and  $Q_{ij}$  the quadrupole tensor:

$$Q_{ij} = \int_{V} \rho(\mathbf{r}') \left[ 3x'_{i}x'_{j} - (r')^{2} \delta_{ij} \right] dV'.$$

If  $Q \neq 0$  then in the far zone  $(r \gg r_0)$  the first term (monopole term) dominates.

If Q = 0 and p = 0 then the third term (quadruple term) dominates in the far zone and etc.

## Interaction energy

By expanding  $\phi_{ext}(\mathbf{r})$  about  $\mathbf{r} = \mathbf{0}$ :

$$W = \int_{V} \rho(\mathbf{r}') \phi_{ext}(\mathbf{r}') dV'$$
$$= Q \phi_{ext}(\mathbf{0}) - \mathbf{p} \cdot \mathbf{E}_{ext}(\mathbf{0})$$
$$- \frac{1}{6} Q_{ij} \frac{\partial (\mathbf{E}_{ext}(\mathbf{0}))_{i}}{\partial x_{j}} + \dots$$

and is the potential energy of a charge distribution  $\rho(\mathbf{r})$  in  $\mathbf{E}_{ext}$ .

#### Gauss' law

For object with charge distribution  $\rho(\mathbf{r}')$  and volume V enclosed by surface S:

$$\int_{S} \mathbf{E} \cdot \mathrm{d}\mathbf{S} = \frac{Q_{enc}}{\epsilon_0}$$

where  $Q_{enc}$  is total charge enclosed by V:

$$Q_{enc} = \int_{V} \rho(\mathbf{r}') \mathrm{d}V'$$

and is useful for symmetric problems.

### Boundaries in electrostatics

Let  $\sigma$  be the charge density of a surface separating electric fields  $E_1$  and  $E_2$ .

1. Normal component of electric field is <u>discontinuous</u> across surface by:

$$\hat{m{n}}\cdot(m{E}_2-m{E}_1)=rac{\sigma}{\epsilon_0}.$$

2. Tangential component of electric field is continuous across surface:

$$E_{\parallel} := \hat{\boldsymbol{n}} \times \boldsymbol{E}_1 = \hat{\boldsymbol{n}} \times \boldsymbol{E}_2.$$

#### Conductors

Conductors have surplus electrons that can move freely when an electric field is applied. **In electrostatics**:

1. Conductors are in equilibrium, all charges are at rest and reside on the surface of the conductor.

Hence inside a conductor  $\rho(\mathbf{r}) = 0$ ,  $\mathbf{E}(\mathbf{r}) = \mathbf{0}$  and  $\phi = \text{constant}$ .

2. An electric field is always  $\underline{\text{normal}}$  to the surface of a conductor:

$$E_{\perp} = \frac{\sigma}{\epsilon_0}$$
 and  $E_{\parallel} = 0$ .

The presence of an external electric field induces a charge distribution  $\sigma$  on the surface of our conductor. This changes the external electric field as it needs to be normal to the surface of the conductor.

### Poisson's equation

Because  $\mathbf{E} = -\nabla \phi$  and  $\nabla \cdot \mathbf{E} = \rho(\mathbf{r})/\epsilon_0$ :

$$abla^2 \phi = -rac{
ho(m{r})}{\epsilon_0}.$$

We can solve this by direct integration or using the **method of images**.

Given volume under consideration place fictitious charge <u>outside</u> the volume such that the system still satisfies Poisson's equation with boundary conditions.

This potential is our solution.

# Electrostatic energy

The work needed to move point charge q from  $r_A$  to  $r_B$  in E(r) is:

$$W_{A\to B} = qV_{A\to B}.$$

Then  $W_{\infty \to B} = q\phi(\mathbf{r}_B)$  since potential  $\phi$  vanishes at infinity.

Generalising, the work needed to move a system of n charges  $q_i$  from infinity to r is a double sum with overcounting as each charge contributes to the electric field:

$$W_e = \frac{1}{2} \frac{1}{4\pi\epsilon_0} \sum_{i,j(i\neq j)}^{n} \frac{q_i q_j}{|\boldsymbol{r}_j - \boldsymbol{r}_i|}.$$

Furthermore the energy needed to move a continuous charge distribution  $\rho(\mathbf{r}')$  from infinity to position  $\mathbf{r}$  is:

$$W_e = \frac{1}{2} \int_V \rho(\mathbf{r}) \phi(\mathbf{r}) dV$$
$$= \frac{\epsilon_0}{2} \int_V |\mathbf{E}(\mathbf{r})|^2 dV.$$

#### Capacitors

A capacitor is formed by two conductors 1 and 2 with equal and opposite charges Q and -Q. The **capacitance** (1CV<sup>-1</sup>) of a capacitor is defined as:

$$C := \frac{Q}{V}$$

where  $Q = \sigma A$  for A is the surface area of one conductor and potential difference  $V = \phi_1 - \phi_2$  from the conductors.

The energy stored in a capacitor is the amount of work done to move charge across the two conductors. So to move charge dq from conductor with +q:

$$dW = \left(\frac{q}{C}\right) dq$$

and integrating this up to Q gives:

$$W = \frac{1}{2} \frac{Q^2}{C}.$$

# Currents

An elementary current is generated by a charge q moving at velocity v.

The bulk current density is:

$$\boldsymbol{J}(\boldsymbol{r}) := \rho(\boldsymbol{r})\boldsymbol{v}$$

for  $\rho(\mathbf{r})$  is the volume charge density.

The surface current density is:

$$K(r) := \sigma(r)v$$

for  $\sigma(\mathbf{r})$  is the surface charge density.

The line charge density is:

$$I(r) := \lambda(r)v$$

for  $\lambda(\mathbf{r})$  is the line charge density.

The infinitesimal current element is:

$$\mathrm{d} \boldsymbol{I}(\boldsymbol{r}) \coloneqq \left\{ \begin{array}{ll} \boldsymbol{J}(\boldsymbol{r}) \mathrm{d} \boldsymbol{V} & \text{volume current} \\ \boldsymbol{K}(\boldsymbol{r}) \mathrm{d} \boldsymbol{S} & \text{surface current} \\ \boldsymbol{I}(\boldsymbol{r}) \mathrm{d} \boldsymbol{r} & \text{line current} \end{array} \right.$$

Current I has units Ampères (A) but the infinitesimal current element  $d\mathbf{I}(\mathbf{r})$  has units of current/volume, etc.

Note:  $1A := 1Cs^{-1}$ 

Consider volume V bounded by surface S with total charge Q. Because the total charge is conserved:

$$\frac{\partial \rho(\boldsymbol{r},t)}{\partial t} + \boldsymbol{\nabla} \cdot \boldsymbol{J}(\boldsymbol{r},t) = 0$$

$$Q = \int_{V} \rho(\boldsymbol{r}, t) dV.$$

An electric field can induce a current in a conductor, via **Ohm's law**:

$$\boldsymbol{J} \approx \sigma_{ij} E_j$$

where  $\sigma_{ij}$  is the conductivity tensor.

- 1. Perfect conductors:  $\sigma \to \infty$  and  $\boldsymbol{E} = \boldsymbol{0}$ .
- 2. Insulators:  $\sigma = 0$ .

The **electromotive force** (emf) is:

$$\mathcal{E}_{1\to 2} := \int_{\boldsymbol{r}_1}^{\boldsymbol{r}_2} \boldsymbol{E} \cdot d\boldsymbol{r}$$
$$= \phi(\boldsymbol{r}_1) - \phi(\boldsymbol{r}_2)$$


since 
$$\boldsymbol{E} = -\boldsymbol{\nabla}\phi$$
. (static case)

### Biot-Savart law

The magnetic field at r generated by a static current loop carrying current I is:


$$\boldsymbol{B}(\boldsymbol{r}) = \frac{\mu_0}{4\pi} \oint_C \frac{I \mathrm{d} \boldsymbol{r}' \times (\boldsymbol{r} - \boldsymbol{r}')}{|\boldsymbol{r} - \boldsymbol{r}'|^3}$$

and is the right grip rule.



Magnetic fields have units Teslas (T), where  $NC^{-1}m^{-1}s = T$  and:

$$\mu_0 = 1.25664 \cdots \times 10^{-6} \text{NA}^{-2}.$$




No force is induced from perpendicular currents.

#### Lozentz force

Through physical experiments the force **density** on a charge distribution  $\rho(\mathbf{r})$  in electric field  $\boldsymbol{E}$  and magnetic field  $\boldsymbol{B}$  is:

$$f := \rho E + J \times B$$

where J is the current density and integrating yields the **right hand rule**.



Current is the movement of charge.

For point charge q at r' with velocity vin E and B its net force is the integral of the force density over volume V:

$$F = q(E + v \times B)$$

since  $\rho(\mathbf{r}) = q\delta(\mathbf{r} - \mathbf{r}')$  and  $\mathbf{J} = \rho(\mathbf{r})\mathbf{v}$ .

## Magnetostatic Maxwell's equations

Because 
$$\nabla \left( \frac{1}{|\boldsymbol{r} - \boldsymbol{r}'|} \right) = -\frac{\boldsymbol{r} - \boldsymbol{r}'}{|\boldsymbol{r} - \boldsymbol{r}'|^3}$$
:

$$\boldsymbol{B}(\boldsymbol{r}) = -\frac{\mu_0}{4\pi} \int_{V} \boldsymbol{J}(\boldsymbol{r}') \times \boldsymbol{\nabla} \left(\frac{1}{|\boldsymbol{r} - \boldsymbol{r}'|}\right) dV'$$
 where we set  $\boldsymbol{\nabla} \cdot \boldsymbol{A} = 0$  and solution:

therefore  $\nabla \cdot \boldsymbol{B} = \boldsymbol{0}$  due to:

This implies that magnetic fields always form **closed loops** — there are no sources or sinks for magnetic fields.

Similarly using the following identity:

$$egin{aligned} oldsymbol{
abla} imes (oldsymbol{u} imes oldsymbol{v}) &= oldsymbol{u}(oldsymbol{
abla} \cdot oldsymbol{v}) + oldsymbol{v} \cdot oldsymbol{
abla} oldsymbol{v} &- oldsymbol{u} \cdot oldsymbol{
abla} oldsymbol{v} - oldsymbol{v} \cdot oldsymbol{v} \cdot oldsymbol{u} &= -4\pi\delta(oldsymbol{r} - oldsymbol{r}') : \end{aligned}$$
and  $oldsymbol{
abla}^2 \left( rac{1}{|oldsymbol{r} - oldsymbol{r}'|} 
ight) = -4\pi\delta(oldsymbol{r} - oldsymbol{r}') :$ 

#### Ampère's law

Using the divergence theorem, there is no magnetic flux through a closed surface:


 $\nabla \times \boldsymbol{B} = \mu_0 \boldsymbol{J}.$ 

$$\oint_{S} \boldsymbol{B} \cdot \mathrm{d}\boldsymbol{S} = 0.$$

From Stokes' theorem:

$$\oint_C \boldsymbol{B} \cdot \mathrm{d}\boldsymbol{r} = \mu_0 I_{enc}$$

which implies that the circulation of a magnetic field  $\boldsymbol{B}$  around a closed loop Cis proportional to the total current I that passes through the enclosed surface.



## Boundaries in magnetostatics

Let conductor with current density Kseparate magnetic fields  $B_1$  and  $B_2$ .

1. Normal component of magnetic field is continuous across surface:

$$\boldsymbol{B}_{\perp} := \boldsymbol{B}_1 \cdot \hat{\boldsymbol{n}} = \boldsymbol{B}_2 \cdot \hat{\boldsymbol{n}}.$$

2. Tangential component of magnetic field is discontinuous across surface:

$$\hat{\boldsymbol{n}} \times (\boldsymbol{B}_2 - \boldsymbol{B}_1) = \mu_0 \boldsymbol{K}.$$

## Magnetic vector potentials

Because  $\nabla \cdot (\nabla \times v) = 0$  and  $\nabla \cdot B = 0$ :

$$\exists A : B = \nabla \times A$$

known as the **vector potential**. Then:

$$egin{aligned} oldsymbol{
abla} imes oldsymbol{B} &= oldsymbol{
abla} imes (oldsymbol{
abla} imes oldsymbol{A}) - oldsymbol{
abla}^2 oldsymbol{A} \ &= \mu_0 oldsymbol{J} \end{aligned}$$

$$: \boldsymbol{\nabla}^2 \boldsymbol{A} = -\mu_0 \boldsymbol{J}$$

$$\boldsymbol{A}(\boldsymbol{r}) = \frac{\mu_0}{4\pi} \int_V \frac{\boldsymbol{J}(\boldsymbol{r}')}{|\boldsymbol{r} - \boldsymbol{r}'|} \mathrm{d}V'$$

 $oldsymbol{
abla} \cdot (oldsymbol{u} imes oldsymbol{v}) = (oldsymbol{
abla} imes oldsymbol{u}) \cdot oldsymbol{v} - (oldsymbol{
abla} imes oldsymbol{v}) \cdot oldsymbol{u}. \quad ext{and boundary condition } \lim_{n \to \infty} oldsymbol{A}(oldsymbol{r}) = oldsymbol{0}.$ 

## Magnetic dipoles

The vector potential for a current loop positioned at the origin in the far zone is:

$$\mathbf{A}(\mathbf{r}) = \frac{\mu_0}{4\pi} \oint_C \frac{I d\mathbf{r}'}{|\mathbf{r} - \mathbf{r}'|}$$


$$= \frac{\mu_0}{4\pi} \oint_C \frac{1}{r} \left( 1 + \frac{\mathbf{r} \cdot \mathbf{r}'}{r^2} + \dots \right) d\mathbf{r}'$$

$$\approx \frac{\mu_0}{4\pi} \frac{\mathbf{m} \times \mathbf{r}}{r^3}$$

where m is the magnetic dipole moment:

$$egin{aligned} oldsymbol{m} &= I \int_S \mathrm{d} oldsymbol{S} \ &= rac{1}{2} \oint_C oldsymbol{r} imes \mathrm{d} oldsymbol{I} \end{aligned}$$

via Stokes' theorem.



## Force and torque

The Lorentz force on a current loop due to an external magnetic field  $\boldsymbol{B}$  is:

$$egin{aligned} m{F} &= I \oint_C \mathrm{d} m{r}' imes m{B}(m{r}') \ &= m{\nabla} (m{m} \cdot m{B}). \end{aligned}$$

The torque on a current loop due to an external magnetic field  $\boldsymbol{B}$  is:

$$egin{aligned} G &= \oint_C oldsymbol{r}' imes [I \mathrm{d} oldsymbol{r}' imes oldsymbol{B}(oldsymbol{r}')] \ &= oldsymbol{m} imes oldsymbol{B}. \end{aligned}$$

#### Motional electromotive force

The electromotive force (emf) is the work needed for unit point charge to circulate around a conductor loop:

$$\mathcal{E} = \oint_C \mathbf{f} \cdot d\mathbf{r}$$
  
=  $\oint_C (\mathbf{E} + \mathbf{v} \times \mathbf{B}) \cdot d\mathbf{r}$ 

for v is the velocity of the charge and fis the force density on point charge.

### Magnetic induction

Faraday's law of induction states that a **change** in magnetic flux  $\Phi$  induces an emf in a conductor loop:


$$\mathcal{E} = -\frac{\mathrm{d}\Phi}{\mathrm{d}t}$$


where **magnetic flux** is defined as the total magnetic field passing through the region bounded by the conductor loop:

$$\Phi = \int_{S} \boldsymbol{B} \cdot d\boldsymbol{S}$$

$$= \boldsymbol{B} \cdot \boldsymbol{S} \text{ if constant } \boldsymbol{B}$$

and any surface S enclosing the region.





For static charges in a conductor loop C with time dependent magnetic field:

$$\mathcal{E} = \oint_C \mathbf{E} \cdot d\mathbf{r} = -\int_S \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{S}$$

and using Stokes' theorem:

$$\mathbf{\nabla} \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}.$$

In words, a time dependent magnetic field always accompanies a spatial and time dependent electric field.

### Galilean relativity

If the velocity of frame S' in S is v:

$$r' = r - vt$$

$$dt' = dt$$

for point P has position r in frame S and position r' in frame S'.

Let circuit C be in motion in frame S with velocity v with respect to B(r,t). Then let C be stationary in frame S'. Since the electromotive force generated is the same regardless of frames, in frame S:

$$\mathcal{E} = \oint_C (\boldsymbol{E} + \boldsymbol{v} \times \boldsymbol{B}) \cdot d\boldsymbol{r}$$

and as v = 0 in frame S':

$$\mathcal{E} = \oint_C \mathbf{E}' \cdot \mathrm{d}\mathbf{r}.$$

Equating the two statements:

$$E' = E + v \times B$$

but only applies at  $v \ll c$ .

## Mutual and self inductance

Consider conductor loops 1 and 2 with current  $I_1$  and  $I_2$ . The magnetic vector potential generated by loop 1 is:

$$\boldsymbol{A}_1(\boldsymbol{r}) = \frac{\mu_0}{4\pi} \oint_{C_1} \frac{I_1 d\boldsymbol{r}_1'}{|\boldsymbol{r} - \boldsymbol{r}_1'|}$$

and the magnetic flux in loop 2 is:

$$\Phi_{2\leftarrow 1} = \frac{\mu_0 I_1}{4\pi} \oint_{C_2} d\mathbf{r}_2' \cdot \oint_{C_1} \frac{d\mathbf{r}_1'}{|\mathbf{r}_2' - \mathbf{r}_1'|}$$
$$= M_{21} I_1$$

where  $M_{21}$  is the Neumann's formula for mutual induction. Then for two loops:

$$\begin{pmatrix} \mathcal{E}_1 \\ \mathcal{E}_2 \end{pmatrix} = - \begin{pmatrix} L_1 & M \\ M & L_2 \end{pmatrix} \begin{pmatrix} \frac{\mathrm{d}I_1}{\mathrm{d}t} \\ \frac{\mathrm{d}I_2}{\mathrm{d}t} \end{pmatrix}$$

where  $M = M_{21} = M_{12}$ .  $L_1$  and  $L_2$  are the self-inductance for each loop.

formula for self inductance

 $M_{21}$  only equal when we have equal areas

# Magnetic field energy

Consider an inductor generating field B with current I and self-inductance L:

$$dW_m = idt \cdot -\mathcal{E}$$

$$= idt \cdot \frac{d\Phi_i}{dt}$$

$$= iLdi$$

and since  $\Phi_{1\leftarrow 1} = IL$  the energy stored our inductor is an integral over current:

$$W_m = \int_0^I dW_m = \frac{\Phi_{1\leftarrow 1}^2}{2L} \text{ or } \frac{1}{2}\Phi_{1\leftarrow 1}I.$$

Because  $\Phi_{1\leftarrow 1} = \int_{S} \boldsymbol{B} \cdot d\boldsymbol{S}$ :

$$W_m = \frac{1}{2} \oint_C \mathbf{A} \cdot I \mathrm{d}\mathbf{r}$$

and generalising this to volume integrals:

$$W_m = \frac{1}{2} \int_V \boldsymbol{J} \cdot \boldsymbol{A} dV$$

where J is the current density. Since:

$$\nabla \cdot (\boldsymbol{u} \times \boldsymbol{v}) = (\nabla \times \boldsymbol{u}) \cdot \boldsymbol{v} - (\nabla \times \boldsymbol{v}) \cdot \boldsymbol{u}$$

and assuming that the field vanish at  $\infty$ :

$$W_m = \frac{1}{2\mu_0} \int_V B^2 \mathrm{d}V$$

with magnetic field density:

$$w_m = \frac{1}{2\mu_0} B^2.$$

### Circuits

Consider an LRC circuit with alternating current source and electromotive force:

$$\mathcal{E}_S = V_S \cos(\phi + \omega t)$$
$$= \text{Re}[V_0 e^{i\omega t}]$$

where  $V_0 = V_S e^{i\phi}$ . Equating emfs:

$$\mathcal{E}_S = V_L + V_C + V_R$$
$$= L \frac{\mathrm{d}I}{\mathrm{d}t} + V_C(t) + IR$$

$$I = C \frac{\mathrm{d}V_C}{\mathrm{d}t}$$

and due to linearity we assume that:

$$I(t) = \text{Re}[I_0 e^{i\omega t}]$$

$$V_C(t) = \text{Re}[V_{C_0}e^{i\omega t}].$$

After subsituting into our equations:


$$V_0 = i\omega L I_0 + V_{C_0} + R I_0$$

$$I_0 = i\omega C V_0$$
 and  $Z := \frac{V_0}{I_0}$ 

which yields solutions:

$$\begin{split} I(t) &= \mathrm{Re}\left[\frac{V_0}{Z}e^{i\omega t}\right] \\ &= \frac{V_S\cos(\omega t + \phi - \psi)}{\left[R^2 + (\omega L - \frac{1}{\omega C})^2\right]^{1/2}} \end{split}$$

and 
$$\psi = \arctan \left[ \frac{\omega L - \frac{1}{\omega C}}{R} \right]$$
.



current/voltage in series/parallel circuits voltage of specific components

## Electromagnetic waves

From considering the capacitor paradox:

$$\nabla \times \boldsymbol{B} = \mu_0 \boldsymbol{J} + \mu_0 \epsilon_0 \frac{\partial \boldsymbol{E}}{\partial t}$$

Since in vacuum  $\rho = 0$  and  $\mathbf{J} = \mathbf{0}$ :

$$\boldsymbol{\nabla}\times(\boldsymbol{\nabla}\times\boldsymbol{B})=\mu_0\epsilon_0\frac{\partial}{\partial t}(\boldsymbol{\nabla}\times\boldsymbol{E})$$

and using  $\nabla \times \boldsymbol{E} = \frac{\partial \boldsymbol{B}}{\partial t}$ :

$$\nabla(\nabla \cdot \boldsymbol{B}) - \nabla^2 \boldsymbol{B} = -\mu_0 \epsilon_0 \frac{\partial^2}{\partial t^2} \boldsymbol{B}$$
$$\implies \nabla^2 \boldsymbol{B} = \mu_0 \epsilon_0 \frac{\partial^2 \boldsymbol{B}}{\partial t^2}.$$

Similarly for our electric field E:

$$oldsymbol{
abla} (oldsymbol{
abla} \cdot oldsymbol{E}) - oldsymbol{
abla}^2 oldsymbol{E} = -\mu_0 \epsilon_0 rac{\partial^2 oldsymbol{E}}{\partial t^2} oldsymbol{E}$$
 $\Longrightarrow oldsymbol{
abla}^2 oldsymbol{E} = \mu_0 \epsilon_0 rac{\partial^2 oldsymbol{E}}{\partial t^2}.$ 

Let F be any component of fields  $E(\mathbf{r}, t)$  or  $B(\mathbf{r}, t)$ . Then it satisfies the following:

$$\nabla^2 F = \mu_0 \epsilon_0 \frac{\partial^2 F}{\partial t^2}.$$

Substituting solutions of form:

$$F(t, x, y, z) = f(\mathbf{k} \cdot \mathbf{x} - \omega t)$$
  

$$\implies |\mathbf{k}|^2 = \mu_0 \epsilon_0 \omega^2$$

and with phase velocity:

$$v_{phase} = \frac{\omega}{|\mathbf{k}|} = \frac{1}{\sqrt{\mu_0 \epsilon_0}}$$
$$= 3.10 \times 10^8 \text{ms}^{-1} = c$$

which is the speed of light and implies that light is also an electromagnetic wave!

## Lorentz transformations

It is then postulated that:

• The speed of light is universal. c is frame invariant and classically only propagate forwards in time.

In Minkowsky spacetime we have that:


$$(\Delta S)^2 = (\Delta S')^2$$

between two frames S, S' and:

$$(\Delta S)^2 := (c\Delta t)^2 - (\Delta x)^2 - (\Delta y)^2 - (\Delta z)^2$$

for events A and B,  $\Delta x = x_B - x_A$ , etc.

- $(\Delta S)^2 = 0$ : light-like separated
- $(\Delta S)^2 > 0$ : time-like separated
- $(\Delta S)^2 < 0$ : space-like separated



A **boost**  $B_x$  in the  $e_x$  direction is defined:

$$m{x}' = egin{pmatrix} \gamma & -eta\gamma & 0 & 0 \ -eta\gamma & \gamma & 0 & 0 \ 0 & 0 & 1 & 0 \ 0 & 0 & 0 & 1 \end{pmatrix} m{x}$$

where  $\boldsymbol{x} = (ct, x, y, z)^T$ .

Generally we can relate reference frames S and S' by a composition of rotations and boosts. This forms a group, denoted by  $SO(3) = \{R_x, R_y, R_z, B_x, B_y, B_z\}$ .

Practically if frame S' is moving at  $ve_x$  with respect to frame S then:

$$ct' = \gamma(ct - \beta x)$$
  
 $x' = \gamma(-\beta ct + x)$ 

$$y' = y$$
 and  $z' = z$ 

where  $\gamma = (1 - \beta^2)^{-1/2}$  and  $\beta = v/c$ .

## Time and length

Consider object in rest in frame S', which is moving with respect to frame S. Then:

- lifetime in  $S: \gamma \tau$
- length in S:  $\ell_0/\gamma$

for time  $\tau$  and length  $\ell_0$  are its physical quantities in frame S'.

### Electromagnetic energy

By considering the Lorentz force with:

$$dW = \mathbf{F} \cdot d\mathbf{r} = \mathbf{F} \cdot \mathbf{v} dt$$

and generalising to a charge distribution:

$$\frac{\mathrm{d}W}{\mathrm{d}t} = \int_{V} \boldsymbol{J} \cdot \boldsymbol{E} \, \mathrm{d}^{3} \boldsymbol{r}.$$

Using Maxwell's equations:

$$\underbrace{\frac{\mathrm{d}W}{\mathrm{d}t}}_{\text{power}} + \int_{\partial V} \mathbf{S} \cdot \mathrm{d}\mathbf{a} + \frac{\mathrm{d}U_{em}}{\mathrm{d}t} = 0$$

where  $U_{em}$  represents the total energy stored in the electric and magnetic fields:

$$U_{em} = \int_{V} \left( \frac{1}{\mu_0} |\boldsymbol{B}|^2 + \epsilon_0 |\boldsymbol{E}|^2 \right) d^3 \boldsymbol{r}$$

and we define the **Poynting vector**:

$$\boldsymbol{S} \coloneqq \frac{1}{\mu_0} \boldsymbol{E} \times \boldsymbol{B}.$$

Likewise its surface integral denotes the *rate* at which energy flows.

If  $\int_{\partial V} \mathbf{S} \cdot d\mathbf{a} < 0$  then power flows into the bounded surface and vice versa.

# Maxwell's stress tensor

Since Newton's second law states that:

$$F = \frac{\mathrm{d}P}{\mathrm{d}t}$$

using the Lorentz force we have that:

$$\frac{\mathrm{d}\boldsymbol{P}}{\mathrm{d}t} = -\frac{\mathrm{d}}{\mathrm{d}t} \int_{V} \epsilon_{0} \mu_{0} \boldsymbol{S} \, \mathrm{d}^{3} \boldsymbol{r} + \int_{\partial V} \boldsymbol{T} \cdot \mathrm{d}\boldsymbol{a}$$

where T is the stress tensor:

$$T_{ij} = \epsilon_0 \left( E_i E_j - \frac{1}{2} \delta_{ij} |\mathbf{E}|^2 \right)$$
  
 
$$+ \frac{1}{\mu_0} \left( B_i B_j - \frac{1}{2} \delta_{ij} |\mathbf{B}|^2 \right).$$

### Relativistic kinematics

Now we interpret particles of constant motion under the context of inertial frames. Define frame S' to be moving at  $ve_x$  with respect to frame S.

If a particle is moving at  $\mathbf{u}' = (u_x', u_y', u_z')$  with respect to frame S' then:

$$cdt' = \gamma(cdt - \beta dx)$$

 $dx' = \gamma(-\beta c dt + dx)$  and so on...

which yields the following relation:

$$\frac{1}{c}u_x' := \frac{\mathrm{d}x'}{c\mathrm{d}t'} \implies \frac{-\beta c + u_x}{c - \beta u_x}$$

where  $\mathbf{u} = (u_x, u_y, u_z)$  is the velocity of the particle with respect to frame S.

### Instantaneous rest frames


Generally, for every object, there exists a *unique* **rest frame** such that it has no velocity with respect to this frame.

Let a particle have instantaneous velocity  $u(t) = \frac{\mathrm{d}x}{\mathrm{d}t}$  with respect to frame S. Then the frame S' with boost  $\beta = u/c$  is its rest frame. The time element in frame S' is the **proper time element**:

$$dt' := d\tau = \frac{1}{c} \left( 1 - \frac{u^2}{c^2} \right)^{1/2} dt.$$

# Invariant $(\Delta S)^2$ trajectories

Good time to work through tutorial sheet 17 question 3.



## Plane wave solutions

In *vacuum*, the Maxwell's equations may be recast into a classical wave equation:

$$\mathbf{\nabla}^2 \{ \mathbf{E}, \mathbf{B} \} = \frac{1}{c^2} \frac{\partial^2}{\partial t^2} \{ \mathbf{E}, \mathbf{B} \}$$
  
 $\mu_0 \epsilon_0 = c^{-2}.$ 

We then look for solutions of linear form:

$$\boldsymbol{E} = \operatorname{Re} \left\{ \boldsymbol{E}_0 e^{i(\omega t - \boldsymbol{k} \cdot \boldsymbol{r})} \right\}$$

$$\boldsymbol{B} = \operatorname{Re} \Big\{ \boldsymbol{B}_0 e^{i(\omega t - \boldsymbol{k} \cdot \boldsymbol{r})} \Big\}$$

known as plane wave solutions:

$$|\mathbf{k}| = \frac{\omega}{c}$$

from subsituting into our wave equation. The frequency  $\omega$  can correspond to a color in the visible electromagnetic spectrum. Since  $\rho=0$  and  $\boldsymbol{J}=\boldsymbol{0}$  we have that:

$$\mathbf{k} \cdot \mathbf{E} = 0, \quad \mathbf{k} \cdot \mathbf{B} = 0,$$

$$\mathbf{k} \times \mathbf{E} = \omega \mathbf{B}$$
 and  $-\mathbf{k} \times \mathbf{B} = \frac{\omega}{c^2} \mathbf{E}$ .

i.e. that  $(\hat{k}, \hat{E}, \hat{B})$  forms a right-handed orthonormal basis and:

$$E = \left(a_1 e^{i\delta_1} \hat{\boldsymbol{\epsilon}}_1 + a_2 e^{i\delta_2} \hat{\boldsymbol{\epsilon}}_2\right) e^{i(\omega t - \boldsymbol{k} \cdot \boldsymbol{x})}$$

$$\implies a_1 \hat{\boldsymbol{\epsilon}}_1 \cos(\omega t - \boldsymbol{k} \cdot \boldsymbol{r} + \delta_1)$$

$$+ a_2 \hat{\boldsymbol{\epsilon}}_2 \cos(\omega t - \boldsymbol{k} \cdot \boldsymbol{r} + \delta_2)$$

where  $a_1, a_2, \delta_1, \delta_2 \in \mathbb{R}$ . The unit vectors  $\hat{\boldsymbol{\epsilon}}_1$  and  $\hat{\boldsymbol{\epsilon}}_2$  are perpendicular to each other as well as the wave vector  $\boldsymbol{k}$ , which defines the direction of wave propagation.

Fixing E also fixes the magnetic field:

$$\boldsymbol{B} = \frac{1}{\omega} \boldsymbol{k} \times \boldsymbol{E}.$$

### Polarisation

Every plane wave solution with fixed  $\omega$  is **monochromatic**. We then define the polarisation vector  $\hat{\boldsymbol{n}}$  of a plane wave as:

$$E = |E|\hat{n}$$
 where  $\hat{n} \cdot k = 0$ .

Hence every electromagnetic wave can be thought of as a superposition of polarised monochromatic transverse waves.

1. **Linear** polarisation:  $\delta_1 = \delta_2$ 

$$\mathbf{E}_{linear} = (a_1 \hat{\boldsymbol{\epsilon}}_1 + a_2 \hat{\boldsymbol{\epsilon}}_2)$$
$$\cdot \cos(\omega t - \mathbf{k} \cdot \mathbf{r} + \delta_1)$$

2. Circular polarisation:  $\delta_1 \pm \frac{\pi}{2} = \delta_2$ 

$$\boldsymbol{E}_{circ} = a_1 \left[ \hat{\boldsymbol{\epsilon}}_1 \cos(\omega t - \boldsymbol{k} \cdot \boldsymbol{r} + \delta_1) \right]$$
$$\mp \hat{\boldsymbol{\epsilon}}_2 \cos(\omega t - \boldsymbol{k} \cdot \boldsymbol{r} + \delta_1)$$

## Energy in electromagnetic waves

Given an arbitrary plane wave solution:

$$\boldsymbol{E} = \boldsymbol{E}_0 \cos(\omega t - \boldsymbol{k} \cdot \boldsymbol{r} + \phi)$$

the corresponding electromagnetic wave energy density enclosed by a volume is:

$$u_{em} = u_e + u_m$$

$$:= \frac{\epsilon_0}{2} |\mathbf{E}|^2 + \frac{1}{2\mu_0} |\mathbf{B}|^2$$

$$= \epsilon_0 |\mathbf{E}_0|^2 \cos^2(\omega t - \mathbf{k} \cdot \mathbf{r} + \phi)$$

where  $u_e = u_m$  for all space and time.

$$\therefore \langle u_{em} \rangle = \epsilon_0 |\boldsymbol{E}_0|^2$$

The Poynting vector can be interpreted as the *flux of energy* in an unit area:

$$egin{aligned} m{S} &= rac{1}{\mu_0} m{E} imes m{B} \ &= rac{1}{\mu_0 \omega} m{E} imes (m{k} imes m{E}) \ &= rac{m{k}}{\omega} rac{1}{\mu_0} |m{E}|^2 \ &\Longrightarrow (cu_{em}) \hat{m{k}}. \end{aligned}$$

## Gauge freedoms

coulomb gauge

lorenz gauge

### Retarded potentials

magnetic and electric potentials for the lorenz gauge

### Electric dipole radiation

compute electric field potential magnetic field vector potential poynting vector

#### 4-vectors

## Electric fields in matter

The presence of an electric field induces a small dipole moment on the constituent atoms of a material that all point in the direction of the field. The material is now has a **polarisation** or dipole *density*:

$$oldsymbol{P}(oldsymbol{r}') = \sum_k oldsymbol{p}_k \delta(oldsymbol{r}' - oldsymbol{r}_k)$$

where  $p_k$  is the dipole moment of the  $k^{th}$  atom. Then superposition gives that:

$$\phi(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int_V \frac{\mathbf{P}(\mathbf{r}') \cdot (\mathbf{r} - \mathbf{r}')}{|\mathbf{r} - \mathbf{r}'|^3} d^3 \mathbf{r}'$$
$$= \frac{1}{4\pi\epsilon_0} \int_V \mathbf{P}(\mathbf{r}') \cdot \mathbf{\nabla}' \left(\frac{1}{|\mathbf{r} - \mathbf{r}'|}\right) d^3 \mathbf{r}'$$

and using the divergence chain rule:

$$\phi(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int_{\partial V} \frac{\sigma_b(\mathbf{r}')}{|\mathbf{r} - \mathbf{r}'|} da$$
$$+ \frac{1}{4\pi\epsilon_0} \int_{V} \frac{\rho_b(\mathbf{r}')}{|\mathbf{r} - \mathbf{r}'|} d^3 \mathbf{r}'$$

where we define  $\sigma_b(\mathbf{r}') = \mathbf{P}(\mathbf{r}') \cdot \hat{\mathbf{n}}$  as the bounded volume charge density and that similarly  $\rho_b(\mathbf{r}') = -\nabla' \cdot \mathbf{P}(\mathbf{r}')$  is our bounded surface charge density.

This potential also generates an electric field, and is consistent with Gauss' law:

$$\epsilon_0 \nabla \cdot \boldsymbol{E} = \rho_f + \rho_b \implies \nabla \cdot \boldsymbol{D} = \rho_f$$

where  $D = \epsilon_0 E + P$  is the **displacement** field and  $\rho_f$  the free charge distribution.

### Magnetic materials