Thermodynamics

Notes by Christopher Shen

Winter 2023

Contents

1	Zeroth law	4
2	Thermodynamics definitions	4
3	Isothermal expansion	4
4	First law	4
5	Heat capacities	5
6	Enthalpy 6.1 Definition	6 6 6 6 6 6
7	Heat engines	7
8	Entropy 8.1 State function entropy	8 8 8 9
9	Second law 9.1 Reversibility	10 10 10
10	Helmholtz and Gibbs free energy	11
11	Maxwell relations11.1 Derivation	12 12 13 13 14 14
12	Phase transitions	15
	12.1 PT diagrams12.2 Van der Waals state equation12.3 PV diagrams	15 15 15
13	Chemical potentials	16

14 Third law 17

- 1 Zeroth law
- 2 Thermodynamics definitions
- 3 Isothermal expansion
- 4 First law

5 Heat capacities

6 Enthalpy

- 6.1 Definition
- 6.2 Applications
- 6.2.1 Latent heats
- 6.2.2 Constant pressure expansion
- 6.2.3 Filling empty tank
- 6.2.4 Chemical reactions

7 Heat engines

include hurricanes application

8 Entropy

8.1 State function entropy

Entropy is defined as:

$$S = \frac{Q}{T},$$

where Q is <u>heat from reservoir</u> and T the reservoir temperature.

Entropy has units JK^{-1} , and if we have a **reversible cyclic** heat engine:

$$\mathrm{d}S = \frac{\mathrm{d}Q}{T}.$$

This is the differential form of entropy. Applying the first law under again **reversible** conditions gives:

$$dU = TdS - PdV$$

The entropy change of a system is:

$$\Delta S = \int_{(1)}^{(2)} \frac{dU}{T} + \int_{(1)}^{(2)} P dV$$
$$= \int_{(1)}^{(2)} \frac{dQ}{T},$$

for a reversible path.

8.2 Entropy of ideal gases

Let's now assume an ideal, monoatomic gas. Then its heat capacity becomes:

$$C_V = \frac{\mathrm{d}U}{\mathrm{d}T}.$$

So $C_V dT = T dS - P dV$ and $C_V = \frac{3}{2} nR$. Combining these:

$$dS = nR \left(\frac{3}{2} \frac{dT}{T} + \frac{dV}{V} \right)$$

which can be discretised to find ΔS . Rearranging we get $T dS = C_V dT + P dV$. Integrating and using identity $C_P - C_V = nR$ we get:

$$\Delta S = nc_V \ln \left(\frac{P_2}{P_1}\right) + nc_P \ln \left(\frac{V_2}{V_1}\right)$$

for here n is moles and the heat capacities are in molar quantities.

8.3 Entropy of mixing

Consider a box with separator, containing n_A moles at V_A of gas A on one side and n_B moles at V_B of gas B on the other. We set $\Delta T = 0$, $\Delta P = 0$ and proceed to mix gases A and B.

The entropy of mixing is:

$$\begin{split} \Delta S &= \Delta S_A + \Delta S_B \\ &= n_i R \ln \left(\frac{V_f}{V_i}\right) \\ &= n_A R \ln \left(\frac{V_A + V_B}{V_A}\right) + n_B R \ln \left(\frac{V_A + V_B}{V_B}\right), \end{split}$$

Since P and T are fixed, the ideal state equation PV = nRT implies that:

$$\frac{V_A + V_B}{V_A} = \frac{n_A + n_B}{n_A}$$

and so we define **inverse mole fractions** as:

$$x_A = \frac{n_A}{n_A + n_B}$$

and

$$x_B = \frac{n_B}{n_A + n_B}.$$

After substituting and dividing through by $n_A + n_B$ we find the **molar specific** entropy of mixing:

$$\Delta s_{mix} = -R(x_A \ln x_A + x_B \ln x_B).$$

8.4 Measuring entropy

Practically, C_P is much easier to measure than C_V . Recall definition:

$$C_P = \frac{\mathrm{d}Q_p}{\mathrm{d}T} = \left(\frac{\mathrm{d}H}{\mathrm{d}T}\right)_p$$

where state function H is the enthalpy. Since H = U + PV:

$$dH = TdS + VdP$$

and dividing by dT:

$$\frac{\mathrm{d}H}{\mathrm{d}T} = T\frac{\mathrm{d}S}{\mathrm{d}T} + V\frac{\mathrm{d}P}{\mathrm{d}T}.$$

If $\Delta P = 0$ then:

$$C_P(T) = T \left(\frac{\mathrm{d}S}{\mathrm{d}T}\right)_P.$$

Rearranging and integrating gives us the change in entropy:

$$\Delta S = \int_{(1)}^{(2)} \frac{C_P(T)}{T} dT.$$

9 Second law

9.1 Reversibility

9.2 Second law

include spontaneous process sections 12 and 13

10 Helmholtz and Gibbs free energy

include chemical reactions and colloidal particles sections 14 and 15

11 Maxwell relations

11.1 Derivation

So from previous sections we have the following four differential relations¹:

$$dU = TdS - PdV,$$

$$dH = TdS + VdP,$$

$$dF = -SdT - PdV,$$

$$dG = -SdT + VdP.$$

For equation of state f(P, V, T) = 0, the **Maxwell relations** are the following:

$$\begin{split} \left(\frac{\partial T}{\partial V}\right)_S &= -\left(\frac{\partial P}{\partial S}\right)_V, \\ \left(\frac{\partial T}{\partial P}\right)_S &= \left(\frac{\partial V}{\partial S}\right)_P, \\ \left(\frac{\partial S}{\partial V}\right)_T &= \left(\frac{\partial P}{\partial T}\right)_V, \\ -\left(\frac{\partial S}{\partial P}\right)_T &= \left(\frac{\partial V}{\partial T}\right)_P. \end{split}$$

Notice how each equation relates entropy S to measurable quantities.

These relations are derived by taking **total differentials** and then applying **Clairaut's theorem**. We are only going to do the first relation:

$$dU = TdS - PdV$$

$$= \left(\frac{\partial U}{\partial S}\right)_{V} dS + \left(\frac{\partial U}{\partial V}\right)_{S} dV$$

Therefore we have that:

$$T = \left(\frac{\partial U}{\partial S}\right)_V$$

and

$$P = -\left(\frac{\partial U}{\partial V}\right)_S.$$

Taking partials again and equating gives us the first relation.

 $^{^1\}mathrm{Here}\ U$ is the internal energy, H is enthalpy, F is the Helmholtz free energy and G is the Gibbs free energy.

11.2 Applications

We can define **isobaric expansivity** β with units K^{-1} as:

$$\beta = \frac{1}{V} \left(\frac{\partial V}{\partial T} \right)_P$$

and isothermal compressibility κ_T with units Pa^{-1} as:

$$\kappa_T = -\frac{1}{V} \left(\frac{\partial V}{\partial P} \right)_T.$$

These may be thought of as volume change per physical unit change.

The Maxwell relations can be used to find entropy. For example:

$$\Delta S = \int_{(1)}^{(2)} dS$$
$$= -\int_{(1)}^{(2)} \left(\frac{\partial V}{\partial T}\right)_{P} dP.$$

11.2.1 Ideal gas internal energy

Now we can show why U = U(T) if we have an ideal gas. Beginning with:

$$dU = TdS - PdV$$

and dividing through by dV gives:

$$\begin{split} \left(\frac{\partial U}{\partial V}\right)_T &= T \left(\frac{\partial S}{\partial V}\right)_T - P \\ &= T \left(\frac{\partial P}{\partial T}\right)_V - P \end{split}$$

via a Maxwell relation. Finally our ideal gas assumption implies that:

$$P = \frac{nRT}{V}$$

and substituting this into the previous expression results in:

$$\left(\frac{\partial U}{\partial V}\right)_T = 0$$

which means that U = U(T).

11.2.2 Difference in heat capacities

We begin with the following expression:

$$C_{P} = C_{V} + \left(P + \left(\frac{\partial U}{\partial V}\right)_{T}\right) \left(\frac{\partial V}{\partial T}\right)_{P}$$

$$= C_{V} + T \left(\frac{\partial P}{\partial T}\right)_{V} \left(\frac{\partial V}{\partial T}\right)_{P}$$

$$= C_{V} + T \left(\frac{\partial P}{\partial T}\right)_{V} \beta V.$$

$$\therefore C_{P} - C_{V} = \beta T V \left(\frac{\partial P}{\partial T}\right)_{V}$$

Then using the following identities:

$$\begin{split} \left(\frac{\partial P}{\partial T}\right)_{V} \left(\frac{\partial V}{\partial P}\right)_{T} \left(\frac{\partial T}{\partial V}\right)_{P} &= -1 \\ \frac{1}{\left(\frac{\partial V}{\partial P}\right)_{T}} &= \left(\frac{\partial P}{\partial V}\right)_{T} \end{split}$$

we get that the difference in heat capacities is:

$$C_P - C_V = \frac{\beta^2}{\kappa_T} TV$$

where β is the **isobaric expansivity** and κ_T is the **isothermal compressibility**. Furthermore it is clear that $C_P - C_V > 0$ for all cases.

11.2.3 Liquefying gases

12 Phase transitions

12.1 PT diagrams

phase transition diagrams (PT) supercritical points phase boundaries triple point clausius clapeyron equation

12.2 Van der Waals state equation

12.3 PV diagrams

13 Chemical potentials

14 Third law