Thermodynamics

#### **Definitions**

Isolated system: No exchanges

Closed system: Only energy exchange

Open system: Energy & mass exchange

#### Intensive state variables:

Independent of mass

#### Extensive state variables:

Proportional to mass

Reservoirs: Infinite/very large system that remains unchanged when in contact with finite system.

## Mechanical equilibrium:

No unbalanced forces

### Thermal equilibrium:

No temperature differences

## Thermodynamic equilibrium:

Intensive state variables of system are <u>constant</u>. Alternatively our system is in <u>mechanical</u> and <u>thermal</u> equilibrium.

### Reversible processes:

Every intermediate is an equilibrium state.  $\,$ 

### Quasi-static processes:

Process sufficiently slow such that only infinitesimal temperature or pressure gradients exist.

Frictionless quasi-static processes are reversible.

## Cyclic processes:

$$\Delta U = 0$$
 and  $W = Q$ 

For conservative forces:

$$\oint \mathrm{d}X = 0$$

where X is a state variable.

Adiabatic processes:  $\Delta Q = 0$ 

Isothermal processes:  $\Delta T = 0$ 

Isobaric processes:  $\Delta P = 0$ 

## Density

We define the density of a material as:

$$\rho = \frac{m}{V}.$$

If mass m is constant:

$$\Delta V = m \left( \frac{1}{\rho_f} - \frac{1}{\rho_i} \right)$$

assuming homogeneous material.

#### Zeroth law

If A is in thermal equilibrium with B and C seperately then B and C are also in thermal equilibrium.

## Ideal gas state equation

Given n moles of gas at temperature T:

$$PV = nRT$$
$$= Nk_BT$$

where  $R = N_A k_B = 8.314 \text{JK}^{-1} \text{mol}^{-1}$ and N the number of molecules.

#### Calculus identities

1. 
$$df(x,y) = \left(\frac{\partial f}{\partial x}\right)_y dx + \left(\frac{\partial f}{\partial y}\right)_x dx$$
  
if  $f = f(x,y)$ .

2. Differential df is **inexact** if:

$$\int_C df$$
 is dependent of path.

$$3. \ \left(\frac{\partial Z}{\partial Y}\right)_X = \left[\left(\frac{\partial Y}{\partial Z}\right)_X\right]^{-1}$$

$$4. \left(\frac{\partial X}{\partial Y}\right)_{Z} \left(\frac{\partial Y}{\partial Z}\right)_{X} \left(\frac{\partial Z}{\partial X}\right)_{Y} = -1$$

#### First law

Total energy E is conserved and:

$$\Delta U = Q - W$$
$$dU = dQ - dW$$

$$\dot{U} = \dot{Q} - \dot{W}$$

where U is internal energy and  $E \geq U$ .

- Heat exchange Q: The energy transfer of two systems at different temperatures in thermal
  - at different temperatures in thermal contact. Q > 0 represents energy transfer into system.
- Work exchange W: The work done <u>on</u> the surroundings by system is represented by W > 0.

Work is generally path dependent.

The work done  $\underline{by}$  a fluid in **reversible** processes is:

$$dW = PdV$$

and has units Joules (J).

# Isothermal expansion

Let  $P_1 > P_2$  where  $P_1$  and  $P_2$  denote system and external pressure respectively. Only mechanical work is exchanged via a piston. By applying a force such that there exists pressure difference dP, our expansion becomes reversible and hence:

$$W_{1\to 2} = nRT \int_{V_1}^{V_2} \frac{\mathrm{d}V}{V}.$$

Note that for isothermal processes under ideal gas assumption,  $\Delta U = 0$ .

## Heat capacity

Heat capacity  $(JK^{-1})$  is defined as:

$$C(P,T) = \lim_{\Delta T \to 0} \frac{\Delta Q}{\Delta T}$$

and is the heat needed to produce unit change in sample temperature.

Specific heat capacity  $(Jkg^{-1}K^{-1})$ :

$$Q = mc\Delta T.$$

We define the  ${\bf isochoric}$  heat capacity as:

$$C_V(T) := \left(\frac{\mathrm{d}Q}{\mathrm{d}T}\right)_V = \left(\frac{\partial U}{\partial T}\right)_V$$

and the **isobaric** heat capacity as:

$$\begin{split} C_P &:= \left(\frac{\mathrm{d}Q}{\mathrm{d}T}\right)_P \\ &= C_V + \left[P + \left(\frac{\partial U}{\partial V}\right)_T\right] \left(\frac{\partial V}{\partial T}\right)_P. \end{split}$$

For ideal gases we have that:

$$C_P - C_V = nR.$$

## Adiabatic expansion

The <u>reversible adiabatic</u> expansion of an **ideal** gas is given by:

$$dU = -PdV$$
 and  $dU = C_V dT$   
 $\implies \frac{dT}{T} + \frac{C_P - C_V}{C_V} \frac{dV}{V} = 0$ 

since U = U(T). Integrating this yields:

$$TV^{\gamma-1} = \text{constant}$$

$$PV^{\gamma} = \text{constant}$$

$$T^{\frac{1}{\gamma-1}}V = \text{constant}$$

where  $\gamma$  is the adiabatic exponent:

$$\gamma = \frac{C_P}{C_V} = \frac{f+2}{f}$$

$$U = \frac{f}{2}nRT$$

and f is degrees of freedom. The practical computation of work done for adiabats is given by:

$$W_{1\to 2} = -\int_{T_1}^{T_2} C_V dT.$$

### General form for first law

Given system with m conjugate pairs  $(x_i, X_i)$  that represent various modes of work exchange:

$$\mathrm{d}U = \mathrm{d}Q + \sum_{i=1}^{m} x_i \mathrm{d}X_i$$

for each  $\{x_i\}$  drives  $\{X_i\}$ .

Thermodynamics

### Enthalpy

The state function enthalpy simplies the description of heat transfer.

Enthalpy has units J and is defined as:

$$H = U + PV$$
.

Under reversible conditions:

$$dH = dU + PdV + VdP$$
$$= dQ + VdP$$

$$: dH = dQ_P \implies C_P = \left(\frac{\partial H}{\partial T}\right)_P.$$

#### Latent heats

Latent heat (J) is heat needed for sample to undergo a phase transition:

$$\Delta U = Q - P\Delta V$$


$$L = Q = \Delta H$$
.

### Carnot's theorem

Peak efficiency of a cyclic heat engine:

$$\begin{split} \eta &:= \frac{W}{Q_H} = \frac{\dot{W}}{\dot{Q_H}} \\ &= 1 - \frac{Q_C}{Q_H} = 1 - \frac{T_C}{T_H} \end{split}$$

and is known as the Carnot cycle:



where AB,CD are isothermal processes and BC, DA are adiabatic processes.

#### Entropy

The state function entropy is a measure of disorder defined as:

$$S = \frac{Q}{T}$$

where Q is heat received from a reservoir at temperature T and units  $JK^{-1}$ .

For <u>reversible</u> processes:

$$\Delta S_{1\to 2} = \int_{T_1}^{T_2} \frac{dQ}{T}$$
$$dU = TdS - PdV$$
$$dH = TdS + VdP.$$

### Entropy of mixing

For ideal gases A and B:

$$\Delta S = n_A R \ln \frac{V_A + V_B}{V_A} + n_B R \ln \frac{V_A + V_B}{V_B}. \label{eq:deltaS}$$

The molar specific entropy of mixing is:

$$\Delta s_{mix} = -R(x_A \ln x_A + x_B \ln x_B)$$
$$x_A = \frac{n_A}{n_A + n_B} \text{ and } x_B = \frac{n_B}{n_A + n_B}.$$

#### Second law

Total entropy cannot decrease:

 $\Delta S_{total} = \Delta S_{system} + \Delta S_{reservoir} \ge 0$ due to the Clausius inequality:

$$dS \ge \frac{dQ}{T}.$$

$$\therefore W_{rev} - W_{irr} = T\Delta S_{irr} > 0$$

### Helmholtz free energy

$$F = U - TS$$
$$dF = -SdT - PdV$$

### Gibbs free energy

$$G = H - TS$$

For reversible processes:

$$dG = -SdT + VdP.$$

#### Chemical reactions

Since  $Q = \Delta U + P_0 \Delta V = \Delta H$ :

- Q < 0: exothermic (heat is released)
- Q > 0: endothermic (heat is absorbed)

at constant pressure  $P_0$ .

Chemical reactions are spontaneous if:

$$\Delta G = \Delta H - T\Delta S < 0.$$

# Maxwell relations

$$\begin{split} \left(\frac{\partial T}{\partial V}\right)_S &= -\left(\frac{\partial P}{\partial S}\right)_V \\ \left(\frac{\partial T}{\partial P}\right)_S &= \left(\frac{\partial V}{\partial S}\right)_P \\ \left(\frac{\partial S}{\partial V}\right)_T &= \left(\frac{\partial P}{\partial T}\right)_V \\ -\left(\frac{\partial S}{\partial P}\right)_T &= \left(\frac{\partial V}{\partial T}\right)_P \end{split}$$

The isobaric expansivity is defined as:

$$\beta = \frac{1}{V} \left( \frac{\partial V}{\partial T} \right)_{P}$$

and the isothermal compressibility:

$$\kappa_T = -\frac{1}{V} \left( \frac{\partial V}{\partial P} \right)_T.$$

### Throttling

Throttling is the <u>adiabatic</u> reduction in gas pressure and is an isenthalpic process. We define the slope of a P-T plot:

$$\mu_{JK} = \left(\frac{\partial T}{\partial P}\right)_{H}$$
$$= \frac{V(T, P)}{C_{P}}(\beta T - 1)$$

as the Joule-Kelvin coefficient.

## Clausius-Clapeyron equation

The slope of any phase boundary is:

$$\frac{\mathrm{d}P}{\mathrm{d}T} = \frac{\Delta S}{\Delta V} = \frac{\Delta H}{T\Delta V}$$

since constant pressure at boundaries.

## Van der Waals state equation

$$\left(P + \frac{an^2}{V^2}\right)\left(V - nb\right) = nRT$$

# Chemical potentials

The Euler equation for a 1-component open system with N particles is:

$$U = TS - PV + \mu N$$

with modified first law statement:

$$dU = TdS - PdV + \mu dN.$$

This gives the Gibbs-Duhem relation:

$$SdT - VdP + Nd\mu = 0$$

where  $\mu$  is the chemical potential:

$$\mu = \frac{G}{N}$$

since G is extensive. At constant T with ideal gas assumptions:

$$\mu(P,T) = RT \ln \frac{P}{P_0} + \mu_0(P,T).$$

Chemical potential  $\mu$  has units J.

#### Third law

$$S = 0$$
 at  $T = 0$ K.

## Questions

1. What is temperature?