#### Definitions

Isolated system: No exchanges

Closed system: Only energy exchange

Open system: Energy & mass exchange

#### Intensive state variables:

Independent of mass

### Extensive state variables:

Proportional to mass

**Reservoirs**: Infinite/very large system that remains unchanged when in contact with finite system.

# Mechanical equilibrium:

No unbalanced forces

#### Thermal equilibrium:

No temperature differences

# ${\bf Thermodynamic\ equilibrium:}$

Intensive state variables of system are <u>constant</u>. Alternatively our system is in <u>mechanical</u> and <u>thermal</u> equilibrium.

#### Reversible processes:

Every intermediate is an equilibrium state.

## Quasi-static processes:

Process sufficiently slow such that only infinitesimal temperature or pressure gradients exist.

Frictionless quasi-static processes are reversible.

#### Cyclic processes:

$$\Delta U = 0$$
 and  $W = Q$ 

For conservative forces:

$$\oint \mathrm{d}X = 0$$

where X is a state variable.

Adiabatic processes:  $\Delta Q = 0$ 

Isothermal processes:  $\Delta T = 0$ 

#### Zeroth law

If A is in thermal equilibrium with B and C seperately then B and C are also in thermal equilibrium.

### Ideal gas state equation

Given n moles of gas at temperature T:

$$PV = nRT$$
$$= Nk_BT$$

where  $R = N_A k_B = 8.314 \text{JK}^{-1} \text{mol}^{-1}$ and N the number of molecules.

#### Calculus identities

1. 
$$\left(\frac{\partial Z}{\partial Y}\right)_{Y} = \left[\left(\frac{\partial Y}{\partial Z}\right)_{Y}\right]^{-1}$$

$$2. \ \left(\frac{\partial X}{\partial Y}\right)_Z \left(\frac{\partial Y}{\partial Z}\right)_X \left(\frac{\partial Z}{\partial X}\right)_Y = -1$$

#### First law

Total energy E is conserved and:

$$dU = dQ - dW.$$

Note Q > 0 represents energy transferred into system. When system does work on surroundings W > 0.

Work done  $\underline{\text{by}}$  fluid in reversible adiabatic processes:

$$\mathrm{d}W = P\mathrm{d}V$$

and is in Joules (J).

### Isochoric heat capacity

$$C_V(T) = \left(\frac{\mathrm{d}Q}{\mathrm{d}T}\right)_V = \left(\frac{\partial U}{\partial T}\right)_V$$

### Isobaric heat capacity

$$C_P = \left(\frac{\mathrm{d}Q}{\mathrm{d}T}\right)_P$$
$$= C_V + \left[P + \left(\frac{\partial U}{\partial V}\right)_T\right] \left(\frac{\partial V}{\partial T}\right)_P$$

Heat capacity has units  $JK^{-1}$ .

For ideal gases we have that:

$$C_P - C_V = nR.$$

Under reversible adiabatic processes:

$$TV^{\gamma-1} = \text{constant}$$

$$PV^{\gamma} = \text{constant}$$

$$T^{\frac{1}{\gamma-1}}V = \text{constant}$$

where  $\gamma$  is the adiabatic exponent:

$$U = \frac{f}{2}nRT$$

$$\gamma = \frac{C_P}{C_V} = \frac{f+2}{f}$$

regardless of degrees of freedom f.

### State function enthalpy

$$H = U + PV$$

$$dH = dU + VdP + PdV$$
$$= dQ + VdP$$

$$\therefore C_P = \left(\frac{\partial H}{\partial T}\right)_P$$

### Chemical reactions

$$Q = \Delta U + P_0 \Delta V = \Delta H$$

Here  $P_0$  is constant.

- Q < 0: exothermic (heat is released)
- Q > 0: endothermic (heat is absorbed)

#### Carnot's theorem

Peak efficiency of a cyclic heat engine:

$$\eta = \frac{\dot{W}}{\dot{Q_H}} = 1 - \frac{Q_C}{Q_H} = 1 - \frac{T_C}{T_H}$$

and is either in terms of rate or value, with units J or  $Js^{-1}$ .

# State function entropy

$$S = \frac{Q}{T}$$

$$: dU = TdS - PdV$$

### Entropy of mixing

$$\Delta S = n_A R \ln \frac{V_A + V_B}{V_A} + n_B R \ln \frac{V_A + V_B}{V_B}$$

$$\Delta s_{mix} = -R(x_A \ln x_A + x_B \ln x_B)$$

$$x_A = \frac{n_A}{n_A + n_B}$$
 and  $x_B = \frac{n_B}{n_A + n_B}$ 

## Second law

$$\Delta S_{total} = \Delta_{system} + \Delta_{reservoir} \ge 0$$

$$dS \ge \frac{dQ}{T}$$

### Helmholtz free energy

$$F = U - TS$$

$$\mathrm{d}F = -S\mathrm{d}T - P\mathrm{d}V$$

# Gibbs free energy

$$G = H - TS$$

$$dG = -SdT + VdP$$

Chemical reactions are spontaneous if:

$$\Delta G = \Delta H - T\Delta S < 0.$$

# Maxwell relations

$$\begin{split} \left(\frac{\partial T}{\partial V}\right)_S &= -\left(\frac{\partial P}{\partial S}\right)_V \\ \left(\frac{\partial T}{\partial P}\right)_S &= \left(\frac{\partial V}{\partial S}\right)_P \\ \left(\frac{\partial S}{\partial V}\right)_T &= \left(\frac{\partial P}{\partial T}\right)_V \\ -\left(\frac{\partial S}{\partial P}\right)_T &= \left(\frac{\partial V}{\partial T}\right)_P \end{split}$$

The isobaric expansivity is defined as:

$$\beta = \frac{1}{V} \left( \frac{\partial V}{\partial T} \right)_{P}$$

and the isothermal compressibility:

$$\kappa_T = -\frac{1}{V} \left( \frac{\partial V}{\partial P} \right)_T.$$

### Clausius-Clapeyron equation

The slope of any phase boundaries is:

$$\frac{\mathrm{d}P}{\mathrm{d}T} = \frac{\Delta S}{\Delta V}.$$

# Van der Waals state equation

$$\left(P + \frac{an^2}{V^2}\right)\left(V - nb\right) = nRT$$

# Chemical potentials

$$\mu = \frac{G}{N}$$

# Third law

$$S = 0$$
 at  $T = 0$ K.